



GE VERNOVA

PROFICY® SOFTWARE & SERVICES

PROFICY HISTORIAN

User Guide

Proprietary Notice

The information contained in this publication is believed to be accurate and reliable. However, GE Vernova assumes no responsibilities for any errors, omissions or inaccuracies. Information contained in the publication is subject to change without notice.

No part of this publication may be reproduced in any form, or stored in a database or retrieval system, or transmitted or distributed in any form by any means, electronic, mechanical photocopying, recording or otherwise, without the prior written permission of GE Vernova. Information contained herein is subject to change without notice.

© 2024 GE Vernova and/or its affiliates. All rights reserved.

Trademark Notices

“GE VERNOVA” is a registered trademark of GE Vernova. The terms “GE” and the GE Monogram are trademarks of the General Electric Company, and are used with permission.

Microsoft® is a registered trademark of Microsoft Corporation, in the United States and/or other countries.

All other trademarks are the property of their respective owners.

We want to hear from you. If you have any comments, questions, or suggestions about our documentation, send them to the following email address:
doc@ge.com

Contents

- Chapter 1. Release Notes.....47**
 - What's New..... 47
 - Resolved Issues..... 55
 - Known Issues and Limitations..... 60
- Chapter 2. Getting Started Guide..... 65**
 - Overview..... 65
 - System Architecture.....69
 - System Components..... 73
 - About the Historian Server.....80
 - About Tags..... 81
 - Prerequisites..... 82
 - Setting Up the Historian Environment.....82
 - Activate the Historian License.....82
 - Hardware Requirements.....87
 - Software Requirements..... 92
 - Compatibility with Other Products..... 94
 - Supported Formats..... 94
 - Optimize Performance.....96
 - Enable Trust.....97
 - VMWare Support.....98
 - Installation..... 100
 - Installation Workflow..... 100
 - The Historian Server..... 104
 - Alarms and Events..... 140
 - Collectors..... 142
 - Client Tools.....150
 - Web-based Clients..... 154

Remote Management Agents.....	187
Install the OPC UA HDA Server.....	191
The Excel Add-In for Historian.....	195
The Excel Add-In for Operations Hub.....	198
ETL.....	202
Stand-Alone Help.....	205
Configuring Certificate-based Security to use MTLS.....	206
Overview of the Certificate-based Security.....	206
Certificate-based Security Specific Configurations.....	214
Upgrade Scenarios when Working with Historian Server Certificates.....	227
Troubleshooting Historian Server Certificates.....	228
Using Proficy Authentication or LDAP Groups.....	229
About Proficy Authentication.....	229
About Proficy Authentication Groups.....	231
Using Server Certificates.....	234
Change the Log Levels of Proficy Authentication.....	234
Migrating Historian Data.....	235
Migrating the Alarms and Events Data.....	235
Using the Migration Tool.....	239
Data Migration Scenarios.....	242
Migration Tool Command-Line Syntax.....	246
Interoperability of Historian Versions.....	247
Migrate User Authentication Data from Historian to Common Proficy Authentication Service.....	248
Implementing Historian Security.....	251
Implementing Historian Security.....	251
Uninstalling Historian.....	294
Uninstalling Historian.....	294
Troubleshooting.....	295

Managing Historian Log Files.....	295
Troubleshooting the Historian Server.....	298
Troubleshooting Web-based Clients.....	300
Chapter 3. Configuration Hub.....	303
Overview.....	303
About Configuration Hub.....	303
Workflow.....	304
Setting up Configuration Hub.....	305
About Setting up Configuration Hub.....	305
Install the Historian Server.....	305
Install Web-based Clients.....	314
Install Collectors.....	331
Perform Post-Installation Tasks.....	335
Upgrade.....	336
Access Configuration Hub.....	336
Historian Plugin Management in Configuration Hub.....	341
Common Tasks.....	353
Setting up a Stand-Alone System.....	356
About Setting up.....	356
Add a Collector.....	357
Add Tags.....	357
Setting up a Horizontally Scalable System.....	359
About Setting up a Horizontally Scalable System.....	359
Add a Server.....	361
Add a Collector.....	362
Add Tags.....	363
Browse Tags using Distributed or Mirror Node Servers when Primary Server is Inactive.....	365
Setting up High Availability.....	367
About Data Mirroring	367

Create.....	368
Create a Data Store.....	370
Creating a Model.....	371
About a Historian Model.....	371
About Object Templates.....	376
Workflow for Creating a Historian Model.....	379
Create an Object Type.....	380
Include a Contained Type.....	385
Create an Object Instance.....	388
Provide Data for a Static Variable.....	390
Collect Data for a Direct Variable.....	392
Collect Data for an Indirect Variable.....	395
Export an Object Type/Instance.....	400
Import an Object Type/Instance.....	402
Copy an Object Type.....	403
Delete a Template.....	407
Delete an Object Instance.....	409
Delete an Object Type.....	410
Managing Historian Systems.....	411
Access a System.....	411
Access the Collectors in a System.....	420
Access Offline Configuration Collectors.....	422
Access the Tags in a System.....	425
Add a System.....	427
Add a Server.....	428
Set Up a Mirror of Mirror.....	429
Remove a Server.....	439
Set a Default Location.....	439
Modify a System.....	440

Configure Advanced Settings.....	441
Configure Labels of Spare Fields.....	444
Set a Default System.....	445
Delete a System.....	445
Managing Mirror Locations.....	446
Create.....	446
Rename.....	447
Add a Machine.....	448
Remove a Machine.....	449
Delete.....	450
Managing Data Stores.....	451
About Data Stores	451
Create a Data Store.....	452
Access a Data Store.....	453
Rename a Data Store.....	458
Set as Default.....	462
Access Archives.....	463
Apply Configuration Template.....	463
Multiple Archive Paths.....	464
Access Activity Logs.....	470
Access Tags.....	470
Specify Tags for Data Collection.....	471
Add a Tag Manually.....	473
View Performance.....	476
Delete.....	478
Adding a Collector Instance.....	479
The Calculation Collector.....	479
CygNet Collector.....	482
The File Collector.....	486

The HAB Collector.....	489
About Adding an iFIX Collector Instance.....	501
The iFIX Collector.....	505
The MQTT Collector.....	510
The MQTT Sparkplug B Collector.....	519
The ODBC Collector.....	527
The OPC Classic Alarms and Events Collector.....	532
The OPC Classic DA Collector.....	534
The OPC Classic HDA Collector.....	540
The OPC UA DA Collector.....	544
The OSI PI Collector.....	549
The OSI PI Distributor.....	553
The Python Collector.....	556
The Server-to-Server Collector.....	559
The Server-to-Server Distributor.....	563
The Simulation Collector.....	567
The Windows Performance Collector.....	571
The Wonderware Collector.....	575
Collector Configuration - Common Fields.....	579
Sending Data to Cloud.....	587
Alibaba Cloud.....	587
AWS Cloud.....	594
Azure Cloud (Key-Value Format).....	601
Azure Cloud (KairosDB Format).....	608
Google Cloud.....	614
Predix Cloud.....	621
Protocols and Port Numbers.....	626
Managing Collector Instances.....	627
Managing Collectors Using Configuration Hub.....	627

Access a Collector.....	628
Access Tags.....	631
Add a Collector.....	632
Enable MTLS Security for Collectors.....	632
Modify a Collector.....	634
Add a Comment.....	635
Access Comments.....	636
Start a Collector.....	637
Stop a Collector.....	638
Restart a Collector.....	639
Pause Data Collection.....	641
Resume Data Collection.....	642
Clear Buffer.....	643
Move Buffer.....	644
Change Destination.....	645
Reset Performance Counters.....	646
Reset Overruns.....	647
Update Collector Credentials.....	648
Apply Configuration Template to a Collector.....	650
Configure Collector Redundancy.....	651
Delete a Collector.....	654
Managing Offline Configuration Collector Instances.....	655
Access Offline Configuration Collectors.....	655
Manage Offline Configuration Collectors.....	657
Access Tags.....	658
Managing Tags.....	659
About Tags.....	659
About Array Tags.....	660
About Collector and Archive Compression.....	660

About Scaling.....	666
About Condition-Based Collection.....	666
Specify Tags for Data Collection.....	667
Add a Tag Manually.....	669
Access a Tag.....	672
Configure Multiple Tags.....	687
Access Trend Chart.....	689
Access Last 10 Values.....	690
Access a Tag Alias.....	694
Export Tags as a CSV File.....	695
Import Tags from a CSV File.....	697
Rename a Tag.....	698
Copy a Tag.....	700
Stop Data Collection.....	702
Resume Data Collection.....	703
Remove a Tag.....	704
Delete a Tag.....	705
Managing Enumerated Sets.....	707
About Enumerated Sets.....	707
Create an Enumerated Set.....	708
Assign an Enumerated Set to a Tag.....	710
Export an Enumerated Set.....	710
Import an Enumerated Set.....	711
Rename Enumerated Set.....	711
Delete Enumerated Set.....	712
Managing Data Attribute Enumerated Set.....	712
About Data Attribute Enumerated Set.....	712
Create a Data Attribute Enumerated Set.....	713
Assign a Data Attribute Enumerated Set to a Tag.....	716

Export Data Attribute Enumerated Sets.....	717
Import Data Attribute Enumerated Sets.....	717
Rename a Data Attribute Enumerated Set.....	718
Delete a Data Attribute Enumerated Set.....	718
Managing User-Defined Data Types.....	719
About UDTs.....	719
Create UDT.....	719
Assign to Tag.....	720
Export User-defined Types.....	721
Import User-defined Types.....	721
Rename User-defined Types.....	722
Delete User-defined Types.....	722
Managing Archives.....	723
About Archives.....	723
Guidelines for Archive Sizing.....	724
Access an Archive.....	725
Create Archives Automatically.....	727
Create Archives Manually.....	728
Back up an Archive.....	730
Back up Archives with Volume Shadow Copy Service.....	731
Restore an Archive.....	733
Close an Archive.....	734
Remove an Archive.....	734
Reading/Writing Data.....	734
Query Data.....	734
Write Data.....	738
About Saved Query.....	741
Managing Alarms and Events.....	750
About Alarms and Events.....	750

Requirements.....	750
Create an Alarm.....	751
Access/Filter Alarms.....	752
Back up Alarms.....	753
Restore Alarms.....	754
About Purging Alarms.....	754
Managing Configuration Templates.....	757
About Configuration Templates.....	757
Create a Configuration Template for Collectors.....	757
Apply Configuration Template to a Collector.....	765
Create a Configuration Template for Data Stores.....	767
Apply the Configuration Template to a Data Store.....	772
Managing Reports.....	773
About Reports.....	773
Generate Reports.....	774
Export the Generated Report as a CSV File.....	781
Save the Generated Report as a PDF File.....	781
Accessing Activity Logs.....	782
Troubleshooting Configuration Hub	784
Chapter 4. Remote Collector Management.....	789
Overview of Remote Collector Management.....	789
Installing Remote Management Agents.....	790
Install Using the Installer.....	790
Install at a Command Prompt.....	793
About Managing Collector Instances Using the RemoteCollectorConfigurator Utility.....	794
Create a Sample JSON File.....	796
Add a Collector Instance.....	797
Modify a Collector Instance.....	799
Collector Instance Parameters.....	801

General Parameters of a Collector.....	814
Delete a Collector Instance.....	817
Add an Offline Collector Instance.....	819
Delete an Offline Collector Instance.....	819
Manage a Collector Remotely.....	820
Troubleshooting Remote Collector Management Issues.....	820
Chapter 5. Using Historian Administrator.....	822
Historian Administrator.....	822
Overview.....	822
Access Historian Administrator.....	823
Historian in a Regulated Environment.....	824
High Availability.....	825
About High Availability.....	825
Enable High Availability.....	827
Register Historian with a Cluster.....	827
Historian Administrator - Pages.....	828
The Main Page.....	828
The Data Store Page.....	835
Searching in Message Panel.....	850
Managing Data Stores.....	851
About Data Stores	851
Create.....	852
Rename.....	855
Move Tags.....	857
Delete.....	860
Managing Archives.....	863
About Archives.....	863
About Remote Storage.....	864
Guidelines for Archive Sizing.....	866

Create Automatically.....	868
Create Manually.....	870
Back up Automatically.....	874
Back up Manually.....	876
Restore.....	881
Configure System File Cache Memory.....	883
Configure DA for Remote Storage.....	884
Reuse a Config File.....	884
Managing Tags.....	885
About Tags.....	885
About Array Tags.....	886
About Collector and Archive Compression.....	886
About Scaling.....	893
About Condition-Based Collection.....	893
Access/Modify.....	894
Add Tags from Source.....	906
Create Manually.....	909
Copy.....	912
Rename.....	915
View Trend Chart.....	918
View Last 10 Values.....	921
Stop Data Collection.....	924
Resume Data Collection.....	929
Get Tag Fields.....	934
Remove.....	934
Delete.....	938
About UDTs.....	941
Manage UDTs.....	942
Assign/Remove Tags from UDTs.....	947

Manage Enumerated Sets.....	951
Assign/Remove Tags from Enumerated Sets.....	955
Managing Collectors.....	959
About Collectors.....	959
Access/Modify a Collector.....	960
Delete a Collector.....	968
Enable Spike Logic.....	970
About Collector Redundancy.....	975
Configure Redundant Collectors.....	978
Maintaining, Operating, and Monitoring Historian.....	983
Maintain, Operate, and Monitor Historian	983
Data Types.....	983
Plan for Data Recovery	988
Develop a Maintenance Plan.....	989
Evaluate and Control Data Compression.....	991
Handle Value Step Changes with Collector Data Compression	992
Reviewing System Alerts and Messages.....	995
Monitor Historian Health and Status.....	995
Monitor Historian Performance	999
Troubleshooting.....	1009
Solve Minor Operating Problems.....	1009
FAQ: Run a Collector as a Service.....	1010
Changing the Base Name of Automatically Created Archives	1011
Configuring the Inactive Timeout Value.....	1012
Configuring Deep Data Tree Warnings.....	1012
Control Data Flow Speeds.....	1013
Configure Inactive Server Reset Timeout.....	1016
Historian Errors and Message Codes	1016
Determining the Version of the Historian Server.....	1019

Return a List of Valid Field Options	1020
Scheduled Software Performance Impact.....	1020
Intellution 7.x Drivers as OPC Servers	1020
Troubleshooting Failed Logins	1021
Troubleshoot Data Collector Configuration.....	1022
Troubleshoot Tags.....	1023
Troubleshoot Historian Performance	1024
Troubleshoot the Archive Service	1025
Chapter 6. Historian Advanced Topics.....	1027
Historian Advanced Topics Overview.....	1027
About Historian Advanced Topics.....	1027
Storage.....	1027
Archive Compression.....	1027
Determining Whether Held Values are Written During Archive Compression.....	1032
Determining Expected Value.....	1033
How Archive Compression Timeout Works.....	1034
Archive De-fragmentation - An Overview.....	1035
About Storing Future Data.....	1037
Retrieval.....	1044
Retrieval.....	1044
Sampling Modes.....	1044
About Retrieving Data from Historian.....	1071
Sampling Modes.....	1072
Calculation Modes.....	1073
Query Modifiers.....	1075
Filtered Data Queries.....	1076
Filter Parameters for Data Queries.....	1076
Filtered Queries in the Excel Add-in Example.....	1078
Filtering Data Queries in the Excel Add-in.....	1079

Hybrid Modes.....	1079
Calculation Modes.....	1085
StepValue Tag Property.....	1152
Comment Retrieval Mode.....	1158
Query Modifiers	1159
Work with Data Stores from the Command Line.....	1186
Using the Command Line to Work with Data Stores.....	1186
Creating a Data Store.....	1186
Deleting a Data Store.....	1186
Examples.....	1187
Measuring Historian Performance.....	1187
About Measuring Performance of Proficy Historian.....	1187
About the Proficy Historian Overview Objects.....	1188
About Proficy Historian Message Queue Object.....	1192
About Proficy Historian Cache Object.....	1196
Chapter 7. Historian Alarms and Events.....	1200
Overview.....	1200
Requirements.....	1200
Installation.....	1201
Upgrade.....	1203
Changing the SQL Server.....	1203
Backing up Data.....	1204
Using Configuration Hub.....	1204
Using the Utility.....	1205
Using Historian Administrator.....	1206
At a Command Prompt.....	1208
Restoring Data.....	1209
Using Configuration Hub.....	1209
Using Historian Administrator.....	1209

Migrating Data.....	1210
Using the Utility.....	1211
At a Command Prompt.....	1212
Querying Data.....	1215
Importing Data.....	1216
Exporting Data.....	1217
Purging Data.....	1218
Using Configuration Hub.....	1220
Using the Utility.....	1221
At a Command Prompt.....	1223
Closing Alarms.....	1225
Using the OPC AE Collector with FIX32 SCADA Systems.....	1225
Chapter 8. Historian REST APIs.....	1227
Introduction to Historian REST APIs.....	1227
Historian APIs.....	1227
About Security and Authentication.....	1227
Standards.....	1229
API Methods.....	1230
API Status Messages.....	1230
Common API Parameters.....	1231
Overview of Commonly Used API Parameters.....	1231
TagNames Parameter.....	1231
Start and End Timestamps Parameter.....	1232
TagSamples Parameter.....	1232
DataSample Parameter.....	1234
SamplingModeType Parameter.....	1235
Direction Parameter.....	1237
CalculationModeType Parameter.....	1237
FilterModeType Parameter.....	1243

ReturnDataFields Parameter.....	1244
Payload Parameter.....	1245
Error Code Definitions.....	1251
Historian REST APIs.....	1254
Overview of the Historian REST APIs.....	1254
Managing Systems.....	1254
Managing Historian Model.....	1287
Managing Collector Instances.....	1329
Collector Type and Subtype.....	1339
Managing Collectors.....	1340
Managing Data Stores.....	1365
Managing Tags.....	1381
Managing Alarms and Events.....	1417
Swagger Documentation.....	1427
Chapter 9. Historian System API.....	1429
Overview of the Historian System API.....	1429
Overview of the Historian System API.....	1429
ihapi.h File Overview.....	1430
ihapi.h File Overview.....	1430
ihConfiguration Functions.....	1433
System API Programming.....	1435
System API Programming.....	1435
System API Functions.....	1436
System API Connect Functions.....	1436
System API Tag Functions.....	1443
Read and Write Functions.....	1455
Archiver Configuration Functions.....	1469
Archiver Backup/Restore Functions.....	1479
User Defined Type Functions.....	1488

Utility Functions.....	1495
Sample Programs.....	1512
Sample Programs.....	1512
Chapter 10. Historian User API.....	1513
Historian User API Overview.....	1513
About the Historian User API.....	1513
Prerequisites.....	1514
Connect Functions.....	1514
Connect Functions Overview.....	1514
ihuConnect.....	1514
ihuConnectEx.....	1516
ihuDisconnect.....	1517
ihuSetConnectionParameters.....	1517
ihuRestoreDefaultConnectionParameters.....	1519
ihuServerRegisterCallbacks.....	1519
ihuBrowseCollectors.....	1520
Archiver Functions.....	1521
Archiver Functions Overview.....	1521
ihuSetArchiverProperty.....	1521
ihuGetArchiverProperty.....	1523
Tag Functions.....	1523
Tag Functions Overview.....	1523
Tag Property Value Types.....	1525
ihuCreateTagCacheContext.....	1527
ihuFetchTagCache.....	1527
ihuFetchTagCacheEx.....	1528
ihuFetchTagCacheEx2.....	1528
ihuFetchTagCacheEx3.....	1529
ihuGetTagNameCacheIndex.....	1530

ihuGetTagNameCacheIndexEx2.....	1530
ihuGetNumericTagPropertyByTagname.....	1531
ihuGetNumericTagPropertyByIndex.....	1531
ihuGetNumericTagPropertyByIndexEx2.....	1532
ihuGetStringTagPropertyByTagName.....	1533
ihuGetStringTagPropertyByTagNameEx2.....	1533
ihuGetStringTagPropertyByIndex.....	1534
ihuGetStringTagPropertyByIndexEx2.....	1535
ihuTagAdd.....	1535
ihuTagDelete.....	1536
ihuTagDeleteEx.....	1537
ihuTagRename.....	1537
ihuTagRenameEx.....	1538
ihuTagCacheCriteriaClear.....	1539
ihuTagCacheCriteriaClearEx2.....	1539
ihuTagCacheCriteriaSetStringProperty.....	1540
ihuTagCacheCriteriaSetStringPropertyEx2.....	1540
ihuTagCacheCriteriaSetNumericProperty.....	1541
ihuTagCacheCriteriaSetNumericPropertyEx2.....	1541
ihuTagClearProperties.....	1542
ihuTagSetStringProperty.....	1542
ihuTagSetNumericProperty.....	1542
ihuCloseTagCache.....	1542
ihuCloseTagCacheEx2.....	1543
Write Functions.....	1543
Write Functions Overview.....	1543
ihuWriteData.....	1543
ihuWriteComment.....	1546
Query Modifiers Functions.....	1547

Query Modifiers Functions Overview.....	1547
ihuBrowseQueryModifiers.....	1547
ihuClearQueryModifiers.....	1548
ihuRetrieveCalculatedDataEx2.....	1548
ihuSetQueryModifiers.....	1549
Read Functions.....	1549
Read Functions Overview.....	1549
ihuReadCurrentValue.....	1550
ihuReadInterpolatedValue.....	1551
ihuReadInterpolatedValueEx.....	1552
ihuReadRawDataByTime.....	1553
ihuReadRawDataByTimeEx.....	1554
ihuReadRawDataByCount.....	1555
ihuReadRawDataByCountEx.....	1556
ihuReadMultiTagRawDataByCount.....	1557
ihuReadMultiTagRawDataByCountEx.....	1557
ihuRetrieveSampledData.....	1558
ihuRetrieveSampledDataEx.....	1559
ihuRetrieveSampledDataEx2.....	1560
ihuRetrieveCalculatedData.....	1561
ihuRetrieveCalculatedDataEx.....	1562
ihuRetrieveCalculatedDataEx3.....	1563
Utility Functions.....	1564
Utility Functions Overview.....	1564
IHU_timestamp_FromParts.....	1564
IHU_timestamp_ToParts.....	1565
ihuServerGetTime.....	1566
Enumerated Sets Functions.....	1566
Enumerated Sets Functions Overview.....	1566

ihuGetEnumeratedSets.....	1567
ihuEnumeratedSetAdd.....	1567
ihuEnumeratedSetRawValue.....	1568
ihuEnumeratedSetsFree.....	1569
ihuEnumeratedSetRename.....	1570
ihuEnumeratedSetDelete.....	1570
ihuEnumeratedStateAdd.....	1571
ihuEnumeratedStateModify.....	1572
ihuEnumeratedStateDelete.....	1572
User-Defined Type Functions.....	1573
User-Defined Type Functions Overview.....	1573
ihuUserDefinedTypeAdd.....	1574
ihuUserDefinedTypeDelete.....	1574
ihuUserDefinedTypeRename.....	1575
ihuUserDefinedTypeExists.....	1576
ihuGetUserDefinedTypes.....	1576
ihuUserDefinedTypeSetProperties.....	1577
ihuUserDefinedTypeFreeProperties.....	1577
Publish Functions.....	1578
Publish Functions Overview.....	1578
Historian User API Error Codes.....	1586
Error Codes.....	1586
Historian User API Sample Programs.....	1588
Sample Programs Overview.....	1588
Chapter 11. Historian SDK.....	1591
Object Model Overview.....	1591
Historian SDK Overview.....	1591
Connect the SDK to the Server	1593
Working with Blob Data.....	1594

Working with Archives.....	1598
SDK Reference.....	1598
Object Summary.....	1598
Alarms Object.....	1598
Archive Object.....	1604
Archives Object.....	1604
Alarms.PurgeAlarmsById.....	1604
Collector Object.....	1605
Collectors Object.....	1605
Data Objects.....	1605
Message Objects.....	1606
OPC Objects.....	1607
Server Objects.....	1607
Tag Objects.....	1608
UserCalcFunction Object.....	1609
Property Reference A-B.....	1609
Method Reference A-B.....	1803
Event Reference A-Z.....	1889
Chapter 12. Historian Utility Suite.....	1894
Alerting System.....	1894
Version Validator.....	1895
DiagnostiX Tool.....	1895
Chapter 13. Collector Tool Kit.....	1897
Collector Toolkit Overview.....	1897
Overview.....	1897
Prerequisites.....	1897
Prerequisites.....	1897
Installing the Collector Toolkit with Historian.....	1899
About Installation.....	1899

Creating the Custom Collector Using the Wizard.....	1899
Installing and Configuring the Collector Toolkit for Linux.....	1900
Installing and Configuring the Collector Toolkit for Linux.....	1900
Configuring Custom Collector Wizard.....	1901
Configuring a Custom Collector using the Wizard.....	1901
Creating a Custom Collector.....	1901
Changing Historian Server Name.....	1902
Changing the Historian Server Name Using Registry.....	1902
Working with collector Interfaces.....	1903
About Interfaces.....	1903
Custom Collector Design.....	1905
Design topics for Creating Custom Collectors.....	1905
Backward Compatibility of the Collector Toolkit.....	1906
Backward Compatibility of the Collector Toolkit.....	1906
Custom Collector Toolkit Interface Technical Reference.....	1906
Custom Collector Toolkit Interface Technical Reference.....	1906
Custom Structure Technical Reference.....	1925
What is a Structure?.....	1925
Custom Collector Toolkit Structure Reference.....	1926
Hierarchical Custom Controller Browsing.....	1976
Browsing Custom Controller in a Hierarchy.....	1976
Developing Hierarchical Browsing using Collector Toolkit	1978
Collector Initialization Callbacks.....	1980
Polled Tag Callbacks.....	1982
Unsolicited Tags Callbacks.....	1984
Chapter 14. Data Collectors - General.....	1990
Data Collectors Overview.....	1990
About Historian Data Collectors.....	1990
Bi-Modal Cloud Data Collectors.....	1993

Data Collector Software Components.....	1995
Supported Windows versions for Data Collectors.....	1995
Data Collector Functions.....	1996
Supported Acquisition Interfaces.....	1998
Best Practices for Working with Data Collectors.....	1998
About Installing Historian Data Collectors.....	1999
Install Collectors.....	1999
Installing a Collector at a Command Prompt.....	2003
Upgrade Collectors.....	2005
Sending Data to Cloud.....	2006
Alibaba Cloud.....	2006
AWS Cloud.....	2012
Azure Cloud.....	2019
Google Cloud.....	2026
Predix Cloud.....	2033
Protocols and Port Numbers.....	2038
Offline Collector Configuration.....	2039
Offline Configuration for Collectors.....	2039
Creating Offline Configuration XML file.....	2040
Collector Interface Properties.....	2041
Tag List and Tag Properties.....	2043
About Updating Tag Properties Dynamically.....	2048
Cloud Collector Specific Registry Configuration.....	2049
Working with Tags.....	2050
Understanding Tag names.....	2050
Adding Tags from a Collector.....	2052
Manually Adding Tags.....	2056
Copy a Tag.....	2060
Search for Tags.....	2061

Remove Tags.....	2063
Browse a Data Source for New Tags.....	2064
About Configuring Collector Options.....	2066
About Collector Redundancy.....	2067
Collect Vendor Attributes.....	2067
Collector Spare Configuration.....	2069
Data Collector Operation and Troubleshooting.....	2069
Data Collector File Locations.....	2069
Pause or Resume Data Collection for All Tags.....	2070
Pause Data Collection for a Subset of Tags.....	2071
Modify User Privileges for Starting a Collector.....	2072
About Monitoring Data Collector Performance Statistics.....	2072
Disabling Rebroadcasting for Historian Data Archiver.....	2073
Troubleshooting Tag Configuration.....	2074
Reviewing the Active Collector Configuration.....	2074
Collector and Archive Compression.....	2076
Data Buffering.....	2076
Editing the Registry to Change the Buffer Size.....	2077
Setting Up Services Recovery Actions in Windows.....	2077
Working with Python Expression Tags.....	2078
Python Expression Tags in Historian.....	2078
Constructing and Adding Python Expression Tags.....	2080
Python Expression Tag Examples.....	2084
Uninstall Collectors.....	2094
Troubleshooting.....	2094
Chapter 15. The Calculation Collector.....	2098
Overview.....	2098
About the Tags Used by the Calculation Collector.....	2099
Workflow for Using the Calculation Collector.....	2100

Configuration.....	2101
Recalculate Tag Values.....	2103
Using Configuration Hub.....	2103
Using Historian Administrator.....	2104
Using the Calculation Collector.....	2106
Write Data to an Arbitrary Tag.....	2106
Creating Triggers.....	2111
Types of Triggers.....	2111
Create a Polled Trigger.....	2112
Examples of Scheduling Polled Triggers.....	2113
Create an Unsolicited Trigger.....	2114
Examples of Scheduling Unsolicited Triggers.....	2117
Calculation Formulas.....	2118
About Calculation Formulas.....	2118
General Guidelines for Defining a Calculation Formula.....	2119
Create a Calculation Formula Using a VBScript Code.....	2121
Create a Calculation Formula Using the Pre-built Functions.....	2123
Create a User-Defined Function.....	2125
Built-in Functions.....	2127
Types of Functions Supported	2135
User-defined Functions.....	2136
Date/Time Shortcuts.....	2138
Converting a Collected Value.....	2138
Calculations Inside Formulas.....	2138
Conditional Calculation.....	2139
Combining Tag Values and Assigning a Trigger.....	2139
Using CreateObject in a Formula.....	2139
Using a File.....	2140
Converting a Number to a String.....	2140

Detecting Recovery Mode Inside a Formula.....	2141
Looping Through Data Using the SDK.....	2141
Using an ADO Query.....	2143
Windows Performance Statistics Physical Memory Usage.....	2144
Windows Performance Statistics Virtual Memory Usage.....	2144
Determining Collector Downtime.....	2144
Analyzing the Collected Data.....	2145
Simulating Demand Polling.....	2146
Native Alarms and Events Functions.....	2147
About Native Alarms and Events Functions.....	2147
Retrieving and Setting Alarm Properties Manually.....	2147
Insert Calculation Functions Manually.....	2148
Data Input.....	2152
Calculation and Server-to-Server Collectors.....	2152
Recovery.....	2152
Manual Recalculation.....	2153
Troubleshoot Calculation Collector.....	2164
Troubleshooting Calculation collector.....	2164
Unsupported Data Types for Calculation Tags.....	2164
Unsupported Calculations in Calculation collector.....	2164
Writing Messages to the Collector Log File for Debugging Purposes.....	2165
Importing Calculations with Line Breaks into Historian.....	2165
Recovery Mode.....	2166
Chapter 16. The CygNet Collector.....	2167
Overview.....	2167
Configuration.....	2168
Using Configuration Hub.....	2168
Using Historian Administrator.....	2172
Specifying Tags for Data Collection.....	2174

Using Configuration Hub.....	2174
Using Historian Administrator.....	2176
Disabling Bad Offline Values.....	2179
Disabling Deleting Values.....	2179
Troubleshooting.....	2179
Chapter 17. The File Collector.....	2181
Overview.....	2181
Configuration.....	2184
Using Configuration Hub.....	2184
Using Historian Administrator.....	2186
Importing Files.....	2188
CSV File Format.....	2188
XML File Format.....	2195
Troubleshooting.....	2205
Chapter 18. The HAB Collector.....	2208
Overview.....	2208
High Availability.....	2210
Configuration.....	2213
The HAB Collector.....	2213
Configure the Tags.....	2219
Configure the Alarms.....	2230
Start the Collector.....	2242
Approve Tag Changes.....	2243
Delete the Collector.....	2245
FAQs.....	2246
Chapter 19. iFIX Collector.....	2251
Overview.....	2251
About Adding an iFIX Collector Instance.....	2251
Specify the Tags for Data Collection.....	2255

Editing FixTag.dat File	2257
Example: Restarting the iFIX Collector Using a Heartbeat.....	2259
Using an STK with the iFIX collector.....	2261
Setting Up.....	2263
Upgrading the iFIX Collectors.....	2263
The Configuration Section for iFIX collectors.....	2264
Collector-Specific Configuration (iFIX).....	2264
Configuration of iFIX Data Collector-Specific Fields.....	2265
Starting an iFIX Collector Instance.....	2266
Troubleshooting.....	2268
Chapter 20. Migrating iFix Data.....	2270
Migrating iFix Data to Historian.....	2270
About Migrating iFix to Historian.....	2270
Historian Migration Utilities.....	2271
Adding the Historian Toolbar.....	2276
Migration Checklist.....	2276
Migrating Classic Historical Data.....	2277
About Migrating Classic Historical Data.....	2277
Migrating Classic Historian Data to Your Historian Database.....	2278
Configuring Classic Migration Options.....	2280
Migrating Advanced Historian Data.....	2284
Migrating Advance Historian Data.....	2284
Migrating iFIX Alarms and Events Collector.....	2291
Migrating iFIX Alarms and Events collector.....	2291
iFIX Alarms and Events collector Migration Options Configuration.....	2293
Alarm Source Options	2293
Alarm Destination Options.....	2295
Troubleshoot iFIX Alarms and Events collector.....	2297
Chapter 21. The MQTT Collector.....	2298

Overview.....	2298
Configuration.....	2300
The MQTT Collector.....	2300
Using Historian Administrator.....	2309
Chapter 22. The MQTT Sparkplug B Collector.....	2312
Overview.....	2312
Adding an MQTT Sparkplug B Collector Instance.....	2317
Add an MQTT Sparkplug B Collector Instance using Configuration Hub.....	2317
Add an MQTT Sparkplug B Collector Instance using RemoteCollector Configurator.....	2325
Configuring an MQTT Sparkplug B Collector Instance.....	2331
Configure an MQTT Sparkplug B Collector Instance using Configuration Hub.....	2331
Configure an MQTT Sparkplug B Collector Instance using Historian Administrator.....	2336
Chapter 23. The ODBC Collector.....	2341
Overview.....	2341
Configuration.....	2343
Using Configuration Hub.....	2343
Using Historian Administrator.....	2347
Mapping the Data Format.....	2349
Data Recovery.....	2353
Reconnecting Automatically.....	2354
Troubleshooting.....	2355
Chapter 24. The OPC Classic DA Collector.....	2356
Overview.....	2356
Configuration.....	2357
Using Configuration Hub.....	2357
Using Historian Administrator.....	2363
Configuring Drivers and Deadbands.....	2366
Specifying Tags for Data Collection.....	2367
Using Configuration Hub.....	2367

Using Historian Administrator.....	2369
Creating OPC Groups.....	2371
Troubleshooting.....	2371
Chapter 25. The OPC Classic HDA Collector.....	2374
Overview.....	2374
Configuration.....	2376
Using Configuration Hub.....	2376
Using Historian Administrator.....	2380
Specifying Tags for Data Collection.....	2382
Using Configuration Hub.....	2382
Using Historian Administrator.....	2384
Data Recovery.....	2387
Reconnecting Automatically.....	2388
Troubleshooting.....	2388
Chapter 26. The OPC Classic Alarms and Events Collector.....	2390
About the OPC Classic Alarms and Events Collector.....	2390
About Event Types, Categories, and Conditions.....	2390
About Event Attributes.....	2391
Workflow for Using the OPC Alarms and Events Collector.....	2391
Configure the OPC Alarms and Events Collector.....	2392
Filter Alarms and Events Data.....	2393
Chapter 27. OPC Classic HDA Server.....	2396
Overview.....	2396
About the Historian OPC Classic HDA Server.....	2397
Setting Up.....	2398
Set Up the Historian OPC Classic HDA Server.....	2398
Enable Tag-Level Security.....	2398
Turn On Debug Mode for Trace Log Files.....	2399
Browse Large Number of Collectors and Tags.....	2399

Reference.....	2400
Supported Attributes.....	2400
Supported Data Types.....	2400
Supported Quality Values.....	2401
Supported Filter Attributes.....	2402
Example Trace Log File.....	2403
OPC Classic HDA Aggregates.....	2403
Average Aggregate	2405
Maximum Aggregate.....	2406
Minimum Aggregate.....	2407
Before Aggregate.....	2407
After Aggregate.....	2408
Nearest Aggregate.....	2408
Proficy Historian Interpolative Aggregate.....	2409
Chapter 28. OPC UA HDA Server.....	2410
Overview.....	2410
About the Historian OPC UA HDA Server.....	2411
Configuration.....	2412
Install the OPC UA HDA Server.....	2412
The OPC UA HDA Server Workflow.....	2416
Configure the OPC UA HDA Server Settings.....	2416
Connect the OPC UA HDA Server and the OPC UA HDA Client.....	2420
Authenticate a User to Connect to the OPC UA HDA Server.....	2421
Supported Attributes.....	2422
Supported Data Types.....	2423
Supported Quality Values.....	2424
Troubleshooting.....	2424
Chapter 29. The OPC UA DA Collector.....	2426
Overview.....	2426

Configuration.....	2428
Using Configuration Hub.....	2428
Using Historian Administrator.....	2432
Trusting a Client Certificate.....	2434
Connecting with Server.....	2434
Working with the Collector.....	2438
Using Configuration Hub.....	2438
Using Historian Administrator.....	2440
About OPC UA DA Collector Groups	2442
Troubleshooting.....	2442
Chapter 30. OSI PI Collector.....	2443
Overview.....	2443
Before You Begin.....	2444
OSI PI Collector Configuration.....	2446
Configuring the OSI PI Collector.....	2446
OSI PI Collector-specific Field Descriptions.....	2448
Tag Attributes Available in Browse.....	2450
Configuring Recovery Mode	2450
OSI PI Collector and Distributor Supported Data Types.....	2451
OSI PI Collector - Notes.....	2451
Starting and Stopping the OSI PI Collector.....	2452
Configuring Auto-synchronization of Digital States.....	2453
Renaming Digital States.....	2453
Deleting Digital States.....	2454
OSI PI Collector Troubleshooting.....	2455
Chapter 31. OSI PI Distributor.....	2457
OSI PI Distributor.....	2457
Overview.....	2457
Getting Started.....	2458

Configuring Multiple OSI PI Distributors to use Registry Keys.....	2459
OSI PI Distributor Configuration.....	2459
Configuring an OSI PI Distributor.....	2459
Tag Attributes Available in Browse.....	2461
OSI PI Collector and Distributor Supported Data Types.....	2461
Starting and Stopping the OSI PI Distributor Service.....	2462
Chapter 32. The Python Collector.....	2463
Overview.....	2463
Supported Data Types.....	2464
Install the Python Collector.....	2464
Adding a Python Collector Instance.....	2465
Add a Python Collector Instance using Configuration Hub.....	2465
Add a Python Collector Instance using RemoteCollectorConfigurator.....	2467
Configuring the Python Collector.....	2470
Configure the Python Collector using Configuration Hub.....	2470
Configure the Python Collector using Historian Administrator.....	2471
Configure Python Library Path using Configuration Hub.....	2472
Using the Python Collector.....	2473
Write Data to an Arbitrary Tag.....	2473
Create Triggers.....	2475
About Calculation Triggers.....	2475
Create a Polled Trigger.....	2476
Create an Unsolicited Trigger	2477
About Calculations.....	2478
About Calculations using Python Collector.....	2478
Create Python Script using Built-in Functions.....	2479
Create Python Script by Importing Third-party or Custom Python Modules or Functions.....	2481
Available Functions.....	2483
Examples of using Calculation Functions.....	2491

Examples: Using the Built-in Functions.....	2491
Examples: Custom or Third-party Python Modules.....	2491
Example: Storing Current Values of Arrays.....	2495
Example: Storing Dictionary Data as Multifield Data.....	2496
Example: Storing Python Integer List in Historian.....	2497
Example: Storing Python String List in Historian.....	2498
Example: Use Historian Data as Input to a Python Script.....	2498
Chapter 33. Server-to-Server Collector.....	2499
Overview.....	2499
Overview.....	2499
About Recovery Mode.....	2503
About Collection of Raw Samples.....	2504
Using the Collector.....	2504
Workflow for Using the Server-to-Server Collector.....	2504
Configure the Server-to-Server Collector Instance.....	2506
Tag Properties that are Copied.....	2508
Tag Properties that are Copied.....	2508
Examples of Data Collection.....	2509
Raw Samples Collection Example.....	2509
Advanced Collection Example.....	2510
Creating Calculation Formulas.....	2512
About Calculation Formulas.....	2512
General Guidelines for Defining a Calculation Formula.....	2513
Create a Calculation Formula Using a VBScript Code.....	2515
Built-in Functions.....	2517
User-defined Functions.....	2525
Create a User-Defined Function.....	2527
Date/Time Shortcuts.....	2529
Create a Calculation Formula Using the Pre-built Functions.....	2529

Types of Functions Supported	2531
Data Input.....	2532
Calculation and Server-to-Server Collectors.....	2532
Recovery.....	2533
Manual Recalculation.....	2533
Examples of Calculation Formulas.....	2545
Converting a Collected Value.....	2545
Calculations Inside Formulas.....	2545
Conditional Calculation.....	2545
Combining Tag Values and Assigning a Trigger.....	2545
Using CreateObject in a Formula.....	2545
Using a File.....	2546
Converting a Number to a String.....	2547
Detecting Recovery Mode Inside a Formula.....	2547
Looping Through Data Using the SDK.....	2548
Using an ADO Query.....	2549
Windows Performance Statistics Physical Memory Usage.....	2550
Windows Performance Statistics Virtual Memory Usage.....	2551
Determining Collector Downtime.....	2551
Analyzing the Collected Data.....	2552
Simulating Demand Polling.....	2552
Chapter 34. The Server-to-Server Distributor	2554
Overview.....	2554
Workflow for Using the Server-to-Server Distributor.....	2555
Configure the Server-to-Server Distributor.....	2555
Chapter 35. The Simulation Collector.....	2558
Overview.....	2558
Configuration.....	2558
Using Configuration Hub.....	2558

Using Historian Administrator.....	2559
Tags with Sequential Values.....	2560
Chapter 36. Windows Performance Collector.....	2562
Windows Performance Collector.....	2562
Overview.....	2562
Windows Performance Collector Feature Summary.....	2562
Windows Performance Collector Configuration.....	2563
Understanding Windows Performance Collector Tag Hierarchy.....	2563
The Configuration Section for Windows Performance Collector.....	2564
Chapter 37. The Wonderware Collector.....	2566
Overview.....	2566
Installation Prerequisites.....	2567
Wonderware Collector Features.....	2567
Hierarchical Tags Available in Browse	2568
Supported Data Types for Wonderware Collector.....	2569
Configuring Wonderware Collector.....	2570
Data Recovery.....	2571
Initiating Manual Recovery.....	2573
Reconnecting to the Wonderware Server.....	2574
Troubleshooting the Wonderware Collector.....	2575
Chapter 38. OLE DB Provider.....	2576
Overview.....	2576
Setting Up.....	2577
Install the OLE DB Provider.....	2577
Connect to a Historian Server.....	2580
Working with Clients.....	2580
Power BI Desktop.....	2580
VisiconX.....	2585
Oracle.....	2587

Crystal Reports.....	2587
Microsoft Excel.....	2592
Visual Basic and ADO.....	2596
Proficy Real-Time Information Portal.....	2600
Linked Servers.....	2600
Working with Queries.....	2606
Access the Historian Interactive SQL Application.....	2607
Run a Query.....	2608
Connect to a Server.....	2609
Save a Query.....	2610
Export Results.....	2611
Optimize the Query Performance.....	2611
Supported SQL Syntax.....	2612
SELECT Statements.....	2613
SET Statements.....	2629
Parameterized SQL Queries.....	2636
Optimize the Query Performance.....	2637
Troubleshooting and Frequently Asked Questions.....	2638
Troubleshooting.....	2638
Frequently Asked Questions.....	2642
Historian Database Tables.....	2647
The Historian Database Tables.....	2647
ihTags Table.....	2651
ihArchives Table.....	2659
ihCollectors Table.....	2661
ihMessages Table.....	2667
ihRawData Table.....	2670
ihHabAlarms Table.....	2680
ihComments Table.....	2682

ihTrend Table.....	2693
ihQuerySettings Table.....	2709
ihCalculationDependencies Table.....	2715
ihAlarms Table.....	2716
ihEnumeratedSets Table.....	2720
ihEnumeratedStates Table.....	2721
ihUserDefinedTypes Table.....	2722
ihFields Table.....	2723
Chapter 39. The Excel Add-In for Historian.....	2725
Overview.....	2725
Setting Up.....	2726
Install Using the Installer.....	2726
Install at a Command Prompt.....	2727
Activate Excel Add-In.....	2728
Querying Data.....	2730
Query Current Values.....	2730
Query Filtered Data.....	2732
Querying Calculated Data.....	2734
Querying Alarms and Events Data.....	2736
Modify a Query.....	2737
Query Modifiers.....	2738
Access Archive Statistics.....	2741
Access Collector Statistics.....	2742
Managing Tags.....	2743
Search for a Tag (Basic).....	2743
Search for a Tag (Advanced).....	2744
Export Tags.....	2746
Add/Modify Tags.....	2747
Import Tags.....	2748

Rename Tags.....	2748
Working with Array Tags.....	2749
Importing and Exporting Data.....	2750
Import Tag Data.....	2750
Importing Alarms and Events Data.....	2750
Export Tag Data	2751
Exporting Alarms and Events Data.....	2752
Working with Messages.....	2754
Search for Messages.....	2754
Import Messages.....	2755
Export Messages.....	2755
Managing Enumerated Sets.....	2756
Export Enumerated Sets.....	2758
Import Enumerated Sets.....	2759
Rename Enumerated Sets.....	2759
Managing User-Defined Types.....	2760
Export User-Defined Types	2761
Import User-Defined Types.....	2762
Reference.....	2762
Excel Add-In Options.....	2762
Reports.....	2764
Relative Time Entries.....	2777
Filter Parameters for Data Queries.....	2778
Batch IDs.....	2780
Sampling Types.....	2781
Calculation Algorithm Types.....	2782
Tag Criteria List.....	2784
Troubleshooting.....	2785
Chapter 40. The Excel Addin for Operations Hub.....	2788

Overview.....	2788
About Operations Hub.....	2789
Setting Up.....	2789
Software Requirements.....	2789
Install Excel Add-In for Operations Hub.....	2790
Copy or Export the Issuer Certificate on Server.....	2791
Install/Import the Issuer Certificate.....	2792
Connect to Operations Hub.....	2793
Querying Data.....	2793
Query Operations Hub Model.....	2794
Troubleshooting.....	2797
Chapter 41. Trend Client.....	2799
Overview.....	2799
Access Trend Client.....	2799
Access Help.....	2799
Managing Tags.....	2799
Add Tags for Analysis.....	2801
Creating a Display.....	2802
Add a Trend Chart.....	2802
Add a Current Value Table.....	2803
Add a Value Card.....	2803
Add a Text Box.....	2804
Access a Display.....	2804
Provide a Title to a Display.....	2805
Filter Data.....	2805
Change the Sampling Mode.....	2806
Change the Time Zone.....	2806
Export Data.....	2807
Set the Refresh Interval.....	2808

Working with a Trend Chart.....	2808
Add a Trend Chart.....	2808
Switch the Y-Axis.....	2810
Change the Format.....	2810
Change the Duration.....	2812
Access the Statistics.....	2813
Change the Sampling Mode.....	2813
Change the Scale of a Trend Chart.....	2814
Managing Favorites.....	2815
Access a Favorite.....	2815
Export a Favorite.....	2815
Import a Favorite.....	2816
Delete a Favorite.....	2816
Chapter 42. Historian Web Admin Console.....	2817
Overview.....	2817
Overview.....	2817
Difference Between the Web Admin Console and Historian Administrator.....	2817
Actions You Can Perform Using the Web Admin Console	2818
Access the Web Admin Console.....	2818
Understanding the Interface.....	2819
Understand the Historian Interface.....	2819
Client Panel	2820
Collector Panel.....	2822
Data Node Panel.....	2826
Configuration Panel.....	2830
Configure General Collector Options.....	2848
Configure General Collector Options.....	2848
Maintain, Operate, and Monitor Historian.....	2854
Plan For Data Recovery.....	2854

Develop a Maintenance Plan	2855
Monitor Historian Performance.....	2855
Evaluate Data Compression Performance.....	2865
Historian Data Types.....	2867
Managing Tags.....	2870
Access a Tag.....	2870
Add a Tag to a Data Source.....	2870
Add a Tag Manually.....	2871
Add a Source Address to a Tag.....	2872
Adding OPC Tags from a Collector.....	2872
Adding Simulation Tags from a Collector.....	2872
Filter and Search Tags.....	2873
Access the Trend Chart of Tag Values.....	2875
Displaying Raw Data Samples	2875
Dynamic Collector Updates.....	2876
Reload Tag Parameters	2877
Rename Tags.....	2879
Stale Tag Management	2881
Delete Tags.....	2881
Managing Data Stores.....	2882
About Data Stores	2882
Moving Tags Between Data Stores.....	2883
Adding a Data Store.....	2884
Deleting a Data Store.....	2884
Editing a Data Store.....	2885
Managing Data Archives.....	2885
Configure Data Archives.....	2885
Chapter 43. Extract, Transform, and Load (ETL).....	2901
Overview.....	2901

Workflow for Transferring Data from eDNA	2902
Workflow for an ODBC Data Source.....	2903
Workflow for Proficy Historian.....	2905
Workflow for PI Historian.....	2906
Installation.....	2908
Upgrade.....	2910
Extracting Data from an eDNA Server.....	2910
Specify Tags Using the Utility.....	2911
Specify Tags Manually.....	2912
Specify Tags Using a Template.....	2913
Specify Tags Using a Blank Spreadsheet.....	2914
Tag Properties.....	2916
Configure.....	2916
Extract Historical Data.....	2922
Start Data Extraction.....	2923
Extracting Data from an ODBC Data Source.....	2924
Specify Tags and Tables Manually.....	2924
Specify Tags and Tables Using a Template.....	2926
Specify Tags and Tables Using a Blank Spreadsheet.....	2928
.....	2931
Table Properties.....	2932
Configure.....	2933
Start Data Extraction.....	2937
Extracting Data from Proficy Historian.....	2938
Specify Tags Manually.....	2938
Specify Tags Using a Template.....	2939
Specify Tags Using a Blank Spreadsheet.....	2940
Tag Properties.....	2942
Configure.....	2942

Extract Historical Data.....	2946
Start Data Extraction.....	2947
Extracting Data from PI Historian.....	2948
Specify Tags Manually.....	2948
Specify Tags Using a Template.....	2949
Specify Tags Using a Blank Spreadsheet.....	2950
Tag Properties.....	2951
Configure.....	2952
Extract Historical Data.....	2956
Start Data Extraction.....	2957
Transferring Data Using BITS.....	2957
Configure BITS.....	2957
Verify Settings.....	2958
Transfer Data.....	2958
Transferring Data Using FTP.....	2959
Configure FTP.....	2959
Transfer Data.....	2960
Loading Data.....	2961
Configure.....	2961
Load Data.....	2965
Reference.....	2965
Example of a Regeneration File.....	2966
Example of a State File.....	2968
Troubleshooting.....	2969


Chapter 1. Release Notes

What's New in Historian 2024

Description	Tracking ID
<p>Configuration Hub Enhancements</p> <p>Configuration Hub provides a better user experience using an IDE model to manage systems, bringing in consistency across the portfolio to manage the configuration and administration of multiple products.</p> <p>The following Historian specific enhancements are made in Configuration Hub:</p>	
<p>Ability to register and manage Configuration Hub plugin for Historian: You can manage the Configuration Hub plugin for Historian using Configuration Hub. You can register a plugin, unregister a plugin, modify a plugin, and view Historian node and plugin-specific details using the Node Manager. For more information, refer to Historian plugin management.</p>	F69440
<ul style="list-style-type: none">• Ability to browse tag details when primary node is inactive: In a horizontally scaled system, when a primary server's central configuration manager is inactive, you can still browse tags by adding distributed or mirror nodes as a backup for the primary server. When you add a node as the backup, the Data Archiver of that node functions as the Configuration Manager, and sends the relevant tag information to the client manager. <p>To facilitate this enhancement, a new Support for Browse Tags, if primary server down property has been added in the Systems > GENERAL section of the DETAILS section.</p> <p>For more information, refer to browse tags using distributed or mirror node servers when primary server is inactive.</p>	F69877
<ul style="list-style-type: none">• Create custom templates for common configurations: You can create configuration templates for both data stores and collectors separately. <p>To facilitate this enhancement, a new Configuration Templates section has been added in the Configuration Hub plugin for Historian. Within the Configuration Templates, you are provided with two different tabs, one tab to configure collector-specific template, and the other tab to configure data store-specific template.</p>	

Description	Tracking ID
<div data-bbox="282 264 1172 441" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: You can apply a data store configuration template to a user-created data store, provided they are not set as the default data store. </div> <p data-bbox="282 474 927 506">For more information, refer to Configuration templates.</p>	
<p data-bbox="201 564 1154 726">Ability to reset collector overruns: You can reset overrun count of a collector instance to zero without restarting the collector. To facilitate this enhancement, a new collector action Reset Overruns has been added. For more information, refer to Reset Overruns.</p>	F70190
<p data-bbox="201 760 1154 1062">Ability to be notified when a restart of collector instance is required: When you modify certain configurations of a collector instance, you will be prompted to restart the collector instance. To facilitate this enhancement, a new confirmation dialog has been added. Whenever you modify certain configuration and save, you will be prompted with an option to restart the collector instance. If you decide not to restart, a notification will be displayed in the DETAILS section, stating that the selected collector instance needs a restart.</p> <div data-bbox="204 1096 1172 1272" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: The modification(s) will take effect only after you restart the collector instance. </div> <p data-bbox="201 1306 862 1337">For more information, refer to Modify collector instance.</p>	
<p data-bbox="201 1369 1146 1629">Ability to validate the destination Historian connection while adding a collector instance: You can test a destination Historian server's connection status while adding a collector instance. This will enable you to connect to a valid, and an active destination Historian server. To facilitate this enhancement, a new Test Connection button has been added in the Collector Initiation section, and also in the Update Collector Credentials: <Collector name> window for all the collectors.</p>	
<p data-bbox="201 1656 1167 1824">Ability to validate the source Historian connection while adding a Server-to-Server Collector or Server-to-Server Distributor collector instance: You can test a source Historian server's connection status while adding a collector instance. This will enable you to connect from a valid, and an active source Historian server. To</p>	

Description	Tracking ID
<p>facilitate this enhancement, a new Test Connection button has been added in the Source Configuration section.</p>	
<p>Ability to configure multiple tags at once: You can select multiple tags and configure their common configurations at once. To facilitate this enhancement, you are now enabled to select multiple tags using their corresponding check boxes, or you can select all the available tags using the check box available in the grid's header.</p> <p>For more information, refer to Configure multiple tags.</p>	
<p>Ability to add and view the actual unit of measure of a tag's value: You can add the actual unit of measure of a tag's value. This will help you to view and add more context to a tag's value that you pull. To facilitate this enhancement, a new EGU Description property has been added in the SCALING section of tag's DETAILS section.</p> <p>The engineering unit that you provide will be displayed under the Engineering Units column in the table view, and as a tool tip in the trend view, when you view the view the last 10 values of the tag, or when you generate a query/write report in the Data page.</p> <p>For more information, refer to the SCALING section in Access Tags.</p>	
<p>Ability to view Tag Creation Audit Trail: You can view the Tag Creation Audit Trail details for a tag. To facilitate this enhancement, new Created By, and Created Time properties have been added in the Tags > DETAILS > GENERAL section.</p>	
<p>Ability to add a stale period check for data store level: You can view the number of days or the frequency for checking data store validity. To facilitate this enhancement, a new Stale Period (Days) property has been added in the MAINTENANCE section in the Data Stores DETAILS section.</p> <p>For more information, refer to the MAINTENANCE section in Access a Data Store.</p>	
<p>Ability to Import/Export: You can import/export tags and their details, user defined-defined types (UDT), and Enumerated sets in a CSV format. This will enable you to export the data, modify the data, and then import them back using Configuration Hub. To facilitate this enhancement, the  and  buttons have been added in the corresponding sections.</p> <p>For more information, refer to the following sections:</p>	

Description	Tracking ID
<ul style="list-style-type: none"> • Import, and Export tag details. • Import, and Export UDT. • Import, and Export Data Attribute Enumerated sets. • Import, and Export Enumerated Sets. 	
<p>Ability to view the grid count and navigate through grids: You can view a grid's total and selected count, and when there are more than 100 rows in a grid, you can use the page count numbers to navigate through the grid details.</p> <p>To facilitate this enhancement, grid count (total and selected) and page numbers have been added below a grid.</p>  <p>The screenshot shows a web interface for tag management. At the top, there's a 'Filter' section with buttons for 'Max Tag Count:1000', 'Collector Name: .Simulation_1 X', 'Tag Name:* X', and 'Description:* X', along with a 'Reset to Default' button. Below this, it says 'Showing newly added tags for collector: .Simulation_1.' and 'Refreshed on 12/20/2023, 12:09:56 PM'. The main table has columns: TAG NAME, DESCRIPTION, COLLECTOR NAME, LAST 10 VALUES, D., TAG ALL., and IS STALE. The table lists 15 tags with IDs from Simulation00001 to Simulation00015. At the bottom right of the table, there is a pagination bar showing '1-100 of 1039' and page numbers '1 2 3 4 5 ... 11'.</p>	
<p>Implement Data Store-level security: Similar to tag-level security, you can also define data store-level security to protect sensitive tags.</p>	F70957

Description	Tracking ID
<div data-bbox="203 262 1172 441" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: However, the security settings defined at the tag level, if any, take the precedence over those at the data store-level. </div> <p>To facilitate this enhancement, the following properties have been added in the SECURITY section, in the data store DETAILS section. For more information, refer to Implementing data store-level security.</p>	
<p>Ability to configure multiple data archive paths: Multiple archive paths feature extends the ability to configure a default archive path for each data store.</p> <p>This feature enables you to automatically store your archives in different locations based on the age of the archive. It can be useful when splitting the data for a data store across multiple hard drives, primarily for performance and cost optimization. Additionally, it could help optimize disk space constraints.</p> <p>To facilitate this enhancement, a Multiple Archive Paths property has been added in the ARCHIVE CREATION section in the data store's DETAILS section. For more information, refer to Multiple archive paths.</p>	F70956
<p>Ability to configure security groups to use Proficy Authentication: You can configure Security Group at global (system) level to use Proficy Authentication. To facilitate this enhancement, a new Use Proficy Authentication option has been added to Security Group in the System's GLOBAL SECURITY section. If you select the Use Proficy Authentication option, the system will use the groups specific to Proficy Authentication (UAA) for authorization. Only the users or groups that belong to the Proficy Authentication will have specific permissions and access rights. For more information, refer to the GLOBAL SECURITY section in Access a System.</p> <div data-bbox="203 1480 1172 1707" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: To use Proficy Authentication security group, you must perform the configurations listed in the Configurations to use Proficy Authentication Security Groups section. </div>	F69870
<p>Ability to generate configuration reports: You can generate report to get a concise summary of tag-specific data of a specific collector. You can select a report from the available predefined templates and generate a categorized report.</p>	F66520

Description	Tracking ID
<div data-bbox="203 262 1172 394" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-bottom: 10px;">  Note: The reports are applicable only to the Historian destination collectors. </div> <p>To facilitate this enhancement, a new Reports section has been added in the Configuration Hub plugin for Historian. Within the Reports section, you are provided with a list of available predefined templates. You can select a template and generate its corresponding report and export it. For more information, refer to About reports.</p>	
<p>Ability to save data query and access it: You can save queries that you use to read tags data. You can use this option to save queries that you may frequently use to read specific tags data. This will help you in the following:</p> <ul style="list-style-type: none"> • Quickly gather insights of specific tags. • Create and save a predefined query only once and use it as needed. • You can use the Shared option to make the query visible to the other users in the same network. <div data-bbox="284 1045 1172 1220" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: Once you share a query, all the other users will also be able to edit, and delete it. Be mindful about making a query as a shared query. </div> <p>To facilitate this enhancement, a new Save Query button has been added in the New Query tab. The button will appear after generating a Read Data report. Additionally, a new Saved Queries tab has been added, which contains the list of all saved queries. For more information, refer to Save a Query.</p> <p>You can also update a saved query. For more information, refer to Update a saved query.</p>	
<p>Other Enhancements</p>	
<p>Term Licensing: In parity with other products within the Proficy portfolio, Historian licensing also supports a term license model. This will give you the flexibility to subscribe to Historian for a subscription fee based on your requirement.</p>	<p>F69872</p>
<p>Enhanced data type support for MQTT Collector: The support of Array tags has been added for the MQTT Collector.</p>	

Description	Tracking ID
<p>ETL Tools Enhancement: Performance improvements are made for the eDNA extractor.</p>	
<p>New MQTT Sparkplug B Collector: You can connect as a Primary Host application and collect data based on the MQTT Sparkplug B specification (Sparkplug 3.0.0). Specifically, you can subscribe to a topic that was published using the Sparkplug B payload and collect time-series data in a structured and understandable format. To facilitate this enhancement, a new MQTT Sparkplug B Collector has been added. You can install this collector and configure it to collect data based on the MQTT Sparkplug B specification (Sparkplug 3.0.0).</p> <p>For more information, refer to MQTT Sparkplug B Collector.</p>	F73170
<p>Ability to extensively use the Python Collector: You can now extensively use Python collector. This collector is available for use in both the Configuration Hub and the Historian Administrator. However, for a seamless user experience, it is recommended to use the collector in the Configuration Hub. To facilitate this enhancement, the following enhancements have been added in the Configuration Hub:</p> <ul style="list-style-type: none"> • Dedicated Python script editor. • Extensive list of built-in functions that you can use in your script. For more information, refer to Available functions. • Extensive list of supported data types. For more information, refer to Supported data types. • Capability to import third-party, custom Python modules and use them in the script. For more information, refer to Import third-party or custom Python Modules. • Capability to configure path for the newly installed Python modules using Configuration Hub. For more information, refer to Configure Python Library Path. 	F63933
<p>Support for Mutual TLS (MTLS) Protocol for Enhanced Security: You can use MTLS protocol for Historian core services and also collectors. To facilitate this enhancement, the following enhancements have been added:</p>	F70082

Description	Tracking ID
<ul style="list-style-type: none"> • Generating the required root certificate for Historian and core services can be done using the installer. You do not have to manually generate and trust the root certificates. For more information, refer to Certificate-based security for MTLS. • An option to Enable MTLS Security for collector specific instances has been added in Configuration Hub. For more information, refer to Enable MTLS Security for Collectors. • An option to encrypt the MTLS messages sent to Historian has been added. For more information, refer to Enable MTLS Security for Collectors. 	
<p>Ability to create data attribute enumerated set: You can create and define a custom text for the quality status and view it in the Attributes column instead of the value when you retrieve the tag data. For example, if your tag is receiving bit positions indicating the quality status (that is, 1 for Old data, 2 for Bad data, and 30 for Good data), you can map the bit position to a custom text and assign it to a set. So, when you view the actual values of the tag, the Attributes column will display the mapped custom text instead of the integer (the bit positions). To facilitate this enhancement, in Configuration Hub, a new DATA ATTRIBUTE ENUMERATED SET option has been added in the Manage Enumerated Sets section. To enable data attribute enumerated set, you must set the DATA ATTRIBUTE ENUMERATED SET option to True. For more information, refer to about data attribute enumerated set.</p> <div data-bbox="203 1207 1172 1562" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Once you created a data attribute enumerated set in Configuration Hub, you can use it in Historian Administrator. However, it is not recommended to modify the created Data Attribute Enumerated set in the Historian Administrator. If you modify it using the Historian Administrator, the DATA ATTRIBUTE ENUMERATED SET field will be changed to False in Configuration Hub.</p> </div>	F73356
<p>Ability to visualize and interact with Historian specific REST APIs using Swagger UI: You can now access Historian REST APIs using Swagger UI. This tool enables you to visualize and interact with the API resources without having any of the implementation logic in place, establishing a fully interactive documentation experience using Swagger. For more information, refer to Swagger Documentation.</p>	F69878
<p>Enhancements in Historian REST APIs for Tags</p>	F70197

Description	Tracking ID
<p>Taglist API: To avoid pagination related issue, you can set the pagesize parameter to 0. This will provide all tags at once without any pagination.</p> <p>Engineering Units: Tag Data response now includes Engineering Units. For example,</p> <pre data-bbox="211 493 1169 1312"> { "ErrorCode": 0, "ErrorMessage": null, "Data": [{ "TagName": "Test2020_Simulation.Simulation00001", "ErrorCode": 0, "DataType": "Float", "EngineeringUnits": null, "HiEngineeringUnits": 200000, "LoEngineeringUnits": 0, "Samples": [{ "TimeStamp": "2023-12-04T13:04:51.000Z", "Value": "93319.5", "Quality": 3, "DataAttributes": [] }] }], }</pre>	

Resolved Issues

Description	Tracking ID
<p>Previously, when you viewed the Last 10 Values of the tags of Server-to-Server collector, the trend was not visible, however, if you right-click on the tags, it was visible. This issue has been resolved in Historian 2024.</p>	01092678 (DE205966)
<p>Previously, there were Apache Tomcat vulnerabilities observed in Historian server. This issue has been resolved in Historian 2024.</p>	01088103, 01086760, 01115035, 01114659, 01113071,

Description	Tracking ID
	01107496, 01130189, 01118147 (DE204880)
Previously, using Web Administrator, when you viewed the Last 10 Values of a tag, the trend data was not displayed. This issue has been resolved in Historian 2024.	01086847 (DE205687)
Previously, on Configuration Hub, when you searched tags by their collection interval, the tags were not returned. This issue has been resolved in Historian 2024.	01083356 (DE205085)
Previously, there were OpenSSL 1.1.1k vulnerabilities observed in Historian. This issue has been resolved in Historian 2024.	01070308, 01050129 (DE204882)
Previously, when you attempted to extract 71 and more good quality codes using the Proficy Historian eDNA ETL tool, and then used them in configuration, all the codes were not being considered. This issue has been resolved in Historian 2024.	01093884 (DE212931)
Previously, when you attempted to start the Historian ETL PI Extract Settings, the settings did not start as the IHELPIExtract services did not start or respond. This issue has been resolved in Historian 2024.	01052974 (DE199961)
Previously, files with the wrong time format were not moved to the Error folder. Instead, they kept executing forever. This issue has been resolved in Historian 2024.	01093946 (DE212928)
Previously, there was an issue in creating a LAX file for unacknowledged and/or not closed alarm. This issues has been resolved in Historian 2024.	01098478 (DE212929)
Previously, when you attempted to load the LAX file containing custom attributes, it did not work. This issue has been resolved in Historian 2024.	01082173 (DE212930)
Previously, using the Proficy Historian Excel Add-in, when you attempted to export tags from a Historian with more than 82,000 tags, it appended an underscore at the beginning of the tag name. This issue has been resolved in Historian 2024.	01093704, 01095104 (DE204980)
Previously, when you attempted to browse, the Show ALL Children was disabled when you had collector with a large hierarchy. This	01106682 (DE208000)

Description	Tracking ID
issue has been resolved in Historian 2024 by providing recursive browsing support for the OPC UA Collector.	
Previously, STA model was not supported for OPC Collector. This issue has been resolved in Historian 2024 by adding support of the STA model.	01097084 (DE208654)
Previously, when you attempted to query string tags in trend mode, there was an increase in the DataArchiver memory until it stopped or became unresponsive. This issue has been resolved in Historian 2024 through memory optimization.	01112199 (DE210018)
Previously, after Historian alarms and events backup, purge, and restore procedures, not all alarms were available. This issue has been resolved in Historian 2024.	01109547 (DE213006)
Previously, when you used tag type Array of string and multifield, memory spike was observed. This issues has been resolved in Historian 2024.	DE204209
Previously, due to memory leak issue, the Historian 2022 Server-Server Collector did not function. This issue has been resolved in Historian 2024 through memory optimization.	DE203744
Previously, in operating system of specific languages, the iFIX collector stopped working when tags were browsed in Historian Administrator. This issue has been resolved in Historian 2024 by updating the latest APIs.	01092706, 01093358 (DE206183)
Previously, when the Historian local security was enabled, and the LDAP user was added to 'ih_security_admins' group, the LDAP user was not able to query data from Historian and did not load Historian plugin on Configuration Hub. This issues has been resolved in Historian 2024.	01081620 (DE208053)
Previously, in a redundant configuration, if you set fail over triggers, the OPC UA collector stopped working on both the collector machines. This issue has been resolved in Historian 2024.	01090819 (DE208653)

Description	Tracking ID
Previously, in a redundant configuration, there were bad values observed in OPC UA Collector. This issue has been resolved in Historian 2024.	01066966 (DE199964)
Previously, in a redundant configuration, there were bad values observed in OPC UA Collector and lot of logs were created. This issue has been resolved in Historian 2024.	01080450 (DE201897)
Previously, the MQTT Collector had memory leak. This issue has been resolved in Historian 2024.	01100809 (DE206909)
Previously, the OPC client ReadRaw call caused Server to fragment memory. This issue has been resolved in Historian 2024.	01112205 (DE210166)
Previously, the collector HDA became unresponsive after adding new tags. This issue has been resolved in Historian 2024.	01094822 (DE205288)
Previously, the OPC Classic HDA Collector restart took more time than expected. This issue has been resolved in Historian 2024.	01090894 (DE205285)
Previously, the OPC Classic HDA Collector was failing with Geo SCADA, bot being on the same machine. This issue has been resolved in Historian 2024.	01047010 (DE199907)
Previously, when you viewed the Last 10 Values of a tag using the OPC UA Collector in Historian Administrator, the data values were reported to be of bad quality, although, the values came from another good tag. This issue has been resolved in Historian 2024.	01111077 (DE210392)
Previously, you were able to enter a Scada Buffer Duration value beyond the actual supported maximum value in the Scada Buffer Duration(Days) field. This issue has been resolved in Historian 2024 by adding a conditional check on the maximum value that is being entered.	01100502 (DE208287)
Previously, when using the OPC UA HDA Collector, tags with bad quality in the Archive were incorrectly shown as having good quality. This issue has been resolved in Historian 2024.	01074939, 01082827 (DE202695)
Previously, the Filtered Data window screen in Excel Add-in was very small. This issue has been resolved in Historian 2024 by increasing the dimension (Height, Width, Top, and Left).	01071028, 01071216, 01084176, 01096784, 01098978 (DE173096, DE199256)

Description	Tracking ID
Previously, when you query Alarms and Events, the Perform_Comment field was blank, although it existed in the database. This issue has been resolved in Historian 2024.	01095954, 01085812 (DE205472, DE205095)
Previously, restoring .zip archives from Historian 7.1 to a Historian 2022 server resulted in an empty archive. This issue has been resolved in Historian 2024.	01048625 (DE199965)
Previously, the OPC UA collector stored the data quality as 'GOOD' when the actual quality was BAD. This issue has been resolved in Historian 2024.	01019528 (DE181224)
Previously, there were some differences in data retrieval using the interpolated or calculated mode between Historian versions 3.1 and 9.1. This issue has been resolved in Historian 2024.	01048854 (DE201650)
Previously, both tags, one of type 'Byte' and the other of type 'Quad Integer', were incorrectly returning same value for the datatype when queried through the User API for properties. This issue has been resolved in Historian 2024.	01055391 (DE199962)
Previously, the configuration manager became unresponsive on primary node unexpectedly, preventing the users from adding tags. This issue has been resolved in Historian 2024.	01072354 (DE212949)
Previously, although the OPC UA Data Access Collector was able to connect and browse some folders but could not see the items that are located under sub-folders. This issue has been resolved in Historian 2024.	01114602 (DE210148)
Previously, the Data Archiver stopped working frequently and there was no information in the log. This issue has been resolved in Historian 2024.	01107015 (DE212951)
Previously, when Historian server stopped working, restarting the services caused the Configuration manager to become unresponsive. This issue has been resolved in Historian 2024.	01107511 (DE209451)
Previously, when using the Excel Add-in for Current Value and Raw Data, if the tag quality was 'BAD', then BAD was displayed instead of	01058496 (DE199960)

Description	Tracking ID
the actual value in the Value column. This issue has been resolved in Historian 2024.	
Previously, when using Condition Based Collection, the Historian OPC Collector stopped working. Also, excessive logs were created. This issue has been resolved in Historian 2024.	1043533 (DE196097)
Previously, when you ran an Interpolated Query in Excel Add-in by setting a specific time interval, the query returned incorrect value. This issue has been resolved in Historian 2024.	1065803 (DE199958)
Previously, in Excel Add-in, the Calculated Data with Query Criteria as String returned incorrect values. This issue has been resolved in Historian 2024.	01031714 (DE198804)
Previously, when the connection to the OPC UA Server was lost, the OPC UA Collector was displaying the tag quality as GOOD, even though the actual quality was BAD. This issue has been resolved in Historian 2024.	1052808 (DE200995)
Previously, on Non-web Admin, when viewing the Default Collector Compression Timeout setting, the value was not visible or updated correctly if the Deadband type was set to Absolute. This issue has been resolved in Historian 2024.	01083360, 1009963 (DE203189)

Known Issues and Limitations

Table 1. Upgrade Related Known Issues

Description	Tracking ID
<p>Upgrading only the Client Tools to 2024 from an older version upgrades the Historian Server, but does not include the MTLS files.</p> <p>Workaround: When upgrading Client Tools to 2024, ensure that you also upgrade the Historian Server to 2024.</p>	DE208482
<p>In a Historian server 2023, AlarmArchiver 2023, and Collectors 2023 setup, if you upgrade only the Alarm archive to 2024, and start the collectors, the collectors do not start.</p>	DE211329

Table 1. Upgrade Related Known Issues (continued)

Description	Tracking ID
<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-bottom: 10px;">  Note: This is also applicable to an upgrade of Historian 2022, AlarmArchiver 2022, and Collectors 2022 setup to 2024. </div> <p>Workaround:</p> <ul style="list-style-type: none"> • Along with the AlarmArchiver, you must upgrade the Historian server to 2024. -OR- • If you do not use MTLs, disable it. 	
<p>If you update AlarmArchiver from 9.1 Alarms & Events to 2024 Alarms & Events, without updating Historian server to 2024, the Data Archiver will not start.</p> <p>Workaround: Along with the AlarmArchiver, you must upgrade the Historian server to 2024.</p>	DE206514
<p>In a 9.0 or 9.1 standard Historian, Alarm Archiver, and AEDB SIM (if any) setup, when you upgrade the Alarm Archiver to 2024, the Data Archiver will also get upgraded to 2024.</p>	DE210847
<p>When you upgrade Web-based clients to Historian 2024 on a non-English operating system, you will see port conflicts that do not allow you to proceed.</p> <p>Workaround: Use the silent installation method to install the Historian Web-based clients.</p>	DE210880
<p>Port conflict occurs when you upgrade Web-based Clients from 2023 to 2024, on a non-English operating system.</p>	DE212901

Table 2. Path Related Issues After Install or Upgrade

Description	Tracking ID
<p>Even if the Historian server is not installed on the C: drive, RemoteCollectorConfigurator.exe is installed in C:\Program Files\GE Digital\NonWebCollectorInstantiationTool.</p>	DE212800
<p>The File collector cannot be processed after upgrading from version 2022 to version 2024.</p>	DE210946

Table 2. Path Related Issues After Install or Upgrade (continued)

Description	Tracking ID
<p>If you installed Calculation collector or Windows Performance collector using either iFIX Proficy installer or CIMPLCITY Proficy installer, they fail to start after you upgrade them to 2024.</p> <p>Workaround: After you upgrade the collectors, copy the collector files to the initial install directory. That is, <code>C:\Program Files (x86)\Proficy\GE Digital\</code>.</p>	516236

Table 3. Security Related Known Issues

Description	Tracking ID
<p>In a setup where you installed Historian collectors along with client tools using the Proficy installer, such as iFIX Proficy installer, if you uninstall the client tools alone, the created MTLS registry gets removed, leaving the MTLS folder intact. This prevents you from using MTLS security.</p>	DE212965
<p>The POSTGRES and Proficy Authentication (UAA) passwords are admissible in the Historian Web Components log.</p>	DE212644

Table 4. Other Known Issues

Description	Tracking ID
<p>If you import tags, along with their CreationTime and CreationUser, that were exported from Configuration hub, the Excel Add-in displays the "Proficy Historian Import Tags Error".</p> <p>Workaround: You must manually remove the CreationTime and CreationUser columns in the exported file before importing it.</p>	DE207159
<p>After you create a Data Attribute Enumerated Set in Configuration Hub, and then edit it using Historian Administrator, the DATA ATTRIBUTE ENUMERATED SET field is changed to False in Configuration Hub.</p>	DE209931
<p>When you use the Python collector to convert a value to boolean type, the results are provided in string format.</p> <p>Workaround: When you convert a value to boolean type, you must store the results as <code>Result = bool(Historian.CurrentValue('TP.Simulation00001'))</code></p>	

Table 4. Other Known Issues (continued)

Description	Tracking ID
Configuration Hub is not able to discover and add a system with Strict client and collector authentication enabled.	DE211901
<p>In Configuration Hub with LDAP and UAA setup, where the security groups are stored in the Domain Controller, the Tags and Data store Security Domain groups are not available for selection when assigning security group to a data store.</p> <p>Workaround: You can create the required security groups locally in Windows. This will ensure that the group becomes available for selection in Configuration Hub.</p>	DE211554
The trend decimal values in Configuration Hub are different from those in Historian Administrator.	DE212903
In Historian Interactive SQL, the sampling mode "rawbyfiltertoggle" is not returning the expected output.	DE212904
Collector Compression is not working as expected for the Calculation collector.	DE212897
In an enterprise setup, when you remove an archive from the system using Configuration Hub or Historian Administrator, the archive is being removed, but it is not being zipped and placed in the <code>Archives\Offline</code> directory.	DE208001
When you add a Server-to-Server Distributor collector instance and try to access it using Configuration Hub in the Source Historian Server machine, it fails to fetch the instance details, and an error is being displayed.	DE213348
<p>Adding tags to the Server-to-Server Distributor Collectors using Configuration Hub is not functioning correctly.</p> <p>Workaround: Add tags to the Server-to-Server Distributor Collector using Historian Administrator connected to Source Historian Server.</p>	DE213362/ DE213694
<p>When using older Historian collectors to connect to Configuration Hub 2024, an error is displayed, and the Interface Details section of the collectors is not loaded.</p> <p>Workaround: Upgrade all collectors to 2024, or install the 2024 Remote Collector Management Agent from the 2024 ISO on the Collector machine.</p>	DE213981


Table 5. Limitations

Description	Tracking ID
Collector compression is not automatically applied to tags created for an MQTT Sparkplug B collector instance that was added with collector compression enabled.	DE212048
Hierarchical browsing of tags is not supported for an OPC collector connected to an iFIX source.	DE204135
Unable to import more than 50000 tags to Historian server for the OPC UA collector using Excel Add-in. Workaround: It is recommended to add less than 30000 tags for a collection interval of 1 second or more.	DE212906


Chapter 2. Getting Started Guide

Overview of Historian


Proficy Historian is a high-performance data archiving system designed to collect, store, and retrieve time-based information at an extremely high speed. The following diagram shows an HMI or an OPC server from which data is collected and stored in Historian.



You can collect data from multiple SCADA systems and various applications, and store them in a central Proficy Historian server.



You can then use various clients to fetch and analyze this data.



Historian contains the following main components:

- **Data collectors:** Collect and analyze the tag data.
- **The Historian server:** Stores tag data.
- **Clients:** Retrieve tag data from the Historian server using APIs.

For information on how these components work in a Historian system, refer to [System Architecture \(on page 69\)](#).

Data Collectors

Collectors are applications that collect data from a wide variety of applications such as iFIX, CIMPLICITY, OPC servers, OSI PI, and text files (.csv or .xml). This data is then stored in the Historian server.

In addition, Historian contains the Calculation and the Server-to-Server collectors. The Calculation collector performs calculations and analyses on Historian data and stores the results in tags on the server. The Server-to-Server collector has the same calculation capabilities as the Calculation collector, but it stores the results in tags on a remote server.

Most collectors can perform first-order deadband compression, a browse-and-add configuration, and store and forward buffering.



Note:

Standard collectors that are included as part of the product will not consume a client-access license (CAL). Other interfaces developed by customers or system integrators using the Collector Toolkit or APIs will consume a CAL for each instance or connection.

Bi-Modal Collectors:

The Historian data collectors can send data to an on-premises Historian server as well as cloud destinations such as Google Cloud, Azure IoT Hub, AWS Cloud, and Predix Cloud. Therefore, these collectors are called bi-modal collectors. The following collectors, however, are not bi-modal collectors; they can send data only to an on-premises Historian server:

- The Calculation collector
- The File collector
- The HAB collector
- The iFIX Alarms and Events collector
- The OPC Classic Alarms and Events collector
- The OSI PI Distributor
- The Python collector
- The Server-to-Server distributor

The Historian Server

The Historian server is the central point for managing all of the client and collector interfaces, storing data and (optionally) compressing and retrieving data.

In the Historian server, data is stored in files called data archives. These files contain all the tag data gathered during a specific period of time (for example, time-based archives such as daily archives). They have the .iha extension.

You can store data of various data types such as Float, Integer, String, Byte, Boolean, Scaled, and binary large object data type (BLOB). The source of the data defines the ability of Historian to collect specific data types. If you have the license to store the alarms and events data, the server also manages the storage and retrieval of OPC Alarms and Events in a SQL Server Express.

You can further segregate your tags and archives into data stores. A data store is a logical collection of tags used to store, organize, and manage tags according to the data source and storage requirements. A data store can have multiple data archives, and includes logical and physical storage definitions.

The primary use of data stores is segregating tags by data collection intervals. For example, you can put name plate or static tags where the value rarely changes in one data store, and put process tags in another data store. This can improve the query performance.

The Historian Data Archiver is a service that indexes all the data by tag name and timestamp and stores the result in an .iha file. The tag name is a unique identifier for a tag (which is a specific measurement attribute). For iFIX users, a Historian tag name normally represents a Node.Tag.Field (NTF). Searching by the tag name and time range is a common and convenient way to retrieve data from Historian. If you use this technique to retrieve data from the archive files, you need not know which archive file contains the data. You can also retrieve data using a filter tag.

Clients

Clients are applications that retrieve data from the archive files using the Historian API.

The Historian API is a client/server programming interface that maintains connectivity to the Historian Server and provides functions for data storage and retrieval in a distributed network environment.


System Architecture

Standard or Stand-Alone Historian Architecture:

In this type of system, there is a single Historian server. It offers the following unique capabilities and benefits for a sustainable competitive advantage:


- Built-in data collection
- Good read/write performance speed
- Enhanced data security

The following image shows the architecture of a stand-alone Historian system (single server):



Horizontally Scalable Historian system:

In addition to the capabilities of a stand-alone Historian system, a horizontally scalable one offers data redundancy and high availability. You can have mirroring of stored data on multiple nodes to provide high levels of data reliability. Data mirroring also involves the simultaneous action of every insert, update, and delete operations that occur on any node. You can spread the data collection, server, administration, and client data retrieval functions across various nodes.




In a typical data mirroring scenario, one server acts as a primary server to which the clients connect. To create a mirror, you must add mirror nodes and establish a data mirroring session relationship between the server instances. All communication goes through Client Manager, and each Client Manager knows about the others.

When a client (either a writing collector or reading client) connects to the Client Manager, it gathers information about each Client Manager, along with all archive, tag, and collector configuration information, from the Configuration Manager, and stores this information locally in its Windows Registry.


A relationship is then established between each remote client and a single Client Manager, which directs read and write requests across the other mirrors. If that relationship is broken, it will establish a new relationship with the next available Client Manager, which assumes the same responsibilities. This bond is maintained until that Client Manager is unavailable, and then the process of establishing a relationship with another Client Manager is repeated.

When more than one node is running, the Client Manager uses a "round robin" method between the good nodes to balance read loads. Each read request is handled by a node as a complete request.

Writes are sent independently but nearly simultaneously to any available data archiver so that the same tag shares a common GUID, name, timestamp, value, and quality as passed to it by the collector.



The following diagram shows the architecture of a horizontally scalable Historian system.



System Components

A typical Historian system contains components for the following functions:

- Data collection/migration
- Data storage
- Data management, analysis, and monitoring
- Data retrieval

All these components communicate with the Historian server through the Historian API. This topic describes the functions performed by each component.

Data Collection/Migration Components

Data collection/migration components are used to collect data from various sources and ingest the data into a Historian server (or to cloud). The following data collection/migration tools are used in Historian:

Data Collectors

Data collectors gather data from a data source based on a schedule or an event, process it, and forward it to the Historian server or a web socket for archiving. The following collector functions are common across all types of collectors (except the File collector):

- Automatically discovering available tags from a data source and presenting them to Historian Administrator and Configuration Hub.
- Providing options to send data to an on-premises Historian server or to cloud through a web socket connection
- Performing a first-level of data compression (collector compression).
- Responding to control requests, such as requests to pause or resume data collection.
- Maintaining a local cache of tag information to sustain collection while the server connection is down.
- Buffering data during loss of connection to the server and forwarding it to the server when the connection is restored.
- Optionally, automatically adjusting timestamps for synchronizing collector and archiver timestamps.
- Supporting the timestamp of both the collector and the device, as applicable.
- Scheduling data polling for a polled collection.

For mission-critical data collection, you can set up redundant collectors. Historian includes a mirroring option for high availability and load balancing, so the data is available all the time.

The File Collector

A File collector imports .csv and .xml files into the Historian server. These files can contain data, alarms, tag names, or other configuration information, and messages that you can import with a File collector.

The Extract, Transform, and Load Tools

Transferring data from one Historian server to another is typically performed by the data collectors. These tools provide a connected streaming data transfer mechanism (except the calculation and file transfer collectors). In a system where a steady network connection is not possible or not cost-effective, a periodic file-oriented data transfer is preferred. The Historian ETL tools consist of a comprehensive set of file-oriented data extraction, transfer, and loading tools.

Migration Tools

Migration tools are used to migrate existing Historian configuration and data and iFIX Alarms and Events collector data to the Historian server. Tags, collection rates, and deadbands for tags configured in Historian can be transferred by the migration tools.

The Collector Toolkit

Collector Toolkit is used to develop a customized collector. You can use Collector Toolkit to write programs that integrate with Historian and leverage the same configuration tools, redundancy schemes, and health monitoring as the collectors. It collects data and messages from a data source and writes them to a data archiver. Each deployment of a collector developed on the Collector Toolkit consumes a client access license (CAL).

Data Storage, Analysis, and Maintenance Components

Data collected by the collection/migration components is stored in the Historian server (or cloud). You can then analyze and maintain the data using the following components:

Historian Alarms and Events

Historian Alarms and Events provides tools to collect, archive, and retrieve alarms and events data in Historian.

Historian Administrator *(on page 822)*

Historian Administrator provides a graphical user interface for performing Historian maintenance functions in a Windows environment including:

- Tag addition, deletion, and configuration.
- Maintaining and backing up archive files.

- Data collector configuration.
- Security configuration.
- Searching and analyzing system alerts and messages.
- Configuring the Calculation collector to create a new tag based on calculations, and storing the result as time series data.
- Setting up your OPC Classic HDA server and OPC UA HDA server.

Historian Administrator

The Web Admin console provides a dashboard, which displays the health of the system in one convenient location. You can view the following diagnostics details:

- **Data node diagnostics:** Displays the Historian servers connected to the system.
- **Collector diagnostics:** Displays the details of the faulty collectors.
- **Client diagnostics:** Displays the top five busiest clients connected to the system.

The dashboard provides interactive configuration management, which helps you configure mirror nodes, tags, collectors, data stores, and archives. However, the functionality of the Calculation collector and the ability to configure OPC HDA servers are not included in the Web Admin console.

The Web Admin console uses a CAL.

The Historian Server

The Historian server performs the following tasks:

- Manages all system configuration information.
- Manages system security, audit trails, and messaging.
- Services write and read requests from distributed clients.
- Performs final data compression.
- Manages archive files.

Historian Diagnostics Manager

The Historian Diagnostics Manager monitors the health of the Historian system and executes a few rules on the nodes, collectors, and clients, and generates the appropriate fault record. The details of these faults are displayed in the Web Admin console.

The following are the faults and their severity level:

Fault Type	Fault Description	Fault Level
Collector Status Fault	Generated when the collector goes to the Unknown or Stopped state.	Error
Collector Overrun Fault	Generated when at least one overrun occurs on a collector in last 24 hours.	Warning
Collector OutOfOrder Fault	Generated when at least one OutOfOrder occurs on a collector in last 24 hours.	Information
Collector StoreForward Fault	Generated when the collector Last Data Sample Time Stamp is delayed by more than an hour.	Information
Collector ConnectDisconnect Fault	Generated when the collector is Disconnected and connected at least once in last 24 hours.	Information
Service DiskSpace Fault	Generated when a node disk space is about to reach its free space limit.	Warning
Client InActive Fault	Generated when a client is not active for the last one hour.	Information
Client BusyRead Fault	Generated when the client makes relatively more number of reads per minute.	Information
Client BusyWrite Fault	Generated when the client makes relatively more number of writes per minute.	Information
Client TimedOutRead Fault	Generated when the client makes a timed out read query.	Warning

Client Manager

Client Manager acts as the client connection manager and message router for the system. It examines messages and forwards them to the correct data archiver or to Configuration Manager. This service is deployed only for mirrored systems.

Configuration Manager

Configuration Manager maintains and distributes the entire system configuration. There can be multiple Historian nodes but only one Configuration Manager. This Configuration Manager node is used to store system configuration, such as tag names, collector names, and Historian node names. This service is deployed only for mirrored systems.

Configuration Hub

Configuration Hub allows you to manage the Historian systems and its components, including:

- Creating a Historian system, and adding its components
- Creating mirror groups
- Creating and managing data stores
- Installing and managing collector instances

Using Configuration Hub, you can achieve high availability of servers in a Historian system.

Remote Collector Manager

Typically, collectors are distributed geographically, and so, accessing them can be challenging and not cost-effective. To overcome this challenge, the Remote Collector Management agent provides the ability to manage collectors remotely.

Historian Tomcat Container

An instance of Tomcat is used exclusively by Historian as an open source Java-based web server to support the Web Admin console and Trend Client. It supports SSL and the use of certificates for enhanced security.

Proficy Authentication Tomcat Container

An instance of Tomcat is used exclusively as an open source Java-based web server to support external Proficy Authentication.

Proficy Historian PostgreSQL Database

An instance of PostgreSQL is used exclusively to store tag names to improve searching for tags in the Trend tool and Web Admin console.

Proficy Authentication PostgreSQL Database

An instance of PostgreSQL is used exclusively to store Proficy Authentication details.

Reverse Proxy Service

Provides secure connection by supporting https protocol.

Indexing Service

The indexing service speeds up search results. It periodically queries the database, creates a tag index, and stores the information in the PostgreSQL database instance.

Excel Add-in for Historian

Excel Add-in is a very useful tool for presenting and analyzing data stored in archive files. Using this tool, you can design custom reports of selected data, automatically process the information, and analyze the results. You can also use it for performing tag maintenance functions in Historian, such as adding tags, importing or exporting tags, or editing tag parameters.

Excel Add-in for Operations Hub

The Excel Add-in for Operations Hub enables you to query historical data of objects and object types defined in Operations Hub.

Customers purchasing Historian Standard or Enterprise licenses now receive a no-cost license for the Operations Hub server and the Historian Analysis run-time application. The Operations Hub server enables customers to define an asset model including tag mapping. The Historian Analysis application is a pre-built Operations Hub HTML5 application that enables users to do advanced trend analyses, including the ability to make annotations.

The OPC Classic HDA Server

The OPC Classic HDA server reads the raw data stored in Historian and sends it to the connected OPC clients. The Historian OPC Classic HDA server complies with OPC Server HDA 1.20 standards.

Historian SDK

The Historian Software Development Kit (SDK) is designed for writing Visual Basic (VB) or Visual Basic for Applications (VBA) scripts. Using the SDK, you can develop your own scripts to perform selected repetitive or complex tasks or to make your own custom user interface. To use the SDK, create a VB/VBA project with the SDK as a project reference.

Data Retrieval Components

Data retrieval components are used to retrieve data that is stored in the Historian server. Historian contains the following data retrieval components:

Historian Alarms and Events

Historian Alarms and Events provides tools to collect, archive, and retrieve alarms and events data in Historian.

Client Manager

Client Manager acts as the client connection manager and message router for the system. The Client Manager will examine messages and forward them to the correct Data Archiver or to the Configuration Manager. This service is deployed only for mirrored systems.

Configuration Manager

Configuration Manager maintains and distributes the entire System configuration. There can be multiple Historian nodes but only one Configuration Manager. This Configuration Manager node is used to store system configuration, such as tag names, collector names and Historian Node names. This service is deployed only for mirrored systems.

Proficy Authentication Tomcat Container

An instance of Tomcat is used exclusively by Historian as an open source Java-based Web server to support an external Proficy Authentication.

Proficy Historian PostgreSQL Database

An instance of PostgreSQL is used exclusively by Historian to store tag names to improve searching for tags in the Trend tool and Web Admin console.

The OPC Classic HDA Server

The Historian OPC Classic HDA server reads the raw data stored in Historian and sends it to the connected OPC Classic HDA collectors. The Historian OPC Classic HDA server is in compliance with OPC Server HDA 1.20 standards.

The OPC UA HDA Server

The Historian OPC UA HDA server retrieves historical process data from Proficy Historian, and sends it to OPC UA HDA clients. It dynamically updates the clients when tags are added and/or deleted in Historian. Clients that comply with this specification can connect to the OPC UA HDA server to retrieve data from Historian.

For information, refer to the OPC UA HDA Server section of the online documentation.

User API

The Historian User API is intended to provide high speed read/write access to Historian data and read access to Historian tags. There is no access to alarms, events, or messages.

Since the Historian User API is the basic building block for connectivity, all Historian functions, including data collection, administration, and data retrieval, use the Historian API. You can use the Historian User API to connect to a local Historian server or a remote one (by just providing the IP address or host name of the server).

Use the API to develop applications in C or C++, which read and write data to the Historian server when the Historian SDK and Historian OLE DB do not meet your project requirements for performance or programming language.

Historian allows you to develop both 32-bit and 64-bit User API programs.



Note:

If you want to build a 32-bit User API program on a 64-bit operating system, then you need to rename the `ihuapi32.lib` to `ihuapi.lib` and include it in your program.

REST APIs

Historian includes a REST API to connect your Java Web-based Clients with Historian data.

Historian SDK

The Software Development Kit (SDK) is designed for writing Visual Basic (VB) or Visual Basic for Applications (VBA) Scripts. Using the SDK, you can develop your own scripts to perform selected repetitive or complex tasks or to make your own custom user interface. To use the SDK, create a VB/VBA project with the SDK as a project reference. Refer to the *SDK Help* system for more information.

Historian Client Access API

The Historian Client Access API is a .NET Core assembly that interacts with Historian from any .NET Core applications. Since it works with .NET Core, it is platform-independent - you can use it on any operating system, such as Windows, Linux, and Mac OS.



Note:

You can still use the old Client Access API, which is a .NET assembly. It is installed when you install Client Tools.

JAVA APIs

Most open source, quick development applications rely on JAVA as their programming language. To enable easier integration with Historian, JAVA APIs are provided. The JAVA APIs support 64-bit Windows Operating Systems.

About the Historian Server

The Historian server is the central point for managing all of the client and collector interfaces, storing data and (optionally) compressing and retrieving data.

In the Historian server, data is stored in files called data archives. These files contain all the tag data gathered during a specific period of time (for example, time-based archives such as daily archives). They have the .iha extension.

You can store data of various data types such as Float, Integer, String, Byte, Boolean, Scaled, and binary large object data type (BLOB). The source of the data defines the ability of Historian to collect specific data types. If you have the license to store the alarms and events data, the server also manages the storage and retrieval of OPC Alarms and Events in a SQL Server Express.

You can further segregate your tags and archives into data stores. A data store is a logical collection of tags used to store, organize, and manage tags according to the data source and storage requirements. A data store can have multiple data archives, and includes logical and physical storage definitions.

The primary use of data stores is segregating tags by data collection intervals. For example, you can put name plate or static tags where the value rarely changes in one data store, and put process tags in another data store. This can improve the query performance.

The Historian Data Archiver is a service that indexes all the data by tag name and timestamp and stores the result in an .iha file. The tag name is a unique identifier for a tag (which is a specific measurement attribute). For iFIX users, a Historian tag name normally represents a Node.Tag.Field (NTF). Searching by the tag name and time range is a common and convenient way to retrieve data from Historian. If you use this technique to retrieve data from the archive files, you need not know which archive file contains the data. You can also retrieve data using a filter tag.

The Historian server performs the following tasks:

- Manages all system configuration information.
- Manages system security, audit trails, and messaging.
- Services write and read requests from distributed clients.
- Performs final data compression.
- Manages archive files.

About Tags

A Historian tag is used to store data related to a property.

For example, if you want to store the pressure, temperature, and other operating conditions of a boiler, a tag will be created for each one in Historian.

When you collect data using a collector, tags are created automatically in Historian to store these values. These tags are mapped with the corresponding properties in the source.

For example, suppose you want to store OSI PI data in Historian. You will specify the OSI PI tags for which you want to collect data. The OSI PI collector creates the corresponding tags in Historian, and it stores the values in those tags.

You can also choose to create tags manually (for example, to store the result of a calculation performed by the Calculation collector).

Prerequisites

Setting Up the Historian Environment

Identify the computers that will function as your clients, data collectors, administration workstations, and archiver.

1. Set up each computer.
See [Hardware Requirements \(on page 87\)](#), and refer to the user manual that accompanies each component for the setup information.
2. Use a login account with administrator rights so that you can install Historian later.
See [Software Requirements \(on page 92\)](#), and refer to the user manual that accompanies each software product for the setup information.
3. Activate the license key on your Historian server node. Additional licenses may be required on other nodes (such as mirroring and collector nodes) depending on your configuration requirements. See [Activate the Historian License \(on page 82\)](#).
4. Disable the guest account in Windows security if you want to limit authentication to known Windows users only.
5. Ensure that the protocols and ciphers (TLS 1.0, 1.1, and 1.2) required to install Historian are available.

Activate the Historian License

Advantage Licensing is the software system for activating and managing product licenses. Using the tools in licensing and our Customer Center website, you can view, activate, and manage licenses at your site.

Using Advantage Licensing, you can:

- View current licenses for the products residing on a computer.
- Choose a licensing method (Internet, local intranet, or file-based).
- Change licenses (Activate, Return, Refresh).

Historian is available in three license types:

- Essentials
- Standard
- Enterprise

The Essentials edition is included as the on-board Historian with the purchase of some iFIX and SIMPLICITY licenses, and cannot be licensed or sold outside of those packages. Essentials edition customers who require options available in the Standard or Enterprise editions or require more than a 1000 tags must purchase either a Standard or Enterprise License with the appropriate tag count.

Historian HD is sold and licensed separately from Historian. Historian HD provides the Historian user a standard method to move Historian tag configuration and historical archive data from a Windows environment to a Hadoop Distributed File System (HDFS). HDFS is the primary distribution storage used by Hadoop applications.

A component that is used only by the Historian HD license is installed with your Historian installation: the Historian Archive Ingestion service. This service is reserved for use only with the Historian HD big data analytics platform and is listed as Manual under Startup Type. Stopping this service does not impact the Historian functionality. Unless you are licensed to use Historian HD, do not attempt to start or monitor this service, as it may impact the ability to run the Historian Data Archiver service.

The following table provides information on the availability of each Historian component for each license type. Optional indicates that the component is not available by default, but can be purchased separately.



Note:

For a Calculation collector and a Server-to-Server collector, you can either opt for standalone use of bi-modal collectors or add Enterprise collectors to the Standard Historian license. Using these options, you can quickly and easily send data from one Historian server to another or directly to Predix Timeseries. For information on the pricing, contact the Support team.

Component	Essentials	Standard	Enterprise	Distributed
Server Functionality				
Data modification	Yes	Yes	Yes	Yes
Client Access Licenses (CALs)	2	2500	2500	2500
Cluster support	No	Yes	Yes	Yes

Component	Essentials	Standard	Enterprise	Distributed
Collector redundancy	Optional	Yes	Yes	Yes
Horizontal scalability (data mirroring)	No	No	Yes	Yes
Data stores	5	10	20	20
Data stores expansion (200)	No	No	Optional	Optional
Digital / Enumerated / Array Tags	Yes	Yes	Yes	Yes
Distributed Historian	No	No	No	Yes
Electronic signatures	No	Optional	Optional	Optional
The Extract, Transform, and Load (ETL) tools	No	No	Yes	Yes
Fault-tolerant computer support	Yes	Yes	Yes	Yes
Maximum historical tags	1,000	50,000	20,000,000	20,000,000
Microsecond support	No	Yes	Yes	Yes
The OLE DB provider	Yes	Yes	Yes	Yes
The OPC Alarms and Events server	No	Optional	Yes	Yes
The OPC Classic HDA server	Yes	Yes	Yes	Yes
The OPC UA HDA server	No	Yes	Yes	Yes
The Historian server	Yes	Yes	Yes	Yes
Remote Collector Management	No	No	Yes	Yes
SCADA buffer (10000 tags, 200 days)	Yes	Yes	Yes	Yes
User-Defined multi-field tags	No	Yes	Yes	Yes
Client Functionality				
The Historian Model	No	Yes	Yes	Yes
The Historian Excel Add-in	Yes	Yes	Yes	Yes
Historian Administrator	Yes	Yes	Yes	Yes
Operations Hub Freemium	No	Yes	Yes	Yes
The Web Admin console	No	Yes	Yes	Yes

Component	Essentials	Standard	Enterprise	Distributed
Trend Client	No	Yes	Yes	Yes
Configuration Hub	Yes	Yes	Yes	Yes
Collector Functionality				
Wonderware Collector with the cloud option	No	Yes	Yes	Yes
The Calculation collector	No	Available as a part of the Enterprise Collectors option	Yes	Yes
Collector Toolkit SDK	No	Yes	Yes	Yes
The CygNet collector with the cloud option	No	Yes	Yes	Yes
Expressions	No	No	Yes	Yes
The File collector	No	Yes	Yes	Yes
The HAB collector	No	Yes	Yes	Yes
The iFIX collector	Yes	Yes	Yes	Yes
The MQTT collector	No	Yes	Yes	Yes
The MQTT Sparkplug B collector	No	Yes	Yes	Yes
The ODBC collector with the cloud option	No	Yes	Yes	Yes
The OPC Classic Alarms and Events collector	No	Optional	Yes	Yes
The OPC DA collector with the cloud option	Yes	Yes	Yes	Yes
The OPC Classic HDA collector with the cloud option	No	Yes	Yes	Yes
The OPC UA Data Access (DA) collector with the cloud option	No	Yes	Yes	Yes
The OSI PI collector with the cloud option	No	Yes	Yes	Yes
The OSI PI distributor	No	Yes	Yes	Yes

Component	Essentials	Standard	Enterprise	Distributed
The Python collector	No	Available as a part of the Enterprise Collectors option	Yes	Yes
The Server-to-Server collector with the cloud option	No	Available as a part of the Enterprise Collectors option	Yes	Yes
The Simulation collector	Yes	Yes	Yes	Yes
The Windows Performance collector	No	Yes	Yes	Yes

**Note:**

* Starting Historian 7.2, SCADA buffer count is increased from 2500 to 10000. Historian Essentials license includes 2500 buffered tags and a 200-day circular buffer if permanent storage is less than 1000 tags (that is, if CIMPLICITY points are 1500 and below). It includes 10000 buffered tags and a 200-day circular buffer if permanent storage is 1000 tags (that is, if CIMPLICITY points are 5000 and above).

To activate the Historian license:

1. If the license is already activated on your system, access License Client, select **Advanced > Clear license information on this computer**.
2. If you received an email containing an activation code, you must migrate to Advantage Licensing. Get the latest licensing software at <http://digitalsupport.ge.com>.

If you did not receive an activation code, follow the instructions about M4 keys at <http://digitalsupport.ge.com>.

3. Download the Historian software.
4. Install the licensing software.
5. Activate the Historian license.

Hardware Requirements

Table 6. Historian Server

Hard-ware Com-ponent	Standard Historian	Enterprise Histori-an, Data Mirroring
RAM	8 GB	16 GB or 32 GB (recommended)
Disk size	80 GB free hard-drive space	250 GB (minimum)
Processor type	Intel Core i3 or i5 or i7 CPU or an equivalent AMD Phenom CPU	Intel Core-i5, i7 family, or equivalent
CPU		Dual/Quad cores
CPU speed	2.4 GHz	2.8 GHz
Recom-mended CPU clock	2.4 GHz	2.8 GHz
Storage type		SAS SSD with RAID Level 0 config-ured
Operating system		<ul style="list-style-type: none"> • Microsoft® Windows® Serv-er 2022 (64-bit). • Microsoft® Windows® Serv-er 2019 (64-bit). • Microsoft® Windows® Serv-er 2016 (64-bit). • Microsoft® Windows® 11 (64-bit). • Microsoft® Windows® 10 (64-bit), Professional ,or En-terprise Edition.
Tags		Up to 50,000
Years of data online		1 year

Table 6. Historian Server (continued)

Hardware Component	Standard Historian	Enterprise Historian, Data Mirroring
Other requirements	<ul style="list-style-type: none"> • A DVD-ROM drive. • 100 Mbps TCP/IP-compatible network interface adapter for network communication and certain I/O drivers. 	

The size of a Historian server is determined by:

- The number of tags from which data is collected. The number of tags is an indicator of the number of concurrent users likely to access the system. The primary factor is server memory requirements; CPU load is a secondary factor. If the number of concurrent users is significantly different from the suggested guidelines, adjust server memory size accordingly.
- The rate of alarms and events collection.
- The frequency of data collection.
- The amount of data you want to keep online.

The following table provides the recommended hardware components for a Historian server with the Standard license based on the number of tags that you want to use. These recommendations may vary based on years of data online, update rate, data compression setting, and other tag configuration parameters.

Hardware Component	Less Than 10,000 Tags	10,000 to 50,000 Tags	100,000 to One Million Tags	One Million to Two Million Tags	Two Million to Five Million Tags
RAM (in GB)	8 GB/16 GB (recommended for a single node setup)	16 or 32	16 or 32	16 or 32	32 or 64
Disk Size (in GB)	100 or 250	250	250	500	500
Processor Type	Intel Core-i5, i7 family, or equivalent	Intel Core-i5, i7 family, or equivalent	Intel Xeon (56xx, E5 family or AMD Opteron 42xx/62xx family)		
CPU	Dual/Quad core	Dual/Quad core	Dual/Quad core	2-socket	2-socket or 4-socket

Hardware Component	Less Than 10,000 Tags	10,000 to 50,000 Tags	100,000 to One Million Tags	One Million to Two Million Tags	Two Million to Five Million Tags
CPU Speed (in GHz)	2.8	2.8	2.8	2.6	2.6
CPU clock speed (in GHz)	2.8	2.8	2.8	2.6	2.6
Storage Type	SAS SSD with RAID level 0 configured	SAS SSD with RAID level 0 configured	Direct-attached or shared storage with SAS enterprise class drives. Hardware RAID controller with cache memory. SAN recommended over NAS		High speed shared storage with SAS or SSD drive types. Hardware RAID controller with cache memory. SAN recommended over NAS.
Years of data online	1	1	1	1	1



Note:

- The Historian server runs only on 64-bit versions of Windows.
- When possible, for performance reasons, consider using computers with multiple disk drives so that archives and buffers can be given their own drive. Or, multiple data stores can each have their own drive.
- Sustained event rate is 60-100 million samples per minute.
- Historian supports Intel Core i3, i5, i7 Duo based processors as long as they are compatible with the operating system.
- Historian does not support Titanium processors.

System performance may vary depending on the hardware specifications, operating system, and tuning parameters. The following table provides sample hardware specifications for medium-sized and large-sized servers.

Hardware Component	For a Medium-Sized Server	For a Large-Sized Server
Processor type	Intel Xeon 5540	Intel Xeon E5-2670 or E5-4650
CPU	Dual socket	Dual socket or quad-socket
CPU speed (in GHz)	2.5	2.7
RAM (in GB)	64	256

Table 7. Collectors

Hardware Component	Recommendation
RAM	8 GB
Disk size	80 GB
Historian collectors	32-bit or 64-bit

 **Note:**
 Wonderware Collector supports 64-bit only



Note:

- Historian Collectors work as 32-bit applications on a 64-bit Windows operating systems using WoW64 mode (Windows-on-Windows 64-bit). However, you can read and write data from a 64-bit Historian Server.
- RAM and Disk Size required may vary based on the collectors available on the system.
- Recommended number of tags per collector is 20 to 30K.
- For iFIX systems, count each Node.Tag.Field (NTF) as a separate tag when you determine the size of the system. For example, FIX.FIC101.F_CV and FIX.FIC101.B_CUALM (current alarm) both count as tags, even though they are derived from the same iFIX tag.

Microsoft Windows Server

Many desktop-class computers are not certified to run Windows. Check the Microsoft website and your computer hardware vendor website for possible conflicts between your hardware and Windows server. These specifications are sufficient to meet the needs of a small pilot application. However, production system requirements may be significantly different depending on many application-specific factors. Please contact your product manager to review the requirements of your application.

Table 8. Microsoft Cluster Service

Hardware Component	Requirement
CPU speed, processor type, and RAM	A 2.6 GHz clock-speed Intel Core i3 or i5 or i7 or Xeon or equivalent AMD Opteron CPU with minimum 8 GB RAM.
Disk size	A 80 GB free hard-drive space and a 40 GB shared SCSI hard-drive (RAID preferred).
Other requirements	Two 100Mbit TCP/IP-compatible network interface adapters for network communication and certain I/O drivers (One for public network, another for private network).



Note:

The configuration of each server added to the cluster must be identical to the other servers in the cluster.

Table 9. Data Mirroring and Redundancy Service

Hardware Component	Requirement
Operating system	A 64-bit Windows operation system.
RAM	Minimum 8 GB RAM. <div data-bbox="479 1480 1421 1659" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  <p>Note: If you are using single node setup, it is recommended to use 32 GB RAM.</p> </div>
Processor type	A dual core processor.

Ensure that you are using the same hardware requirement for the mirror node as well.

Network Speed

For a large Configuration Hub setup, it is recommended that the network speed is 1 GBPS.



Note:

- If you are using a single node setup, then it is recommended to use 32 GB RAM.
- Ensure that you are using the same hardware requirement for the mirror node as well.
- You must have a minimum of 10 GB free space available for the data archiver to start.
- Many desktop-class computers are not certified to run Windows server. Check the Microsoft website and your computer hardware vendor website for possible conflicts between your hardware and Windows server. These specifications are sufficient to meet the needs of a small pilot application. However, production system requirements may be significantly different depending on many application-specific factors. Please contact your product manager to review the requirements of your application.

Software Requirements

This topic describes the minimum software requirements for Historian.

- **Operating System:** Historian requires one of the following operating systems, with latest service packs or revisions:
 - Microsoft® Windows® Server 2022 (64-bit)
 - Microsoft® Windows® Server 2019 (64-bit)
 - Microsoft® Windows® Server 2016 (64-bit)
 - Microsoft® Windows® 11 (64-bit)
 - Microsoft® Windows® 10 (64-bit), Professional ,or Enterprise Edition.



Note:

The Historian server runs on a 64-bit Windows operating system only.

Historian 7.2 32-bit components such as Collectors, Excel Add-in 32-bit, Interactive SQL 32-bit, APIs, and Non-Web Administrator work as 32-bit application on 64-bit Windows operating systems using WoW64 mode (Windows-on-Windows 64-bit). However, you can read and write data from a 64-bit Historian Server.

If you use Historian 6.0 or later on Windows Server 2008 R2, you must go for a Full Installation and not Core Installation of Windows.

- **Network Interface Software:** The TCP/IP network protocol is required.
- **Microsoft®.NET Core or .NET Framework:** Historian requires the following .NET frameworks: To install the framework, you must configure your proxy server for internet access.
 - **Microsoft®.NET Core Framework 3.1:** This is required if you want to use the new Client Access API.
 - **Microsoft®.NET Framework 4.8:** This is required on the machine on which you will install the Excel Add-in for Operations Hub. In addition, this is required for Historian collectors.
 - **Microsoft®.NET Framework 4.6.1:** This is required for all the other Historian components. You can install it manually, or you will be prompted to download and install it while installing Historian.

**Note:**

If your machine is Firewall/proxy-enabled, Microsoft .NET Framework may not be installed automatically. In that case, before installing Historian, you must install Microsoft .NET Framework manually (if it is not available).

- **Microsoft® SQL Server®:** Historian requires one of the following 32-bit or 64-bit Microsoft® SQL Server® SQL server systems to configure archiving for alarms and events or to use Historian as a linked server:
 - Microsoft® SQL Server® 2022
 - Microsoft® SQL Server® 2019
 - Microsoft® SQL Server® 2017

**Note:**

The collation for your alarms and events database must match the collation of your SQL Server. This happens automatically by default unless the alarms and events database is moved to another SQL server.

- **Browser:** You can access the Web Admin console and Trend Client using the following browsers:
 - Firefox version 46 or later
 - Google Chrome version 92 or later

To access Configuration Hub, use Google Chrome only.

- **Screen Resolution:** You can access Configuration Hub, the Web Admin console, and Trend Client using the following screen resolutions:
 - 1280 x 1024
 - 1366 x 768

- **Microsoft Excel:** The Excel Add-in for Historian or the Excel Add-in for Operations Hub requires any of the following versions of Excel:
 - Microsoft® Excel® 2021 (32 & 64 bit)
 - Microsoft® Excel® 2019 (32 & 64 bit)
 - Microsoft® Excel® 2016 (32 & 64 bit)
 - Microsoft® Excel® 2013 (32 & 64 bit)

- **Web Server:** The web server requires the following applications:
 - Microsoft®.NET Framework 4.6.1
 - Historian Client Tools 7.0 or later
 - OLE DB, User API, and Historian Client Access Assembly

Compatibility with Other Products

Several other products work with Historian. The following is a general set of versions tested to work with the Historian 2024 product.

Product	Supported Version
CIMPLICITY	2022, 2023
iFIX	2022, 2023, 2024 beta
Proficy Plant Applications	2023, 2024 beta
Workflow	2.6 SP2
Proficy Operations Hub	2023.1, 2024 beta
Configuration Hub	2024
Proficy Authentication	2024
Dream Reports	2023 Patch 1
Habitat	5.12

Historian REST APIs are required to integrate between Historian and Operations Hub. Historian REST APIs are installed automatically when you [install Historian Web-based Clients \(on page 155\)](#).

Supported Regional Settings, Data Types, and Date/Time Formats

Supported Regional Settings

Historian supports the following regional settings available in Control Panel:

- Decimal symbol - one character
- Digit grouping symbol
- List separator - one character
- Time style
- Time separator
- Short date style
- Date separator

Supported Data Types

Data Type	Size
Single Float	4 bytes
Double Float	8 bytes
Single Integer	2 bytes
Double Integer	4 bytes
Quad Integer	8 bytes
Unsigned Quad Integer	8 bytes
Unsigned Single Integer	2 bytes
Unsigned Double Integer	4 bytes
Byte	1 byte
Boolean	1 byte
Fixed String	Configured by user.

Data Type	Size
Variable String	No fixed size.
Binary Object	No fixed size. Historian does not support the use of the Binary Object data type with the Data Collectors. Refer to the SDK online Help for more information on working with BLOB data types.
Scaled	2 bytes

Supported Date Formats

Historian supports the following short date formats, some of which may not be available in certain language versions of Windows:

- dd/mm/yy
- dd/yy/mm
- mm/dd/yy
- mm/yy/dd
- yy/dd/mm
- yy/mm/dd

Avoid changing the time style or short date style in regional settings to values that are outside of the standard styles provided.

Optimize Performance

You can optimize performance in the following ways:

- **Optimize virtual memory:** Through the use of paging files, Windows allocates space on your hard drive for use as if it were actually memory. This space is known as virtual memory. This topic describes how to optimize the virtual memory on the Historian archiver computer.



Note:

If the paging file is set to grow dynamically, your system may experience severe performance problems during runtime. To ensure optimal performance, the Initial Size and Maximum Size values for the paging file must be the same so that the paging file does not grow dynamically. For more information on creation and sizing of Windows paging files, refer to Microsoft Windows Help.

- **Optimize the server performance:** If the file sharing and printer sharing options on the computer on which you want to install Historian is set to maximize data throughput, it can lead to excessive paging when dealing with large files, which can interfere with applications like Historian. You can change these settings to optimize the performance.

1. To optimize virtual memory:
 - a. Access Control Panel, and then select **System > Advanced system settings > Advanced**.
 - b. Under **Performance**, select **Settings > Advanced**.
 - c. Under **Virtual Memory**, select **Change**.
 - d. In the **Initial size** and **Maximum size** fields, enter a value equal to three times your physical memory.
 - e. Select **Set**, and then select **OK**.
2. To optimize server performance:
 - a. Access Control Panel.
 - b. Select **Network and Sharing Center**.
 - c. Select the network that you use.
The **<network name> Status** window appears.
 - d. Select **File and Printer Sharing for Microsoft Networks**, and select **Properties**.
 - e. Select **Properties**.
 - f. Ensure that the **Maximize Data Throughput for Network Applications** option is selected.
 - g. Select **OK**.

Enable Trust for Proficy Historian for a Self-signed Certificate

During Historian installation, a self-signed certificate is generated that you use with Historian web applications. A self-signed certificate is a certificate that is signed by itself rather than signed by a trusted authority. Therefore, a warning appears in the browser when connecting to a server that uses a self-signed certificate until it is permanently stored in your certificate store. This topic describes how to ensure that Google Chrome trusts the self-signed certificate.

1. Using Google Chrome, access the site to which you want to connect.
A message appears to inform you that the certificate is not trusted by the computer or browser.
2. Select **Not Secure** in the URL, and then select **Certificate**.
The **Certificate** window appears.

3. Select **Certification Path**, select the root certificate, and then select **View Certificate**.
The **Certificate** window appears, displaying the **General**, **Details**, and **Certification Path** sections.
4. Select **Details**, and then select **Copy to File**.
5. Follow the on-screen instructions to save the certificate to a local file. Use the default format: **DER encoded binary X.509 (.CER)**.
6. Right-click the .CER file that you have exported, and select **Install Certificate**.
The **Certificate Import Wizard** window appears.
7. Select **Trusted Root Certificate Authorities**, and then select **OK**.



Note:

Do not let the wizard select the store for you.

A **Security Warning** window may appear. If it does, ignore the message by selecting **Yes**. The certificate is installed.

8. Restart the browser, and connect to the server.
9. Open the URL authenticated by the certificate.
If error messages do not appear, the certificate is successfully imported.

VMWare Support

Historian provides support for VMware ESXi server version 5.0 and later. The virtualization capability provided by VMware lets you run multiple virtual machines on a single physical machine, with each virtual machine sharing the resources of that one physical computer. Please be aware that while we have tested VMware ESXi 5.0 and above, issues with the VMware software or the virtualized environment are outside the scope of GE Vernova's responsibility. You must use VMWare Compatibility Hardware and Software before installing Historian 7.0 or greater Data Archiver on a Virtual Machine. For the current release, the only supported type of Proficy licensing for use with VMware is keyless (software) licensing.



Note:

VMware Player is not supported.



Important:

Advanced features of the ESXi server (such as VMotion, High Availability, and Clustering support) have not been tested with Historian.

For information regarding VMware compatibility and its supported software and hardware environments, refer to <http://www.vmware.com/resources/guides.html>.

VMWare Best Practices and Limitations

Disk Growth

To prevent disk growth during run time, make sure you pre-allocate the hard disk in your VMware image.



Important:

If the VMware disk needs to grow at runtime because of IHA growth or creation, the Data Archiver will be slowed. If there is not enough disk space on the host machine to grow the VMware disk, the archiver may lose data.

Suspended Images/Power Metered Images

ESXi servers have power meter functions and options as well as the ability to suspend images to conserve power. We do not recommend or support these functions due to the potential effects on the Guest operating system, specifically in regards to polling I/O and timely updates.

I/O Devices and Connections and VMware

There are a multitude of devices and methods of communications on the market. These devices may be used if you can successfully connect them from the virtual machine through the physical HOST, but we do not support the setup of that connection. Be aware that device drivers used to write to proprietary cards for the ESXi HOSTS as part of virtual device setup can cause issues.

USB Controller Limitations

The USB controller has these limitations when using Historian and VMware:

- Minimum virtual hardware version 7 is required.
- Only one USB controller of each type can be added to a virtual machine.
- The USB arbitrator can monitor a maximum of 15 USB controllers. If your system includes an additional number of controllers and you connect USB devices to these controllers, the devices are not available to be passed through to a virtual machine.
- You must add a USB controller to a virtual machine before you can add a USB device.
- You must remove all USB devices from a virtual machine before you can remove the controller

USB Device Limitations

USB devices have these limitations when using Historian and VMware:

- A virtual machine may have up to 20 USB devices attached to it; however, each unique USB device can only be attached to one virtual machine at a time.
- Unsupported USB devices may not interact as expected with other ESXi features.

Additional VMware Notes

GE Vernova cannot guarantee the performance of the Historian software in a virtualized environment due to the wide range of parameters associated with the hardware, configuration, memory settings, third-party software installations, and the number of virtual machines running; all of which can affect performance. Therefore, GE Vernova cannot provide support related to the performance of the Historian software running on a virtual machine if it is determined that the issue is related to the virtual environment. Also, GE Vernova does not provide support or troubleshoot a customer's virtual machine infrastructure.

It is the responsibility of you, the customer, to ensure that the performance of the Historian software and any third-party applications (especially those not recommended by GE Vernova) are adequate to meet the needs of your run mode environment. GE Vernova does not support issues related to functionality that is not available as a result of running in a virtual machine infrastructure. Examples include the functionality of card level drivers such as those for the Genius® family of drivers, the Allen-Bradley® DH/DH+ drivers, the Cyberlogic's MBX® Driver for the SA85 card, as well as functions requiring direct video access. Check with the vendor of your third-party application for support statements regarding that third-party product's ability to run in a virtualized environment.

For more detailed information regarding VMware specifications and requirements, visit the VMware web site: <http://www.vmware.com/resources/compatibility/search.php>.

Installation

Historian Installation Workflow

1. Design your system architecture.

Decide what collectors to instantiate on which nodes, which computers to designate as the Historian server and Historian Administrator, whether or not they will be web-based, and how much memory and disk space you can assign to buffers and archives. Record the computer names of each node.

2. Ensure that data sources are installed.
3. [Set up your Historian environment \(on page 82\)](#).

4. On the server node, launch the installer, select **Install Historian**, and follow the on-page instructions to [install Historian \(on page 105\)](#) on a single server or in a distributed environment.
5. [Activate your product license \(on page 82\)](#).
6. [Install the collectors \(on page 142\)](#).
7. Restart your computer if prompted to do so.
8. As needed, [install Web-based Clients \(on page 154\)](#).
9. Perform post install setup for MTLS features, by installing certificates. For more information, refer to Overview of certificate-based security.
10. For the Windows-based Historian Administrator clients, start the Administrator from **Historian Startup Group**.

When the home page for Historian Administrator appears, you are ready to set up archives, collectors, and tags in the **Data Store Maintenance**, **Collector Maintenance**, and **Tag Maintenance** pages.

The following table provides a list of installation options available in Historian, along with purpose of installing each one.

Installation Option	When to Install
Historian Server (on page 104)	<p>Installing the Historian server is mandatory to work with Historian. If you want to use Web-based Clients, you must provide the Proficy Authentication server details while installing the Historian server.</p> <p>When you install the Historian server, the following components are installed as well:</p> <ul style="list-style-type: none"> • The RemoteCollectorConfigurator utility: A command-line tool, which allows you to manage collectors remotely. • The Proficy Authentication Configuration tool: A utility that allows you to specify the Proficy Authentication server details to match with the Proficy Authentication server used by Web-based Clients.
Alarms and Events (on page 140)	<p>Install Alarms and Events if you want to retrieve and store alarms and events data from any OPC-</p>

Installation Option	When to Install
	compliant alarms and events server using the OPC Classic Alarms and Events collector.
Collectors (on page 142)	<p>Installing collectors is mandatory to collect and store data in Historian.</p> <p>When you install collectors, all the collectors and the Remote Management Agents are installed. You must then create instances of each collector and manage them using Configuration Hub.</p> <p>When you install collectors, if iFIX/CIMPLICITY are installed on the same machine, instances of the following collectors are created automatically:</p> <ul style="list-style-type: none"> • The iFIX collector • The iFIX Alarms & Events collector • The OPC Classic Data Access collector for CIMPLICITY • The OPC Classic Alarms and Events collector for CIMPLICITY
Client Tools (on page 150)	<p>Install Client Tools if you want the following components:</p> <ul style="list-style-type: none"> • Client Tools • Historian Administrator • OLE DB driver and samples • The OPC Classic HDA server • User API and SDK • Historian Client Access API • Collector Toolkit
Web-based Clients (on page 154)	<p>Install Web-based Clients if you want to manage Historian administrative tasks and analyze the data using components such as Configuration Hub, the Web Admin console, Trend Client, and REST APIs.</p>

Installation Option	When to Install
	<p>To use Web-based Clients, you need Proficy Authentication (UAA server) to handle user authentication. It provides identity-based security for applications and APIs. It supports open standards for authentication and authorization, including Oauth2.</p> <p>During the Web-based Clients installation, you can choose to install a Proficy Authentication instance and Configuration Hub, or you can use existing ones.</p>
Historian Remote Management Agents (on page 187)	<p>Remote Management Agents (RMA) include Remote Collector Manager, which is used to manage collectors remotely.</p> <p>RMA is installed automatically when you install collectors. If, however, you are using RMA version 8.1, and you want to upgrade only RMA (and not the collectors), use this option.</p>
Excel Add-in for Historian (on page 195)	<p>Install Excel Add-in for Historian make bulk changes to tag parameters using Excel, and then import it to Historian. You can also perform mathematical, retrieve selected data, generate reports and charts, and so on.</p>
Excel Add-in for Operations Hub (on page 198)	<p>Install Excel Add-in for Operations Hub if you want to query historical data of objects and object types defined in Operations Hub.</p>
ETL Tools (on page 202)	<p>Install the Historian Extract, Transform, and Load (ETL) tools if you want to transfer data where there is limited internet connectivity.</p>
The OPC UA HDA Server (on page 191)	<p>Install the OPC UA HDA server if you want to use Historian as an OPC UA HDA server. You can then connect any OPC UA HDA clients with the server.</p>
Standalone Help (on page 205)	<p>Install Standalone Help to access the Historian product documentation offline.</p>

About Installing the Historian Server for the First Time

You can choose one of the following types of installation:

- **Single server:** This is for a stand-alone Historian system, which contains only one Historian server. This type of system is suitable for a small-scale Historian setup.
- **Mirror primary server and distributed/mirror node:** This is for a horizontally scalable Historian system, which contains multiple Historian servers, all of which are connected to one another. This type of system is used to scale out the system horizontally. For example, if you have 5,00,000 tags in your Historian system, you can distribute them among the various servers to improve performance.

In this setup, one of the nodes acts the primary server, whereas the others are the distributed/mirror servers. Configuration Manager and the embedded web services are installed only on the primary server, which are used by the distributed/mirror servers as well.

When the Archive Duration property is changed in a distributed environment, the changes will take effect after 15 minutes.

The distributed environment works only for tag data; it does not work for alarms and events data. Therefore, do not install alarm archiver in a distributed environment.

In this setup, one of the nodes acts the primary server, whereas the others are the distributed/mirror nodes.

For all these types of installation, you can use [the GUI-based installer \(on page 105\)](#) or [the Command Prompt window \(on page 114\)](#). You can also [install the Historian server in a cluster environment \(on page 119\)](#).

This section provides the high-level steps in installing the Historian server for the first time. You can perform the same steps to upgrade the server. If you are upgrading from either Historian 6.0 Enterprise or previous releases of Historian 7.2 (including any of the service packs), both Client Manager and Configuration Manager services will be removed. However, this will have no impact on your data or use of Historian unless you intend to use a distributed system.



Note:

The number of alarms in the Historian Alarms and Events database, and the frequency of new events being added during the installation, impact the time it takes to install Historian. For example, an installation for a system with 1.5 million alarms can take up to three hours to complete.

**Important:**

You cannot use size-based archives with a Historian Mirror Primary Server and Historian Mirror Node installation. This is because having archives of different sizes introduces archive synchronization risks in a mirrored environment. The restriction is enforced on all Historians, even those not using mirroring.

**Important:**

Be aware that you cannot close your current archive with a Historian Mirror Primary Server and Historian Mirror Node installation. This is because closing the current archive introduces archive synchronization risks in a mirrored environment. The restriction is enforced on all Historians, even those not using mirroring.


Install the Historian Server Using the Installer

- set up the Historian environment.
- If you want to install web-based clients and view Historian license information on Configuration Hub, you must provide the Configuration Hub and Proficy Authentication server details during installation. Therefore, ensure that you have already set up Proficy Authentication in Configuration Hub. For more information on setting up Proficy Authentication in Configuration Hub, refer to https://www.ge.com/digital/documentation/confighub/version2023/t_authentication_setup.html.
- If you are changing the role of a Historian server that was previously a distributed/mirror server to any other configuration (single-server or mirror primary server), you must first uninstall Historian.
- If you are installing a distributed/mirror server, use the same configuration, license key, installation drive, Proficy Authentication instance, and domain as the primary server.


This topic describes how to install the Historian server using the installer.

You can also install it at a command prompt.


1. Log in as an administrator to the machine on which you want to install the Historian server.
2. Run the `InstallLauncher.exe` file.
3. Select **Install Historian Server**.
The welcome page appears.
4. Select **Next**.
The license agreement appears.
5. Select the **Accept** check box, and then select **Next**.
The **Where do you want to install Historian?** page appears.



6. If needed, change the default installation drive of the Historian server, and then select **Next**. The **Override the default Historian data Path?** page appears.



7. If needed, change the default folder of the log files, and then select **Next**. If you want to include the Historian server in a cluster, enter the path to the shared folder of the cluster.
The **Register with Configuration Hub** page appears.



8. Select the **Use existing Proficy Authentication and Configuration Hub Instance** check box, and provide values as described in the following table.

This step is needed only in the following cases:

- The Historian Server and the Web-based clients will be on two different machines.
- You already installed Proficy Authentication and Configuration Hub, and you want to use the Historian Web-based clients and view the Historian license information on Configuration Hub.

If you do not select the **Use existing Proficy Authentication and Configuration Hub Instance** during the installation, to use the Historian Web-based clients and view the Historian license information on Configuration Hub, you must use the Proficy Authentication Tool from the Start menu to register with Proficy Authentication and Configuration Hub servers.

If you do not have Proficy Authentication and Configuration Hub installed, and you intend to use the Historian Web-based clients and view the Historian license information on Configuration Hub, you can install them while installing the Web-based clients.



Note:

Proficy Authentication is required for user authentication. It provides identity-based security for applications and APIs. It supports open standards for authentication and authorization, including Oauth2.

Register with Configuration Hub

By registering, you'll be able to work with Historian **web-based clients**, and you can also view Historian **license** information on Configuration Hub.

Use existing Proficy Authentication and Configuration Hub Instance

Proficy Authentication server name:

Proficy Authentication Public https Port:

Proficy Authentication Admin Client Id:

Proficy Authentication Admin Client Secret:

Configuration Hub server name:

Configuration Hub Public https port:

Test Connection Status: Test connection with Proficy Authentication and Configuration Hub is pending; click Test Connection

- Ensure to provide the highly privileged admin Client ID and Secret which was created while installing Proficy Authentication Server

Field	Description
Proficy Authentication server name	Enter the name of the machine on which the Proficy Authentication server is installed. If the machine uses a fully qualified domain name (FQDN), provide the FQDN. By default, the local hostname is considered.
Proficy Authentication Public https port	Enter the port number used by the Proficy Authentication service. The default value is 443. Ensure that this port number matches the one

Field	Description
	on the TCP Port Assignments page during Web-based Clients installation.
Proficy Authentication Admin Client Id	The client ID to connect to the Proficy Authentication service.
Proficy Authentication Admin Client Secret	The password to connect to the Proficy Authentication service.
Configuration Hub server name	The server name or the FQDN of the existing Configuration Hub server, as displayed in the address bar of the browser when you access Configuration Hub from the machine where Configuration Hub is installed.
Configuration Hub Public https port	The web server (https) port that you want to use for Configuration Hub. By default, it is 5000.
Test Connection	Option to test the status of the connection with external Proficy Authentication server.

**Note:**


If you change the Proficy Authentication server for Web-based Clients later, you must also change the Proficy Authentication server for the Historian server. This can be done using the Proficy Authentication Configuration Tool located at `<Install Drive>:\Program Files\Proficy\Proficy Historian\x64\Server` without the need to install the Historian server again. Alternatively, you can search for the Proficy Authentication Tool in the Windows search bar and open it.

9. Select **Next**.

The **Historian Security Groups** page appears.


Using Historian security groups provides an added layer of control over access to your Historian system.

By default, the option to create Historian security groups is not selected.



10. If you want the installer to create [Historian security groups \(on page 256\)](#), select the corresponding check box, and then select **Next**.


The **Choose the type of install you want to perform** page appears.



11. Select the type of the Historian server that you want to install, and then select **Next**.

- **Historian Single Server:** This is for a stand-alone Historian system, which contains only one Historian server. This type of system is suitable for a small-scale Historian setup.
- **Historian Mirror Primary Server:** This is for a horizontally scalable Historian system, which contains multiple Historian servers, all of which are connected to one another. Installing this server will allow you to add machines and distributed/mirror servers to this system.
- **Historian Distributed/Mirror Node:** This is for a horizontally scalable Historian system. Installing this server will allow you to add this node to a primary server.

The **Historian Server Certificate-based Security** page appears.



12. If you want to enable certificate-based security (MTLS-based security), leave the **Enable Certificate-based Security** check box selected, and then enter **Root Certificate Password**.

**Note:**

Ensure to use the same password to create MTLS (client) certificates. For more information on creating MTLS (client) certificates, refer to [Generate MTLS certificate](#).

For more information on certificate-based security, refer to [overview of the Certificate-based Security in Historian \(on page 206\)](#).

**Warning:**

If you do not select the **Enable Certificate-based Security** check box during the installation, you must generate the root certificates manually, as described in the [Manually Install Certificates for Historian](#) section. However, this is not recommended.

13. Select **Next**.

The **You are ready to install** page appears.

14. Select **Install**.

The installation begins.

15. After the installation, when you are asked to reboot your system, select **Yes**.

The Historian server is installed on your machine in the following folder: *<installation drive>*: \Program Files\Proficy\Proficy Historian\x64\Server, and the following registry path is created: HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services.

In addition, the following components are installed:

- **The RemoteCollectorConfigurator utility:** A command-line tool, which allows you to manage collectors remotely. By default, it is located in the C:\Program Files\GE Digital\NonWebCollectorInstantiationTool folder. For instructions on using this utility, refer to About Installing and Managing Collectors Remotely.
- **The Proficy Authentication Configuration tool:** A utility that allows you to specify the Proficy Authentication server details to match with the Proficy Authentication server used by Web-based Clients. By default, it is located in the C:\Program Files\Proficy\Proficy Historian\x64\Server folder. For instructions on using this tool, refer to [Register with Configuration Hub \(on page 137\)](#).

Install the Historian Server at a Command Prompt

- [Set up the Historian environment \(on page 82\)](#).
- If you want to install web-based clients and manage the Historian node in Configuration Hub, you must provide the Configuration Hub and Proficy Authentication server details during installation. Therefore, ensure that you have already set up Proficy Authentication in Configuration Hub. For more information on setting up Proficy Authentication in Configuration Hub, refer to https://www.ge.com/digital/documentation/confighub/version2023/t_authentication_setup.html.
- If you are changing the role of a Historian server that was previously a distributed/mirror server to any other configuration (single-server or mirror primary server), you must first [uninstall Historian \(on page 294\)](#).
- If you are installing a distributed/mirror server, use the same configuration, license key, installation drive, Proficy Authentication instance, and domain as the primary server.

This topic describes how to install single-server Historian at a command prompt. You can also [install the Historian server using the installer \(on page 105\)](#).

After you install Historian at a command prompt, you can choose to generate a template XML file, which contains the installation parameters and the values that you have provided. You can use this XML file for

subsequent installations. Similarly, you can use a template XML file instead of providing command-line arguments.

1. Open Command Prompt, and navigate to the <DVD drive>:\Historian folder (for example, E:\Historian).
2. Run the following command:

```
install.exe <argument>=<value> <flag> HistorianCmd=<installation type>
```

For example,

To install Historian Server without configuring web-based clients, run the following command:

```
install.exe RootDrive=E:\ EnableCertificateSecurity=1 ServerCertPassPhrase="Password"
CreateHistorianSecurityGroups=false -silent HistorianCmd=HistorianCore
```

To install Historian Server and configure web-based clients, run the following command:

```
install.exe RootDrive=E:\ ActiveUaaBaseUrl=https://histmachine123.test.com:443/uaa AdminClientId="admin"
AdminClientSecret="secret" ConfighubServerName="histmachine123.test.com" ConfighubhttpsPort="5000"
EnableCertificateSecurity=1 ServerCertPassPhrase="Password" CreateHistorianSecurityGroups=false -silent
HistorianCmd=HistorianCore
```

The following table provides a list of installation types that you can enter.

Installation Type	Description
StandAlone	Enter this value if you want to install a stand-alone Historian system.
HistorianCore	Enter this value if you want to install a primary server in a horizontally scalable system.
mirror	Enter this value if you want to install a distributed/mirror server in a horizontally scalable system.

The following table provides a list of arguments that you must enter.

Argument	Description
RootDrive	The drive letter where the Historian server binary files will be installed.
DataPath	The disk path where the Historian data files will be stored.

Argument	Description
HistAdministrator-Password	The password for the built-in administrator account.
ActiveUaaBaseUrl	<p>The URL to connect to Proficy Authentication to allow Web-based Clients to access Historian. Only if you want to use Web-based Clients, this parameter is required for user authentication. Proficy Authentication provides identity-based security for applications and APIs. It supports open standards for authentication and authorization, including OAuth2.</p> <p>Proficy Authentication details are required if you want to use Web-based Clients.</p> <p>By default, the local hostname and the port number of 443 are considered. If the Proficy Authentication service is on the same machine on which you are installing the Historian server, you can accept the default value. If, however, the Proficy Authentication service is on a different machine or uses a different port number, replace those values in the URL as follows:</p> <pre data-bbox="581 1031 1419 1083">https://<local host name>:<port number>/uaa</pre> <p>where:</p> <ul data-bbox="630 1161 1403 1415" style="list-style-type: none"> ◦ <i><Proficy Authentication server></i> is the name of the machine on which Proficy Authentication is installed. If the machine uses a fully qualified domain name (FQDN), provide the FQDN. ◦ <i><port number></i> is the one that you have specified for the public https port in the TCP Port Assignments page during Web-based Clients installation. <div data-bbox="573 1451 1419 1808" style="border: 1px solid #00a0c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note:</p> <p>You can install a Proficy Authentication service using Operations Hub or Historian Web-based Clients. You can provide the URL of an existing Proficy Authentication instance. Or, if a Proficy Authentication service is not available, you can install it during Web-based Clients installation. In that case, provide the server name where Proficy Authentication is installed.</p> </div>
AdminClientId	The client ID to connect to the Proficy Authentication service.

Argument	Description
<code>AdminClientSecret</code>	The password to connect to the Proficy Authentication service.
<code>ConfighubServerName</code>	The server name or the FQDN of the existing Configuration Hub server, as displayed in the address bar of the browser when you access Configuration Hub from the machine where Configuration Hub is installed.
<code>ConfighubhttpsPort</code>	The web server (https) port that you want to use for Configuration Hub. By default, it is 5000.
<code>CreateHistorianSecurityGroups</code>	<p>Indicates whether you want the installer to create Historian security groups.</p> <p>Using Historian security groups provides an added layer of control over access to your Historian system.</p> <p>Enter true or false. If you enter true:</p> <ul style="list-style-type: none"> ◦ You must add a Windows user to the appropriate group (on page 278) (for example, add an administrative user to the iH Security Admins group). Only then you can configure this server. ◦ If the Historian server and collectors are installed on the same machine, you can skip this step; by default, the machine name of the local Historian server is considered. If, however, they are installed on different machines, you must provide the credentials of the Windows user who can access the Historian server machine. In addition, if security groups are available, add the user to the appropriate group (on page 278) (for example, add an administrative user to the iH Security Admins group). Only then you can access Web-based Clients without LDAP. <p>For more information, refer to Implementing Historian Security (on page 251).</p>
<code>EnableCertificateSecurity</code>	<p>Indicates whether you want the installer to enable certificate-based security (MTLS-based security).</p> <ul style="list-style-type: none"> ◦ To enable certificate-based security, set this value to 1. ◦ To disable certificate-based security, set this value to 0. <p>For more information on the certificate-based security, refer to overview of the Certificate-based Security in Historian (on page 206).</p>

Argument	Description
ServerCertPassPhrase	<p>If you enabled certificate-based security, enter the passphrase for the server certificate.</p> <div style="border: 1px solid #00a0c0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: Ensure to use this passphrase as the password to create MTLS (client) certificates. For more information on creating MTLS (client) certificates, refer to Generate MTLS certificate. </div>

The following table provides a list of flags that you can use.

Flag	Description
[-q], [-quiet], [-s], [-silent]	Use any of these flags for a silent installation. The installation will then happen in the background (without a UI).
[-passive]	Use this flag for a passive installation. The progress of the installation then appears on your screen.
/t	<p>Use this flag to generate the template file, which will contain all the installation arguments and the values that you have provided for each of them. You can then use this file for subsequent installations.</p> <p>By default, this file is named <code>Template_Historian.xml</code>, and it is placed in the <code>temp</code> folder, defined by the <code>%temp%</code> environment variable. If, however, you want to save the file in another folder as well, enter: <code>/t TemplateOutputDirectory=<path></code></p>
/c TemplateInputFile=<path>	Use this flag to use a template file (instead of providing command-line arguments). However, if you do provide command-line arguments as well, they take precedence over the values in the template.

The Historian server is installed on your machine in the following folder: *<installation drive>*: \Program Files\Proficy\Proficy Historian\x64\Server, and the following registry path is created: HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services.

In addition, the following components are installed:

- **The RemoteCollectorConfigurator utility:** A command-line tool, which allows you to manage collectors remotely. By default, it is located in the C:\Program Files\GE Digital\NonWebCollectorInstantiationTool folder. For instructions on using this utility, refer to Remote Collector Management.
- **The Proficy Authentication Configuration tool:** A utility that allows you to specify the Proficy Authentication server and Configuration Hub server details to match with the Proficy Authentication server used by Web-based Clients, and also register the Historian node with Proficy Authentication server and Configuration Hub server. By default, it is located in the C:\Program Files\Proficy\Proficy Historian\x64\Server folder. Alternatively, you can search for the Proficy Authentication Tool in the Windows search bar and open it. For instructions on using this tool, refer to [Register with Configuration Hub \(on page 137\)](#).

While installing the Historian server, if you have allowed the installer to create Historian security groups, create a local Windows user with the format <Web-based Clients server name>.admin, and [add the user to the ihSecurityAdmins group \(on page 278\)](#).

This user will log in to Web-based Clients.

Alternatively, you can create Proficy Authentication users in an external Proficy Authentication and map their security groups. For information, refer to [About Proficy Authentication Groups \(on page 231\)](#).

Depending on whether the Historian server will use local or domain security groups, select the appropriate option in Historian Administrator.

Set Up High Availability of the Historian Server


Historian works with Microsoft Failover Cluster Manager to ensure high availability of the server.

In a cluster environment, multiple servers are installed, which share the same data. Each of these servers is called a node. One of them acts as the primary server, while the others are standby servers. If the primary server is down, one of the standby servers is used. See the following figure for an example.




Note:

Cluster supports only domain security.



1. Ensure that your network is enabled for multicast traffic.
2. Create a shared drive on your network that all the servers in the cluster can access, and create a database folder in that drive.
3. On each node that you want to add to the cluster:

- a. [Install the Failover Clustering feature.](#)
- b. [Install the Historian server \(on page 105\).](#) During the installation, in the **Historian Data Path** field, enter the path to the folder on the shared drive that you have created.



4. If you are upgrading the Historian server on a passive node, an error message may appear behind the installer screen, stating that the Archives directory is not created. You can ignore this message, or you can make the node active before upgrading the Historian server.

1. If you have upgraded the Historian server, on all the cluster nodes:
 - a. Right-click the cluster, and then select **Properties > Resource Types**.
 - b. If the user-defined resource types are not available, select **Add**.
 - c. Select *<Installation folder of the Historian server>/x64/Server/Historian.dll* as the resource DLL path with Historian and AlarmArchiver as both the resource type names and display names.

The Historian servers are now part of the cluster, thus achieving high availability. The remaining steps are required only for first-time installation of the Historian server (not upgrade).

2. Access the primary node of the cluster.
3. [Create a failover cluster.](#)
4. [Add a storage to the failover cluster.](#)

5. Add user-defined resource types, Historian and AlarmArchiver, to the cluster. These resources are created when you install the Historian server.
 - a. Right-click the cluster, and then select **Properties > Resource Types**.
 - b. If the user-defined resource types are not available, select **Add**.
 - c. Select `<Installation folder of the Historian server>/x64/Server/ Historian.dll` as the resource DLL path with Historian and AlarmArchiver as both the resource type names and display names.
6. Select **Roles > Create Empty Role**.

A role is created.
7. Add the Historian application to the cluster:
 - a. Select the role.
 - b. In the **Actions** section, select **Add Resource > Historian**.
 - c. Follow the on-screen instructions to add the new Historian resource to the role.
8. Add a client access point to the role:
 - a. Select the role.
 - b. In the **Actions** section, select **Add Resource > Client Access Point**.
 - c. Follow the on-screen instructions to add a client access point to the role.
9. Add a storage to the role:
 - a. Select the role.
 - b. In the **Actions** section, select **Add Storage**.
 - c. Follow the on-screen instructions to add the storage that you have created in step 3. You can use a storage only once.
10. Add the following dependencies to the Historian resource:
 - a. Double-click the Historian resource.

The **Historian Properties** window appears.
 - b. Select **Dependencies**.
 - c. Select **Insert**, and add the following dependencies using the AND operation.
 - Client access point
 - IP address
 - Storage
11. Add the Alarm Archiver resource to the cluster:
 - a. Select the role.
 - b. In the **Actions** section, select **Add Resource > Alarm Archiver**.

- c. Follow the on-screen instructions to add the alarm archiver resource to the role.
- d. Double-click the Alarm Archiver resource.
The **Alarm Archiver Properties** window appears.
- e. Select **Dependencies**.
- f. Select **Insert**, and then add the Historian service as a dependency. You do not need to add the cluster disk and IP address as dependencies.


12. Add generic services.

- a. In the **Summary** section of the Historian role, right-click the Client Manager resource, and then select **Properties > Dependencies**.
- b. Add the IP address as a dependency, and then select **Apply**.
- c. Select **General**, select the **Use Network Name for Computer Name** check box, and then select **OK**.

13. Repeat the previous step for the following services:

- Configuration Manager
- Diagnostics Manager
- Historian Embedded PostgreSQL Database
- Historian Embedded Tomcat Container
- Historian Indexing Service

The services appear under the Historian role.



14. Select the Historian role, and then in the **Actions** section, select **Start Role**.

The Historian servers are now part of the cluster, thus achieving high availability.

Set Up a Mirror of Mirror

1. [Install Historian server \(on page 105\)](#) on each machine that you want to use in the mirror of mirror setup.
2. [Set up Configuration Hub \(on page 305\)](#) on each machine that you want to use in the mirror of mirror setup.
3. [Add a system \(on page 427\)](#). The server that you specify while adding the system serves as the primary server for the system.
4. [Create data stores \(on page 370\)](#) in the primary server in the public/IT network with the same name as the data stores in the primary server in your organization network.


You can set up a mirror of the Historian server in a network different from that of your organization. When you do so, any tag/data update requests to the Historian server can be routed to the public and IT network instead of your organization's network.



Note:

For the Historian Enterprise Mirror Architecture, only "Time based" archives are supported.

Single-Node Setup: The following image shows two networks - OT and IT - with a Historian server installed in each network. These networks communicate using port 14000.



In this setup:


1. Server 1 is the primary server in the OT network; it stores data from collectors.
2. Server 2 is the primary server in the IT network; it is connected to clients.

3. When a tag/data is created, updated, or deleted, Client Manager 1 communicates the same with Client Manager 2 (installed with Server 2 in the IT network).
4. The change in the tag/data is replicated in Server 2 (that is, data is created, updated, or deleted accordingly).
5. The latest data is retrieved from Server 2 using the clients.


Mirror Setup: The following image shows two mirrors:

- Mirror 1 includes Mirror Server 1 and Mirror Node 1, which is a backup/standby node for Mirror Server 1; both these machines are in the OT network.
- Mirror 2 includes Mirror Server 2 and Mirror Node 2, which is a backup/standby node for Mirror Server 2; both these machines are in the IT network.


Client Manager 1 in Mirror Server 1 communicates with Client Manager 2 in Mirror Server 2.




If Mirror Server 1 goes down, Client Manager M1 in Mirror Node 1 communicates with Client Manager 2 in Mirror Server 2.




Similarly, if Mirror Server 2 goes down, Client Manager 1 in Mirror Server 1 communicates with Client Manager M2 in Mirror Node 2.



If both Mirror Server 1 and Mirror Server 2 are down, Client Managers M1 and M2 communicate with each other.



If Mirror Server 1 and/or Mirror Server 2 are available, the connection is re-established using these primary servers.




Thus, you can choose to always retrieve data from either Mirror Server 2 or Mirror Node 2. In addition, the store-and-forward functionality is available (in case Client Managers are not yet connected).

This topic describes how to set up a mirror of mirror for the configuration described in the preceding example. It includes the following high-level steps:

1. Installing the Historian server on all the machines
2. Setting up mirror 1
3. Setting up mirror 2
4. Setting up a mirror of mirror

Installing the Historian server


1. On the machines designated as the mirror primary servers (Mirror Server 1 and Mirror Server 2 in the example), [install the Historian server \(on page 105\)](#). During the installation, select **Historian Mirror Primary Server** on the **Choose the type of install you want to perform** page.



2. On the machines designated as mirror nodes (Mirror Node 1 and Mirror Node 2 in the example), [install the Historian server \(on page 105\)](#). During the installation, select **Historian Distributed/Mirror Node** on the **Choose the type of install you want to perform** page.

Set up Mirror 1:


3. On the mirror primary server in your organization's network (Mirror Server 1 in the example), [access Configuration Hub \(on page 336\)](#).
4. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
5. Expand Mirror Server 1.
A list of servers in the system appears.
6. Select **+**.



Machine Name	STATUS	Archive Compre...	Write Cache Hit ...	CONSUMPTION R...	Read Thread Usa...	Write Thread Us...	Out Of
[icon]	Connected	43.3	0.5	0.45	0	0	0
[icon]	Not Connected	NA	NA	NA	NA	NA	NA

The **Add Server Machine: <system name>** window appears.

7. Enter the host name or IP address of the mirror node in your organization's network (Mirror Node 1 in the example), and then select **Add**.
The distributed server is added to the system. A distributed location is added in the server.
8. Right-click Mirror Node 1, and then select **Browse Locations**.



Machine Name	Archive Compre...	Write Cache Hit R...	CONSUMPTION R...	Read Thread Usa...	Write Thread Usa...
torsk-collectorsclient	3.5	0.5	0.33	0	0
collectorsclien6	4	NA	NA	NA	NA

A list of distributed locations in the system appears.

9. Select **Mirror Locations**.
A list of mirror locations in the system appears.
10. In the upper-right corner of the main section, select **+**.

The **Add Mirror Location** window appears.

11. Provide values as described in the following table.

Field	Description
MIRROR LOCATION NAME	Enter a name for the mirror location. A value is required and must be unique for the system.
SERVER MACHINES	Select the servers that you want to add to the mirror group (Mirror Server 1 and Mirror Node 1 in this example). This box contains a list of all the servers in the system. You must add minimum two servers to a mirror location.

12. Select **Add**.

Mirror Node 1 is created.

13. Right-click the system name, and then select **Add Data Store**.

The **Add Data Store: Mirror Node 1** window appears.

14. Enter values as described in the following table.

Field	Description
DATA STORE NAME	Enter a unique name for the data store. A value is required. You can use all alphanumeric characters and special characters except / \ * ? < > You must provide the same name for the mirror setup in the IT network (mirror 2 in the example).
DESCRIPTION	Enter a description for the data store.
Set as default data store for the system	Select this check box if you want to set this data store as the default one. A default data store is the one that is considered if you do not specify a data store while adding a tag. You can set only one data store as default.

15. Select **Add**.

Mirror 1 is configured.

Set up Mirror 2:

16. On the mirror primary server in the IT network (Mirror Server 2 in the example), [access Configuration Hub \(on page 336\)](#).
17. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
18. Expand Mirror Server 2.
A list of servers in the system appears.
19. Select **+**.

Machine Name	STATUS	Archive Compre...	Write Cache Hit ...	CONSUMPTION R...	Read Thread Usa...	Write Thread Us...	Out Of
[blurred]	Connected	43.3	0.5	0.45	0	0	0
[blurred]	Not Connected	NA	NA	NA	NA	NA	NA

The **Add Server Machine: <system name>** window appears.

20. Enter the host name or IP address of the mirror node in your organization's network (Mirror Node 2 in the example), and then select **Add**.
The distributed server is added to the system. A distributed location is added in the server.
21. Right-click the system name, and then select **Browse Locations**.

Machine Name	STATUS	Archive Compre...	Write Cache Hit R...	CONSUMPTION R...	Read Thread Usa...	Write Thread Usa...
torsk-collectorsclient		3.5	0.5	0.33	0	0
collectorsclien6		4	NA	NA	NA	NA

A list of distributed locations in the system appears.

22. Select **Mirror Locations**.
A list of mirror locations in the system appears.
23. In the upper-right corner of the main section, select **+**.

The **Add Mirror Location** window appears.

24. Provide values as described in the following table.

Field	Description
MIRROR LOCATION NAME	Enter a name for the mirror location. A value is required and must be unique for the system.
SERVER MACHINES	Select the servers that you want to add to the mirror group (Mirror Server 2 and Mirror Node 2 in this example). This box contains a list of all the servers in the system. You must add minimum two servers to a mirror location.

25. Select **Add**.

Mirror Node 2 is created.

26. Right-click Mirror Node 2, and then select **Add Data Store**.

The **Add Data Store: Mirror Node 2** window appears.

27. Enter values as described in the following table.

Field	Description
DATA STORE NAME	Provide the same name that you provided while setting up mirror 1.
DESCRIPTION	Enter a description for the data store.
Set as default data store for the system	Select this check box if you want to set this data store as the default one. A default data store is the one that is considered if you do not specify a data store while adding a tag. You can set only one data store as default.

28. Select **Add**.

Mirror 2 is configured.

Set up Mirror of Mirror:

29. Access Configuration Hub in the primary server in the OT network (Mirror Server 2).

30. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.

A list of systems appears in the main section.

31. Expand Mirror Server 1.

A list of servers in the system appears.

32. Select **+**.

The **Add Server Machine: <system name>** window appears.

33. Enter the host name or IP address of the mirror server in the IT network (Mirror Server 2 in the example), select the **Set as Mirror of Mirror** check box, and then select **Add**.

The distributed server is added to the system. A distributed location is added in the server.

34. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.

35. Expand Mirror Server 1.

A list of servers in the system appears. In the example, Mirror Server 1, Mirror Node 1, and Mirror Server 2 appear.

A mirror of mirror is configured with one primary node and one mirror node each in the OT and IT networks. As needed, you can add more mirror nodes in each network.

Upgrade the Historian Server

If any Historian applications or components are open, close them before upgrading the Historian server.

If you are upgrading from either Historian 6.0 Enterprise or previous releases of Historian 7.2 (including any of the service packs), both Client Manager and Configuration Manager services will be removed. However, this will have no impact on your data or use of Historian unless you intend to use a distributed system.

[Install the Historian server \(on page 104\)](#).

The Historian server is upgraded to the latest version.

About Historian Log Files

Historian creates the following types of log files:

- **The .IHA files:** These files contain data about archives. They are created by the Historian server after data collection begins. By default, these files are located in the `C:\Historian Data\Archives` folder.
- **The .IHC files:** These files contain data about Historian configuration. They are created by the Historian server. By default, these files are located in the `C:\Historian Data\Archives` folder.

There are two types of .IHC files:

- `*CentralConfig.ihc`: This is the master configuration file used by Configuration Manager.
- `*config.ihc`: This is used by the data archiver and is generated from `*CentralConfig.ihc`. This is to maintain consistency between Historian versions.

- **The .LOG files:** These files contain logging data (such as events, warnings, and errors). They are created by the archiver and the collectors. By default, they are located in the `C:\Historian Data\LogFiles` folder.
- **The .SHW files:** These files contain configuration data. They are created by the archiver and the collectors. By default, they are located in the `C:\Historian Data\LogFiles` folder.

FAQs on Installing Historian in a Distributed Environment

- What happens when a node that was down is up and running? Is the data written to one node synchronized with another?

There is no automatic synchronization. If a node is down, the information to be written is buffered by Client Manager, or if Client Manager is down, it is buffered by the collector. When the node is up and running, data is written to the data archiver.

- There is only one Configuration Manager on the primary node. Can I still configure if the primary node is down?

No. If the Configuration Manager is not available, you can read the configuration (because this information is stored in the collectors), but you cannot edit or modify the configuration.

- Is Configuration Manager a single point of failure?

Yes. If the primary node is down, you cannot edit the configuration. However, since information about the configuration is stored in the registry of each client, the information is still available as read-and-write-only when the primary node is down.

If the Configuration Manager service is down, you cannot query tags and data in a horizontally scalable system. However, you can query tags and data in the following scenarios:

- The Historian system contains only one node, which is installed as the primary mirror Historian server.
 - The Historian system contains only one mirror location, and there are no data stores in the distributed locations.
- What happens if a node crashes in the middle of a read/write request?

The operation continues to function in the same way as in prior releases. Client Manager holds a copy of the message request; therefore, once the node is up and running, the write operation is resumed. However, read requests will fail.

- The server where my primary node is installed is down. What is the expected behavior?

The Web Admin console and Trend Client will not be available; you can access tag configuration using Historian Administrator, but you will not be able to edit tag configuration. All other existing clients continue to work as expected, with the ability to collect and store data, search for tags, trend and report on tag information. A new user connection with default Historian server set to primary must connect to the primary node to get information about all the nodes before it gains the ability to automatically failover when the primary node is down.

- Client Manager on the primary node is down, but the server is running. What is the expected behavior?

The Web Admin console and Trend Client, along with all other existing clients, will work as expected with the ability to do configuration changes, collect and store data, search for tags, trend and report on tag information. A new user connection with default Historian server set to primary must connect to the primary node to get information about all the mirrors before it gains the ability to automatically failover when the primary node is down.

- One of the data archivers is down, but at least one is active. What is the expected behavior?

The system should continue to function as designed. The Web Admin console, Trend Client, Historian Administrator, as well as other clients continue to work as expected, with the ability to collect and store data, search for tags, trend and report on tag information.

- If there are calculated tags in a distributed environment, are the calculations done on all nodes?

Yes.

- Are Historian tag statistics created independently? Can they be different between different nodes?

Yes. These are queries, not tags, to a specific data archiver. As writes are independent, one data archiver may be ahead of another, so the statistics may vary slightly.

- How do we ensure that the data is consistent across data archivers?

Tag information is consistent; there is only one tag. The time stamp and value are sent to all the nodes.

- Are there specific log files that I should be looking for to help diagnose issues with failure modes?

No changes were made to the logs for data archiver; however, there are new log files for Client Manager and Configuration Manager.

- There are now two *.ihc files: *config.ihc and *CentralConfig.ihc. What is the difference between the two?

*CentralConfig.ihc is the master configuration file used by Configuration Manager. The *config.ihc file is used by the data archiver and is generated from *CentralConfig.ihc. This is to maintain consistency between Historian versions.

- With mirroring, is Microsoft Cluster Server still supported? What is the recommended approach?

Mirroring is offered as a substitute to Microsoft Cluster Server. Mirroring provides high availability for locations. Microsoft Cluster Server has not been tested or validated to date with Historian systems.

- Should I install SQL server in a distributed environment?

No. SQL server is only required for the Historian Alarms and Events database.

- How does mirroring work with Historian Alarms and Events SQL logging?

There is still an alarm archiver; it does not go through Client Manager, so it connects with SQL as earlier.

- How does Historian Alarms and Events fit with their syncing?

There is one database, so everyone talks to the same SQL database. You can cluster the database, but that is separate from mirroring.

- How does mirroring work in a workgroup environment or non-domain?

Mirroring is not supported in Workgroups.

- Are there any issues when making changes in Historian Administrator and a mirrored system?

You must establish a mirror using the Historian Configuration Hub, but compatibility with all APIs has been maintained. Therefore, you can make tag changes in either the Web Admin or the VB Windows Admin, and those changes will show up in both Admins.

- Are there any plans to add more than three mirrors?

No performance benefits have been seen beyond three mirrors.

- Do redundant collectors behave differently in a distributed environment?

No.

- Are there any conflicts when using port 14000 for Historian to Historian communications (for example, Site to Corporate)?

No. Client Manager is now on port 14000, data archiver is on port 14001, and Configuration Manager is on port 14002.

- If load balancing uses round robin reads, does the cache need to be loaded separately on both machines, and will it decrease performance?

It does require more memory. Client Manager decides where to send the messages, and it knows about the configuration. There is some overhead, but it is overcome by having multiple data archivers to service multiple requests. That is why there is a 1.5X improvement with two mirrors, instead of 2X.

- Are there any additional considerations if a distributed system is used with other GE applications such as Workflow or Plant Applications?

No. It still looks like one Historian to other applications.

- Is the store-and-forward feature also used in a distributed environment?

Yes. This is a feature of the collector. Once the message is sent to Client Manager, it is done. If the Client Manager cannot reach one of the data archivers, it buffers the request until the archiver is available.

- In a distributed environment, do existing queries and reports work the same?

Yes. Everything works the same as it did before. It sees it as a single Historian and communicates over the same ports through the same API.

- Does the Historian OPC Classic HDA server still work in a distributed environment?

Yes.

- If data is being written to two data archivers, does this double the traffic from the collector?

No. It does not double traffic from the collector; it sends a single message to Client Manager. The traffic is doubled between the Client Manager and the two data archivers.

Register with Configuration Hub

Ensure the following:

- [Installed Web-based Clients \(on page 154\)](#), specifying the details of the new Proficy Authentication and Configuration Hub servers.

The Historian server and Web-based Clients must always point to the same Proficy Authentication server and Configuration Hub server. Only then you can access Web-based Clients (such as Configuration Hub, Trend Client, the Web Admin console, and REST APIs), and also view Historian license information on Configuration Hub. Therefore, you can use the Proficy Authentication Tool in the following cases:

- If you changed the Proficy Authentication server used by Web-based Clients, the Historian server must point to the same Proficy Authentication and Configuration Hub servers.
- If you did not select the **Use existing Proficy Authentication and Configuration Hub Instance** during the Historian Server, and now you want to register with the Proficy Authentication and Configuration Hub servers to use the Historian Web-based clients and view Historian license information on Configuration Hub.

This topic describes how to register the Historian Server with the Proficy Authentication server and Configuration Hub server without the need to reinstall it.

1. Access the `UAAConfiguration.exe` file. By default, it is located at `<Install Drive>:\Program Files\Proficy\Proficy Historian\x64\Server`.

Alternatively, you can search for the Proficy Authentication Tool in the Windows search bar and open it.

The **Proficy Authentication Configuration tool** window appears, displaying the Proficy Authentication server details that you specified while installing the Historian server. Also, it allows you to specify the Configuration Hub server details.

2. In **Proficy Authentication Server Details**, provide the following details as described in the table below.

Field	Description
Proficy Authentication server name	Enter the name of the machine on which the Proficy Authentication server is installed. If the machine uses a fully qualified domain name (FQDN), provide the FQDN. By default, the local hostname is considered.
Public https port	Enter the port number used by the Proficy Authentication service. The default value is 443. Ensure that this port number matches the one on the TCP Port Assignments page during Web-based Clients installation.
Admin Client Id	The client ID to connect to the Proficy Authentication service.
Admin Client Secret	The password to connect to the Proficy Authentication service.
Proficy Authentication Test Connection	Option to test the status of the connection with external Proficy Authentication server.

3. In **Configuration Hub Server Details**, provide the following details as described in the table below.

Table 10.

Field	Description
Configuration Hub server name	The server name or the FQDN of the existing Configuration Hub server, as displayed in the address bar of the browser when you access Configuration Hub from the machine where Configuration Hub is installed.
Configuration Hub Public https port	The web server (https) port that you want to use for Configuration Hub. By default, it is 5000.
Configuration Hub Test Connection	Option to test the status of the connection with an existing Configuration Hub server.

4. Select **Configure**.

The Proficy Authentication server and Configuration Hub details are updated for the Historian server. The changes are reflected as soon as you refresh the browser in which you have opened any of the Web-based Clients components (such as Configuration Hub, the Web Admin console, Trend Client).

If testing the connection fails, try these steps:

- Verify that you can ping the Proficy Authentication server. If you cannot ping the Proficy Authentication server, add the IP address and the server name in the `hosts` file located in `C:\Windows\System32\drivers\etc`.
- Ensure that the following services are running on the Proficy Authentication server machine:
 - Proficy Operations Hub Httpd Reverse Proxy
 - Proficy Authentication Tomcat Web Server
 - All the GE Proficy Configuration Hub services
- Verify that the Proficy Authentication server details provided during Web-based Clients installation match the ones you have specified in the Proficy Authentication Configuration tool.

Historian Installation Limitations

- You cannot close your current archive with a Historian Mirror Primary Server and Historian Mirror Node installation. This is because closing the current archive introduces archive synchronization risks in a mirrored environment. The restriction is enforced on all Historians, even those not using mirroring.
- You cannot use size-based archives with a Historian Mirror Primary Server and Historian Mirror Node installation. This is because having archives of different sizes introduces archive synchronization risks in a mirrored environment. The restriction is enforced on all Historians, even those not using mirroring.

Alarms and Events

Install Alarms and Events

- You must install Historian Alarms and Events on the same machine as the data archiver.
- If you have chosen to connect Historian to a remote SQL server, the following conditions must be satisfied:
 - The Historian Alarm Archiver service must be run on a user account that has privileges to log in to the SQL server using Windows authentication.
 - The default backup path, which you can set on the Archive page, must be a shared directory that is accessible to both the Historian Data Archiver and the remote SQL server. It is recommended that this shared directory be placed on the same computer as the Historian Data Archiver service.

1. Run the `InstallLauncher.exe` file.

2. Select **Install Alarms and Events**.

The **Alarms and Events Archiver** page appears.

Proficy Historian Setup Maintenance

Alarm and Event Archiver
Specify SQL server database details for archiver.

The Alarm and Event archiver require access to SQL Server.

Server Name

Database Name

Use Windows Authentication

Admin User Password

InstallShield

< Back Next > Exit

3. If needed, change the values in the **Server Name** and **Database Name** fields to provide the name of the SQL server and the name of the database where the alarms and events data is archived.
4. If you want to use the SQL server credentials, clear the **Use Windows Authentication** check box, and then enter the SQL server login credentials in the **Admin User** and **Password** fields. If you want to use Windows authentication, select the **Use Windows Authentication** check box. When you do so, the **Admin User** and **Password** fields are disabled.
5. Select **Next**.
6. When prompted to restart your system, select **Yes**.

Historian Alarms and Events is installed in the following folder: *<installation drive>*:
 \Program Files\Proficy\Proficy Historian\x86\Server, and the following registry path is created: HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\ Intellution, Inc.
 \iHistorian\Services\AlarmArchiver

7. To verify that the Alarms service has started, access the **Services** window, and check the status of the Historian Alarm Archiver service.

If the **Startup Type** field is set to **Automatic**, the service is started automatically when the system is started or restarted.

Upgrade Alarms and Events

- If Alarms and Events were installed prior to Historian 7.0, you must install them separately.
- If you want to upgrade from Historian 4.5, since the database schema are different, if you select the same database name that is pre-populated by default, you will get an error message: `Later or Higher version of Alarms and Events database is already installed. Hence, you cannot proceed further.` You need to enter a different database name and then proceed with the upgrade.

[Install Alarms and Events \(on page 140\).](#)

Alarms and Events are upgraded to the latest version.

About Installing Historian Data Collectors

When you install collectors, the required binaries are downloaded. In addition, if iFIX/CIMPLICITY are installed on the same machine as the collectors, instances of the following collectors are created:

- The iFIX collector
- The iFIX Alarms & Events collector
- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

If an iFIX collector instance created in version 9.0 exists, after you upgrade collectors, another instance of the iFIX collector is created. Because of this, the Remote Collector Manager (RCM) will not work correctly. Therefore, if you want to use RCM, you must delete one of the instances. If needed, you can manually create another instance of the iFIX collector using Configuration Hub or the RemoteCollectorConfigurator utility. This is applicable to the iFIX Alarms and Events collector as well.



Note:

If you want to upgrade collectors earlier than version 7.1, additional registries that you create manually are deleted. Therefore, we recommend that you back them up, uninstall the collectors, and then install the latest version.

Install Collectors Using the Installer


After you install collectors, the following artefacts will be available:

- **Executable files:** These files are required to add a collector instance.
- **Instances of the following collectors:**
 - The iFIX collector
 - The iFIX Alarms & Events collector
 - The OPC Classic Data Access collector for CIMPLICITY
 - The OPC Classic Alarms and Events collector for CIMPLICITY


These instances will be created only if iFIX and/or CIMPLICITY are installed on the same machine as the collectors.

- **The Remote Collector Management agent:** Provides the ability to manage collectors remotely.

1. Run the `InstallLauncher.exe` file.
2. Select **Install Collectors**.
The welcome page appears.
3. Select **Next**.
The license agreement appears.
4. Select the **Accept** check box, and then select **Next**.
The default installation drive appears.



5. If needed, modify the installation drive, and then select **Next**.
The data directory page appears.



6. If needed, change the folder for storing the collector log files, and then select **Next**.
The destination Historian server page appears.

Historian Server Details

Provide a valid windows user of the default Historian server to which the Remote Collector Manager will connect.

Historian Server:

User Name:

Password:

Confirm Password:

Note: If you have created security groups or enabled strict client/collector authentication, provide the destination Historian credentials. If the password changes, you must reinstall Remote Management Agents to reset the password.

7. Provide the credentials of the Windows user account of the destination Historian server to which you want Remote Management Agent to connect.

These details are required for Remote Collector Manager to connect to Historian to manage the collectors remotely. If you are installing collectors on same machine as the Historian server, and if strict collector authentication is disabled, you need not provide these details; by default, the machine name of the local Historian server is considered. If, however, they are installed on different machines, or if strict collector authentication is enabled, you must provide the credentials of the Historian server user.

8. Select **Next**.

The **You are ready to install** page appears.

9. Select **Install**.

The installation begins.

10. When you are prompted to reboot your system, select **Yes**.

The collector executable files are installed in the following folder: `<installation drive>:\Program Files (x86)\GE Digital\<collector name>`. The iFIX collectors are installed in the following folder: `C:\Program Files\GE\iFIX`. The following registry paths are created:

- `HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\ GE Digital\iHistorian\Services\<collector type>`
- `HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\iHistorian\Services\<collector type>`

In addition, if iFIX and/or CIMPLICITY are installed on the same machine as the collectors, instances of the following collectors are created:

- The iFIX collector
- The iFIX Alarms & Events collector
- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

Installing a Collector at a Command Prompt

After you install collectors and Remote Management Agent, the following artefacts will be available:

- **Executable files:** These files are required to add a collector instance.
- **Instances of the following collectors:**
 - The iFIX collector
 - The iFIX Alarms & Events collector
 - The OPC Classic Data Access collector for CIMPLICITY
 - The OPC Classic Alarms and Events collector for CIMPLICITY

These instances will be created only if iFIX and/or CIMPLICITY are installed on the same machine as the collectors.

- **The Remote Collector Management agent:** Provides the ability to manage collectors remotely.

Using Configuration Hub, you will then add a collector instance and begin using the collector.

This topic describes how to install collectors at a command prompt. You can also [install them using the installer \(on page 143\)](#).

1. Navigate to the `Collectors` folder in the installation folder.
2. At a command prompt, enter:

```
Collectors_Install.exe -s RootDrive=<value> DestinationServerName=<value>
DataPath="<value>" UserName1=<value> Password=<value>
```

Parameter	Description	Default Value
RootDrive	The installation drive for the collectors.	C:\
DataPath	The folder for storing the collector log files.	C:\Proficiency Historian Data
DestinationServerName	<p>The host name of the destination Historian server to which you want collectors to send data.</p> <p>This is required for Remote Collector Manager to connect to Historian to manage the collectors remotely. If you are installing collectors on the same machine as the Historian server, and if strict collector authentication is disabled, you need not provide the server name; by default, the machine name of the local Historian server is considered. If, however, they are installed on different machines, or if strict collector authentication is enabled, you must provide the credentials of the Historian server user.</p>	local host name
UserName1	The username of the Windows user of the destination Historian server. A value is required only if the destination Historian server and collectors are on different machines.	

Parameter	Description	Default Value
Password	The password of the Windows user of the destination Historian server. A value is required only if the destination Historian server and collectors are on different machines.	

For example: `Collectors_Install.exe -s RootDrive=C:\ DestinationServerName=myservername DataPath="C:\Proficy Historian Data" UserName=user123 Password=xyz123`

- Restart the machine. If you uninstall a collector or install another one before restarting the machine, an error may occur.

The collector executable files are installed. In addition, if iFIX and/or CIMPLICITY are installed on the same machine as the collectors, instances of the following collectors are created:

- The iFIX collector
- The iFIX Alarms & Events collector
- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

1. Ensure that the Windows user that you have specified while installing collectors is added to the iH Security Admins and iH Collector Admins groups.
2. [Enable trust for a client certificate for Configuration Hub.](#)
3. [Enable trust for a self-signed certificate on Chrome \(on page 97\).](#)
4. [Import an issuer certificate.](#)

You are now ready to use Configuration Hub. To add and manage collector instances, you can use Configuration Hub or Remote Collector Management. For instructions specific to setting up the iFIX collector and the iFIX Alarms and Events collector, refer to [Working with iFIX Collectors](#).

Upgrade Collectors

- Ensure that you are attempting to upgrade the collectors that were installed using the Historian Installation Package. If you previously installed the collectors using the Proficy Installer, such as the iFIX Proficy Installer, you must upgrade the collectors using the Proficy Installer only.
- If an iFIX collector instance created in version 9.0 exists, after you upgrade collectors, another instance of the iFIX collector is created. Because of this, the Remote Collector Manager (RCM)

will not work correctly. Therefore, if you want to use RCM, you must delete one of the instances. If needed, you can manually create another instance of the iFIX collector using Configuration Hub or the RemoteCollectorConfigurator utility. This is applicable to the iFIX Alarms and Events collector as well.

- For collectors earlier than version 7.1, additional registries that you create manually are deleted. Therefore, we recommend that you back up them, uninstall the collectors, and then install the latest version.

[Install the collectors \(on page 142\)](#).

The collectors are upgraded to the latest version.

Client Tools

Install Client Tools


When you install Client Tools, the following components are installed by default:

- Client Tools
- Historian Administrator
- OLE DB provider (driver and samples)
- The OPC Classic HDA server
- User API and SDK
- Historian Client Access API
- Collector Toolkit

This topic describes how to install Client Tools using the installer. You can also [install it at a command prompt \(on page 153\)](#).

1. Run the `InstallLauncher.exe` file.
2. Select **Install Client Tools**.

The **Select Features** page appears, displaying a list of components that you can install with Client Tools.



By default, the check boxes for components such as **Historian Administrator**, **HDA Server**, **OLE DB**, and **User API and SDK** are selected. If you do not want to install them at this time, clear the check boxes. You cannot, however, clear the **Proficy Historian Client Tools** check box.

 **Important:**


If you are reinstalling, you must select all of the previously installed components. If you do not do so, the component will be uninstalled.

By default, the **Historian Excel Add-in 64-bit** check box is cleared. If you want to install Excel Add-In along with Client Tools installation, select the check box.

 **Note:**

If using certain versions of Windows (like Windows 10 or Windows 2019), you may receive an error message while installing Excel Add-In, stating that some of the DLL files are not registered. You can ignore these messages.

The **Historian Server Security** page appears.



3. Select the user account that should be granted the access to administer Historian.
You are provided with the following options:

Option	Description
All Users	If you select this option, all local, including domain user accounts will have the administrator access of the Historian server. If needed, to control access, you can configure security groups after installation.
Specific User	If you select this option, the user that you select will have the administrator access of the Historian server. If needed, you can grant a restricted or administrator access to other users after installation.

4. Select **Next**.
5. When you are asked to reboot your system, select **Yes**.

Client Tools, along with the selected components, are installed in the following folder: `<installation drive>:\Program Files\Proficy\Proficy Historian\x86\<tool name>`. If you have selected HDA Server, Microsoft .NET Framework 4.5 and the OPC Core Components 3.00 redistributable are installed as well.

Install Client Tools at a Command Prompt

1. If you want to install Excel Add-In for Historian, install one of the following 32-bit or 64-bit Microsoft® Excel® applications:
 - Microsoft® Excel® 2019
 - Microsoft® Excel® 2016
 - Microsoft® Excel® 2013
 - Microsoft® Excel® 2010
2. [Install Client Tools using the installer \(on page 150\)](#) on a machine. When you do so, a template file named `setup.iss` is created at `C:\Windows`. This file stores the installation options that you have provided. You can then use this template to install Client Tools at a command prompt on other machines.

When you install Client Tools, the following components are installed by default:

- Client Tools
- Historian Administrator
- OLE DB driver and samples
- The OPC Classic HDA server
- User API and SDK
- Historian Client Access API
- Collector Toolkit

1. Copy the `setup.iss` file to the machine on which you want to install Client Tools at a command prompt.
2. In the folder in which you have copied the file, run the following command: `setup.exe /s /sms`
The installer runs through the installation steps.



Note:

If using certain versions of Windows (like Windows 10 or Windows 2019), you may receive an error message, stating that some of the DLL files are not registered. You can ignore these messages.

3. When prompted to reboot your system, select **Yes**.

Client Tools are installed.

If you have installed Excel Add-in, [activate it \(on page 197\)](#).

About Installing Web-based Clients

Using Web-based Clients, you can configure and manage Historian systems and their components using a browser.

When you install Web-based Clients, you can install the following components:

- Configuration Hub: Allows you to manage Historian systems and its components. You can set up stand-alone as well as horizontally scalable systems. You can also add collector instances and manage them.
- Trend Client: Provides access to process and equipment data, allowing you to quickly troubleshoot and make improvements, leading to time and cost savings through the use of trend charts and current value tables.
- The Web Admin console: Allows you to monitor, supervise, archive, retrieve, and control data gathered from Historian systems.
- The Proficy Authentication service (optional): Provides identity-based security for applications and APIs. It supports open standards for authentication and authorization, including OAuth2. You can install Proficy Authentication and Configuration Hub, or you can point to existing Proficy Authentication and Configuration Hub instances.
- Rest APIs: Allow you to query data from a Historian server.

You can install Web-based Clients [using a GUI-based installer \(on page 155\)](#) or [at a command prompt \(on page 171\)](#).



Important:

When you install Web-based Clients:



- If you want to reinstall the same version of Web-based Clients, you must uninstall and then install Web-based Clients.
- If, even after installing Web-based Clients, you cannot access a web component, start the Proficy Operations Hub Httpd Reverse Proxy and the Data Archiver services.

Install Web-based Clients Using the Installer

1. [Install the Historian server \(on page 105\)](#). During the installation, in the **Register with Configuration Hub** page, select the **Use existing Proficy Authentication and Configuration Hub Instance** check box, and then provide the Proficy Authentication server and Configuration Hub server details.




Note:

This step is needed only in the following cases:

- The Historian Server and the Web-based clients will be on two different machines.
- You already installed Proficy Authentication and Configuration Hub, and you want to use the Historian Web-based clients and view the Historian license information on Configuration Hub.

If you do not select the **Use existing Proficy Authentication and Configuration Hub Instance** during the installation, to use the Historian Web-based clients and view the Historian license information on Configuration Hub, you must use the [Proficy Authentication Tool \(on page 137\)](#) to register with Proficy Authentication and Configuration Hub servers.

If you do not have Proficy Authentication and Configuration Hub installed, and you intend to use the Historian Web-based clients and view the Historian license information on Configuration Hub, you can install them while installing the Web-based clients.



2. If you want to use Web-based Clients in a cluster environment, ensure that your network is enabled for multicast traffic, and [set up high availability](#) on each node in the cluster.

This topic describes how to install Web-based Clients using a GUI-based installer.

You can also [install Web-based Clients using the command line](#).

During the installation, you can choose to use Web-based Clients in a cluster environment, thus ensuring high availability of connection to the Historian server using the client applications.

1. Run the `InstallLauncher.exe` file.
2. Select **Install Web-based Clients**.
The welcome page appears.
3. Select **Next**.
The license agreement appears.
4. Select the **Accept** check box, and then select **Next**.
The **TCP port assignments** page appears.

TCP port assignments

Public https port:	443
Proficy Authentication http port:	9480
Proficy Authentication database port:	9432
Historian http port:	8070
Historian database port:	8432

Cancel Previous Next

5. As needed, change the values for TCP port assignments as described in the following table, and then select **Next**.

Field	Description
Public https port	Port for https protocol communication used by Web-based Clients (through a firewall). The default value is 443. Ensure that this port number matches the one you specify while installing the Historian server. In addition: <ul style="list-style-type: none"> ◦ If you will install Operations Hub later on the same machine, the value that you provide in this field is populated while installing Operations Hub. ◦ If you have already installed Operations Hub on the same machine, this field is disabled and populated with the value you have provided while installing Operations Hub.
Proficy Authentication http port	Port for http protocol communication used by the Proficy Authentication service. The default value is 9480.

Field	Description
Proficy Authentication database port	Port for the Proficy Authentication database. The default value is 9432.
Historian http port	Port for the http protocol communication used by Web-based Clients. The default value is 8070.
Historian database port	Port for the PostgreSQL Historian database. The default value is 8432.

The **Fully Qualified Domain Name(s)** page appears.

- If you will install Operations Hub later on the same machine, the value that you provide in the **FQDNs** field is populated while installing Operations Hub.
- If you have already installed Operations Hub on the same machine, the **FQDNs** field is disabled and populated with the value you have provided while installing Operations Hub.

Fully Qualified Domain Name(s).

To allow users to access Historian web applications remotely using fully qualified domain names (FQDN), please list one or more here, separated by commas. Otherwise, you may leave this blank.

FQDNs:

Cancel Previous Next

6. In the **FDQNs** field, enter the fully qualified domain names, and then select **Next**.

This enables you to access Historian web applications remotely. You can use it to access the Web Admin console using alias names. Enter the values separated by commas.

To access the Web Admin console using any of the following URLs, enter

```
Test.abc.ge.com,localhost,127.0.0.1,aliasName
```

- [https:// Test.abc.ge.com /historian-visualization/hwa](https://Test.abc.ge.com/historian-visualization/hwa)
- [https:// 127.0.0.1 /historian-visualization/hwa](https://127.0.0.1/historian-visualization/hwa)
- [https:// aliasName /historian-visualization/hwa](https://aliasName/historian-visualization/hwa)
- [https:// localhost /historian-visualization/hwa](https://localhost/historian-visualization/hwa)



Important:


- Do not enter a space between the values.
- You must add the IP address and alias name in the `hosts` file located at `C:\Windows\System32\drivers\etc`. The IP address that you add must be a static or fixed IP address.

Format: `<IP address> <alias name>`

Example: `1.2.3.4 myservername`

- FQDN is not supported for Configuration Hub.

The **Cluster Configuration** page appears.



If, however, you are upgrading Web-based Clients, this page does not appear. In that case, skip the next step.


7. If you want high availability of Web-based Clients, select the **Cluster Node** check box, and enter values as described in the following table.

Field	Description
Historian Database Folder	Provide the database folder in the shared drive that you have created. The default value is C:\ProgramData\GE\OperationsHub. You <i>must</i> change this value.
Cluster FQDN	Enter the client access point of the role for which you have added the resources while setting up high availability (on page 182) .
Multicast Address	If needed, modify the common IP address that all the nodes in the cluster can use. Enter a value between 224.0.0.0 and 239.255.255.255

Field	Description
	(or a hostname whose IP address falls in this range). The default value is 228.0.0.4.
Historian Cluster Membership Port	If needed, modify the common port number that all the nodes in the cluster can use. The default value is 45564. This port number, in conjunction with the multicast address, is used to create the cluster.
Historian Cluster Receiver Port	If needed, modify the multicast port number that you want to use for incoming Historian data. The default value is 4000.

8. Select **Next**.

The **Proficy Authentication** page appears, allowing you to choose whether you want to install Proficy Authentication along with Web-based Clients installation or use an existing Proficy Authentication.



Proficy Authentication

Use Existing Proficy Authentication:

Admin client Secret:

Re-enter Secret:

Note: The default Client ID is <admin>. As the admin Client is highly privileged, choose a strong secret and safekeep it.

Note: The username to login to Historian web-based clients is <[redacted].admin>. This is case-sensitive.

Cancel Previous Next

- If you want to install Proficy Authentication, clear the **Use Existing Proficy Authentication** check box. If you want to include Proficy Authentication in the cluster, you must install Proficy Authentication locally on each cluster node.
 - If you want to use an existing Proficy Authentication server, select the **Use Existing Proficy Authentication** check box. Proficy Authentication is detected if you installed it using a unified installer or Operations Hub, or if Historian uses Proficy Authentication installed remotely from an earlier version.
9. If you want to install Proficy Authentication, enter the **Admin client secret**, re-enter the secret, and then select **Next**.

The admin client secret must satisfy the following conditions:

- Must not contain only numbers.
- Must not begin or end with a special character.
- Must not contain curly braces.



Note:

The format of username for Historian Web-based Clients is <host name>.admin, where <host name> is the machine on which Web-based Clients are installed. And, the default client ID is admin. Both the host name and client ID are case-sensitive.

If, however, the Proficy Authentication server hostname is long, resulting in a username longer than 20 characters, Windows does not allow you to create the user. In that case, you can create a Proficy Authentication user, and then [create the corresponding Windows user](#), using the `uaa_config_tool` utility.

10. Alternatively, if you want to use an existing Proficy Authentication service (that is, a Proficy Authentication instance already installed by an external application such as Operations Hub):
- a. Select the **Use Existing Proficy Authentication** check box.
The fields for the existing Proficy Authentication service appear.

b. Enter values as described in the following table.


Field	Description
Proficy Authentication Base URL	<p>Enter the URL of the external Proficy Authentication server in the following format: <code>https://<Proficy Authentication server name>:<port number></code>, where <i><Proficy Authentication server name></i> is the FQDN or hostname of the machine on which Proficy Authentication is installed. By default, the port number is 443.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Do not enter a trailing slash character.</p> </div>
Admin Client ID	Enter the client name that you provided while installing the external Proficy Authentication. The default value is admin.
Admin Client Secret	Enter the client secret that you provided while installing the external Proficy Authentication.

c. Select **Test Connection**.

The results of the connection test appear. You cannot proceed until the connection is successful.

11. Select **Next**.

The **Configuration Hub Installation** page appears, allowing you to choose whether you want to install Configuration Hub along with Web-based Clients or use an existing Configuration Hub.



The screenshot shows the "Configuration Hub Installation" dialog box. It has a dark background with a grid pattern. The title "Configuration Hub Installation" is at the top. Below it is a checkbox labeled "Use Existing Configuration Hub:" which is currently unchecked. The main area contains several input fields with labels on the left and values in the boxes: "Install Location:" with "C:\Program Files (x86)\GE\" and a "Browse" button; "Plugin-Name:" with "Historian_"; "Server Port:" with "5000"; "Container Port:" with "4890"; "ConfigHub Admin Port:" with "4920"; "Client ID:" with "admin"; "Client Secret:" with an empty field; and "Re-enter Secret:" with an empty field. A yellow note at the bottom reads: "Note: Credentials used here are needed for registering other products with this Configuration Hub. Make sure to save these credentials for future registrations and upgrades to Configuration Hub." At the bottom of the dialog are three buttons: "Cancel" (grey), "Previous" (blue), and "Next" (blue).

Configuration Hub allows you to add and manage a collector instance remotely. For more information, refer to [About Configuration Hub](#).

If, however, an earlier version of Configuration Hub is available on the same machine, you will be prompted to enter the details of the existing Configuration Hub, and it will be upgraded to the latest version. If that happens, skip the next step.

**Important:**

By default, Configuration Hub points to the same Proficy Authentication server as the one you provided during the Historian server installation. If you want to install Web-based Clients in a cluster environment, ensure that:

- Configuration Hub does not use the same Proficy Authentication server as that used by the cluster.
- The Proficy Authentication and Configuration Hub details must be the same for all cluster nodes.

12. If you want to install Configuration Hub, ensure that the **Use Existing Configuration Hub** check box is cleared, and then provide values as described in the following table.

Field	Description
Install Location	If needed, modify the installation folder for Configuration Hub.
Plugin Name	If needed, modify the name of the Configuration Hub plugin for Historian. The default value is in the following format: Historian_<host name>. If, however, you are installing Web-based Clients in a cluster environment, the default value is Historian_<cluster name>. You can modify this value, but provide the same value for all the nodes in the cluster.
Server Port	If needed, modify the port number that you want to use for the web server. The default value is 5000. If you want to install Web-based Clients in a cluster environment, provide the same value for all the nodes in the cluster.
Container Port	If needed, modify the port number for the Configuration Hub container. The default value is 4890.
ConfigHub Admin Port	This is the port number of the Configuration Hub admin. The default value is 4890. If needed, you can change the port number.

Field	Description
Client ID	Enter the username to connect to Configuration Hub. The default value is admin. The value that you enter can contain: <ul style="list-style-type: none"> ◦ All English alphanumeric characters (ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghijklmnopqrstuvwxyz_0123456789) ◦ The following special characters: ><:~!@#%&*?
Client Secret	Enter the password to connect to Configuration Hub. The value that you enter can contain: <ul style="list-style-type: none"> ◦ Must contain at least eight characters. ◦ All English alphanumeric characters (ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghijklmnopqrstuvwxyz_0123456789) ◦ The following special characters: ><:~!@#%&*?
Re-enter Secret	Re-enter the password to connect to Configuration Hub.

13. Alternatively, if you want to use an existing Configuration Hub:

- a. Select the **Use Existing Configuration Hub** check box. This check box is disabled if an existing Configuration Hub is detected.
The fields for the existing Configuration Hub appear.

Configuration Hub Installation

Use Existing Configuration Hub:

Plugin-Name:

Server Name:

Server Port:

Client ID:

Client Secret:

[Test Connection](#)

Test Connection Status: Test connection with Existing Configuration Hub Server is pending; click [Test Connection](#)

Enter the Client ID and Secret that you provided while installing Configuration Hug plugin for Historian to register with existing Configuration Hub.

b. Provide values as described in the following table.

Field	Description
Plugin Name	If needed, modify the name of the Configuration Hub plugin for Historian. The default value is in the following format: Historian_<host name>
Server Name	Enter the server name or the FQDN of the existing Configuration Hub server, as displayed in the address bar of the browser when you access Configuration Hub from the machine where Configuration Hub is installed.
Server Port	If needed, modify the port number that you want to use for the web server. The default value is 5000.


Field	Description
Client ID	If needed, modify the username to connect to Configuration Hub. The default value is admin.
Client Secret	Enter the password to connect to Configuration Hub.

c. Select **Test Connection**.

The results of the connection test appear. You cannot proceed until the connection is successful.


14. Select **Next**.

The default installation drive appears.




15. If needed, change the installation drive for Web-based Clients, and then select **Next**.

The log files location page appears.



16. If needed, change the location for log files, and then select **Next**.
The destination Historian server page appears.



17. Provide the name of the destination Historian server to which Web-based Clients are connected by default. When you login to Configuration Hub, the default system will point to this server.



Note:

- Provide the name of either Historian single-server or mirror primary server because the systems in Configuration Hub will be either a stand-alone system or a horizontally scalable system.
- If you want to connect to a remote Historian server, you must disable the **Enforce Strict Client Authentication** and **Enforce Strict Collector Authentication** options using Historian Administrator in the remote server.

18. Select **Next**.

The **You are ready to install** page appears.

19. Select **Install**.

The Web-based Clients installation begins.

20. When you are prompted to reboot your machine, select **Yes**.


Historian Web-based Clients are installed in the following folder: `<installation drive>\Program Files\GE`, and the following registry paths are created:

- HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital
- HKEY_LOCAL_MACHINE\SOFTWARE\GE

If you want to use Configuration Hub installed using other products such as iFIX, Plant Applications, and so on, [set up authentication](#) to point to the Proficy Authentication instance.

Install Web-based Clients at a Command Prompt

1. [Install the Historian server \(on page 105\)](#). During the installation, in the **Configure Web-based Clients** page, select the **Do you wish to continue configuring web-based clients** check box, and provide the Proficy Authentication server and Configuration Hub server details.



2. If you want to use Web-based Clients in a cluster environment, ensure that your network is enabled for multicast traffic, and [set up high availability](#) on each node in the cluster.

This topic describes how to install Web-based Clients at a command prompt. You can also [install Web-based Clients using an installer \(on page 154\)](#).

During the installation, you can choose to use Web-based Clients in a cluster environment, thus ensuring high availability of connection to the Historian server using the client applications.

1. If you want to install Web-based Clients with the default values, run the following command:

```
install.exe /quiet AdminClientSecret=<password> ConfigHubClientSecret=<password>
```

2. If you want to modify the default values, run the following command:

```
install.exe /quiet AdminClientSecret=<password> ConfigHubClientSecret=<password> <parameter>=<value>
```

The following table describes the installation parameters.

Parameter	Description	Default Value
PublicPort	<p>Port for https protocol communication used by Web-based Clients. Ensure that the value for this parameter matches the one you specify while installing the Historian server. In addition:</p> <ul style="list-style-type: none"> ◦ If you will install Operations Hub later on the same machine, the value that you provide for this parameter is populated while installing Operations Hub. ◦ If you have already installed Operations Hub on the same machine, provide the same value that you provided while installing Operations Hub. 	443

Parameter	Description	Default Value
UAAHttpPort	Port for http protocol communication used by the Proficy Authentication service.	9480
UAADatabasePort	Port for the Proficy Authentication database.	9432
HistorianHttpPort	Port for the http protocol communication used by Web-based Clients.	8070
HistorianDatabasePort	Port for the PostgreSQL Historian database.	8432
EmbeddedWebServerAlternativeNames	<p>The fully qualified domain names to access Historian web applications remotely. You can use it to access the Web Admin console using alias names. Enter the values separated by commas.</p> <p>For example, to access the Web Admin console using any of the following URLs, enter <code>Test.abc.ge.com,localhost,127.0.0.1,aliasName</code></p> <ul style="list-style-type: none"> ◦ https:// Test.abc.ge.com /historian-visualization/hwa ◦ https:// 127.0.0.1 /historian-visualization/hwa ◦ https:// aliasName /historian-visualization/hwa ◦ https:// localhost /historian-visualization/hwa 	

Parameter	Description	Default Value
	<p>! Important:</p> <ul style="list-style-type: none"> ◦ Do not enter a space between the values. ◦ If you have already installed Operations Hub on the same machine, enter the same value that you have provided while installing Operations Hub. ◦ If you will install Operations Hub later on the same machine, the value that you provide for this parameter is used while installing Operations Hub. ◦ You must add the IP address and alias name in the <code>hosts</code> file located at <code>C:\Windows\System32\drivers\etc</code>. The IP address that you add 	

Parameter	Description	Default Value
	<p> must be a static or fixed IP address.</p> <p>Format: <code><IP address> <alias name></code></p> <p>Example: <code>1.2.3.4 my-servername</code></p> <ul style="list-style-type: none"> ◦ FQDN is not supported for Configuration Hub. 	
<code>AdminClientId</code>	The client ID to connect to the Proficy Authentication service.	
<code>AdminClientSecret</code>	<p>The password to connect to the Proficy Authentication service. The password must satisfy the following conditions:</p> <ul style="list-style-type: none"> ◦ Must not contain only numbers. ◦ Must not begin or end with a special character. ◦ Must not contain curly braces. <p>If the password does not satisfy these conditions, the installation may be successful, but Web-based Clients will not work.</p>	Not applicable

Parameter	Description	Default Value
	<div data-bbox="667 260 1034 1570" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px;"> <p> Note:</p> <p>The format of user-name for Historian Web-based Clients is <host name>.admin, where <host name> is the machine on which Web-based Clients are installed. And, the default client ID is admin. Both the host name and client ID are case-sensitive.</p> <p>If, however, the Proficy Authentication server hostname is long, resulting in a username longer than 20 characters, Windows does not allow you to create the user. In that case, you can create a Proficy Authentication user, and then create the corresponding Windows user, using the uaa_config_tool utility.</p> </div>	
UseExternalUaa	Identifies whether you want to use an external Proficy Authentication service (that is, a Proficy Authentication instance already installed by an external application such as Operations	0

Parameter	Description	Default Value
	Hub). If you want to use external Proficy Authentication, enter 1.	
<code>ActiveUaaBaseUrl</code>	The base URL to connect to external Proficy Authentication. A value is required only if you want to connect to an external Proficy Authentication service. Enter a value in the following format: <code>https://<Proficy Authentication server machine name>:<public https port number></code> . By default, the port number is 443.	
<code>DoConfigHubNeedToInstall</code>	Identifies whether you want to install Configuration Hub as part of the web-based clients. You can enter 1 to install, or 0 to not install Configuration Hub as you may already have it installed.	0
<code>ConfigHubContainerPort</code>	The web server (https) port that you want to use for Configuration Hub.	5000
<code>ContainerPort</code>	The port for the Configuration Hub container.	4890
<code>ConfigHubAdminPort</code>	The port for the administration service for Configuration Hub.	4920
<code>ConfigHubInstallFolder</code>	The installation folder for Configuration Hub.	<code>C:\Program Files (x86)\GE\Configuration-Hub</code>
<code>UseExternalConfigHub</code>	Identifies whether you want to use Configuration Hub in-	0

Parameter	Description	Default Value
	stalled with iFIX or on a remote machine. If you want to use an external Configuration Hub, enter 1.	
RootDrive	Enter the path pointing to a remote Configuration Hub. For example E:\	
ExternalConfigHubMachineName	Enter the server name or the FQDN of the existing Configuration Hub server, as displayed in the address bar of the browser when you access Configuration Hub from the machine where Configuration Hub is installed.	
ConfigHubClientID	<p>The username to connect to Configuration Hub. The value that you enter can contain:</p> <ul style="list-style-type: none"> ◦ All English alphanumeric characters (ABCDEFGHIJKLMNOPSRTUVWXYZ abcdefghijklmnopqrstuvwxy_0123456789) ◦ The following special characters: ><:~!@#\$%^&*? 	admin
ConfigHubClientSecret	<p>The password to connect to Configuration Hub. The value that you enter can contain:</p> <ul style="list-style-type: none"> ◦ Must contain at least eight characters. ◦ All English alphanumeric characters (ABCDE- 	

Parameter	Description	Default Value
	FGHIJKLMNOPQRS- TUVXYZ abcde- fghijklmnopqrstu- vwxyz_0123456789) ◦ The following special characters: ><:~!@#\$ %^&*?	
IsClusterNode	Indicates whether you want to install Web-based Clients in a cluster environment. If you want to install Web-based Clients in a cluster environ- ment, enter 1. This is not ap- plicable if you are upgrading Web-based Clients.	0
PostgresBaseDir	The folder in the shared drive that you want to use for His- torian database if you want to add the Web-based Clients server to a cluster.	C:\ProgramData\GE\Opera- tions Hub
ClusterFQDN	Enter the client access point of the role for which you have added the resources while set- ting up high availability (on page 182) .	
MulticastAddress	The common IP address that all the nodes in the cluster can use. Enter a value between 224.0.0.0 and 239.255.255.255 (or a hostname whose IP ad- dress falls in this range).	228.0.0.4
HistorianClusterMembership- Port	The common port number that all the nodes in the cluster can use. This port number, in con-	45564

Parameter	Description	Default Value
	junction with the multicast address, is used to create the cluster.	
HistorianClusterReceiverPort	The multicast port number that you want to use for incoming Historian data.	4000
DataPath	The path to the log files.	C:\ProgramData\HistorianWebBasedClientsLogs
DestinationHistorian	<p>The name of the destination Historian server.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: If you want to connect to a remote Historian server, you must disable the Enforce Strict Client Authentication and Enforce Strict Collector Authentication options using Historian Administrator in the remote server.</p> </div>	

To install Web-based Clients with local Proficy Authentication and local Configuration Hub, run the following command:

```
Install.exe /quiet PublicPort=443 UAAHttpPort=9480 UAADatabasePort=9432 HistorianHttpPort=8070
HistorianDatabasePort=8432 AdminClientId=admin AdminClientSecret=abc
ConfigHubContainerPort=5000 ContainerPort=4890 ConfigHubInstallFolder="C:\Program Files
(x86)\GE\ConfigurationHub"
ConfigHubClientID=admin ConfigHubClientSecret=xyz
DataPath="C:\ProgramData\HistorianWebBasedClientsLogs"
```

To install Web-based Clients with local UAA and an external Configuration Hub, run the following command:

```

Install.exe /quiet PublicPort=443 UAAHttpPort=9480 UAADatabasePort=9432 HistorianHttpPort=8070
HistorianDatabasePort=8432 AdminClientId=admin AdminClientSecret=secret123 UseExternalUaa=1
ActiveUaaBaseUrl=https://TESTHIST4.test.com:443
UseExternalConfigHub=1 ExternalConfigHubMachineName=test2019-2 ConfigHubClientID=admin
ConfigHubClientSecret=secret321litc DataPath="E:\ProgramData\HistorianWebBasedClientsLogs"
DoConfigHubNeedToInstall=0 RootDrive="E:\"

```

To install Web-based Clients with external Proficy Authentication and a local Configuration Hub, run the following command:

```

Install.exe /quiet PublicPort=443 UAAHttpPort=9480 UAADatabasePort=9432 HistorianHttpPort=8070
HistorianDatabasePort=8432 AdminClientId=admin AdminClientSecret=abc UseExternalUaa=1
ActiveUaaBaseUrl=https://<external UAA machine hostname>:443
ConfigHubContainerPort=5000 ContainerPort=4890 ConfigHubInstallFolder="C:\Program Files
(x86)\GE\ConfigurationHub"
ConfigHubClientID=admin ConfigHubClientSecret=xyz
DataPath="C:\ProgramData\HistorianWebBasedClientsLogs"

```

To install Web-based Clients in a cluster environment with local Proficy Authentication and local Configuration Hub, run the following command:

```

Install.exe /quiet PublicPort=443 UAAHttpPort=9480 UAADatabasePort=9432
HistorianHttpPort=8070 HistorianDatabasePort=8432 AdminClientId=admin AdminClientSecret=abc
ConfigHubContainerPort=5000
ContainerPort=4890 ConfigHubInstallFolder="C:\Program Files (x86)\GE\ConfigurationHub"
ConfigHubClientId=admin ConfigHubClientSecret=xyz DataPath="C:\ProgramData\HistorianWebBasedClientsLogs"
DestinationHistorian=<Historian server host name> IsClusterNode=1
PostgresBaseDir="E:\pgsql" ClusterFQDN="cluster.domain.com"
HistorianClusterMembershipPort=45564 HistorianClusterReceiverPort=4000
UAAClusterMembershipPort=45565 UAAClusterReceiverPort=4005 MulticastAddress=228.0.0.4

```

Web-based Clients are installed in the following folder: *<installation drive>*:\Program Files \GE, and the following registry paths are created:

- HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital
- HKEY_LOCAL_MACHINE\SOFTWARE\GE

If you want to use Configuration Hub installed using other products such as iFIX, Plant Applications, and so on, [set up authentication](#) to point to the Proficy Authentication instance.

Connect to a Remote Proficy Authentication Service

Provide the details of the external Proficy Authentication instance while [installing Web-based Clients \(on page 154\)](#).

To host a Proficy Authentication service, you can use the same machine on which Web-based Clients are installed or a different one. This topic describes how to connect to a Proficy Authentication service that is set up on a machine different from the one on which you have installed Web-based Clients.


1. Access the Web Admin console.
2. Select **Not Secure**, and then select **Certificate**.
3. Select the root CA certificate in the **Certificate Path** section.
The **Certificate Export Wizard** window appears.
4. Select the **Base-64 encoded X.509 (.CER)** format.
5. Install the certificate in Trusted Root Certification Authorities store.
6. Rename the certificate file from `.cer` to `.pem`.
7. Access Certificate Management Tool.
8. Access the **External Trust** section and import the renamed certificate.
9. Select **No** when prompted to restart GeOphubMasterStarter.
10. Restart the **Proficy Historian Tomcat** service.
11. Reopen the browser.

[Map the user groups of the remote Proficy Authentication service with the Historian Proficy Authentication group](#)

Set Up High Availability of Web-based Clients

1. Create a shared drive on your network that all the nodes in the cluster can access, and create a folder in that drive.
2. On each node that you want to add to the cluster:
 - a. [Install the Failover Clustering feature](#).
 - b. If you want to use an existing Proficy Authentication instance, ensure that all the cluster nodes point to the same Proficy Authentication instance. Note that for *all* the cluster nodes, the Proficy Authentication credentials of the node on which you installed Proficy Authentication *last* will be considered.

In a cluster environment, multiple servers are installed, which share the same data. Each of these servers is called a node. One of them acts as the primary node, while the others are standby nodes. If the primary node is down, one of the standby nodes is used.



When you install Web-based Clients in a cluster environment, the web servers are added to the cluster. You can then achieve high availability of connection between the Historian server and the client applications.

For example, if Configuration Hub on the primary node is unable to connect to the Historian server, the user session on the standby node is activated. Therefore, you will still be able to connect to the Historian server using Configuration Hub installed on the standby node.

The following services are shared between the primary and standby nodes in a cluster:

- Historian Indexing Service
- Proficy Historian PostgreSQL Database

Historian works with Microsoft Failover Cluster Manager to ensure high availability of Web-based Clients. Using Failover Cluster Manager, you must add these services to the cluster.

1. Access the primary node of the cluster.
2. [Create a failover cluster.](#)
3. [Add a storage to the failover cluster.](#)
4. Select **Roles > Create Empty Role**.
A role is created.
5. Add a client access point to the role:
 - a. Select the role.
 - b. In the **Actions** section, select **Add Resource > Client Access Point**.
 - c. Follow the on-screen instructions to add a client access point to the role.
6. Add a storage to the role:

- a. Select the role.
- b. In the **Actions** section, select **Add Storage**.
- c. Follow the on-screen instructions to add the storage that you have created in step 3. You can use a storage only once.

7. Ensure that your network is enabled for multicast traffic. To do so, run the following command:

```
netsh <interface name> <IP address> show joins
```

A list of IP multicast groups that have been joined through an interface appears. If you do not specify an interface name, a list of multicast groups for all interfaces appears.

8. [Install Web-based Clients \(on page 155\)](#). During the installation, select the **Cluster Node** check box, and provide the details.
 9. [Import the Proficy Authentication certificate \(on page 182\)](#) into all the cluster nodes. Copy the certificate in the following path from any node in the cluster and paste it in the same folder in all the other nodes: C:\Program Files\GE\Operations Hub\httpd\conf\cert.
10. Add resources to the role:

- a. Select the role.
- b. In the **Actions** section, select **Add Resource > Generic Service**.
The **New Resource Wizard** window appears.
- c. In the list of resources, select **Historian Indexing Service**, and then follow the on-screen instructions to add the service.

11. Perform the previous step to add the Proficy Historian PostgreSQL Database resource as well.

12. Add the following dependencies for each of these resources:

- a. Double-click a resource.
The **<resource name> Properties** window appears.
- b. Select **Dependencies**.
- c. Select **Insert**, and add dependencies for each resource as described in the following table, using the AND operation.

Resource Name	Dependencies
Proficy Historian PostgreSQL Database	<ul style="list-style-type: none"> ▪ IP Address ▪ Storage ▪ The network name

Resource Name	Dependencies
Historian Indexing Service	<ul style="list-style-type: none"> ▪ IP Address ▪ Storage ▪ The network name ▪ Proficy Historian PostgreSQL Database

13. Select the role, and then in the **Actions** section, select **Start Role**.

When you later install Web-based Clients and provide the cluster details, Web-based Clients will be part of the cluster, thus achieving high availability.

1. Restart the following services on all the cluster nodes:
 - Historian Indexing Service
 - Proficy Historian PostgreSQL Database
2. On the machine on which you have installed the Historian server, update the URI of the following registry key to point to the cluster FQDN: `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc\iHistorian\SecurityProvider\OAuth2`.

Upgrade Web-based Clients

- When you upgrade, Web-based Clients and associated data will be lost. Therefore, back up Web-based Clients and associated data using the `uaa_config_tool` utility provided in the `Utilities` folder of the ISO package. For information, refer to [Migrate User Authentication Data from Historian to Common Proficy Authentication Service \(on page 248\)](#).



Tip:

After installation, `uaa_config_tool` is available in the following folder as well:
`<installation drive>\Program Files\GE Digital\Historian Config`

- You cannot upgrade Web-based Clients from a version earlier than 8.0. This is because, starting 8.0, Web-based Clients are installed separately (not as part of the Historian server installation). Therefore, you must do either of the following:
 - Install Web-based Clients on a new machine.
 - Uninstall the Historian server (remember to back up the Proficy Authentication using the `UAA_config_tool` utility), and then install Web-based Clients.
- If the machine name has changed, you must uninstall and reinstall Web-based Clients.

- If you want to use a different Proficy Authentication server from the previous one, you must manually migrate the Proficy Authentication data to new Proficy Authentication server using the `uaa_config_tool` utility.
- If you want to switch from using a local Proficy Authentication to using an external Proficy Authentication (or vice versa), you must manually change the Proficy Authentication details.

1. [Install Web-based Clients \(on page 154\)](#).

Web-based Clients will be upgraded to the latest version.

2. Clear the browser cache.

You can now access Web-based Clients.

Configure Web-based Clients

You can configure the following settings for Web-based Clients:

- Reconfigure Proficy Authentication to point to a different Proficy Authentication server.
- Reconfigure the same Proficy Authentication instance to resolve any issues with login.
- Re-register Configuration Hub to resolve any issues.
- Unregister Configuration Hub, and register another one.

To perform these tasks, Historian provides a utility called Web Based Clients Configuration. It is installed during Web-based Clients installation.

To run this utility, run the `Web_Clients_Configuration_Tool.exe` file. By default, it is located in the following folder: `C:\Program Files\GE Digital\Historian Config`

Remote Management Agents


Install Remote Management Agent Using the Installer

Ensure that all the collectors that you want to manage remotely are in the running state.

If the collectors that you have installed are earlier than version 9.0, you must install Remote Management Agent on each machine on which the collectors that you want to manage are installed. For collectors version 9.0 or later, Remote Management Agent are automatically installed when you install collectors.

This topic describes how to install Remote Management Agent using the installer. You can also [install them at a command prompt \(on page 190\)](#).

1. Run the `InstallLauncher.exe` file.
2. Select **Install Remote Management Agents**.
The welcome page appears.
3. Select **Next**.
The license agreement appears.
4. Select the **Accept** check box, and then select **Next**.
The default installation drive appears.



5. If needed, modify the installation drive, and then select **Next**.
The destination Historian server page appears.

Historian Server Details

Provide a valid windows user of the default Historian server to which the Remote Collector Manager will connect.

Historian Server:

User Name:


Password:

Confirm Password:

Note: If you have created security groups or enabled strict client/collector authentication, provide the destination Historian credentials. If the password changes, you must reinstall Remote Management Agents to reset the password.

6. Enter the details of the Historian server to which Remote Management Agent will connect, and then select **Next**.

The **Data Directory** page appears.



7. As needed, modify the location of the data directory, or leave the default value, and then select **Next**.

The **You are ready to install** page appears.

8. Select **Install**.

- Remote Collector Management is installed on your machine.
- A folder named `Historian Remote Management Agents` is created in the `GE Digital` folder in the installation location that you specified.
- Remote Collector Management is running, and a `.shw` file is created in the log folder. This file contains the details of the collectors that are running on the machine.
- For each collector that you manage using Remote Collector Management, a new entry named `ServiceName` is created in the collector registry. If the `ServiceName` key is not created or updated incorrectly, refer to [Troubleshooting Remote Collector Management Issues \(on page 820\)](#).

Install Remote Management Agent at a Command Prompt

Ensure that all the collectors that you want to manage remotely are in the running state.

If the collectors that you have installed are earlier than version 9.0, you must install Remote Management Agent on each machine on which the collectors that you want to manage are installed. For collectors version 9.0 or later, Remote Management Agent are automatically installed when you install collectors.

This topic describes how to install Remote Management Agent at a command prompt. You can also [install them using the installer \(on page 187\)](#).

1. Access the command prompt, and navigate to the RMA folder in the install media.
2. Run the following command, replacing the values in angular brackets with the appropriate values:

```
HistorianRMA_Install.exe -s RootDrive=<installation drive> DestinationServerName=<Destination Historian server name>
UserNamel=<Windows username> Password=<Windows password> DataPath="C:\Proficy Historian Data\LogFiles"

HistorianRMA_Install.exe -s RootDrive=C:\ UserNamel=Administrator Password=AdminPassword
DestinationServerName=VMHISTWEBAUTO DataPath="C:\Proficy Historian Data\LogFiles"
```

- Remote Collector Management is installed on your machine.
- A folder named `Historian Remote Management Agents` is created in the `GE Digital` folder in the installation location that you specified.
- Remote Collector Management is running, and a `.shw` file is created in the log folder. This file contains the details of the collectors that are running on the machine.
- For each collector that you manage using Remote Collector Management, a new entry named `ServiceName` is created in the collector registry. If the `ServiceName` key is not created or updated incorrectly, refer to [Troubleshooting Remote Collector Management Issues \(on page 820\)](#).

Install the OPC UA HDA Server


[Install Historian \(on page 104\)](#).



Note:

You can install Historian and the OPC UA HDA server on the same machine or on different machines.

1. Run the Historian installer.
2. Select **Install Historian OPC UA HDA Server**.
The welcome page appears.
3. Select **Next**.
The license agreement appears.



4. Select the **Accept** check box, and then select **Next**.

The **Where to install the Historian OPC UA HDA Server** page appears, asking you to select the installation drive.

5. Select the installation drive, and then select **Next**. You can retain the default one, or choose a different one.

The **OPC UA HDA Server Attributes** page appears.

OPC UA HDA Server Attributes.

Historian OPCUA HDA Server :

Port Number : 48010


URI : opc.tcp://sitahiststnd:48010

Cancel Previous Next

6. Provide values as described in the following table, and then select **Next**.

Field	Description
Historian OPCUA HDA Server	Enter the host name or the IP address of the machine on which you want to install the OPC UA HDA server. By default, the local host name appears.
Port Number	Enter the port number that you want the OPC UA HDA server to use.
URI	The URI to access the OPC UA HDA server. This field is disabled and populated with a value in the following format: <code>opc.tcp://<host name>:<port number></code> , where <code><host name></code> and <code><port number></code> are the values that you have entered in the preceding fields.

The **Historian Server Details** page appears.



Historian Server Details.

Historian Server Name : myhistserver

Historian Server User Name :

Historian Server Password :

Cancel Previous Next

7. Provide values as described in the following table, and then select **Next**.

Field	Description
Historian Server Name	Enter the name of the Historian server that you want to connect to the OPC UA HDA server.
Historian Server User Name	Enter the username of the Historian server.
Historian Server Password	Enter the password of the Historian server.

The **You are ready to install** page appears.

8. Select **Install**.

The Historian OPC UA HDA server is installed. Reboot the machine when prompted to do so.

- If you have installed the OPC UA HDA server on a remote machine, enable the firewall.
- Install an OPC UA client.
- Configure the OPC UA HDA server.

The Excel Add-In for Historian

Install the Historian Excel Add-in Using the Installer

Install one of the following 32-bit or 64-bit Microsoft® Excel® applications:

- Microsoft® Excel® 2019
- Microsoft® Excel® 2016
- Microsoft® Excel® 2013
- Microsoft® Excel® 2010

You can install Excel Add-In separately or during Client Tools installation. This topic describes how to install Excel Add-In separately using the installer. You can also [install it at a command prompt \(on page 195\)](#). However, if installing via a command prompt, do not install the Excel Add-In on the machine that you have installed the Historian Administrator or data archiver.

1. Run the `InstallLauncher.exe` file.
2. Select **Install Excel Add-in for Historian**.

The installer runs through the installation steps.



Note:

If using certain versions of Windows (like Windows 10 or Windows 2019), you may receive an error message, stating that some of the DLL files are not registered. You can ignore these messages.

3. When prompted to reboot your system, select **Yes**.

Excel Add-In is installed.

[Activate Excel Add-In \(on page 197\)](#).

Install the Historian Excel Add-in at a Command Prompt

1. Install one of the following 32-bit or 64-bit Microsoft® Excel® applications:
 - Microsoft® Excel® 2019
 - Microsoft® Excel® 2016
 - Microsoft® Excel® 2013
 - Microsoft® Excel® 2010
2. [Install Excel Add-in using the installer \(on page 195\)](#) on your machine:

- a. Open the Command Prompt as an Administrator. (From the Start menu, right-click the Command Prompt app, and select Run as Administrator.)
- b. On the Historian install media, navigate to the Excel folder.
- c. Run the following command line: `setup.exe -r`.
- d. When the install runs, select the Excel option and leave the other options greyed out as they cannot be removed.

When you run this install, a template file named `setup.iss` is created at `C:\Windows`. This file stores the installation options that you have provided during the installation.

After completing the installation, you can then use this `.iss` file to install Excel Add-in at a command prompt on other machines.

On the other Client machine where you want to install the Excel Add-in, place a copy of the **setup.iss** on the local directory and open a Command Prompt (Run as Administrator). Run the silent install with following command:

```
setup.exe /s
```

If your `iss` file is not called **setup.iss** or is in different directory than `setup.exe` you need to add the flag: `/f1`. For example:

```
setup.exe /s /sms /f1"C:\Temp\setup.iss
```

Wait for few minutes (probably 3-5 minutes) for the install to complete.

You can install Excel Add-In separately or during Client Tools installation. However, do not install Excel Add-In on the machine on which you have installed Historian Administrator or data archiver.

1. Copy the `setup.iss` file to each machine on which you want to install Excel Add-in at a command prompt.
2. In the folder that contains the `setup.iss` file, run the following command: `setup.exe /s /sms`
The installer runs through the installation steps.



Note:

If using certain versions of Windows (like Windows 10 or Windows 2019), you may receive an error message, stating that some of the DLL files are not registered. You can ignore these messages.

3. When prompted to reboot your system, select **Yes**.


Excel Add-In is installed.

Activate Excel Add-In (on page 197).

Activate Excel Add-In

Install Excel Add-In (on page 195).


1. Open a new Microsoft Excel worksheet.
2. Select **File > Options**.
The **Excel Options** window appears.
3. Select **Add-Ins**.
4. In the **Manage** box, select **Excel Add-ins**, and then select **Go**.
The **Add-Ins** window appears.



5. Select the **Proficy Historian Add-In** and **Proficy_Historian_Helper** check boxes, and then select **OK**.
If the **Proficy Historian Add-In** and **Proficy_Historian_Helper** check boxes do not appear, select **Browse** to locate the `Historian.xla` file for the check boxes to appear. This file is created if you have installed Microsoft Excel after installing Excel Add-In. By default, the `Historian.xla`

file is located in the C:\Program Files\Proficy\Historian or C:\Program Files (x86)\Proficy\Historian folder.

Excel Add-In is now ready to use and the **Proficy Historian** menu is now available in the Microsoft Excel toolbar.



Software Requirements

The following components are required to use Excel Add-in for Operations Hub:

Component	Version	Description
Operations Hub	2.0 and above.	<p>If you have purchased the standard or enterprise license of Historian, you receive a no-cost license for Operations Hub, which enables you to:</p> <ul style="list-style-type: none"> • Access to the Historian Analysis run-time application, which is an in-built HTML5 application in Operations Hub. • Perform advanced trend analysis, including inserting annotations. • Define an asset model including tag mapping.
Microsoft Excel	2016 and 2019 (32 bit or 64 bit)	
Historian REST APIs		Historian REST APIs are required to integrate between Historian and Operations Hub. Historian REST APIs are installed automat-

Component	Version	Description
		ically when you install Historian Web-based Clients (on page 155) .

Install Excel Add-In for Operations Hub

Install the [Historian server \(on page 104\)](#) and other [software requirements \(on page 198\)](#).


1. Run the `InstallLauncher.exe` file.
2. Select **Install Excel Add-in for Operations Hub**.
The welcome page appears.
3. Select **Next**.
4. Read and accept the license agreement, and then select **Next**.
5. Select the available disk to install the Excel Add-in for Operations Hub, and then select **Next**.



Note:

We recommend that you select the drive where Microsoft Excel is installed.

6. Provide the details of Operations Hub, and then select **Next**.



Provide the Operations Hub details:

Operations Hub Server:

Operations Hub UAA Server(url):

Cancel Previous Next

The **You are ready to install** page appears.

7. Select **Install**.


Excel Add-In for Operations Hub is installed.

[Copy/export the issuer certificate \(on page 200\)](#), and then [install/import it \(on page 201\)](#).

Copy or Export the Issuer Certificate on Server

[Install Excel Add-In for Operations Hub \(on page 199\)](#).

This topic describes how to copy or export the issuer certificate on Server. If this is not done, you will get an error while querying data as shown in the image below.



1. Navigate to the machine where Operations Hub is installed.
2. Select **Site Information (Not secure)**.
3. Select **Certificate (invalid)**.
The **Certificate** window appears.
4. Select **Certificate Path**.
5. Select the Root CA certificate.
6. Select **Details**.
7. Select **Copy to file**.
The **Certificate Export Wizard** window appears.
8. Select **DER encoded binary X.509(.CER)** format and select **Next**.
9. Select **Browse** to save the certificate file at desired location.
10. Complete the certificate export.

[Install or import the certificate \(on page 201\)](#).

Install/Import the Issuer Certificate

[Copy or export the issuer certificate \(on page 200\)](#) on the machine on which Excel Add-In for Operations Hub is installed.

1. Right-click the certificate, and then select **Install Certificate**.
The **Certificate Import Wizard** page appears
2. Select **Local Machine**, and then, select **Next**.
3. Select **Place all certificates in the following store**.
4. Select **Trusted Root certification Authorities**, and then select **OK**.
5. Select **Next**, and then select **Finish**.
The certificate is imported.

[Configure the Operations Hub server \(on page 202\)](#).

Connect to Operations Hub

To query a model defined in Operations Hub, you must first connect to the Operations Hub server. You will then receive a token from the server, which will be used for authentication.

1. Select **Configuration** menu in Admin.
The **Operations Hub Configuration** window appears.
2. Provide values as described in the following table.

Field	Details
Operations Hub Server	The Operations Hub server name to which you want to connect and get the data.
Operations Hub Proficy Authentication Server (url)	The URL of the Proficy Authentication service of Operations Hub. Example: https://<ophubservername>/uaa



Note:

The **Token Status** field indicates the status of the connection with Operations Hub server.

3. Select **Connect**.
The login page appears.
4. Provide the **User Identifier** and **Password** to connect to Operations Hub.
5. Select **Open UaaAuthSchemeHandler**.
Operations Hub Server to which you are connected and the status of the token appears.
6. Select **Save** to save the Operations Hub server details. The configuration will be retained and used when you open excel add-in again.

Install the Historian ETL Tools

- If you want to use the Historian Extract, Transform, and Load (ETL) tools to transfer data from a PI Historian server, install the PI SDK package.
- If you want to use the ETL tools to transfer data from an eDNA server, copy the following eDNA binaries to the <installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract folder:

- EzDnaApi.dll
- EzDNAApiNet.dll


By default, these files are available in the following folder on the machine on which the eDNA server is installed: `C:\Program Files(x86)\eDNA`

Installing ETL installs the following tools:

- The Extract tool
- The Transform tool
- The Load tool

This topic describes how to install ETL to extract, transform, and load data from an onsite Historian machine to the destination Historian server. You must install Historian ETL on both the onsite Historian machine and the destination Historian server (that is, the source and destination machines for data transfer).

1. Run the `InstallLauncher.exe` file.
2. Select **Install Historian ETL Tools**.
The welcome page appears.
3. Select **Next**.
The license agreement appears.
4. Select the **Accept** check box, and then select **Next**.
The default installation drive appears.



5. If required, modify the installation drive for Historian ETL, and then select **Next**.

A message appears, stating that you are ready to install ETL.

6. Select **Install**.

The Historian ETL tools are installed on your machine.

- The following folders are created in the `<installation drive>/Program Files/GE Digital` folder:
 - Historian ETL eDNA Extract
 - Historian ETL Extract
 - Historian ETL Load
 - Historian ETL ODBC Extract
 - Historian ETL PI Extract
 - Historian ETL Transform
- The following services are installed:
 - Historian ETL eDNA Extract
 - Historian ETL Extract
 - Historian ETL ODBC Extract_x64

- Historian ETL ODBC Extract_x86
- Historian ETL Load
- Historian ETL PI Extract
- The following registry paths are created:
 - HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\GE Digital\Historian ETL eDNA Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\GE Digital\Historian ETL ODBC Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\Historian ETL Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\Historian ETL ODBC Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\Historian ETL PI Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\Historian ETL Load

1. If you want to extract data from an eDNA server, copy the `Customdna.ini` file in the eDNA server into the `C:\Windows` folder on the machine on which you have installed ETL.
2. Extract data from [an eDNA server \(on page 2910\)](#), [ODBC data source \(on page 2924\)](#), [Proficy Historian \(on page 2938\)](#), or [PI Historian \(on page 2948\)](#).

About Installing Help

Historian documentation is available both online and offline. This topic describes how to install the offline Help documentation. Online Help is available here: <https://www.ge.com/digital/documentation/historian/>

You can install Help using a GUI-based installer or at the command prompt.

Install Standalone Help Using the Installer

This topic describes how to install Help using the installer. You can also [install Help at a command prompt \(on page 206\)](#).

1. Run the `InstallLauncher.exe` file.
2. Select **Install Standalone Help**.
The welcome page appears.
3. Select **Next**.
The license agreement appears.
4. Select the **Accept** check box to accept the license agreement, and select **Next**.
5. If needed, change the installation drive, and then select **Next**.
6. If needed, change the port number for the NodeJS server to run. This step is required if the default port number is not available.

7. Select **Next**.
8. Select **Install**.

The Help is installed.

9. Select **Next**.

The standalone Help is installed in the following folder: `<installation drive>:\Program Files\Proficy\Proficy Historian\ProficyDoc`. You can access the Help from any of the Historian applications or by accessing the `index.html` file.

Install Help at a Command Prompt

This topic describes how to install Help at a command prompt. You can also [install Help using the installer \(on page 205\)](#).

1. Navigate to the `Help` folder.
2. If you want to use the default installation drive (`C:/`) and port number (`7070`), run the following command:

```
Help_Install.exe -s
```

Otherwise, run the following command:

```
Help_Install.exe -s RootDrive=<installation drive> PortNumber=<port number>
```

The Help is installed. You can access the Help from any of the Historian applications or by accessing the `index.html` file. By default, this file is available in the `C:\Program Files (x86)\GE Digital\Historian Help` folder.

Configuring Certificate-based Security to use MTLS

Overview of the Certificate-based Security

Historian uses the Mutual Transport Layer Security (MTLS) protocol along with certificate-based security to strengthen the authentication mechanism and build trusted connections among the core Historian services, and also collectors.




Note:

MTLS Security and **MTLS Data Encryption** are not applicable to the File collector.

The core Historian services include:

- Data Archiver
- Client Manager
- Configuration Manager
- Diagnostic Manager

When you install Historian, you are provided with the **Enable Certificate-based Security** check box to enable Certificate-based Security and generate root certificate with a password for Server and the core services. By selecting this option, the installer will generate the root certificates, machine specific certificates, and the core services certificates in the <Install directory>\Program Files \Proficy\Proficy Historian\MTLS folder, and add it to Trusted Root Certification Authorities in the machine.

**Warning:**

If you do not select the **Enable Certificate-based Security** check box during installation, you must generate the root certificates manually, as described in the Manually Install Certificates for Historian section. However, this is not recommended.

Certificate	Applicability
ica_key.cer and ica_key.pfx	Root certificates.
ClientManager.cer, and ClientManager.pfx	Historian Core Services specific certificates.
ConfigManager.cer, and ConfigManager.pfx	
DataArchiver.cer, and DataArchiver.pfx	
DiagnosticManager.cer, and DiagnosticManager.pfx	
<Machine name>.cer, and <Machine name>.pfx	Machine specific certificates.

If you want to connect a distributed/mirror node to a Historian primary mirror server, or you want to connect your collectors to a remote Historian server, you need the server specific root certificates (ica_key.cer and ica_key.pfx) on the client machine to establish a successful handshake. To establish a successful handshake, you must copy the root certificates from the server machine and place them in the machines where the mirror nodes or collectors are installed. For more information, see the table below.

After installation, based on the install type, you must perform the following configuration:

Installation Type	Description	Configurations
<p>Historian Single Server</p>	<p>This is for a stand-alone Historian system, which contains only one Historian server. This type of system is suitable for a small-scale Historian setup.</p>	<p>Collectors and server are installed on the same machine</p> <p>You do not have to perform any additional configurations.</p> <p>To use MTLS for collectors, you must enable the MTLS security for the collector instance as needed. For more information, refer to Enable MTLS Security for Collectors.</p> <p>Collectors and server are installed on different machines (Collectors trying to connect to a remote Historian)</p> <ol style="list-style-type: none"> 1. On the server machine, from the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder, copy

Installation Type	Description	Configurations
		<p>the following root certificate files: ica_key.cer and ica_key.pfx, and then place them in the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder on the collector machine. For more information, refer to Copy server root certificate to the client machine.</p> <ol style="list-style-type: none"> 2. On the collector machine, add the copied certificates to the Trusted Root Certification Authorities folder. For more information on how to add a certificate to the Trusted Root Certification Authorities folder, refer to Adding a Certificate to the Trusted Root Certification Authorities Folder. 3. Generate MTLS certificate (client certificate) on the collector machine. For more information on how to generate MTLS certificate (client certificate), refer to Generate MTLS certificate. 4. To use MTLS for collectors, you must enable the MTLS security for the collector instance as needed. For more information, refer to Enable MTLS Security for Collectors.
<p>Historian Mirror Primary Server</p>	<p>This is for a horizontally scalable Historian system, which contains multiple Historian servers, all of which are connected to one another. This will be the primary server for the distributed/mirror node(s).</p>	<p>Collectors and Historian primary mirror server are installed on the same machine</p> <p>You do not have to perform any additional configurations.</p> <p>To use MTLS for collectors, you must enable the MTLS security for the collector in-</p>

Installation Type	Description	Configurations
		<p>stance as needed, for more information, refer to Enable MTLS Security for Collectors.</p> <p>Collectors and Historian primary mirror server are installed on different machines (Collectors trying to connect to a remote Historian primary mirror server)</p> <ol style="list-style-type: none"> 1. On the mirror server machine, from the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder, copy the following root certificate files: ica_key.cer and ica_key.pfx, and then place them in the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder on the collector machine. For more information, refer to Copy server root certificate to the client machine. 2. On the collector machine, add the copied certificates to the Trusted Root Certification Authorities folder. For more information on how to add a certificate to the Trusted Root Certification Authorities folder, refer to Adding a Certificate to the Trusted Root Certification Authorities Folder. 3. Generate MTLS certificate (client certificate) on the collector machine. For more information on how to generate MTLS certificate (client certificate), refer to Generate MTLS certificate. 4. To use MTLS for collectors, you must enable the MTLS security for

Installation Type	Description	Configurations
		the collector instance as needed, for more information, refer to Enable MTLS Security for Collectors.
Historian Distributed/Mirror Node	This is for a horizontally scalable Historian system. Installing this server will allow you to add this node to a primary server.	<p>Configuration on the distributed/ mirror node machine(s)</p> <ol style="list-style-type: none"> 1. On the Historian mirror primary server machine, from the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder, copy the following root certificate files: ica_key.cer and ica_key.pfx, and then place them in the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder on the distributed/mirror node machine(s). For more information, refer to Copy server root certificate to the client machine. 2. On the distributed/mirror node machine(s), add the copied certificates to the Trusted Root Certification Authorities folder. For more information on how to add a certificate to the Trusted Root Certification Authorities folder, refer to Adding a Certificate to the Trusted Root Certification Authorities Folder. 3. Generate MTLS certificate (client certificate) on the distributed/mirror node machine(s). For more information on how to generate MTLS certificate (client certificate), refer to Generate MTLS certificate.

Installation Type	Description	Configurations
		<p>Collectors and distributed/mirror node are installed on the same machine</p> <p>You do not have to perform any additional configurations.</p> <p>To use MTLS for collectors, you must enable the MTLS security for the collector instance as needed, for more information, refer to Enable MTLS Security for Collectors.</p> <p>Collectors and distributed/mirror node are installed on different machines (Collectors trying to connect to a remote distributed/mirror node)</p> <ol style="list-style-type: none"> 1. On the Historian mirror primary server machine, from the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder, copy the following root certificate files: ica_key.cer, ica_key.pfx, and then place them in the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder on the distributed/mirror node machine(s). For more information, refer to Copy server root certificate to the client machine. 2. On the distributed/mirror node machine(s), add the copied certificates to the Trusted Root Certification Authorities folder. For more information on how to add a certificate to the Trusted Root Certification Authorities folder, refer to Adding a Certifi-

Installation Type	Description	Configurations
		<p>cate to the Trusted Root Certification Authorities Folder.</p> <ol style="list-style-type: none"> 3. On the Historian distributed/mirror node machine, from the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder, copy the following root certificate files: ica_key.cer, ica_key.pfx, and then place them in the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder on the collector machine. For more information, refer to Copy server root certificate to the client machine. 4. On the collector machine, add the copied certificates to the Trusted Root Certification Authorities folder. For more information on how to add a certificate to the Trusted Root Certification Authorities folder, refer to Adding a Certificate to the Trusted Root Certification Authorities Folder. 5. Generate MTLS certificate (client certificate) on the collector. For more information on how to generate MTLS certificate (client certificate), refer to Generate MTLS certificate. 6. To use MTLS for collectors, you must enable the MTLS security for the collector instance as needed, for more information, refer to Enable MTLS Security for Collectors.

**Note:**

If you are using a cluster node setup, you can follow the configurations similar to the Historian Single Server installation type on all the nodes.

Certificate-based Security Specific Configurations

Copy Server root certificate to the Client Machine

If you want to connect a distributed/mirror node to a Historian primary mirror server, or you want to connect your collectors to a remote Historian server, you need the server specific root certificates (ica_key.cer and ica_key.pfx) on the client machine to establish a successful handshake. To establish a successful handshake, you must copy the root certificates from the server machine and place them on the machines where the mirror nodes or collectors are installed.


1. On the server machine, from the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder, copy the following root certificate files: ica_key.cer and ica_key.pfx.
2. On the client machine (remote mirror nodes or collectors) place them in the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder.
3. Add the certificate to the Trusted Root Certification Authorities folder.

Adding a Certificate to the Trusted Root Certification Authorities Folder


If you want to connect a distributed/mirror node to a Historian primary mirror server, or you want to connect your collectors to a remote Historian server, the root certificate needs to be added to the Trusted Root Certification Authorities folder on the local machine (that is distributed/mirror node or collector machine).

On the primary server machine, from the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder, copy the following root certificate files: ica_key.cer and ica_key.pfx, and then place them in the <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder on the local machine (that is distributed/mirror node or collector machine).


1. Double-click the `ica_key.cer` file. The certificate dialog appears as shown in the following image.




2. Select **Install Certificate** to launch the Certificate Import Wizard.
3. Click **Next** to continue. The **Certificate Import Wizard** window appears as shown in the following image.




4. Select **Local Machine** and click **Next** to continue. The following screen appears.



5. Select **Place all certificates in the following store**, and click **Browse** to display the list of stores from where Trusted Root Certification Authorities can be selected.
6. Select the **Trusted Root Certification Authorities**, and click **OK**. The following dialog box appears.



7. Click **Next** to continue. The **Completing the Certificate Import Wizard** window appears.



8. Click **Finish** to add the certificate to the **Trusted Root Certification Authorities**.

Generate MTLS Certificate

If you want to connect a distributed/mirror node to a Historian primary mirror server, or if you want to connect your collectors to a remote historian server, you must generate the client certificates (MTLS Certificate) specific to the distributed/mirror node or collector machine. This will create the needed machine specific certificates and registries. You can also generate core services certificates if needed.

You must install the distributed/mirror node, or in the case of collectors, you must install collectors.

To generate client certificates (MTLS certificates), run the `MTLSCertificatesInstall.exe` utility from the command prompt with Administrator privileges.

1. Launch from the command prompt with Administrator privileges in the following format: `c:`

```
\Program Files\Proficy\Proficy Historian\MTLS\MTLSCertificatesInstall.exe [Password]
[Certificate Validity] [Create only client Certificate] [Remote Historian Machine Name]
```

```
Microsoft Windows [Version 10.0.17763.5329]
(c) 2018 Microsoft Corporation. All rights reserved.

E:\Program Files\Proficy\Proficy Historian\MTLS>MTLSCertificatesInstall.exe
The file "MTLSCertificatesInstall.exe" is signed and the signature was verified.

Error : Command line options are not provided.

*****Usage*****
*****

Below is the example for creating the core service certificates with root certificate password
[Password="x123y456" NumberOfDays=365(Certificate Validity)]

MTLSCertificatesInstall.exe x123y456 365

Below is the example for creating the client certificates with root certificate password
[Password="x123y456" NumberOfDays=3650(Certificate Validity) CreateOnlyClientCert=0 RemoteHistorianMachineName=ServerName]

MTLSCertificatesInstall.exe x123y456 3650 1 DemoServerName

*****
*****
```

For example,

```
C:\Program Files\Proficy\Proficy Historian\MTLS\MTLSCertificatesInstall.exe P@55w0RD 3650 1 DemoServerName
```

The **MTLSCertificatesInstall.exe** utility takes the following arguments:

Argument	Description
Password	<p>Specifies the word or phrase that you use to protect your certificate. The Password argument is mandatory, whereas Number of Days is optional. An example Passphrase is: P@55w0rd.</p> <div data-bbox="862 1524 1427 1854" style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note: The same Password used for creating the root certificate needs to be used here. This is so that the Password will be same while passing the argument between executables. The MTLSCertificatesInstall.exe utility uses this pass-</p> </div>

Argument	Description
	 word to open the root certificate private key (ica_key.pfx) and sign the core services certificates.
NumberOfDays	<p>Optional. Specifies the Number of Days for the root certificate to be valid. After the specified days, the certificate validity expires.</p> <p>If you do not pass any value for Number of Days, the setting defaults to 365 days. For example, if the Number of Days is 3650, the certificate is valid for 10 years from the generated date.</p>
CreateOnlyClientCert	Specifies that only client certificates with a root certificate password must be created. You must enter 1 to install only the client certificates.
RemoteHistorianMachineName	Specifies the remote Historian server to which you want to connect to.

The client certificates are created and added to the Trusted Root Certification Authorities Folder. For example, if the machine name is **Node1**, the certificates are created as **Node1.cer** and **Node1.pfx**.

2. After the required certificates are generated, restart the machine. Without valid certificates, core services cannot establish connections to each other.

Generate Root Certificates for Proficy Historian Server Manually (Not recommended)

This topic describes how to install root certificates and the certificates for core services, for use with the MTLS feature for Proficy Historian.



Note:

This topic is applicable if you did not enable certificate-based security during the installation of Historian server. If you enabled certificate-based security during the installation, the root



certificate and core services certificates are generated by default and stored at <Install directory>\Program Files\Proficy\Proficy Historian\MTLS folder.

MTLS Binaries

To support MTLS, the Historian install media includes the following files. These files are located in the MTLS folder in the Proficy Historian install folder:

- CreateRootCertificate.exe
- MTLSCertificatesInstall.exe
- openssl.exe
- legacy.dll
- libcrypto-3-x64.dll
- libssl-3-x64.dll
- openssl.cnf

CreateRootCertificate.exe and **MTLSCertificatesInstall.exe** are the two command-line utilities for generating the certificates. The other binaries are the dependent components.

Location of MTLS Binaries

The following figure shows an example of the binaries folder for MTLS feature, when Proficy Historian 2024 is installed in “C” drive:

This PC > Windows (C:) > Program Files > Proficy > ProficyHistorian > MTLS

Name	Date modified	Type	Size
CreateRootCertificate.exe	12/15/2022 11:41 AM	Application	22 KB
MTLSCertificatesInstall.exe	12/15/2022 11:41 AM	Application	37 KB
openssl.exe	3/15/2022 9:20 PM	Application	700 KB
legacy.dll	3/15/2022 9:20 PM	Application exten...	152 KB
libcrypto-3-x64.dll	3/15/2022 9:20 PM	Application exten...	5,008 KB
libssl-3-x64.dll	3/15/2022 9:20 PM	Application exten...	754 KB
openssl.cnf	3/15/2022 9:20 PM	CNF File	13 KB

To generate root certificate, use the `CreateRootCertificate.exe` utility (in the MTLS folder in the Historian install folder) from a command prompt with **Administrator privileges**, as described in the following steps.

1. Right-click the Command Prompt, and select **Run as Administrator**.
2. Navigate to the MTLS folder in the Historian installed path. For example:

```
cd C:\Program Files\Proficy\Proficy Historian\MTLS
```

3. Run the `CreateRootCertificate.exe` command using the following arguments:

Argument	Description
EnableMTLS	<p>Specifies whether MTLS is enabled. If you do not specify a value, MTLS feature is enabled by default (and set to 1 by default):</p> <ul style="list-style-type: none"> ◦ 0 – MTLS feature is disabled ◦ 1 – MTLS feature is enabled <p>For example, if you want to disable the certificate-based security, simply pass “0” to the tool.</p>
Password	<p>Specifies the word or phrase that you use to protect your certificate. The Password argument is mandatory, whereas Number of Days is optional. An example Passphrase is: P@55w0rd.</p>
The Number of Days	<p>Optional. Specifies the Number of Days for the root certificate to be valid. After the specified days, the certificate validity expires.</p> <p>If you do not pass any value for Number of Days, the setting defaults to 365 days. For example, if the Number of Days is 3650, the certificate is valid for 10 years from the generated date.</p>



Note:

If you fail to pass any values to this command-line, the command will fail to create the root certificate.


The following is an example of the command-line. In this example, MTLS is enabled, the passphrase is P@55w0rd, and the certificate will be valid for 3650 days (10 years):

```
C:\Program Files\Proficy\Proficy Historian\MTLS CreateRootCertificate.exe 1 P@55w0rd 3650
```

4. After executing `CreateRootCertificate.exe`, locate the root keys generated in the same MTLS folder:

- **ica_key.pfx** – Password protected certificate that contains the private key to sign the core services certificates.
- **ica_key.cer** – Root certificate contains the public and different attributes of the certificate.

The following figure shows examples of the root certificates.



After generating the root certificate, this certificate needs to be added to the “Trusted Root Certification Authorities” certificate store on the Local Machine.

Installing Certificates for Core Services

For generating certificates for core service, run the `MTLSCertificatesInstall.exe` utility from the command prompt with Administrator privileges.

1. Launch from the command prompt with Administrator privileges. For example:

```
C:\Program Files\Proficy\Proficy Historian\MTLS\MTLSCertificatesInstall.exe P@55w0rd 3650
```

The `MTLSCertificatesInstall.exe` utility takes the following arguments:

Argument	Description
Password	Specifies the word or phrase that you use to protect your certificate. The Password argument is mandatory, whereas Number of Days is optional. An example Passphrase is: P@55w0rd.


Argument	Description
	<div data-bbox="873 279 922 327" style="float: left; margin-right: 5px;"></div> <p>Note: The same Password used for creating the root certificate needs to be used here. This is so that the Password will be same while passing the argument between executables. The MTLSCertificateInstall.exe utility uses this password to open the root certificate private key (ica_key.pfx) and sign the core services certificates.</p>

For each service, two certificates will be generated as shown in the following figure:

Program Files > Proficy > Proficy Historian > MTLs

Name	Date modified	Type	Size
CreateRootCertificate.exe	12/15/2022 5:48 PM	Application	168 KB
MTLSCertificatesInstall.exe	12/15/2022 1:38 PM	Application	212 KB
openssl.exe	3/15/2022 9:20 PM	Application	700 KB
legacy.dll	3/15/2022 9:20 PM	Application exten...	152 KB
libcrypto-3-x64.dll	3/15/2022 9:20 PM	Application exten...	5,008 KB
libssl-3-x64.dll	3/15/2022 9:20 PM	Application exten...	754 KB
openssl.cnf	3/15/2022 9:20 PM	CNF File	13 KB
ClientManager.pfx	12/15/2022 6:54 PM	Personal Informati...	3 KB
ConfigManager.pfx	12/15/2022 6:54 PM	Personal Informati...	3 KB
DataArchiver.pfx	12/15/2022 6:54 PM	Personal Informati...	3 KB
DiagnosticManager.pfx	12/15/2022 6:54 PM	Personal Informati...	3 KB
ica_key.pfx	12/15/2022 5:50 PM	Personal Informati...	3 KB
ClientManager.cer	12/15/2022 6:54 PM	Security Certificate	2 KB
ConfigManager.cer	12/15/2022 6:54 PM	Security Certificate	2 KB
DataArchiver.cer	12/15/2022 6:54 PM	Security Certificate	2 KB
DiagnosticManager.cer	12/15/2022 6:54 PM	Security Certificate	2 KB
ica_key.cer	12/15/2022 5:50 PM	Security Certificate	2 KB

2. Double-click each service .cer file as shown in the following figure, and check whether each generated certificate has a valid root certificate chain.



3. After all required certificates are generated, restart the core Historian services. Without valid certificates, core services cannot establish connections to each other.

Upgrade Scenarios when Working with Historian Server Certificates

Be aware of the following when upgrading your Historian:


- By default, certificate-based security is enabled. Your configuration for certificates is automatic, unless you are installing or upgrading a distributed/mirror node. If you do not configure your certificates in this scenario, your Historian services may not start when you run it for the first time.
- You will need to regenerate the certificates if you uninstall the existing version and reinstall any version that supports certificate-based security.
- You will need to regenerate the certificates for Historian in-place upgrades that support certificate-based security.
- You will NOT need to regenerate the certificates for SIM over SIM upgrades that support the MTLS feature.

Troubleshooting Historian Server Certificates

Be aware of the following when working with certificates in Historian:

- When you install Historian, you are presented with three install types: **Historian Single Server**, **Historian Mirror Primary Server**, and **Historian Distributed/Mirror Node**. The MTLS protocol and certificate-based security is enabled by default for all install types. If you are installing a **Historian Single Server** or the **Historian Mirror Primary Server**, the security settings will be automatically configured by the installer. However, if you are installing a **Historian Distributed/Mirror Node**, you must configure the security settings manually after installation, for more information, refer to Overview of certificate-based security.
- You will need to follow the same procedure for installing certificates when certificates expire in the future.
- Prior to adding any new root certificate to the Trusted Root Certification Authorities folder, it is a better practice to remove an existing root certificate from the store first.
- After the root certificates are added to the Trusted Root Certification Authorities folder, all core services need to be restarted.
- If the MTLS authentication fails due to a mismatch in certificates, improperly generated certificates, expired certificates, or any issue related certificates, it will not cause the core Historian Services to stop. These services will be in running state, but the trusted connections among these services will fail. In this scenario, sometimes client tools will not be able to connect to the services. Sometimes client tools connect to Client Manager but cannot do any operations on Historian server. They simply show the "Not Connected" error.
- After trusted connections among core Historian services succeed, they will be in the same trusted state until these services are stopped or restarted.
- It is strongly recommended to provide same expiration date (in the Number of days field) for the root and all other core services certificates.
- If you forget to install the certificates, some of your core Historian services may not start after you complete your Historian install or upgrade.
- If you do not provide the same root certificate password while creating other services certificates, the MTLSCertificatesInstaller.exe tool returns a "Wrong Password" error.

- To see any specific errors that may be caused by certificate-based security, you need to enable full debugging by adding the “FF” hexadecimal value to the DEBUGMODE registry as shown in the following figure.



Using Proficy Authentication or LDAP Groups

About Proficy Authentication

In Historian, user authentication is handled using Proficy Authentication, which provides user account and authentication (UAA) service. Proficy Authentication provides identity-based security for applications and APIs. It supports open standards for authentication and authorization, including Oauth2.

When a user is created, modified, or deleted in Historian, the associated user account is being created, modified, or deleted in the Proficy Authentication instance, respectively.



Note:

This is done in the back-end automatically. Therefore, most users will not require knowledge on UAA to perform basic user management, except when additional configuration is required.

To use Proficy Authentication, you can choose between the following options while installing Web-based Clients:

- **Use a local Proficy Authentication service:** Use this option if you want to create a local Proficy Authentication instance. This is the default option. You can create this while installing Web-based Clients.
- **Using an existing Proficy Authentication service:** Use this option if you are currently using a Proficy Authentication service on a remote machine. You can install this service using Historian Web-based Clients, or you can use any other UAA service (such as Proficy Authentication installed using Operations Hub). You can then manage these users in Web-based Clients. The users in the remote Proficy Authentication service can then use Web-based Clients.

You can use Proficy Authentication plugin in Configuration Hub to manage groups, manage users, and map LDAP groups, and SAML groups with the Proficy Authentication groups.

For more information, refer to Proficy Authentication in Configuration Hub at <https://www.ge.com/digital/documentation/confighub/>.

- **Manage Identity Providers**

- [Add LDAP identity provider](#)
- [Modify LDAP identity provider](#)
- [Enable SAML](#)
- [Add SAML identity provider](#)
- [Modify SAML identity provider](#)
- [Delete Identity Provider](#)

- **Manage Groups**

- [Overview of Historian groups in Proficy Authentication.](#)
- [Create groups](#)
- [Map groups](#)
- [Modify groups](#)
- [Add or remove users in a group](#)
- [Add or remove sub-groups in a group](#)
- [Delete group](#)

- **Manage Users**

- [Create users](#)
- [Add LDAP or LDAPS users](#)
- [Add or remove groups for a user](#)

- [Reset user password](#)
- [Delete user](#)

About Proficy Authentication Groups

A Proficy Authentication group is created for a specific type of users who will likely perform the same type of activities.

If you have groups in a remote Proficy Authentication service, you can use them with Historian using the Proficy Authentication LDAP Integration tool. This section describes how to map the groups in the remote Proficy Authentication service with Historian counterparts. By default, Historian contains the following Proficy Authentication groups:

- **historian_visualization.admin:** Provides access to Trend Client and the Web Admin console.
- **historian_visualization.user:** Allows access to Trend Client.
- **historian_rest_api.read:** Provides read access to public REST API.
- **historian_rest_api.write:** Provides write access to public REST API.
- **historian_rest_api.admin:** Provides read/write access to public REST API.
- **historian_enterprise.admin:** Provides read/write access to Configuration Hub APIs.
- **historian_enterprise.user:** Provides access to view Configuration Hub APIs.
- **ih_archive_admins:** Provides the ability to create, modify, and remove archives.
- **ih_audited_writers:** Allows data writes and to produce a message each time a data value is added or changed.
- **ih_collector_admins:** Allows the ability to add collector instances and change their destination.
- **ih_readers:** Provides access to the ability to read data and system statistics. Also allowed access to Historian Administrator.
- **ih_security_admins:** Provides access to Historian power security users. Security administrators have rights to all Historian functions.
- **ih_tag_admins:** Provides access to allow the ability to create, modify, and remove tags. Tag-level security can override rights given to other Historian security groups. Tag admins can also browse collectors.
- **ih_unaudited_logins:** Allow connections to the Data Archiver without creating login successful audit messages.
- **ih_unaudited_writers:** Provides the ability to write data without creating any messages. Tag, archive, and collector changes log messages regardless of whether the user is a member of the `ih_audited_writers` group.

**Note:**

Instead of mapping the groups, you can choose to map individual users with Historian users. For instructions, refer to [Managing Proficy Authentication Users Using the Configuration Tool \(on page 284\)](#).

Workflow


1. Provide the details of the remote Proficy Authentication service while [installing Web-based Clients \(on page 154\)](#).
2. [Connect to the remote Proficy Authentication service \(on page 182\)](#).
3. [Map the Proficy Authentication groups](#) with that of the Historian Proficy Authentication instance. You can map the groups in [LDAP and LDAPS \(LDAP via SSL\)](#).

Configurations Checklist to use Proficy Authentication Security Groups

In Configuration Hub, the **Global Security** section in the system **DETAILS** section enables you to specify the authorization for Historian security groups. To use Proficy Authentication security groups, you must perform the configurations listed in this topic.

This topic intends to be a checklist for you to perform the configurations that are needed to use Proficy Authentication security groups for authorization.

1. Access Configuration Hub using `ch_admin` as the username.



2. In the **NAVIGATION** pane, expand **Proficy Authentication**, and then select **Security**.
3. Add the same Windows Login user (For example, if you logged in as Administrator, use Administrator), and then map the user with all admin groups. For more information on adding users and mapping the users to groups, refer to [Create groups, Add or remove users in a group and Map groups](#). For more information on Historian security groups, refer to [Overview of Historian groups in Proficy Authentication](#).
4. In the **Users** tab, from the list of users, select the predefined user, that is `<hostname>.admin`, and then map it to `ih_security_admins`. For more information, refer to [Map groups](#).

5. Add the users defined in Proficy Authentication using the same password to **Local users & Group**. This will enable you to access thick clients (VB admin, iHSQL). For more information on how to add a user to **Local users & Group**, refer to Adding Users to Windows Security Group.

Alternatively, you can add the users by adding registry entries.

- a. In the `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\Servers` and `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Servers` registry paths, add the following registries.

Name	Type	Data
UAA	REG_SZ	https://hostname.domain:433/uaa/oauth/token For example, https://testmachine.ge.com:443/uaa/oauth/token.
UseUaaAuthentication	REG_DWORD	0x00000001.

- b. Save the registries.
6. Now, you can [Access Configuration Hub \(on page 336\)](#) using the predefined username, that is, <hostname>.admin and password.
7. In the **NAVIGATION** pane, in the Configuration Hub plugin for Historian, access **Systems**, and then select the system as needed.

The system appears in the main section. The system details appear in the **DETAILS** section.

8. In the **GLOBAL SECURITY** section, select **Use Proficy Authentication**.
9. On the top-right corner, select **Save**.
10. Restart all the services, including the Remote Collector Management (RCM) service.

Now you can use the Proficy Authentication security groups for authorization.

To know if your configurations were saved, check the following:

- The CollectorManager.shw status must be **Connected**.
- The DataArchiver.shw security settings must be as shown below.

```

Security Settings
=====
Security Group Source : Proficy Authentication
Security Provider : OAuth2
URI : https://hostname:domain:443/uaa/checktoken
UAA : https://hostname:domain:443/uaa/oauth/token
Use Client Windows User for Logon : TRUE
Use ADSI calls : FALSE
Strict Client Authentication : TRUE
Strict Collector Authentication : TRUE
Allow Anonymous WCF Clients : FALSE
Anonymous User Name : Guest

```

Using Server Certificates

To use server certificates with Historian, use the Certificate Management tool. This tool supports the following combination of files to import the certificate chain and the private key:

- A PEM file that contains the certificate chain and the private key.
- A PEM file that contains the certificate chain, and another PEM file for the private key.
- A PFX file that has the certificate chain and the private key.

For instructions on using the Certificate Management tool, refer to https://www.ge.com/digital/documentation/opshub/windows/windows/c_about_certificate_management.html.

Change the Log Levels of Proficy Authentication

1. Access the `log4j.properties` file in the following folder: `C:\Program Files\GE\Operations Hub\uaa-tomcat\webapps\uaa\WEB-INF\classes`
2. For each module, select one of the following log levels depending on your requirement:
 - TRACE
 - DEBUG
 - INFO
 - WARN
 - ERROR
 - FATAL
 - OFF
3. If you want to disable Tomcat logging:

- a. Stop the Proficy Authentication Tomcat Web Server service.
 - b. In the `C:\Program Files\GE\Operations Hub\uaa-tomcat\bin` folder, rename the `tomcat8w.exe` file `UaaTomcat.exe`, and run this application as an administrator.
 - c. Select **Logging**.
 - d. Remove the auto keyword from the Redirect Stdout and Redirect Stderr labels.
 - e. Start the Proficy Authentication Tomcat Web Server service.
4. If you want to change the Tomcat log level:
- a. Stop the Proficy Authentication Tomcat Web Server service.
 - b. Access the `context.xml` file located in the `C:\Program Files\GE\Operations Hub\uaa-tomcat\conf`.
 - c. In the Context tag, add: `swallowOutput="true"`
 - d. Access the `logging.properties` file in the same folder, and set the **2localhost.org.apache.juli.AsyncFileHandler.level** to one of the following values, which are in the order of less verbose to more verbose:
 - SEVERE
 - WARNING
 - INFO
 - CONFIG
 - FINE
 - FINER
 - FINEST
 - ALL
 - e. Start the Proficy Authentication Tomcat Web Server service.

Migrating Historian Data

Migrating the Alarms and Events Data

If you have upgraded Historian, you must migrate the alarms and events data as well. Only then you can retrieve the data.

The steps to migrate depend on the Microsoft SQL version in which the alarms and events data is stored:

- If using Microsoft SQL 2008 or later, you can install Historian and its components, install a supported version of Microsoft SQL, and then migrate the data.
- If using a version earlier than Microsoft SQL 2008, you must first migrate the data to Microsoft SQL 2008, and then migrate it to a supported version of Microsoft SQL.

To migrate data, you can choose one of the following options:

- **Before upgrading to the latest version of Historian:** In this case, you can use Historian Administrator of the older version of Historian to migrate the data.
- **After upgrading to the latest version of Historian:** In this case, you can use the Proficy Alarm Database Migration tool, which is provided with Historian.

This section describes how to migrate data using the migration tool.

Workflow for Migrating Alarms and Events Data

If the alarms and events data is currently in Microsoft SQL 2008 or later:

1. Install the following components on the target machine in the given sequence:
 - a. [Historian \(on page 104\)](#)
 - b. [Alarms and Events \(on page 140\)](#)
 - c. [Collectors \(on page 142\)](#)
 - d. [Client Tools \(on page 150\)](#)
 - e. [Standalone Help \(on page 205\)](#)
2. [Back up the alarms and events data \(on page 237\)](#).
3. Install Microsoft SQL on the target machine. Refer to [Software Requirements \(on page 92\)](#) for a list of supported versions.
4. Restore the data that you have backed up to Microsoft SQL.
5. As needed, perform calculations on the migrated data. Ideally, you must create an archive already to store the calculated data. For unsolicited calculation tags, migration of data will cause the calculation to be triggered automatically for the time associated with the migrated data points. Archives will potentially grow beyond the configured default size. To avoid this issue, adjust the value for the `DataIsReadOnlyAfter` field on the **Security** section of the **Data Store Maintenance** page of Historian Administrator (or the `ActiveHours` property) so that the value is large enough to contain the calculated data. By default, this value is 1 month.

If the alarms and events data is currently in a version earlier than Microsoft SQL 2008:

1. Using Microsoft SQL Server Management Studio, back up the alarms and events data. If the database is large, consider taking a partial backup instead of a full backup.
2. Install Microsoft SQL Server 2008 on the target machine.
3. Restore the data that you have backed up in step 1.
4. In Microsoft SQL Server Management Studio, under **Databases**, right-click the database that you have restored, and then select **Properties > Options**.
5. In the **Compatibility level** field, select **SQL Server 2008**.
6. Install the following components on the target machine in the given sequence:
 - a. [Historian \(on page 104\)](#)
 - b. [Alarms and Events \(on page 140\)](#)
 - c. [Collectors \(on page 142\)](#)
 - d. [Client Tools \(on page 150\)](#)
 - e. [Standalone Help \(on page 205\)](#)
7. [Back up the alarms and events data \(on page 237\)](#) that you have restored in step 3.
8. Install a supported version of Microsoft SQL on the target machine. Refer to [Software Requirements \(on page 92\)](#) for a list of supported versions.
9. Restore the data that you have backed up in step 7 to Microsoft SQL.
10. As needed, perform calculations on the migrated data. Ideally, you must create an archive already to store the calculated data. For unsolicited calculation tags, migration of data will cause the calculation to be triggered automatically for the time associated with the migrated data points. Archives will potentially grow beyond the configured default size. To avoid this issue, adjust the value for the `DataIsReadOnlyAfter` field on the **Security** section of the **Data Store Maintenance** page of Historian Administrator (or the `ActiveHours` property) so that the value is large enough to contain the calculated data. By default, this value is 1 month.

Back Up the Alarms and Events Data

Install the following components in the given sequence:

1. [Historian \(on page 104\)](#)
2. [Alarms and Events \(on page 140\)](#)
3. [Collectors \(on page 142\)](#)
4. [Client Tools \(on page 150\)](#)
5. [Standalone Help \(on page 205\)](#)

If, however, the alarms and events data is currently in a version earlier than Microsoft SQL 2008, you must first migrate the data to Microsoft SQL 2008, and change the compatibility level to **SQL Server 2008**.

1. Go to the `<Historian installation folder>\Proficy DataBase` folder, and open the `Proficy.Historian.AandE.Migration.exe` file.
The **Backup Existing Alarms and Events** window appears.
2. In the **Time Range** section, in the **From** and **To** fields, select the start time and end time of the backup duration.
We recommend that you select small duration if you have many alarms. If you want to migrate the alarms in blocks of time, choose the oldest alarms first.
3. In the **Database Name** field, enter the name of the database that you want to back up. Typically, this will be the same as the Microsoft SQL server you are using.
4. Depending on whether you want to use Windows credentials or Microsoft SQL credentials, select either **Use Windows Authentication** or **Use SQL Authentication**, respectively.
5. In the **User Id** and **Password** fields, enter the login credentials. Provide the username of a user who has the permission to connect and back up alarms.
6. In **Backup Folder Path** field, provide the absolute path, including the file name, to store the backed up alarms (for example, `c:\temp\March2010.bak`). You can enter the path of a local file or a remote one, depending on whether the Microsoft SQL server is installed on the local machine or a remote machine.
7. Select **Test Connection** to check if the source database is active and the information is accurate.
The **Begin Backup** button is activated.
8. Select **Begin Backup**.
The alarms and evens data is backed up. The count of the rows that are backed up appears.

Install a supported version of Microsoft SQL, and [restore the data \(on page 238\)](#) that you have backed up. Refer to [Software Requirements \(on page 92\)](#) for a list of supported versions.

Restore the Alarms and Events Data

Install Microsoft SQL. Refer to [Software Requirements \(on page 92\)](#) for a list of supported versions.

1. Go to the `<Historian installation folder>\Proficy DataBase` folder, and open the `Proficy.Historian.AandE.Migration.exe` file.
The **Backup Existing Alarms and Events** window appears.
2. Select **Migrate Alarms and Events Backup**.
3. In the **Backup Folder Path** field, provide the absolute path of the file (including the file name) in which you want to restore the data (for example, `c:\temp\March2010.bak`). You can enter the path of a local file or a remote one, depending on whether the Microsoft SQL server is installed on the local machine or a remote machine.
4. In the **Database Name** field, enter the name of the database that you want to back up. Typically, this value is the same as the Microsoft SQL server you are using.

5. Depending on whether you want to use Windows credentials or Microsoft SQL credentials, select either **Use Windows Authentication** or **Use SQL Authentication**, respectively.
6. In the **User Id** and **Password** fields, enter the login credentials. Provide the username of a user who has the permission to connect and back up alarms.
7. Select **Test Connection** to check if the source database is active and the information is accurate. The **Begin Migrator** button is activated.
8. Select **Begin Migrator**.
The alarms and events data is restored. The count of the rows that are restored appears.

Using the Migration Tool

The IHA Migration Tool (`MigrateIHA.exe` for 32 bit or `MigrateIHA_x64.exe` for 64 bit) allows you to migrate data up to 30 years old if the data is already stored in `IHA` files from any version of Historian. Use the Migration Tool to move data from one archiver to another when you cannot simply restore the `IHA` in Historian Administrator.

The Migration Tool opens an `IHA` file as a binary data file and reads the raw samples from it. Those raw samples are then written to a destination archiver, in a similar way to how an OPC collector or File collector would write data. Any errors returned from the data archiver are reported in the main window and repeated in the log file.



Note:

- You can migrate UserDefined types, MultiField tags, and Array tags.
- When you are migrating the data stores, the source data store is created in the destination.
- Using this Migration Tool, you can upgrade from two previous versions of Historian to the latest version.
- The performance of this tool is impacted with the addition of Client Manager and Configuration Manager. For best performance, use this on a Single Server install only.

Migrating Historical Data

You need to run this tool as an administrator to migrate and create the log files in the `C:\` directory.

To migrate historical data stored in `IHA` files from any version of Historian:

1. In the `Historian` folder, double-click the Migration Tool executable (`MigrateIHA.exe` for 32-bit or `MigrateIHA_x64.exe` for 64-bit) to open the IHA Migration Utility.

The icon for the executable looks as follows: 

2. Select **Configure Options** from the **Options** menu.
3. Enter or modify any specific configuration information.

When choosing an `IHC` file, do not specify one currently in use by the Data Archiver. (For more information, see [Configuring Migration Options \(on page 240\)](#).)

4. Select **File > Migrate Historical Data**.

The **Select Historical Data File(s)** window appears.

5. Select a historical file and select **Open**.

Refer to the **IHA Migration Utility** main page for information on the progress of the migration and any encountered errors.



Note:

The IHA Migration Utility page only displays the most recent lines of the log file. For the full set of logged messages, refer to the log file, typically located in `C:\IHAMigration.Log`.

6. Optionally, perform these steps:

- a. You can upgrade the older version's archive files to the latest version by selecting the bulk upgrade option.

Stop the Data Archiver service and select **File > Bulk Upgrade Historical Data**.

If you do a bulk upgrade of historical data immediately after you install the latest version on Historian, then save on upgrading while the system reboots.

- b. To clear the log messages displayed in the page, select **File > Clear Display**.

- c. To view the logs saved in the `IHAMigration.log` file, select **File > View Log File > ..**

Configuring Migration Options

1. In the Migration tool (`MigrateIHA.exe` for 32 bit or `MigrateIHA_x64.exe` for 64-bit), select **Options > Configure Options**.

The **Migration Options** window appears showing the default server information and the default migration options.

2. Enter options the following options.

Related reference

[Server Pane \(on page 241\)](#)

[Options Pane \(on page 242\)](#)

[Tags to Migrate Pane \(on page 242\)](#)

[Time to Migrate Pane \(on page 242\)](#)

Server Pane

Field	Description
Server	The default server (set during installation). If you do not want to write data to the default server, enter the desired server in this field.
Username and Password	If you have created and established Security Groups in your Historian Security Environment, you may need to enter the user name and password here. By default, if you do not supply any information, the current logged in user will be used in security checking.

Options Pane

It is always advisable to take a copy of the configuration file and work on the copy rather than working on the original file.

Tags to Migrate Pane

Option	Description
Migrate All Tags	Select this option to migrate all the tags from the selected archiver.
Migrate only tags that exist in destination	Select this option to migrate all the tags that exists in the source destination.
Migrate using tag mask	Select this option to migrate tags with the mask specified. You can specify an exact tag name to migrate that tag only.
Migrate only tags that exist in source config file	To migrate the tags that are present only with the source config file.

Time to Migrate Pane

Option	Description
Use IHA TimeFrame	Select this option to migrate all the tags which has the IHA time frame.
Use Below TimeFrame	Select this option to migrate all the tags in the specified time frame. You need to specify the Start Date/Time and End Date/Time if you select this option.

Data Migration Scenarios

You can migrate tags and their data on the same Historian Server or between servers. When migrating your data, consider the following guidelines:

- Get new collection working first

When the data is collected from the collectors or the API programs, then you should consider adding the tag definitions into the destination server and directing data to be written there before you start migration, because migration may take several hours or days.

- Migrate data from oldest to newest

It is advisable to migrate the oldest data first and then the newest, to make the optimal use of archive space.

- Pay attention to TagID

Every tag in Historian 4.5 and above has a property called TagID, that uniquely identifies it and allows data retrieval to locate the data. Even if you have a tag of with the same name in another archiver, that tag has a different TagID and is considered as a different tag. You can see the TagID of a tag in the Excel Tag Export. Preserve that number when moving a tag from one system to another.

The following are commonly used scenarios while migrating data on the same Historian server or between servers.

- Migrating a Tag and its data from one data store into another data store.
- Merging a Historian Server into an existing data store on another machine. .

Migrating a Tag and its Data

If you want to separate a single large user data store of tag into multiple smaller data stores on the same machine, and if your software license allows it, then you should assign the tag to the new data store and then migrate the data.

Consider when data is collected for the year 2009 in `Tag1`. The collected data is archived in the default User data store. If you want to move `Tag1` residing in the `User` data store to another data store, (for example, the `Motor` data store), then you must create the `Motor` data store if it does not already exist and if your license allows it.

The next step is to change the data store of the tag. You can change the data store of the tag either using Historian Administrator or using Excel Tag Import. The new incoming data gets collected in the Motor data store. If you do a raw data query, you will get only the latest data and the previous data will not be available. To get the old data, you must migrate the data residing in the `User` data store to the `Motor` data store.

To migrate a tag and its data from one data store to another data store on the same server:

1. Use `iharchivebackup -c` to make a backup of the `.ihc` file.
The backup of the Config file is automatically created in the `Archives` folder.
2. In Historian Administrator, back up each archive from oldest to newest.

3. Launch the Migration Tool (`MigrateIHA.exe` for 32-bit or `MigrateIHA_x64.exe` for 64-bit) using Administrator privileges.
4. Select **Options > Configure Options**.
5. In the **Server** pane, enter the **Server name**.
6. In the **Options** pane, enter the **IHC File** path in the **Config File** path field, using the browse button. This is the path to the IHC backup that you made in step 1.
7. In the **Tags to Migrate** pane, select the **Migrate Using Tag Mask** option and enter the **Tag Name** you moved to the new data store.
8. In the **Time to Migrate** pane, ensure the **Use IHA TimeFrame** option is selected.
9. Select **File > Migrate Historical Data**.
10. Select the archive file that you backed up in Step 2 and monitor the progress of the migration. When the migration is complete, query the data to see the migrated data can be queried. Repeat with the remaining archives from oldest to newest.

As needed, perform calculations on the migrated data. Ideally, you must create an archive already to store the calculated data. For unsolicited calculation tags, migration of data will cause the calculation to be triggered automatically for the time associated with the migrated data points. Archives will potentially grow beyond the configured default size. To avoid this issue, adjust the value for the `DataIsReadOnlyAfter` field on the **Security** section of the **Data Store Maintenance** page of Historian Administrator (or the `ActiveHours` property) so that the value is large enough to contain the calculated data. By default, this value is 1 month.

Merging a Historian Server

A typical scenario is to merge a Historian Server into an existing data store on another machine.

If your system architecture has evolved from multiple smaller servers into fewer large archives, you can eliminate the smaller machines while preserving all your tag configuration and collected data.

Consider the following example. You have two machines, Machine A and Machine B. Machine A is running current or any earlier version of Historian and has 100 tags and 10 archive files. The data of these tags are collected from the collector and is being queried by users. Machine B is running the current version of Historian.

**Note:**

- This example does not include Alarm migration. If Machine A was being used to store alarms, then you need to migrate those before eliminating Machine A.
- You cannot migrate tags with Enumerated Data Sets. If you want to migrate data for Enumerated Data Sets, then you must create the Enumerated Data Sets in Historian Administrator or Microsoft Excel and then migrate the tags.
- To migrate tags which are condition based triggers, then you must create the condition-based triggers for that tag in Historian Administrator or Microsoft Excel and then migrate the tags.

You can migrate data only if the file format of the archive files format is `.IHA`. If the back-up archive is in `.zip` format, extract the `zip` files and copy all the `.IHA` files separately in a folder.

1. Before migrating, copy the `.IHC` and all the `.IHA` files from Machine A to Machine B.
2. Launch the Migration Tool (`MigrateIHA.exe` for 32-bit or `MigrateIHA_x64.exe` for 64-bit) with Administrator privileges.
3. Select **Options > Configure Options**.
4. In the **Server** pane, enter the **Server name**.
5. In the **Tags to Migrate** pane, ensure that the **Migrate All Tags** option is selected
6. In the **Options** pane, enter the **IHC File** path in the **Config File** path field, using the browse button. The path you enter is the path to the `.IHC` file brought over from Machine A.
7. In the **Time to Migrate** pane, ensure the **Use IHA TimeFrame** option is selected.
8. Ensure **Throttle Output** is selected.
9. To migrate the data, select **File > Migrate Historical Data** and select the archive file that has the oldest data.

The tags and data are migrated to the default data store in time slices. The **MigrateIHA** window displays the progress and any Tag Add or Data Add errors are displayed in the log file. You can estimate the remaining time by watching the progress.
10. Repeat the previous steps for each of the remaining archives, from oldest to newest data.
11. Add the collector to the Historian Server on Machine B.

See the *Adding a Data Collector to an Historian Server* topic in *Data Collectors - General*.

Migration Tool Command-Line Syntax

Command Syntax

- For 32-bit:

```
MigrateIHA.exe "<IHA file name with full path>" "<IHC filename with full path>"
```

- For 64-bit:

```
MigrateIHA_x64.exe "<IHA file name with full path>" "<IHC filename with full path>"
```

Command-line Options

Option	Description
<code>/NOTHROTTL</code>	This does not throttle any part of the migration process, but may impact resources on the server. Optionally, you can remove this switch as required. By default, throttling is rated at 5000 events per second.
<code>/NOMESSAGES</code>	This does not migrate messages into the newly created archive. Using this switch may or may not reduce the size of your archives, depending on the number of messages stored in the archive. By default, messages are migrated if this switch is not used.
<code>/EXISTINGTAGS</code>	This will migrate data for only those tags that exist in the destination archiver.
<code>/b</code>	This option of the <code>start.exe</code> file allows the IHA Migration tool to start without opening a new window for each instance. If you are migrating a pre 4.5 IHA file you will need to have the IHC file for that IHA and specify the IHC file in the Options window or on the command line. Otherwise, you will get a warning message.
<code>/wait</code>	This option of the <code>start.exe</code> file allows each instance of the IHA Migration tool to complete the migration before starting the next migration in the sequence.
<code>/NOIHC</code>	This option skips verifying for IHC file and proceed with the migration. IHC file is not required, if batch command have <code>/NOIHC</code> option.

Notes

- If you are migrating from a command line, provide IHC file, else, use /NOIHC option to omit the IHC file.
- If you do not have the IHC or you are not sure you have the correct IHC then you should use the pre-4.5 version of MigrateIHA to migrate the IHA. Otherwise, the data will not migrate correctly.
- You should keep a copy of the original IHA file.
- The IHC must contain all the tags that are in the IHA file, so use the most current IHC you have.
- You must use double quotes when you enter the IHA and IHC file even if you do not have spaces in your file path or file name.
- Migrating an IHA will upgrade it to 4.5 format.
- If you are migrating a 4.5 IHA you should provide the IHC file in the Options window but if you do not have the IHC you can safely continue past the warning message.

Creating a Batch File to Migrate Multiple IHA Files

The IHA Migration utility migrates only one archive at a time by design. However, if you need to add more than one archive at a time, you can create a batch file to automate multiple archive merges.

When creating a batch file you need to provide the batch file with a logical name and save the batch (.bat) file in a location that can be easily accessed using the command prompt.



Note:

When migrating any archive, you should start with the archive with the oldest data first, followed by newer data, in sequence, to minimize the amount of disk space used in the Data Archiver.

For example:

```
cd c:\Program Files\Historian
start /b /wait migrateiha /NOTHROTTLE /NOMESSAGES
"c:\Historian Data\Backups\server_Archive001.iha"
"c:\Historian Data\Backups\server_Config.ihc".
```

Interoperability of Historian Versions

Interoperability guidelines for Historian versions include:

- Historian Collectors below v6.0 can write to Historian v7.0 Archivers; however, since the earlier collector versions cannot automatically connect to a mirror, users need to point those collectors to the mirror system.
- Historian Clients below v6.0 can retrieve data from Historian v7.0 Archivers.
- Historian v7.0 or later Clients can retrieve data from a single Historian Data Archiver below v6.0.
- Historian v7.0 or later Collectors can write to a single Historian Data Archiver below v6.0.
- An SDK program built on an Historian v7.0 or later node does not run on an Historian below v6.0.
- An SDK program that you created in Historian below v7.0 must be rebuilt on a computer with Historian v7.0 or later if you want to run it on that version.
- It is recommended that you use consistent versions of client and server applications. If you do use different client and server versions of the Historian, regularly back up all archives and tag configurations.



Note:

To determine the version of the server, client, and SDK, select the **About** link in Historian Administrator. The version of the Historian installer can be seen in the **Control Panel / Uninstall programs**; this version is different from the Historian core version seen in Historian Administrator **About** link.

Migrate User Authentication Data from Historian to Common Proficy Authentication Service

Starting Historian 8.0 version, you can use the common Proficy Authentication service.



Note:

You can either choose the common Proficy Authentication deployed by any other products such as, Operations Hub, Plant Apps; or the common Proficy Authentication deployed by Historian.

To use the common Proficy Authentication service, you must migrate the Proficy Authentication data should from Historian to the new local or external Proficy Authentication.

To enable this migration of data the `uaa_config_tool` is introduced.

**Note:**

- While migrating Proficy Authentication details, we are setting default password as user123 for all the users. You should change it using Proficy Authentication config tool once migration is done.
- While setting up new password, it may ask you to enter the port number. By default, the port number is 443. If you have provided a different value in the Public https port field in the TCP port assignments page while installing Web-based Clients, you must provide that value.
- Using this tool, you can back up the Proficy Authentication data only for Historian 7.2 or earlier. And, you can migrate the data to Historian 8.0 or later.

**Important:**

Back up the data before upgrading to the latest version of Web-based Clients.

It includes the following tasks:

1. Back up Historian Proficy Authentication data.
 2. Migrate the data to an existing common Proficy Authentication service.
1. Open Command Prompt.
 2. Mount the ISO and navigate to the Utilities folder where the `uaa_config_tool.exe` file is located. After installation, `uaa_config_tool` is available in the following folder as well: `<installation drive of Historian>\Program Files\GE Digital\Historian Config`

**Important:**

You should back up the data before upgrading to 8.0 (Web-based Clients)

3. Enter the following command to take a back up of the data:

```
C:\ uaa_config_tool.exe backup_data -d "<destination folder>"
```

`<destination folder>` is the location where you want to save the back up files. Note that you must enter the value in quotes.

**Note:**

You may be prompted to enter the password twice for Historian Database and Proficy Authentication. Enter the password as GEIP123User

Back up is generated and the data is saved in the destination folder.

4. Copy the backup files to the machine where Web-based Clients are installed.
5. Enter the following command to migrate the data:

```
uaa_config_tool.exe migrate_data -h <host-addr> -m <portnum> -u <username> -s <secret> -l
"<location path of backup files>"
```

Example: `uaa_config_tool.exe migrate_data -h vmhistwin2016 -m 443 -u admin -s gowt43df -l "c:\myuaabackupfiles"`

**Note:**

While migrating Proficy Authentication details, it may ask for port number at migrating historian database. The default value is 8432. If, however, you have provided a different value in the **Historian database port** field in the **TCP port assignments** page while installing Web-based Clients, provide that value.

Value	Description
<host-addr>	Address of the host or destination where you want to migrate the data.
<portnum>	Port number of the destination.
<username>	Username
<secret>	Client Secret
<location path of backup files>	Source location where the data is backed up.

- The data is migrated to the destination that is, common Proficy Authentication service.
- The `umtlog` file is generated containing the details about backup and migration for users and groups.
- The `User_migration_report` is generated which contains the migration status of the user data.

**Note:**

Creation and migration of users and groups can fail if the user or group already exists in the destination.

If user migration fails, you can change the username in the backup file and repeat Step 5.

Implementing Historian Security

Implementing Historian Security

Historian is a high performance data archiving system designed to collect, store, and retrieve time-based information efficiently. By default, access to these Historian archives, tags, and data files is available to any valid operating system user account. In this default environment, all users are allowed to read, write, change, and delete archives, tags, or data files in Historian Administrator, SDK, migration tools, and Excel Add-In. However, you may want to make these features and data available only to authorized personnel. You can do this by creating and defining Historian security groups in your Windows Security.

Historian includes an Electronic Signature and Electronic Records security feature. This option provides installations related to the FDA's 21 CFR Part 11 regulation or any site interested in added security or tracking the ability to require a signature and password every time a change in data or configuration is requested. For more information on the Electronic Signature and Electronic Records feature, refer to [Historian in a Regulated Environment \(on page 824\)](#).

To ensure a secure environment when using Historian security, do not create any local user accounts unless Historian is set up on a standalone machine.

Whether or not you use Historian security, make sure that you disable Guest accounts on your computer to limit access to valid Windows user accounts.

To run Proficy Authentication commands, refer to [Managing Proficy Authentication Users Using the Configuration Tool \(on page 284\)](#).

About Protecting Your Process

If you want to restrict access to Historian archives, files, and tags, or protect your data files from unauthorized changes, you can enable Historian security. Using security is optional and is disabled by default. By enabling security, you can restrict access to:

- Modifying data using Excel Add-In
- Updating security for individual tags or groups of tags

- Creating, modifying, and removing tags
- Tag protection (adding, modifying, removing, and so on) can be applied at a global level to all tags or at the individual tag level.

Refer to *Implementing Tag Level Security* for more information.

- Reading data in the iFIX Chart object, Excel Add-In, and Migration Utilities
- Writing data
- Starting and stopping collectors
- Creating and deleting collectors
- Creating, modifying, and deleting archives

Historian uses the operating system security groups to create a security structure. You can enable security for a particular set of functions by adding specific Historian Security Groups to your groups. You can also add security groups to your domain controller.

By defining one or all of the groups, you begin to set up a security structure. Refer to the *Historian Security Groups* section for more information on the Historian Security Groups available.

Strict Authentication

With Historian's strict user account authentication features, `Enforce Strict Client Authentication` and `Enforce Strict Collector Authentication`, you can control access to the Historian server and safeguard user account credentials.

With strict authentication enabled, only known user accounts configured on the Data Archiver server computer will be able to access a Historian server. Similarly, enabling strict collector authentication enforces the same requirement for incoming collector connections.

For an account to be known at the Data Archiver, it has to exist on that archiver as a local account or exist on a Domain Controller available to the data archiver. Historian will access the local accounts or Domain Controller via Microsoft's Security Support Provider Interface (SSPI) and this involves having a Kerberos server setup optionally to assist in account validation.

By default, strict client and collector authentication is enabled on new installations to maximize security. When upgrading from a previous version of Historian, strict client and collector authentication is disabled to allow compatibility with older clients or collectors that cannot be upgraded concurrently.

It is recommended that all clients and collectors receive timely upgrade to the latest version, which permits enabling both strict client and collector authentication on the server for the highest security configuration.

By treating clients and collectors separately, it is possible to accommodate new and legacy authentication during the upgrade process. However, upgrading all clients and collectors to the latest version immediately will achieve a high level of security. The two options, Enforce Strict Client Authentication and Enforce Strict Collector Authentication, permit flexibility during the upgrade process by selectively accommodating legacy clients and collectors.

Local and Domain Security Groups:

You can choose local or domain security groups to access Historian. To do so, in **Historian Administrator > Data Stores > Security**, select **Use Local** or **Use Domain**. The following table provides recommended group to use based on the machine configuration and the security group of the logged-in user.

Machine Configuration	Security Group of the Logged-In User	Recommended Security Group
Workgroup	Local	Local
Domain	Local	Domain For domain machines, we recommend that you log in with a domain-level user and create security groups in the domain controller machine.
Domain	Domain	Domain

Strict Authentication Options:

This table provides guidelines about the different combinations of strict client and collector authentication options and their use:

Strict Client Authentication	Strict Collector Authentication	Comment
Enabled	Enabled	Use this for highest available security. You will need to install SIMs, if available on all pre-6.0 collectors and clients. Clients can refer to any program that connects to the Data Archiver. This includes Historian Administrator, Microsoft Excel, any OLE DB program, user written programs, or any other Proficity software.

Strict Client Authentication	Strict Collector Authentication	Comment
Enabled	Disabled	Use this if you are unable to upgrade collectors to the latest version if there is no SIM update for your collector.
Disabled	Enabled	Use this if you have to support legacy clients and you are unable to install the SIM update on all clients.
Disabled	Disabled	Use this for maximum compatibility with existing systems.

Trusted Connections in Distributed Historian Service Environment:

This trusted connection works only in the Domain environment and it is enabled by default.



Note:

If you are adding a mirror copy to an existing node, make sure that both the nodes are in the same domain.

If you want to work in the workgroup setup, contact Online technical support & GlobalCare:www.digitalsupport.ge.com.

Disabling Strict Client and Collector Authentication

To permit older versions of clients and collectors to access a Historian 7.0 (or later) server, disable strict client and collector authentication.

1. Open the page and select **DataStore Maintenance Security**.
2. In the **Global Security** section:
 - Select the **Disabled** option button for **Enforce Strict Client Authentication**.
 - Select the **Disabled** option button for **Enforce Strict Collector Authentication**.

Security Strategy Guidelines

When you begin to implement security, you should first define a clear strategy. Consider the following when beginning to set up your security strategy:

- If you disabled the Guest account, a user must provide a valid username and password even if no groups are created.
- Protection is only provided for the functional areas for which you have built the associated Historian Security Groups.

- If you only choose to define some of the security groups, all users still have all access to any uncreated groups. All users are still assumed to be a member of a group unless that group has been created, with the exception of iH Audited Writers group. You must add the iH Audited Writers group to the Windows security groups so that a user can become a member of this group.

For example, if you elect to define the iH Security Admins group and iH Archive Admins group, both the members associated with those defined groups and all other valid users still have access to such functions as creating and modifying tags until you create the iH Tag Admins security group.

- If you implement any Historian Security groups, you must first add and define the iH Security Admins group.

**Note:**

If you do not create and define the iH Security Admins group, all valid users are assumed to be members of this group. This membership overrides any other security group that you set.

See also [Historian Security Groups \(on page 256\)](#).

Setting Historian Login Security

Use Historian Login Security settings if you want to validate users at the Data Archiver, instead of at the client. By applying these settings, users and applications are forced to provide a user name and password at connect time so that the archiver can validate them. For example, users in the security group such as `ihSecurity Admins` will be checked by the Archiver.

For Historian Login Security settings, you can view and set the property from the HistorianSDKsample server properties. The current setting is shown in the data archiver `SHW` file.

Historian Login Security property is available only in Historian SDK.

To set login security using the Historian SDK:

1. Run the SDK sample.
2. Connect to a server.
3. Select the server in the list box.
The **Server Properties** window appears.
4. On the right side of the window, locate the **AllowClientValidation** setting. By default, this value is set to `TRUE`. Select to set to `FALSE`, and select **OK**.

Historian Security Groups

Historian provides the following security groups:

iH Security Admins

Historian power security users. Security Administrators have rights to all Historian functions. This group also has the ability to change tag level security, archive security, and modify the Electronic Records and Signatures option. This is the only Historian security group that overrides tag level security.

iH Collector Admins

Allowed to start and stop collectors, browse collectors, configure collectors, and add new collectors.

iH Tag Admins

Allowed to create, modify, and remove tags. Tag level security can override rights given to other Historian security groups. Tag Admins can also browse collectors.

iH Tag Admins are not responsible for setting Tag Level Security. This task can only be performed by an iH Security Admins. For more information on setting Tag Level Security, refer to the *Implementing Tag Level Security* section.

iH Archive Admins

Allowed to create, modify, remove, backup, and restore archives.

iH UnAudited Writers

Allowed to write data without creating any messages.

iH UnAudited Logins

Allowed to connect the DataArchiver without creating login successful audit messages.

iH Audited Writers

Allowed to write data and to produce a message each time a data value is added or changed.

Tag, archive, and collector changes log messages regardless of whether the user is a member of the iH Audited Writers Group.

iH Readers

Allowed to read data and system statistics. Also allowed access to Historian Administrator.

Use this table to identify the types of user groups you need to create and define in your security system.

Function	iH Security Admins	iH Un-Audited Writers	iH Un-Audited Login	iH Audited Writers	iH Readers	iH Archive Admins	iH Tag Admins	iH Collector Admins
Create Tags: <ul style="list-style-type: none"> • Excel Add-In • SDK • Historian Admins • File collector 	X						X	
Remove Tags: <ul style="list-style-type: none"> • Historian Admins • SDK 	X						X	
Modify Tags:	X						X	

Function	iH Security Admins	iH Un-Audited Writers	iH Un-Audited Login	iH Audited Writers	iH Readers	iH Archive Admins	iH Tag Admins	iH Collector Admins
<ul style="list-style-type: none"> • Excel Add-In • SDK • Historian Admins • File collector 								
Modify Archive Security: <ul style="list-style-type: none"> • SDK • Historian Admins 	X							
Backup Archive: <ul style="list-style-type: none"> • SDK • Historian 	X					X		

Function	iH Security Admins	iH Un-Audited Writers	iH Un-Audited Login	iH Audited Writers	iH Readers	iH Archive Admins	iH Tag Admins	iH Collector Admins
an Admins								
Restore Backup: <ul style="list-style-type: none"> • SDK • Historian Admins 	X					X		
Create Archive: <ul style="list-style-type: none"> • SDK • Historian Admins 	X					X		
Start/Stop Collector: <ul style="list-style-type: none"> • SDK • Historian 	X							X

Function	iH Security Admins	iH Un-Audited Writers	iH Un-Audited Login	iH Audited Writers	iH Readers	iH Archive Admins	iH Tag Admins	iH Collector Admins
Admins • Mission Control (iFIX)								
Browse Collector: • Historian Admins	X							X
Read Data: • Chart Object • Excel Add-In • SDK	X				X			
Write Data (UnAudited):	X	X	X					

Function	iH Security Admins	iH Un-Audited Writers	iH Un-Audited Login	iH Audited Writers	iH Readers	iH Archive Admins	iH Tag Admins	iH Collector Admins
<ul style="list-style-type: none"> • Excel Add-In • SDK 								
Write Data (Audited): <ul style="list-style-type: none"> • Excel Add-In • SDK 	X			X				
Modify Data: <ul style="list-style-type: none"> • Excel Add-In • SDK 	X	X	X	X				
Update Security for Tag: <ul style="list-style-type: none"> • Excel Add-In • SDK • Historian 	X							

Function	iH Security Admins	iH Un-Audited Writers	iH Un-Audited Login	iH Audited Writers	iH Readers	iH Archive Admins	iH Tag Admins	iH Collector Admins
ri-an Admins								
Migrate: • Migration Tools	X							
Login Connection Messages	X	X		X	X	X	X	X
Recalculate Data	X		X	X				X

Configure Internet Protocol Security (IPSEC)

Historian supports encryption based on Internet Protocol Security to secure traffic between various Historian components and collectors without the need to use VPN or other security protocols.


1. Run `wf.msc`.

The **Windows Defender Firewall with Advanced Security** window appears.


2. Create a security method:

- a. Select **Actions > Properties**.


The **Windows Defender Firewall with Advanced Security on Local Computer** window appears.



- b. Select **IPsec Settings > Customize**.
The **IPsec Defaults** window appears.




- c. Under **Key exchange (Main Mode)**, select **Advanced > Customize**.
The **Customize Advanced Key Exchange Settings** window appears.



d. Select **Add**.

The **Add Security Method** window appears.


e. Select the algorithms that you want to use for each purpose. The following image shows an example.



Important:

You must provide the same values for all the machines for which you want to configure IP security.

The security method that you have added appears in the list.




f. Move the security method that you have added to the top of the list. We recommend that you remove the other methods.

g. Select **OK**.

3. Add integrity and encryption algorithms:

a. In the **Customize IPsec Defaults** window, under **Data protection (Quick Mode)**, select **Advanced > Customize**.

The **Customize Data Protection Settings** window appears.



- b. Select the **Require encryption for all connection and security rules that use these settings** check box.
- c. Under **Data integrity and encryption**, select **Add**.
The **Add Integrity and Encryption Algorithms** window appears.

Add Integrity and Encryption Algorithms

Protocol

ESP (recommended)
ESP protocol provides privacy and integrity for the packet payload. ESP is compatible with Network Address Translation (NAT).

ESP and AH
Adding the AH protocol provides additional integrity for the IP header. This option is not compatible with NAT.

Algorithms

Encryption algorithm: AES-CBC 128

i Faster and stronger than 3DES. Compatible only with Windows Vista and later.

Integrity algorithm: SHA-1

i Stronger than MD5, uses slightly more resources.

Key lifetimes

Minutes: 60

KB: 1,000,000

OK **Cancel**

d. Under **Protocol**, ensure that **ESP** is selected.

e. Select the algorithms that you want to use for each purpose, and then select **OK**.

The algorithms that you have selected appear in the list.


f. Move the algorithms to the top of the list. We recommend that you remove the remaining items in the list.

g. Select **OK**.

4. Create a first authentication method:

a. In the **Customize IPsec Defaults** window, under **Authentication Method**, select **Advanced > Customize**.

The **Customize Advanced Authentication Methods** window appears.



b. Under **First authentication methods**, select **Add**.

The **Add First Authentication Method** window appears.

Add First Authentication Method ✕

Select the credential to use for first authentication:

Computer (Kerberos V5)

Computer (NTLMv2)

Computer certificate from this certification authority (CA):

 Signing algorithm: RSA (default) ▾

 Certificate store type: Root CA (default) ▾

Browse...

Accept only health certificates Advanced...

Enable certificate to account mapping

Preshared key (not recommended):

Preshared key authentication is less secure than other authentication methods. Preshared keys are stored in plaintext. When preshared key authentication is used, Second Authentication cannot be used.

OK Cancel

- c. Provide the CA certificate that you want to use, and then select **OK**.
The certificate that you have provided appears in the list.

d. Move the certificate to the top of the list. We recommend that you remove the remaining items in the list.

e. Select **OK**.

5. Create a connection security rule:

For Windows x86, run the following set of commands to create a rule:


```
netsh advfirewall
consec
add rule name=""<rule name>" endpoint1=any endpoint2=any protocol=tcp port1=any port2=2010
action=requestinrequestout
```

For other versions, perform the following steps:

a. In the **Windows Defender Firewall with Advanced Security** window, select **Connection Security Rules**.

b. Select **Actions > New Rule**.


The **New Connection Security Rule Wizard** window appears.



- c. Select **Custom**, and then select **Next**.
- d. Both for Endpoint 1 and Endpoint 2, select **Any IP Address**, and then select **Next**.
- e. Select **Require authentication for inbound and outbound connections**, and then select **Next**.
- f. Select **Default**, and then select **Next**.
- g. Enter values as described in the following table, and then select **Next**.

Field	Description
Protocol type	Select TCP .
Endpoint 1 port	Select All Ports .
Endpoint 2 port	Select Specific Ports , and then enter 2010.

- h. Select when to apply the rule, and then select **Next**.
 - i. Enter a name and description for the rule, and then select **Finish**.
The rule appears in the **Connection Security Rules** window.
 - j. Ensure that the rule is enabled.
6. If using Microsoft Windows Server 2019, 2016, 2012 R2 and/or Windows 8, 8.1, open up port number 5000:
- a. In the **Windows Defender Firewall with Advanced Security** window, select **Inbound Rules**.
 - b. Select **Actions > New Rule**.
The **New Inbound Rule Wizard** window appears.



- c. Select **Custom**, and then select **Next**.
- d. Select **All programs**, and then select **Next**.
- e. Enter values as described in the following table, and then select **Next**.

Field	Description
Protocol type	Select UDP .
Protocol number	Leave the default value as is.
Local port	Select Specific Ports , and then enter 5000.
Remote port	Leave the default value as is.

- f. Both for the local and remote IP addresses, set the scope to **Any IP address**, and then select **Next**.
- g. Select **Allow the connection**, and then select **Next**.

- h. Select when to apply the rule, and then select **Next**.
- i. Enter a name and description for the rule, and then select **Finish**.
The rule appears in the **Inbound Rules** window.
- j. Ensure that the rule is enabled.

IPSEC is now configured on the machine.

7. Repeat all the steps above on all the machines that host the Historian server and/or its components/clients.
8. To verify that the IPSEC cryptography is used:
 - a. Ensure that the Historian server is running.
 - b. Ensure that the collectors are connected to the Historian server, and that the collectors are running.
 - c. Specify the tags for data collection. You can do so using [Configuration Hub \(on page 357\)](#) or [Historian Administrator \(on page 909\)](#).
 - d. Verify that the collector is collected data.
 - e. On each machine on which you configured IPSEC, run `wf.msc`.
The **Windows Defender Firewall with Advanced Security** window appears.
 - f. Select **Monitoring > Security Associations > Main Mode**.
The **Main Mode** section displays the connection that you have created.

Security Setup Example

The following example takes you through the process of establishing your security needs and defining and setting up the levels of security.

For this example, assume the following user needs in a plant of 14 users:

User	Needs	Added to Security Group
USER1	Power user. Needs total access to security.	iH Security Admins
USER2	<ul style="list-style-type: none"> • Read/Write Data (no messages). • Create, modify, and delete tags. 	<ul style="list-style-type: none"> • iH UnAudited Writers • iH Tag Admins
USER3		

User	Needs	Added to Security Group
USER5 USER6 USER8	<ul style="list-style-type: none"> • Backup, restore, and create archives. • Connect to Data Archiver without creating login successful audit messages 	<ul style="list-style-type: none"> • iH Archive Admins • iH UnAudited Logins
USER4 USER7	<ul style="list-style-type: none"> • iRead/Write Data (no messages). • iCreate, modify, and delete tags. • iStart/Stop Collectors. • iBackup, restore, and create archives. 	<ul style="list-style-type: none"> • iH UnAudited Writers • iH Tag Admins • iH Collector Admins • iH Archive Admins
USER9-14	Read Data.	iH Readers

1. Establish the needs of your users. For this example, assume the user needs in a plant of 14 users, as described in the previous table.
2. Add and define the iH Security Admins Group.
Once you determine that you want to establish a security structure, you must create and define the iH Security Admins group. This group of users is typically the "power users" of the Historian. Security Administrator rights allow them to manage configuration and give them free rein to the entire system. For this example, only USER1 would be added to the iH Security Admins group.
3. Establish and create any other Historian Security Groups as needed.

**Note:**

Any user with Windows administrative permissions can add or remove Windows groups and users. As such, an administrator on a Windows computer, can add himself to any Historian security group.

Set up the functional security groups as needed. For this example, Write, Tag, Archive, and Collector security is required, so the groups associated with those functions should be added and defined. There is no need for Audited Writers and all valid users can read data, so neither the iH Audited Writers Group nor the iH Readers Group need to be added.

4. Define any individual Tag Level security.

In addition to defining iH Tag Admins that have the power to create, modify, and remove tags, you can also define individual tag level security to restrict access to sensitive tags. You can grant read, write, or administrative privileges per tag. For more information on setting Tag Level security, refer to the *Implementing Tag Level Security* section.

Setting Up Historian Security Groups

This section describes how to add the Historian Security Groups to your local and domain Windows security systems.

You can choose whether Historian uses LOCAL or DOMAIN security by selecting an option on the **Security** section of the **Data Store Maintenance** page in Historian Administrator. If you select the local security option, the groups are defined as local groups on the Historian server. If you select the Domain security option, the groups are defined as global groups in the primary domain controller of the Historian server. With domain security, Historian locates the Primary Domain Controller (PDC), if available, or a Backup Domain Controller (BDC) in order to establish groups. If the PDC and all BDCs are unavailable, the system locks all users out until rights can be established with a valid PDC or BDC.

**Note:**

If you change this setting, you must stop and re-start the Historian server for this change to take effect.

Creating a Local Group on Windows

1. Do a Windows search and open **Computer Management**.

The **Computer Management** console appears.

2. In the left-side pane, expand **System Tools**, and then expand **Local Users and Groups**.

3. Select **Groups** in the system tree.

The list of all the available groups appear.

4. In the right-side pane, select **Groups > More Actions**, and then select **New Group**.

The **New Group** window appears.

5. Enter the Historian Security Group name in the **Group Name** field.

For a list of available Historian Security Groups and their functions, see [Historian Security Groups \(on page 256\)](#).

**Note:**

You must enter the Historian Security Group name exactly as it appears. The security groups are case sensitive.

6. Optionally, enter a description of the Historian Security Group in the **Description** field.
7. Select **Create**.
8. Select **Close**.

Adding Users to Windows Security Group

Add your users to the Windows system.

1. Do a Windows search and open **Computer Management**.

The **Computer Management** console appears.

2. In the left-side pane, expand **System Tools**, and then expand **Local Users and Groups**.

3. Select **Groups** in the system tree.

The list of all the available groups appear.

4. Select the group to which you want to add users.

5. In the right-side pane, select the user > **More Actions**, and then select **Properties**.

The user **Properties** window appears.

6. Select **Add**.

7. Select the users or groups to add from the listed users or enter the names of the users or groups you want to add in the bottom field.

8. Select **Add**.



Note:

To validate the user or group names that you are adding, select **Check Names**.

9. When you have added all users to the group, select **OK**.

Adding a Local or a Domain User

1. Verify object type is **Users** or **Groups**.

2. If you want to add a local user, verify the **From This Location** setting is your local machine. (Select **Locations** to specify the local machine, if required.). If you want to add a domain user:

- a. Select **Locations** to specify the domain, if required.

- b. Select **Entire Directory** or the specific domain underneath **Entire Directory**.

- c. Select **OK**.

3. Select **Advanced**.

The **Advanced** window appears.

4. Select **Find Now**.

5. From the list of users, select the users or groups to add or enter the names of the users or groups you want to add in the bottom field.

6. In the **Advanced** window, select **OK**.

7. In the **Select Users** window, select **OK**.

8. In the **Group Properties** window, select **OK**.


Active Directory Setup - an Overview

Historian Active Directory setup supports integration with complex models that include the following complexities:

- Users and administrators may belong to different domains within a forest.
- Domains may have sub-domains (multi-level) that need to inherit or refine on inherited permissions
- Group names may be longer than average to cater for group differentiation

The Active Directory setup supports authentication and authorization of users as members of groups from trusted or sub-domains (including assigning appropriate Historian access rights in line with Historian security roles/groups access).

The following figure provides an overview of the Active Directory setup with examples:



Configuring the Domain Users for active directory setup

To configure the domain (single\multi) environment in Historian Administrator:

Historian Security Groups should be created on the machine where the Domain controller of the Historian Server is installed. The India.Europe.US.com domain controllers must contain the following Historian groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins
- iH Archive Admins
- iH UnAudited Writers
- iH UnAudited Logins
- iH Readers
- iH Audited Writers



Note:


Historian Security Groups should be of type **Domain-Local** only.

1. On the **Data Stores** section, under **Security > Global Security**, select the **Use domain** option.

The screenshot shows the Proficy Historian web interface. The top navigation bar includes links for Main, Tags, Collectors, DataStores, Messages, and Help. Below this, there are buttons for 'Rename Data Store', 'Add Data Store', 'Add New Archive(s)', and 'Restore an Archive from Backup'. The main content area is divided into two sections: 'Data Stores' and 'Security Options'. The 'Data Stores' section shows a dropdown menu set to 'User' and a table of archives. The 'Security Options' section has tabs for 'Archive Details', 'Data Store Details', 'Data Store Options', 'Global Options', 'Security', and 'Alarms'. The 'Global Security' section is active, showing radio buttons for 'Use Local' and 'Use Domain', with 'Use Domain' selected and circled in blue. Below this are options for 'Enforce Strict Client Authentication' and 'Enforce Strict Collector Authentication', both set to 'Enabled'. The 'Electronic Signatures / Records' section shows 'Require Point Verification' set to 'Disabled'. A 'Verification Message' text area contains the text: 'You Are Attempting To Perform An Audited Action. Please Confirm Your Username and Password to Continue'. An 'Update' button is located at the bottom right of the 'Security Options' section.

Name	Start Time
User_ConfigServer6_Archiv...	9/20/2018 5:00:00 ...
User_ConfigServer6_Archiv...	9/19/2018 5:00:00 ...
User_ConfigServer6_Archiv...	9/18/2018 5:00:00 ...
User_ConfigServer6_Archiv...	9/17/2018 5:00:00 ...
User_ConfigServer6_Archiv...	9/16/2018 5:00:00 ...
User_ConfigServer6_Archiv...	9/15/2018 5:00:00 ...
User_ConfigServer6_Archiv...	9/14/2018 5:00:00 ...
User_ConfigServer6_Archiv...	9/13/2018 5:00:00 ...
User_ConfigServer6_Archiv...	9/12/2018 5:00:00 ...
Empty	

2. Stop the Historian Services.
3. Add the Registry Entries for ClientManager, ConfigManager and DataArchiver as shown below.
Registry path: `\HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\`



4. Start the Historian Services. The new registry entries will now be read by the corresponding Historian service.

Accessing Historian Server using Domain Users - Examples

Example 1: European domain user trying to connect to Historian Server installed in India.Europe.US.com Domain Controller (DC).

1. Create a user **EuropeUser1** in Europe.US.com DC.
2. Add the user (i.e. EuropeUser1) from Europe.US.com to "iH Security Admin" group in India.Europe.US.com DC.
3. Log in to Historian Client using EuropeUser1 as shown below.



4. EuropeUser1 is added to iH Security Admin. The user will get full access to Historian Server.

Example 2: US domain user trying to connect to Historian Server (which is installed in India.Europe.US.com Domain Controller (DC)).

- a. Create a user **USUser1** in US.com DC.
- b. Add the user (i.e. USUser1) from US.com to "iH Readers" group in India.Europe.US.com DC
- c. Log in to Historian Client using USUser1 as shown below.



5. USUser1 is added to iH Readers. The user will get only data read access to Historian Server.

Adding Nested Domain Groups to Historian Security Groups

The following procedure describes, a European domain group user trying to connect to Historian server, installed in India.Europe.US.com Domain Controller.

1. Create a user **EuropeGroupUser1** in Europe.US.com DC.
2. Create a group **EuropeGroup1**.
3. Add the EuropeGroupUser1 to EuropeGroup1.
4. Add the group (i.e. EuropeGroup1) from Europe.US.com to "iH Security Admin" group in India.Europe.US.com DC
5. Log in to Historian Client using EuropeGroupUser1.
6. If a new user gets added to EuropeGroup1, then the user gets automatically synced with Historian Security Groups.



Note:

As EuropeGroupUser1 is added to iH Security Admin, user will get full access to Historian Server.

US domain group user trying to connect to Historian Server installed in India.Europe.US.com Domain Controller.

- a. Create a user **USGroupUser1** in US.com DC (if not exist).
- b. Create a group USGroup1.
- c. Add the USGroupUser1 to USGroup1.
- d. Add the group (i.e. USGroup1) from US.com to “iH Security Admin” group in India.Europe.US.com DC
- e. Login to Historian Client using USGroupUser1.
- f. If a new user gets added to USGroup1, then it gets automatically synced with Historian Security Groups.



Note:

As USGroupUser1 is added to iH Readers, user will get data read access to Historian Server

Managing Proficy Authentication Users Using the Configuration Tool

Use the Proficy Authentication Config tool to perform the following tasks:

- Add a local Proficy Authentication user.



Note:

Here a local Proficy Authentication user means a user defined by Proficy Authentication, not by an external identity provider such as LDAP.

- Remove a local Proficy Authentication user.
- Reset the password for a local Proficy Authentication user.
- Add a local Proficy Authentication user to an existing group.

Since OAuth2 scopes are implemented as Proficy Authentication groups, this means the same as adding a scope to a user.

- Remove a local Proficy Authentication user from an existing group.

A user who performs these functions acts as the admin client and needs to know the secret of the admin client. The tool does provide a way for the user to cache the secret safely to be used later.

By default, this tool is available in the following folder: `C:\Program Files\GE Digital\Historian Config`. Run the tool from a Windows command prompt window.

Syntax

The tool's syntax follows this format:

```
uaa_config_tool verb [options]
```

where verb is one of the following:

- `add_user`
- `remove_user`
- `set_user_password`
- `add_user_to_group`
- `remove_user_from_group`
- `clear_secret`

Run the tool without a verb or any other options to view the help page.

The `uaa_config_tool` utility prompts for a port number. This is the port number that you have specified in the Public HTTPS Port field in the **TCP PORT ASSIGNMENTS** page. By default, it is set to 443. If you have changed the public HTTPS port number, enter the number. Otherwise, enter 443.

Options can be specified in the form of single dash followed by a short name, or double dash followed by a long name, followed by the value of the option, if any. For example, you can specify the user name `Alice` by either

```
-u Alice
```

or

```
--UserName Alice
```

Table 11. Options

Short name	Long name	Remark
<code>-t</code>	<code>--Target</code>	URL of the Proficy Authentication instance that the command should be performed on. Typically, the URL is <code>https://localhost:443/uaa</code> , which is the default value. This option is optional and is only needed when the user wants to run the command against a remote Proficy Authentication instance (which is not recommended due to security concerns).
<code>-n</code>	<code>--ClientId</code>	ID of the client that the user is acting as. By default, it is <code>admin</code> . This option is optional and is only needed when the ad-

Table 11. Options (continued)

		min has set up the Proficy Authentication to delegate certain operations to others.
-s	--ClientSecret	This is the secret used to authenticate the user for acting as the admin client (or an alternative client given in a <code>--ClientId</code> option). If the user has elected to cache the secret previously, then this option can be omitted. Otherwise, it has to be provided. The password must satisfy the following conditions: <ul style="list-style-type: none"> • Must not contain only numbers. • Must not begin or end with a special character. • Must not contain curly braces.
-c	--CacheSecret	This option is not followed by a value and is optional. If specified, the tool will cache the client secret so when the next time this tool is invoked the secret does not have to be specified. Note that the secret is encrypted and only the current Windows logon user can access and decrypt.
-u	--UserName	Name of the user that the tool is being invoked for. For example, the user that is being added or removed.
-p	--UserPassword	The password for the user being added or whose password is being reset. The option is only needed for the <code>add_user</code> and <code>set_user_password</code> commands.
-g	--Group	Name of the Proficy Authentication group (scope) that the user is being added to or removed from. The option is only needed for the <code>add_user_to_group</code> and <code>remove_user_from_group</code> commands.

Examples

- To add a user named alice with the password Pa55word and the admin client secret myclientsecret (this is the admin client secret that you entered while installing Web-based Clients):

```
uaa_config_tool add_user -u alice -p Pa55word -s myclientsecret -c
```

If the Proficy Authentication server is on a remote machine named webhost.lab:

```
uaa_config_tool add_user -u alice -p Pa55word -s myclientsecret -t https://webhost.lab:443/uaa -c
```

- To provide user privileges to access the Web Admin console and Trend Client:

```
uaa_config_tool add_user_to_group -u alice -g historian_visualization.user -t https://webhost.lab:443/uaa
```

- To provide admin privileges to access the Web Admin console and Trend Client:

```
uaa_config_tool add_user_to_group -u alice -g historian_visualization.admin -t https://webhost.lab:443/uaa
```

- To provide Configuration Hub privileges, add alice to the group `historian_enterprise.admin`, using the previously cached admin secret:

```
uaa_config_tool add_user_to_group -u Alice -g historian_enterprise.admin -t https://webhost.lab:443/uaa
```

- To remove alice from a remote instance of Proficy Authentication as an alternative client (that is, other than `admin`) `useradmin`:

```
uaa_config_tool remove_user -u alice -t https://webhost.lab:443/uaa -n useradmin -s MyOtherNonSecret
```

- To clear any cached client secret:

```
uaa_config_tool clear_secret
```



Note:

If the Windows logon account is not shared, it is not necessary to clear cached secret, since the cache is encrypted and only the same Windows user account can decrypt.

When there are Historian security groups on the local historian machine or on the domain server:

1. Create a new user account on the local Historian machine or on the domain server with same login name and password as the local Proficy Authentication user.
2. Add the new user to the appropriate Historian Security group on the local historian machine or on the domain server.

Create a Proficy Authentication Reader Client

To fetch Historian data, previously, you had to manually add each user to iH security groups. Only then the users could fetch the data. Now, this process has been simplified. All you must do is create a Proficy Authentication client. The Proficy Authentication client will be automatically added to the iH Readers security group on the server side. Therefore, you can use the client to fetch Historian data using REST APIs.

1. Access the Proficy Authentication Config tool, which is located in the following folder by default:
C:\Program files\GE Digital\Historian Config\uaa_config_tool
2. Access Command Prompt as an administrator, and then run the following command:

```
uaa_config_tool add_historian_reader_client -u <client name> -p <client password>
-n <username> -s <password> -t https://<Proficy Authentication URI>:443/uaa
```

To create a client named client1:

```
uaa_config_tool add_historian_reader_client -u client1 -p password123
-n user1 -s userpassword123 -t https://Proficy Authentication URI2010:443/uaa
```

The Proficy Authentication reader client is created. However, if it already exists, a message appears, stating the same.

About Accessing Cross-Domain Historian

You can now access Historian across various domains regardless of the domain to which your user account belongs. To do so:

- Ensure that all the domain controllers across various domains trust one another.
- Create iH security groups on each leaf node that contains the Historian server that you want to access.
- Ensure that you are part of at least one iH security group. You can be part of an iH security group directly, or you can be part of a universal domain group, which must be part of the iH security group.

About Domain Security Groups

When you configure Historian to use domain security groups, the data archiver attempts to locate the groups on the primary domain controller (PDC) or one of the backup domain controllers (BDC). When using a PDC, if a primary or backup domain controller cannot be located when the Historian Data Archiver service starts, access to Historian is denied to all users.

For troubleshooting, .shw file of the data archiver lists all PDCs and BDCs available at the time of archiver startup. Use this list to verify that the Historian server has visibility into the appropriate domain.

When using a PDC, after the list of Domain Controllers has been established, the Historian Server will use that list to query for Security Group Membership on an as needed basis. If at any time a request for Group Membership information is made and the Primary Domain Controller is not available, Historian selects the first Backup Domain Controller and attempts the same request. If a Backup Domain Controller successfully responds to the request, the process of querying for Group Membership can stop. Otherwise,

Historian will attempt to query Group Membership information from the next available Backup Domain Controller. If no Backup Domain Controller successfully responds, access to the system is denied.

Changing security group configuration from Local to Domain or vice versa requires that the Historian Data Archiver service be restarted for the change to take effect.

Establishing Your Security Rights

Your security identity is established upon connecting to the server. This occurs through the following steps:

1. Specifying a user name and password of an account.

Upon connection, the system checks to see if you have a valid Windows 2003 account. If you have supplied a username and password (through the Excel Add-In for example), security checks that user. If username and password are not supplied and you are on a Windows 2003 or Windows 2008 machine or higher, security checks the currently logged in user.



Note:

If you do not pass a domain name the account will be checked locally in the same way a mapped drive attempt happens. You have to specify a username and password that exists on the server.

2. Determining group membership of that account.

Once the account is validated, the server determines group membership. For more information on the process and hierarchy of the groups, refer to the Security Checking Process diagram below.

3. Caching membership profile.


Once the group and tag membership are determined, it is cached for the connection and not looked up again. If users are added to or deleted from a group, the cache is not updated.



Note:

The cache information is per connection, and not per IP address. In other words, it is cached per application and not per system.

Figure 1. Security Checking Process



*** When security groups are defined in Proficy Authentication, the user must belong to the appropriate group. Not being a part of a specific group does not, by default, grant full access. *d**

Implementing Tag-level Security

In addition to defining the iH Tag Admins who have the power to create, modify, and remove tags, you can also define individual tag level security to protect sensitive tags.

Set tag level security in Historian Administrator. You need the Historian Security Groups to implement tag-level security. You can use a Windows pre-defined group (power users, for example) or create your own separate group specifically for this function. For more information on creating and adding groups, refer to [Setting Up Historian Security Groups \(on page 277\)](#).

Users must have iH Security Admins rights to set individual tag level security, browse, or query tags in Historian Administrator.



Note:

Tag security is not enforced in the Trend Client when it comes to browsing the full list of tags. Security, however, is enforced when it comes to trending data for tags for which you have permission. For example, if you are logged into the Trend Client as a user that is a member of the User Group assigned to a tag's security Read Group, you will still be able to browse all Historian tags. However, you are only allowed to trend the tags for which the user is a member of the User Group assigned to the tag's security Read Group,

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears.
3. Select the row containing the tag whose security you want to define.
The tag details appear in the **DETAILS** section.
4. Enter values as described in the following table.

Field	Description
Read Group	<p>The Windows security group that can retrieve the tag data and plot it in a trend chart.</p> <p>For example, if you select a group with power users, in addition to members of the iH Security Admins group, only a member of the power users group will be able to read data for that tag. Even a member of the iH Readers group will not be able to access data for that tag, unless they are also defined as a member of the power users group.</p>

Field	Description
Write Group	The Windows security group that can write tag data (for example, using the Excel Add-in for Historian).
Administer Group	The Windows security group that can create, modify, and delete the tag.

**Note:**

- If you are using domain groups (instead of local groups), the **Read Group**, **Write Group**, and **Administer Group** fields contain only the groups whose names begin with iH<space> (case-sensitive). Therefore, ensure that the group that you want to use begins with iH<space>. For more information on the security groups, refer to [Historian security groups \(on page 256\)](#).
- If you are using Proficy Authentication, any custom groups that you created must be defined in Proficy Authentication and added to the group whose names begin with ih_<group_name>. For more information on the Proficy Authentication groups, refer to [about Proficy Authentication groups \(on page 231\)](#).

Implementing Data Store-level Security

In addition to defining the iH Tag Admins who have the power to create, modify, and remove tags, the individual tag-level security, you can also define individual data store-level security to protect sensitive tags.

**Note:**

The security settings defined at the tag level, if any, take the precedence over those at the data store-level.

You need the Historian Security Groups to implement data store-level security. You can use a Windows pre-defined group (power users, for example) or create your own separate group specifically for this function. For more information on creating and adding groups, refer to [Setting Up Historian Security Groups \(on page 277\)](#).

Users must have iH Security Admins rights to set individual data store level security.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**. A list of all the data stores appears.

- Select the row containing the data store whose security you want to define.
The data store details appear in the **DETAILS** section.
- In the **SECURITY** section, enter values as described in the following table.

Field	Description
Read Group	The Windows security group that can retrieve the tag data and plot it in a trend chart for the selected data store. For example, if you select a group with power users, in addition to members of the iH Security Admins group, only a member of the power users group will be able to read data of the tags for that data store. Even a member of the iH Readers group will not be able to access data of the tags for the selected data store, unless they are also defined as a member of the power users group.
Write Group	The Windows security group that can write tag data for the selected data store (for example, using the Excel Add-in for Historian).
Administer Group	The Windows security group that can create, modify, and delete the tags for the selected data store.

**Note:**

When it comes to the group security, the security settings applied at the tag level, if any, take the precedence over those at the data store level.

**Note:**

- If you are using domain groups (instead of local groups), the **Read Group**, **Write Group**, and **Administer Group** fields contain only the groups whose names begin with iH<space> (case-sensitive). Therefore, ensure that the group that you want to use begins with iH<space>. For more information on the security groups, refer to [Historian security groups \(on page 256\)](#).
- If you are using Proficy Authentication, any custom groups that you created must be defined in Proficy Authentication and added to the group whose names begin with ih_<group_name>. For more information on the Proficy Authentication groups, refer to [about Proficy Authentication groups \(on page 231\)](#).

For more information on System Global security settings, refer to [access system \(on page 411\)](#).

Uninstalling Historian

Uninstalling Historian

Uninstalling Historian removes all saved Favorites from your Trend Client and all Users and Scopes you created. To keep these and other configurations on an upgrade, do not uninstall Historian unless you are changing server roles as previously described. If you must uninstall Historian on an upgrade, you can Export your favorites and save your data and tag configuration files for future use.

For information on uninstalling OPC Data Collectors, refer to the *Modifying and Uninstalling OPC Collectors* section of the *Historian Data Collectors* manual.

- When you want to uninstall Web-based Clients:
 - If you select the **Purge database during uninstall** check box, the entire database will be purged, and you must recreate the Proficy Authentication details, favourites, and so on. Therefore, if you want to retain Proficy Authentication details, do not select that check box.
 - If you have installed Operations Hub on the same machine, and if there is a shared Proficy Authentication package between Operations Hub and Web-based Clients, in some cases, a message appears, asking you to first uninstall Operations Hub before uninstalling Web-based Clients. You can, however, uninstall Web-based Clients first; the shared Proficy Authentication package will not be deleted in that case.
 - Configuration Hub will not be uninstalled because it is a common component. If needed, you can uninstall it separately.

- If you uninstall Historian after installing the Excel Add-In as described, ensure that you clear the **Historian** check box in the Microsoft Excel **Add-Ins** window. If you do not clear this option, you will receive an error each time you open Microsoft Excel.

1. To uninstall Historian from your computer:

- a. Double-click the **Programs / Uninstall a Program** link in the Control Panel.
- b. Select **Historian** and select **Uninstall**.

**Note:**

Historian archives are not removed by default. If you need to remove them, delete the folder manually.

A progress bar appears, showing that the software is being uninstalled. This may take some time.

To abort the uninstall, select **Cancel**.

2. To remove all related software from your computer:
 - a. Double-click the **Programs / Uninstall a Program** link in the Control Panel.
 - b. Select **Proficy Common Licensing**, and select **Uninstall**.


Troubleshooting

Managing Historian Log Files

Use the Historian LogTool to view, generate, or compress log files to use for troubleshooting.

Logtool.exe is located in the historian installation directory, for example: `C:\Program Files\Proficy\Proficy Historian\X64`.


1. Go to your installation directory and execute the Logtool.exe file.
The **LogTool** appears, displaying the **View Log** section.



2. Select a component from the left panel to see the available log files, and select **View Log**.
3. Select **Generate Logs** to enable or disable the debug logging mode for Historian components:

This tool will enable/Disable the debug mode for Historian components. However, leaving the debug mode enabled for longer time consume the disk space

1. Select the component
2. Choose enable/disable option
3. Select apply



- a. Select a Historian Component and select **Enable** or **Disable**.




Note:

Leaving debug mode enabled for a component consumes disk space.

- b. Select **Apply**.

4. Select **Gather Logs** and select **Zip the log files** to compress the log files and select **Open zip file location** to view the zip files.



Troubleshooting the Historian Server

iFIX-Related Files in C Drive Even if iFIX is not Installed

Description

If you install only Historian without installing iFIX, you may find some iFIX-related files in the C drive.

Workaround

You can ignore/delete them. If, however, you plan to install iFIX later, you must reinstall Historian Client Tools after installing iFIX.

Error Message when Upgrading the Historian Server on a Passive Node in a Cluster

Description

If you are upgrading the Historian server on a passive node, an error message may appear behind the installer screen, stating that the Archives directory is not created.

Error Message

Unable to create Archives directory.

Workaround

You can ignore this message, or you can make the node active before upgrading the Historian server.

Historian Server Rejects Collector or Client User Credentials

Description

If a client or collector is attempting to connect to the Historian server with strict authentication enabled on a Kerberos configuration, the server rejects valid credentials and does not allow the connection.

Workaround

Ensure that the server time and the domain controller time match with each other.

Historian Resource in a Cluster Environment is not Online

Workaround

Ensure that the cluster feature is included in your license.

Historian Resource Runs for a Long Duration and Fails Over

Workaround

Debug the log messages of the Data Archiver and the Clusters before taking appropriate actions.

While Label Error

Description

If the PFX file that you want to use with Historian does not contain a full-chained certificate, a while label error message appears.

Workaround

1. Create a PEM file from the PFX file by copying the content from all the certificates (such as root, intermittent, and leaf certificates) to the PEM file. It results in a full-chained certificate.
2. Get a KEY file from the vendor. Or, use a KEY file extracted from the PFX file using the Certificate Management tool. To do so, import the PFX file. The certificate and the KEY file will then be available in the `<Operations Hub installation`

location>\httpd\conf\cert folder. You can then use the `server.key` file in the folder.

3. Using the Certificate Management tool, import the PEM and KEY files to the machines on which the Historian server, the Operations Hub server, and clients are installed.

Troubleshooting Web-based Clients

Unable to Access Configuration Hub After Upgrading Web-based Clients

Description

After you upgrade Web-based Clients, you cannot access Configuration Hub.

Workaround

Clear your browser cache.

Error Occurs When You Try to Access Web-based Clients

Description

If you have logged in to Operations Hub, and then if you try to access Web-based Clients, and vice versa, an error occurs. This is because the user credentials of the first application to which you have logged in are used to log in to the other one as well.

Workaround

Try one of the following steps:

- Add the scopes of each application user to the other application.
- If you log in to Web-based Clients first, on the login page of Operations Hub, re-log in with the Operations Hub user. If you log in to Operations Hub first, log out of Operations Hub, log in to Web-based Clients, and then log in to Operations Hub, using the credentials of the respective users for each application.

Unable to Access Web-based Clients

Description

When you upgrade Historian, after installing Web-based Clients, a message asking you to restart the machine does not appear. Because of this, sometimes, you cannot access Web-based Components such as Configuration Hub, Trend Client, the Web Admin console, and REST APIs.

Workaround

Restart the machine, or start the following services:

- Proficy Historian PostgreSQL Database
- Proficy Historian Tomcat Server
- Proficy Operations Hub Httpd Reverse Proxy
- Proficy Authentication PostgreSQL Database
- Proficy Authentication Tomcat Web Server

Certificate Issues When Trying to Log in

Workaround

[Connect to a Remote Proficy Authentication Service \(on page 182\)](#)

Web-based Clients are not connected to the Historian server

Workaround

- Ensure that the **Enforce Strict Client Authentication** and **Enforce Strict Collector Authentication** options are disabled in the **Data Stores Security** section in Historian Administrator.
- Ensure that the Proficy Authentication URL used by Web-based Clients matches the one you provided while installing the Historian server. If not, [change the Proficy Authentication server \(on page 137\)](#) so that the Historian server points to the same Proficy Authentication server as Web-based Clients.

Clients or Users Not Created

Description

Clients or users are not created because the required services were not running during the installation of Web-based Clients.

- An error message appears when you access Web-based Clients or Trend Client.
- The visualization client is not found. The following error message appears: No client with requested id: historian_visualization
- When you attempt to log in to Proficy Authentication, a message appears, stating that the credentials are incorrect.

Workaround

[Configure Web-based Clients \(on page 186\)](#) to point to a different Configuration Hub and Proficy Authentication instance.

The Reverse Proxy Service Stops Working

Description

If you install iFIX on a machine that has Historian Web-based Clients, the reverse proxy service stops working.

Workaround


Restart the reverse proxy service - Proficy Operations Hub Httpd Reverse Proxy.

Chapter 3. Configuration Hub

Overview

About Configuration Hub

The Configuration Hub application allows you to manage the Historian models, Historian systems, and their components.



Advantages of Using Configuration Hub:

- **Creating a Historian model:** You can create and manage object models, which is a hierarchical classification of objects. A model contains object types, variables, and instances.
- **A single application that enables you to manage multiple Historian systems:** A Historian system is a network of Historian servers that collect, store, and retrieve data related to tags, alarms, and events. You can create and manage Historian systems using Configuration Hub. In addition, you can manage collectors, data stores, and tags.
- **Horizontal scalability:** You can increase the storage capacity of a Historian system by connecting multiple software entities so that they work as a single logical unit. This will improve the

performance of the Historian system. The storage capacity depends on the number of Historian licenses that you have purchased.

- **High availability:** You can create mirror locations in a Historian system to achieve high availability of the server. If one of the servers is not available, you can retrieve data from the remaining servers in the mirror location.
- **Ease of setting up:** You can install all the collectors used in a Historian system easily by providing the required details with the help of the user-friendly interface.

Types of Historian Systems

- **Stand-Alone:** In a stand-alone Historian system, there is only one Historian server. This type of system is suitable for a small-scale Historian setup. For information on setting up a stand-alone Historian system, refer to [About Setting up a Stand-Alone Historian System \(on page 356\)](#).
- **Horizontally scalable:** In a horizontally scalable Historian system, there are multiple Historian servers, all of which are connected to one another. This type of system is used to scale out the system horizontally. For example, if you have 5,00,000 tags in your Historian system, you can distribute them among the various servers to improve performance. For information on setting up a horizontally scalable system, refer to [About Setting up a Horizontally Scalable System \(on page 359\)](#).

Limitations

- If only one machine remains in a mirror location, you cannot remove it.
- If you install Configuration Hub and the Web Admin console on the same machine, and use self-signed certificates for both of them, the login page for Configuration Hub does not appear. To prevent this issue, disable the domain security policies:
 1. Access the following URL: `chrome://net-internals/#hsts`
 2. In the **Domain Security Policy** section, in the **Delete domain security policies** field, enter the domain name for Configuration Hub, and then select **Delete**.
- If the primary server is down, you cannot add tags using a distributed node because the Configuration Manager service is down.

Configuration Hub Workflow

This topic provides the high-level steps in using Configuration Hub.

1. [Set up Configuration Hub](#). This involves installing the Historian server, the collectors, and Web-based Clients.
2. [Apply the license \(on page 82\)](#).

- Depending on your requirements, set up [a stand-alone system \(on page 356\)](#) or [a horizontally scalable system \(on page 359\)](#). This involves adding the required components.

**Note:**

When you set up Configuration Hub, by default, a system and a data store are created. You can add more systems and data stores as needed.

- For a horizontally scalable system, you can choose to [set up high availability \(on page 367\)](#).
- As needed, [create an object model \(on page 371\)](#).
- [Specify the tags for data collection \(on page 357\)](#).

After you perform these initial steps, data is collected and stored in the Historian server. You can then retrieve and analyze the data.

Setting up Configuration Hub

About Setting up Configuration Hub

To set up Configuration Hub, you must perform the following steps:

- [Install the Historian server \(on page 105\)](#).
 - For a stand-alone Historian server, install single-server Historian.
 - For a horizontally scalable Historian server, install the mirror primary server and distributed/mirror servers.
- [Install Web-based Clients \(on page 155\)](#).
- [Install collectors \(on page 143\)](#).
- [Perform the post-installation tasks \(on page 335\)](#).

If you want to upgrade Configuration Hub, refer to [Upgrade Configuration Hub \(on page 336\)](#).

After you install or upgrade the required components, you can [access Configuration Hub \(on page 336\)](#).

Install the Historian Server Using the Installer

- set up the Historian environment.
- If you want to install web-based clients and view Historian license information on Configuration Hub, you must provide the Configuration Hub and Proficy Authentication server details during installation. Therefore, ensure that you have already set up Proficy Authentication in Configuration


Hub. For more information on setting up Proficy Authentication in Configuration Hub, refer to https://www.ge.com/digital/documentation/confighub/version2023/t_authentication_setup.html.

- If you are changing the role of a Historian server that was previously a distributed/mirror server to any other configuration (single-server or mirror primary server), you must first uninstall Historian.
- If you are installing a distributed/mirror server, use the same configuration, license key, installation drive, Proficy Authentication instance, and domain as the primary server.


This topic describes how to install the Historian server using the installer.

You can also install it at a command prompt.


1. Log in as an administrator to the machine on which you want to install the Historian server.
2. Run the `InstallLauncher.exe` file.
3. Select **Install Historian Server**.
The welcome page appears.
4. Select **Next**.
The license agreement appears.
5. Select the **Accept** check box, and then select **Next**.
The **Where do you want to install Historian?** page appears.



- If needed, change the default installation drive of the Historian server, and then select **Next**.
The **Override the default Historian data Path?** page appears.



- If needed, change the default folder of the log files, and then select **Next**. If you want to include the Historian server in a cluster, enter the path to the shared folder of the cluster.
The **Register with Configuration Hub** page appears.



8. Select the **Use existing Proficy Authentication and Configuration Hub Instance** check box, and provide values as described in the following table.

This step is needed only in the following cases:

- The Historian Server and the Web-based clients will be on two different machines.
- You already installed Proficy Authentication and Configuration Hub, and you want to use the Historian Web-based clients and view the Historian license information on Configuration Hub.

If you do not select the **Use existing Proficy Authentication and Configuration Hub Instance** during the installation, to use the Historian Web-based clients and view the Historian license information on Configuration Hub, you must use the Proficy Authentication Tool from the Start menu to register with Proficy Authentication and Configuration Hub servers.

If you do not have Proficy Authentication and Configuration Hub installed, and you intend to use the Historian Web-based clients and view the Historian license information on Configuration Hub, you can install them while installing the Web-based clients.



Note:

Proficy Authentication is required for user authentication. It provides identity-based security for applications and APIs. It supports open standards for authentication and authorization, including Oauth2.

Register with Configuration Hub

By registering, you'll be able to work with Historian **web-based clients**, and you can also view Historian **license** information on Configuration Hub.

Use existing Proficy Authentication and Configuration Hub Instance

Proficy Authentication server name:

Proficy Authentication Public https Port:

Proficy Authentication Admin Client Id:

Proficy Authentication Admin Client Secret:

Configuration Hub server name:

Configuration Hub Public https port:

Test Connection Status: Test connection with Proficy Authentication and Configuration Hub is pending; click Test Connection

- Ensure to provide the highly privileged admin Client ID and Secret which was created while installing Proficy Authentication Server

Field	Description
Proficy Authentication server name	Enter the name of the machine on which the Proficy Authentication server is installed. If the machine uses a fully qualified domain name (FQDN), provide the FQDN. By default, the local hostname is considered.
Proficy Authentication Public https port	Enter the port number used by the Proficy Authentication service. The default value is 443. Ensure that this port number matches the one

Field	Description
	on the TCP Port Assignments page during Web-based Clients installation.
Proficy Authentication Admin Client Id	The client ID to connect to the Proficy Authentication service.
Proficy Authentication Admin Client Secret	The password to connect to the Proficy Authentication service.
Configuration Hub server name	The server name or the FQDN of the existing Configuration Hub server, as displayed in the address bar of the browser when you access Configuration Hub from the machine where Configuration Hub is installed.
Configuration Hub Public https port	The web server (https) port that you want to use for Configuration Hub. By default, it is 5000.
Test Connection	Option to test the status of the connection with external Proficy Authentication server.

**Note:**


If you change the Proficy Authentication server for Web-based Clients later, you must also change the Proficy Authentication server for the Historian server. This can be done using the Proficy Authentication Configuration Tool located at `<Install Drive>:\Program Files\Proficy\Proficy Historian\x64\Server` without the need to install the Historian server again. Alternatively, you can search for the Proficy Authentication Tool in the Windows search bar and open it.

9. Select **Next**.

The **Historian Security Groups** page appears.


Using Historian security groups provides an added layer of control over access to your Historian system.

By default, the option to create Historian security groups is not selected.



10. If you want the installer to create [Historian security groups \(on page 256\)](#), select the corresponding check box, and then select **Next**.


The **Choose the type of install you want to perform** page appears.



11. Select the type of the Historian server that you want to install, and then select **Next**.

- **Historian Single Server:** This is for a stand-alone Historian system, which contains only one Historian server. This type of system is suitable for a small-scale Historian setup.
- **Historian Mirror Primary Server:** This is for a horizontally scalable Historian system, which contains multiple Historian servers, all of which are connected to one another. Installing this server will allow you to add machines and distributed/mirror servers to this system.
- **Historian Distributed/Mirror Node:** This is for a horizontally scalable Historian system. Installing this server will allow you to add this node to a primary server.

The **Historian Server Certificate-based Security** page appears.



12. If you want to enable certificate-based security (MTLS-based security), leave the **Enable Certificate-based Security** check box selected, and then enter **Root Certificate Password**.

**Note:**

Ensure to use the same password to create MTLS (client) certificates. For more information on creating MTLS (client) certificates, refer to [Generate MTLS certificate](#).

For more information on certificate-based security, refer to [overview of the Certificate-based Security in Historian \(on page 206\)](#).

**Warning:**

If you do not select the **Enable Certificate-based Security** check box during the installation, you must generate the root certificates manually, as described in the [Manually Install Certificates for Historian](#) section. However, this is not recommended.

13. Select **Next**.

The **You are ready to install** page appears.

14. Select **Install**.

The installation begins.

15. After the installation, when you are asked to reboot your system, select **Yes**.

The Historian server is installed on your machine in the following folder: `<installation drive>:\Program Files\Proficy\Proficy Historian\x64\Server`, and the following registry path is created: `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services`.

In addition, the following components are installed:

- **The RemoteCollectorConfigurator utility:** A command-line tool, which allows you to manage collectors remotely. By default, it is located in the `C:\Program Files\GE Digital\NonWebCollectorInstantiationTool` folder. For instructions on using this utility, refer to About Installing and Managing Collectors Remotely.
- **The Proficy Authentication Configuration tool:** A utility that allows you to specify the Proficy Authentication server details to match with the Proficy Authentication server used by Web-based Clients. By default, it is located in the `C:\Program Files\Proficy\Proficy Historian\x64\Server` folder. For instructions on using this tool, refer to [Register with Configuration Hub \(on page 137\)](#).

Install Web-based Clients Using the Installer

1. [Install the Historian server \(on page 105\)](#). During the installation, in the **Register with Configuration Hub** page, select the **Use existing Proficy Authentication and Configuration Hub Instance** check box, and provide the Proficy Authentication server and Configuration Hub server details.



Note:


This step is needed only in the following cases:

- The Historian Server and the Web-based clients will be on two different machines.
- You already installed Proficy Authentication and Configuration Hub, and you want use the Historian Web-based clients and view the Historian license information on Configuration Hub.

If you do not select the **Use existing Proficy Authentication and Configuration Hub Instance** during the installation, to use the Historian Web-based clients and view the Historian license information on Configuration Hub, you must use the [Proficy Authentication Tool \(on page 137\)](#) to register with Proficy Authentication and Configuration Hub servers.



If you do not have Proficy Authentication and Configuration Hub installed, and you intend to use the Historian Web-based clients and view the Historian license information on Configuration Hub, you can install them while installing the Web-based clients.



2. If you want to use Web-based Clients in a cluster environment, ensure that your network is enabled for multicast traffic, and [set up high availability](#) on each node in the cluster.

This topic describes how to install Web-based Clients using a GUI-based installer.

You can also [install Web-based Clients using the command line](#).

During the installation, you can choose to use Web-based Clients in a cluster environment, thus ensuring high availability of connection to the Historian server using the client applications.

1. Run the `InstallLauncher.exe` file.
2. Select **Install Web-based Clients**.


The welcome page appears.

3. Select **Next**.

The license agreement appears.

4. Select the **Accept** check box, and then select **Next**.

The **TCP port assignments** page appears.




5. As needed, change the values for TCP port assignments as described in the following table, and then select **Next**.

Field	Description
Public https port	Port for https protocol communication used by Web-based Clients (through a fire-wall). The default value is 443. Ensure that this port number matches the one you specify while installing the Historian server. In addition: <ul style="list-style-type: none"> ◦ If you will install Operations Hub later on the same machine, the value that you provide in this field is populated while installing Operations Hub. ◦ If you have already installed Operations Hub on the same machine, this field is disabled and populated with the value you have provided while installing Operations Hub.

Field	Description
Proficy Authentication http port	Port for http protocol communication used by the Proficy Authentication service. The default value is 9480.
Proficy Authentication database port	Port for the Proficy Authentication database. The default value is 9432.
Historian http port	Port for the http protocol communication used by Web-based Clients. The default value is 8070.
Historian database port	Port for the PostgreSQL Historian database. The default value is 8432.

The **Fully Qualified Domain Name(s)** page appears.

- If you will install Operations Hub later on the same machine, the value that you provide in the **FQDNs** field is populated while installing Operations Hub.
- If you have already installed Operations Hub on the same machine, the **FQDNs** field is disabled and populated with the value you have provided while installing Operations Hub.



Fully Qualified Domain Name(s).

To allow users to access Historian web applications remotely using fully qualified domain names (FQDN), please list one or more here, separated by commas. Otherwise, you may leave this blank.

FQDNs:

Cancel Previous Next

6. In the **FDQNs** field, enter the fully qualified domain names, and then select **Next**.

This enables you to access Historian web applications remotely. You can use it to access the Web Admin console using alias names. Enter the values separated by commas.

To access the Web Admin console using any of the following URLs, enter

`Test.abc.ge.com,localhost,127.0.0.1,aliasName`

- [https:// Test.abc.ge.com /historian-visualization/hwa](https://Test.abc.ge.com/historian-visualization/hwa)
- [https:// 127.0.0.1 /historian-visualization/hwa](https://127.0.0.1/historian-visualization/hwa)
- [https:// aliasName /historian-visualization/hwa](https://aliasName/historian-visualization/hwa)
- [https:// localhost /historian-visualization/hwa](https://localhost/historian-visualization/hwa)

! **Important:**

- Do not enter a space between the values.
- You must add the IP address and alias name in the `hosts` file located at `C:\Windows\System32\drivers\etc`. The IP address that you add must be a static or fixed IP address.


Format: `<IP address> <alias name>`



Example: 1.2.3.4 myservername

- FQDN is not supported for Configuration Hub.

The **Cluster Configuration** page appears.



If, however, you are upgrading Web-based Clients, this page does not appear. In that case, skip the next step.


7. If you want high availability of Web-based Clients, select the **Cluster Node** check box, and enter values as described in the following table.

Field	Description
Historian Database Folder	Provide the database folder in the shared drive that you have created. The default value is C:\ProgramData\GE\OperationsHub. You <i>must</i> change this value.

Field	Description
Cluster FQDN	Enter the client access point of the role for which you have added the resources while setting up high availability (on page 182) .
Multicast Address	If needed, modify the common IP address that all the nodes in the cluster can use. Enter a value between 224.0.0.0 and 239.255.255.255 (or a hostname whose IP address falls in this range). The default value is 228.0.0.4.
Historian Cluster Membership Port	If needed, modify the common port number that all the nodes in the cluster can use. The default value is 45564. This port number, in conjunction with the multicast address, is used to create the cluster.
Historian Cluster Receiver Port	If needed, modify the multicast port number that you want to use for incoming Historian data. The default value is 4000.

8. Select **Next**.

The **Proficy Authentication** page appears, allowing you to choose whether you want to install Proficy Authentication along with Web-based Clients installation or use an existing Proficy Authentication.



Proficy Authentication

Use Existing Proficy Authentication:

Admin client Secret:

Re-enter Secret:

Note: The default Client ID is <admin>. As the admin Client is highly privileged, choose a strong secret and safekeep it.

Note: The username to login to Historian web-based clients is <[redacted].admin>. This is case-sensitive.

Cancel Previous Next

- If you want to install Proficy Authentication, clear the **Use Existing Proficy Authentication** check box. If you want to include Proficy Authentication in the cluster, you must install Proficy Authentication locally on each cluster node.
 - If you want to use an existing Proficy Authentication server, select the **Use Existing Proficy Authentication** check box. Proficy Authentication is detected if you installed it using a unified installer or Operations Hub, or if Historian uses Proficy Authentication installed remotely from an earlier version.
9. If you want to install Proficy Authentication, enter the **Admin client secret**, re-enter the secret, and then select **Next**.

The admin client secret must satisfy the following conditions:

- Must not contain only numbers.
- Must not begin or end with a special character.
- Must not contain curly braces.



Note:

The format of username for Historian Web-based Clients is <host name>.admin, where <host name> is the machine on which Web-based Clients are installed. And, the default client ID is admin. Both the host name and client ID are case-sensitive.

If, however, the Proficy Authentication server hostname is long, resulting in a username longer than 20 characters, Windows does not allow you to create the user. In that case, you can create a Proficy Authentication user, and then [create the corresponding Windows user](#), using the uaa_config_tool utility.

10. Alternatively, if you want to use an existing Proficy Authentication service (that is, a Proficy Authentication instance already installed by an external application such as Operations Hub):

a. Select the **Use Existing Proficy Authentication** check box.

The fields for the existing Proficy Authentication service appear.

b. Enter values as described in the following table.

Field	Description
Proficiency Authentication Base URL	Enter the URL of the external Proficiency Authentication server in the following format: <code>https://<Proficiency Authentication server name>:<port number></code> , where <i><Proficiency Authentication server name></i> is the FQDN or hostname of the machine on which Proficiency Authentication is installed. By default, the port number is 443. <div data-bbox="472 478 1419 611" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: Do not enter a trailing slash character. </div>
Admin Client ID	Enter the client name that you provided while installing the external Proficiency Authentication. The default value is admin.
Admin Client Secret	Enter the client secret that you provided while installing the external Proficiency Authentication.

c. Select **Test Connection**.

The results of the connection test appear. You cannot proceed until the connection is successful.

11. Select **Next**.

The **Configuration Hub Installation** page appears, allowing you to choose whether you want to install Configuration Hub along with Web-based Clients or use an existing Configuration Hub.

Configuration Hub Installation

Use Existing Configuration Hub:

Install Location: Browse

Plugin-Name:

Server Port:

Container Port:

ConfigHub Admin Port:

Client ID:

Client Secret:

Re-enter Secret:

Note: Credentials used here are needed for registering other products with this Configuration Hub. Make sure to save these credentials for future registrations and upgrades to Configuration Hub.

Configuration Hub allows you to add and manage a collector instance remotely. For more information, refer to [About Configuration Hub](#).

If, however, an earlier version of Configuration Hub is available on the same machine, you will be prompted to enter the details of the existing Configuration Hub, and it will be upgraded to the latest version. If that happens, skip the next step.



Important:

By default, Configuration Hub points to the same Proficy Authentication server as the one you provided during the Historian server installation. If you want to install Web-based Clients in a cluster environment, ensure that:

- Configuration Hub does not use the same Proficy Authentication server as that used by the cluster.
- The Proficy Authentication and Configuration Hub details must be the same for all cluster nodes.

12. If you want to install Configuration Hub, ensure that the **Use Existing Configuration Hub** check box is cleared, and then provide values as described in the following table.

Field	Description
Install Location	If needed, modify the installation folder for Configuration Hub.
Plugin Name	If needed, modify the name of the Configuration Hub plugin for Historian. The default value is in the following format: Historian_<host name>. If, however, you are installing Web-based Clients in a cluster environment, the default value is Historian_<cluster name>. You can modify this value, but provide the same value for all the nodes in the cluster.
Server Port	If needed, modify the port number that you want to use for the web server. The default value is 5000. If you want to install Web-based Clients in a cluster environment, provide the same value for all the nodes in the cluster.
Container Port	If needed, modify the port number for the Configuration Hub container. The default value is 4890.
ConfigHub Admin Port	This is the port number of the Configuration Hub admin. The default value is 4890. If needed, you can change the port number.
Client ID	<p>Enter the username to connect to Configuration Hub. The default value is admin. The value that you enter can contain:</p> <ul style="list-style-type: none"> ◦ All English alphanumeric characters (ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghijklmnopqrstuvwxyz_0123456789) ◦ The following special characters: ><:~!@#\$\$%^&*?

Field	Description
Client Secret	Enter the password to connect to Configuration Hub. The value that you enter can contain: <ul style="list-style-type: none"> ◦ Must contain at least eight characters. ◦ All English alphanumeric characters (ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghijklmnopqrstuvwxyz_0123456789) ◦ The following special characters: ><:~!@#%&*?
Re-enter Secret	Re-enter the password to connect to Configuration Hub.

13. Alternatively, if you want to use an existing Configuration Hub:

- a. Select the **Use Existing Configuration Hub** check box. This check box is disabled if an existing Configuration Hub is detected.

The fields for the existing Configuration Hub appear.

Configuration Hub Installation

Use Existing Configuration Hub:

Plugin-Name:

Server Name:

Server Port:

Client ID:

Client Secret:

[Test Connection](#)

Test Connection Status: Test connection with Existing Configuration Hub Server is pending; click [Test Connection](#)

Enter the Client ID and Secret that you provided while installing Configuration Hug plugin for Historian to register with existing Configuration Hub.

[Cancel](#) [Previous](#) [Next](#)

b. Provide values as described in the following table.


Field	Description
Plugin Name	If needed, modify the name of the Configuration Hub plugin for Historian. The default value is in the following format: Historian_<host name>
Server Name	Enter the server name or the FQDN of the existing Configuration Hub server, as displayed in the address bar of the browser when you access Configuration Hub from the machine where Configuration Hub is installed.
Server Port	If needed, modify the port number that you want to use for the web server. The default value is 5000.
Client ID	If needed, modify the username to connect to Configuration Hub. The default value is admin.
Client Secret	Enter the password to connect to Configuration Hub.

c. Select **Test Connection**.


The results of the connection test appear. You cannot proceed until the connection is successful.

14. Select **Next**.


The default installation drive appears.



15. If needed, change the installation drive for Web-based Clients, and then select **Next**.
The log files location page appears.



16. If needed, change the location for log files, and then select **Next**.
The destination Historian server page appears.



17. Provide the name of the destination Historian server to which Web-based Clients are connected by default. When you login to Configuration Hub, the default system will point to this server.



Note:

- Provide the name of either Historian single-server or mirror primary server because the systems in Configuration Hub will be either a stand-alone system or a horizontally scalable system.
- If you want to connect to a remote Historian server, you must disable the **Enforce Strict Client Authentication** and **Enforce Strict Collector Authentication** options using Historian Administrator in the remote server.

18. Select **Next**.

The **You are ready to install** page appears.

19. Select **Install**.

The Web-based Clients installation begins.

20. When you are prompted to reboot your machine, select **Yes**.

Historian Web-based Clients are installed in the following folder: *<installation drive>*:\Program Files\GE, and the following registry paths are created:

- HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital
- HKEY_LOCAL_MACHINE\SOFTWARE\GE

If you want to use Configuration Hub installed using other products such as iFIX, Plant Applications, and so on, [set up authentication](#) to point to the Proficy Authentication instance.

Install Collectors Using the Installer


After you install collectors, the following artefacts will be available:

- **Executable files:** These files are required to add a collector instance.
- **Instances of the following collectors:**
 - The iFIX collector
 - The iFIX Alarms & Events collector
 - The OPC Classic Data Access collector for CIMPLICITY
 - The OPC Classic Alarms and Events collector for CIMPLICITY


These instances will be created only if iFIX and/or CIMPLICITY are installed on the same machine as the collectors.

- **The Remote Collector Management agent:** Provides the ability to manage collectors remotely.

1. Run the `InstallLauncher.exe` file.
2. Select **Install Collectors**.
The welcome page appears.
3. Select **Next**.
The license agreement appears.
4. Select the **Accept** check box, and then select **Next**.
The default installation drive appears.



5. If needed, modify the installation drive, and then select **Next**.
The data directory page appears.



6. If needed, change the folder for storing the collector log files, and then select **Next**.
The destination Historian server page appears.

Historian Server Details

Provide a valid windows user of the default Historian server to which the Remote Collector Manager will connect.

Historian Server:

User Name:

Password:

Confirm Password:

Note: If you have created security groups or enabled strict client/collector authentication, provide the destination Historian credentials.
If the password changes, you must reinstall Remote Management Agents to reset the password.

Cancel Previous Next

7. Provide the credentials of the Windows user account of the destination Historian server to which you want Remote Management Agent to connect.

These details are required for Remote Collector Manager to connect to Historian to manage the collectors remotely. If you are installing collectors on same machine as the Historian server, and if strict collector authentication is disabled, you need not provide these details; by default, the machine name of the local Historian server is considered. If, however, they are installed on different machines, or if strict collector authentication is enabled, you must provide the credentials of the Historian server user.

8. Select **Next**.

The **You are ready to install** page appears.

9. Select **Install**.

The installation begins.

10. When you are prompted to reboot your system, select **Yes**.

The collector executable files are installed in the following folder: *<installation drive>*:\Program Files (x86)\GE Digital*<collector name>*. The iFIX collectors are installed in the following folder: C:\Program Files\GE\iFIX. The following registry paths are created:

- HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\ GE Digital\iHistorian\Services*<collector type>*
- HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\iHistorian\Services*<collector type>*

In addition, if iFIX and/or CIMPLICITY are installed on the same machine as the collectors, instances of the following collectors are created:

- The iFIX collector
- The iFIX Alarms & Events collector
- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

Perform Post-Installation Tasks

1. If you do not want strict authentication, disable the **Enforce Strict Client Authentication** and **Enforce Strict Collector Authentication** options under Historian Administrator > **Data Stores > Security**.
2. While installing the Historian server, if you have allowed the installer to create Historian security groups, create a local Windows user with the format *<Web-based Clients server name>.admin*, and [add the user to the ihSecurity Admins group](#). This user will log in to Web-based Clients. Alternatively, you can create Proficy Authentication users in an external Proficy Authentication and map their security groups. For information, refer to [About Proficy Authentication Groups](#).

Depending on whether the Historian server will use local or domain security groups, select the appropriate option in [Historian Administrator](#).

3. Ensure that the Windows user that you have specified while installing collectors is added to the iH Security Admins and iH Collector Admins groups.
4. [Enable trust for a client certificate for Configuration Hub](#).
5. [Enable trust for a self-signed certificate on Chrome](#).
6. [Import an issuer certificate](#).

You are now ready to use Configuration Hub.

[Access Configuration Hub \(on page 336\)](#).

Upgrade Configuration Hub

If you install Web-based Clients before uninstalling the previous version, you cannot modify the Configuration Hub credentials. If an earlier version of Configuration Hub is available on the same machine, you will be allowed to use the same; you cannot install Configuration Hub again.

1. Uninstall Configuration Hub.
2. [Set up Configuration Hub \(on page 305\)](#).

Access Configuration Hub

Perform the tasks outlined in [About Setting up Configuration Hub \(on page 305\)](#).

1. Double-click the Configuration Hub icon on your desktop ().
The Configuration Hub login page appears.
2. Depending on whether you want to use Proficy Authentication or custom authentication, select the appropriate tab. If custom authentication is not applicable, skip this step.

**Note:**

For instructions on setting up authentication, refer to https://www.ge.com/digital/documentation/confighub/version2024/t_authentication_setup.html


3. Select the Configuration Hub node that you want to access, and then select **Continue to Login**.
The Proficy Authentication login page appears.
If you cannot access the login page, start the GE Operations Hub Httpd Reverse Proxy and the Data Archiver services.
4. Log in with your credentials.

**Note:**


By default, the username is `<host name>.admin`, and the password is the value that you have entered in the **Admin client secret** field on the **Proficy Authentication Service** page during Web-based Clients installation.

The Configuration Hub application appears, displaying the following sections:

- **The Navigation section:** Contains a list of systems that you have added. In addition, it helps you navigate to the Model, Collectors, and Tags sections. You can also [access Proficy Authentication](#) to create users and groups.



- **The main section:** Displays content based on your selection in the **NAVIGATION** section. For example, if you select a Historian system, you can access a list of servers in the system. You can also navigate to the system statistics as shown in the following image.



Similarly, if you select **Model** in the **NAVIGATION** section, you can access the Historian model.

- **The Details section:** Contains the details of the item selected in the main section. For example, If you select a system, you can view the description of the system, and add data stores and mirror locations using the **Details** section.

DETAILS		
<p> <i>Search</i></p>		
<p>▼ General Properties</p>		
Name	ctorcollector...	
System Type	Horizontally S...	
Primary Server	oriz-collectors...	
Description	oriz-collectors...	
Default System	Yes	
Collectors	10	
Tags	1	
Data Stores	3	
Clients	3	
<p>▼ System Defaults</p>		
Default Locati...	oriz-collec...	
Default Data S...	User	
<p>▼ Alarms and Events</p>		
Alarm Rate	0 (Alarms/min)	
<p>▼ License</p>		
Historian Tags	1 (214748364...	
Scada Tags	0 (2500 Licens...	
Users	1 (1000 Licens...	
Data Stores	3 (200 License...	
Calculations	Enabled	

Depending on your requirements, set up a stand-alone system or a horizontally scalable system.

Historian Plugin Management in Configuration Hub

About Historian Plugin Management in Configuration Hub

The Historian plugin in Configuration Hub enables you to perform several tasks like monitor, supervise, retrieve, and control gathering functions from a server, client, or one or more remote nodes. However, it operates as a web-based application.

When you install the Historian server and web-based clients, the Configuration Hub application is installed along with Proficy Authentication. Additionally, the Historian node and plugin are automatically registered with the Proficy Authentication and Configuration Hub based on the Historian HTTP and database port numbers.


After installing the Historian Server and the Web-based clients, if you access the Configuration Hub, you can see the Historian plugin displayed in the **NAVIGATION** pane. Also, the Historian node and the plugin can be seen in the **Administration** plugin > **Node Manager**.



Note:

However, if during installation, the Historian node did not properly register with the Proficy Authentication and Configuration Hub, and did not appear in the Node Manager, you can [add a Historian node \(on page 344\)](#) on Configuration Hub using the Node Manager.


The Node Manger consolidates control over product and license details, and you can view the corresponding Historian node's certificate, and license details. Using the Node Manager, if needed, you can [modify a plugin display name \(on page 347\)](#), [unregister a plugin \(on page 350\)](#), and if you want to register it at a later stage, you can [register the plugin \(on page 348\)](#) again.



View Historian Node Details


Using the Historian node, you can view the Historian node-specific certificate and license details, and also plugin-specific details.

1. Double-click the Configuration Hub icon on your desktop ()
The Configuration Hub login page appears.




2. Login with the default user credentials. That is, <hostname>.admin.

- The Configuration Hub application appears, listing the Historian plugin in the **NAVIGATION** pane.
- In the **NAVIGATION** pane, select and expand **Administration**, and then select **Node Manager**. The Node Manager administration page appears, listing the available Historian node and the plugin.
 - To view the Historian node-specific license details, select the node. The node-specific details appear in the right-side section. Also, the license details are displayed in the **License Expiry** and **Status** columns.



- To view the plugin-specific details, expand the node and select the plugin. The plugin-specific details appear in the right-side section.




If you have the needed permission, you can perform additional certificate and node management tasks. For more information, refer to **Administration Plugin** in the [Configuration Hub help](#).


Add a Historian Node (Optional)

The steps listed in this topic are only needed if the Historian node was not properly configured during the installation and is not being displayed in the Node Manager.


1. Double-click the Configuration Hub icon on your desktop ()
The Configuration Hub login page appears.




2. Login with the default user credentials. That is <hostname>.admin.
The configuration hub application appears, listing the Historian plugin in the **NAVIGATION** pane.




3. In the **NAVIGATION** pane, select and expand **Administration**, and then select **Node Manager**.



The node manager administration page appears.



- In the upper-right corner, select **+**.
The **Add Node Manager** window appears.



Add Node Manager ✕


HOST NAME

DISPLAY NAME

PORT NUMBER ?
  [Not Trusted](#)

5. Enter the **HOST NAME**. Here, it is the Historian node host name in a fully qualified domain name format. For example, testmachine123.testdomain.com.
6. Enter the **DISPLAY NAME** for the Historian node.
7. Enter the **PORT NUMBER** of the host that you entered.
8. You must trust the node manager certificate. To trust the certificate, select **Not Trusted**.
The **Certificate Details** window appears, listing the certificate information.
9. Read the certificate details and if you trust, select **Trust**.
In the **Add Node Manager** window, the certificate status changes to trusted.
10. Select **Test Connection**.
If the connection is successful, a success message appears. If not, check the host name and the port are correct.
11. Select **Add**.
The Historian node along with the plugin are added.


By default, the plugin gets registered.



In rare cases, for some reason, if the plugin is not registered, you can [register the plugin \(on page 348\)](#).


Modify a Historian Plugin Display Name

1. Double-click the Configuration Hub icon on your desktop ().
- The Configuration Hub login page appears.



2. Login with the default user credentials. That is <hostname>.admin.
The configuration hub application appears, listing the Historian plugin in the **NAVIGATION** section.
3. In the **NAVIGATION** pane, select and expand **Administration**, and then select **Node Manager**.
The Node Manager administration page appears, listing the available Historian node and the plugin.
4. Select and right-click the node, and then select **Manage**.

The **Manage Plug-ins** window appears.



5. Change the plugin display name and select **Update**.


The changes you made are updated and applied to the plugin.

Register a Historian Plugin

If you had unregistered a plugin and want to register it again, or if, for some reason, the plugin was not registered after installation, you can register the plugin using the Node Manager, provided that you have the Historian node in the Node Manager. If the Historian node did not register properly, you must first [add a Historian node \(on page 344\)](#) and then register the Historian node and its plugin.

1. Double-click the Configuration Hub icon on your desktop ()

The Configuration Hub login page appears.




2. Login with the default user credentials. That is <hostname>.admin.

The configuration hub application appears, listing the Historian plugin in the **NAVIGATION** section.

3. In the **NAVIGATION** pane, select and expand **Administration**, and then select **Node Manager**.

The Node Manager administration page appears, listing the available Historian node and the plugin.



4. Select and right-click the plugin, and then select **Register**.

Alternatively, you can select and right-click the node, and then select **Manage**.

You can register the plugin using the **Register** button available in the **Manage Plug-ins** window.

The **Register Plug-in** window appears.

5. Enter the values as described in the following table:

Field	Description
PLUGIN HOST	The host name of the plugin in a fully qualified domain name format.
PRODUCT TYPE	The product type for the plugin. For example, Historian.
DISPLAY NAME	The plugin name that you want to see below the Node Manager.

6. Select **Register**.

The plugin gets registered and added in the **NAVIGATION** pane.


7. For the plugin to work, you must refresh the browser or log out and log in again to restart Configuration Hub.

8. Now try accessing the plugin.

Unregister a Historian Plugin


If you need to unregister a plugin, you can do that using the Node Manager.

1. Double-click the Configuration Hub icon on your desktop ().
The Configuration Hub login page appears.



The login page features the GE Vernova logo at the top left. Below the logo, the text "Welcome!" is centered. There are two input fields: "User Identifier" and "Password". Below these fields is a blue "SIGN IN" button. At the bottom, there is a faint "Forgot your password?" link.


2. Login with the default user credentials. That is <hostname>.admin.
The configuration hub application appears, listing the Historian plugin in the **NAVIGATION** pane.
3. In the **NAVIGATION** pane, select and expand **Administration**, and then select **Node Manager**.
The node manager administration page appears.



The screenshot shows the Node Manager Administration page. The left sidebar (NAVIGATION) is expanded to show "Administration" > "Node Manager". The main content area displays a table of installed plugins. The "Historian" plugin is highlighted with a red box, and its "Unregister" button is visible.

Display Name	Product Type	License Expiry	Status
Configuration Hub	Configuration Hub		
Proficy Authentication	Proficy Authentication		
Historian_Node	Node Manager		
Historian_...	HISTORIAN	Registered	Unregister

4. Select and right-click the plugin, and then select **Unregister**.
Alternatively, you can select and right-click the node, and then select **Manage**.
The **Manage Plug-ins** window appears, listing all the available plugins.



5. Select the plugin as needed.



6. Select **Unregister**.



The plugin gets unregistered.



Alternatively, you can also unregister a plugin from the Plugin **DETAILS** section by selecting **X** on the top-left corner in the **PLUG-IN** section.

This will prompt you whether to delete the plugin. Selecting **Continue** will unregister the plugin.

Common Tasks in Configuration Hub

Task	Procedure
<p>Show or hide the Navigation or the Details section.</p>	<ol style="list-style-type: none"> In the upper-right corner of the page, select . Select the check boxes for the sections that you want to show. 
<p>Show or hide columns in a table.</p> <div data-bbox="203 955 592 1218" style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: You cannot hide some of the columns (for example, the COLLECTOR NAME column).</p> </div>	<ol style="list-style-type: none"> In the upper-right corner of the table, select .  <p>The Table Settings window appears.</p> <ol style="list-style-type: none"> Select the check boxes in the SHOW COLUMN column, and then select Apply.

Task	Procedure
<p>Reorder columns in a table.</p> <div data-bbox="203 342 594 520" style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: You cannot reorder some of the columns.</p> </div>	<p>1. In the upper-right corner of the table, select .</p> <div data-bbox="690 342 1421 766" style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;">  </div> <p>The Table Settings window appears.</p> <p>2. Use the arrow buttons in the RE-ORDER column, and then select Apply.</p>
<p>Refresh a page/table.</p>	<p>In the upper-right corner of the main section or a table, select .</p> <div data-bbox="609 1050 1421 1522" style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;">  </div>

Task	Procedure
<p>Select multiple tags or clear the selection.</p>	<ul style="list-style-type: none"> To select multiple tags, select the check boxes corresponding to the tags as needed. <p>Alternatively, to select all the available tags, select the check box in the upper-left corner of table header.</p> 
<p>Navigate through grids in a page</p>	<p>When there are more than 100 rows in a grid, page numbers are enabled at the bottom-right corner. You can use these page numbers to navigate through the grid and access other available rows.</p>  <p>In addition to this, you can also see a grid's count (both total and selected).</p>

Setting up a Stand-Alone System

About Setting up a Stand-Alone Historian System

In a stand-alone Historian system, there is only one Historian server. This type of system is suitable for a small-scale Historian setup.

To set up a stand-alone Historian system, you must first [set up Configuration Hub \(on page 305\)](#).

Components of a Historian System: In a Historian system, the following components are used. This list is not comprehensive. For a complete list, refer to [System Components \(on page 73\)](#).

- **The Historian server:** You must install a single-server Historian, and [apply the license \(on page 82\)](#).
- **A Historian system:** A Historian system is a network of Historian servers that collect, store, and retrieve data related to tags, alarms, and events.

By default, a system is created when you set up Configuration Hub.

- **A data store:** A data store is a logical collection of tags used to store, organize, and manage tags according to your requirements. The primary use of data stores is segregating tags by data collection intervals. For example, you can put name plate or static tags (where the value rarely changes) in one data store, and put process tags in another data store. This can improve the query performance.

By default, a user data store is created when you set up Configuration Hub. You can add more as needed.

- **A collector instance:** Collectors are the applications that collect data from a data source, and send it to an on-premises Historian server or a cloud destination such as Predix Time Series and Azure IoT hub.

You must [add a collector instance \(on page 357\)](#) to begin collecting data. You can choose the type of the collector depending on your need. You can use any existing instances (created during collector installation or ported during an upgrade).

- **Tags:** Tags are the parameters for which you want to store data (for example, temperature, pressure, torque).

You must [specify the tags \(on page 357\)](#) for which you want to collect data.

- **Data archiver:** This is a service that indexes all the data by tag name and timestamp, and stores the result in an .iha file.

By default, this is installed when you install the Historian server.

- **Clients:** These are applications that retrieve data from the archive files using the Historian API.

By default, these are installed when you set up Configuration Hub.

Add a Collector Instance

Before you begin using a collector, you must add an instance of the collector. You can add multiple instances of the same collector or instances of multiple collectors. To add multiple instances of a collector, perform the steps once again.

You can add and configure the following types of collector instances:

- [The Calculation collector \(on page 479\)](#)
- [The CygNet collector \(on page 482\)](#)
- [The File collector \(on page 486\)](#)
- [The HAB collector \(on page 489\)](#)
- [The iFIX collector \(on page 505\)](#)
- [The MQTT collector \(on page 510\)](#)
- [The MQTT Sparkplug B collector \(on page 519\)](#)
- [The ODBC collector \(on page 527\)](#)
- [The OPC Classic Alarms and Events collector \(on page 532\)](#)
- [The OPC Classic DA collector \(on page 534\)](#)
- [The OPC Classic HDA collector \(on page 540\)](#)
- [The OPC UA DA collector \(on page 544\)](#)
- [The OSI PI collector \(on page 549\)](#)
- [The OSI PI distributor \(on page 553\)](#)
- [The Server-to-Server collector \(on page 559\)](#)
- [The Server-to-Server distributor \(on page 563\)](#)
- [The Simulation collector \(on page 567\)](#)
- [The Windows Performance collector \(on page 571\)](#)
- [The Wonderware collector \(on page 575\)](#)


Add Tags for the Data Store Using Configuration Hub

- [Add the collector instance \(on page 357\)](#) using which you want to collect data. Ensure that the collector is running.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, [create it \(on page 370\)](#).

This topic describes how to specify the tags for which you want to collect data by browsing through the tags in the data source. For example, for an iFIX collector, if there are 1,00,000 tags in the iFIX server, you must specify the ones for which you want to collect data. Only then data is collected for those tags.

In addition to adding tags from the data source, you can [create tags manually \(on page 473\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **+**.



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. A value is required.
COLLECTED TYPE	Specify whether you want to browse through all the tags in the data source or only from the tags that you have not added yet. A value is required.
SOURCE TAG NAME	Enter the name of the tag (either completely or partially) to narrow down the search results.
SOURCE TAG DESCRIPTION	Enter the description of the tag (either completely or partially) to narrow down the search results.

5. Select **Search Tags**.
A list of tags that match *all* the criteria that you have specified appears. If a tag is already added, it is disabled.
6. Select the check box corresponding to each tag for which you want to collect data.

Add Tags from Collector
 Add Manually

COLLECTOR NAME*
 COLLECTED TYPE*
 SOURCE TAG NAME
 SOURCE TAG DESCRIPTION

SEARCH RESULTS FOR SOURCE TAGS NAMES

<input type="checkbox"/>	TAG NAME	DESCRIPTION
	<i>Filter</i>	<i>Filter</i>
<input type="checkbox"/>	Simulation.Simulation00001	Simulation.Simulation00001
<input type="checkbox"/>	Simulation.Simulation00002	Simulation.Simulation00002
<input type="checkbox"/>	Simulation.Simulation00003	Simulation.Simulation00003
<input type="checkbox"/>	Simulation.Simulation00004	Simulation.Simulation00004
<input type="checkbox"/>	Simulation.Simulation00005	Simulation.Simulation00005
<input type="checkbox"/>	Simulation.Simulation00006	Simulation.Simulation00006
<input type="checkbox"/>	Simulation.Simulation00007	Simulation.Simulation00007
<input type="checkbox"/>	Simulation.Simulation00008	Simulation.Simulation00008
<input type="checkbox"/>	Simulation.Simulation00009	Simulation.Simulation00009
<input type="checkbox"/>	Simulation.Simulation00010	Simulation.Simulation00010
<input type="checkbox"/>	Simulation.Simulation00011	Simulation.Simulation00011
<input type="checkbox"/>	Simulation.Simulation00012	Simulation.Simulation00012

DATASTORE*

7. In the **DATA STORE** field, if you want to store the data in a different data store than the user data store, select the same.

8. Select **Add Tag**.

Data collection begins for the selected tags.

As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.

Setting up a Horizontally Scalable System

About Setting up a Horizontally Scalable System

In a horizontally scalable Historian system, there are multiple Historian servers, all of which are connected to one another. This type of system is used to scale out the system horizontally. For example, if you have 5,00,000 tags in your Historian system, you can distribute them among the various servers to improve performance.

To set up a horizontally scalable system, you must first [set up Configuration Hub \(on page 305\)](#).

Components of a Historian System: In a Historian system, the following components are used. This list is not comprehensive. For a complete list, refer to [System Components \(on page 73\)](#).

- **The Historian servers:** You must install the following types of Historian servers:
 - **Primary:** A primary server is the only server in a system where the Configuration Manager service runs. For the entire system, Configuration Manager manages the system configuration licensed by the user (that is, the number of tags, options, and so on). Each system can have only one primary server.

You must [apply the Enterprise license \(on page 82\)](#) to the primary server.

- **Distributed/Mirror:** These servers collect and store data. If added to a mirror group/location, you can [achieve high availability \(on page 367\)](#).

You must [apply the Distributed license \(on page 82\)](#) to the distributed/mirror servers.

- **A Historian system:** A Historian system is a network of Historian servers that collect, store, and retrieve data related to tags, alarms, and events.

By default, a system is created when you set up Configuration Hub.

- **Data stores:** A data store is a logical collection of tags used to store, organize, and manage tags according to your requirements. The primary use of data stores is segregating tags by data collection intervals. For example, you can put name plate or static tags (where the value rarely changes) in one data store, and put process tags in another data store. This can improve the query performance.

By default, a user data store is created when you set up Configuration Hub. You can add more as needed.

- **Locations:** These are virtual entities in which data stores are created. They are used for storage. The following types of locations are used in a horizontally scalable system:
 - **Distributed location:** This location is created automatically when you install a Historian mirror primary server, or when you install a Historian distributed/mirror node and add it to the primary server. You cannot modify or delete this location, and you cannot create another one.
 - **Mirror location:** This location is used to replicate data collected in a data store. For more information, refer to [About Data Mirroring \(on page 367\)](#).
- **A collector instance:** Collectors are the applications that collect data from a data source, and send it to an on-premises Historian server or a cloud destination such as Predix Time Series and Azure IoT hub.

You must [add a collector instance \(on page 357\)](#) to begin collecting data. You can choose the type of the collector depending on your need. You can use any existing instances (created during collector installation or ported during an upgrade).

- **Tags:** Tags are the parameters for which you want to store data (for example, temperature, pressure, torque).

You must [specify the tags \(on page 357\)](#) for which you want to collect data.

- **Data archiver:** This is a service that indexes all the data by tag name and timestamp, and stores the result in an .iha file.

By default, this is installed when you install the Historian server.

- **Clients:** These are applications that retrieve data from the archive files using the Historian API.

By default, these are installed when you set up Configuration Hub.

Add a Distributed/Mirror Server

1. [Install Historian server \(on page 105\)](#) on the machine that you want to add as a distributed server.
2. [Add a system \(on page 427\)](#). The server that you specify while adding the system serves as the primary server for the system.

If you want to create a horizontally scalable Historian system, you must first add a primary server, and then add one or more distributed/mirror machines to scale out the primary server horizontally and thus, improve performance.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
3. Expand the system in which you want to add a distributed/mirror server.
A list of servers in the system appears.
4. Select **+**.

System	Historian Server																														
Filter	Filter																														
<div style="border: 1px solid #0070c0; padding: 5px;"> <div style="display: flex; justify-content: space-between; align-items: center;"> SERVERS + ⚙ </div> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th>Machine Name</th> <th>STATUS</th> <th>Archive Compre...</th> <th>Write Cache Hit ...</th> <th>CONSUMPTION R...</th> <th>Read Thread Usa...</th> <th>Write Thread Us...</th> <th>Out Of</th> </tr> </thead> <tbody> <tr> <td>██████████</td> <td style="color: green;">✔ Connected</td> <td>43.3</td> <td>0.5</td> <td>0.45</td> <td>0</td> <td>0</td> <td>0</td> </tr> <tr> <td>██████████</td> <td style="color: red;">✘ Not Connected</td> <td>NA</td> <td>NA</td> <td>NA</td> <td>NA</td> <td>NA</td> <td>NA</td> </tr> </tbody> </table> </div>								Machine Name	STATUS	Archive Compre...	Write Cache Hit ...	CONSUMPTION R...	Read Thread Usa...	Write Thread Us...	Out Of	██████████	✔ Connected	43.3	0.5	0.45	0	0	0	██████████	✘ Not Connected	NA	NA	NA	NA	NA	NA
Machine Name	STATUS	Archive Compre...	Write Cache Hit ...	CONSUMPTION R...	Read Thread Usa...	Write Thread Us...	Out Of																								
██████████	✔ Connected	43.3	0.5	0.45	0	0	0																								
██████████	✘ Not Connected	NA	NA	NA	NA	NA	NA																								

The **Add Server Machine: <system name>** window appears.

5. Enter the host name or IP address of the machine that you want to add, and then select **Add**.
The distributed server is added to the system. A distributed location is added in the server. You cannot modify or delete this location.
- If you want high availability of one or more data stores in the server, [create a mirror location \(on page 368\)](#), and then [add the data stores \(on page 370\)](#). If not, [add the data store \(on page 370\)](#) to the distributed location.
 - If you want to set a distributed node as backup to the primary node, [set a distributed node as backup \(on page 365\)](#).

Add a Collector Instance

Before you begin using a collector, you must add an instance of the collector. You can add multiple instances of the same collector or instances of multiple collectors. To add multiple instances of a collector, perform the steps once again.

You can add and configure the following types of collector instances:

- [The Calculation collector \(on page 479\)](#)
- [The CygNet collector \(on page 482\)](#)
- [The File collector \(on page 486\)](#)
- [The HAB collector \(on page 489\)](#)
- [The iFIX collector \(on page 505\)](#)
- [The MQTT collector \(on page 510\)](#)
- [The MQTT Sparkplug B collector \(on page 519\)](#)
- [The ODBC collector \(on page 527\)](#)
- [The OPC Classic Alarms and Events collector \(on page 532\)](#)
- [The OPC Classic DA collector \(on page 534\)](#)
- [The OPC Classic HDA collector \(on page 540\)](#)
- [The OPC UA DA collector \(on page 544\)](#)
- [The OSI PI collector \(on page 549\)](#)
- [The OSI PI distributor \(on page 553\)](#)
- [The Server-to-Server collector \(on page 559\)](#)
- [The Server-to-Server distributor \(on page 563\)](#)
- [The Simulation collector \(on page 567\)](#)
- [The Windows Performance collector \(on page 571\)](#)
- [The Wonderware collector \(on page 575\)](#)


Add Tags for the Data Store Using Configuration Hub

- Add the collector instance (on page 357) using which you want to collect data. Ensure that the collector is running.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, create it (on page 370).

This topic describes how to specify the tags for which you want to collect data by browsing through the tags in the data source. For example, for an iFIX collector, if there are 1,00,000 tags in the iFIX server, you must specify the ones for which you want to collect data. Only then data is collected for those tags.

In addition to adding tags from the data source, you can create tags manually (on page 473).

1. Access Configuration Hub (on page 336).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **+**.



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. A value is required.
COLLECTED TYPE	Specify whether you want to browse through all the tags in the data source or only from the tags that you have not added yet. A value is required.

Field	Description
SOURCE TAG NAME	Enter the name of the tag (either completely or partially) to narrow down the search results.
SOURCE TAG DESCRIPTION	Enter the description of the tag (either completely or partially) to narrow down the search results.

5. Select **Search Tags**.

A list of tags that match *all* the criteria that you have specified appears. If a tag is already added, it is disabled.

6. Select the check box corresponding to each tag for which you want to collect data.

Add Tags from Collector Add Manually

COLLECTOR NAME* COLLECTED TYPE* SOURCE TAG NAME SOURCE TAG DESCRIPTION

[Redacted]_Simulation All Source Tags * *

[Search Tags](#)

SEARCH RESULTS FOR SOURCE TAGS NAMES

<input type="checkbox"/>	TAG NAME	DESCRIPTION
	<i>Filter</i>	<i>Filter</i>
<input type="checkbox"/>	[Redacted] Simulation.Simulation00001	[Redacted] Simulation.Simulation00001
<input type="checkbox"/>	[Redacted] Simulation.Simulation00002	[Redacted] Simulation.Simulation00002
<input type="checkbox"/>	[Redacted] Simulation.Simulation00003	[Redacted] Simulation.Simulation00003
<input type="checkbox"/>	[Redacted] Simulation.Simulation00004	[Redacted] Simulation.Simulation00004
<input type="checkbox"/>	[Redacted] Simulation.Simulation00005	[Redacted] Simulation.Simulation00005
<input type="checkbox"/>	[Redacted] Simulation.Simulation00006	[Redacted] Simulation.Simulation00006
<input type="checkbox"/>	[Redacted] Simulation.Simulation00007	[Redacted] Simulation.Simulation00007
<input type="checkbox"/>	[Redacted] Simulation.Simulation00008	[Redacted] Simulation.Simulation00008
<input type="checkbox"/>	[Redacted] Simulation.Simulation00009	[Redacted] Simulation.Simulation00009
<input type="checkbox"/>	[Redacted] Simulation.Simulation00010	[Redacted] Simulation.Simulation00010
<input type="checkbox"/>	[Redacted] Simulation.Simulation00011	[Redacted] Simulation.Simulation00011
<input type="checkbox"/>	[Redacted] Simulation.Simulation00012	[Redacted] Simulation.Simulation00012

DATASTORE*
User

7. In the **DATA STORE** field, if you want to store the data in a different data store than the user data store, select the same.

8. Select **Add Tag**.


Data collection begins for the selected tags.

As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.

Browse Tags using Distributed or Mirror Node Servers when Primary Server is Inactive


In a horizontally scaled system, there can be multiple Historian servers that are connected to one another. That is, if there are 100000 tags in your system, you can distribute them among the various servers. Similarly, you can view the tags and their values in all the servers.

For example, consider the following setup:



In general, the Historian configuration manager of the primary node stores the tag information of all the data stores in the system. Whenever a client machine requests tag information, the Historian configuration manager sends the corresponding information for all nodes (primary, distributed 1, and distributed 2) to the client machine through the client manager. Suppose the central configuration manager is inactive, in that case, the client manager of the primary node sends the tag information corresponding to the primary node (data store 1) to the client machine. Consequently, the tag information of the other nodes will not be sent to the client machine.

To overcome this, you can assign the other nodes as backups for the primary node's central configuration manager. Therefore, whenever the central configuration manager is inactive, the Data Archiver (DA) of the backup node functions as a configuration manager and sends all tag information to the client manager. The client manager will then forward the tag information response to the client machine. With this, you can still browse tags and their details when the primary node's configuration manager is inactive.



This topic describes how to set a distributed node as a backup node for the primary node.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, expand **Systems**, and then select the system that you want to access.
The selected system and its details appear.
3. Expand the system to see the corresponding servers.

MACHINE NAME	STATUS	ARCHIVE CO...	WRITE CA
Primary Node	Connected	30.2	0.4
Distributed Node 1	Connected	36.9	0.5
Distributed Node 2	Connected	37.7	0.5

SERVICE	STATUS	P...
ConfigManage	Connected	14C
DataArchiver_	Connected	14C
ClientManager	Connected	14C
DiagnosticsMe	Not Connected	14C

4. Select a distributed node that you want to set as the backup.
The selected distributed node's details appear in the **DETAILS** section.

The screenshot shows the Historian Configuration Hub interface. On the left, there is a navigation sidebar with options like Security, White Labelling, Historian, Systems, cfm vm, Model, Collectors, Tags, and Data Stores. The main area displays a table of servers with columns for Machine Name, Status, Archive CO..., and Write. The 'Support for Browse Tags, if pri...' toggle is highlighted with a red box. The right sidebar shows configuration fields for General and Server Services.

5. In the **GENERAL** section, enable **Support for Browse Tags, if primary server down**.

6. In the upper-left corner, select **save**.

The selected distributed node is set as a backup for the primary node's configuration manager.

If your primary node's configuration manager is inactive, you can still browse the tags and their details corresponding to all the nodes within the horizontally scaled system.

Setting up High Availability

About Data Mirroring


Historian provides mirroring of stored data on multiple nodes to provide high levels of data reliability. Data Mirroring also involves the simultaneous action of every insert, update and delete operations that occurs on any node. Data mirroring provides continuous data read and write functionality.

In a typical data mirroring scenario, one server acts as a primary server to which the clients connect. All communication goes through the Client Manager, and each Client Manager knows about the others. Mirrors must be set up in a single domain.

When you create a mirror location, you add one or more servers to the group, and then create the data stores whose data you want to replicate. For example, suppose you want to create a data store for collecting the data for 100 tags, for which you want high availability. In that case, you must create a mirror location, add two or more servers to the mirror location, and then create the data store. When you do so, the data retrieved in the data store is stored in all the servers in the mirror location. If one of the servers is down, you can retrieve the data from the other servers in the group.

Mirror Node Setup

The following diagram helps you to understand a typical single mirror node setup.



Create a Mirror Location


Add one or more distributed servers (on page 361) to the system in which you want to create a mirror group.

If you want high availability of one or more data stores, you must create a mirror group (also called a mirror location), and then add servers to it. When you do so, the data in the data stores of the mirror locations is replicated. Therefore, even if one of the servers is down, you can retrieve data from the other servers in the mirror location, thus achieving high availability.

The following conditions apply when you create a mirror location:

- You must add minimum two servers to a mirror location. The maximum number of servers that you can add depends on your Historian license.
- You can add a mirror location only in a horizontally scalable Historian system.
- You can rename a mirror location, remove a machine from a mirror location, or add an additional one even after you create the mirror location. However, if only one machine remains in the group, you cannot remove it.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
The **Systems** section appears, displaying a list of systems.
3. Right-click the system in which you want to create a mirror location (or select **☰**), and then select **Browse Locations**.



A list of distributed locations in the system appears.

4. Select **Mirror Locations**.

A list of mirror locations in the system appears.

5. In the upper-right corner of the main section, select **+**.

The **Add Mirror Location** window appears.

6. Provide values as described in the following table.

Field	Description
MIRROR LOCATION NAME	Enter a name for the mirror location. A value is required and must be unique for the system.
SERVER MACHINES	Select the servers that you want to add to the mirror group. This box contains a list of all the servers in the system. You must add minimum two servers to a mirror location.

7. Select **Add**.

The mirror location is created.

[Add a data store to the mirror location \(on page 370\)](#).

Create a Data Store

The number of data stores that you can create depends on your license.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**.
Alternatively, you can select **Systems**, right-click the system in which you want to create a data store (or select ) , and then select **Browse Data Stores**.
The **Data Stores** section appears.
3. Select  .
If Historian Standard version, then the **Add Data Store** window appears.

If Historian Enterprise version, then the **Add Data Store: <location name>** window appears.
4. Enter values as described in the following table.

Field	Description
DATA STORE NAME	Enter a unique name for the data store. A value is required. You can use all alphanumeric characters and special characters except / \ * ? < >
DESCRIPTION	Enter a description for the data store.
LOCATION	Enter the host name or IP address of the distributed location on which you want to create the data store. This field is available only for a horizontally scalable system.
Is Default	Switch the toggle on if you want to set this data store as the default one. A default data store is the one that is considered if you do not specify a data store while adding a tag. You can set only one data store as default.

5. Select  .

The data store is created.

When you add tags to the data store, it will have its own set of .IHA (iHistorian Archive) files. Ensure that you back up the new data store archives periodically.


Creating a Model

About a Historian Model

A Historian model is a hierarchical classification of various objects in a system. A model contains the following components:

- Object Types
- Contained Types
- Object Instances
- Variables


Object Type: An object type is a blueprint, which you want to replicate that will have a common structure (common properties/attributes and contained types). These object types can be the products you manufacture, your assets, byproducts, or anything else for which you want to classify information hierarchically and inherit properties/attributes. For example, in an automobile manufacturing unit, the vehicles you manufacture are object types (for example, a car or a scooter).




Contained Types: A contained type is an object type that you can include in another object type. For example, suppose you manufacture cars with the following types of engines:

- Petrol
- Diesel

You can then create one contained type for a petrol engine and one for a diesel engine. Similarly, you can create contained types for various types of brake systems, testing parameters, and so on.




When you create an object type for a car, you can include any of these contained types.




You can include multiple contained types in a single object instance. In addition, you can include a single contained type in multiple object instances.

Object Instances: Each item of an object type that you manufacture is called an object instance. For example, if you manufacture three cars, each one is an instance.




An object instance is specific to a Historian system. An object type, however, is not associated with a system.

Variables: Each attribute or property of an object is called a variable. These variables are common across all objects of a certain type. They represent tags whose values are collected by data collectors. For example, a car can have the following variables.



When you create instances of an object type, by default, the variables in the object type are inherited to all the instance as well. You can choose to include or exclude one or more of these variables for each instance.

In the following image, all the variables of the car object type are inherited to each of the instances. However, the first two instances do not include Storage. And the third instance does not include Mileage and Fuel Type.



If an object type contains contained types, the variables in the contained types are inherited as well.

After you create an object instance, you must store the values of each variable of the instance. To do so, you must map each variable with a Historian tag or create one, depending on the type of the variable.

Types of Variables:

- **Direct:** Tags for these variables are created in Historian when you select a collector instance. For instructions on collecting data for these types of tags, refer to [Collect Data for a Direct Variable \(on page 392\)](#).
- **Indirect:** These variables are mapped with existing Historian tags. For instructions on collecting data for these types of tags, refer to [Collect Data for an Indirect Variable \(on page 395\)](#).
- **Static:** These variables have a static value, which you provide when you create an object instance. For instructions on providing data for these types of tags, refer to [Provide Data for a Static Variable \(on page 390\)](#).

Limitations:

- An OPC UA model is not supported.
- If the name of a tag associated with a variable in a model contains a period (.), you cannot import the tag while importing the model into a Historian system.


About Object Templates

When you create an object type, you create a template. A template contains attributes/properties of an object type, called variables. When you apply a template to an object instance, the variables included in the template are added to the object instance.


Types of Templates:

- **Default Template:** The default template contains generic/common variables of an object type. Each object type contains one and only one default template; you cannot delete it.
- **Custom Template:** In addition to the default template, if needed, you can create one or more custom templates for an object type. When you do so, you can choose to include variables from the default template or other custom templates in the same object type.

For example, suppose you have an automobile manufacturing unit. You can create a default template that contains generic details about an automobile. Each of these details is a variable.



In addition to the default template, you can create custom templates for the object type, and add variables to it. For example, in the automobile object type, you can create a template for a car and another one for a scooter. Some of the variables in the default template (such as storage and gear system) may not be applicable to a scooter. Therefore, you can exclude them.



When you later create instances of the object type, you can choose any of the three templates. When you do so, all the variables in the template are included in the object instance. You will then capture values of these variables in Historian.

Workflow for Creating a Historian Model

To create a model and store tag values of object instances, you must perform the following steps.

Step Number	Description	Notes
1	Set up Configuration Hub (on page 305).	This step is required. It involves installing the required components to get started with Configuration Hub.
2	Create a collector instance (on page 357).	This step is required. It involves creating a collector instance using which you want to collect data from the object instance and store it in an on-premises Historian server or a cloud destination.
3	Specify the tags for data collection (on page 357).	This step is required. It involves specifying the tags for which you want to collect data by browsing through the tags in the data source. For example, for an iFIX collector, if there are 1,00,000 tags in the iFIX server, you must specify the ones for which you want to collect data. Only then data is collected for those tags. You will later map these tags with the variables in each object instance, thus collecting data for the variables (explained later in this workflow).
4	Create an object type (on page 380).	This step is required. It involves creating an object type, a default template, one or more custom templates as needed, and adding variables to each object type.
5	Create an object instance (on page 388).	This step is required. It involves creating an object instance and applying the required


Step Number	Description	Notes
6	Provide/collect data for static (on page 390) , direct (on page 392) , and indirect (on page 395) variables.	<p>template from the object type. The object instance then inherits the variables from the object type.</p> <p>This step is required. You can provide data for the following types of variables:</p> <ul style="list-style-type: none"> • Static: For a static variable, the value does not change; therefore, you just provide the value of the variable. • Direct: For a direct variable, you associate the variable with a collector instance and a tag. When you do so, the tag is created in Historian, and values for the variable are collected by the collector instance and stored in Historian. • Indirect: For an indirect variable, you associate the variable with a collector instance and an <i>existing</i> Historian tag. The values for the variable are then collected by the collector instance and stored in Historian. <p>For more information on the types of variables, refer to About a Historian Model (on page 371).</p>

Create an Object Type

When you create an object type, you also create the default template, custom templates, and variables for each template. For information on each of these template types and variables, refer to [About Object Templates \(on page 376\)](#) and [About a Historian Model \(on page 371\)](#).

This topic describes how to create an object type. You can also [copy one \(on page 403\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select **⋮**, and then select **Browse Model**.
The **Model** section appears.
3. In the upper-right corner of the section, select **+**.




The **New Object Type** window appears.

4. Enter values as described in the following table.

Field	Description
NAME	<p>Enter a name for the object type. A value is required and must be unique.</p> <p>The value that you enter:</p> <ul style="list-style-type: none"> ◦ Must begin with a letter or a number. ◦ Can contain up to 256 characters. ◦ Can include any of the following special characters: /!#{}%\$-_ ◦ Must not include a space or any of the following characters: ~`+^;,:?'"*=@
DESCRIPTION	Enter a description for the object type.


5. Select **Create**.
The object type is created.
6. In the main section, under **Object Types**, right-click the object type that you have created (or select **⋮**), and then select **Edit**.



The **<object type name>** section appears. The **OBJECT TYPE TEMPLATE** field contains the default template.

7. To add variables to the default template:

a. In the **Variables** table, select **New**.



A blank row appears in the table.

b. Enter values as described in the following table.

Column	Description
VARIABLES	<p>Enter the name of the variable. A value is required and must be unique for the object type.</p> <p>The value that you enter:</p> <ul style="list-style-type: none"> ▪ Must begin with a letter or a number. ▪ Can contain up to 256 characters.

Column	Description
VARIABLE TYPE	<ul style="list-style-type: none"> ▪ Can include any of the following special characters: /!#{}%\$-_ ▪ Must not include a space or any of the following characters: ~`+^:;,?"*=}{@ <p>Choose one of the following types of variables:</p> <ul style="list-style-type: none"> ▪ Direct: Tags for these variables are created in Historian for a selected collector instance. ▪ Indirect: These variables are mapped with existing Historian tags. ▪ Static: These variables have a static value, which you provide when you create an object instance.
DATATYPE	Select the data type of the variable.
DESCRIPTION	Enter a description for the variable.
INCLUDE	Switch the toggle to indicate whether you want to include the variable in the template.

**Note:**

After you apply a template to an object instance, you cannot modify or delete a variable in the object type; you can only add more variables. You can, however, [copy the object type \(on page 403\)](#), and modify or delete variables in the copied one.

c. Press ENTER.


The default template is created, along with the variable that you have added. You can add more variables or include/exclude variables later too.

**Note:**

If you want to create a variable by copying an existing one, select the check box next to the variable that you want to copy, and then select . You can copy only one variable at a time.

8. To create a custom template:

a. Next to the **TEMPLATE** field, select **☰**, and then select **New**.



The **New Object Template** window appears.


b. Enter values as described in the following table.

Field	Description
NAME	<p>Enter a name for the template. A value is required and must be unique.</p> <p>The value that you enter:</p> <ul style="list-style-type: none"> ▪ Must begin with a letter or a number. ▪ Can contain up to 256 characters. ▪ Can include any of the following special characters: /!#{}%\$-_ ▪ Must not include a space or any of the following characters: ~`+^;,:?"*={}@
DESCRIPTION	Enter a description for the template.

c. Repeat step 7 to add variables to the custom template.

The custom template is created, along with the variables. You can add more variables, and include/exclude existing variables later too.

9. In the upper-left corner of the page, select **Save**.



The object type, along with the default template, custom templates, and variables, is created.

[Create an object instance \(on page 388\).](#)

Include a Contained Type in an Object Type


[Create an navigation object type \(on page 380\)](#) that you want to use as a contained type.

A contained type is an object type that you can include in another object type. When you do so, you can reuse the variables in the contained type without creating them again manually. These variables are inherited by object instances of the object type in which you include the contained type.

You can include a single contained type in multiple object types and multiple contained types in a single object type.


For more information, refer to [About a Historian Model \(on page 371\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a contained type, select **⋮**, and then select **Browse Model**.
The **Model** section appears.
3. Under **Object Types**, right-click the object type in which you want to include the contained type (or select **⋮**), and then select **Edit**.



The **<object type name>** section appears, displaying a list of variables in the object type.

4. Select **Contained Types**.



A list of contained types in the object type appears.

5. In the **CONTAINED TYPES** table, select **New**.

NAME	DESCRIPTION
Vehicle	vehicle description

OBJECT TYPE TEMPLATE

Default_Template_Vehicle ▼ ⋮

Variables **Contained Types**

CONTAINED TYPES					New
<input type="checkbox"/>	ALIAS	TYPE	TEMPLATE		
<input type="checkbox"/>	MyObjType	MyObjectType	Default_Template_MyObjectType		
<input type="checkbox"/>	manufacturecontain	Manufacture	Default_Template_Manufacture		


A blank row appears in the table.

6. Enter values as described in the following table, and press ENTER.

Field	Description
ALIAS	<p>Enter a name for the contained type. A value is required. It need not match the original name of the contained type that you want to include.</p> <p>The value that you enter:</p> <ul style="list-style-type: none"> ◦ Must begin with a letter or a number. ◦ Can contain up to 256 characters. ◦ Can include any of the following special characters: /!#{}%\$-_ ◦ Must not include a space or any of the following characters: ~`+^:;,?"*=@
TYPE	<p>Select the object type that you want to include as a contained type. This field contains a list of all the object types in the Historian system.</p>
TEMPLATE	<p>Select the template from the object type that you want to include. This field contains a list of templates in the object type. Only the variables in the selected template will be inherited by instances of the object type in which you want to include the contained type.</p>

The contained type is included in the object instance.

7. In the upper-left corner of the page, select **Save**.



The changes to the object type are saved.

[Create an object instance \(on page 388\)](#). The object instance will include the variables directly added in the object type, along with the ones in the selected template in the contained type.

Create an Object Instance

[Create an object type \(on page 380\)](#).


For each item of an object type, you must create an object instance so that you can capture values of the variables in the instance. These values are then stored in Historian.



Note:

After you create an object instance, you cannot rename, import, export, or delete a variable, contained types, or templates in the associated object type; you can only create new ones.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select **⋮**, and then select **Browse Model**.
The **Model** section appears.
3. In the **SYSTEM** list, select the system in which you want to create an object instance.
4. Under **Object Types**, right-click the object type whose instance you want to create (or select **⋮**), and then select **Add Object Instance**.



The **New Object Instance** window appears.

5. Enter values as described in the following table.

Field	Description
NAME	<p>Enter a name for the object instance. A value is required and must be unique for the object type.</p> <p>The value that you enter:</p> <ul style="list-style-type: none"> ◦ Must begin with a letter or a number. ◦ Can contain up to 256 characters. ◦ Can include any of the following special characters: /!#{}%\$-_ ◦ Must not include a space or any of the following characters: ~`+^;,:?"*=@
DESCRIPTION	Enter a description for the object instance.
OBJECT TYPE	This field is disabled and populated with the object type that you have selected.
OBJECT TYPE TEMPLATE	Select the template that you want to apply to the object instance.

 **Note:**
After you apply a template to an object instance, you cannot modify or delete a

Field	Description
	 variable in the object type; you can only add more variables.

6. Select **Create**.

The object instance is created.

7. In the **Model** section, under **Instances**, expand the instance that you have created, and then expand **Variables**.

A list of variables inherited from the template in the object type appear.

8. Select a variable.

The details of the variable appear in the **DETAILS** section.



Tip:

If the **DETAILS** section does not appear, in the upper-right corner of the page, select , and then select **DETAILS**.

- [Provide data for static variables \(on page 390\)](#).
- Collect data for [direct \(on page 392\)](#) and [indirect \(on page 395\)](#) variables.

Provide Data for a Static Variable

A static variable contains a fixed value. Therefore, when you create an object instance, you can access the variable, and provide its value.

1. [Access Configuration Hub \(on page 336\)](#).

2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.

Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select , and then select **Browse Model**.

The **Model** section appears.

3. Under **Object Instances**, expand the object instance, expand **Variables**, and then select the variable whose data you want to provide.

MODEL ELEMENT
 <i>Filter</i>
▼ Object Instances
>  Audi
>  MyObjInstance1
▼  MyObjectInstance2
▼  Variables
 MyObjVariable
 MyObjVariable2
 MyStaticVariable
 MyIndirectVariable
 MyStaticVariable1


The details of the variable appear in the **DETAILS** section.




Note:

If the **DETAILS** section does not appear, in the upper-right corner of the page, select , and then select **DETAILS**.

- In the **DETAILS** section, in the **Static Value** field, enter the value that you want to provide for the variable, and then press ENTER.



5. In the upper-left corner of the page, select **Save**.



The value for the variable is saved.

Collect Data for a Direct Variable

1. Create a collector instance (on page 357) using which you want to collect data for the variable.
2. Add the tag (on page 357) using which you want to collect data.


To collect data of a direct variable, you must associate the variable with a collector instance and a tag. When you do so, the tag is created in Historian, and values for the variable are collected by the collector instance and stored in Historian.



Important:

If the name of a tag associated with a variable in a model contains a period (.), you cannot import the tag while importing the model into a Historian system.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select **⋮**, and then select **Browse Model**.
The **Model** section appears.
3. Under **Object Instances**, expand the object instance, expand **Variables**, and then select the variable whose data you want to collect.



The details of the variable appear in the **DETAILS** section.



Note:

If the **DETAILS** section does not appear, in the upper-right corner of the page, select , and then select **DETAILS**.

4. In the **Source Address** field, select .

DETAILS
✕

🔍

Field	Value
▼ General	
Variable Name	MyObjVariable2
Tag Name	
Description	
Comment	
Step Value	<input type="checkbox"/>
Last Modified Time	
Last Modified User	
▼ Collection	
Collector	
Source Address	
Data Type	
Value	
Enumerated Set	

The **Browse Source Tag** window appears.

5. Enter values as described in the following table.


Field	Description
COLLECTOR NAME	Enter the name of the collector using which you want to collect data of the variable. A value is required.
COLLECTED TYPE	Specify whether you want to browse through all the tags in the data source or only from the tags that you have not added yet. A value is required.
SOURCE TAG NAME	Enter the name of the tag (either completely or partially) to narrow down the search results.
SOURCE TAG DESCRIPTION	Enter the description of the tag (either completely or partially) to narrow down the search results.

6. Select **Search Tags**.

A list of tags that match *all* the search criteria appears.

7. Select the collector tag that you want to map with the variable, and then select **Apply**.

8. In the upper-left corner of the page, select **Save**.



The tag is mapped with the variable. A corresponding tag is created in Historian. The details of the tag and the collector instance are disabled and populated in the **DETAILS** section. All the data that is collected for the tag is now stored in Historian (or in a cloud destination as configured in the collector instance).

Collect Data for an Indirect Variable

1. Add or ensure there is a collector instance (on page 357) which you want to collect data for the variable.
2. Add the tag (on page 357) that you want to map with the variable.

To collect data of an indirect variable, you must associate the variable with a collector instance and an existing Historian tag. The values for the variable are then collected by the collector instance and stored in Historian.



Important:

- If the name of a tag associated with a variable in a model contains a period (.), you cannot import the tag while importing the model into a Historian system.
- If you want to later delete the tag, first remove the mapping between the tag and the variable.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select , and then select **Browse Model**.
The **Model** section appears.
3. Under **Object Instances**, expand the object instance, expand **Variables**, and then select the variable whose data you want to collect.

MODEL ELEMENT
 <i>Filter</i>
▼ Object Instances
>  Audi
>  MyObjInstance1
▼  MyObjectInstance2
▼  Variables
 MyObjVariable
 MyObjVariable2
 MyStaticVariable
 MyIndirectVariable
 MyStaticVariable1


The details of the variable appear in the **DETAILS** section.



Note:


If the **DETAILS** section does not appear, in the upper-right corner of the page, select , and then select **DETAILS**.

- In the **DETAILS** section, in the **Tag Name** field, select  .



The **Tag Selection: <variable name>** window appears.

5. Select **Search** to search for tags.
6. Enter the search criteria, and then select **Search**. You can enter a name or a value partially or use the wildcard character asterisk (*). You can add more search criteria by selecting **Add Attribute**. The list of tags are filtered based on the search criteria.
7. Select the collector tag that you want to map with the variable, and then select **Apply**.
8. In the upper-left corner of the page, select **Save**.



You can choose any of the following options provided while mapping the indirect variable with an existing Historian tag to save in Historian with or without the model hierarchy.




Table 12.

Field	Description
Use as is	Choosing this option will not update the Historian tag name. Mapping Information will be saved only in model database. Mapping information won't be available with Historian (when you export and try to trend with trending tools like Operations Hub, you will not be able to trend as they are connected to Historian Database).
Create Alias	Choosing this option creates an alias of Historian tag mapped with indirect variable. This option will save the model tag both in the model database and Historian database as an alias. When you export the model, you will be able to trend and see the data. (This is the default option.)
Rename Permanently	Choosing this option will permanently rename the Historian tag mapped with the model indi-

Field	Description
	rect variable and removes the existing tag. So, there will be chance that existing trends using this Historian tag might have impact.

Export an Object Type/Instance

When you create an object type or an object instance, you can use it only in the Historian system in which you have created it. If, however, you want to use the object type/instance in a different Historian system or Operations Hub, you can export it and then import it into the other Historian system or Operations Hub.


The following conditions apply when you export an object type/instance:

- You can export each object type/instance separately or all the object types and object instances in a Historian system at once.
- You can choose to export the variables or object instances of an object type (or both).
- You can choose to export the variables and templates of an object instance (or both). You cannot, however, export templates to Operations Hub.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**. Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select **☰**, and then select **Browse Model**. The **Model** section appears.
3. If you want to export all the object types/instances in the Historian system, in the upper-right corner of the main section, select .



If you want to export a single object type/instance, under **Object Types** or **Object Instances**, right-click the object type/instance that you want to export (or select **☰**), and then select **Export**.



The **Export Model** window appears. Depending on whether you are exporting all the object types/instances in the system or just a single one, the **File name** field contains a value in the following format: *<host name>.csv* or *<object type>.csv* or *<object instance.csv*.

4. If needed, modify the value in the **File name** field.
5. Depending on whether you want to export to another Historian system or Operations Hub, select the appropriate option.
6. Operations Hub 2023 supports multi model with multiple roots, you can choose the version while exporting the model either to 2023 or versions prior to 2023.

Export Model

FILE NAME
WIN10-SAI.csv

EXPORT TO
 Historian Operations Hub

SELECT VERSION
Before 2023

2023
Before 2023

Not Started. 0%

Close Export

7. Depending on whether you want to export the templates, the object instances, or both, ensure that the corresponding check boxes are selected. However, you can export templates only to a Historian system, not to Operations Hub.

8. Select **Export**.

The object types/instances, along with the underlying object variables, are exported in to a .csv file.

Import an Object Type/Instance

When you create an object type or an object instance, you can use it only in the Historian system in which you have created it. If, however, you want to use the object type/instance in a different Historian system or Operations Hub, you can export it and then import it into the other Historian system or Operations Hub.

You can import each object type/instance separately or all the object types/instances in a Historian system at once.




Important:

If the name of a tag associated with a variable in a model contains a period (.), you cannot import the tag while importing the model into a Historian system.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select , and then select **Browse Model**.
The **Model** section appears.

3. In the upper-right corner of the main section, select .



The **Import Model** window appears.

4. Select **Choose File**, and then select the .csv file that contains the object types/instances that you want to import.
5. Depending on whether you want to import the templates, the object instances, or both, ensure that the corresponding check boxes are selected.
6. Select **Import**.

The object types/instances are imported.


Copy an Object Type

When you create an object type, you also create the default template, custom templates, and variables for each template. For information on each of these template types and variables, refer to [About a Historian Model \(on page 371\)](#) and [About Object Templates \(on page 376\)](#).

When you copy an object type, all the templates and variables are copied too.

This topic describes how to copy an object type. You can also [create one \(on page 380\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select **⋮**, and then select **Browse Model**.
The **Model** section appears.
3. Under **Object Types**, select the object type that you want to copy, and then select **Duplicate**.



The **Duplicate Object Type** window appears.


4. Enter values as described in the following table.

Field	Description
NAME	<p>Enter a name for the object type. A value is required and must be unique.</p> <p>The value that you enter:</p> <ul style="list-style-type: none"> ◦ Must begin with a letter or a number. ◦ Can contain up to 256 characters. ◦ Can include any of the following special characters: /!#{}%\$-_ ◦ Must not include a space or any of the following characters: ~`+^;,:?'"*=@
DESCRIPTION	Enter a description for the object type.

5. Select **Create**.

The object type is copied, along with the variables and templates in the original object type.

6. Right-click the object type that you have copied (or select **⋮**), and then select **Edit**.




The **<object type name>** section appears. The **OBJECT TYPE TEMPLATE** field contains all the templates in the original object type. In addition, each template contains all the variables as defined in the original object type.

7. To add more variables to a template:

a. In the **OBJECT TYPE TEMPLATE** field, select the template to which you want to add more variables.

b. In the **Variables** table, select **New**.



A blank row appears in the table.

c. Enter values as described in the following table.

Column	Description
VARIABLES	Enter the name of the variable. It must be unique for the object type.
VARIABLE TYPE	Choose one of the following types of variables: <ul style="list-style-type: none"> ▪ Direct: Tags for these variables are created in Historian when you select a collector instance. ▪ Indirect: These variables are mapped with existing Historian tags. ▪ Static: These variables have a static value, which you provide when you create an object instance.
DATATYPE	Select the data type of the variable.
DESCRIPTION	Enter a description for the variable.
INCLUDE	Switch the toggle to indicate whether you want to include the variable in the template.



Tip:

If you want to modify a variable, change the values in the aforementioned fields.
 If you want to delete a variable, select the check box next to the variable, and then select .



Note:

After you apply a template to an object instance, you cannot modify or delete a variable in the object type; you can only add more variables.

d. Press ENTER.


The default template is modified, and the new variables have been added. You can add more variables or include/exclude variables later too.



Note:

If you want to create a variable by copying an existing one, select the check box next to the variable that you want to copy, and then select . You can copy only one variable at a time.

8. In the upper-left corner of the page, select **Save**.




The object type, along with the default template, custom templates, and variables, is created.

[Create an object instance \(on page 388\).](#)

Delete a Template


This topic describes how to delete a custom template. You cannot delete a template that is in use (that is, an object instance has been created for the object type). And, you cannot delete the default template in an object type.

1. [Access Configuration Hub \(on page 336\).](#)
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select , and then select **Browse Model**.
The **Model** section appears.
3. In the main section, under **Object Types**, right-click the object type from which you want to delete a template (or select ) , and then select **Edit**.




The **<object type name>** section appears. The **OBJECT TYPE TEMPLATE** field contains the default template.

4. In the **OBJECT TYPE TEMAPLTE** field, select the template that you want to delete.
5. Next to the **OBJECT TYPE TEMPLATE** field, select **☰**, and then select **Delete**.



A message appears, asking you to confirm that you want to delete the template.


6. Select **Yes**.
The template is deleted.
7. In the upper-left corner of the page, select **Save**.



The changes to the object type are saved.

Delete an Object Instance

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select **Model**, and then select **Browse Model**.
The **Model** section appears.
3. Under **Object Instances**, right-click the object instance that you want to delete (or select **Model**), and then select **Delete**.



A message appears, asking you to confirm that you want to delete the object instance. If there are direct variables in the object type, you can also choose to delete the tags associated with these variables (along with their data).


4. Select **Yes**.

The object instance is deleted, along with the underlying variables and templates.

Delete an Object Type

You cannot delete an object type if it is used in an object instance; you must first [delete the object instance \(on page 409\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Model**.
Alternatively, you can select **Systems**, and then in the row containing the system in which you want to create a model, select **⋮**, and then select **Browse Model**.
The **Model** section appears.
3. Under **Object Types**, right-click the object type that you want to delete (or select **⋮**), and then select **Delete**.



A message appears, asking you to confirm that you want to delete the object type.

4. Select **Yes**.

The object type is deleted, along with the underlying variables and templates in the object type.

If, however, the object type is used in an object instance, a message appears, asking you to first delete the object instance.

Managing Historian Systems

Access a System

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, expand **Systems**, and then select the system that you want to access.

The system appears in the main section. The following details of the system appear in the **DETAILS** section.

Table 13. The General Section

Field	Description
Name	The name of the system.
System Type	The type of the system (whether stand-alone or distributed).
Primary Server	The primary server of the system.
Description	The description of the system.
Default System	<p>Indicates whether the system is a default one. If yes, when you log in to Configuration Hub, this system appears by default. The following conditions apply for a default system:</p> <ul style="list-style-type: none"> ◦ You can have only one default system in Configuration Hub. ◦ You cannot delete a default system. <p>For instructions of setting a default system, refer to Set a Default System (on page 445).</p>
Collectors	The number of collectors in the system.
Tags	The number of tags in the system.
Data Stores	<p>The number of data stores in the system.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Tip: If you hover over, the names of the data stores will be displayed.</p> </div>
Clients	The number of clients in the system.
Server Time	The current time of the server.
Server Version	The version of the server.
Demo Mode	Indicates whether the server is currently in demo-license mode.
Clustered	Indicates whether the server is currently in clustered environment.

Table 14. The System Defaults Section

Field	Description
Default Data Store	The default data store in the system. A default data store is the one that is considered if you do not specify a data store while adding a tag. For instructions on setting a data store as default, refer to Set a Default Data Store (on page 462) .
Default Location	The default location in the system. A default location is a server in a system which is considered when you do not specify a location while creating a Data Store. By default, the distributed location on the primary server is the default location. You can, however, set a different default location. To set the default location select  .

Table 15. The Alarms and Events Section

Field	Description
Alarms Rate	The rate at which alarm data (on page 750) is collected in the system.

Table 16. The License Section

Field	Description
Historian Tags	<p>The number of tags in the system (out of the total number of licensed tags).</p> <div style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note: If this field displays 100 tags and the Users field displays 1 client, you are likely running in demonstration mode and may have incorrectly installed your hardware key.</p> </div>
Scada Tags	The number of SCADA tags in the system (out of the total number of licensed SCADA tags).
Users	The number of users in the system (out of the total number of users authorized to access Historian using the software key and license).

Field	Description
	<p>The number of users that are authorized to access Historian is strictly based on the software key and license. However, if you have utilized your available Client Access Licenses (CAL) and need an additional one to use the system in an emergency, you have an option to reserve a CAL. This reserved CAL allows you to access the server. To do so, provide the reserved CAL to the system administrators and add them to the ih Security Admins group. A system administrator can then connect to Historian in an emergency.</p> <p>This facility is optional and does not provide a guaranteed connection. It only eliminates the emergency situations when a CAL is preventing you from accessing the system and may not work if there are other conditions. For example, if the Historian server is busy, you will not be able to connect using this feature.</p>
Data Stores	The number of data stores in the system (out of the total number of licensed data stores).
Calculations	Indicates whether the Calculation collector is licensed on the software key.
Server to Server	Indicates whether the Server-to-Server collector is licensed on the software key.
OPC HDA Server	Indicates whether the OPC Classic HDA server is licensed on the software key.
OPC UA HDA Server	Indicates whether the OPC UA HDA server is licensed on the software key.
Model	Indicates whether the object model is licensed on the software key.
Electronic Signature	Indicates whether electronic signature is licensed on the software key.

Table 17. The Global Security Section

Field	Description
Security Group	<p>Indicates the type of authorization you want to use for the Historian security groups. The following options are available:</p> <ul style="list-style-type: none"> ◦ Use Domain- If you select this option, the system will use the groups specific to this domain for authorization. Only the users and groups that belong to the domain will have specific permissions and access rights. For more information on the security groups, refer to Historian security groups (on page 256). ◦ Use Local- If you select this option, the system will use the groups specific to the local system for authorization. ◦ Use Proficy Authentication- If you select this option, the system will use the groups specific to Proficy Authentication (UAA) for authorization. Only the users or groups that belong to the Proficy Authentication will have specific permissions and access rights. For more information on the Proficy Authentication groups, refer to about Proficy Authentication groups (on page 231). <p>Before you select this option, ensure that you perform the configurations listed in Configurations to use Proficy Authentication Security Groups (on page 232).</p>
Enforce Strict Client Authentication	If you enable this option, only known user accounts configured on the Data Archiver server computer will be able to access the Historian server.
Enforce Strict Collector Authentication	If you enable this option, only known collector connections configured on the Data Archiver server computer will be able to send data to the Historian server.

For more information on global security, refer to [Strict Authentication \(on page 252\)](#).

Table 18. The Electronic Signatures/Records Section

Field	Description
<p>Require Point Verification</p>	<p>Indicates whether you must enter identifying information whenever you attempt a restricted action. Whenever you attempt to change the system configuration (for the tag, archive, or collector), a tag value, or another record, you must electronically sign the action with a username and password. If the user is authorized to make this change, the identity of the person, the action performed, and the time it was performed, are all recorded in the audit trail.</p> <p>Note:</p> <ul style="list-style-type: none"> ◦ The audit features are not dependent on this feature being enabled. Historian audits all user actions regardless of whether this option is enabled. <p>Enabling electronic signatures and electronic records also requires you to reverify your identity when you use the Historian Excel Add-in, modify or create a tag, or import data or messages.</p> <p>Note: This feature is available only if you have purchased the Electronic Signatures and Electronic Records option.</p>
<p>Verification Message</p>	<p>When point verification is enabled, whenever you attempt to perform an action specified as requiring point verification, you are prompted to authenticate.</p> <ul style="list-style-type: none"> ◦ USERNAME: This is populated with the user that is logged in to Configuration Hub and disabled. ◦ PASSWORD: The logged in user's password. ◦ DOMAIN: The logged in user's domain.

3. Expand the system in the main section.

A list of servers in the system appears, displaying the following information.

Field	Description
MACHINE NAME	<p>In a stand-alone Historian system, this column displays the host name of the Historian server. In a horizontally scalable Historian system, this column displays the host name of the primary server.</p>
STATUS	<p>The current status of the Historian system.</p>
ARCHIVE COMPRESSION	<p>The current effect of archive data compression. At the system level, this value is calculated as the average of the corresponding values of individual servers in the system.</p> <p>If the value is zero, it indicates that archive compression is either ineffective or turned off. To increase the effect of data compression, increase the value of archive compression deadbands on individual tags in the Tags section to activate compression.</p> <p>In calculating the effect of archive compression, Historian counts internal system tags as well as data source tags. Therefore, when working with a very small number of tags and with compression disabled on data source tags, this field may indicate a value other than zero. If you use a realistic number of tags, however, system tags will constitute a very small percentage of total tags and will therefore not cause a significant error in calculating the effect of archive compression on the total system.</p>
WRITE CACHE HIT RATIO	<p>The hit ratio of the write cache in percentage of total writes. At the system level, this value is calculated as the average of the corresponding values of individual servers in the system.</p> <p>It is a measure of how efficiently the system is collecting data. Typically, this value should range from 95 to 99.99%. If the data is changing rapidly over a wide range, however, the hit percentage drops significantly because current values differ from recently cached values. More regular sampling may increase the hit percentage. Out-of-order data also reduces the hit ratio.</p>

Field	Description
CONSUMPTION RATE	<p>The rate at which the archive disk space is consumed. At the system level, this value is calculated as the sum of the corresponding values of individual servers in the system.</p> <p>If the value is too high, you can reduce it by slowing the poll rate on selected tags or data points or by increasing the filtering on the data (widening the compression deadband to increase compression).</p>
READ THREAD USAGE	<p>The percentage of the read threads currently in use by the system. At the system level, this value is calculated as the average of the corresponding values of individual servers in the system.</p>
WRITE THREAD USAGE	<p>The percentage of the write threads currently in use by the system. At the system level, this value is calculated as the average of the corresponding values of individual servers in the system.</p>
OUT OF ORDER WRITE RATE	<p>The number of out-of-order events per minute. At the system level, this value is calculated as the sum of the corresponding values of individual servers in the system.</p>
MIN DISK SPACE LEFT	<p>The minimum free disk space in MB that must be available on the computer. If the minimum space required is not available when the collector starts, the collector will shut down.</p>
FAILED WRITE RATE (EVENTS/MIN)	<p>The number of samples that failed to be written per minute. At the system level, this value is calculated as the sum of the corresponding values of individual servers in the system.</p> <p>Since failed samples are a measure of system malfunctions or an indication of offline archive problems, this value should be zero. If you observe a non-zero value, investigate the cause of the problem and take corrective action.</p> <p>Historian also generates a message if a writing a sample fails. Note that the message only appears once per tag, for a succession of failed writes associated with that tag. For example, if the number displayed in this field is 20, but they all pertain to one Historian tag, you will only receive one message until that Historian tag is functional again.</p>


Field	Description
MEMORY USAGE	Indicates how much server memory is being consumed.
READ QUEUE RATE (40 MSG/ MIN)	The number of read requests processed per minute, that came into the archiver from all clients.
WRITE QUEUE RATE (MSG/ MIN)	The number of write requests processed per minute, that came into the archiver from all clients.
MESSAGE QUEUE RATE (MSG/ MIN)	The number of messages processed per minute.
READ QUEUE SIZE (EVENTS)	The total number of messages present in the Read queue.
WRITE QUEUE SIZE (EVENTS)	The total number of messages present in the Write queue.
MESSAGE QUEUE SIZE (MSG)	The total number of messages present in the Message queue.

**Tip:**

You can show/hide/reorder columns in the table. For instructions, refer to [Common Tasks in Configuration Hub \(on page 353\)](#).

- To access the system performance, right-click the system (or select **☰**), and then select **View Server Performance**.

The **<system name> - Performance** section appears, displaying graphs for some of the metrics described in the previous table.



Access the Collectors in a System

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, expand **Systems**, and then select the system whose collectors you want to access.
The system appears in the main section.
3. Right-click the system whose collectors you want to access (or select **☰**), and then select **Browse Collectors**.

This displays the list of Historian collectors and Offline configuration collectors. By default, the Historian collector instances added to the system appear, displaying the following information.

Column	Description
COLLECTOR NAME	The name of the collector instance. If you select the link in this column, the details of the collector instance appears.
STATUS	The status of the collector. Contains one of the following values:

Column	Description
	<ul style="list-style-type: none"> ◦ Started ◦ Stopped ◦ Running ◦ Paused ◦ Unknown
CONFIGURATION	<p>The source of the tag configuration for the collector. Contains one of the following values:</p> <ul style="list-style-type: none"> ◦ HISTORIAN: Indicates that tags are configured using Historian Administrator. ◦ OFFLINE: Indicates that tags are configured using an offline configuration (on page 2039) file.
MACHINE	The name of the machine on which the collector is installed.
VERSION	The version number of the collector.
REDUNDANCY	<p>Indicates whether collector redundancy is enabled, which decreases the likelihood of lost data due to software or hardware failures. For more information, refer to About Collector Redundancy (on page 975).</p>
REPORT RATE	The average rate at which the collector is sending data. This is a general indicator of load on the collector.
OVERRUNS	<p>The total number of data events not collected. In normal operation and under normal conditions, this value should always be zero. If the value is not zero, which indicates that data is being lost, you must take steps to reduce peak load on the system by increasing the collection interval.</p>
COMPRESSION	The effectiveness of collector compression. If the value is low, you can increase the compression deadbands to pass fewer values and thus increase the effect of compression.
OUT OF ORDER	The total number of out-of-order samples for the collector.
TAG COUNT	The number of tags for which the collector collects data.
COMMENTS	The comments that you have entered for the collector.

i Tip:

- To access the details of a collector, select the row containing the collector instance. The details appear in the **DETAILS** section.
- You can show/hide/reorder columns in the table. For instructions, refer to [Common Tasks in Configuration Hub \(on page 353\)](#).

Access Offline Configuration Collectors

Offline Configuration Collectors are the instances of collectors whose destination is the cloud and display the configuration details as Offline Configuration.

Add Collector Instance: santhoshwin10

<ul style="list-style-type: none"> Collector Selection Simulation Collector Source Configuration santhoshwin10 Destination Configuration Predix Timeseries Collector Initiation 	CLIENT ID*	CLIENT SECRET*
	<i>Enter client ID</i>	<i>Enter secret</i>
	ZONE ID*	PROXY
	<i>Enter zone ID</i>	<i>Enter proxy</i>
	PROXY USERNAME	PROXY PASSWORD
	<i>Enter username</i>	<i>Enter password</i>
DATAPoint ATTRIBUTES (OPTIONAL) ⓘ		
ATTRIBUTE + Add Attributes		
CONFIGURATION DETAILS		
CHOOSE CONFIGURATION*		
<input type="radio"/> Historian Configuration <input checked="" type="radio"/> Offline Configuration		

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, expand **Systems**, and then select the system whose collectors you want to access.
The system appears in the main section.
3. Right-click the system whose collectors you want to access (or select **☰**), and then select **Browse Collectors**.
This displays the list of Historian collectors and Offline configuration collectors. By default, the Historian collector instances added to the system appear, displaying the following information.

**Tip:**

- To access the details of a collector, select the row containing the collector instance. The details appear in the **DETAILS** section.
- You can show/hide/reorder columns in the table. For instructions, refer to [Common Tasks in Configuration Hub \(on page 353\)](#).

The Details panel for the Offline Configuration Collector Interface contains information regarding the instance configuration provided for the destination while installing software




like Predix, MQTT, or Azure. For example, here is an example of the Details panel for the Offline Configuration Collector:

DETAILS	
Search...	
FIELD	VALUE
▾ INSTANCE CONFIGURATION	
Historian Server	SANTHOSHWIN10
Destination	Predix Timeseries
Cloud Destination Address	wss://gateway-predix-data-
Identity Issuer	https://9d4d55e0-14e1-4a4
Client ID	HistQA
Client Secret	
Zone ID	d459998a-656c-46c2-b525-
Proxy	http://PITC-Zscaler-America
Proxy Username	
Proxy Password	
Configuration	Offline
Configuration Historian S...	none

Manage Offline Configuration Collectors

Like other Historian collectors, Offline Configuration collectors can also be managed by selecting different options:



Refer to the following sections on how to use these options:

- [Start a Collector \(on page 637\)](#)
- [Stop a Collector \(on page 638\)](#)
- [Restart a Collector \(on page 639\)](#)
- [Delete the Buffer Files of a Collector \(on page 643\)](#)
- [Move the Buffer Files of the Collector \(on page 644\)](#)
- [Delete a Collector Instance \(on page 654\)](#)

Access the Tags in a System

This topic describes how to access all the tags in a system, regardless of whether they are added to a collector instance. You can also [access all the tags added to a collector instance \(on page 631\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, expand **Systems**, and then select the system whose tags you want to access.
3. Right-click the system whose tags you want to access (or select ) , and then select **Browse Tags**.

The tags added to the system appears, displaying the following information.

Column	Description
TAG NAME	The name of the tag.
DESCRIPTION	The description of the tag.
COLLECTOR NAME	The name of the collector instance to which you have added the tag.
LAST 10 VALUES	The last 10 values collected for the tag, plotted as a trend chart. If you pause over the chart, the minimum, maximum, first, and last values among the 10 values appear.
DATA COLLECTION	Indicates the status of the data collection.
TAG ALIAS	Indicates whether the tag contains aliases, which are created when you rename the tag using an alias (on page 698) .



Tip:

You can show/hide/reorder columns in the table. For instructions, refer to [Common Tasks in Configuration Hub \(on page 353\)](#).

4. To narrow down your search results:

You can enter a name or a value partially or use the wildcard character asterisk (*).

 - a. Select **Search**.
 - b. Enter the search criteria, and then select **Apply**. You can add more search criteria by selecting **Add Attribute**.

The list of tags are filtered based on the search criteria. The search criteria that you have provided appear at the top of the page. You can remove any of the criteria as needed.



Tip:

To access the details of a tag, select the row containing the tag. The details appear in the **DETAILS** section.

Add a System

Install Historian on the machine that you want to add. If you want to create a stand-alone system, [install single-server Historian \(on page 105\)](#). If you want to create a horizontally scalable system, [install Historian primary server \(on page 105\)](#).

If you want to manage a Historian system using Configuration Hub, you must add it to Configuration Hub.

When you access Configuration Hub for the first time, a default Historian system is available. In a distributed environment, the primary server of this system is the machine whose Configuration Hub details you enter while installing Web-based Clients. This topic describes how to add another system.



Note:

Adding a Historian system is specific to the logged-in user.

1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
3. Select **+**.
The **Add System** window appears.
4. Provide values as specified in the following table.

Field	Description
SYSTEM NAME	Enter a name for the Historian system. This name must be unique for a user.
HISTORIAN SERVER	Enter the host name or the IP address of the system that you want to add. This name must be unique for a user.
DESCRIPTION	Enter a description for the system.

The **Add Server Machine: <system name>** window appears.

5. Enter the host name or IP address of the machine that you want to add, and then select **Add**.
The distributed server is added to the system. A distributed location is added in the server. You cannot modify or delete this location.
- If you want high availability of one or more data stores in the server, [create a mirror location \(on page 368\)](#), and then [add the data stores \(on page 370\)](#). If not, [add the data store \(on page 370\)](#) to the distributed location.
 - If you want to set a distributed node as backup to the primary node, [set a distributed node as backup \(on page 365\)](#).

Set Up a Mirror of Mirror

1. [Install Historian server \(on page 105\)](#) on each machine that you want to use in the mirror of mirror setup.
2. [Set up Configuration Hub \(on page 305\)](#) on each machine that you want to use in the mirror of mirror setup.
3. [Add a system \(on page 427\)](#). The server that you specify while adding the system serves as the primary server for the system.
4. [Create data stores \(on page 370\)](#) in the primary server in the public/IT network with the same name as the data stores in the primary server in your organization network.


You can set up a mirror of the Historian server in a network different from that of your organization. When you do so, any tag/data update requests to the Historian server can be routed to the public and IT network instead of your organization's network.



Note:

For the Historian Enterprise Mirror Architecture, only "Time based" archives are supported.

Single-Node Setup: The following image shows two networks - OT and IT - with a Historian server installed in each network. These networks communicate using port 14000.




In this setup:

1. Server 1 is the primary server in the OT network; it stores data from collectors.
2. Server 2 is the primary server in the IT network; it is connected to clients.
3. When a tag/data is created, updated, or deleted, Client Manager 1 communicates the same with Client Manager 2 (installed with Server 2 in the IT network).
4. The change in the tag/data is replicated in Server 2 (that is, data is created, updated, or deleted accordingly).
5. The latest data is retrieved from Server 2 using the clients.


Mirror Setup: The following image shows two mirrors:

- Mirror 1 includes Mirror Server 1 and Mirror Node 1, which is a backup/standby node for Mirror Server 1; both these machines are in the OT network.
- Mirror 2 includes Mirror Server 2 and Mirror Node 2, which is a backup/standby node for Mirror Server 2; both these machines are in the IT network.


Client Manager 1 in Mirror Server 1 communicates with Client Manager 2 in Mirror Server 2.




If Mirror Server 1 goes down, Client Manager M1 in Mirror Node 1 communicates with Client Manager 2 in Mirror Server 2.




Similarly, if Mirror Server 2 goes down, Client Manager 1 in Mirror Server 1 communicates with Client Manager M2 in Mirror Node 2.



If both Mirror Server 1 and Mirror Server 2 are down, Client Managers M1 and M2 communicate with each other.



If Mirror Server 1 and/or Mirror Server 2 are available, the connection is re-established using these primary servers.




Thus, you can choose to always retrieve data from either Mirror Server 2 or Mirror Node 2. In addition, the store-and-forward functionality is available (in case Client Managers are not yet connected).

This topic describes how to set up a mirror of mirror for the configuration described in the preceding example. It includes the following high-level steps:

1. Installing the Historian server on all the machines
2. Setting up mirror 1
3. Setting up mirror 2
4. Setting up a mirror of mirror

Installing the Historian server


1. On the machines designated as the mirror primary servers (Mirror Server 1 and Mirror Server 2 in the example), [install the Historian server \(on page 105\)](#). During the installation, select **Historian Mirror Primary Server** on the **Choose the type of install you want to perform** page.



2. On the machines designated as mirror nodes (Mirror Node 1 and Mirror Node 2 in the example), [install the Historian server \(on page 105\)](#). During the installation, select **Historian Distributed/Mirror Node** on the **Choose the type of install you want to perform** page.

Set up Mirror 1:

3. On the mirror primary server in your organization's network (Mirror Server 1 in the example), [access Configuration Hub \(on page 336\)](#).
4. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
5. Expand Mirror Server 1.
A list of servers in the system appears.
6. Select **+**.




The **Add Server Machine: <system name>** window appears.

- Enter the host name or IP address of the mirror node in your organization's network (Mirror Node 1 in the example), and then select **Add**.

The distributed server is added to the system. A distributed location is added in the server.

- Right-click Mirror Node 1, and then select **Browse Locations**.



A list of distributed locations in the system appears.

- Select **Mirror Locations**.

A list of mirror locations in the system appears.

- In the upper-right corner of the main section, select **+**.

The **Add Mirror Location** window appears.

- Provide values as described in the following table.

Field	Description
MIRROR LOCATION NAME	Enter a name for the mirror location. A value is required and must be unique for the system.

Field	Description
SERVER MACHINES	Select the servers that you want to add to the mirror group (Mirror Server 1 and Mirror Node 1 in this example). This box contains a list of all the servers in the system. You must add minimum two servers to a mirror location.

12. Select **Add**.

Mirror Node 1 is created.

13. Right-click the system name, and then select **Add Data Store**.

The **Add Data Store: Mirror Node 1** window appears.

14. Enter values as described in the following table.

Field	Description
DATA STORE NAME	Enter a unique name for the data store. A value is required. You can use all alphanumeric characters and special characters except / \ * ? < > You must provide the same name for the mirror setup in the IT network (mirror 2 in the example).
DESCRIPTION	Enter a description for the data store.
Set as default data store for the system	Select this check box if you want to set this data store as the default one. A default data store is the one that is considered if you do not specify a data store while adding a tag. You can set only one data store as default.

15. Select **Add**.

Mirror 1 is configured.

Set up Mirror 2:

16. On the mirror primary server in the IT network (Mirror Server 2 in the example), [access Configuration Hub \(on page 336\)](#).


17. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.

A list of systems appears in the main section.

18. Expand Mirror Server 2.

A list of servers in the system appears.

19. Select **+**.




The **Add Server Machine: <system name>** window appears.

20. Enter the host name or IP address of the mirror node in your organization's network (Mirror Node 2 in the example), and then select **Add**.

The distributed server is added to the system. A distributed location is added in the server.

21. Right-click the system name, and then select **Browse Locations**.



A list of distributed locations in the system appears.

22. Select **Mirror Locations**.

A list of mirror locations in the system appears.

23. In the upper-right corner of the main section, select **+**.

The **Add Mirror Location** window appears.

24. Provide values as described in the following table.

Field	Description
MIRROR LOCATION NAME	Enter a name for the mirror location. A value is required and must be unique for the system.

Field	Description
SERVER MACHINES	Select the servers that you want to add to the mirror group (Mirror Server 2 and Mirror Node 2 in this example). This box contains a list of all the servers in the system. You must add minimum two servers to a mirror location.

25. Select **Add**.
Mirror Node 2 is created.
26. Right-click Mirror Node 2, and then select **Add Data Store**.
The **Add Data Store: Mirror Node 2** window appears.
27. Enter values as described in the following table.

Field	Description
DATA STORE NAME	Provide the same name that you provided while setting up mirror 1.
DESCRIPTION	Enter a description for the data store.
Set as default data store for the system	Select this check box if you want to set this data store as the default one. A default data store is the one that is considered if you do not specify a data store while adding a tag. You can set only one data store as default.

28. Select **Add**.
Mirror 2 is configured.

Set up Mirror of Mirror:

29. Access Configuration Hub in the primary server in the OT network (Mirror Server 2).
30. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
31. Expand Mirror Server 1.
A list of servers in the system appears.
32. Select .
The **Add Server Machine: <system name>** window appears.
33. Enter the host name or IP address of the mirror server in the IT network (Mirror Server 2 in the example), select the **Set as Mirror of Mirror** check box, and then select **Add**.
The distributed server is added to the system. A distributed location is added in the server.
34. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.

A list of systems appears in the main section.

35. Expand Mirror Server 1.

A list of servers in the system appears. In the example, Mirror Server 1, Mirror Node 1, and Mirror Server 2 appear.

A mirror of mirror is configured with one primary node and one mirror node each in the OT and IT networks. As needed, you can add more mirror nodes in each network.

Remove a Distributed/Mirror Server

- [Delete the data stores \(on page 2884\)](#) in the machine (using the Web Admin console).
- If the machine is added to a mirror location, [remove it from the location \(on page 449\)](#).

You cannot delete the default server in a system.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appear in the main section.
3. Expand the system from which you want to remove a distributed/mirror server.
A list of servers in the system appears.
4. In the row containing the server that you want to remove, select **⋮**, and then select **Delete Server**.
A message appears, asking you to confirm that you want to remove the distributed machine from the system.
5. Select **Delete**.
The machine is removed from the system.

Set a Default Location

A default location is a server in a system which is considered when you do not specify a location while [adding a data store \(on page 370\)](#). By default, the distributed location in the primary server is the default location. You can, however, set a different default location. The following conditions apply when you set a default location:

- You can have only one default location in a system.
- You cannot delete a default location.
- You can set any of the distributed/mirror locations as default.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
3. Select the system in which you want to set a default location.
The details of the system appear in the **DETAILS** section.
4. Expand **System Defaults**, and then next to **Default Location**, select .
The **Default Location: <system name>** window appears. The **Location** box contains a list of all the servers in the system.
5. Select the location that you want to set as default, and then select **Set as Default**.
The location is set as default.

Modify a Historian System

You can change the following details of a system:

- Name
- Description
- Default data store
- Default location (in case of a horizontally scalable system)

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, expand **Systems**, and then select the system that you want to modify.
The details of the system appear in the **DETAILS** section.
3. Modify values as specified in the following table.

Field	Description
Name	Enter a name for the Historian system. This value must be unique for a user.
Description	Enter a description for the system.

4. If you want to change the default data store:
 - a. Under **System Defaults**, next to **Default Data Store**, select .
The **Default Data Store: <system name>** window appears.
 - b. Select the data store that you want to set as default, and then select **Set as Default**.

The default data store is changed.

5. If you want to change the default location:

- a. Under **System Defaults**, next to **Default Location**, select . The **Default Location: <system name>** window appears. The **Location** box contains a list of all the servers in the system.
- b. Select the location that you want to set as default, and then select **Set as Default**.

The changes to the system are saved automatically.

Configure Advanced Settings of a System

You can now configure a few advanced settings for the Archiver, Collector, and Data Store to achieve some specific functionality in Historian. You must be careful while modifying the configuration as this might impact the stability and security of the Historian System.

Ensure that you are a member of the iH Security Admins group.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**. A list of systems appears in the main section.
3. Right-click the system whose advanced settings you want to configure, and then select **Advanced Configuration**. The advanced settings of the system appear, displaying the **Server** section by default.
4. Enter values as described in the following table.



Note:

If you have changed the values of any * marked fields, restart the Historian Data Archiver service. Only then will your changes be reflected.

Field	Description
ALARM TIMESTAMP CHECK	Specify whether you want to speed up, slow down, or disable alarm timestamp checking:

Field	Description
	<ul style="list-style-type: none"> ◦ 0 - Disabled: Select this option if you want to disable alarm timestamp checking. Only the data is sent to the alarm archiver. ◦ 1 - Fast: Select this option if you want to check the timestamp of the alarm data for the last 10 minutes. ◦ 2 - Slow: Select this option if you want to check the timestamp of the alarm data beyond the last 10 minutes.
ALLOW DATA OVERWRITES	Switch the toggle to enable or disable overwriting data.
ARCHIVER MEMORY SIZE	Enter the memory usage in MB that you want to allocate to an archive. If you enter 0, Data Archiver will dynamically allocate the memory usage. If Data Archiver is running on a 32-bit operating system, you can allocate upto 1800 MB. If Data Archiver is running on a 64-bit operating system, we recommend that you use the default value.
BUFER MEMORY MAX	Enter the maximum memory buffer size in MB that an archiver queue can use before switching to disk buffer.
COLLECTOR IDLE TIME (SECONDS)	Enter the number of seconds of no data collection after which a collector is considered idle.
DEBUG MODE	Specify whether you want to enable or disable the debug mode. If you enable this option, the debug information is included in the Historian log files, which helps you troubleshoot issues. However, this can result in large size of the log files.
DISABLE CA HOSTING	Enable CA Hosting to continue using the Client Access API based clients when you have converted a Mirror Primary to a standalone server while installing the Historian server.
DO NOT ZIP ARCHIVES	Switch the toggle to store the archive files as .zip files. This will help optimize the storage space of the archive files. However, if you are collecting alarm data as well, the alarm data may not be backed up. Also, you cannot export alarm data to another Data Archiver. Therefore, exercise caution while enabling this option if you are collecting alarm data as well.
FIREWALL PERMISSION	Use this parameter to disable port 14000 in the firewall. By default, Historian installation enables port 14000 in the firewall.

Field	Description
MAINTAIN AUTO RECOVERY FILE	Switch the toggle if you want to back up the archive and configuration files (.iha and .ihc files) every hour. This will prevent data loss. However, these files are used by Historian internally. Also, exercise caution in enabling this option because it can impact Historian performance.
MAX QUERY TIME (SECONDS)	Enter the maximum time in seconds that a query can take to process. After this time limit exceeds, the query is terminated.
MAXIMUM QUERY INTERVALS	Enter the maximum number of samples per tag that Historian can return from a query on non-raw data. You can use this setting to limit the number of query results on non-raw data.
NUMBER OF READ THREADS	Enter the number of read threads to use parallel reading of data. The minimum number you can enter is 8.
NUMBER OF WRITE THREADS	Enter the number of write threads to use parallel writing of data.
USE ADSI CALLS	Switch the toggle to allow Data Archiver to use Active Directory Service Interfaces (ADSI) calls.

5. Select **Save**.
6. Expand **Collector**, and then select the collector whose settings you want to configure.
The fields specific to the selected collector appear.
7. Enter values as described in the following table.

Field	Description
BUFFER FLUSH MULTIPLIER	Select the multiplier to the buffer flow speed while using the store-and-forward feature: <ul style="list-style-type: none"> ◦ 0: Select this option if you want to disable throttling. ◦ 1: Select this option if you want normal speed. ◦ 2: Select this option if you want the collector to never send data faster than twice the normal speed.
NUM INTERVALS FLUSH	Specify how quickly you want the collector to send data to Data Archiver. The value you enter in this field is multiplied by 100 milliseconds. For example, if you enter 5, the collector sends data to Data Archiver every 500 milliseconds. We recommend that you enter 5.

8. Select **Save**.

A message appears, asking you whether you want to save and restart the collector as well.

9. If you want to save your changes and restart the collector as well, select **Save and Restart**. If you want to just save your changes, select **Save**. In that case, you must restart the collector later for the changes to reflect.

Your changes are saved. If you have selected **Save and Restart**, the collector is restarted.

10. Expand **Data Store**, and then, select the data store whose settings you want to configure.

The fields specific to the selected data store appear,

11. Enter values as described in the following table.

Field	Description
ALLOW FUTURE DATA	Switch the toggle to enable storing future data (on page 1037) .
CREATE OFFLINE ARCHIVES	Switch the toggle to create offline archives. This is to avoid receiving an outside-active-hours error. It happens if you attempt to store data when the current archive file is set to read-only.

12. Select **Save**.

The advanced settings are configured for the data store.

Configure Labels of Spare Fields

For each tag, a set of five spare fields are available, which are named Spare 1 to Spare 5. You can use these fields to enter values for any tag details apart from those captured in the tag fields (for example, the name, location, and phone number of the manufacturer of a device).

This topic describes how to change the label of these spare fields at the system level. The changes are then cascaded to all the tags in the system.

You can configure any or all of these fields. The new labels of the fields then appear under **SPARE FIELDS** in the **DETAILS** section when you access a tag.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, expand **Systems**, and then select the system that you want to modify.
The details of the system appear in the **DETAILS** section.
3. Right-click the system whose spare fields you want to configure (or select **☰**), and then select **Configure Spare Fields Labels**.
The **Configure Spare Fields Labels: <system name>** window appears.
4. Enter values in the available fields, and then select **Save**.

For example, if you want to capture the name, location, and phone number of the manufacturer of a device, enter Name, Location, and Phone Number in the **SPARE FIELD 1 LABEL**, **SPARE FIELD 2 LABEL**, and **SPARE FIELD 3 LABEL** fields.

The labels of the spare fields are configured. When you access a tag, the new labels appear under **SPARE FIELDS** in the **DETAILS** section.



Note:

The labels that you have configured only appear in Configuration Hub. For other applications, such as Historian Administrator, Trend Client, and so on, Spare 1 to Spare 5 are displayed. The values of spare fields can be configured for tags.

Set a Default System

If you set a system as default, when you log in to Configuration Hub, this system appears by default. The following conditions apply when you set a system as default:

- You can have only one default system in Configuration Hub.
- You cannot delete a default system.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
3. Right-click the system that you want to set as default (or select **☰**), and then select **Set as Default System**.
The system is set as default.

Delete a Historian System

You can delete a Historian system if you no longer want to manage it using Configuration Hub. You cannot, however, delete a system if it is set as default.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
3. Right-click the system that you want to delete (or select **☰**), and then select **Delete**.
A message appears, asking if you want to delete the system.
4. Select **Delete**.
The system is deleted.

Managing Mirror Locations

Create a Mirror Location

Add one or more distributed servers ([on page 361](#)) to the system in which you want to create a mirror group.

If you want high availability of one or more data stores, you must create a mirror group (also called a mirror location), and then add servers to it. When you do so, the data in the data stores of the mirror locations is replicated. Therefore, even if one of the servers is down, you can retrieve data from the other servers in the mirror location, thus achieving high availability.

The following conditions apply when you create a mirror location:

- You must add minimum two servers to a mirror location. The maximum number of servers that you can add depends on your Historian license.
- You can add a mirror location only in a horizontally scalable Historian system.
- You can rename a mirror location, remove a machine from a mirror location, or add an additional one even after you create the mirror location. However, if only one machine remains in the group, you cannot remove it.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**. The **Systems** section appears, displaying a list of systems.
3. Right-click the system in which you want to create a mirror location (or select **☰**), and then select **Browse Locations**.

The screenshot shows the Configuration Hub interface. A system named 'torsc-collectorsclient' is selected, and a context menu is open. The menu items are: View System Performance, Set as Default System, Add Server, Browse Collectors, Browse Tags, **Browse Locations** (highlighted with a red box), Browse Clients, Delete, and Browse Model. The background shows a table with columns: Machine Name, Archive Compres..., Write Cache Hit R..., CONSUMPTION R..., Read Thread Usa..., and Write Thread Usa... The table contains two rows of data.

Machine Name	Archive Compres...	Write Cache Hit R...	CONSUMPTION R...	Read Thread Usa...	Write Thread Usa...
torsc-collectorsclient	5.5	0.5	0.33	0	0
collectorsclien6	4	NA	NA	NA	NA

A list of distributed locations in the system appears.

4. Select **Mirror Locations**.

A list of mirror locations in the system appears.

5. In the upper-right corner of the main section, select **+**.

The **Add Mirror Location** window appears.

6. Provide values as described in the following table.

Field	Description
MIRROR LOCATION NAME	Enter a name for the mirror location. A value is required and must be unique for the system.
SERVER MACHINES	Select the servers that you want to add to the mirror group. This box contains a list of all the servers in the system. You must add minimum two servers to a mirror location.

7. Select **Add**.

The mirror location is created.

[Add a data store to the mirror location \(on page 370\).](#)


Rename a Mirror Location

1. [Access Configuration Hub \(on page 336\).](#)

2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.

The **Systems** section appears, displaying a list of systems.

3. Right-click the system in which you want to rename a mirror location (or select **☰**), and then select **Browse Locations**.



A list of distributed locations in the system appears.

4. Select **Mirror Locations**.


A list of mirror locations in the system appears.

5. Select the location that you want to rename.

The details of the mirror location appear in the **Details** section.

6. In the **Name** field, enter the new name of the mirror location.

7. In the upper-left corner of the page, select **Save**.




The mirror location is renamed.

Add a Machine to a Mirror Location

If you want to add machine to a mirror location that already contains machines, and if you want to copy the archive and configuration information from the existing machines to the new machine, perform the following steps:

1. Copy the archive files and configuration files from an existing machine in the mirror location to the one that you have added.
2. Rename the configuration file <machine name>_Config.ihc.
1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
The **Systems** section appears, displaying a list of systems.
3. Right-click the system to which you want to add a machine (or select **⋮**), and then select **Browse Locations**.



A list of distributed locations in the system appears.

4. Select **Mirror Locations**.

A list of mirror locations in the system appears.

5. Right-click the mirror location in which you want to add a machine (or select **...**), and then select **Add Server Machine**.

The **Add Machine: <mirror location>** window appears. The **SERVER MACHINES** field contains a list of machines in the system that are not yet added to the mirror location.

6. In the **SERVER MACHINES** field, select the machine that you want to add to the mirror location, and then select **Add**.

The machine is added to the mirror location.

Remove a Machine from a Mirror Location


If a mirror location contains only one machine, you cannot remove it.

1. [Access Configuration Hub \(on page 336\)](#).

2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.

The **Systems** section appears, displaying a list of systems.

3. Right-click the system from which you want to remove a machine (or select **...**), and then select **Browse Locations**.



A list of distributed locations in the system appears.

4. Select **Mirror Locations**.

A list of mirror locations in the system appears.

5. Right-click the mirror location from which you want to remove a machine (or select **☰**), and then select **Remove Server Machine**.

The **Remove Server Machine: <mirror location>** window appears, displaying a list of machines in the mirror location.

6. Select the machine that you want to remove, and then select **Remove**.

A message appears, asking you to confirm that you want to remove the machine from the mirror location.

7. Select **Remove**.

The machine is removed from the mirror location.


Delete a Mirror Location

Delete all the data stores in the mirror location; you cannot delete a mirror location if it contains a data store.

1. [Access Configuration Hub \(on page 336\)](#).

2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
The **Systems** section appears, displaying a list of systems.

3. Right-click the system in which you want to delete a mirror location (or select **☰**), and then select **Browse Locations**.



A list of distributed locations in the system appears.

4. Select **Mirror Locations**.

A list of mirror locations in the system appears.

5. Right-click the mirror location that you want to delete (or select **☰**), and then select **Delete Mirror Location**.

A message appears, asking you to confirm that you want to delete the mirror location.

6. Select **Delete**.

The mirror location is deleted.

Managing Data Stores

About Data Stores

A data store is a logical collection of tags. It is used to store, organize, and manage tags according to the data source and storage requirements. A data store can have multiple archive files (*.IHA), and includes both logical and physical storage definitions.

Tags can be segregated into separate archives through the use of data stores. The primary use of data stores is to segregate tags by data collection intervals. For example, you can put a name plate or static tags where the value rarely changes into one data store, and your process tags into another data store. This can improve query performance.

Historian data stores are stored as archive files that contain data gathered from all data sources during a specific period of time. You can write and read data from the archive files.

You can define two types of data stores:

- **Historical Data Store:** Tags stored under historical data store will store data as long as the disk space is available. Depending on your license, you may be able to create multiple historical data stores. The maximum number of historical data stores supported depends on the license.
- **SCADA Buffer Data Store:** Tags stored under the SCADA buffer data store will store data for a specific duration of time based on license.

When you install the Historian server, two historical data stores are installed by default.

- **System:** Stores Historian messages and performance tags. This is only for internal usage within Historian, and you cannot add tags to this data store. You cannot rename or delete the system data store.
- **User:** Stores tag data. This is a default data store. You can rename and delete a user data store as long as there is another default data store set for tag addition.

Based on your license, a SCADA Buffer data store may also be installed. It stores short-term tags and data.

Create a Data Store

The number of data stores that you can create depends on your license.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**. Alternatively, you can select **Systems**, right-click the system in which you want to create a data store (or select **☰**), and then select **Browse Data Stores**.
The **Data Stores** section appears.
3. Select **+**.
If Historian Standard version, then the **Add Data Store** window appears.

If Historian Enterprise version, then the **Add Data Store: <location name>** window appears.
4. Enter values as described in the following table.

Field	Description
DATA STORE NAME	Enter a unique name for the data store. A value is required. You can use all alphanumeric characters and special characters except / \ * ? < >
DESCRIPTION	Enter a description for the data store.

Field	Description
LOCATION	Enter the host name or IP address of the distributed location on which you want to create the data store. This field is available only for a horizontally scalable system.
Is Default	Switch the toggle on if you want to set this data store as the default one. A default data store is the one that is considered if you do not specify a data store while adding a tag. You can set only one data store as default.

5. Select .

The data store is created.

When you add tags to the data store, it will have its own set of .IHA (iHistorian Archive) files. Ensure that you back up the new data store archives periodically.

Access a Data Store

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**. Alternatively, you can select **Systems**, right-click the system in which the data store is available (or select ), and then select **Browse Data Stores**. The **Data Stores** section appears.
3. Select the data store that you want to access. The **DETAILS** section displays the following details of the data store.

Table 19. General

Field	Description
Data Store Name	The name of the data store. A value is required and must be unique for the system.
Description	The description of the data store.
State	The current state of the data store: <ul style="list-style-type: none"> ◦ Running: Indicates that the data store is actively storing data. ◦ Stopped: Indicates that the data store is not storing data. This field is read-only.

Field	Description
Location	The host name or IP address of the distributed location on which the data store has been created. This field is available only for a horizontally scalable system. It is disabled.
Storage Type	<p>The storage type of the data store, which can be one of the following values:</p> <ul style="list-style-type: none"> ◦ Historical: Tags stored in a historical data store will store data as long as disk space is available. The maximum number of Historical data stores supported depends on the license. ◦ SCADA Buffer: Tags stored under SCADA buffer data store will store data for a specific duration of time based on license. <p>This field is disabled.</p>
System Default Storage	Indicates whether the data store is a default one. If yes, while creating a tag, this data store will be used by default.
Number of Tags	The number of tags in the data store. For instructions on how to add a tag, refer to Add Tags for the Data Store Using Configuration Hub (on page 357) and Add a Tag Manually (on page 473) .

Table 20. Archive Creation

Field	Description
Create Archive By	<p>Indicates whether you want to create a new archive automatically after the current one reaches a specific size or after a specific duration. This field is enabled only if you switch the Automatically Create Archives toggle on.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Size: Select this option if you want to create a new archive when the current one reaches a specific size. Specify the size in the Default Size (MB) field (which appears only if you select Size).

Field	Description
	<ul style="list-style-type: none"> ◦ Days or Hours: Select one of these options if you want to create a new archive after a specific duration. Specify the duration in the Archive Duration field (which appears only if you select Days or Hours).
Default Size (MB)	The default size of an archive after which a new one will be automatically created if you switch the Automatically Create Archives toggle on. The Default Size (MB) field appears only if you select Size in the Create Archive By field.
Automatically Create Archives	Indicates whether you want to create an archive automatically (on page 727) after the current one is full. An archive file is considered full based on the size or duration you specify in the Create Archive By and the Archive Duration or Default Size fields.
Overwrite Old Archives	<p>Indicates whether you want to overwrite an old archive file when a new one is created.</p> <p>If you enable this option, the oldest archived data is replaced with the latest one when the latest archive default size is reached. Since this action deletes historical data, exercise caution in using this feature. Be sure that you have a backup of the archive so that you can restore it later. Best practice is to create an additional archive to prevent premature loss of data due to overwriting. For example, if you want to save 12 months of data into 12 archives, create 13 archives.</p>
Archive Duration	The duration after which a new archive will be automatically created if you switch the Automatically Create Archives toggle on. The Archive Duration field appears only if you select Days or Hours in the Create Archive By field.
Multiple Archive Paths	Indicates whether you want to create multiple archive paths for the selected data store. This field allows you to back up your high-volume archives to another storage path, for example, an external storage disk. For more information, refer to about multiple archive path (on page 464) and configure multiple archive paths (on page 468) .

Table 21. Maintenance


Field	Description
Default Archive Path	The default folder in which you want to create archives.
Default Backup Path	The default folder in which you want to place the backup archives.
Base Archive Name	A prefix that you want to add to all the archive name.
Base Archive Filename	A prefix that you want to add to all the archive filenames.
Free Space Required (MB)	<p>Indicates the remaining disk space required after a new archive is created. If the available space is less than the requirement, a new archive is not created. The default value is 5000 MB.</p> <p>This field is not applicable to alarms and events archives. The alarms and events archiver will continue writing to the alarms and events archive until the drive is full. If this occurs, the alarms and events archiver will buffer incoming alarms and events data until the drive has free space. An error message is logged in the Historian message log.</p>
Store OPC Quality	Indicates whether OPC data quality is stored.
Use Caching	Indicates whether caching is enabled. When reading data from the archiver, some data is saved in the system memory and retrieved using caching. This results in faster retrieval as the data is already stored in the buffer.
Stale Period (Days)	Indicates the number of days after which the data store is considered stale.
Stale Period Check (Days)	Indicates the number of days or the frequency for checking data store validity.

Table 22. Security

Field	Description
Data is Read-Only After (Hours)	The number of hours for data to be stored in a read/write archive. After the time lapses, that portion of the archive file is automatically made read-only. Incoming data values with timestamps prior to this time are rejected. A single archive file, there-

Field	Description
	fore, may have a portion made read-only, another portion that is read/write containing recently written data, and another that is unused free space.
Generate Message on Data Update	Indicates whether an audit log entry will be made any time the value of a previously archived data point is overwritten. This log entry will contain both the original and new values.
Read Group	<p>The Windows security group that can retrieve the tag data and plot it in a trend chart for the selected data store.</p> <p>For example, if you select a group with power users, in addition to members of the iH Security Admins group, only a member of the power users group will be able to read data of the tags for that data store. Even a member of the iH Readers group will not be able to access data of the tags for the selected data store, unless they are also defined as a member of the power users group.</p>
Write Group	The Windows security group that can write tag data for the selected data store (for example, using the Excel Add-in for Historian).
Administer Group	The Windows security group that can create, modify, and delete the tags for the selected data store.
For more information, refer to implementing Data store-level security (on page 292) .	
<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px;">  Note: When it comes to the group security, the security settings applied at the tag level, if any, take the precedence over those at the data store level. </div>	

4. As needed, modify values in the available fields.
5. In the upper-left corner of the page, select **Save**.



The data store is modified.

Rename a Data Store

You cannot rename the system data store. You can rename a user data store as long as there is another default data store set for tag addition.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**. Alternatively, you can select **Systems**, right-click the system in which the data store is available (or select **☰**), and then select **Browse Data Stores**.

The **Data Stores** section appears.

3. Select the data store that you want to access.
The details section displays the following details of the data store.

Table 23. General

Field	Description
Data Store Name	The name of the data store. A value is required and must be unique for the system.
Description	The description of the data store.
State	The current state of the data store (whether it is running). This field is disabled.
Location	The host name or IP address of the distributed location on which the data store has been created. This field is available only for a horizontally scalable system. It is disabled.

Field	Description
Storage Type	<p>The storage type of the data store, which can be one of the following values:</p> <ul style="list-style-type: none"> ◦ Historical: Tags stored in a historical data store will store data as long as disk space is available. The maximum number of Historical data stores supported depends on the license. ◦ SCADA Buffer: Tags stored under SCADA buffer data store will store data for a specific duration of time based on license. <p>This field is disabled.</p>
System Default Storage	<p>Indicates whether the data store is a default one. If yes, while creating a tag, this data store will be used by default.</p>
Number of Tags	<p>The number of tags in the data store. For instructions on how to add a tag, refer to Add Tags for the Data Store Using Configuration Hub (on page 357) and Add a Tag Manually (on page 473).</p>

Table 24. Archive Creation

Field	Description
Automatically Create Archives	<p>Indicates whether you want to create a new archive (on page 723) automatically after the current one is full. An archive file is considered full based on the size or duration you specify in the Create Archive By and the Archive Duration or Default Size fields.</p>
Overwrite Old Archives	<p>Indicates whether you want to overwrite an old archive file when a new one is created.</p> <p>If you enable this option, the oldest archived data is replaced with the latest one when the latest archive default size is reached. Since this action deletes historical data, exercise caution in using this feature. Be sure that you have a backup of the archive so that you can restore it later. Best practice is to create an additional archive to prevent premature loss of data due to</p>

Field	Description
	overwriting. For example, if you want to save 12 months of data into 12 archives, create 13 archives.
Create Archive By	<p>Indicates whether you want to create a new archive automatically after the current one reaches a specific size or after a specific duration. This field is enabled only if you switch the Automatically Create Archives toggle on.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Size: Select this option if you want to create a new archive when the current one reaches a specific size. Specify the size in the Default Size (MB) field (which appears only if you select Size). ◦ Days or Hours: Select one of these options if you want to create a new archive after a specific duration. Specify the duration in the Archive Duration field (which appears only if you select Days or Hours).
Default Size (MB)	The default size of an archive after which a new one will be automatically created if you switch the Automatically Create Archives toggle on. The Default Size (MB) field appears only if you select Size in the Create Archive By field.
Archive Duration	The duration after which a new archive will be automatically created if you switch the Automatically Create Archives toggle on. The Archive Duration field appears only if you select Days or Hours in the Create Archive By field.

Table 25. Maintenance


Field	Description
Default Archive Path	The default folder in which you want to create archives.
Default Backup Path	The default folder in which you want to place the backup archives.
Base Archive Name	A prefix that you want to add to all the archive files.
Free Space Required (MB)	Indicates the remaining disk space required after a new archive is created. If the available space is less than the requirement, a new archive is not created. The default value is 5000 MB.

Field	Description
	This field is not applicable to alarms and events archives. The alarms and events archiver will continue writing to the alarms and events archive until the drive is full. If this occurs, the alarms and events archiver will buffer incoming alarms and events data until the drive has free space. An error message is logged in the Historian message log.
Store OPC Quality	Indicates whether OPC data quality is stored.
Use Caching	Indicates whether caching is enabled. When reading data from the archiver, some data is saved in the system memory and retrieved using caching. This results in faster retrieval as the data is already stored in the buffer.

Table 26. Security

Field	Description
Data is Read-Only After (Hours)	The number of hours for data to be stored in a read/write archive. After the time lapses, that portion of the archive file is automatically made read-only. Incoming data values with timestamps prior to this time are rejected. A single archive file, therefore, may have a portion made read-only, another portion that is read/write containing recently written data, and another that is unused free space.
Generate Message on Data Update	Indicates whether an audit log entry will be made any time the value of a previously archived data point is overwritten. This log entry will contain both the original and new values.

4. As needed, modify values in the available fields.
5. In the upper-left corner of the page, select **Save**.




The data store is modified.

Set a Default Data Store

A default data store is the one that is considered if you do not specify a data store while adding a tag.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**.
Alternatively, you can select **Systems**, right-click the system in which the data store is available (or select ) , and then select **Browse Data Stores**.
3. Select the system whose default data store you want to change.
The details of the system appear in the **DETAILS** section.
4. Under **System Defaults**, next to **Default Data Store**, select  .
The **Default Data Store: <data store name>** window appears, displaying a list of data stores in the system.
5. Select the data store that you want to set as default, and then select **Set as Default**.
6. In the upper-left corner of the page, select **Save**.



The data store is set as default.

Access the Archives in a Data Store

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**.
Alternatively, you can select **Systems**, right-click the system in which the data store is available (or select **ooo**), and then select **Browse Data Stores**.

The **Data Stores** section appears.

3. Right-click the data store whose archives you want to access (or select **ooo**), and then select **Browse Archives**.

The archives in the data store appear, indicating the current one and the old ones.

Apply the Configuration Template to a Data Store

You can apply the created template to user-created data store as needed. You will be prompted to confirm whether you want to overwrite few of the configuration values with the values in the template.

- Ensure that you have a [data store created \(on page 370\)](#).
- Ensure that you have a [configuration template for data stores \(on page 767\)](#).


This topic describes how to apply a data store configuration template to a data store. You can apply a data store configuration template to a user-created data store, provided they are not the default data store.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**.
The **Data Stores** section appears.
3. Right-click the data store (or select **ooo**), and then select **Apply Configuration Template**.

DATA STORE NAME	STATE	DEFAULT	NUMBER OF TAGS	STORAGE TYPE
DHSSystem	Running	False	0	Historical
Historical_Data_Store	Running	False	0	Historical
ScadaBuffer	Running	False	0	ScadaBuffer
User (Default)	Running	True	12,546	Historical

FIELD	VALUE
GENERAL	
Data Store Name	Historical_Data_Store
Description	This is a Data Store fo...
State	Running
Browse Tags	Historical
Add Tags	ScadaBuffer
View Data Store Performance	<input type="checkbox"/>
Browse Archives	0
Browse Activity Log	<input type="checkbox"/>
Apply Configuration Template	Size
Delete	500
Automatically Create ...	<input type="checkbox"/>
Overwrite Old Archiv...	<input type="checkbox"/>
MAINTENANCE	
Default Archive Path	C:\Proficy Historian D...

The **Apply Configuration Template** window appears, listing the available templates.



Note:

You can apply a data store configuration template to a user-created data store, provided they are not the default data store.

4. Select **Apply**.

A confirmation window appears, prompting you to confirm whether you want to overwrite few of the configuration values with the values in the template.

5. Select **Ok**.

6. In the upper-left corner, select **Save**.

The configurations in the template are applied to the data store.

Multiple Archive Paths

About Multiple Archive Paths

Multiple archive paths feature extends the ability to configure a default archive path for each data store.

This feature enables you to automatically store your archives in different locations based on the age of the archive. It can be useful when splitting the data for a data store across multiple hard drives, primarily for performance and cost optimization. Additionally, it could help optimize disk space constraints.

For instance, in a performance and cost optimization scenario, the most recent data could reside on a fast/expensive NVMe or SSD drive, intermediate data on a slower/cheaper local HDD, and older data on even slower/cheaper long-term storage (for example, NAS or cloud). The requirement for the drive is that it must be mapped to the Historian server node as a drive or folder and accessible by the DataArchiver service. For example, it could be a shared drive such as \\Server\HistorianData mapped to H:\HistorianData. The physical location of the drive does not matter if the DataArchiver service can access it.

**Note:**

There are many sources of drives and various methods to map them. The Historian team has not tested all possibilities and cannot guarantee compatibility with every configuration. However, if the drive can be accessed (with read and write permissions) by the DataArchiver service, it will likely function properly.

About Multiple Archive Path Configuration

Configuration for multiple archive paths can be done on a per-data store basis. Additionally, each data store could have different configurations, so you can decide whether you want to configure multiple archive paths for all the data stores or not. When configuring the archive paths, you can specify a path and an age.

Where,

The age defines how far in the past the archive end time must be before it could be moved.

The path is the directory where the archive will be moved to.

Once the end time of the archive becomes older than the current time minus the age, the archive will be moved. Since moving an archive can be a slow process, ensure that the archive is not modified during the move. Therefore, only archives that have become read-only can be moved. Archives become read-only when their end time is older than the **Data is Read Only After (Hours)** property. Therefore, be sure to set your time offsets greater than this property. If you set it smaller than this property, then the value of the property is used instead.

The duration of the move depends on the size of the archives and the speed of the source and destination disks. During the move, the source archive is still available for reading. Once the move has completed successfully, the source archive is deleted.

A move is stopped in the following scenarios:

- If a move failure occurs: The move is stopped, and an appropriate message is logged in the log file. The move retires later.
- If system shuts down during the move: The move is stopped. Since archives are being moved and deleted during this process, it is important to have proper backups of the system in case errors occur.



Note:

When configuring archive paths in a Mirror setup, the configured paths must exist on all mirror nodes.

Example of Multiple Archive Paths

Consider that your system setup includes the following:

- A fast NVME drive (N:), though not very large.
- A slow HDD (H:), which is larger compared to the fast NVME drive (N:).
- A remote NAS drive mapped to (Z:), the largest of the three drives.



Note:

All the three drives use the \Proficy Historian Data\Archives directory.

Your system design requirement is to have your frequently used data on the NVME for the best performance. The NVME drives greatly improve read and write performance than the traditional HDDs. Looking at your data access needs, data storage rate, and the NVME size, you decide to have three months of data there. You do the same for the HDD and decide to have nine months of data there. Data older than that goes to the NAS drive. For a simpler understanding, let us consider that you decide to have daily archives. Finally, you decide that data becomes read-only in a month.

Before you configure multiple archive paths, know the following:

- The multiple archive paths feature is available for any data store other than the System data store.
- While moving archives can be helpful, if not managed well, it may strain disk resources and impact system performance. Although it is ensured that system performance is not impacted by moving

archives, it is recommended that you move archives in smaller sizes and be mindful that your configurations do not affect system performance.

- Archive performance, particularly read performance, is crucial to be considered. When data is moved to slower drives, slower read performance is expected, but this is acceptable only for data on those slower paths. Data reads on faster paths should remain unaffected. To manage this, the Historian treats all paths except the default one as "slower" locations. Determining which archives are needed for queries can be challenging until after the query is executed.

For instance, queries like "Raw By Number" reading backwards could require access to any archive in the past. However, queries with specific time ranges reveal which archives will be necessary. If the system identifies that archives on these "slower" drives are required, the query will be executed at a lower priority using Low Priority Read Threads. The configured number of read threads is divided into three categories: High, Medium, and Low, each with its specific number of threads. Additionally, each category can utilize lower priority threads if necessary.

For example, a high priority query initially uses a High priority thread but can use a Medium or Low priority thread if all high priority threads are busy. The same flexibility applies to Medium priority queries. It is important to note that thread priority does not affect Windows thread priority; all threads run at the same Windows priority level, so executing queries on Low Priority threads does not affect their performance. Instead, it operates as a thread reservation system. By identifying and assigning "slow" queries to Low priority threads, High and Medium threads remain available for other queries. Generally, most queries are Medium priority unless programmatically changed. You must determine the appropriate number of read threads to configure to ensure adequate resources are provided.

Example Configuration procedure

1. Configure the default path. This can be done in the same way as you do for data stores. In this example, this is set to N:\Proficy Historian Data\Archives.
2. [Configure the archive locations \(on page 468\)](#) based on the time.

Time Offset (Hours)	Path
2232 (3 months)	h:\Proficy Historian Data\Archives
8760 (1 year)	Z:\Proficy Historian Data\Archives

Based on the configuration, the DataArchiver will periodically look if any archives need to be moved. Only archives that are closed (that is, are time-based or have a fixed end time), and are read-only will be checked. The DataArchiver will check the archive's end time against each configured age, from smallest to

largest. The first age where the archive end time is older will be used to determine the directory to which the archive must move to.

So, based on this example, the following will happen:


1. The newly created archive will go into the normal default path, that is, N:\Proficy Historian Data\Archives. That archive will exist and be written to until after a month. At that point, it will become read-only because that is what was configured.
2. When the archive is three months (2232 hours) old, the DataArchiver will move the archive to H:\Proficy Historian Data\Archive, as the end time is older than the 2232 hours that you configured and less than the 8760 hours. If the move is successful, the original archive is deleted. This process will repeat when the archive is older than 8760 hours.
3. Then it will be moved to Z:\Proficy Historian Data\Archives. Here it will stay unless the configuration is changed. If, for example, the 8760 was changed to 16520, then an archive that was 10000 hours old would be moved back to H:\Proficy Historian Data\Archives.

Configure Multiple Archive Paths


Multiple archive paths feature extends the ability to configure a default archive path for each data store.

- Ensure that you read [about multiple archive paths \(on page 464\)](#).
- You already have a **Default Archive Path** configured for this data store.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**. The **Data Stores** section appears.
3. Select the data store as needed. The **DETAILS** section displays the details of the data store.
4. In the **ARCHIVE CREATION** group, in the **Multiple Archive Paths** property, select .



The **Multiple Archive Paths Configuration** window appears.



ARCHIVE PATH *	DURATION (HOURS) *
D:\Proficy Historian Data	744

+ Add Path

Cancel Done

5. In **ARCHIVE LOCATION**, enter the path as needed.
6. In **DURATION (HOURS)**, enter a duration after which the archive files should be transferred to the specified path.



Note:

The duration you specify must be greater than the archive hours specified in **Data is Read-Only After (Hours)** property.

7. To add more paths, select **Add Path**.
8. After you add the paths and duration as needed, select **Done**.

The specified multiple archive paths are added. The archive files in the existing path will be transferred to the new path after the specified duration from their creation or modification.

Access the Activity Logs of a Data Store

Activity logs are generated when activities are performed on tags and collectors in a data store.

Examples:

- When a tag is created, modified, or deleted
- When a collector instance is created, modified, or deleted
- When data collection for a tag or a collector begins or ends
- When an archive is created or will be closed soon

You can access these logs for each tag/collector or for all the tags and collectors in a system. You can filter these logs based on the start and end dates, priority, topics, and the content in the logs. You can also export all the logs or selected ones.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**.
Alternatively, you can select **Systems**, right-click the system in which the data store is available (or select **☰**), and then select **Browse Data Stores**.
The **Data Stores** section appears.
3. Right-click the data store whose archives you want to access (or select **☰**), and then select **Browse Activity Logs**.
The activity logs of the data store appear. You can filter on the Start Time and End Time along with other fields to search for activity log.

Access the Tags in a Data Store

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**.
Alternatively, you can select **Systems**, right-click the system in which the data store is available (or select **☰**), and then select **Browse Data Stores**.
The **Data Stores** section appears.
3. Right-click the data store whose tags you want to access (or select **☰**), and then select **Browse Tags**.
The tags in the data store appear, indicating the current status of the data collection for each tag.


Add Tags for the Data Store Using Configuration Hub

- Add the collector instance (on page 357) using which you want to collect data. Ensure that the collector is running.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, create it (on page 370).

This topic describes how to specify the tags for which you want to collect data by browsing through the tags in the data source. For example, for an iFIX collector, if there are 1,00,000 tags in the iFIX server, you must specify the ones for which you want to collect data. Only then data is collected for those tags.

In addition to adding tags from the data source, you can create tags manually (on page 473).

1. Access Configuration Hub (on page 336).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **+**.



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. A value is required.
COLLECTED TYPE	Specify whether you want to browse through all the tags in the data source or only from the tags that you have not added yet. A value is required.

Field	Description
SOURCE TAG NAME	Enter the name of the tag (either completely or partially) to narrow down the search results.
SOURCE TAG DESCRIPTION	Enter the description of the tag (either completely or partially) to narrow down the search results.

5. Select **Search Tags**.

A list of tags that match *all* the criteria that you have specified appears. If a tag is already added, it is disabled.

6. Select the check box corresponding to each tag for which you want to collect data.

Add Tags from Collector Add Manually

COLLECTOR NAME* COLLECTED TYPE* SOURCE TAG NAME SOURCE TAG DESCRIPTION

[Redacted]_Simulation All Source Tags * *

[Search Tags](#)

SEARCH RESULTS FOR SOURCE TAGS NAMES

<input type="checkbox"/>	TAG NAME	DESCRIPTION
	<i>Filter</i>	<i>Filter</i>
<input type="checkbox"/>	[Redacted] Simulation.Simulation00001	[Redacted] Simulation.Simulation00001
<input type="checkbox"/>	[Redacted] Simulation.Simulation00002	[Redacted] Simulation.Simulation00002
<input type="checkbox"/>	[Redacted] Simulation.Simulation00003	[Redacted] Simulation.Simulation00003
<input type="checkbox"/>	[Redacted] Simulation.Simulation00004	[Redacted] Simulation.Simulation00004
<input type="checkbox"/>	[Redacted] Simulation.Simulation00005	[Redacted] Simulation.Simulation00005
<input type="checkbox"/>	[Redacted] Simulation.Simulation00006	[Redacted] Simulation.Simulation00006
<input type="checkbox"/>	[Redacted] Simulation.Simulation00007	[Redacted] Simulation.Simulation00007
<input type="checkbox"/>	[Redacted] Simulation.Simulation00008	[Redacted] Simulation.Simulation00008
<input type="checkbox"/>	[Redacted] Simulation.Simulation00009	[Redacted] Simulation.Simulation00009
<input type="checkbox"/>	[Redacted] Simulation.Simulation00010	[Redacted] Simulation.Simulation00010
<input type="checkbox"/>	[Redacted] Simulation.Simulation00011	[Redacted] Simulation.Simulation00011
<input type="checkbox"/>	[Redacted] Simulation.Simulation00012	[Redacted] Simulation.Simulation00012

DATASTORE*
User

7. In the **DATA STORE** field, if you want to store the data in a different data store than the user data store, select the same.

8. Select **Add Tag**.

Data collection begins for the selected tags.


As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.

Add a Tag Manually

- Add the collector instance ([on page 357](#)) using which you want to collect data.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, [create it \(on page 370\)](#).

After you create a collector instance, you [specify which tags from the source must be used for data collection \(on page 357\)](#). In addition, if you want to use the same tag twice (say, with a different collection interval or collector compression settings), you can add the tag manually. You can also create a calculation tag or a tag to store the values imported using the Excel Add-in.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **+**.



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Select **Add Manually**.

Add Tags from Collector
 Add Manually

COLLECTOR NAME* Select..
 COLLECTED TYPE* All Source Tags
 SOURCE TAG NAME *
 SOURCE TAG DESCRIPTION *

SEARCH RESULTS FOR SOURCE TAGS NAMES



Click on 'Search Tags' to view results

DATASTORE*

5. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. If, however, this tag is not associated with a collector, you can leave the field blank (for example, you want to ingest this data manually instead of using a collector).
SOURCE ADDRESS	Specify the source tag to which you want to map the one you are creating. This field is enabled only if you select a value in the COLLECTOR NAME field. When you select □□□ , the Browse Source Tag: <collector name> window appears. Provide the search criteria to find the tag that you want to map.
TAG NAME	<p>Enter a name for the tag. A value is required and must be unique for the Historian server.</p> <p>The value that you enter:</p> <ul style="list-style-type: none"> ◦ Must begin with a letter or a number. ◦ Can contain up to 256 characters.

Field	Description
	<ul style="list-style-type: none"> ◦ Can include any of the following special characters: /! #{}%\$-_ ◦ Must not include a space or any of the following characters: ~`+^;,:?*"=@
DATA TYPE	<p>Select the data type of the tag data. To find out the data types supported by a collector, refer to the documentation on the collector that you have created.</p> <div style="border: 1px solid #ffc107; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Important: If you select an unsupported data type, you may receive incorrect data or even lose data.</p> </div> <p>If you select Multi-Field, the USER-DEFINED TYPE NAME field appears, and the ENUMERATED SET and ARRAY TAG fields are disabled.</p> <p>If you select Fixed String, the STRING LENGTH field appears.</p>
STRING LENGTH	<p>Enter the maximum character length allowed for the tag data. This field appears only if the value in the DATA TYPE field is Fixed String. A value is required.</p> <p>You can enter a value between 1 and 255. The default value is 8.</p>
USER-DEFINED TYPE NAME	<p>Select the user-defined data type (UDT) (on page 719) that you want to assign to the tag. This field appears only if the value in the DATA TYPE field is Multi-Field. A value is required.</p>
ENUMERATED SET	<p>Select the enumerated set (on page 707) that you want to assign to the tag. This field is not applicable for string and multi-field data types (enumerated sets) and for array tags.</p>
ARRAY TAG	<p>Switch the toggle to indicate whether the tag stores an array of data. This field is disabled if you select a value in the ENUMERATED SET field or if the value in the DATA TYPE field is Multi-Field.</p> <p>For information on array tags, refer to About Array Tags (on page 660).</p>

Field	Description
TIME RESOLUTION	<p>Select the time resolution for the tag. A value is required.</p> <p>For example, if you select Seconds, when you plot the data on a trend chart, the timestamp of the data points will be one second apart.</p>
DATA STORE	<p>If you want to store the data in a different data store than the user data store, select the same.</p>

6. Select **Add Tag**.

Data collection begins for the selected tags.

As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.

View the Performance of a Data Store

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**. Alternatively, you can select **Systems**, right-click the system in which the data store is available (or select **☰**), and then select **Browse Data Stores**. The **Data Stores** section appears.
3. Right-click the data store whose performance you want to access (or select **☰**), and then select **View Data Store Performance**. The performance of the data store appears, displaying the following information.

Field	Description
ARCHIVE COMPRESSION	<p>The current effect of archive data compression. If the value is zero, it indicates that archive compression is either ineffective or disabled. To increase the effect of data compression, increase the value of archive compression deadbands on individual tags.</p> <p>In calculating the effect of archive compression, Historian counts internal system tags as well as data source tags. Therefore, when working with a very small number of tags and with compression disabled on data source tags, this field may indicate a value other than zero. If you use a realistic number of</p>

Field	Description
	tags, however, system tags will constitute a very small percentage of total tags and will therefore not cause a significant error in calculating the effect of archive compression on the total system.
WRITE CACHE HIT	The hit ratio of the write cache in percentage of total writes. It is a measure of how efficiently the system is collecting data. Typically, this value should range from 95 to 99.99%. If the data is changing rapidly over a wide range, however, the hit percentage drops significantly because current values differ from recently cached values. More regular sampling may increase the hit percentage. Out-of-order data also reduces the hit ratio.
RECEIVE RATE	Indicates how busy the server is at a given instance and the rate at which the server is receiving data from collectors.
FREE SPACE	Indicates how much disk space (in MB) is left in the current archive.
CONSUMPTION RATE	Indicates how fast the archive disk space is consumed. If the value is too high, you can reduce it by slowing the poll rate on selected tags or data points or by increasing the filtering on the data (widening the compression deadband to increase compression).
EST. DAYS TO FULL	<p>Indicates how much time is left before the archive is full, based on the current consumption rate. This value is dynamically calculated by the server and becomes more accurate as an archive file gets closer to completion. This value is only an estimate and will vary based on a number of factors, including the current compression effectiveness. The system sends messages notifying you at 5, 3, and 1 days until full. After the archive is full, a new archive must be created (can be automatic or manual).</p> <p>To increase this value, you must reduce the consumption rate. To ensure that collection is not interrupted, make sure that the Automatically Create Archives option is enabled.</p> <p>You may also want to enable the Overwrite Old Archives option if you have limited disk capacity. Enabling this option, however,</p>

Field	Description
	means that some old data will be lost when new data overwrites the data in the oldest online archive. Use this feature only when necessary.
FAILED WRITES	<p>Indicates the number of samples that failed to be written. Since failed writes are a measure of system malfunctions or an indication of offline archive problems, this value should be zero. If you observe a non-zero value, investigate the cause of the problem and take corrective action.</p> <p>Historian also generates a message if a write fails. Note that the message only appears once per tag, for a succession of failed writes associated with that tag. For example, if the number displayed in this field is 20, but they all pertain to one Historian tag, you will only receive one message until that Historian tag is functional again.</p>
ALERTS SINCE STARTUP	Indicates a count of system warnings or alerts generated since the last startup. A high value here may indicate a problem of some kind. You should review the alerts and determine the probable cause. The count resets to zero on restart. The message database, however, may contain more alerts than this value.
MESSAGE SINCE STARTUP	Displays a count of system messages generated since the last startup. The system resets the value to zero on restart. The message database, however, may contain more messages than this value.

Delete a Data Store

The following conditions apply when deleting a data store:

- You cannot delete the system data store.
- You cannot delete a data store if it contains tags. If you remove the tags from the system or permanently delete them, you can delete the data store. However, the archives are not deleted.
- You cannot delete the default data store. You can delete a user data store as long as there is another default data store set for tag addition.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**.
The **Data Stores** section appears.
3. Right-click the data store that you want to delete (or select ) , and then select **Delete**.
A message appears, asking you to confirm that you want to delete the data store.
4. Select **Delete**.
The data store is deleted. However, the archives in the data store are not deleted.

Adding a Collector Instance


Add and Configure a Calculation Collector

Using the Calculation collector, you can perform data calculations on values already in the archiver. It retrieves data from tags in the Historian archive, performs the calculation, and then stores the resulting values into new archive tags.

You can create a Calculation collector only for an on-premises Historian server, not for a cloud destination.

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select  .



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Calculation Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears. The **HISTORIAN SERVER** field is disabled and populated.

7. Select **Next**.

The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default; the other options are disabled. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the value you selected in the **MACHINE NAME** field in the **Collector Selection** section.

8. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

9. Select **Next**.

The **Collector Initiation** section appears.

10. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
 - Must not exceed 15 characters.
 - Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
11. In the **RUNNING MODE** field, select one of the following options.
- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
 - **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

12. Select **Add**.


The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

13. Under **COLLECTOR SPECIFIC CONFIGURATION**, configure values as described in the following table.

Field	Description
Calculation Timeout (sec)	The maximum time a calculation must be performed before being terminated. The default value is 10 seconds. If the calculation takes longer, it is cancelled, and a bad data quality sample is stored in the destination tag with a subquality, calculation error.
Max Recovery Time (hr)	The maximum time, in hours till now, that the collector will attempt to restore data. This is applicable only to event-based tags. The default value is 4 hours. If you want to disable automatic calculation of the tag, set the value of this field to 0.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.

Field	Description
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

- If needed, enter values in [the other sections \(on page 579\)](#).
- In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

- If needed, restart the collector.

[Specify the tags \(on page 357\)](#) whose data you want to collect using the collector.

Add and Configure a CygNet Collector

A CygNet collector collects data from a CygNet server and stores it in the Historian server. For more information, refer to [Overview of the CygNet Collector \(on page 2167\)](#).




Note:

You cannot send data to a cloud destination using a CygNet collector.

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

- [Access Configuration Hub \(on page 336\)](#).
- In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
- In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Cygnnet Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. In the **SERVER SITE** field, enter the host name or IP address of the CygNET server from which you want to collect data.

8. Select **Next**.

The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default; the other options are disabled.

9. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: `<Historian server name>_Cygnet`

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must contain the string `CygnEt`.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.


14. Under **COLLECTOR SPECIFIC CONFIGURATION**, configure values as described in the following table.

Field	Description
Re-covery Time	<p>The maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the CygNet server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>By default, this value is set to 0, which means data recovery is not attempted. The maximum value you can provide is 168 hours (that is, 7 days).</p>

Field	Description
Thread Count	The maximum number of threads that you want collector to use to query data from the CygNet server.
CygNet Debug Mode	<p>The debug mode for the collector. You can enter a value between 0 and 255, where 0 turns off debugging and 255 enables detailed debugging (with query transactions).</p> <div data-bbox="386 493 1421 718" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Do not turn on debugging for a long period. If you do so, very large log files are created, which can consume a great deal of disk space. We recommend a maximum of 10 minutes.</p> </div>
General Optimized	Indicates whether you want to apply optimization on the tag data reads.
Service-Site	Identifies the CygNet site or data source from which the CygNet collector collects data. A value is required.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

15. If needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags (on page 357) whose data you want to collect using the collector.

Add and Configure a File Collector

A File collector is used to send data from one Historian server to another one.




Note:

- You cannot send data to a cloud destination using the File collector.
- You can create only one instance of the File collector.

For more information, refer to [Overview of the File Collector \(on page 2181\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance. The collector will send data to this machine.
5. In the **COLLECTOR TYPE** field, select **File Collector**, and then select **Get Details**.
The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.
6. Select **Next**.

The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default; the other options are disabled.

7. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

8. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: `<Historian server name>_File`

9. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.


- Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
10. In the **RUNNING MODE** field, select one of the following options.
- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
 - **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

11. Select **Add**.
- The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.
12. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
Scan Interval	The interval, in seconds, after which the collector initiates an import operation. The maximum value that you can enter is 65.
CSV File Spec	The file extension for a CSV file to be imported. You can specify more than one extension type, such as csv, txt, dat.
XML File Spec	The file extension for an XML file to be imported.
Purge Processed (days)	The number of days after which you want the contents of the <code>Processed Files</code> folder to be automatically purged.
Purge Error (days)	The number of days after which you want the contents of the <code>Error Files</code> folder to be automatically purged.

13. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).
14. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.


15. If needed, restart the collector.

[Import files using the collector \(on page 2188\).](#)

Add and Configure a HAB Collector

The HAB collector collects data from Habitat, which is a SCADA application that contains real-time data. The collector interacts with the Habitat Sampler application to fetch data from the Habitat database records and stores the data in a Historian server. For more information, refer to [Overview of the HAB Collector \(on page 2208\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. On the right, next to Settings in the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Hab Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. Enter values as described in the following table.

Field	Description
SERVER SITE	Enter name that you want to assign to the site. A value is required and must be unique. It is used by Habitat to identify the collector instance. By default, this field is populated with a value in the following format: <code><Historian server name>Hab</code>
SERVER 1 (under NODE 1)	Enter the host name or IP address of the Habitat server in the primary site from which you want to collect data. This server acts as the primary/active server from which the collector receives data. A value is required.
SERVER 1 (under NODE 2)	Enter the host name or IP address of the Habitat server in the second/backup site from which you want to collect data. This server acts as a standby server in case server 1 under node 1 fails. A value is required. If you do not have a secondary/backup site, enter the same value as SERVER 1 under node 1.
SERVER 2 (under NODE 1)	Enter the host name or IP address of the Habitat server that you want to use as a standby server in the same site as server 1. This server acts as a standby server in case server 1 under node 2 fails.
SERVER 2 (under NODE 2)	Enter the host name or IP address of the Habitat server in the secondary/backup site from which you want to collect data. This server acts as a standby server in case server 2 under node 1 fails. For example, suppose Machine A and Machine B are in node AB, and Machine X and Machine Y are in node XY. Suppose you

Field	Description
	<p>want to use Machine A as the primary server and the remaining machines as standby servers. In that case, enter values as follows:</p> <ul style="list-style-type: none"> ◦ SERVER 1 (under Node 1): Machine A ◦ SERVER 2 (under Node 1): Machine B ◦ SERVER 1 (under Node 2): Machine X ◦ SERVER 2 (under Node 2): Machine Y <p>If Machine A fails, the Machine B becomes active. If Machine B fails, Machine X becomes active. If Machine X fails, Machine Y becomes active.</p>
SOCKET	The socket number (port number) used by the Habitat Sampler application to connect. Each collector instance can connect to only one socket. The default value is 8040.
RETRY	The duration, in seconds, after which the collector tries to communicate with the site. The default value is 5 seconds.

8. Select **Next**.

The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. The other options are disabled because you cannot send data to a cloud destination using the HAB collector.

9. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears. By default, the **COLLECTOR NAME** field is populated with a value in the following format: `<Historian server name>_Hab`

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.

- Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
12. In the **SamplerID** field, enter the user ID to connect to Habitat Sampler.

By default, this field contains the Collector Name. You can first provide the Collector Name and update the Sample ID field as this field will automatically take the Collector Name.

13. In the **RUNNING MODE** field, select one of the following options.
- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled. By default, this option is selected.
 - **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

14. Select **Add**.

The collector instance is added. The fields specific to the collector appear in the **DETAILS** section.

15. Depending on whether you want to configure tags or alarms, select  next to the corresponding field under **Collection Definitions**.

DETAILS	
FIELD	VALUE
<div style="background-color: #f2f2f2; padding: 2px;"> ▼ General </div>	
Collector Name	██████████_Hab
Collector Type	Hab Collector
Description	██████████_Hab
Memory Buffer Size(MB)	20
Minimum Free Space(MB)	150
Total Events Collected	0
Total Events Reported	0
<div style="background-color: #f2f2f2; padding: 2px;"> ▼ Collection Definitions </div>	
Data Collection Definitions	0 
Alarm Collection Definitions	0 

The **Data Collections** or **Alarm Collections** section appears.


16. Select **+**, and then enter values in the available fields for [data collection and/or alarm collection \(on page 495\)](#). You can also copy a collection definition by right-clicking it and selecting **Duplicate**.
17. Under **COLLECTOR SPECIFIC CONFIGURATION**, configure values as described in the following table.

Field	Description
Auto Tag Sync	<p>If you enable this option, the collector creates tags automatically in Historian based on the key value. In addition, any tag changes in Habitat (such as adding, renaming, and deleting tags) will reflect automatically in Historian. No manual steps are required.</p> <p>If you disable this option, any tag changes in Habitat will be captured in the <code><collector name>_Tag_Unconfirmed.xml</code> file. Only after you approve these changes (on page 2243), they are reflected in Historian.</p>
Tag Deletion Type	<p>Specify whether deleted tags in Habitat that you have approved must be deleted or disabled for data collection in Historian. Enter one of the following values:</p>

Field	Description
	<ul style="list-style-type: none"> ◦ DISABLE_TAG (this is the default value) ◦ DELETE_TAG
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

18. As needed, provide values in the [the other sections common to all collectors \(on page 579\)](#).

19. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

20. [Start the collector \(on page 637\)](#).

If you have disabled the automatic tag sync option in the configuration file, tag changes in Habitat (such as adding, renaming, and deleting tags) are captured in the `<collector_name>_tag.xml` file. You must approve the changes so that they are reflected in Historian. To do so:

1. Right-click the HAB collector instance that you have created, and then select **Confirm Queued Tags**.

A list of tags that have been changed appears.

2. Select the check boxes corresponding to the tags whose changes you want to approve, and then select **Confirm**. You can filter the list using the **TAG TYPE** field.

The tag changes are approved. The status of the tags is updated in the `<collector_name>_tag.xml` file (that is, the Confirmed parameter is set to true).

Collection Definitions of a HAB Collector

Table 27. Tag Data Collection Definition Parameters

Parameter	Description
DEFINITION NAME	<p>The name of the collection definition. A value is required and must be unique.</p> <div data-bbox="617 520 1421 783" style="border: 1px solid #ccc; border-radius: 10px; padding: 10px; background-color: #fff9c4;"> <p>! Important: You must not change the name after the collector starts collecting data. If, however, you want to change the name after the collector has started collecting data, refer to FAQs on HAB Collector (on page 2246).</p> </div>
STATUS	Indicates whether the collection definition is enabled. If an error occurs while processing the collection definition, the collector automatically disables the collection definition.
FAMILY	The name of the Habitat family from which you want to collect data (for example, EMS, DTS). A value is required and must be unique.
APPLICATION	The name of the Habitat application from which you want to collect data (for example, SCADA). A value is required.
DATABASE	The name of the Habitat database from which you want to collect data (for example, SCADAMOM). A value is required.
RECORD TYPE	The name of the HDB record from which you want to collect data (for example, ANALOG,POINT,COUNT). A value is required. Enter any record type that contains the composite key and MRID fields (because the collector uses these two fields to create tags).
COLLECTION TYPE	<p>Indicates whether you want to perform polled or unsolicited data collection.</p> <ul style="list-style-type: none"> • Polled: Indicates a periodic data collection, where data is collected at a regular time interval (indicated as PERIODIC in Habitat). • Unsolicited: Indicates that data is collected only when values have changed since the last time data was collected (indicated as EXCEPTION in Habitat).

Table 27. Tag Data Collection Definition Parameters (continued)

Parameter	Description
KEY	The value that will be used to filter tags for data collection. A value is required. You can use the wildcard character * to get a range of values. For example, if you want to collect data from all tags that begin with SUBSTN.LAKEVIEW, enter: SUBSTN.LAKEVIEW*.*.*.*
PREFIX FIELD	The prefix that you want to use for tags. You can provide a different value for each collection definition, which helps you identify tags based on the collection definition.
TAG NAME FIELD	<p>Determines how the tags created in Historian must be named. A value is required.</p> <p>For example, if you want the tags to be named after the value in the LOC_CIRCLG field, enter LOC_CIRCLG. When you do so, if the value in the LOC_CIRCLG field in Habitat is DOUGLAS, the tag created in Historian will be named <TagPrefix value>.<AlarmPrefix value>.DOUGLAS.</p> <p>You can enter multiple values separated by commas.</p> <p>For example, if you want the tags to be named after the values in the LOC_CIRCLG and PRIOR_CIRCLG fields, enter LOC_CIRCLG, PRIOR_CIRCLG. When you do so, if the values in the LOC_CIRCLG and PRIOR_CIRCLG fields are Douglas and 1 respectively, the tag created in Historian will be named <TagPrefix value>.<AlarmPrefix value>.DOUGLAS.1.</p>
MRID FIELD	The MRID of the record. A value is required. If, however, MRID is not available, enter the composite key or any other unique identifier of the record.
DESCRIPTION FIELD	The description of the tag. A value is required.
VALUE FIELD	<p>The name of the property that stores the tag value in Habitat. A value is required.</p> <p>You can enter multiple values, separated by commas. One Historian tag will be created for each value you enter in this field.</p>

Table 27. Tag Data Collection Definition Parameters (continued)

Parameter	Description
TIMESTAMP FIELD	<p>The name of the property that stores the timestamp of a tag in Habitat. You can use a HDB timestamp or custom/alias timestamps.</p> <p>Examples:</p> <p>For analog, you can use:</p> <ul style="list-style-type: none"> • FIELDTIME: A combination of FLDTIME_ANALOG and FLD-MSEC_ANALOG, in the hour: min:sec: millisec format. • SCADATIME: Used to capture SCTIME_ANALOG in the hour: min:sec: millisec format. • SAMPLETIME: The time at which the data sample was collected in Habitat in the hour: min:sec format. <p>For point, you can use:</p> <ul style="list-style-type: none"> • FIELDTIME: A combination of FLDTIME_POINT and FLD-MSEC_POINT, in the hour: min:sec: millisec format. • SCADATIME: Used to capture SCTIME_POINT in the hour: min:sec: millisec format. • SAMPLETIME: The time at which the data sample was collected in Habitat in the hour: min:sec format. <p>For count, you can use:</p> <ul style="list-style-type: none"> • FIELDTIME: A combination of FLDTIME_COUNT and FLD-MSEC_COUNT, in the hour: min:sec: millisec format. • SAMPLETIME: The time at which the data sample was collected in Habitat in the hour: min:sec format. <p>You can edit the names of these custom/alias timestamps using the registry entries FieldTimeCustomFieldName, ScadaTimeCustomFieldName, and SampleTimeCustomFieldName respectively.</p>
QUALITY FIELD	The name of the property that stores the tag quality in Habitat.
SAMPLE RATE	The rate at which you want to collect or poll data. A value is required.

Table 27. Tag Data Collection Definition Parameters (continued)

Parameter	Description
	<p>For example, if the sample rate is 10 seconds:</p> <ul style="list-style-type: none"> • For a polled collection type, data is written to Data Archiver every 10 seconds. • For an unsolicited collection type, the collector checks for any data changes every 10 seconds. Only if there are changes, the data is written to Data Archiver.
SAMPLE UNIT	<p>The unit of measurement for the sample rate. A value is required. Valid values:</p> <ul style="list-style-type: none"> • sec • min • hour • day • week • month
PERMANENT	<p>Indicates whether you want to store the data in buffer files in Habitat in the event of a connection loss. We strongly recommend that you set this parameter to true to prevent loss of data.</p>

Table 28. Alarm Data Collection Definition Parameters

Parameter	Description
DEFINITION NAME	<p>The name of the collection definition. A value is required and must be unique.</p> <div style="border: 1px solid orange; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Important: You must not change the name after the collector starts collecting data. If, however, you want to change the name after the collector has started collecting data, refer to FAQs on HAB Collector (on page 2246).</p> </div>

Table 28. Alarm Data Collection Definition Parameters (continued)

Parameter	Description
STATUS	Indicates whether the collection definition is enabled. If an error occurs while processing the collection definition, the collector automatically disables the collection definition.
FAMILY	The name of the Habitat family from which you want to collect data (for example, EMS, DTS). A value is required and must be unique.
APPLICATION	The name of the Habitat application from which you want to collect data (for example, SCADA). A value is required.
DATABASE	The name of the Habitat database from which you want to collect data (for example, ALARMLIST). A value is required.
RECORD TYPE	The name of the HDB record from which you want to collect data (for example, CIRCLG, ALMQ). A value is required. Enter any record type that contains the composite key and MRID fields (because the collector uses these two fields to create tags).
KEY	This field is not applicable to alarms. Enter *.
TAG NAME FIELD	<p>Determines how the tags created in Historian must be named. A value is required.</p> <p>For example, if you want the tags to be named after the value in the LOC_CIRCLG field, enter <code>LOC_CIRCLG</code>. When you do so, if the value in the LOC_CIRCLG field in Habitat is DOUGLAS, the tag created in Historian will be named <code><TagPrefix value>.<AlarmPrefix value>.DOUGLAS</code>.</p> <p>You can enter multiple values separated by commas.</p> <p>For example, if you want the tags to be named after the values in the LOC_CIRCLG and PRIOR_CIRCLG fields, enter <code>LOC_CIRCLG,PRIOR_CIRCLG</code>. When you do so, if the values in the LOC_CIRCLG and PRIOR_CIRCLG fields are Douglas and 1 respectively, the tag created in Historian will be named <code><TagPrefix value>.<AlarmPrefix value>.DOUGLAS.1</code>.</p>

Table 28. Alarm Data Collection Definition Parameters (continued)

Parameter	Description
PREFIX	The prefix that you want to use for tags. A value is required. You can provide a different value for each collection definition, which helps you identify tags based on the collection definition.
VALUE	The name of the property that stores the tag value in Habitat. A value is required. You can enter multiple values, separated by commas (for example, <code>TEXT_CIRCLG, PRIOR_CIRCLG, TIME_CIRCLG</code>). The values will then be concatenated in the corresponding Historian tag.
TIMESTAMP	This field is not applicable to alarms. Leave the field blank. You can use the VALUE FIELD field to provide the timestamp (for example, <code>TIME_CIRCLG</code>).
QUALITY	This field is not applicable to alarms. Leave the field blank.
DISABLED	Switch the toggle to enable alarm filtering. You can then collect data only for the filtered alarms.
ALARM LOCATION	The alarm location based on which you want to filter alarm data. A value is required if alarm filtering is enabled. You can enter multiple values separated by commas (for example, <code>LA,NY</code>). The default value is <code>*</code> , which indicates that data for that parameter is not filtered.
ALARM AREA	The alarm area based on which you want to filter alarm data. A value is required if alarm filtering is enabled. You can enter multiple values separated by commas (for example, <code>LAKEVIEW,RICHVIEW</code>). The default value is <code>*</code> , which indicates that data for that parameter is not filtered.
ALARM CATEGORY	The alarm category based on which you want to filter alarm data. A value is required if alarm filtering is enabled. You can enter multiple values separated by commas (for example, <code>PressureSensor,Motion-Sensor</code>). The default value is <code>*</code> , which indicates that data for that parameter is not filtered.
ALARM PRIORITY	The alarm priority based on which you want to filter alarm data. A value is required if alarm filtering is enabled. You can enter multiple

Table 28. Alarm Data Collection Definition Parameters (continued)

Parameter	Description
	values separated by commas (for example, 1,2). The default value is *, which indicates that data for that parameter is not filtered.
ALARM EXCEPTION	The alarm exception based on which you want to filter alarm data. A value is required if alarm filtering is enabled. You can enter multiple values separated by commas. The default value is *, which indicates that data for that parameter is not filtered.
SAMPLE RATE	The rate at which you want to collect data. A value is required.
SAMPLE UNIT	The unit of measurement for the sample rate. A vaue is required. Valid values: <ul style="list-style-type: none"> • sec • min • hour • day • week • month
PERMANENT	Indicates whether you want to store the data in buffer files in Habitat in the event of a connection loss. We strongly recommend that you set this parameter to true to prevent loss of data.

About Adding an iFIX Collector Instance

This topic provides guidelines on how to configure the iFIX collector using Configuration Hub based on the running mode of iFIX. It also describes the collector behaviour and recommended configuration in each case.

iFIX Running Mode	Recommended Configuration for the iFIX Collector	Collector Behaviour After You Add the Collector Instance
iFIX is running in service mode and is secured. The iFIX Alarms and Events and the OPC Alarms and Events Servers are running as service.	Configure the iFIX collector services under a user account under which iFIX is running as a service. While adding an instance of the iFIX collector or the iFIX	<ul style="list-style-type: none"> • The iFIX collector starts running as a service. It appears in the collectors list in Configuration Hub.

iFIX Running Mode	Recommended Configuration for the iFIX Collector	Collector Behaviour After You Add the Collector Instance
	<p>Alarms and Events collector using Configuration Hub, select Service Under Specific User Account.</p>	<ul style="list-style-type: none"> • You can run the collector at a command prompt using the Collector Start action. A shortcut is created in the Windows Start menu so that you can run the collector in the command-line mode. • By default, when not started as an SCU task, the iFIX collector points to the iFIX nodename. You must configure the iFIX node in the Collector Configuration section in Historian Administrator.
<p>iFIX is running as a service and is not secured.</p> <p>The iFIX Alarms and Events and the OPC Alarms and Events servers are running as service.</p>	<p>You can configure the iFIX collector service using a local system account or a specific user account.</p>	<ul style="list-style-type: none"> • The iFIX collector starts running as a service. • You can run the collector at a command prompt using the Collector Start action. A shortcut is created in the Windows Start menu so that you can run the collector in the command-line mode. • By default, when not started as an SCU task, the iFIX collector points to the iFIX nodename. You must configure the iFIX node in the Collector Configuration section in Historian Administrator.

iFIX Running Mode	Recommended Configuration for the iFIX Collector	Collector Behaviour After You Add the Collector Instance
<p>iFIX is not running as a service mode and is secured.</p>	<p>Configure the iFIX collector services under a user account that is added in the IFIXUSERS group. Do not configure as a local system service. While adding an instance of the iFIX collector or the iFIX Alarms and Events collector using Configuration Hub, select Service Under Specific User Account.</p>	<ul style="list-style-type: none"> • Since Remote Collector Manager tries to start the collector as a service, and iFIX is not running as a service, an error message appears while adding a collector instance. However, the instance is configured successfully although it does not appear in the collectors list in Configuration Hub. • A shortcut is created in the Windows Start menu so that you can run the collector in the command-line mode, and the related registry folder is created. • You must start the collector manually for the first time using the shortcut. It will then connect to the Historian server, and it will then appear in the collectors list in Configuration Hub. • Once connected to server, you can start/stop it at a command prompt.
<p>iFIX is not running as a service mode, and is not secured.</p>	<p>You can configure the iFIX collector service using a local system account or a specific user account.</p>	<ul style="list-style-type: none"> • Since Remote Collector Manager tries to start the collector as a service, and iFIX is not running as a

iFIX Running Mode	Recommended Configuration for the iFIX Collector	Collector Behaviour After You Add the Collector Instance
		<p>service, an error message appears while adding a collector instance. However, the instance is configured successfully.</p> <ul style="list-style-type: none"> • A shortcut is created in the Windows Start menu so that you can run the collector in the command-line mode, and the related registry folder is created. • You must start the collector manually for the first time using the shortcut. It will then connect to the Historian server. • Once connected to server, you can start/stop it at a command prompt.
<p>iFIX is not running.</p>	<p>You can configure the iFIX collector service using a local system account or a specific user account, as per the security configuration of iFIX.</p>	<ul style="list-style-type: none"> • Since Remote Collector Manager tries to start the collector as a service, and iFIX is not running as a service, an error message appears while adding a collector instance. However, the instance is configured successfully although it does not appear in the collectors list in Configuration Hub. • A shortcut is created in the Windows Start menu so that you can run the

iFIX Running Mode	Recommended Configuration for the iFIX Collector	Collector Behaviour After You Add the Collector Instance
		<p>collector in the command-line mode, and the related registry folder is created.</p> <ul style="list-style-type: none"> • After you start iFIX, you must start the collector manually for the first time using the shortcut. It will then connect to the Historian server. • Once connected to server, you can start/stop it at a command prompt.

Add and Configure an iFIX Collector

Ensure that iFIX is running in a Windows-service mode. For more information, refer to [About Adding an iFIX Collector Instance \(on page 501\)](#).


The iFIX collectors collect data from iFIX and store it in the Historian server. They include:

- The iFIX collector
- The iFIX Alarms and Events collector

When you install collectors, if iFIX is installed on the same machine as the collectors, instances of the iFIX collectors are created automatically. This topic describes how to create additional instances if needed.

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select .



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **iFIX Alarms Events Collector** or **iFIX Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears. The **iFIX SERVER** field is disabled and populated.

7. Select **Next**.

The **Destination Configuration** section appears. The **Historian Server** option is selected by default. You cannot select any other option for an iFIX Alarms and Events collector.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

8. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
- **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

- b. If you need to send data to an on-premises Historian server, select **Historian Server**.
If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

9. Select **Next**.

10. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled. By default, this option is selected.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

11. Select **Next**.

The **Collector Initiation** section appears.

12. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

13. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if iFIX is running in a secured mode, or if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter the credentials of the iFIX user in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start iFIX.

14. Select **Add**.

The collector instance is added, and appears in the Collectors list. A shortcut is created so that you can open it at a command prompt.

If iFIX is not running in a service mode, an error message may appear. However, the collector instance is created; therefore, you can ignore the error message. Although the collector instance does not appear in the list of collectors in Configuration Hub, a shortcut is created. You can run the collector manually at a command prompt or as a SCU task. For more information, refer to [About Adding an iFIX Collector Instance \(on page 501\)](#).

15. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure the values as described in the following table.


Field	Description
Nodes to Browse	Enter the mask that you want to use to select tags when browsing for tags in the collector. The default value is FIX.

Field	Description
	<p>If you want to browse for tags on other iFIX nodes via FIX networking, you can enter the other node name(s) here, separated by commas with no spaces. You must have the iFIX system configured for networking. For more information, refer to the iFIX product documentation on iFIX networking.</p> <div data-bbox="862 604 1419 1178" style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note:</p> <p>If you have modified iFIX node name, then you must also update the value in the Nodes to Browse field before browsing for tags in the iFIX collector.</p> <p>When you browse multiple nodes for tags to add to an iFIX collector, do not use space characters between node names or between the required comma and next node name. All characters after the space are ignored.</p> </div>
<p>Tag Browse Criteria</p>	<p>Specify the tags for data collection (on page 357).</p> <div data-bbox="862 1318 1419 1629" style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note:</p> <p>If you want to add block or field types to the list, edit the <code>FixTag.dat</code> file for Historian Administrator you are using. Refer to Editing FixTag.dat File (on page 2257) for more information.</p> </div>
<p>MTLS Security</p>	<p>Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.</p>

Field	Description
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

16. As needed, enter values in [the other sections common o all collectors \(on page 579\)](#).

17. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

18. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,

- If you have selected **Historian Configuration**, [specify the tags using Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: `<installation folder of Historian>\GE Digital\<collector name>`. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination. This option is not applicable to an iFIX Alarms and Events collector.

Add and Configure an MQTT Collector

1. Ensure that you have an MQTT broker.



Note:


We have tested with the MQTT brokers Mosquitto 2.0.15 and HiveMQ-4.2.1. You can, however, use other MQTT brokers as well.

2. If you want to use username/password-based authentication or certificate-based authentication to connect the MQTT broker and the MQTT collector, configure the authentication in the MQTT broker.
3. If you want to use certificate-based authentication, ensure that the following files are available on your collector machine:
 - CA server root file
 - Private key file
 - Client certificate file

The MQTT collector collects data published to a topic using an MQTT broker. For more information, refer to [Overview of the MQTT Collector \(on page 2298\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **MQTT Collector**, and then select **Get Details**. The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. Enter values as described in the following table.

Field	Description
MQTT BROKER ADDRESS	Enter the host name of the MQTT broker using which you want to collect data. A value is required.
MQTT BROKER PORT	Enter the port number of the MQTT broker. A value is required.
TOPIC	<p>Enter the MQTT topic from which you want to collect data. A value is required. You can enter multiple topics separated by commas.</p> <p>If you want to use the Sparkplug B format, enter a value in the following format: <code>namespace/group_id/message_type/edge_node_id/device_id</code></p> <p>where:</p> <ul style="list-style-type: none"> ◦ <code>namespace</code> is the Sparkplug version. Enter <code>spBv1.0</code>. ◦ <code>group_id</code> is the ID of the group of nodes from which you want to collect data. ◦ <code>message_type</code> is the message type from which you want to collect data. The collector processes data only from NDATA and DDATA message types. ◦ <code>edge_node_id</code> is used to identify the MQTT EoN node within the infrastructure. ◦ <code>device_id</code> a device attached to the MQTT EoN node either physically or logically. <p>You can use the wildcard character <code>#</code> for any of these parameters (except for namespace).</p>
USERNAME	Enter the username to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
PASSWORD	Enter the password to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.

Field	Description
CA SERVER ROOT FILE	Enter the path to the CA server root file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
PRIVATE KEY FILE	Enter the path to the private key file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
CLIENT CERTIFICATE FILE	Enter the path to the client certificate file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
REQUESTED QUALITY OF SERVICE (QoS) LEVEL	<p>Select the quality of service that you want to use while collecting data from an MQTT broker.</p> <ul style="list-style-type: none"> ◦ QoS 0: Indicates that the message is delivered at most once or it is not delivered at all. ◦ QoS 1: Indicates that the message is always delivered at least once. ◦ QoS 2: Indicates that the message is delivered once. <p>For more information, refer to https://www.hivemq.com/blog/mqtt-essentials-part-6-mqtt-quality-of-service-levels/.</p>
MQTT VERSION	Select the version of the MQTT that you want to use.
CLEAN SESSION	<p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ True: Select this option if you do not want to create a new session when the MQTT broker and the collector are disconnected from each other. ◦ False: Select this option if you want to retain the session when the MQTT broker and the collector are disconnected from each other. This ensures that there is no loss of data. If you want to choose this option, ensure that you have selected QoS 1 or QoS 2 in the REQUESTED QUALITY OF SERVICE (QoS) LEVEL field.
SESSION EXPIRY INTERVAL	Enter the duration, in seconds, after which the data will be discarded when connection between the MQTT broker and collector is re-established.

Field	Description
	<p>For example, if you enter 100 in this field, and if the MQTT broker and collector are disconnected for 90 seconds, the data is collected. If, however, the MQTT broker and the collector are disconnected for more than 100 seconds, the data will be discarded.</p> <p>This field is applicable only for MQTT V5 and only if you set the CLEAN SESSION field to False.</p>
CONTENT TYPE	<p>Select the format that you want to use for the payload:</p> <ul style="list-style-type: none"> ◦ JSON: Select this option if you want to use the KairosDB format. ◦ SparkPlug B v1.0: Select this option if you want to use the Sparkplug format.

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.
- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).
 - b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears.

11. If needed, modify the value in the **COLLECTOR NAME** field. The value must be unique, must contain the string `MQTT`, and must not contain a space.

The value that you enter:

- Must be unique.
- Must contain the string `MQTT`.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

14. In the **COLLECTOR SPECIFIC CONFIGURATION** and **INSTANCE CONFIGURATION** sections, configure the values as described in the following table.

COLLECTOR SPECIFIC CONFIGURATION

Field	Description
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

INSTANCE CONFIGURATION


Field	Description
MQTT Broker Address	Enter the host name of the MQTT broker using which you want to collect data. A value is required.
MQTT Broker Topic	<p>Enter the MQTT topic from which you want to collect data. A value is required. You can enter multiple topics separated by commas.</p> <p>If you want to use the Sparkplug B format, enter a value in the following format: <code>namespace/group_id/message_type/edge_node_id/device_id</code></p> <p>where:</p> <ul style="list-style-type: none"> ◦ <code>namespace</code> is the Sparkplug version. Enter <code>spBv1.0</code>. ◦ <code>group_id</code> is the ID of the group of nodes from which you want to collect data. ◦ <code>message_type</code> is the message type from which you want to collect data. The collector processes data only from NDATA and DDATA message types.

Field	Description
	<ul style="list-style-type: none"> ◦ <code>edge_node_id</code> is used to identify the MQTT EoN node within the infrastructure. ◦ <code>device_id</code> a device attached to the MQTT EoN node either physically or logically. <p>You can use the wildcard character # for any of these parameters (except for namespace).</p>
MQTT Brker Port	Enter the port number of the MQTT broker. A value is required.
Username	Enter the username to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
Password	Enter the password to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
CA Server Root File	Enter the path to the CA server root file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
Private Key File	Enter the path to the private key file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
CLIENT Certificate File	Enter the path to the client certificate file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
Requested Quality Of Service (QoS) Level	<p>Select the quality of service that you want to use while collecting data from an MQTT broker.</p> <ul style="list-style-type: none"> ◦ QoS 0: Indicates that the message is delivered at most once or it is not delivered at all. ◦ QoS 1: Indicates that the message is always delivered at least once. ◦ QoS 2: Indicates that the message is delivered once. <p>For more information, refer to https://www.hivemq.com/blog/mqtt-essentials-part-6-mqtt-quality-of-service-levels/.</p>
MQTT Version	Select the version of the MQTT that you want to use.

Field	Description
<p>CLEAN Session</p>	<p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ True: Select this option if you do not want to create a new session when the MQTT broker and the collector are disconnected from each other. ◦ False: Select this option if you want to retain the session when the MQTT broker and the collector are disconnected from each other. This ensures that there is no loss of data. If you want to choose this option, ensure that you have selected QoS 1 or QoS 2 in the REQUESTED QUALITY OF SERVICE (QOS) LEVEL field.
<p>SESSION Expiry Interval</p>	<p>Enter the duration, in seconds, after which the data will be discarded when connection between the MQTT broker and collector is re-established.</p> <p>For example, if you enter 100 in this field, and if the MQTT broker and collector are disconnected for 90 seconds, the data is collected. If, however, the MQTT broker and the collector are disconnected for more than 100 seconds, the data will be discarded.</p> <p>This field is applicable only for MQTT V5 and only if you set the CLEAN SESSION field to False.</p>
<p>Content Type</p>	<p>Select the format that you want to use for the payload:</p> <ul style="list-style-type: none"> ◦ JSON: Select this option if you want to use the KairosDB format. ◦ SparkPlug B v1.0: Select this option if you want to use the Sparkplug format.

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,

- If you have selected **Historian Configuration**, specify the tags using [Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: `<installation folder of Historian>\GE Digital\<collector name>`. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Add an MQTT Sparkplug B Collector Instance using Configuration Hub

1. Install [the Historian server \(on page 104\)](#) and [collectors \(on page 142\)](#).
2. Ensure that you have an MQTT broker.
3. If you want to use username/password-based authentication or certificate-based authentication to connect the MQTT broker and the MQTT Sparkplug B collector, configure the authentication in the MQTT broker.
4. If you want to use certificate-based authentication, ensure that the following files are available on your collector machine:
 - CA server root file
 - Private key file
 - Client certificate file

This topic describes how to add and configure an MQTT Sparkplug B collector instance using Configuration hub. You can also add and configure an MQTT Sparkplug B collector instance using RemoteCollectorConfigurator.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select .

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION
Filter	Filter	Filter	Filter	Filter
Simulation	Running	Historian		
SamplePythonCollector	Unknown	Historian		

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

- In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
- In the **COLLECTOR TYPE** field, select **MQTT Sparkplug B Collector**, and then select **Get Details**.

 **Note:**
 The **INSTALLATION DRIVE** and **BASE DATA DIRECTORY** fields cannot be changed. This is the drive location and the data directory folder that you provided during Collectors installation.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are populated with the drive location and the data directory folder.

- Select **Next**.
 The **Source Configuration** section appears.
- Enter the values as described in the following table:

Field	Description
BROKER CONFIGURATION	
BROKER ADDRESS	Enter the host name of the MQTT broker using which you want to collect data. A value is required.
BROKER PORT	Enter the port number of the MQTT broker. A value is required.
CLIENT ID	Enter the client ID of the MQTT Sparkplug B collector is running. This is required if you want to send the data to a cloud destination. If you do not have a client ID set up, by default, the interface name is taken.

Field	Description
PRIMARY HOST ID	Enter the unique host ID of the Collector. The Collector will publish the STATE message topic using this host ID and then the Publisher will subscribe and start publishing the topics to this host ID.
REORDER TIMEOUT	Enter the duration for waiting before sending a CMD message if a sequence is skipped. You can enter the duration in milliseconds.
MQTT VERSION	Select the version of the MQTT that you want to use. The following versions are supported: <ul style="list-style-type: none"> ◦ MQTT_V311 ◦ MQTT_V5
<p>TOPIC: The parameters that need to be included in the topic:</p> <pre style="background-color: #f0f0f0; padding: 5px;">Namespace/Groupname/<Message Type>/NodeID/<DeviceID></pre> <p>You can also use wildcards in the GROUP ID, EDGE NODE ID, and DEVICE ID fields. The following wildcards are supported:</p> <ul style="list-style-type: none"> ◦ + (single-level wildcard): Supported for all the three fields. ◦ # (Multi-level wildcard): Supported for the EDGE NODE ID and DEVICE ID <p>+ (Single-level wildcard): Can be used to subscribe to only one topic level. For example, if you subscribe to a topic <code><Admin>/+/<ABC-123></code>, you will receive messages from all the nodes corresponding to the group and device. That is,</p> <pre style="background-color: #f0f0f0; padding: 5px;"><Admin>/Node1/<ABC-123> <Admin>/Node2/<ABC-123> <Admin>/Node3/<ABC-123> ... <Admin>/Noden/<ABC-123></pre> <p># (Multi-level wildcard): Can be used to subscribe to any number of levels within a topic. For example, if you subscribe to a topic <code><Admin>/#</code>, you will receive messages from all the nodes and devices corresponding to the group,</p>	

Field	Description
<pre> <Admin>/Node1/<ABC-123> <Admin>/Node2/<ABC-123> <Admin>/Node3/<ABC-123> <Admin>/Node1/<ABC-124> <Admin>/Node2/<ABC-124> ... <Admin>/Noden/<Devicen> </pre>	
<p>GROUP ID</p>	<p>Enter the Sparkplug B group name to which you want your collector to subscribe. If this is empty along with the other fields below TOPIC, the collector will subscribe to all the available groups, nodes, and devices.</p>
<p>EDGE NODE ID</p>	<p>Enter the Sparkplug B edge node ID to which you want your collector to subscribe. If this is empty, then the Collector will subscribe to all the edge nodes corresponding to the entered GROUP ID. If the GROUP ID and DEVICE ID are also empty, then the collector will subscribe to all the available groups, nodes and devices.</p>
<p>DEVICE ID</p>	<p>Enter the Sparkplug B device name. If this is empty, the collector subscribes to node messages if a NODE ID is entered, otherwise, if a DEVICE ID is entered, it subscribes to device messages.</p>
<p>TAG CONFIGURATION</p>	
<p>TAG NAME PREFIX FORMAT</p>	
<p>ELEMENT</p>	<p>Enter a prefix to be included in the tag. By using this field, you can clearly identify a tag. For example, you can clearly differentiate the tags that are collected.</p> <p>The following options are available:</p>

Field	Description
	<ul style="list-style-type: none"> ◦ <interfacename> ◦ <groupid> ◦ <edgenodeid> ◦ <deviceid> <p>For example, if all four fields are provided and the interface/collector name is "sparkplug1" and the Topic contains group id = g1 edge node id = n1, device id = d1 then device tags will be created in Historian as "sparkplug1.g1.n1.d1.tag1".</p>
DELIMITER	<p>Enter a delimiter you need to be included in the tag. You can use any special characters as delimiter. However, it is recommended that you use a delimiter that is ideal and clear to be identified. For example, "/", ".", "_".</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: "?" and "*" are not allowed. </div>
PREVIEW	<p>The preview of how the tags will be created and stored based on the TAG PREFIX and the DELIMITER that you selected.</p>
TAG MASK	
TAGS TO ADD	<p>Provide a mask along with wildcard to collect those tags that include the mask you provided and store in Historian. For example, *Pressure*. This will collect all the tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be collected. Similarly, if you enter *Pres?, all the tags that contain "pres" at the beginning will be collected. It can be "Pressure", "Press", or "Pres1".</p>

Field	Description
	<div style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;">  Note: Whenever a new tag is collected, the collector verifies the tag availability in the Historian and, if not present, adds the tag, then adds the data samples, streaming the data to the Historian server or a cloud destination. </div>
TAGS TO EXCLUDE	Provide a mask along with wildcard to exclude those tags that include the mask you provided. For example, *Pressure*. This will exclude all the tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be excluded. Similarly, if you enter *Pres?, all the tags that contain "pres" at the beginning will be excluded. It can be "Pressure", "Press", or "Pres1".
AUTHENTICATION	
USER CREDENTIALS	
USERNAME	Enter the username to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
PASSWORD	Enter the password to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
SSL/TLS	
CA SERVER ROOT FILE	Enter the path to the CA server root file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.

Field	Description
PRIVATE KEY FILE	Enter the path to the private key file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
CLIENT CERTIFICATE FILE	Enter the path to the client certificate file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.

8. Select **Next**.

The **Destination Configuration** section appears.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.
- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).
 - b. If you need to send data to an on-premises Historian server, select **Historian Server**.
If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. After you selected the destination, select **Next**.

The **Collector Initiation** section appears.

11. If needed, modify the value in the **COLLECTOR NAME** field.



Note:

If you will be using the collector in Historian Administrator, the **COLLECTOR NAME** must include Sparkplug B in it.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

14. If needed, enter values in [available fields \(on page 579\)](#).

15. In the upper-left corner of the page, select **Save**.

16. If needed, restart the collector.


- Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,
 - If you have selected **Historian Configuration**, specify the tags using [Configuration Hub \(on page 357\)](#).
 - If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of Historian>\GE Digital\<<collector name>*. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.
- If needed, you can [configure the collector instance \(on page 2331\)](#).

Add and Configure an ODBC Collector Using Configuration Hub

The ODBC collector collects data from an application based on an ODBC driver. For more information, refer to [Overview of the ODBC Collector \(on page 2341\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **ODBC Collector**, and then select **Get Details**.
The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.
6. Select **Next**.
The **Source Configuration** section appears.
7. Enter values as described in the following table.

Field	Description
ODBC SERVER	Enter the host name or IP address of the ODBC server from which you want to collect data. A value is required.
USERNAME	Enter the username to connect to the ODBC server. A value is required.
PASSWORD	Enter the password to connect to the ODBC server. A value is required.

8. Select **Next**.
The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.
 - a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).
 - b. If you need to send data to an on-premises Historian server, select **Historian Server**.
 If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.
 If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.
 If the entered credentials are valid, a successful connection message appears.
10. Select **Next**.
 The **Collector Initiation** section appears.
11. If needed, modify the value in the **COLLECTOR NAME** field.
 The value that you enter:
 - Must be unique.
 - Must contain the string `ODBC`.
 - Must not exceed 15 characters.
 - Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.


The collector instance is added. The fields specific to the collector appear in the **DETAILS** section.

14. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
Recovery Time (hours)	<p>Enter the maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the ODBC server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>By default, this value is set to 0, which means data recovery is not attempted. The maximum value you can provide is 168 hours (that is, 7 days).</p>
Throttle (Milliseconds)	<p>Enter the frequency, in milliseconds, at which you want the ODBC collector to query the ODBC</p>

Field	Description
	<p>server for tag data. This will minimize the load on the ODBC server. You can enter a value up to 16 hours.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: If this field is blank, enter the required minimum value of 100 milliseconds.</p> </div>
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).
16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,

- If you have selected **Historian Configuration**, [specify the tags using Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of*

Historian>\GE Digital\<<collector name>. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.


Add and Configure an OPC Classic Alarms and Events Collector

The OPC Classic Alarms and Events collector collects alarms and events data from any OPC 1.0 or OPC 2.0 compliant OPC server.

You can create an OPC Alarms and Events collector only for an on-premises Historian server, not for a cloud destination.

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **OPC Alarms and Events Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. In the **OPC A&E SERVER** field, enter the host name or IP address of the OPC server from which you want to collect alarms and events data.

8. Select **Next**.

The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default; the other options are disabled. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the value you selected in the **MACHINE NAME** field in the **Collector Selection** section.

9. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

10. Select **Next**.

The **Collector Initiation** section appears.

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.


The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

14. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure the values as described in the following table.

Field	Description
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.


[Specify the tags \(on page 357\)](#) whose data you want to collect using the collector.

Add and Configure an OPC Classic Data Access Collector

The OPC Classic Data Access (DA) collector collects data from any OPC 1.0 or OPC 2.0 compliant OPC Classic server. For more information, refer to [Overview of the OPC Classic DA Collector \(on page 2356\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **OPC Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. Enter values as described in the following table.

Field	Description
OPC SERVER	Select the machine on which you have installed the OPC Classic DA server from which you want to collect data.

Field	Description
MACHINE NAME	Enter the host name or IP address of the OPC server. This field appears only if you have selected a remote OPC server. A value is required.
OPC DA SERVER PROG ID	Enter the prog ID of the OPC server. This field appears only if you have selected a remote OPC server. A value is required.

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.
- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).
 - b. If you need to send data to an on-premises Historian server, select **Historian Server**.
If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: `<system name>_OPC_<OPC server name>`

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.


14. Under **COLLECTOR SPECIFIC CONFIGURATION**, configure values as described in the following table.

Field	Description
OPC Server Prog ID	The program ID of the OPC server from which you want to collect data.
Read Mode	The read mode that you want the collector to use. For information, refer to the documentation of the OPC server that you are using or the OPC specification on the OPC Foundation website.
First Browse Criteria	<p>A comma-separated first-level search criterion for browsing tags from the data source. The top-level and second-level criteria are used together by the AND operation to browse tags.</p> <p>For example, if you enter <code>USGB014</code> in the First Browse Criteria field and <code>F_CV, B_CUALM</code> in the Second Browse Criteria field, it returns all the tags that contain:</p> <ul style="list-style-type: none"> ◦ <code>USGB014</code> -and- ◦ <code>F_CV</code> or <code>B_CUALM</code>
Second Browse Criteria	A comma-separated second-level search criterion for browsing tags from the data source. The top-level and second-level criteria are used together by the AND operation to browse tags.
Threading Model	<p>The type of the threading model selected for the collector. The model selected must match the threading model of the OPC server.</p> <ul style="list-style-type: none"> ◦ Multithreaded: Select this option for better performance. We recommend that you configure your collector to use the default multi-threading model. ◦ Apparent: Select this option for best compatibility. Some OPC servers do not work well with multi-threading. If you experience problems running your collector with multi-threading, use the apartment model.

Field	Description
	The default setting is multi-threaded. For information, refer to the documentation of the OPC server you are using.
Configuration Changes	<p>Indicates whether the collector configuration changes are processed in real time or after restarting the collector.</p> <ul style="list-style-type: none"> ◦ Made On-Line: Select this option to process any configuration changes immediately (after 30 seconds) after you select the Update button. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Note:</p> <ul style="list-style-type: none"> ▪ Some OPC servers cannot handle processing configuration changes online. If you experience any instability with changes made online, use the next option. </div> <ul style="list-style-type: none"> ◦ Made After Collector Restart: Select this option to hold all configuration changes until you manually restart the collector.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,


- If you have selected **Historian Configuration**, [specify the tags for data collection \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of Historian>\GE Digital\<collector name>*. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Add and Configure an OPC Classic HDA Collector

The OPC Classic Historical Data Access (HDA) collector collects data from any OPC HDA 1.2 - compliant OPC Classic HDA server. For more information, refer to [Configure the OPC Classic HDA Collector Using Historian Administrator \(on page 2380\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
3. In the upper-right corner of the main section, select .



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **OPC HDA Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. Enter values as described in the following table.

Field	Description
OPC HDA SERVER	Select the machine on which you have installed the OPC Classic HDA server from which you want to collect data.
MACHINE NAME	Enter the host name or IP address of the OPC server. This field appears only if you have selected a remote OPC server. A value is required.
OPC DA SERVER PROG ID	Enter the prog ID of the OPC server. This field appears only if you have selected a remote OPC server. A value is required.

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

- b. If you need to send data to an on-premises Historian server, select **Historian Server**.
If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears.

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must contain the string `OPCHDA`.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.


The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

14. As needed, under **COLLECTOR SPECIFIC CONFIGURATION**, configure values as described in the following table.

Field	Description
Recovery Time	<p>It indicates the maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the OPC server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>You can enter a value between 1 and 150.</p>
MTLS Security	<p>Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.</p>
MTLS Data Encryption	<p>Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).</p>
<p>For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632).</p>	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,


- If you have selected **Historian Configuration**, specify the tags using [Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: `<installation folder of Historian>\GE Digital\<collector name>`. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Add and Configure an OPC UA Data Access Collector

The OPC UA Data Access (DA) collector gathers and collects data from a OPC UA 1.0-compliant OPC UA DA server. For more information, refer to [Configure an OPC UA DA Collector Using Historian Administrator \(on page 2432\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **OPC UA DA Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. In the **OPC UA SERVER URI** field, enter the URI to connect to the OPC server in the following format:

```
opc.tcp://<host name or IP address of the OPC UA server>:<port number>
```

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

- b. If you need to send data to an on-premises Historian server, select **Historian Server**.
 If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.
 If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.
 If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: `<Historian server name>_OPCUACollector_<number>`

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must contain the string `OPCUACollector`.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.


14. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
OPC UA Server URL	The URI to connect to the OPC UA server. Enter a value in the following format: <code>opc.tcp://<host name or IP address of the OPC UA server>:<port number></code>
Secured Connectivity	Indicates whether you want a secured connection between the OPC UA server and the collector. By default, this field is set to false. You can establish a secured connectivity in one of the following ways: <ul style="list-style-type: none"> ◦ Using certificates: To use certificates, switch off the User Security toggle. ◦ Using user authentication: To use user authentication, switch on the User Security toggle.
User Security	This field is enabled only if you have enabled secured connectivity. Switch on this toggle if you want to use user authentication to connect to the OPC server. When you do so, the User Name and Password fields are enabled. You can either enter the user credentials in these fields, or you can use the values in the <code>ClientConfig.ini</code> file. For instructions, refer to Connect with the OPC UA DA Server Securely (on page 2434) .

Field	Description
Username	This field is enabled only if you have set the secured connectivity to true and switched on the User Security toggle. Enter the username that you want to use to connect to the OPC server. If you do not provide a value, the username from the <code>ClientConfig.ini</code> file is considered.
Password	This field is enabled only if you have set the secured connectivity to true and selected the Enable User Security check box. Enter the password that you want to use to connect to the OPC server. If you do not provide a value, the password from the <code>ClientConfig.ini</code> file is considered.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

If you have enabled secured connection, [establish a secured connection between the OPC server and the collector \(on page 2434\)](#).


Add and Configure an OSI PI Collector

Install PI AF SDK version 2.7.5 or later.

The OSI PI collector collects data from an OSI PI server. For more information, refer to [Overview of the OSI PI Collector \(on page 2443\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **OSI PI Collector**, and then select **Get Details**.
The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.
6. Select **Next**.
The **Source Configuration** section appears.
7. Enter values as described in the following table.

Field	Description
PI SERVER	Enter the host name or IP address of the OSI PI server from which you want to collect data. A value is required.
PI USERNAME	Enter the username to connect to the OSI PI server.
PI PASSWORD	Enter the password to connect to the OSI PI server.

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

a. If you need to send data to a cloud destination, select the cloud destinations as needed.

- **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
- **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
- **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: *<host name or IP address of the PI server>_PICollector*

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector appear in the **DETAILS** section.


14. In the **COLLECTOR SPECIFIC CONFIGURATION** sections, configure values in the following table.

Field	Description
Max Recovery Time (hours)	Enter the maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection be-

Field	Description
	<p>tween the collector and the OSI PI server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>The default value is 4 hours.</p>
Data Source	<p>Specify whether you want to collect data from PI archive or PI snapshot:</p> <ul style="list-style-type: none"> ◦ Archive: Stores timeseries-based data. ◦ Snapshot: Stores the most recent values of tags.
MTLS Security	<p>Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.</p>
MTLS Data Encryption	<p>Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).</p>
<p>For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632).</p>	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,

- If you have selected **Historian Configuration**, specify the tags using [Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of Historian>\GE Digital\<collector name>*. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.


Add and Configure an OSI PI Distributor

Install PI AF SDK version 2.7.5 or later.

An OSI PI distributor collects data from a Historian server and sends it to an OSI PI server. For more information, refer to [Overview of the OSI PI Distributor \(on page 2457\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **OSI PI Distributor Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. Enter values as described in the following table.

Field	Description
HISTORIAN SOURCE SERVER	Enter the host name or IP address of the Historian server from which you want to collect data. A value is required.
USERNAME	Enter the username to connect to the Historian server. A value is required.
PASSWORD	Enter the password to connect to the Historian server. A value is required.

8. Select **Next**.

The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **PI Server** option is selected by default; the other options are disabled.

9. Enter values as described in the following table.

Field	Description
PI SERVER	Enter the host name or IP address of the OSI PI server to which you want to send data. A value is required.
PI USERNAME	Enter the username to connect to the OSI PI server.
PI PASSWORD	Enter the password to connect to the OSI PI server.

10. Select **Next**.

The **Collector Initiation** section appears.

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector instance appear in the **DETAILS** section.


14. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values in the following table.

Field	Description
Max Recovery Time (hours)	<p>Enter the maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the OSI PI server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p>

Field	Description
	The default value is 4 hours.
Data Source	Specify whether you want to collect data from PI archive or PI snapshot: <ul style="list-style-type: none"> ◦ Archive: Stores timeseries-based data. ◦ Snapshot: Stores the most recent values of tags.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.


[Specify the tags \(on page 357\)](#) whose data you want to collect using the collector.

Add a Python Collector Instance using Configuration Hub

- [Install Python Collector \(on page 2464\)](#).

This topic describes how to add a Python collector instance using Configuration hub.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select .



COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION
Simulation	Running	Historian		
PythonCollector	Running	Historian		

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Python Collector**, and then select **Get Details**.



Note:

The **INSTALLATION DRIVE** and **BASE DATA DIRECTORY** fields cannot be changed. This is the drive location and the data directory folder that you provided during Collectors installation.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are populated with the drive location and the data directory folder.

6. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

7. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

- b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

8. After you selected the destination, select **Next**.

The **Collector Initiation** section appears.

9. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
 - Must not exceed 15 characters.
 - Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
10. In the **RUNNING MODE** field, select one of the following options.
 - **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
 - **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

11. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.


[Specify the tags \(on page 357\)](#) whose data you want to collect using the collector.

Add and Configure a Server-to-Server Collector

The Server-to-Server collector collects data and messages from a source Historian server to a destination Historian server or a cloud destination. For more information, refer to [Overview of the Server-to-Server Collector \(on page 2499\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Server to Server Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. In the **HISTORIAN SOURCE SERVER** field, enter the host name or IP address of the Historian server from which you want to collect data. By default, the local host name appears.
8. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

9. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is populated with the collector machine name, you can change it in case of a remote Historian server.

10. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.
 - a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).
 - b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD**.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**.

If the entered credentials are valid, a successful connection message appears.
11. Select **Next**.

The **Collector Initiation** section appears.
12. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

 - Must be unique.
 - Must not exceed 15 characters.
 - Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
13. In the **RUNNING MODE** field, select one of the following options.
 - **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user).

If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
 - **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

14. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.


15. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
Alarm Replication	Indicates whether you want to enable or disable alarm replication. If you enable alarm replication, all collected alarm data will be transferred from the source server to the destination server. If you enable alarm replication, you also enable alarm recovery. However, if you set the Max Recovery Time value to zero, alarm recovery does not happen.
Message Replication	Indicates whether you to want to enable or disable message replication. If you enable message replication, messages will be transferred from the source server to the destination server. You can use this data for audits. If you enable message replication, you also enable message recovery. However, if you set the Max Recovery Time value to zero, message recovery does not happen.
Calculation Timeout (sec)	The maximum time allowed for a tag's calculation formula to execute before being terminated. The default value is 10 seconds.
Max Recovery Time (hr)	The maximum duration, in hours, for which the collector will attempt to restore data during recovery logic. The default value is 4 hours.
Add Prefix to Messages	The prefix to identify replicated messages on the destination. Alarms and events data will automatically have a prefix added to it with the following syntax: <code>MachineName_Datasource</code>

Field	Description
	For example, if your alarm is forwarded from the server <code>Almserver12</code> with a data source named <code>OPCAE</code> , the prefix will be <code>Almserver12_OPCAЕ</code> .
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

16. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

17. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

18. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,

- If you have selected **Historian Configuration**, [specify the tags using Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: `<installation folder of Historian>\GE Digital\<collector name>`. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.


Add and Configure a Server-to-Server Distributor

The Server-to-Server distributor is used to send data from a smaller Historian server to a larger, centralized on-premises Historian server. For more information, refer to [Overview of the Server-to-Server](#)

Distributor (on page 2554). If you want to send data to a cloud destination, use the Server-to-Server collector (on page 559) instead.

This topic describes how to add a collector instance using Configuration Hub. You can also add a collector instance using the RemoteCollectorConfigurator utility (on page 797), which does not require you to install Web-based Clients.

1. Access Configuration Hub (on page 336).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Server to Server Distributor Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. In the **HISTORIAN SOURCE SERVER** field, enter the host name or IP address of the Historian server from which you want to collect data. By default, the local host name appears.

8. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

9. Select **Next**.

The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default; the other options are disabled. In addition, the **DESTINATION HISTORIAN SERVER** field is populated with the collector machine name, you can change it in case of a remote Historian server.

10. In the **USERNAME** and **PASSWORD** fields, enter the credentials to access the destination Historian server. Values are required only for a remote Historian server.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered is valid.

11. Select **Next**.

The **Collector Initiation** section appears.

12. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

13. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

14. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.


15. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
Alarm Replication	Indicates whether you want to enable or disable alarm replication. If you enable alarm replication, all collected alarm data will be transferred from the source server to the destination server. If you enable alarm replication, you also enable alarm recovery. However, if you set the Max Recovery Time value to zero, alarm recovery does not happen.
Message Replication	Indicates whether you to want to enable or disable message replication. If you enable message replication, you also enable message recovery. However, if you set the Max Recovery Time value to zero, message recovery does not happen.
Calculation Timeout (sec)	The maximum time allowed for a tag's calculation formula to execute before being terminated. The default value is 10 seconds.
Max Recovery Time (hr)	The maximum duration, in hours, for which the collector will attempt to restore data during recovery logic. The default value is 4 hours.
Add Prefix to Messages	<p>The prefix to identify replicated messages on the destination.</p> <p>Alarms and events data will automatically have a prefix added to it with the following syntax:</p> <pre style="background-color: #f0f0f0; padding: 5px; border: 1px solid #ccc;">MachineName_Datasource</pre> <p>For example, if your alarm is forwarded from the server <code>Almserver12</code> with a data source named <code>OPCAE</code>, the prefix will be <code>Almserver12_OPCAE</code>.</p>
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.

Field	Description
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

16. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

17. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

18. If needed, restart the collector.


[Specify the tags \(on page 357\)](#) whose data you want to collect using the collector.

Add and Configure a Simulation Collector

The Simulation collector generates random numbers and string patterns for demonstration purposes. For more information, refer to [Overview of the Simulation Collector \(on page 2558\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Simulation Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears. The **COLLECTOR MACHINE NAME** field is disabled and populated.

7. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

8. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

a. If you need to send data to a cloud destination, select the cloud destinations as needed.

- **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
- **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
- **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

9. Select **Next**.

The **Collector Initiation** section appears.

10. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

11. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

12. Select **Add**.


The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

13. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
Number of Tags	The number of Historian tags that you want the create for the collector.
Function Period (seconds)	The period, in seconds, of the <code>SIN,STEP</code> , and <code>RAMP</code> functions implemented in the collector.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

14. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

15. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

16. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,


- If you have selected **Historian Configuration**, [specify the tags using Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of Historian>\GE Digital\<<collector name>*. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Add and Configure Windows Performance Collector

The Windows Performance collector collects Windows performance counter data. For more information, refer to [Overview of the Windows Performance Collector \(on page 2562\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select .



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
 5. In the **COLLECTOR TYPE** field, select **Windows Performance Collector**, and then select **Get Details**.
- The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.
6. Select **Next**.

The **Source Configuration** section appears. The **WINDOWS MACHINE NAME** field is disabled and populated.

7. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

8. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

- b. If you need to send data to an on-premises Historian server, select **Historian Server**.
If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

9. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: `<Historian server name>_WindowsPerfMon`

10. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

11. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

12. Select **Add**.

The collector instance is added.

13. Select the collector instance.


The fields specific to the collector section appear in the **DETAILS** section.

14. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

15. As needed, enter values in the [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,


- If you have selected **Historian Configuration**, specify the tags using [Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of Historian>\GE Digital\<collector name>*. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Add and Configure a Wonderware Collector

The Wonderware Collector gathers data samples from a Wonderware Historian 2014 R2 server and stores it in the Proficiency Historian server. For more information, refer to [Overview of the Wonderware Collector \(on page 2566\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select .



The screenshot displays the 'Collectors' page in the Configuration Hub. The page title is 'Collectors' and it shows a list of 'Historian Collectors' under the 'Offline Configuration Collectors' section. The page is refreshed on 12/8/2022, 11:34:01 AM. A red box highlights a plus sign icon in the upper right corner of the main section, indicating where to click to add a new collector. The table below shows two collectors: 'Calculation' and 'Simulation', both with a status of 'Running'.

COLLECTOR NAME	STATUS
Calculation	Running
Simulation	Running

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Wonderware Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears. The field is disabled and populated.

7. In the **WONDERWARE SERVER** field, enter the host name or IP address of the Wonderware Historian server from which you want to collect data.
8. Enter values in the **USERNAME** and **PASSWORD** fields to connect to the Wonderware Historian server.
9. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

10. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.
 - a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).
 - b. If you need to send data to an on-premises Historian server, select **Historian Server**.
If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

11. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: `<Historian server name>_Wonderware`

12. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must contain the string `wonderware`.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

13. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

14. Select **Add**.

The collector instance is added.


15. Select the collector instance.

The fields specific to the collector section appear in the **DETAILS** section.

16. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
Recovery Time (hours)	<p>Enter the maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the Wonderware Historian server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>The default value is 0 hours.</p>
Throttle (Milliseconds)	<p>Enter the frequency of Wonderware data polling. This is to minimize the load on the Wonderware Historian server. By default, Wonderware Collector tries to query the tag data every 100 milliseconds based on the collection interval time. You can change this value to any time between 100 milliseconds to 16 hours.</p>
MTLS Security	<p>Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.</p>
MTLS Data Encryption	<p>Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).</p>
<p>For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632).</p>	

- As needed, enter values in the [the other sections common to all collectors \(on page 579\)](#).
- In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

- If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,

- If you have selected **Historian Configuration**, [specify the tags using Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: `<installation folder of Historian>\GE Digital\<<collector name>`. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Collector Configuration - Common Fields

This topic provides a list of general fields that you can configure for any collector instance. These fields appear in the **DETAILS** section when you select a collector instance. For fields specific to a cloud destination, refer to [Alibaba Cloud \(on page 587\)](#), [AWS Cloud \(on page 594\)](#), [Azure Cloud \(on page 601\)](#), [Google Cloud \(on page 614\)](#), and [Predix Cloud \(on page 621\)](#). For fields specific to the collector type, refer to the topics on adding and configuring each individual collector.

After you enter/modify a value in these fields, the changes are saved automatically after you place the cursor in a different field. Until the changes are saved, the values appear in bold formatting.

Table 29. The General Section

Field	Description
Collector Name	The name of the collector instance. This field is disabled.
Collector Type	The type of the collector instance. This field is disabled.
Description	The description of the collector instance. This field is disabled.
Memory Buffer Size (MB)	The size of the memory buffer currently assigned to the store-and-forward function. The memory buffer stores data during short-term or momentary interruptions of the server connection; the disk buffer handles long duration outages. To estimate the size you need for this buffer, you need to know how fast the collector is trying to send data to the

Table 29. The General Section (continued)

Field	Description
	<p>server and how long the server connection is likely to be down. With those values and a safety margin, you can compute the required size of the buffer.</p> <p>The default value is 20.</p>
Minimum Free Space (MB)	<p>The minimum free disk space that must be available on the computer. If the minimum space required is not available when the collector starts, the collector will shut down.</p>
Total Events Collected	<p>This field is disabled.</p>
Total Events Reported	<p>This field is disabled.</p>

Table 30. The Tags section

Field	Description
Tag Prefix	<p>The prefix that will be added to each tag that you configure for the collector instance. This field is disabled and populated with the name of the collector instance.</p> <p>This field applies to all collectors except File and Calculation collectors.</p>
Collection Interval Value	<p>The interval at which the collector collects data for all the tags configured in the collector instance.</p> <ul style="list-style-type: none"> • For polled data collection, this value represents the time required to complete a poll of tags in the collector. • For unsolicited data collection, it represents the frequency at which data is retrieved from tags in the collector. The collection interval can be individually configured for each tag. <p>You can set this value for each tag as well.</p>

Table 30. The Tags section (continued)

Field	Description
	<div style="border: 1px solid #f0e68c; padding: 10px; background-color: #fff9c4;"> <p>! Important: For an OPC collector, to avoid collecting redundant values when using device timestamps, specify a collection interval that is greater than the OPC server update rate.</p> </div>
Collection Interval	The units of measure for the collection interval value.
Collection Type	<p>The type of the data collection:</p> <ul style="list-style-type: none"> • Polled: Data is collected based on a scheduled time interval. This type of data collection is supported only for: <ul style="list-style-type: none"> ◦ The Calculation collector ◦ The HAB collector ◦ The iFIX collector ◦ The OPC Classic DA collector ◦ The OPC UA DA collector ◦ The Python collector ◦ The Simulation collector ◦ The Windows Performance collector • Unsolicited: Data is collected based on an event. This type of data collection is supported only for: <ul style="list-style-type: none"> ◦ The Calculation collector ◦ The HAB collector ◦ The MQTT collector ◦ The MQTT Sparkplug B collector ◦ The ODBC collector ◦ The OPC Classic DA collector ◦ The OPC Classic HDA collector ◦ The OPC UA DA collector ◦ The OSI PI collector ◦ The OSI PI distributor

Table 30. The Tags section (continued)

Field	Description
	<ul style="list-style-type: none"> ◦ The Python collector ◦ The Server-to-Server collector ◦ The Server-to-Server distributor ◦ The Wonderware Collector
Time Assigned By	<p>Indicates whether the timestamp for the collected data is set based on the data source or the collector. For example, for an OSI PI collector, if you select Source, the timestamp of the OSI PI server is considered for the values collected by the collector. If you select Collector, the timestamp of the collector is considered.</p>

Table 31. The Collector Compression Section

Field	Description
Collector Compression	<p>Indicates whether you want to apply collector compression, which is a smoothing filter to data retrieved from the data source. By ignoring small changes in values that fall within a deadband centered around the last reported value, only significant changes are stored in Historian, thus consuming less archive storage space.</p> <p>For more information, refer to About Collector and Archive Compression (on page 660).</p>
Deadband	<p>Indicates whether you want to apply a deadband based on the percentage of values or on absolute values.</p> <p>For example, if you set the deadband to 20% for a range of 0 to 500 engineering units, the deadband value is 100 units, which is 50 units on each side. Therefore, only if the difference between two values is greater than 50, they are stored in Historian.</p>

Table 31. The Collector Compression Section (continued)

Field	Description
	<div data-bbox="820 325 1421 588" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If the data quality changes from good to bad or vice versa, the values are stored in Historian regardless of the deadband value. </div>
Deadband Value	<p>The deadband value that you want to use for values collected by the collector. Depending on whether you have selected percent or absolute, the deadband value is determined.</p> <p>For example, if you want to set a deadband of 5 units on either side of a value (that is, value +/- 5), enter 10 in the Deadband Value field, and select Absolute in the Deadband field. Similarly, if you want to set a deadband of 5% on either side of a value, enter 10 in the Deadband Value field, and select Percent in the Deadband field.</p> <p>For more information, refer to About Collector and Archive Compression (on page 660).</p>
Compression Timeout	<p>The time for one poll cycle for which collector compression is not used, thus sending all the samples to Historian.</p> <p>This is used for a Calculation collector or Server-to-Server collector, when calculations fail, you may possibly observe collector compression (even if it is not enabled), thus producing no results or bad quality data. In such cases, you can use compression timeout, thus sending all the samples to Historian.</p> <p>For more information, refer to About Collector and Archive Compression (on page 660).</p>

Table 31. The Collector Compression Section (continued)

Field	Description
Compression Timeout Interval	The units of measure for compression timeout.
Spike Logic Control	<p>Indicates whether you want to apply spike logic to tag values. When you apply spike logic, in the event of a sudden change in tag values, a data sample is inserted just before the spike. The timestamp of the inserted sample is determined by your polling interval. If samples are collected at 1 second intervals, the inserted sample's timestamp will be 1 second before the spike. This helps clearly identify the spike, and retains a more accurate picture of the data leading up to it.</p> <p>For more information, refer to Enable Spike Logic (on page 970).</p>
Multiplier	<p>Specifies how much larger a spike value must be than the deadband range before the spike logic is invoked.</p> <p>For example, if you enter 3 in the Multiplier field, and the deadband is set to 5%, the spike logic will not be invoked until the difference between the spike value and the previously archived data point is 15% of the EGU range.</p>
Interval	<p>Specifies how many samples must have been compressed before the spike logic is invoked. For example, if you enter 4 in the Interval field, and 6 values have been compressed since the last archived data sample, the spike logic will be invoked.</p>

Table 32. The Collector Options Section

Field	Description
Online Tag Configuration Changes	Indicates whether you want tag configuration changes to reflect immediately. If you disable this option, any tag configuration changes will reflect only after you restart the collector instance.
Browse Source Address Space	Indicates whether you want to allow browsing for tags in the source. You may sometimes want to disable this option to reduce processing load on the collector.
Synchronize Timestamps to Server	<p>Indicates whether you want to adjust the timestamp of data to align with the time setting in the Historian server. Note that this does not change the time setting in the collector machine; it only calculates the timestamp based on the difference between the time settings in the server machine and the collector machine, independent of time zone or daylight saving differences.</p> <div data-bbox="821 1108 1414 1717" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <ul style="list-style-type: none"> This option is applicable only if the timestamp of the collector is considered (instead of that of the data source - as specified in the Time Assigned By field). If this option is disabled, and if the time in the collector machine is more than 15 minutes ahead of the time in the server machine, data will not be stored in Historian. </div>
Source/Device Timestamp in	The source/device timestamp format. Either UTC or Local.

Table 32. The Collector Options Section (continued)

Field	Description
Delay Collection at Startup (sec)	The duration, in seconds, after which you want the data collection to begin post tag configuration.

Table 33. The Advanced Section

Field	Description
Debug Mode	<p>The debug mode for collector logs. 0 indicates normal log level, whereas 255 indicates that debugging is enabled.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: Leaving the debug mode enabled for a long time consumes disk space.</p> </div>
Message Compression	Indicates whether you want to apply message compression.

Table 34. The Collector Status Output Section

Field	Description
Rate Output Address	<p>The address in the source database into which the collector writes the output of events/minute. This will help an operator (or a HMI/SCADA application) learn the performance of the collector. Values are captured once a minute.</p> <p>You must enter the address of a writable analog field.</p> <p>For example, for an iFIX collector, enter the address of an iFIX tag in the following format: <code><node name>.<tag name>.<field name></code> (for example, <code>MyNode.MySIM_AO.F_CV</code>).</p>
Status Output Address	The address in the source database into which the collector writes the current value of its status (for example, running, stopped). This will help an opera-

Table 34. The Collector Status Output Section (continued)

Field	Description
	<p>tor (or a HMI/SCADA application) learn the current status of the collector. The value is updated only if the status of the collector changes.</p> <p>You must enter the address of a writable text field of at least eight characters.</p> <p>For an iFIX collector, use TX tag for the output address. Enter the address in the following format: <code><node name>.<tag name>.<field name></code> (for example, <code>MyNode.MyCollector_TX.A_CV</code>).</p>
Heartbeat Output Address	<p>The address in the source database into which the collector writes the heartbeat signal output. Values are captured once a minute.</p> <p>You must enter the address of a writable analog field.</p> <p>For an iFIX data collector, use an iFIX tag for the output address. Enter the address in the following format: <code><node name>.<tag name>.<field name></code> (for example, <code>MyNode.MyCollector_TX.A_CV</code>).</p> <p>You can program the iFIX database to generate an alarm if values are not written every minute, notifying you that the collector has stopped.</p>

Sending Data to Cloud

Send Data to Alibaba Cloud

Generate a password using [the utility](#). While generating the password, use the same algorithm that you will use to connect to Alibaba Cloud.

To send data to Alibaba Cloud, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector
- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

1. Access Alibaba IoT Platform console.

2. [Create a product](#). When you do so:

- In the **Node Type** field, select **Directly Connected Device**.
- In the **Network Connection Method** field, select **Wi-Fi**.
- In the **Data Type** field, select **ICA Standard Data Format**.

* Product Name

* Node Type

 Directly Connected Device

 Gateway sub-device

 Gateway device

Networking and Data Format

* Network Connection Method

* Data Type ?

[✓ Checksum Type](#)
[✓ Authentication Mode](#)

More

[✓ Product Description](#)

3. Note down the region ID for the region you have selected. For a list of region IDs, refer to <https://www.alibabacloud.com/help/doc-detail/40654.htm>.
4. Access the product certificate, and note down the product secret and product key values.
5. [Create a device](#).
6. [Access Configuration Hub \(on page 336\)](#).
7. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the system appears.
8. If needed, select the system in which you want to add a collector instance.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE
Filter	Filter	Filter	Filter
.Distributor	Unknown	Historian	
.Simulation	Running	Historian	
.To_WIN10TECH	Unknown	Historian	

9. In the upper-right corner of the main section, select **+**.

Data Stores-win1... × **Collectors** × DETAILS ×

SYSTEM
 [Redacted]

Historian Collectors Offline Configuration Collectors

Refreshed on 12/8/2022, 11:34:01 AM ↻ + ⚙️

COLLECTOR NAME	STATUS
Filter	Filter
Calculation	Running
Simulation	Running

No data to display.

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

10. In the **COLLECTOR TYPE** field, select a collector type, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

11. Select **Next**.

The **Source Configuration** section appears, populating the hostname of the collector machine.

12. As needed, enter values in the available fields, and then select **Next**.

The **Destination Configuration** section appears.

13. In the **CHOOSE DESTINATION** field, select **MQTT**, and then provide values as described in the following table.

Field	Description
HOST ADDRESS	<p>Enter a value in the following format: <code><product name>.iot-as-mqtt.<region ID>.aliyuncs.com</code>. A value is required.</p> <p>For example: <code>a23dr53dwr.t-iot-as-mqtt.cn-shanghai.aliyuncs.com</code></p>
PORT	<p>Enter 1883. A value is required.</p>
CLIENT ID	<p>Enter a value in the following format: <code><device name> securemode=<value>,signmethod=<algorithm name></code>. A value is required.</p> <ul style="list-style-type: none"> ◦ For securemode, enter 2 for direct TLS connection, or enter 3 for direct TCP connection. ◦ For signmethod, specify the signature algorithm that you want to use. Valid values are hmacmd5, hmacsha1, hmacsha256, and sha256. You must use the same algorithm to generate the password. <p>For example: <code>MyDevice securemode=3,signmethod=hmacsha1</code></p>

Field	Description
TOPIC	<p>Enter a value in the following format: <code>/sys/<product name>/<device name>/thing/event/property/post</code>. A value is required.</p> <p>For example: <code>/sys/a23dr53dwrt/MyDevice/thing/event/property/post</code></p>
USERNAME	<p>Enter a value in the following format: <code><device name><product name></code>. A value is required.</p> <p>For example: <code>MyDevicea23dr53dwrt</code></p>
PASSWORD	<p>Enter the password that you have generated. A value is required.</p>
CHOOSE CONFIGURATION	<p>Select the type of the configuration to specify the tags whose data you want to collect. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Historian Configuration: Select this option if you want to add the tags manually using Historian Administrator (on page 659). If you select this option, the CONFIGURATION HISTORIAN SERVER field appears. ◦ Offline Configuration: Select this option if you want to provide the tag names using the offline configuration (on page 2039) file instead of adding tags manually. By default, this file is located in the following location: <code><installation folder of Historian>\GE Digital\<collector name></code>

14. Select **Next**.

The **Collector Initiation** section appears.

15. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

16. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

17. Select **Add**.

The collector instance is created.

18. Specify the tags for which you want to collect data.

- If you have selected **Historian Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags manually \(on page 357\)](#).
- If you have selected **Offline Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags using the offline configuration file \(on page 2039\)](#).

The collector begins sending Historian data to the device that you have created.

Send Data to AWS IoT Core

To send data to an AWS IoT Code, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector
- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

1. Access the **AWS Management Console** page.


2. Search and select **IoT Core**.

The **AWS IoT** page appears.

3. [Create a policy](#) allowing the permissions that you want to grant on your device (for example, iot:Connect, iot:Publish, iot:Subscribe, iot:Receive). For the resource, provide the topic name. If, however, you want to use all topics, enter *****.

4. [Create a thing](#), linking it with the policy that you have created.


5. Download the certificates and key files for the device to communicate. In addition, download the root CA certificate.



Important:

This is mandatory, and it is the only time you can download the certificates.

6. In the left navigation pane, select **Settings**.
7. Make a note of the endpoint that appears.




8. [Access Configuration Hub \(on page 336\)](#).
9. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the system appears.

10. If needed, select the system in which you want to add a collector instance.



11. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

12. In the **COLLECTOR TYPE** field, select a collector type (except the File collector and the Server-to-Server collector), and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

13. Select **Next**.

The **Source Configuration** section appears, populating the hostname of the collector machine.

14. As needed, enter values in the available fields, and then select **Next**.

The **Destination Configuration** section appears.

15. In the **CHOOSE DESTINATION** field, select **MQTT**, and then provide values as described in the following table.

Field	Description
HOST ADDRESS	Enter the endpoint that you have noted down. A value is required.
PORT	Enter 8883. A value is required.
CLIENT ID	Enter the thing name. A value is required.
TOPIC	Enter the MQTT topic to which you want the collector to publish data. A value is required. For information on topic names, refer to https://docs.aws.amazon.com/iot/latest/developer-guide/topics.html .
USERNAME	Enter any value. Since we will use a certificate-based authentication, username and password will not be used; however, you must still enter a value.

Field	Description
PASSWORD	Enter any value. Since we will use a certificate-based authentication, username and password will not be used; however, you must still enter a value.
CA SERVER ROOT FILE	Enter the path of the root CA certificate file that you have downloaded.
CLIENT CERTIFICATE	Enter the path of the device certificate that you have downloaded.
PRIVATE KEY FILE	Enter the path of the private key file that you have downloaded.
PUBLIC KEY FILE	Enter the path of the public key file that you have downloaded.
CHOOSE CONFIGURATION	<p>Select the type of the configuration to specify the tags whose data you want to collect. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Historian Configuration: Select this option if you want to add the tags manually using Historian Administrator (on page 659). If you select this option, the CONFIGURATION HISTORIAN SERVER field appears. ◦ Offline Configuration: Select this option if you want to provide the tag names using the offline configuration (on page 2039) file instead of adding tags manually. By default, this file is located in the following location: <code><installation folder of Historian>\GE Digital\<collector name></code>

16. Select **Next**.

The **Collector Initiation** section appears.

17. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

18. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

19. Select **Add**.

The collector instance is created.


20. Specify the tags for which you want to collect data.

- If you have selected **Historian Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags manually \(on page 357\)](#).
- If you have selected **Offline Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags using the offline configuration file \(on page 2039\)](#).

The collector begins sending Historian data to the thing that you have created.

21. Access AWS IoT Core, and in the left pane, select **Test**.

The **MQTT test client** page appears.



22. Subscribe to the topic to which the collector is publishing data, and then select **Subscribe**.

The messages received from the topic appear, indicating that the collector is sending data to the AWS IoT device.

AWS supports a payload of maximum 128 KB. Therefore, if the message size is greater than 128 KB, create a registry key named CloudMaxSamplesPerMsg for the collector instance, and decrease the value to 700 or less. If, however, you want to send more data in a message, we recommend that you create another collector instance and send data to another thing resource in AWS.

**Tip:**

To find out the message size, [modify the collector instance \(on page 634\)](#) and set the log level to 3 or more.

23. Create a [VPC destination](#) or an [HTTP destination](#) for the messages.
24. [Monitor the data that you have collected.](#)

Send Data to Azure Cloud in the Key-Value Format

To send data to an Azure IoT Hub device, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector
- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

This topic describes how to send data in the key-value format. In this format, the message size is bigger because names of the tag properties are repeated. However, it provides clarity to novice users. For example: `{"body":`

```
[{"tagname": "Azure_Iot_simulation_tag_1", "epochtime": 1629730936000, "tagvalue": 7129.124023438, "quality": 3},
{"tagname": "Azure_Iot_simulation_tag_2", "epochtime": 1629730936000, "tagvalue": 123.3738924567, "quality": 3}] , "message"
```

You can also [send data in the KairosDB format \(on page 608\)](#).


**Note:**

Data in Azure IoT Hub is stored for maximum seven days, after which it is deleted from the hub. Therefore, you must consume the data within seven days. Based on your requirement, you can store it in a relevant Azure storage. You can then use Azure functions or streaming analytics to analyse the data.

1. Create Azure IoT Hub.

i Tip:
 To choose the correct Azure IoT Hub tier based on your data throughput, refer to <https://docs.microsoft.com/en-us/azure/iot-hub/iot-hub-devguide-quotas-throttling>. For guidance on choosing the appropriate subscription, refer to <https://azure.microsoft.com/en-us/pricing/details/iot-hub/>

2. After you create Azure IoT Hub, select **Go to resource**, and then note down the hostname:




3. Create devices in Azure IoT Hub to group related tag information; thus mapping a collector instance to a device. We recommend that you create one device per collector instance. Ensure that the device is running.


When you create a device, use the following guidelines to choose the authentication type:

- **Symmetric Key:** Select this option if you want to use a Shared Access Signature (SAS) authentication.
- **X.509 Self-Signed:** Select this option if you want to create self-signed certificates using OpenSSL. We recommend that you use these certificates only for testing purposes. For instructions, refer to <https://docs.microsoft.com/en-us/azure/iot-hub/tutorial-x509-self-sign>.
- **X.509 CA Signed:** Select this option if you want to use CA-signed certificates


4. If you have selected **Symmetric Key** in the previous step, select the link in the **Device ID** column, and note down the shared access key value.



5. [Access Configuration Hub \(on page 336\)](#).
6. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
7. If needed, select the system in which you want to add a collector instance.
8. If needed, select the system in which you want to add a collector instance.



9. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

10. In the **COLLECTOR TYPE** field, select a collector type, and then select **Get Details**.
The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.
11. Select **Next**.
The **Source Configuration** section appears.
12. As needed, enter values in the available fields.
13. Select **Next**.

The **Destination Configuration** section appears.

The screenshot shows a configuration window titled "Add Collector Instance:". On the left, a vertical navigation pane lists four steps: "Collector Selection" (Simulation Collector), "Source Configuration" (WIN10TECH), "Destination Configuration" (MQTT), and "Collector Initiation". The "Destination Configuration" step is currently selected and highlighted in blue. The main area of the window is divided into sections: "CHOOSE DESTINATION*" with radio buttons for "Historian Server", "Predix Timeseries", "Azure IoT Hub", and "MQTT" (which is selected); "HOST ADDRESS*" and "PORT*" with input fields labeled "Enter Address" and "Enter Port"; "CLIENT ID*" and "TOPIC*" with input fields labeled "Enter Client ID" and "Enter Topic"; an "AUTHENTICATION" section with a toggle for "AUTO REFRESH" (which is turned on); "USER CREDENTIAL" section with "USERNAME*" and "PASSWORD" input fields labeled "Enter Username" and "Enter Password"; and an "SSL/TLS" section. At the bottom, there are "Previous", "Cancel", and "Next" buttons.

14. Select **MQTT**, and provide values as described in the following table.

Field	Description
HOST ADDRESS	Enter the host name of the resource that you have noted down in step 2. A value is required and must be in the following format: <code><Azure IoT Hub name>.azure-devices.net</code>
PORT	Enter 8883.
CLIENT ID	Enter the ID of the device that you created in step 3. A value is required and must be unique for an MQTT broker.
TOPIC	Enter <code>devices/<device ID>/messages/events</code> .
AUTO REFRESH	Indicates whether you want to automatically create/refresh the SAS authentication token when it expires.

Field	Description
	<ul style="list-style-type: none"> ◦ If you switch the toggle off, you must manually provide the token as soon as it expires. ◦ If you switch the toggle on, you must provide the shared access key that you have noted down in step 4. And, you can leave the PASSWORD field blank. <p>This is applicable only if you have selected Symmetric Key in step 3.</p>
USERNAME	<p>Enter a value in the following format: <code><host name or IP address>/<device ID>/?api-version=2018-06-30</code></p>
PASSWORD	<p>Enter the SAS token. This is applicable only if you have selected Symmetric Key in step 3 and if you have switched off the AUTO REFRESH toggle.</p> <p>For instructions on generating a SAS token, refer to https://docs.microsoft.com/en-us/azure/cognitive-services/translator/document-translation/create-sas-tokens?tabs=Containers.</p>
DEVICE SHARED KEY	<p>Enter the shared access key value that you noted down in step 4. A value is required. This is applicable only if you have selected Symmetric Key in step 3 and if you have switched the AUTO REFRESH toggle on.</p>
CA SERVER ROOT FILE	<p>Enter the path of the CA server root file that you want to use. You can find the file here: https://github.com/Azure-Samples/loTMQTTSample/blob/master/loTHubRootCA_Baltimore.pem.</p>
CLIENT CERTIFICATE	<p>Enter the path to the client certificate. A value is required. This is applicable only if you have selected one of these options in step 3:</p>

Field	Description
	<ul style="list-style-type: none"> ◦ X.509 Self-Signed: If you have selected this option, you can generate the certificate using OpenSSL. ◦ X.509 CA Signed: If you have selected this option, you would receive the certificate from CA.
PRIVATE KEY FILE	<p>Enter the complete path to the private key file. A value is required. This is applicable only if you have selected one of these options in step 3:</p> <ul style="list-style-type: none"> ◦ X.509 Self-Signed: If you have selected this option, you can generate the key file using OpenSSL. ◦ X.509 CA Signed: If you have selected this option, you would receive the key file from CA.
PUBLIC KEY FILE	<p>Enter the path to the public key file. This is applicable only if you have selected one of these options in step 3:</p> <ul style="list-style-type: none"> ◦ X.509 Self-Signed: If you have selected this option, you can generate the key file using OpenSSL. ◦ X.509 CA Signed: If you have selected this option, you would receive the key file from CA.
CHOOSE CONFIGURATION	<p>The type of the configuration to specify the tags whose data you want to collect. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Historian Configuration: Select this option if you want to add the tags manually (on page 357). If you select this option, the CONFIGURATION HISTORIAN SERVER field appears. ◦ Offline Configuration: Select this option if you want to provide the tag names using the offline configuration (on page

Field	Description
	<p>2039) file instead of adding tags manually. By default, this file is located in the following location: <i><installation folder of Historian>\GE Digital\<collector name></i></p>
<p>CONFIGURATION HISTORIAN SERVER</p>	<p>The host name of the machine from which you want to access Historian Administrator to add the tags manually for the collector. This field appears only if you have selected Historian Configuration in the CHOOSE CONFIGURATION field.</p>

15. Select **Next**.

The **Collector Initiation** section appears.

16. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.

- Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
17. In the **RUNNING MODE** field, select one of the following options.
- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
 - **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

18. Select **Add**.

The collector instance is created.

19. Specify the tags for which you want to collect data.

- If you have selected **Historian Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags manually \(on page 357\)](#).
- If you have selected **Offline Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags using the offline configuration file \(on page 2039\)](#).

The collector begins sending Historian data to the Azure IoT Hub device that you have created.

Send Data to Azure Cloud in the KairosDB Format

To send data to an Azure IoT Hub device, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector
- The OPC UA DA collector
- The OSI PI collector
- The Server-to-Server collector

- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

This topic describes how to send data in the KairosDB format. In this format, the message size is less because names of the tag properties are not repeated. For example: `[{"<tag name>": "Cloud_GCYSS3X2E.Simulation00001", "<timestamp, tag value, and quality>": [[1586260104000, 132560.203125000, 3]]}]`. If you use this format, you can only use SAS-based authentication; you cannot use certificate-based authentication.

You can also [send data in the key-value format \(on page 601\)](#).

**Note:**


Data in Azure IoT Hub is stored for maximum seven days, after which it is deleted from the hub. Therefore, you must consume the data within seven days. Based on your requirement, you can store it in a relevant Azure storage. You can then use Azure functions or streaming analytics to analyse the data.

1. Create Azure IoT Hub.

**Tip:**

To choose the correct Azure IoT Hub tier based on your data throughput, refer to <https://docs.microsoft.com/en-us/azure/iot-hub/iot-hub-devguide-quotas-throttling>. For guidance on choosing the appropriate subscription, refer to <https://azure.microsoft.com/en-us/pricing/details/iot-hub/>


2. [Create devices in Azure IoT Hub](#) to group related tag information; thus mapping a collector instance to a device. We recommend that you create one device per collector instance. Ensure that the device is running.
When you create a device, use only in the Symmetric Key authentication.
3. Select the link in the **Device ID** column, and note down the primary connection string value.



4. [Access Configuration Hub \(on page 336\)](#).
5. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
6. If needed, select the system in which you want to add a collector instance.
7. If needed, select the system in which you want to add a collector instance.



8. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

- In the **COLLECTOR TYPE** field, select a collector type, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

- Select **Next**.

The **Source Configuration** section appears.

- As needed, enter values in the available fields.

- Select **Next**.

The **Destination Configuration** section appears.

- Select **Azure IoT Hub**, and provide values as described in the following table.

Field	Description
DEVICE CONNECTION STRING	Identifies the Azure IoT device to which you want to send data. Enter the primary connection string value that you have noted down in step 3.

Field	Description
TRANSPORT PROTOCOL	<p>The protocol that you want to use to send data to Azure IoT Hub. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ HTTP ◦ MQTT ◦ AMQP ◦ MQTT_OVER_WEBSOCKETS ◦ AMQP_OVER_WEBSOCKETS <p>For information on which protocol to use, refer to Protocols and Port Numbers (on page 626).</p>
PROXY	<p>Identifies the URL of the proxy server to be used for both the authentication process and for sending data. If the collector is running on a network where proxy servers are used to access web resources outside of the network, then you must provide the proxy server settings. However, it does not affect the proxy server used by Windows when establishing secure connections. As a result, you must still configure the proxy settings for the Windows user account under which the collector service runs.</p>
PROXY USERNAME	The username to connect to the proxy server.
PROXY PASSWORD	The password to connect to the proxy server.
CHOOSE CONFIGURATION	<p>The type of the configuration to specify the tags whose data you want to collect. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Historian Configuration: Select this option if you want to add the tags manually (on page 357). If you select this option, the CONFIGURATION HISTORIAN SERVER field appears.

Field	Description
	<ul style="list-style-type: none"> ◦ Offline Configuration: Select this option if you want to provide the tag names using the offline configuration (on page 2039) file instead of adding tags manually. By default, this file is located in the following location: <code><installation folder of Historian>\GE Digital\<collector name></code>
CONFIGURATION HISTORIAN SERVER	<p>The host name of the machine from which you want to access Historian Administrator to add the tags manually for the collector. This field appears only if you have selected Historian Configuration in the CHOOSE CONFIGURATION field.</p>

The collector instance is created and connected to the Azure IoT Hub device.

14. Select **Next**.

The **Collector Initiation** section appears.

15. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

16. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

17. Select **Add**.

The collector instance is created.

18. Specify the tags for which you want to collect data.

- If you have selected **Historian Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags manually \(on page 357\)](#).
- If you have selected **Offline Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags using the offline configuration file \(on page 2039\)](#).

The collector begins sending Historian data to the Azure IoT Hub device that you have created.

Send Data to Google Cloud

1. Download the Google root CA certificate from <https://pki.google.com/roots.pem>.
2. [Create public/private key pairs](#). Use OpenSSL only for testing purposes.

To send data to a Google Cloud device, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector

- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector
- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

1. Access Google Cloud Platform.
2. [Create a project](#). Note down the project ID.
3. [Create a registry](#).

When you create the registry:

- Use the MQTT protocol.
- You can choose to provide a CA certificate.

Note down the registry ID and the region values.

4. [Add a device to the registry](#).

When you add the device:


- Allow device communication.
- Upload the public key or enter the details manually.

Note down the device ID.

5. [Access Configuration Hub \(on page 336\)](#).
6. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
7. If needed, select the system in which you want to add a collector instance.
8. If needed, select the system in which you want to add a collector instance.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE
<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>
..._Distributor	Unknown	Historian	
..._Simulation	Running	Historian	
..._To_WIN10TECH	Unknown	Historian	

9. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

10. In the **COLLECTOR TYPE** field, select a collector type, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

11. Select **Next**.

The **Source Configuration** section appears.

12. As needed, enter values in the available fields.

13. Select **Next**.

The **Destination Configuration** section appears.

14. Select **MQTT**, and provide values as described in the following table.

Field	Description
HOST ADDRESS	Enter <code>mqtt.googleapis.com</code> . A value is required.
PORT	Enter 8883 or 443.
CLIENT ID	Enter the ID of the device that you created in the following format: <code>projects/<project ID>/locations/<cloud region>/registries/<registry ID>/devices/<device ID></code> . For example: <code>projects/mygcpproject/locations/asia-east1/registries/testmqttgcpiot/devices/gcptesting</code> A value is required and must be unique for an MQTT broker.
TOPIC	Enter <code>devices/<device ID>/events</code> .
AUTO REFRESH	Indicates whether you want to automatically refresh the authentication token when it expires. If you switch the toggle off, you must manually

Field	Description
	provide the token as soon as it expires. Google Cloud accepts only those tokens that expire in 24 hours or less; therefore, we recommend that you switch the toggle on.
USERNAME	Enter any value. This value is not used, but only if you enter a value, you can proceed.
PASSWORD	If you have switched the AUTO REFRESH toggle on, leave this field blank. Historian generates a JSON Web Token (JWT) and uses it automatically.
CA SERVER ROOT FILE	Enter the path of the Google root CA certificate that you have downloaded.
CLIENT CERTIFICATE	Enter the path to the client certificate.
PRIVATE KEY FILE	Enter the complete path to the private key file. A value is required.
PUBLIC KEY FILE	Enter the path to the public key file. A value is required.
CHOOSE CONFIGURATION	<p>The type of the configuration to specify the tags whose data you want to collect. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Historian Configuration: Select this option if you want to add the tags manually (on page 357). If you select this option, the CONFIGURATION HISTORIAN SERVER field appears. ◦ Offline Configuration: Select this option if you want to provide the tag names using the offline configuration (on page 2039) file instead of adding tags manually. By default, this file is located in the following location: <code><installation folder of Historian>\GE Digital\<collector name></code>


- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

18. Select **Add**.

The collector instance is created.

19. Access Google Cloud Platform, and select **Pub/Sub > Topics**.



20. Select **Messages > PULL**.

Messages published to the topic that you have created appear. These messages contain the data sent by the collector instance. You can verify that the message content is correct by selecting **Message body**.

Send Data to Predix Cloud

To send data to Predix Cloud, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector

- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

1. [Register with the Timeseries service or any UAA service that you want to use](#). Note down the destination address, URI, client ID, client secret, and the zone ID that you have provided.
2. [Access Configuration Hub \(on page 336\)](#).
3. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the system appears.
4. If needed, select the system in which you want to add a collector instance.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE
.Distributor	Unknown	Historian	
.Simulation	Running	Historian	
.To_WIN10TECH	Unknown	Historian	

5. In the upper-right corner of the main section, select .

COLLECTOR NAME	STATUS
Calculation	Running
Simulation	Running

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

- In the **COLLECTOR TYPE** field, select a collector type (except the File collector and the Server-to-Server collector), and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

- Select **Next**.

The **Source Configuration** section appears, populating the hostname of the collector machine.

- As needed, enter values in the available fields, and then select **Next**.

The **Destination Configuration** section appears.

- In the **CHOOSE DESTINATION** field, select **Predix Timeseries**, and then provide values as described in the following table.

Field	Description
CLOUD DESTINATION ADDRESS	The URL of a data streaming endpoint exposed by the Predix Time Series instance to which you want to send data. Typically, it starts with "wss://". This value is used as part of the interface name and default tag prefix of the collector. Your Predix Time Series administrator can provide this URL.

Field	Description
IDENTITY ISSUER	The URL of an authentication endpoint for the collector to authenticate itself and acquire necessary credentials to stream to the Predix Time Series. In other words, this is the issuer ID of the Proficy Authentication instance that you want to use to connect to Predix Time Series. Typically, it starts with <code>https://</code> and ends with <code>/oauth/token</code> .
CLIENT ID	Identifies the collector when interacting with Predix Time Series. This is equivalent to the username in many authentication schemes. The client must exist in the Proficy Authentication instance identified by the identity issuer, and the system requires that the <code>timeseries.zones. {ZoneId}. ingest</code> and <code>timeseries.zones. {ZoneId}. query</code> authorities are granted access to the client for the Predix Zone ID specified. Your Predix Time Series administrator can provide this information.
CLIENT SECRET	The secret to authenticate the collector. This is equivalent to the password in many authentication schemes.
ZONE ID	Unique identifier of the instance to which the collector will send data.
PROXY	Identifies the URL of the proxy server to be used for both the authentication process and for sending data. If the collector is running on a network where proxy servers are used to access web resources outside of the network, then you must provide the proxy server settings. However, it does not affect the proxy server used by Windows when establishing secure connections. As a result, you must still configure the proxy settings for the Windows user account under which the collector service runs.
PROXY USERNAME	The username to connect to the proxy server.
PROXY PASSWORD	The password to connect to the proxy server.
DATAPPOINT ATTRIBUTES	The attributes or parameters related to a datapoint that you want the collector to collect. Select Add Attributes to specify the attributes. You can add maximum five attributes for each collector instance.

11. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

13. Select **Add**.

The collector instance is created.

14. Specify the tags for which you want to collect data.

- If you have selected **Historian Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags manually \(on page 357\)](#).
- If you have selected **Offline Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags using the offline configuration file \(on page 2039\)](#).

The collector begins sending Historian data to Predix Timeseries.

Protocols and Port Numbers

The following table provides a list of protocols that are available to send data to Azure IoT Hub, guidelines on which protocol to choose, and the port number that each protocol uses.

Protocol	When to Use	Port Number
HTTP	Use this protocol if the data that you want to send is not large and/or the default ports for the other protocols are not available.	80
MQTT	MQTT is lightweight compared to AMQP, and is widely used. Use this protocol if you want to send data using low bandwidth and/or you do not want to connect to multiple devices using the same connection.	8883
AMQP	AMQP is more reliable compared to other protocols. It sends data in batches, and hence, the network traffic is less compared to that of MQTT. Use this protocol if you want to send a large amount of data from multiple collectors frequently.	5671
MQTT over web sockets	MQTT is lightweight compared to AMQP, and is widely used. In addition, communication using web sockets is more reliable and secure. Use this protocol if you want to send data using low bandwidth and securely.	443
AMQP over web sockets	AMQP is more reliable compared to other protocols. It sends data in batches, and hence, the network traffic is less compared to that of MQTT. In addition, communication using web sockets is more reliable and secure. Use this protocol if you want to send a large amount of data from multiple collectors frequently and securely.	443

Managing Collector Instances

About Managing Collectors Using Configuration Hub

Collectors are used to collect data from various sources and send it to Historian. For a list of collectors and their usage, refer to [About Historian Data Collectors \(on page 1990\)](#).

After you install collectors and Remote Management Agent, the following artefacts will be available:

- **Executable files:** These files are required to add a collector instance.
- **Instances of the following collectors:**
 - The iFIX collector
 - The iFIX Alarms & Events collector
 - The OPC Classic Data Access collector for CIMPLICITY
 - The OPC Classic Alarms and Events collector for CIMPLICITY

These instances will be created only if iFIX and/or CIMPLICITY are installed on the same machine as the collectors.

- **The Remote Collector Management agent:** Provides the ability to manage collectors remotely.

You can then add a collector instance. This section describes how to [add a collector instance using Configuration Hub \(on page 357\)](#). You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

Access a Collector Instance

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.

A list of collectors appears, displaying the following columns:

Column	Description
COLLECTOR NAME	The name of the collector instance. If you select the link in this column, the details of the collector instance appears.
STATUS	The status of the collector. Contains one of the following values: <ul style="list-style-type: none"> ◦ Started ◦ Stopped ◦ Running ◦ Paused
CONFIGURATION	The source of the tag configuration for the collector. Contains one of the following values: <ul style="list-style-type: none"> ◦ HISTORIAN: Indicates that tags are configured using Historian Administrator. ◦ OFFLINE: Indicates that tags are configured using an offline configuration (on page 2039) file.

Column	Description
MACHINE	The name of the machine on which the collector is installed.
VERSION	The version number of the collector.
REPORT RATE	The average rate at which the collector is sending data. This is a general indicator of load on the collector.
OVERRUNS	The total number of data events not collected. In normal operation and under normal conditions, this value should always be zero. If the value is not zero, which indicates that data is being lost, you must take steps to reduce peak load on the system by increasing the collection interval.
COMPRESSION	The effectiveness of collector compression. If the value is low, you can increase the compression deadbands to pass fewer values and thus increase the effect of compression.
OUT OF ORDER	The total number of out-of-order samples for the collector.
REDUNDANCY	Indicates whether collector redundancy is enabled, which decreases the likelihood of lost data due to software or hardware failures. For information, refer to About Collector Redundancy (on page 975) .
TAG COUNT	The number of tags for which the collector collects data.
COMMENTS	The comments that you have entered for the collector.

**Tip:**

You can also add, reorder, and remove columns from the table. For instructions, refer to [Common Tasks in Configuration Hub \(on page 353\)](#).

3. Select the row containing the collector whose details you want to access.

The details of the collector appear in the **DETAILS** section.

**Note:**

If the **DETAILS** section does not appear, in the upper-right corner of the page, select , and then select **Details**.

4. If you want to access the collector performance, right-click the collector (or select **☰**), and then select **View Collector Performance**.

The screenshot shows the 'Historian Collectors' page in the Configuration Hub. A table lists various collectors with columns for Collector Name, Status, Configuration, Machine, and Versic. A context menu is open over the table, and the 'View Collector Performance' option is highlighted with a red box. The table data is as follows:

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSIC
ulation	Unknown	Historian		
	Running	Historian		
nCollector	Running	Historian		
.Calculation	Running	Historian		
.MQTTSparkplugB	Running	Historian		
.Python	Unknown	Historian		
.Python_1	Unknown	Historian		
.Python_2	Unknown	Historian		
.Simulation	Running	Historian		

The **Collector Performance** section appears, displaying the following graphs:

- **REPORT RATE:** The rate at which the collector collects data.
- **TOTAL EVENTS REPORTED:** The total number of events reported to the Historian archive from the collector. This number may not match the total events collected due to collector compression.
- **STATUS:** The status of the collector plotted at regular intervals.
- **COLLECTOR COMPRESSION:** The collector compression (in percentage) applied to tag values plotted at regular intervals.
- **OUT OF ORDER:** The number of samples that have been received out of sequence. Even though data is still stored, a steadily increasing number of out-of-order events indicates a problem with data transmission that you should investigate. For example, a steadily increasing number of out-of-order events when you are using the OPC Collector means that there is an out-of-order between the OPC server and the OPC collector. This may also cause an out-of-order between the OPC collector and the data archiver but that is not what this graph indicates.
- **OVERRUNS:** The number of overruns in relation to the total events collected. Overruns are a count of the total number of data events not collected on their scheduled polling cycle. An overrun occurs when the data source is changing tag values faster than the collector collecting values, which causes it to consistently remain behind the archiver updates. It implies that the collector is running against the hardware and/or network limits and you may consider partitioning the tags into two or more sets, each with separate collector instances.


In a normal operation, this value should be zero. You may be able to reduce the number of overruns on the collector by increasing the tag collection intervals (per tag).

- **MINIMUM EVENT RATE:** Specifies the minimum number of data samples per minute sent to the archiver from all the collector instance.
- **TOTAL EVENTS COLLECTED:** The total number of events collected from the data source by the collector instance.
- **MAXIMUM EVENT RATE:** Specifies the maximum number of data samples per minute sent to the archiver from all the collector instance.

Access the Tags in a Collector Instance

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears.
3. Right-click the collector instance whose tags you want to access (or select **☰**), and then select

Browse Tags.



A list of tags for which the collector instance collects data appears.

4. To narrow down your search results, select **Search**, enter the search criteria, and then enter **Search**.
You can add more search criteria by selecting **Add Attribute**.
You can enter a name or a value partially or use the wildcard character asterisk (*).
The list of tags are filtered based on the search criteria.

Add a Collector Instance

Before you begin using a collector, you must add an instance of the collector. You can add multiple instances of the same collector or instances of multiple collectors. To add multiple instances of a collector, perform the steps once again.

You can add and configure the following types of collector instances:

- [The Calculation collector \(on page 479\)](#)
- [The CygNet collector \(on page 482\)](#)
- [The File collector \(on page 486\)](#)
- [The HAB collector \(on page 489\)](#)
- [The iFIX collector \(on page 505\)](#)
- [The MQTT collector \(on page 510\)](#)
- [The MQTT Sparkplug B collector \(on page 519\)](#)
- [The ODBC collector \(on page 527\)](#)
- [The OPC Classic Alarms and Events collector \(on page 532\)](#)
- [The OPC Classic DA collector \(on page 534\)](#)
- [The OPC Classic HDA collector \(on page 540\)](#)
- [The OPC UA DA collector \(on page 544\)](#)
- [The OSI PI collector \(on page 549\)](#)
- [The OSI PI distributor \(on page 553\)](#)
- [The Server-to-Server collector \(on page 559\)](#)
- [The Server-to-Server distributor \(on page 563\)](#)
- [The Simulation collector \(on page 567\)](#)
- [The Windows Performance collector \(on page 571\)](#)
- [The Wonderware collector \(on page 575\)](#)

Enable MTLS Security for Collectors

Mutual TLS (MTLS) protocol is a secure and strong authentication mechanism. Using this protocol, you can also encrypt the data between Historian Server and Collectors.

Ensure that you have configured certificate-based security.

This topic describes how to enable MTLS security and encrypt data for collectors.




Note:

MTLS Security and **MTLS Data Encryption** are not applicable to the File collector.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. Select the row containing the collector for which you want to enable **MTLS Security** and **MTLS Data Encryption**.
The details of the collector appear in the **DETAILS** section.

 **Note:**

If the **DETAILS** section does not appear, in the upper-right corner of the page, select , and then select **Details**.




COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION
Calculation	Unknown	Historian		7.2.1089.0
Python	Starting	Historian		12.0.6572.0
Calculation	Running	Historian		12.0.6572.0
File	Running	Historian		12.0.6572.0
MQTTSparkplugB	Running	Historian		12.0.6572.0
Python	Unknown	Historian		12.0.6529.0

4. In the **COLLECTOR SPECIFIC CONFIGURATION** section, enable **MTLS Security**.

 **Note:**

You can enable **MTLS Security** and **MTLS Data Encryption** only if the collector is running.

5. After you enable **MTLS Security**, enable **MTLS Data Encryption**.



6. In the upper-right corner, select **Save**.
You will be prompted to restart the collector.

- To apply the changes, select **Restart Now**.

If you select **Restart Later**, a notification appears in the **DETAILS** section, stating that the selected collector instance needs a restart.

Modify a Collector Instance

This topic describes how to modify a collector instance using Configuration Hub. You can also [modify a collector instance using the RemoteCollectorConfigurator utility \(on page 799\)](#), which does not require you to install Web-based Clients.



Note:

- If the status of a collector instance is unknown, you cannot modify it.
- You cannot modify the instance of an offline collector.

- [Access Configuration Hub \(on page 336\)](#).
- In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors appears.



Tip:

You can filter the collectors by the system name.

Historian Collectors		Offline Configuration Collectors			
Refreshed on 12/20/2023, 2:56:26 PM +					
COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANCY
Filter	Filter	Filter	Filter	Filter	Filter
	● Running	Historian			
SamplePythonCollector	● Running	Historian			

- Select the collector instance that you want to modify. The details of the collector appear in the **DETAILS** section.



Tip:

If the **DETAILS** section does not appear, in the upper-right corner of the page, select and then select **Details**.

- As needed, modify values in the [available fields \(on page 579\)](#).

**Note:**

- You cannot modify the destination of a collector.
- For collectors earlier than version 9.0:
 - You cannot modify the details in the **INSTANCE CONFIGURATION** section.
 - Some of the details, such as the collector type, do not appear.

5. After you modify the values, in the upper-left corner of the page, select **Save**.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDU
Filter	Filter	Filter	Filter	Filter	Filter
Calculation	Unknown	Historian			
Distributor	Unknown	Historian			
File	Running	Historian			

Based on the values that you modified, you might be prompted to restart the collector. For the modifications to take effect, you must restart the collector.

6. Select **Restart Now**.

The collector instance restarts and the modifications take effect.

If you select **Restart Later**, a notification appears in the **DETAILS** section, stating that the selected collector instance needs a restart.

Add a Comment to a Collector Instance

This topic describes how to add a comment to a collector instance.

**Note:**

- You cannot modify or delete comments.
- You cannot add comments to offline collectors.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears.



Tip:

You can filter the collectors by the system name.

Historian Collectors		Offline Configuration Collectors			
Refreshed on 12/20/2023, 2:56:26 PM					
COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANCY
<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>
[blurred]	● Running	Historian	[blurred]	[blurred]	[blurred]
SamplePythonCollector	● Running	Historian	[blurred]	[blurred]	[blurred]

3. Select the collector instance to which you want to add a comment.

The details of the collector appear in the **DETAILS** section, along with a list of comments at the end.



Tip:

If the **DETAILS** section does not appear, in the upper-right corner of the page, select , and then select **Details**.

4. In the **DETAILS** section, in the text box below **Comments**, enter your comment, and then select **Add Comment**.

The comment is added to the collector instance.

Access a Comment on a Collector Instance

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears.



Tip:

You can filter the collectors by the system name.

Historian Collectors		Offline Configuration Collectors			
Refreshed on 12/20/2023, 2:56:26 PM					
COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANCY
<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>
[blurred]	● Running	Historian	[blurred]	[blurred]	[blurred]
SamplePythonCollector	● Running	Historian	[blurred]	[blurred]	[blurred]

3. Select the collector instance whose comments you want to access.

The details of the collector appear in the **DETAILS** section, along with a list of comments at the end.



Tip:

If the **DETAILS** section does not appear, in the upper-right corner of the page, select , and then select **Details**.

- To access comments in full screen, select . If you want to search for a comment, enter the search criteria in the **Search** field. You can also filter the comments based on a date and time range by selecting the values in the **FROM** and **TO** fields.

The comments are filtered based on the search criteria.

Start a Collector

You can start a collector using one of the following options:

- **Service:** Select this option if you want to start the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Command Line:** Select this option if you want to start the collector at a command prompt using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

- [Access Configuration Hub \(on page 336\)](#).
- In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors appears.



Tip:

You can filter the collectors by the system name.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANCY
Filter	Filter	Filter	Filter	Filter	Filter
SamplePythonCollector	● Running	Historian			

- Right-click the collector instance that you want to start (or select ) , and then select **Start**.

The screenshot shows the 'Collectors-Historian' interface. At the top, there's a 'SYSTEM' section and a 'Historian Collectors' section with the subtitle 'Offline Configuration Collectors'. A refresh button and a '+' icon are visible. Below this is a table with columns: COLLECTOR NAME, STATUS, CONFIGURATION, MACHINE, and VERSIC. The table contains several rows with various collector names and their statuses (Unknown, Running). A context menu is open over the table, listing actions like 'Start', 'Stop', 'Restart', 'Pause Data Collection', etc. The 'Start' button is highlighted with a red box.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSI
Simulation	Running	Historian		
Python_2	Unknown	Historian		
Python_1	Unknown	Historian		
Python	Unknown	Historian		
MQTTSparkplugB	Running	Historian		
Calculation	Running	Historian		
Collector	Running	Historian		
Simulation	Unknown	Historian		

The **Start: <collector name>** window appears.

4. Under **RUNNING MODE**, select one of the following options:

- **Service:** Select this option if you want to start the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Command Line:** Select this option if you want to start the collector at a command prompt using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

5. Select **Start**.

The collector is started, and the data collection begins. The status of the collector in the **Collectors** section changes to Starting and then to Running. If, however, the connection fails, the status changes to Unknown.



Note:

If auto-refresh is not enabled, refresh the collector manually.

Stop a Collector

When you stop a collector, the collector stops collecting data, and it is disconnected from the destination. If, however, you want the collector to remain connected to the destination, you can instead [pause data collection \(on page 641\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.

A list of collectors appears.

i Tip:
You can filter the collectors by the system name.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANT
SamplePythonCollector	Running	Historian			

3. Right-click the collector instance that you want to stop (or select **☰**), and then select **Stop**.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION
ulation	Unknown	Historian		
nCollector	Running	Historian		
.Calculation	Running	Historian		
.MQTTSparkplugB	Running	Historian		
.Python	Unknown	Historian		
.Python_1	Unknown	Historian		
.Python_2	Unknown	Historian		
.Simulation	Running	Historian		

The **Stop: <collector name>** window appears. The **COLLECTOR MACHINE** and **CURRENT RUNNING MODE** fields are populated and disabled.

4. If the collector is running in the command-line mode, enter values in the **USERNAME** and **PASSWORD** fields.

5. Select **Stop**.

The collector is stopped, and the data collection is paused. The status of the collector in the **Collectors** section changes to Stopped.


Restart a Collector

You can restart a collector to stop and start it again. You can restart a collector only if it is running. However, when you modify a collector instance, based on the values you modify, you will be prompted

and given the option to restart the collector before you save the modifications. Without restarting, the modifications will not take effect.


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors appears.

i Tip:
You can filter the collectors by the system name.



COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANCY
SamplePythonCollector	Running	Historian			

3. Right-click the collector instance that you want to restart (or select **☰**), and then select **Restart**.



COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSIC
Simulation	Unknown	Historian		
PythonCollector	Running	Historian		
MQTTSparkplugB	Running	Historian		
Python	Unknown	Historian		
Python_1	Unknown	Historian		
Python_2	Unknown	Historian		
Simulation	Running	Historian		

The **Restart: <collector name>** window appears. The **COLLECTOR MACHINE** and **CURRENT RUNNING MODE** fields are populated and disabled.

4. If the collector is running in the command-line mode, enter values in the **USERNAME** and **PASSWORD** fields.
5. Select **Restart**.
The collector is restarted, and the data collection is resumed.

Pause the Data Collection of a Collector

When you pause data collection, the collector stops collecting the data. However, the collector is still connected to the destination. If you want to disconnect the collector from the destination, [stop the collector \(on page 638\)](#).



Note:

You cannot pause the data collection of an offline collector.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors appears.



Tip:

You can filter the collectors by the system name.

Historian Collectors		Offline Configuration Collectors			
COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANCY
Filter	Filter	Filter	Filter	Filter	Filter
SamplePythonCollector	Running	Historian			

3. Right-click the collector instance for which you want to pause data collection (or select **⋮**), and then select **Pause Data Collection**.

The screenshot shows the 'Collectors-Historian' interface. A table lists various collector instances with columns for Collector Name, Status, Configuration, Machine, and Version. A context menu is open over one of the entries, showing options like 'Start', 'Stop', 'Restart', and 'Pause Data Collection'. The 'Pause Data Collection' option is highlighted with a red box.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSIC
ulation	Unknown	Historian		7.2.1089
	Running	Historian		12.0.654
nCollector	Running	Historian		12.0.654
.Calculation	Running	Historian		12.0.654
.MQTTSparkplugB	Running	Historian		12.0.654
.Python	Unknown	Historian		12.0.652
.Python_1	Unknown	Historian		12.0.652
.Python_2	Unknown	Historian		12.0.652
.Simulation	Running	Historian		12.0.654

A message appears, asking you to confirm whether you want to pause data collection.

4. Select **Pause**.

The data collection is paused, and the collector is stopped.

Resume the Data Collection of a Collector

1. [Access Configuration Hub \(on page 336\)](#).

2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.

A list of collectors appears.

i Tip:
You can filter the collectors by the system name.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANCY
SamplePythonCollector	Running	Historian			

3. Right-click the collector instance for which you want to resume data collection (or select **⋮**), and then select **Resume Data Collection**.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION
Simulation	Unknown	Historian		
PythonCollector	Running	Historian		
.Calculation	Running	Historian		
.MQTTSparkplugB	Running	Historian		
.Python	Unknown	Historian		
.Python_1	Unknown	Historian		
.Python_2	Unknown	Historian		
.Simulation	Running	Historian		

A message appears, asking you to confirm whether you want to resume data collection.

4. Select **Resume**.


The collector is started, and the data collection is resumed.

Delete the Buffer Files of a Collector

When you delete buffer files, the collector is stopped, and after the buffer files are deleted, it is restarted.


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears.

i Tip:
You can filter the collectors by the system name.



COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANT
Filter	Filter	Filter	Filter	Filter	Filter
SamplePythonCollector	Running	Historian			

3. Right-click the collector instance whose buffer files you want to delete (or select **☰**), and then select **Clear Buffer**.



COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSIC
ulation	Unknown	Historian		
nCollector	Running	Historian		
_Calculation	Running	Historian		
_MQTTSparkplugB	Running	Historian		
_Python	Unknown	Historian		
_Python_1	Unknown	Historian		
_Python_2	Unknown	Historian		
_Simulation	Running	Historian		

A message appears, asking you to confirm that you want to clear the buffer files.

4. Select **Clear**.
The **Clear Buffer: <collector name>** window appears.
5. If the collector is running in the command-line mode with a specific user account, enter values in the **USERNAME** and **PASSWORD** fields.

6. Select **Clear**.

The buffer files of the collector are deleted.


Move the Buffer Files of the Collector

We recommend that you move the buffer files to a new folder within the same drive. You cannot move files to a folder on a network shared drive.

When you move buffer files, the collector is stopped, and after the buffer files are moved, it is restarted.


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors appears.

Tip: You can filter the collectors by the system name.



COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANCY
Filter	Filter	Filter	Filter	Filter	Filter
SamplePythonCollector	Running	Historian			

3. Right-click the collector instance whose buffer files you want to move (or select **☰**), and then select **Move Buffer**.



COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSIC
Filter	Filter	Filter	Filter	Filter
Simulation	Unknown	Historian		
Collector	Running	Historian		
Calculation	Running	Historian		
MQTTSparkplugB	Running	Historian		
Python	Unknown	Historian		
Python_1	Unknown	Historian		
Python_2	Unknown	Historian		
Simulation	Running	Historian		

- Browse Tags
- Add Tags
- View Collector Performance
- Start
- Stop
- Restart
- Pause Data Collection
- Resume Data Collection
- Clear Buffer
- Move Buffer**
- Change Destination Server
- Reset Performance Counters
- Reset Overrides
- Update Collector Credentials
- Browse Activity Log
- Apply Configuration Template
- Delete

The **Move Buffer: <collector name>** window appears. The **CURRENT LOCATION, COLLECTOR MACHINE**, and **RUNNING MODE** fields are populated and disabled.

- In the **TARGET LOCATION** field, enter the path of the folder to which you want to move the buffer files.
- If the collector is running in the Windows service mode, select **Move Buffer**. If the collector is running in the command-line mode, enter values in the **USERNAME** and **PASSWORD** fields, and then select **Move Buffer**.

The buffer files are moved, and the collector is started.

Change the Destination Server of a Collector

- Ensure that Historian is installed on the new destination server to which you want the collector to send data.
 - Ensure that the collector whose destination server you want to change is running.
- [Access Configuration Hub \(on page 336\)](#).
 - In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors appears.




Tip:

You can filter the collectors by the system name.

Historian Collectors		Offline Configuration Collectors			
COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANCY
Filter	Filter	Filter	Filter	Filter	Filter
	● Running	Historian			
SamplePythonCollector	● Running	Historian			

Refreshed on 12/20/2023, 2:56:26 PM

- Right-click the collector instance whose destination server you want to change (or select **⋮**), and then select **Change Destination Server**.




The **Change Destination Server: <collector name>** window appears. The **COLLECTOR MACHINE**, **CURRENT RUNNING MODE**, and **CURRENT DESTINATION SERVER** fields are populated and disabled.

4. In the **NEW RUNNING MODE** field, select one of the following options:
 - **Service**: Select this option if you want to start the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
 - **Command Line**: Select this option if you want to start the collector in the command-line mode. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.
 5. In the **NEW DESTINATION SERVER** field, enter the host name or IP address of the new destination server to which you want the collector to send data.
 6. In the **USERNAME** and **PASSWORD** fields, enter the credentials to access the new destination server.
 7. Select **Change Server**.
The destination server of the collector is changed, and the collector is stopped.
1. Update the network message compression of the collector by modifying the collector instance using Configuration Hub.
 2. Reconfigure the collector properties using Historian Administrator.
 3. [Restart the collector \(on page 639\)](#).

Reset Performance Counters

This topic describes how to reset performance counters for a collector. Performance counters are used to monitor the performance of Historian components. You can reset it to zero if you want to reset the performance counters.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears, displaying the details.
3. Select the row containing the collector whose details you want to access.
4. Right-click the collector (or select **☰**), and then select **Reset Performance Counters**.



A confirmation window appears, prompting you whether or not to reset the performance counters to zero.


5. Select **Reset**.
All the performance counters are reset, including overruns.

Reset Overruns

This topic describes how to reset overruns count. Overruns are a count of the total number of data events not collected on their scheduled polling cycle. In normal operation, this value should be zero, if not, you can reset it to zero.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears, displaying the details.
3. Select the row containing the collector whose details you want to access.

- Right-click the collector (or select **☰**), and then select **Reset Overruns**.



A confirmation window appears, prompting you whether or not to reset the performance counter to zero.

- Select **Reset**.

The Overruns are reset.

Update Collector Credentials

Whenever there are some changes in the credentials of the destination Historian server, you can update the credentials for the collectors using that server. This topic describes how to update the collector credentials.

- [Access Configuration Hub \(on page 336\)](#).
- In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears, displaying the details.
- Select the row containing the collector whose details you want to access.
- Right-click the collector (or select **☰**), and then select **Update Collector Credentials**.

The screenshot shows the 'Collectors-Historian' interface. At the top, there's a 'SYSTEM' header and a 'DETAILS' tab. Below that, a search bar and a 'Refreshed on 12/22/2023, 11:13:12 PM' timestamp are visible. A table lists various collectors with columns for 'COLLECTOR NAME', 'STATUS', 'CONFIGURATION', 'MACHINE', and 'VERSIC'. A context menu is open over the table, listing actions like 'Start', 'Stop', 'Restart', 'Pause Data Collection', etc. The 'Update Collector Credentials' option is highlighted with a red box.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSIC
Filter	Filter	Filter	Filter	Filter
ulation	Unknown	Historian		
	Running	Historian		
nCollector	Running	Historian		
.Calculation	Running	Historian		
MQTTSparkplugB	Running	Historian		
Python	Unknown	Historian		
Python_1	Unknown	Historian		
Python_2	Unknown	Historian		
.Simulation	Running	Historian		

The **Update Collector Credentials: <Collector name>** window appears.

The 'Update Collector Credentials' dialog box is shown. It features a yellow information banner at the top stating: 'After successfully updating the credentials please restart the Remote Collector Manager in the Collector Machine.' Below this, there are input fields for 'DESTINATION SERVER', 'COLLECTOR DESTINATION-HISTORIAN CREDENTIALS', 'USERNAME' (with 'testuser13' entered), and 'PASSWORD' (masked with dots). At the bottom, there are four buttons: 'Reset', 'Test Connection', 'Cancel', and 'Update'.

5. Update the **USERNAME** and **PASSWORD**, and select **Test Connection**.
Testing connection will help you to validate if the destination server credentials that you entered are valid or not.
6. Select **Update**.
The updated credentials are saved.
7. Restart the Remote Collector Manager in the collector machine.


Apply Configuration Template to a Collector

You can apply the created template to collectors as needed. You will be prompted to confirm whether you want to overwrite few of the configuration values with the values in the template.


- Ensure that you have a [collector instance added \(on page 357\)](#).
- Ensure that you created a [configuration template for collectors \(on page 757\)](#).

This topic describes how to apply a configuration template to a collector.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears.
3. Right-click the collector (or select **ooo**), and then select **Apply Configuration Template**.



The **Apply Configuration Template** window appears, listing the available templates.



4. Select **Apply**.

A confirmation window appears, prompting you to confirm whether you want to overwrite few of the configuration values with the values in the template.

5. Select **Ok**.

6. In the upper-left corner, select **Save**.

The configurations in the template are applied to the collector.

Configure Collector Redundancy

1. [Create the collector instances \(on page 357\)](#) that you want to use for collector redundancy. All these collectors must be of the same type.



Note:

Collector redundancy is not available and supported for the following collectors:

- File Collector.
- Calculation Collector.




- Python Collector.
- Server-to-Server Collector.
- Server-to-Server Distributor.
- OSI PI Collector.
- OSI PI Distributor.

2. [Create tags \(on page 909\)](#) in the primary collector.
3. If you want to use the values of a watchdog tag as a failover trigger, [create the watchdog tag \(on page 909\)](#) in the primary collector.

Collector redundancy ensures that collection of your data remains uninterrupted. It uses two or more collectors that gather data from a single source. For more information, refer to [About Collector Redundancy \(on page 975\)](#).

This topic describes how to set up redundancy between two collectors - one primary and the other secondary. You can, however, set up multiple secondary collectors.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors appears.



3. For the primary collector, in the **DETAILS** section, under **REDUNDANCY**, switch the **Redundant Collector** toggle. And then, in the upper-left corner of the page, select **Save**. Redundancy is enabled for the primary collector.
4. Repeat the previous step for the secondary collector. Redundancy is enabled for the secondary collector.

5. For the secondary collector, in the **DETAILS** section, under **REDUNDANCY**, in the **Backup For** field, select the primary collector, and then select **Save**.

The secondary collector is configured as a backup for the primary collector.



Note:

If you want to add another collector in the redundancy group, in the **Backup For** field, select the secondary collector.

6. If you want to manually trigger a failover, perform the following steps. Or, if you want to configure automatic triggers, skip to the next step.
 - a. Select the collector that you want to make active.
 - b. In the **DETAILS** section, under **REDUNDANCY**, in the **Make Active Collector** field, select **Active Collector**.
7. For the secondary collector, in the **DETAILS** section, under **REDUNDANCY FAILOVER TRIGGERS**, enter values as described in the following table, and then select **Save**.

Field	Description
Collector Status	Switch the toggle if you want to trigger failover when the primary collector stops collecting data.
Watchdog Tag	Select  , and then select the tag whose values you want to use as a trigger. <div data-bbox="667 1234 1421 1365" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: The watchdog tag must be in the primary collector.</p> </div>
Failover on Bad Quality	Switch the toggle if you want to trigger failover when bad data is collected for the watchdog tag.
Failover on value	Specify whether you want to trigger a failover if the value of the watchdog tag is non-zero. You can use this option only if you have not used the No Value change interval field.
No Value change interval	Enter the duration in seconds after which you want to trigger a failover if the values of the watchdog tag do not change for the

Field	Description
	specified duration. You can use this option only if you have not used the Failover on value field.

The failover triggers are configured. As soon as any of these conditions are satisfied, the secondary collector becomes active and collects data.

Delete a Collector Instance

If you no longer want to use a collector instance to collect data, you can delete it. When you delete a collector instance, the Windows service for the collector, the Registry folder, and the buffer files are deleted as well.

This topic describes how to delete a collector instance using Configuration Hub. You can also [delete a collector instance using the RemoteCollectorConfigurator utility \(on page 817\)](#), which does not require you to install Web-based Clients.



Note:

When you delete an offline collector instance, the corresponding configuration file is not deleted. However, if another collector instance of the same interface name is created, the existing configuration file is replaced by a template configuration file.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors appears.




Tip:

You can filter the collectors by the system name.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION	REDUNDANT
Filter	Filter	Filter	Filter	Filter	Filter
SamplePythonCollector	● Running	Historian	[blurred]	[blurred]	

3. Right-click the collector instance that you want to delete (or select **⋮**), and then select **Delete**.



A message appears, asking you to confirm that you want to delete the collector instance.

4. If you want to delete the tags as well, select the **Delete associated tags** check box.
5. Select **Delete**.

The collector instance is deleted.

Managing Offline Configuration Collector Instances

Access Offline Configuration Collectors

Offline Configuration Collectors are the instances of collectors whose destination is the cloud and display the configuration details as Offline Configuration.

Add Collector Instance: santhoshwin10

Collector Selection
Simulation Collector

Source Configuration
santhoshwin10

Destination Configuration
Predix Timeseries

Collector Initiation

CLIENT ID* <i>Enter client ID</i>	CLIENT SECRET* <i>Enter secret</i>
ZONE ID* <i>Enter zone ID</i>	PROXY <i>Enter proxy</i>
PROXY USERNAME <i>Enter username</i>	PROXY PASSWORD <i>Enter password</i>

DATAPOINT ATTRIBUTES (OPTIONAL) ⓘ

ATTRIBUTE

[+ Add Attributes](#)

CONFIGURATION DETAILS

CHOOSE CONFIGURATION*

Historian Configuration Offline Configuration

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, expand **Systems**, and then select the system whose collectors you want to access.
The system appears in the main section.
3. Right-click the system whose collectors you want to access (or select **☰**), and then select **Browse Collectors**.
This displays the list of Historian collectors and Offline configuration collectors. By default, the Historian collector instances added to the system appear, displaying the following information.

i Tip:

- To access the details of a collector, select the row containing the collector instance. The details appear in the **DETAILS** section.
- You can show/hide/reorder columns in the table. For instructions, refer to [Common Tasks in Configuration Hub \(on page 353\)](#).


The Details panel for the Offline Configuration Collector Interface contains information regarding the instance configuration provided for the destination while installing software

 like Predix, MQTT, or Azure. For example, here is an example of the Details panel for the Offline Configuration Collector:

DETAILS ✕	
<input type="text" value="Search..."/>	
FIELD	VALUE
▾ INSTANCE CONFIGURATION	
Historian Server	SANTHOSHWIN10
Destination	Predix Timeseries
Cloud Destination Address	wss://gateway-predix-data-
Identity Issuer	https://9d4d55e0-14e1-4a4
Client ID	HistQA
Client Secret	
Zone ID	d459998a-656c-46c2-b525-
Proxy	http://PITC-Zscaler-America
Proxy Username	
Proxy Password	
Configuration	Offline
Configuration Historian S...	none

Manage Offline Configuration Collectors

Like other Historian collectors, Offline Configuration collectors can also be managed by selecting different options:




Refer to the following sections on how to use these options:

- [Start a Collector \(on page 637\)](#)
- [Stop a Collector \(on page 638\)](#)
- [Restart a Collector \(on page 639\)](#)
- [Delete the Buffer Files of a Collector \(on page 643\)](#)
- [Move the Buffer Files of the Collector \(on page 644\)](#)
- [Delete a Collector Instance \(on page 654\)](#)

Access the Tags in the Offline Configuration Collector Instance

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears.

3. Right-click the Offline Configuration collectors you want to access (or select **☰**), and then select **Browse Tags**.



A list of tags for which the Offline Configuration collector instance collects data appears.

4. To narrow down your search results, select **Search**, enter the search criteria, and then enter **Search**.

You can add more search criteria by selecting **Add Attribute**.

You can enter a name or a value partially or use the wildcard character asterisk (*).

The list of tags are filtered based on the search criteria.

Managing Tags

About Tags

A Historian tag is used to store data related to a property.

For example, if you want to store the pressure, temperature, and other operating conditions of a boiler, a tag will be created for each one in Historian.

When you collect data using a collector, tags are created automatically in Historian to store these values. These tags are mapped with the corresponding properties in the source.

For example, suppose you want to store OSI PI data in Historian. You will specify the OSI PI tags for which you want to collect data. The OSI PI collector creates the corresponding tags in Historian, and it stores the values in those tags.

You can also choose to create tags manually (for example, to store the result of a calculation performed by the Calculation collector).

About Array Tags

You can store a set of values with a single timestamp and single quality and then read the elements individually or as an array.

The following conditions apply when using an array tag:

- You need not specify the size of an array tag. Data Archiver will store the number of elements that were written.
- You can change a tag to an array tag later as well. However, when you do so, only the latest data is retrieved. If you want to get the old data, you must change the tag back to its previous type.
- The maximum number of elements that an array tag can store is 10,000.
- You cannot associate an enumerated set or a user-defined data type (UDT) with an array tag.
- Fixed String and Scaled data types are not supported.
- Scaling, collector compression, and archive compression do not apply to an array tag.
- You cannot use an array element as a calculation trigger.
- You cannot plot a trend chart for an array tag.
- TagStats calculation mode is not supported.

About Collector and Archive Compression

Collector Compression

Collector compression applies a smoothing filter to data retrieved from the data source. By ignoring small changes in values that fall within a deadband centered around the last reported value, only significant changes are reported to the archiver. Fewer samples reported yields less work for the archiver and less archive storage space used.

You can specify the deadband value. For convenience, if you enter a deadband percentage, Historian Administrator shows the deadband in engineering units. For example, if you specify a 20% deadband on 0 to 500 EGU span, it is calculated and shown as 100 engineering units. If you later change the limits to 100 and 200, the 20% deadband is now calculated as 20 engineering units.

The deadband is centered around the last reported sample, not simply added to it or subtracted. If your intent is to have a deadband of 1 unit between reported samples, you must enter a compression deadband of 2 so that it is one to each side of the last reported sample. In the previous example of 0 to 500 EGU range, with a deadband of 20%, the deadband is 100 units; This means that only if the value changes by more than 50 units, it is reported.

Changes in data quality from good to bad, or bad to good, automatically exceed collector compression and are reported to the archiver. Any data that comes to the collector out of time order will also automatically exceed collector compression.

It is possible for collected tags with no compression to appear in Historian as if the collector or archive compression options are enabled. If collector compression occurs, you will notice an increase in the percentage of the compression value in the **Collectors** section of the **System Statistics** page in Historian Administrator. When archive compression occurs, you will notice the archive compression value and status bar change on the **System Statistics** page.

For instructions on setting collector compression, refer to [Access/Modify a Tag \(on page 894\)](#).

Even if collector compression is not enabled, you may notice it in the following scenarios:

- When a succession of bad data quality samples appears, Historian collects only the first sample in the series. No new samples are collected until the data quality changes. Historian does not collect the redundant bad data quality samples, and this is reflected in the collector compression percentage.
- For a Calculation or Server-to-Server collector, when calculations fail, producing no results or bad quality data, collector compression is used. The effect of Collector Compression Timeout is to behave, for one poll cycle, as if the collector compression feature is not being used. The sample collected from the data source is sent to the archiver. Then the compression is turned back on, as configured, for the next poll cycle with new samples being compared to the value sent to the archiver.

**Note:**

Array tags do not support archive and collector compression. If the tag is an array tag, then the **Compression** tab is disabled.

Handling Value Step Changes with Collector Data Compression

If you enable collector compression, the collector does not send values to the archiver any new input values if the value remains within its compression deadband. Occasionally, after several sample intervals inside the deadband, an input makes a rapid step change in value during a single sample interval. Since there have been no new data points recorded for several intervals, an additional sample is stored one interval before the step change with the last reported value to prevent this step change from being viewed as a slow ramp in value. This value marks the end of the steady-state, non-changing value period, and provides a data point from which to begin the step change in value.



Note:

You can configure individual tags can be configured to retrieve step value changes.

The collector uses an algorithm that views the size of the step change and the number of intervals since the last reported value to determine if a marker value is needed. The following is an example of the algorithm:

```
BigDiff=abs(HI_EGU-LO_EGU)*(CompressionDeadbandPercent/(100.0*2.0))*4.0

If ( Collector Compression is Enabled )

If ( Elapsed time since LastReportedValue>=( SampleInterval * 5 ) )

If ( abs(CurrentValue-LastReportedValue) > BigDiff )

Write LastReportedValue,TimeStamp=(CurrentTime-SampleInterval)
```

In the example above, if a new value was not reported for at least the last 4 sample intervals, and the new input value is at least 4 deltas away from the old value (where a single delta is equal to half of the compression deadband), then a marker value is written.



Note:

These settings are also adjustable from the Registry. Please contact [technical support](#) for more information.

Value Spike with Collector Compression

For example, a collector reads a value X once per second, with a compression deadband of 1.0. If the value of X is 10.0 for a number of seconds starting at 0:00:00 and jumps to 20.0 at 0:00:10, the data samples read would be:

Time	X Value
0:00:00	10.0 (steady state value)
0:00:01	10.0
0:00:02	10.0
0:00:03	10.0
0:00:04	10.0
0:00:05	10.0
0:00:06	10.0

Time	X Value
0:00:07	10.0
0:00:08	10.0
0:00:09	10.0
0:00:10	20.0 (new value after step change)

To increase efficiency, the straightforward compression would store only 2 of these 11 samples.

Time	X Value
0:00:00	10.0 (steady state value)
0:00:10	20.0 (new value after step change)


However, without the marker value, if this data were to be put into a chart, it would look like the data value **ramped** over 10 seconds from a value of 10.0 to 20.0, as shown in the following chart.



The addition of a **marker value** to the data being stored results in the following data values:

Time	X Value
0:00:00	10.0 (steady state value)
0:00:09	10.0 (inserted Marker value)
0:00:10	20.0 (new value after step change)

If you chart this data, the resulting trend accurately reflects the raw data and likely real world values during the time period as shown in the following chart.



Evaluating and Controlling Data Compression

You can achieve optimum performance in Historian by carefully controlling the volume of dynamic data it collects and archives. You need enough information to tell you how the process is running, but you do not need to collect and store redundant or non-varying data values that provide no useful information.

Control Data Flow

You can control the amount of online or dynamic data the system handles at a given time by adjusting certain system parameters. The general principle is to control the flow of data into the archive either by adjusting the rate at which the collectors gather data or by adjusting the degree of filtering (compression) the system applies to the data collected.

Adjust the following parameters to *reduce* the rate of data flow into the server.

- Reduce the polling rate by increasing the collection interval for unsolicited and polled collection.
- Enable collector compression and optionally use compression timeout.
- Set the compression deadband on the collectors to a wider value.
- Use the collector compression timeout.

Adjust the following parameters to *increase the filtering* applied by the archiver in the server.

- Enable archive (trend) compression.
- Set the archive compression deadband to a wider value.
- Where possible, use the scaled data type and enable input scaling on selected tags.
- Where possible, select milliseconds or microseconds rather than seconds for time resolution.
Seconds is optimum for most common devices. This affects disk space.

Evaluate Data Compression Performance

You can determine how effectively data compression is functioning at any given time by examining the system statistics displayed on the **System Statistics** page of Historian Administrator.

The compression field at the top of the page shows the current effect of archive compression. Values for this parameter should typically range from 0 to 9%. If the value is zero, it indicates that compression is either ineffective or turned off. If it shows a value other than zero, it indicates that archive compression is operating and effective. The value itself indicates how well it is functioning. To increase the effect of data compression, increase the value of archive compression deadband so that compression becomes more active.

Archive Compression

Archive compression is used to reduce the number of samples stored when data values for a tag form a straight line in any direction. For a horizontal line (non-changing value), the behavior is similar to collector compression. But, in archive compression, it is not the *values* that are being compared to a deadband, but the *slope of line* those values produce when plotted value against time. Archive compression logic is executed in the data archiver and, therefore, can be applied to tags populated by methods other than collectors.

You can use archive compression on tags where data is being added to a tag by migration, or by the File collector, or by an SDK program for instance. Each time the archiver receives a new value for a tag, the archiver computes a line between this incoming data point and the last archived value.

The deadband is calculated as a tolerance centered about the slope of this line. The slope is tested to see if it falls within the deadband tolerance calculated for the previous point. If the new point does not exceed the tolerance, it is not stored in the archive. This process repeats with subsequent points. When an incoming value exceeds the tolerance, the value held by the archiver is written to disk and the incoming sample is withheld.

The effect of the archive compression timeout is that the incoming sample is automatically considered to have exceeded compression. The withheld sample is archived to disk and the incoming sample becomes the new withheld sample. If the Archive Compression value on the System Statistics page indicates that archive compression is occurring, and you did not enable archive compression for the tags, the reason could be because of internal statistics tags with archive compression enabled.

For instructions on setting archive compression, refer to [Access/Modify a Tag \(on page 894\)](#).

About Scaling

Scaling converts a data value from a raw value expressed in an arbitrary range of units, such as a number of counts, to one in engineering units, such as gallons per minute or pounds per square inch. The scaled data type can serve as a third form of data compression, in addition to collector compression and archive compression, if it converts a data value from a data type that uses a large number of bytes to one that uses fewer bytes.

About Condition-Based Collection

Condition based collection is a method to control the storage of data for data tags by assigning a condition. Data is always collected but it is only written to the Data Archiver if the condition is true; otherwise, the collected data is discarded.

This condition is driven by a trigger tag; a tag collected by the collector evaluating the condition. Ideally, Condition based Collection should be used only with tags that are updating faster than the trigger tag. Condition based collection can be used to archive only the specific data which is required for analysis, rather than archiving data at all times, as the collector is running.

For example, if a collector has tags for multiple pieces of equipment, you can stop collection of tags for one piece of equipment during its maintenance. It is typically used on tags that use fast polled collection but you don't want to use collector compression. While the equipment is running, you want all the data but when the equipment is stopped, you don't want any data stored. The trigger tag would also typically use polled collection. But, either tag could use unsolicited collection.

The condition is evaluated every time data is collected for the data tag. When a data sample is collected, the condition is evaluated and data is either queued for sending to archiver, or discarded. If the condition

cannot be evaluated as true or false, like if the trigger tag contains a bad data quality or the collector is not collecting the trigger tag, the condition is considered true and the data is queued for sending.

No specific processing occurs when the condition becomes true or false. If the condition becomes true, no sample is stored to the data tag using that condition, but the data tag will store a sample next time it collects. When the condition becomes false, no end of the collection marker is stored until the data tag is collected.

For example, if the condition becomes false at 1:15 and the data tag gets collected at 1:20, the end of collection marker will be created at 1:20 and have a timestamp of 1:20, not 1:15.

Condition based collection is supported by only archiver and collectors of Historian version 4.5 and above. Condition based collection does not apply to alarm collectors. This condition based collection is applicable to the following collectors only:

- Simulation Collector
- OPC Collector
- iFIX Collector
- PI Collector

For instructions on setting the condition-based collection, refer to [Access/Modify a Tag \(on page 894\)](#).


Add Tags for the Data Store Using Configuration Hub

- [Add the collector instance \(on page 357\)](#) using which you want to collect data. Ensure that the collector is running.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, [create it \(on page 370\)](#).

This topic describes how to specify the tags for which you want to collect data by browsing through the tags in the data source. For example, for an iFIX collector, if there are 1,00,000 tags in the iFIX server, you must specify the ones for which you want to collect data. Only then data is collected for those tags.

In addition to adding tags from the data source, you can [create tags manually \(on page 473\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select  .



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. A value is required.
COLLECTED TYPE	Specify whether you want to browse through all the tags in the data source or only from the tags that you have not added yet. A value is required.
SOURCE TAG NAME	Enter the name of the tag (either completely or partially) to narrow down the search results.
SOURCE TAG DESCRIPTION	Enter the description of the tag (either completely or partially) to narrow down the search results.

5. Select **Search Tags**.

A list of tags that match *all* the criteria that you have specified appears. If a tag is already added, it is disabled.

6. Select the check box corresponding to each tag for which you want to collect data.

Add Tags from Collector
 Add Manually

COLLECTOR NAME*
 COLLECTED TYPE*
 SOURCE TAG NAME
 SOURCE TAG DESCRIPTION

SEARCH RESULTS FOR SOURCE TAGS NAMES

<input type="checkbox"/>	TAG NAME	DESCRIPTION
	<i>Filter</i>	<i>Filter</i>
<input type="checkbox"/>	Simulation.Simulation00001	Simulation.Simulation00001
<input type="checkbox"/>	Simulation.Simulation00002	Simulation.Simulation00002
<input type="checkbox"/>	Simulation.Simulation00003	Simulation.Simulation00003
<input type="checkbox"/>	Simulation.Simulation00004	Simulation.Simulation00004
<input type="checkbox"/>	Simulation.Simulation00005	Simulation.Simulation00005
<input type="checkbox"/>	Simulation.Simulation00006	Simulation.Simulation00006
<input type="checkbox"/>	Simulation.Simulation00007	Simulation.Simulation00007
<input type="checkbox"/>	Simulation.Simulation00008	Simulation.Simulation00008
<input type="checkbox"/>	Simulation.Simulation00009	Simulation.Simulation00009
<input type="checkbox"/>	Simulation.Simulation00010	Simulation.Simulation00010
<input type="checkbox"/>	Simulation.Simulation00011	Simulation.Simulation00011
<input type="checkbox"/>	Simulation.Simulation00012	Simulation.Simulation00012

DATASTORE*

7. In the **DATA STORE** field, if you want to store the data in a different data store than the user data store, select the same.

8. Select **Add Tag**.

Data collection begins for the selected tags.


As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.

Add a Tag Manually

- [Add the collector instance \(on page 357\)](#) using which you want to collect data.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, [create it \(on page 370\)](#).


After you create a collector instance, you [specify which tags from the source must be used for data collection \(on page 357\)](#). In addition, if you want to use the same tag twice (say, with a different collection interval or collector compression settings), you can add the tag manually. You can also create a calculation tag or a tag to store the values imported using the Excel Add-in.

1. Access Configuration Hub (on page 336).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **+**.



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Select **Add Manually**.



5. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. If, however, this tag is not associated with a collector, you

Field	Description
	can leave the field blank (for example, you want to ingest this data manually instead of using a collector).
SOURCE ADDRESS	Specify the source tag to which you want to map the one you are creating. This field is enabled only if you select a value in the COLLECTOR NAME field. When you select ○○○ , the Browse Source Tag: <collector name> window appears. Provide the search criteria to find the tag that you want to map.
TAG NAME	<p>Enter a name for the tag. A value is required and must be unique for the Historian server.</p> <p>The value that you enter:</p> <ul style="list-style-type: none"> ◦ Must begin with a letter or a number. ◦ Can contain up to 256 characters. ◦ Can include any of the following special characters: /! #{}%\$-_ ◦ Must not include a space or any of the following characters: ~`+^:;,?"*=@
DATA TYPE	<p>Select the data type of the tag data. To find out the data types supported by a collector, refer to the documentation on the collector that you have created.</p> <div style="border: 1px solid #ffc107; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Important: If you select an unsupported data type, you may receive incorrect data or even lose data.</p> </div> <p>If you select Multi-Field, the USER-DEFINED TYPE NAME field appears, and the ENUMERATED SET and ARRAY TAG fields are disabled.</p> <p>If you select Fixed String, the STRING LENGTH field appears.</p>
STRING LENGTH	<p>Enter the maximum character length allowed for the tag data. This field appears only if the value in the DATA TYPE field is Fixed String. A value is required.</p> <p>You can enter a value between 1 and 255. The default value is 8.</p>

Field	Description
USER-DEFINED TYPE NAME	Select the user-defined data type (UDT) (<i>on page 719</i>) that you want to assign to the tag. This field appears only if the value in the DATA TYPE field is Multi-Field . A value is required.
ENUMERATED SET	Select the enumerated set (<i>on page 707</i>) that you want to assign to the tag. This field is not applicable for string and multi-field data types (enumerated sets) and for array tags.
ARRAY TAG	Switch the toggle to indicate whether the tag stores an array of data. This field is disabled if you select a value in the ENUMERATED SET field or if the value in the DATA TYPE field is Multi-Field . For information on array tags, refer to About Array Tags (<i>on page 660</i>).
TIME RESOLUTION	Select the time resolution for the tag. A value is required. For example, if you select Seconds , when you plot the data on a trend chart, the timestamp of the data points will be one second apart.
DATA STORE	If you want to store the data in a different data store than the user data store, select the same.

6. Select **Add Tag**.

Data collection begins for the selected tags.

As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.

Access a Tag

To search for a tag, you can choose from the following options:

- Access all the tags in all the systems available in the Historian server.
- Access the tags added to a specific collector instance.
- Access the tags added to all the collector instances in a specific Historian system.

You can narrow down the search results further by performing a search.

**Note:**

By default, maximum one million tags are retrieved. If the Historian clients are configured to retrieve more than a million tags, to retrieve all of them, add the `MaxTagsToRetrieve` registry key under `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\DataArchiver\`, and then set the maximum number of tags that you want to retrieve. Restart the Historian Data Archiver service for the change to reflect.


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears, displaying the following information.

Column	Description
TAG NAME	The name of the tag.
DESCRIPTION	The description of the tag.
COLLECTOR NAME	The name of the collector instance to which you have added the tag.
LAST 10 VALUES	The last 10 values collected for the tag, plotted as a trend chart. If you pause over the chart, the minimum, maximum, first, and last values among the 10 values appear.
TAG ALIAS	Indicates whether the tag contains aliases, which are created when you rename the tag using an alias (on page 698) .

**Tip:**

You can show/hide/reorder columns in the table. For instructions, refer to [Common Tasks in Configuration Hub \(on page 353\)](#).


3. If you want to access the tags specific to a Historian system, in the drop-down list box in the upper-left corner of the main section, select the system.



Alternatively, you can access the system from the **NAVIGATION** section, right-click the system (or select **ooo**), and then select **Browse Tags**.

The list of tags is filtered to display only the tags specific to the system.

4. If you want to narrow down the search results, select **Search**.



Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*).

The tags are filtered based on the search criteria.

5. Select the row containing the tag that you want to access.

The tag details appear in the **DETAILS** section.

Table 35. The General Section

Field	Description
Tag Name	The name of the tag. This field is disabled and populated.
Description	The description of the tag.
Comment	Comments that apply to the tag.

Field	Description
StepValue	Indicates that the actual measured value changes in a sharp step instead of a smooth linear interpolation. This option is applicable only for numeric data. Enabling this option only affects data retrieval; it has no effect on data collection or storage.
Last Modified Time	The date the last tag parameter modification was made. This field is disabled and populated.
Last Modified User	The name of the person who last modified the tag configuration parameters. This field is disabled and populated.

Table 36. The Collection Section

Field	Description
Collector	The name of the collector that collects data for the selected tag.
Source Address	<p>The address for the tag in the data source. Leave this field blank for tags associated with the Calculation or Server-to-Server collector.</p> <p>For Python Expression tags, this field contains the full applicable JSON configuration, which includes an indication of the source address.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note:</p> <p>When exporting or importing tags using the Excel Add-in for Historian, the Calculation column, not the SourceAddress column, holds the formulas for tags associated with the Calculation or Server-to-Server collector.</p> </div>
Data Type	<p>The data type of the tag.</p> <p>The main use of the scaled data type is to save space, but this results in a loss of precision. Instead of using 4 bytes of data, it only uses 2 bytes by storing the data as a percentage of the EGU limit. Changing the EGU limits will result in a change in the values that are displayed. For example, if the original EGU values were 0 to 100 and a value of 20 was stored using the scaled data type and if the EGUs are changed to 0 to 200, the original value of 20 will be represented as 40.</p>

Field	Description
	<div style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;">  Note: If you change the data type of an existing tag between a numeric and a string or binary data type (and vice versa), the tag's compression and scaling settings will be lost. </div>
Value	The number of bytes for a fixed string data type. This field is enabled only for fixed string data types.
Enumerated Set Name	The name of the enumerated set (on page 707) that you want to assign to the tag.
Array Tag	Indicates that the tag is an array tag (on page 660) .
Location	The distributed location of the system in which the tag data is stored (applicable only for a horizontally scalable system).
Data Store	The data store in which the tag data is stored.
Collection	Indicates whether data collection is enabled or disabled for the tag. If you disable collection for the tag, Historian stops collecting data for the tag, but does not delete the tag or its data.
Collection Type	The type of data collection used for this tag, which can be polled or unsolicited. Polled means that the data collector requests data from the data source at the collection interval specified in the polling schedule. Unsolicited means that the data source sends data to the collector whenever necessary (independent of the data collector polling schedule).
Collection Interval	The time interval between readings of data from this tag. With Unsolicited Collection Type, this field defines the minimum interval at which unsolicited data should be sent by the data source.
Collection Offset	Used with the collection interval to schedule collection of data from a tag. For example, to collect a value for a tag every hour at thirty minutes past the hour (12:30, 1:30, 2:30, and so on), enter a collection interval of 1 hour and an offset of 30 minutes. Similarly, to collect a value each day at 8am, enter a collection interval of 1 day and an offset of 8 hours.

Field	Description
	<div style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;">  Note: If you enter a value in milliseconds, the value must be in intervals of 1000 ms. For example, 1000, 2000, and 3000 ms are valid values, but 500 and 1500 ms are invalid. The minimum value is 1000 ms. </div>
Time Resolution	The precision for timestamps, which can be either seconds, milliseconds or microseconds.
Condition-Based	Indicates whether condition-based data collection (on page 666) is enabled.
Trigger Tag	The name of the trigger tag used in the condition.
Comparison	<p>The comparison operator that you want to use in the condition. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Undefined: Collection will resume only when the value of the triggered tag changes. This is considered an incomplete configuration, so condition-based collection is turned off and all the collected data is sent to archiver. ◦ < =: Setting condition as trigger tag value less than or equal to the compare value. ◦ > = Setting condition as trigger tag value greater than or equal to the compare value. ◦ <: Setting condition as trigger tag value less than the compare value. ◦ >: Setting condition as trigger tag value greater than the compare value. ◦ =: Setting condition as trigger tag value equals compare value. ◦ ! =: Setting condition as trigger tag value not the same as compare value.
Compare Value	A target value that you want to compare with the value of the trigger tag. If using = and != comparison parameters, ensure that the format of the compared value and triggered tag are the same. For example, for a float type trigger tag, the compare value must be a float value; otherwise, the condition result is an invalid configuration. When the config-

Field	Description
	uration is invalid, condition-based collection is disabled and all data is sent to archiver.
End of Collection Markers	Indicates whether end-of-collection markers are enabled. This will mark all the tag's values as bad, and sub-quality as ConditionCollectionHalted when the condition becomes false. Trending and reporting applications can use this information to indicate that the real-world value was unknown after this time until the condition becomes true and a new sample is collected. If disabled, a bad data marker is not inserted when the condition becomes false.

Table 37. The Collection Options Section

Field	Description
Data Collection	Indicates whether data collection is enabled or disabled for the tag. If you disable collection for the tag, Historian stops collecting data for the tag, but does not delete the tag or its data.
Collection Type	<p>The type of data collection used for this tag:</p> <ul style="list-style-type: none"> ◦ Polled: The data collector requests data from the data source at the collection interval specified in the polling schedule. ◦ Unsolicited: The data source sends data to the collector whenever necessary (independent of the data collector polling schedule).
Collection Interval	The time interval between readings of data from this tag. For unsolicited collection type, this field defines the minimum interval at which unsolicited data should be sent by the data source.
Collection Offset Value and Collection Offset	<p>Used with the collection interval to schedule collection of data from a tag. For example, to collect a value for a tag every hour at thirty minutes past the hour (12:30, 1:30, 2:30, and so on), enter a collection interval of 1 hour and an offset of 30 minutes. Similarly, to collect a value each day at 8am, enter a collection interval of 1 day and an offset of 8 hours.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: If you enter a value in milliseconds, the value must be in intervals of 1000 ms. For example, 1000, 2000, and 3000 ms are </div>

Field	Description
	 valid values, but 500 and 1500 ms are invalid. The minimum value is 1000 ms.
Time Resolution	The precision for timestamps, which can be either seconds, milliseconds or microseconds.
Condition based collection	Indicates whether condition-based data collection (on page 666) is enabled.
Trigger Tag	The name of the trigger tag used in the condition.
Comparison	<p>The comparison operator that you want to use in the condition. This field is enabled only if you have enabled condition-based collection. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Undefined: Collection will resume only when the value of the triggered tag changes. This is considered an incomplete configuration, so condition-based collection is turned off and all the collected data is sent to archiver. ◦ < =: Setting condition as trigger tag value less than or equal to the compare value. ◦ > = Setting condition as trigger tag value greater than or equal to the compare value. ◦ <: Setting condition as trigger tag value less than the compare value. ◦ >: Setting condition as trigger tag value greater than the compare value. ◦ =: Setting condition as trigger tag value equals compare value. ◦ !=: Setting condition as trigger tag value not the same as compare value.
Compare Value	A target value that you want to compare with the value of the trigger tag. If using = and != comparison parameters, ensure that the format of the compared value and triggered tag are the same. For example, for a float type trigger tag, the compare value must be a float value; otherwise, the condition result is an invalid configuration. When the configuration is invalid, condition-based collection is disabled and all data is sent to archiver.

Field	Description
End of Collection Markers	Indicates whether end-of-collection markers are enabled. This will mark all the tag's values as bad, and sub-quality as ConditionCollectionHalted when the condition becomes false. Trending and reporting applications can use this information to indicate that the real-world value was unknown after this time until the condition becomes true and a new sample is collected. If disabled, a bad data marker is not inserted when the condition becomes false.

Table 38. The Scaling Section

Field	Description
EGU Description	<p>The Engineering Units (EGU) provide context to a tag's value by providing an accurate representation of the tag values through their corresponding units. This will help you to know the units of data that you pull.</p> <p>For example, you can enter "Temperature" or "degree Celsius" in EGU Description for a single tag or multiple tags associated with temperature values.</p> <p>When you view the last 10 values of the tag (on page 690), or when you generate a query (on page 734)/write (on page 738) report in the Data page, EGU you enter will be displayed under the Engineering Units column in the table view and as a tool tip in the trend view.</p>
Hi Engineering Units	<p>The current value of the upper range limit of the span for this tag.</p> <p>Engineering Hi and Lo are retrieved automatically for F_CV fields for iFIX tags; all others are left at default settings. When adding tags from the server using an OPC Collector, the OPC Collector queries the server for the EGU units and EGU Hi/Lo limits. However, not all OPC Servers make this information available. Therefore, if the server does not provide the limits when requested to do so, the collector automatically assigns an EGU range of 0 to 10,000.</p>

Field	Description
Lo Engineering Units	The current value of the lower range limit of the span for this tag.
Input Scaling	<p>Indicates whether input scaling is enabled, which converts an input data point to an engineering units value.</p> <p>For example, to rescale and save a 0 - 4096 input value to a scaled range of 0 - 100, enter 0 and 4096 as the low and high input scale values and 0 and 100 as the low and high engineering units values, respectively.</p> <p>If a data point exceeds the high or low end of the input scaling range, Historian logs a bad data quality point with a ScaledOut-OfRange subquality. In the previous example, if your input data is less than 0, or greater than 4096, Historian records a bad data quality for the data point.</p> <p>OPC Servers and TRUE Values: Some OPC servers return a TRUE value as -1. If your OPC server is returning TRUE values as -1, modify the following scaling settings:</p> <ul style="list-style-type: none"> ◦ Hi Engineering Units: Enter 0. ◦ Lo Engineering Units: Enter 1. ◦ Hi Scaling Value: Enter 0. ◦ Lo Scaling Value: Enter -1. ◦ Input Scaling: Enable this option.
Hi Scaling Value	The upper limit of the span of the input value.
Lo Scaling Value	The lower limit of the span of the input value.

Table 39. The Collector Compression Section

Field	Description
Collector Compression	Indicates whether collector compression (on page 660) is enabled.
Collector Deadband and Deadband value	The current value of the compression deadband. This value can be computed as a percent of the span, centered around the data value or given as an absolute range around the data value.

Field	Description
	<div data-bbox="574 268 1421 575" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: Some OPC servers add and subtract the whole deadband value from the last data value. This effectively doubles the magnitude of the deadband compared to other OPC servers. To determine how your specific server handles deadband, refer to the documentation of your OPC server. </div> <p data-bbox="570 611 678 638">Example:</p> <p data-bbox="570 680 1421 890">Suppose the engineering units are 0 to 200. Suppose the deadband value is 10%, which is 20 units. If the deadband value is 10% and the last reported value is 50, the value will be reported when the current value exceeds $50 + 10 = 60$ or is less than $50 - 10 = 40$. Note that the deadband (20 units) is split around the last data value (10 on either side.)</p> <p data-bbox="570 932 1421 1058">Alternatively, you could specify an absolute deadband of 5. In this case, if the last value was 50, a new data sample will be reported when the current value exceeds 55 or drops below 45.</p> <p data-bbox="570 1100 1421 1352">If compression is enabled and the deadband is set to zero, the collector ignores data values that do not change and records any that do change. If you set the deadband to a non-zero value, the collector records any value that lies outside the deadband. If the value changes drastically, a pre-spike point may be inserted. For information, refer to Enable Spike Logic (on page 970).</p>
Engineering Unit	<p data-bbox="570 1381 1421 1507">Converts the deadband percentage into engineering units and displays the result. This value establishes the deadband range that is centered around the new value.</p> <p data-bbox="570 1549 1421 1717">This field represents a calculated number created to give an idea of how large a deadband you are creating in engineering units. The deadband is entered in percentage and Historian converts the percentage in to engineering units.</p>
Compression Timeout and Compression Timeout Interval	<p data-bbox="570 1738 1421 1864">Indicates the maximum amount of time the collector will wait between sending samples for a tag to the archiver. This time is maintained per tag, as different tags report to the archiver at different times.</p>

Field	Description
	<p>For polled tags, this value should be in multiples of your collection interval. After the timeout value is exceeded, the tag stores a value at the next scheduled collection interval, and not when the timeout occurred. For example, if you have a 10-second collection interval, a 1-minute compression timeout, and a collection that started at 2:14:00, if the value has not changed, the value is logged at 2:15:10 and not at 2:15:00.</p> <p>For unsolicited tags, a value is guaranteed in, at most, twice the compression timeout interval.</p> <p>A non-changing value is logged on each compression timeout. For example, an unsolicited tag with a 1-second collection interval and a 30-second compression timeout is stored every 30 seconds.</p> <p>A changing value for the same tag may have up to 60 seconds between raw samples. In this case, if the value changes after 10 seconds, then that value is stored, but the value at 30 seconds (if unchanged) will not be stored. The value at 60 seconds will be stored. This leaves a gap of 50 seconds between raw samples which is less than 60 seconds.</p> <p>Compression timeout is supported in all collectors except the PI collector.</p>

Table 40. The Archive Compression Section

Field	Description
Archive Compression	Indicates whether archive compression (on page 660) is enabled. If enabled, Historian applies the archive deadband settings against all reported data from the collector.
Archive Deadband and Deadband value	The current value of the archive deadband, expressed as a percent of span or an absolute number.
Engineering Unit	Converts the deadband percentage into engineering units and displays the result. This value establishes the deadband range that is centered around the new value.

Field	Description
Compression Timeout and Compression Timeout Interval	<p>The maximum amount of time from the last stored point before another point is stored, if the value does not exceed the archive compression deadband.</p> <p>The data archiver treats the incoming sample after the timeout occurs as if it exceeded compression. It then stores the pending sample.</p>

Table 41. The Advanced Section

Field	Description
Time Assigned By	<p>The source of the timestamp for a data value is either the collector or the data source.</p> <p>All tags, by default, have their time assigned by the collector. When you configure a tag for a polled collection rate, the tag is updated based on the collection interval. For example, if you set the collection interval to 5 seconds with no compression, then the archive will be updated with a new data point and timestamp every 5 seconds, even if the value is not changing.</p> <p>However, if you set the Time Assigned By field to Source for the same tag, the archive only updates when the device timestamp changes. For example, if the poll time is still 5 seconds, but if the timestamp on the device does not change for 10 minutes, no new data will be added to the archive for 10 minutes.</p> <div data-bbox="570 1339 1419 1472" style="border: 1px solid #00a0c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note: This field is disabled for Calculation and Server-to-Server tags.</p> </div>
Time Zone Bias	<p>The number of minutes from GMT that should be used to translate timestamps when retrieving data from this tag. For example, the time zone bias for Eastern Standard time is -300 minutes (GMT-5).</p> <p>This field is not used during collection. Use this option if a particular tag requires a time zone adjustment during retrieval other than the client or server time zone. For example, you could retrieve data for two tags with different time zones by using the tag time zone selection in the iFIX chart.</p>

Field	Description
Time Adjustment	<p>If the Server-to-Server collector is not running on the source computer, select the Adjust for Source Time Difference option to compensate for the time difference between the source archiver computer and the collector computer.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: This field only applies to tags associated with the Server-to-Server collector that use a polled collection type. </div>

Table 42. The Security Section

Field	Description
Read Group	<p>The Windows security group that can retrieve the tag data and plot it in a trend chart.</p> <p>For example, if you select a group with power users, in addition to members of the iH Security Admins group, only a member of the power users group will be able to read data for that tag. Even a member of the iH Readers group will not be able to access data for that tag, unless they are also defined as a member of the power users group.</p>
Write Group	The Windows security group that can write tag data (for example, using the Excel Add-in for Historian).
Administer Group	The Windows security group that can create, modify, and delete the tag.

For more information, refer to [implementing tag-level security \(on page 291\)](#).

**Note:**

When it comes to the group security, the security settings applied at the tag level, if any, take the precedence over those at the data store level.

**Note:**

If you are using domain groups (instead of local groups), the **Read Group**, **Write Group**, and **Administer Group** fields contain only the groups whose names begin with iH<space> (case-sensitive). Therefore, ensure that the group that you want to use begins with iH<space>.

Table 43. The Delta Query Section

Field	Description
Delta Max Value	The maximum value that a tag can have. It also called the rollover point of the counter or totalizer. If the tag values exceed MaxValue, the counter is reset to the minimum value. If you do not provide MaxValue, the delta query cannot check for a positive counter wrap.
Delta Min Value	The minimum value that a tag can have. If the tag values are less than MinValue (and the counter is going in the negative direction), the tag values are reset to MaxValue. If you do not provide MinValue, 0 is considered.
Delta Max Positive RPH	The maximum rate per hour between two consecutive data points in the positive direction. If two consecutive data points exceed this value, they are not considered in a delta query.
Delta Max Negative RPH	<p>The maximum rate per hour between two consecutive data points in the negative direction. If two consecutive data points exceed this value, they are not considered in a delta query.</p> <p>The Delta Max Positive RPH and Delta Max Negative RPH values are used to determine if a counter wrap has occurred or if the counter has been manually reset. They help ignore data points whose values increase or decrease drastically.</p>

For information on how these values are calculated, refer to [Counter Delta Queries \(on page 1113\)](#).

The Spare Fields section

Spare configuration enables you to add additional configuration to the tag using the **Spare Field 1** to **Spare Field 5** fields in all the collectors except in a Server-to-Server collector, Server-to-Server distributor, and an OSI PI distributor.

- In case of an OSI PI distributor, data is read from the Historian tag displayed in the **Source Address** field and sent to the OSI PI tag name displayed in the **Spare Field 1** field. To control the source and destination tags, change the **Source Address** and **Spare Field 1** values. You can add or update values in the remaining spare fields.
- In case of Server-to-Server collector and Server-to-Server distributor, you can update the **Spare Field 1** to **Spare Field 4** values, but the **Spare Field 5** field is used only for internal purposes. Therefore, do not update the **Spare Field 5** field.

The TAG ALIAS Section

Contains a list of the old names of the tag that you have renamed using an alias. For more information, refer to [Rename a Tag \(on page 698\)](#).

Configure Multiple Tags

This topic describes how to select multiple tags and configure their properties. This allows you to select two or more tags and configure their relevant properties at once. By default, 100 tags are listed at once in the grid. If you need to configure more than 100 tags simultaneously, you can use the page numbers at the bottom-right corner of the grid to navigate to the next available tags and select them as needed. Depending on the data types of the tags you select, all the properties that are relevant to the selected tags will be available in the **DETAILS** section for configuration.

Before you begin the configuration of multiple tags, know the following:


- When you select multiple tags, only the common properties will be displayed in the **DETAILS** section.
- The configuration values displayed in the **DETAILS** section will be of the last tag that is selected. However, the properties you update will be applied to all the other selected tags.
- When you configure multiple tags, only the configured properties are updated, and all the other properties remain unchanged.
- When you select multiple tags, aliases are disabled.

The table below provides the properties that will be disabled based on the selection of different tag data types.


Tag Data Type/ Tag Type	Properties Disabled
Array, Blob, Multifield	Compression, Scaling, Calculation, and Delta mode.

Tag Data Type/ Tag Type	Properties Disabled
Fixed string, Variable string	Compression, Scaling, Calculation, and Delta mode.
Calculation	None.
Calculation combined with other tag data types	Condition based collection, Time assigned by, and other relevant properties. For example, if you select Calculation, Array, and Blob, Condition based collection, Time assigned by, Compression, Scaling, Calculation, and Delta mode are disabled.
Non-calculation, Array, Multifield	All the properties other than General, Collection, Scaling, Compression, Advanced, Security, Delta, and Spare.
Multifield	Array tag.
UDT, Enum tags	Enumerated set.
Array, Blob, Scaled, Fixed string, Variable string	Enumerated set.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.



3. To select multiple tags, select the check boxes corresponding to the tags as needed.
Alternatively, to select all the available tags, select the check box in the upper-left corner in the grid header.




4. In the **DETAILS** section, edit the available properties as needed.
5. After you edit, in the top-left corner of the main ribbon bar, select **Save**.

Access the Trend Chart of Tag Values

This topic describes how to access the values of a tag in a trend chart. The difference in the timestamp of consecutive values depends on the time resolution of the tag. For example, if the time resolution is seconds, the timestamp of consecutive values of the tag will be one second apart.

You can plot the trend chart for up to 10 tags at a time.


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears.
3. If you want to narrow down the search results, select **Search**.



Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*).

The list of tags are filtered based on the search criteria.

4. If you want to access the trend chart of a single tag, right-click the tag (or select **☰**), and then select **Trend**.



If you want to access the trend chart for multiple tags, select the check boxes corresponding to the tags, right-click (or select **☰**), and then select **Trend**. You can select up to 10 tags.

The tag values are plotted on a trend chart. You can switch between the trend view and the table view.



Tip:

You can also filter the chart by changing the duration, sampling type, time interval, and so on by selecting .

Access the Last 10 Values of a Tag

This topic describes how to access the last 10 values of a tag up to the current time. The difference in the timestamp of consecutive values depends on the time resolution of the tag. For example, if the time resolution is seconds, the timestamp of consecutive values of the tag will be one second apart.

**Note:**

If a tag name contains a comma or a semicolon, you cannot view the last 10 values of the tag.


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears.
3. If you want to narrow down the search results, select **Search**.

The screenshot shows the Configuration Hub interface for the 'TAGS' section. At the top, there is a 'SYSTEM' dropdown menu. Below it is a search bar with a 'Search' button highlighted in red. To the right of the search bar are filter buttons for 'MaxNumberOfTags: 1000', 'CollectorName: X', 'TagName: * X', and 'Description: * X', along with a 'Reset to Default' button. The main area displays a table of tags with columns for TAG NAME, DESCRIPTION, COLLECTOR NAME, and LAST 10 VALUES. The table is currently empty, showing only the column headers and filter icons. The refresh time is indicated as 'Refreshed on 2021-12-21 11:22:30'.

<input type="checkbox"/>	TAG NAME	<input type="checkbox"/> DESCRIPTION	<input type="checkbox"/> COLLECTOR NAME	<input type="checkbox"/> LAST 10 VALUES
<input type="checkbox"/>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	
<input type="checkbox"/>	<input type="checkbox"/> Pressure			
<input type="checkbox"/>	<input type="checkbox"/> .Simulation.Simulation00002		.Simulation	

Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*). The list of tags are filtered based on the search criteria.

4. If you want to access the last 10 values of a single tag, right-click the tag (or select **⋮**), and then select **View Last 10 Values**.



The last 10 values of the tag appear, along with the timestamp and quality of each value. You can switch between the trend view and the table view.

5. If you want to access the last 10 values of multiple tags, select the check boxes corresponding to the tags, right-click (or select **ooo**), and then select **Trend**. You can select up to 10 tags.

In table view you can view data attributes which are introduced to store the 128-bit subquality for every sample.



Note:

SCADA applications such as Habitat support data samples with several quality types. To support such SCADA applications, Historian is now enhanced to store up to 128-bit quality types, which are stored in the data attributes. These attributes are extended qualities that you can store more than the regular qualities and subqualities (such as good and bad). In addition to regular qualities, the HAB collector collects extends qualities such as replaced, suspect, garbage, old, and so on.

The Data Attributes are displayed in the table view along with Timestamp, Value, and Quality. Data Attributes are supported for Current Value, Raw by Number, Raw by Time, Lab, and Lab to Raw. In addition:

- For an array tag, all the values in the array appear for each timestamp.
- For a tag using an enumerated set, values of all the states appear for each timestamp.
- For a tag using a user-defined data type (UDT), values for all the fields appear for each timestamp.

6. For the selected tag, to view the results in a table, select **Table**.

Tags-Historian
Tag Data-Historian

Query Builder

TIME
START DATE
6/13/2023, 7:35:50 PM

MODE
SAMPLING
MODE
Raw By
Number

SAMPLE
DIRECTION
Backward

SAMPLES
10

Trend
Table
Last updated on 6/13/2023, 7:35:50 PM.


Time Stamp	Value	QUALITY	Data Attributes	Engineering Units(Descript...	Hi Engineering ...	Lo Engineering ...
<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>
TAG NAME: CALCULATE1						
TAG NAME: SIMULATION-08-06.SIMULATION00001 (CONTINUES ON THE NEXT PAGE)						
6/13/2023, 7:35:49	151897.0938	Good		Hertz	200000.0	1.5
6/13/2023, 7:35:48	175432.7812	Good		Hertz	200000.0	1.5
6/13/2023, 7:35:47	135246.3125	Good		Hertz	200000.0	1.5
6/13/2023, 7:35:46	119895.6172	Good		Hertz	200000.0	1.5
6/13/2023, 7:35:45	159313.0312	Good		Hertz	200000.0	1.5
6/13/2023, 7:35:44	134184.2812	Good		Hertz	200000.0	1.5
6/13/2023, 7:35:43	162261.0938	Good		Hertz	200000.0	1.5
6/13/2023, 7:35:42	9797.868164	Good		Hertz	200000.0	1.5

1 2

Tip: You can also filter the values by changing the duration, sampling type, time interval, engineering units, and so on by selecting

Time Stamp	Value	QUALITY	Data Attributes
12/6/2022, 12:40:07 PM	61122.47266	Good	22.21.20.19.14.13.12.11.6.5.4.3
12/6/2022, 12:40:09 PM	28003.78516	Good	22.21.20.19.14.13.12.11.6.5.4.3
12/6/2022, 12:40:11 PM	176995.1406	Good	22.21.20.19.14.13.12.11.6.5.4.3
12/6/2022, 12:40:13 PM	4205.450684	Good	22.21.20.19.14.13.12.11.6.5.4.3
12/6/2022, 12:40:14 PM	174858.8594	Good	22.21.20.19.14.13.12.11.6.5.4.3
12/6/2022, 12:40:16 PM	148283.3281	Good	22.21.20.19.14.13.12.11.6.5.4.3
12/6/2022, 12:40:18 PM	2050.84375	Good	22.21.20.19.14.13.12.11.6.5.4.3
12/6/2022, 12:40:20 PM	158946.5	Good	22.21.20.19.14.13.12.11.6.5.4.3
12/6/2022, 12:40:22 PM	194219.7969	Good	22.21.20.19.14.13.12.11.6.5.4.3
12/6/2022, 12:40:23 PM	96792.50781	Good	22.21.20.19.14.13.12.11.6.5.4.3

7. For the selected tag, to view the results in a trend chart, select **Trend**.



Access a Tag Alias


After you rename a tag, the old name is called the tag alias. You can retrieve tag data using the tag alias as well. When you copy a tag, the tag alias is also captured to aid in an audit trail.



Note:


If a tag name contains a comma or a semicolon, you cannot view the tag alias.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears.
3. If you want to narrow down the search results, select **Search**.



Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*). The list of tags are filtered based on the search criteria.

4. Right-click the tag whose alias you want to access (or select **...**), and then select **View Aliases**.



Alternatively, you can select  in the **TAG ALIAS** column. All the tag aliases of the selected tag appear.

Export Tags as a CSV File

This topic describes how to export tags as a CSV file. You can export tags from Configuration Hub as a CSV file and add/modify tags in bulk and then import them. You can also import the CSV file that was exported using Excel Add-in.



Note:

Similarly, you can also export enumerated sets, and user-defined types from the **Manage Enumerated Sets** and **Manage User-Defined Types** windows.


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**. A list of all the tags appears, displaying the corresponding details.
3. Select and then select any one of the following options:

Option	Description
Download CSV of this View	Select this option if you want to download the selected tags and their corresponding details as listed in the tags grid.
Download CSV with Tag Details	Select this option if you want to download the selected tags and all their details, including configurations, from the DETAILS section.



Note:

Irrespective of the number of tags you select, all the available tags will be exported.



4. Enter a name for the file and save it in a location as needed.

Import Tags from a CSV File

This topic describes how to import tags into Configuration Hub from a CSV file. You can either export tags and their details as a CSV file and edit them, and then import them back, or you can import tags and their details from another CSV file that you created externally, like Excel Add-in.




Note:

Similarly, you can also import enumerated sets, and user-defined types from the **Manage Enumerated Sets** and **Manage User-Defined Types** windows.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears, displaying the corresponding details.
3. In upper-right corner of the grid, select .

<input type="checkbox"/>	TAG NAME	DESCRIPTION	COLLECTOR NAME	LAST 10 VALUES	D.	TAG ALL...	IS STALE
<input type="checkbox"/>	Attribute_test		.Simulation_1		● On		False
<input type="checkbox"/>	Simulation_1.Constant	.Simulation_1...	.Simulation_1		● On		False
<input type="checkbox"/>	Simulation_1.Constant_1%Noise	.Simulation_1...	.Simulation_1		● On		False
<input type="checkbox"/>	Simulation_1.Constant_20%Noise	.Simulation_1...	.Simulation_1		● On		False
<input type="checkbox"/>	Simulation_1.Constant_5%Noise	.Simulation_1...	.Simulation_1		● On		False
<input type="checkbox"/>	Simulation_1.Ramp	.Simulation_1...	.Simulation_1		● On		False
<input type="checkbox"/>	Simulation_1.Ramp_1%Noise	.Simulation_1...	.Simulation_1		● On		False
<input type="checkbox"/>	Simulation_1.Ramp_20%Noise	.Simulation_1...	.Simulation_1		● On		False
<input type="checkbox"/>	Simulation_1.Ramp_5%Noise	.Simulation_1...	.Simulation_1		● On		False
<input type="checkbox"/>	Simulation_1.RampDownOnly	.Simulation_1...	.Simulation_1		● On		False

The **Import Tags** page appears.



4. Select **Choose File**, and then select the CSV file as needed.



Note:

If you import any irrelevant CSV file, the import will fail and you will be notified.

5. Select **Import**.

The tags and their details are imported.

Rename a Tag

To rename a tag, you must be a member of the administrator's group with tag-level security.

When you rename a tag, you can choose between the following options:

- **Rename using an alias:** In this case, the old name is called the tag alias. You can retrieve tag data using the tag alias as well. When you copy a tag, the tag alias is captured as well to aid in an audit trail.




Note:

If a tag name contains a comma or a semicolon, you cannot view the tag alias.

- **Rename permanently:** In this case, the old name is no longer captured. Therefore, you can create another tag with this old name. You cannot store and forward data using the old name. This implies that data for the tag is collected separately for the new name.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears.


3. If you want to narrow down the search results, select **Search**.




Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*). The list of tags are filtered based on the search criteria.

4. Right-click the tag that you want to rename (or select **⋮**).

5. If you want to rename the tag using an alias, select **Rename**.



If you want to rename the tag permanently, select **Permanent Rename**.



The **Rename Tag: <tag name>** window or the **Permanent Rename Tag: <tag name>** window appears.

6. Enter the new name of the tag, and then select **Rename**. The tag name must be unique in the Historian server.

The tag is renamed. If you have renamed using an alias, the **TAG ALIAS** column displays , indicating that the tag now has an alias.

If you have renamed the tag permanently:


- If the tag is used as a trigger, reassign the trigger.
- [Restart the collector instance \(on page 639\)](#).

Copy a Tag

If you want to create a tag with the same properties as another one, you can copy it, and then modify the properties as needed. When you copy a tag, the tag alias is captured as well to aid in an audit trail.


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears.

3. If you want to narrow down the search results, select **Search**.



Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*). The list of tags are filtered based on the search criteria.

4. Right-click the tag that you want to copy (or select **⋮**), and then select **Copy**.



The **Copy Tag: <tag name>** window appears.

5. In the **NEW TAG NAME** field, provide a name for the tag. A value is required and must be unique for the Historian system.


6. Select **Copy**.

The tag is copied, inheriting the properties of the original tag. In addition, data collection begins for the tag.

Stop the Data Collection of a Tag


If you want to stop using a tag for a while, you can stop the data collection of the tag, which allows you to resume the data collection later. If, however, you no longer want to use the tag or its data, you can [remove it from the system \(on page 704\)](#) or [delete it \(on page 705\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears.
3. If you want to narrow down the search results, select **Search**.



Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*). The list of tags are filtered based on the search criteria.

4. Right-click the tag for which you want to stop data collection (or select **⋮**), and then select **Stop Data Collection**.




A message appears, asking you to confirm that you want to stop the data collection for the tag.

5. Select **Stop**.

Data collection is stopped for the tag.

Start the Data Collection of a Tag

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears.
3. If you want to narrow down the search results, select **Search**.



Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*). The list of tags are filtered based on the search criteria.

4. Right-click the tag for which you want to start data collection (or select **☰**), and then select **Start Data Collection**.

A message appears, asking you to confirm that you want to start the data collection for the tag.

5. Select **Start**.

Data collection is started for the tag.

Remove a Tag from a System


When you remove a tag from a system, the tag and its data will still be available. Therefore, you cannot create a tag with the same name. If, however, you no longer need the tag or its data, you can [delete it \(on page 705\)](#). Or, you can choose to [stop the data collection \(on page 702\)](#) for the tag, which allows you to [resume the data collection \(on page 703\)](#) later.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**. A list of all the tags appears.
3. If you want to narrow down the search results, select **Search**.

The screenshot shows the Configuration Hub interface for the 'Tags' section. At the top, there is a 'SYSTEM' dropdown menu. Below it is a search bar with a magnifying glass icon and the text 'Search', which is highlighted with a red box. To the right of the search bar are filter buttons: 'MaxNumberOfTags: 1000', 'CollectorName: X', 'TagName: * X', and 'Description: * X'. A 'Reset to Default' button is also present. Below the search bar, there is a refresh button and a timestamp 'Refreshed on 2021-12-21 11:22:30'. The main area contains a table with columns: 'TAG NAME', 'DESCRIPTION', 'COLLECTOR NAME', and 'LAST 10 VALUES'. Each column has a filter icon and the word 'Filter' below it. The table lists two tags: 'Pressure' and '_Simulation.Simulation00002'. Each tag has a checkbox and a pencil icon to its left.

Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*). The list of tags are filtered based on the search criteria.

4. Right-click the tag that you want to remove (or select **☰**), and then select **Remove Tag From System**.



A message appears, asking you to confirm that you want to remove the tag from the system.

5. Select **Remove**.


The tag is removed from the system.

Delete a Tag

If the tag that you want to delete is associated with a variable in a Historian model, remove the mapping between the variable and the tag.


When you delete a tag, it is deleted from Historian, and the tag data will no longer be available. If, however, you want the tag data to be available, instead of deleting the tag, [remove it from the system \(on page 704\)](#). Or, you can choose to [stop the data collection \(on page 702\)](#) for the tag, which allows you to [resume the data collection \(on page 703\)](#) later.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of all the tags appears.
3. If you want to narrow down the search results, select **Search**.



Enter the search criteria, and then select **Search**. You can add more attributes by selecting **Add Attribute**. You can enter a name or a value partially or use the wildcard character asterisk (*). The list of tags are filtered based on the search criteria.

4. Right-click the tag that you want to delete (or select **⋮**), and then select **Delete**.



A message appears, asking you to confirm that you want to delete the tag.

5. Select **Delete**.

The tag is deleted.

Managing Enumerated Sets

About Enumerated Sets

An enumerated data set provides an enhanced way of displaying data. It enables you to retrieve numeric data as string state values. You can use the string values in reports, charts, etc.

An enumerated set contains several states. A state is the number-string value pair in a set. It contains a set of numeric values and their corresponding string values. You can define an enumerated set for a single value or a range of values. These state values are defined for data states stored in Data Archiver. Data is retrieved using the value of the state. You have to define state values within a set to assign enumerated values.

Table 44. Example of a Single-Value Enumerated Set

State Name	State Value
Manual	0
Automatic	1

Table 45. Example of a Range-of-Values Enumerated Set:

State Name	State Value
ON	0 to 100
OFF	101 to 200

State names can be duplicated. If duplicated states exist, take precautions to avoid unpredictable results. For example, a tag is associated with an enumerated set defined as follows.

State Name	State Value
0	Open
1	Close
2	Close
2	Open

The server will return unpredictable results due to the State Name duplication for an input of 2.



Note:

You cannot assign an enumerated set to an array tag.

Create an Enumerated Set

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **☰**, and then select **Manage Enumerated Sets**.

The **Manage Enumerated Sets: <system name>** window appears.

The screenshot shows the 'Manage Enumerated Sets' interface. On the left sidebar, there is a '+ New Set' button highlighted with a red box. Below it, there is a 'Saved Sets (0)' section with a search bar and a 'No data to display.' message. The main area is currently empty.

4. Select **New Set**, and enter values as described in the following table.

The fields to create enumerated sets appear.

The screenshot shows the 'Manage Enumerated Sets' form with the following fields filled out:

- SET NAME***: Enumerated Set1
- DESCRIPTION**: Process Data
- DATA ATTRIBUTE ENUMERATED SET**: True False
- ENUMERATE BY**: Single Value Range
- STATES** table:

NAME*	VALUE*	DESCRIPTION
Automatic	1	Automatic Feed

 There is a '+ Add State' button below the states table and a 'Save Set' button in the bottom right corner.

Field	Description
SET NAME	Enter a name for the set.
DESCRIPTION	Enter a description for the set.
DATA ATTRIBUTE ENUMERATED SET	This is not applicable if you are creating an enumerated set. Set this to False .

Field	Description
ENUMERATE BY	Specify whether you want to define a single value or a range of values. A single value is best used with integer values because they match exactly. A range of values can be used with floating point values because they may not match exactly due to rounding.
NAME	Enter a name for the state.
VALUE	Enter a numeric value for the state; string values such as on/off are not supported. This field appears only if you select Single Value in the ENUMERATE BY field.
START RANGE and END RANGE	Enter the start and end values of the range. Enter only numeric values; string values are not supported. These fields appear only if you select Range in the ENUMERATE BY field. If you want to assign ON for values 0-100, enter ON in the NAME field, and enter 0 and 100 in the START RANGE and END RANGE fields.
DESCRIPTION (under STATES)	Enter a description for the state.

- For each state that you want to create, select **Add State**, and repeat the previous steps.
- Select **Save Set**.
- If needed, add more sets, and then select **Done**.

The enumerated set is created.

Manage Enumerated Sets : XXXXXXXXXX

[+ New Set](#)

Saved Sets (1)

Enumerated Set1

SET NAME *
Enumerated Set1 🗑️

DESCRIPTION
Process Data

DATA ATTRIBUTE ENUMERATED SET
 True False

ENUMERATE BY
 Single Value Range

STATES

NAME *	VALUE *	DESCRIPTION
Automatic	1	Automatic Feed

[+ Add State](#)

[Save Set](#)

Assign the enumerated set to a tag (on page 710).

Assign an Enumerated Set to a Tag

- [Create the tag \(on page 357\)](#) for which you want to use an enumerated set.
- [Create the enumerated set \(on page 708\)](#) that you want to assign to a tag.

If you assign an enumerated set to a tag, when you retrieve the tag data, instead of the actual values, the corresponding state names appear.


Example of an Enumerated Set

Suppose you have created the following states in an enumerated set:

State Name	State Range
ON	0 to 100
OFF	101 to 200

Suppose you assign the enumerated set to a tag. If the tag values are, say, 50, 100, 75, and 104, when you retrieve the tag values, ON, ON, ON, and OFF, respectively, are retrieved instead of the actual tag values.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select the tag to which you want to assign an enumerated set.
The details of the tag appear in the **DETAILS** section.
4. Under **Collection**, select **Enumerated Set**.



5. In the upper-left corner of the page, select **Save**.
The selected enumerated set is assigned to the tag.

Export an Enumerated Set

This topic describes how to export enumerated sets as a CSV file. You can export enumerated sets from Configuration Hub as a CSV file, add/modify sets in bulk, and then import them. You can also import the CSV file that was exported using Excel Add-in.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **...**, and then select **Manage Enumerated Sets**.

The **Manage Enumerated Sets: <system name>** window appears.

4. In **Saved Sets**, select .
5. Enter a name for the file and save it in a location as needed.

Import an Enumerated Set

This topic describes how to import enumerated sets into Configuration Hub from a CSV file. You can either export enumerated sets and their details as a CSV file and edit them, and then import them back, or you can import enumerated sets and their details from another CSV file that you created externally, like Excel Add-in.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **...**, and then select **Manage Enumerated Sets**.

The **Manage Enumerated Sets: <system name>** window appears.

4. In **Saved Sets**, select .
- The **Import Saved Sets** page appears.
5. Select **Choose File**, and then select the CSV file as needed.



Note:

If you import any irrelevant CSV file, the import will fail and you will be notified.

6. Select **Import**.
The enumerated sets and their details are imported.
7. In the **Manage Enumerated Sets: <system name>**, select **Done**.

Rename Enumerated Set

You can rename an enumerated set if needed.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **☰**, and then select **Manage Enumerated Sets**.
The **Manage Enumerated Sets: <system name>** window appears.
4. Select the enumerated set that you want to rename.
Details corresponding to the selected data set are displayed.
5. In **SET NAME**, rename the name of the set.
6. Select **Save Set**.
The set name is renamed.
7. Click **Done**.
The changes are saved.

Delete an Enumerated Set

This topic describes how to delete an enumerated set.



Note:

You cannot delete an enumerated set if it is assigned to a tag.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **☰**, and then select **Manage Enumerated Sets**.
The **Manage Enumerated Sets: <system name>** window appears.
4. Select the enumerated set that you want to delete, or select **☰**, and then select **Delete Set**. Or,
select  next to the Set name.
A message appears, asking you to confirm that you want to delete the set.
5. Select **Delete**.
The enumerated set is deleted.

Managing Data Attribute Enumerated Set

About Data Attribute Enumerated Set

A data attribute enumerated set enables you to specify whether you want to define a custom text for the sub-quality status and view it in the **Attributes** column instead of the value when you retrieve the tag data. For example, if your tag is receiving bit positions indicating the sub-quality status (that are, 1 for Old data, 2 for Bad data, and 30 for Good data), you can map the bit position to a custom text and assign it to a

set. So, when you view the actual values of the tag, the **Attributes** column will display the mapped custom text instead of the integer (the bit positions). For example, if you mapped a custom text name "good-16" to a value of 16, and the bit position of an incoming value is 16, it will display "good-16" in the **Attributes** column instead of 16.


Table 46. Example of an Attribute Enumerated Set

State Name	State Value
Uninitiated	0
Old	1
Bad	2
Not in Service	10
Good	30

Create a Data Attribute Enumerated Set

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **☰**, and then select **Manage Enumerated Sets**.

The **Manage Enumerated Sets: <system name>** window appears.



4. Select **New Set**, and enter values as described in the following table.
The fields to create enumerated sets appear.

Manage Enumerated Sets [User]

+ New Set

Saved Sets (0) [Download] [Refresh]

No data to display.

SET NAME *
Attribute_Enumerated_Set1

DESCRIPTION
Sub_Quality_Attribute

DATA ATTRIBUTE ENUMERATED SET True False



ENUMERATE BY Single Value Range

NAME *	VALUE *	DESCRIPTION
Attribute_Enum_Sub_Quality	16	16-Good

[+ Add State](#)

Save Set


Field	Description
SET NAME	Enter a name for the set.
DESCRIPTION	Enter a description for the set.
DATA ATTRIBUTE ENUMERATED SET	<p>Specify whether you want to define a custom text for the sub-quality status and view it in the Attributes column instead of the value when you retrieve the tag data. For example, if your tag is receiving bit positions indicating the sub-quality status (that are, 1 for Old data, 2 for Bad data, and 30 for Good data), you can map the bit position to a custom text and assign it to a set. So, when you view the actual values of the tag, the Attributes column will display the mapped custom text instead of the integer (the bit positions). For example, if you mapped a custom text name "good-16" to a value of 16, and the bit position of an incoming value is 16, it will display "good-16" in the Attributes column instead of 16.</p> <p>To create an attribute enumerated set, you must set DATA ATTRIBUTE ENUMERATED SET to True. If you choose this option, the ENUMERATED BY field is set to Single Value and becomes read-only.</p> <div style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: It is not recommended to modify the created Data Attribute Enumerated set in Historian Administrator. If you modify it using Historian Administrator, the DATA ATTRIBUTE ENUMERATED SET field will be changed to False in Configuration Hub.</p> </div>

Field	Description
	<p>Example- Before applying the Data Attribute Enumerated Set</p>  <p>Example- After applying the Data Attribute Enumerated Set</p> 
ENUMERATE BY	<p>Specify whether you want to define a single value or a range of values.</p> <p>For data attribute enumerated set, single value is selected by default and disabled.</p>
NAME	<p>Enter a name for the state.</p>
VALUE	<p>Enter a numeric value for the state; string values such as on/off are not supported. This field appears only if you select Single Value in the ENUMERATE BY field.</p>
DESCRIPTION (under STATES)	<p>Enter a description for the state.</p>

5. For each state that you want to create, select **Add State**, and repeat the previous steps.

6. Select **Save Set**.
7. If needed, add more sets, and then select **Done**.

The data attribute enumerated set is created.



Assign a Data Attribute Enumerated Set to a Tag

- [Create the tag \(on page 357\)](#) for which you want to use an enumerated set.
- Create a data attribute enumerated set that you want to assign to a tag.

If you assign a data attribute enumerated set to a tag, when you retrieve the tag data, the corresponding custom text that was mapped appears.


Example of a Data Attribute Enumerated Set

Suppose you have created the following states in a data attribute enumerated set:

State Name	State Value
Old	1
Bad	2
Good	30

Suppose you assign the data attribute enumerated set to a tag. If the tag's quality status are, say, 30, 30, 1, and 2, when you retrieve the tag values, Good, Good, Old, and Bad, respectively, are retrieved instead of the actual quality status values in the **Attributes** column.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select the tag to which you want to assign an enumerated set.
The details of the tag appear in the **DETAILS** section.
4. Under **Collection**, select **Data Attribute Enumerated Set**.



5. In the upper-left corner of the page, select **Save**.

The selected data attribute enumerated set is assigned to the tag.

Export Data Attribute Enumerated Sets

This topic describes how to export data attribute enumerated sets as a CSV file. You can export data attribute enumerated sets from Configuration Hub as a CSV file add/modify sets in bulk and then import them. You can also import the CSV file that was exported using Excel Add-in.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **☰**, and then select **Manage Enumerated Sets**.

The **Manage Enumerated Sets: <system name>** window appears.

4. In **Saved Sets**, select **↑**.

5. Enter a name for the file and save it in a location as needed.

Import Data Attribute Enumerated Sets

This topic describes how to import data attribute enumerated sets into Configuration Hub from a CSV file. You can either export data attribute enumerated sets and their details as a CSV file and edit them, and then import them back, or you can import data attribute enumerated sets and their details from another CSV file that you created externally, like Excel Add-in.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **☰**, and then select **Manage Enumerated Sets**.

The **Manage Enumerated Sets: <system name>** window appears.

4. In **Saved Sets**, select .
- The **Import Saved Sets** page appears.
5. Select **Choose File**, and then select the CSV file as need.



Note:

If you import any irrelevant CSV file, the import will fail and you will be notified.

6. Select **Import**.
The data attribute enumerated sets and their details are imported.
7. In the **Manage Enumerated Sets: <system name>**, select **Done**.

Rename a Data Attribute Enumerated Set

You can rename a data attribute enumerated set if needed.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select , and then select **Manage Enumerated Sets**.
The **Manage Enumerated Sets: <system name>** window appears.
4. Select the data attribute enumerated set that you need to rename.
Details corresponding to the selected data set are displayed.
5. In **SET NAME**, rename the name of the set.
6. Select **Save Set**.
The set name is updated.
7. Click **Done**.
The changes are saved.

Delete a Data Attribute Enumerated Set

This topic describes how to delete a data attribute enumerated set.



Note:

You cannot delete a data attribute enumerated set if it is assigned to a tag.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select , and then select **Manage Enumerated Sets**.
The **Manage Enumerated Sets: <system name>** window appears.

4. Select the data attribute enumerated set that you want to delete, or select , and then select

Delete Set. Or, select  next to the Set name.

A message appears, asking you to confirm that you want to delete the set.

5. Select **Delete**.

The data attribute enumerated set is deleted.

Managing User-Defined Data Types

About User-Defined Data Types

Sometimes, a single tag cannot store all the required details of a parameter. For example, if you want to store the name, address, and phone number of the manufacturer of a machine, it may not be feasible to store all these details in a single tag, which uses a single data type. In such cases, you can create a user-defined data type (UDT), which includes one or more fields, and then apply that type to Historian tags. Each of these fields in a UDT can contain a different data type based on your requirement.

The following conditions apply when working with a UDT:

- You must have appropriate security permissions to create, modify, and delete a UDT. The type can have its own Administrator security group.
- You cannot create an array tag that uses a UDT.
- UDTs cannot have fields of Scaled or FixedString data types.
- Scaling, collector compression, and archive compression do not apply to UDT tags.
- You cannot associate an enumerated set with a UDT tag.
- A UDT supports maximum 100 fields.

Create User-Defined Data Types

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select , and then select **Manage User-Defined Types**.
The **Manage User-Defined Types: <system name>** window appears.
4. Select **New Type**, and enter values as described in the following table.

Field	Description
TYPE NAME	Enter a name for the user-defined data type (UDT).
DESCRIPTION	Enter a description for the UDT.

Field	Description
ADMINISTER GROUP	Specify the Windows Security Group that you want to assign to the UDT.
DATA QUALITY	Select one of the following options: <ul style="list-style-type: none"> ◦ Store Individual Quality: Select this option to store field-level quality. Storing individual qualities consumes more disk space. ◦ Store Master Field Quality: Select this option if you want to assign the same quality as the master field to all the other fields in the UDT. If you select this option, the data sample will have a single quality similar to how an array tag works.
MASTER	Select the radio button corresponding to the field that you want to set as master. When you do so, the data type of this field is used for all the remaining fields in the UDT as well. Only one field can be the master in a UDT. The MASTER column appears only if you select Store Master Field Quality under DATA QUALITY .
NAME	Enter a name for the field.
DESCRIPTION (under FIELD)	Enter a description for the field.
DATA TYPE	Select the data type for the field. If you select Store Master Field under DATA QUALITY , and if you set this field as master, the data type of this field will be applied to the remaining fields in the UDT as well.

- For each field that you want to create, select **Add Field**, and provide the required details.
- Select **Save Type**.
- If needed, add more UDTs, and then select **Done**.
The UDT is created.


[Assign the UDT to a tag \(on page 720\)](#).

Assign a User-Defined Data Type to a Tag

- [Create the tag \(on page 357\)](#) for which you want to assign a user-defined data type (UDT).
- [Create the UDT \(on page 719\)](#) that you want to assign to the tag.

When you assign a UDT to a tag, the tag can collect data of various data types.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select the tag for which you want to assign a UDT.
The details of the tag appear in the **DETAILS** section.
4. Under **Collection**, in the **User Defined Type Name** field, select the UDT that you want to assign.
5. In the upper-left corner of the page, select **Save**.



The UDT is assigned to the tag.

Export User-defined Types

This topic describes how to export user-defined types as a CSV file. You can add/modify them in bulk, and then import them. You can also import the CSV file that was exported using Excel Add-in.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **☰**, and then select **Manage User-Defined Types**.

The **Manage User-Defined Types: <system name>** window appears.

4. In **Saved Types**, select .
5. Enter a name for the file and save it in a location as needed.

Import User-defined Types

This topic describes how to import user-defined types into Configuration Hub from a CSV file. You can either export user-defined types and their details as a CSV file and edit them, and then import them back, or you can import user-defined types and their details from another CSV file that you created externally, like excel add-in.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.

3. Select , and then select **Manage User-Defined Types**.

The **Manage User-Defined Types: <system name>** window appears.

4. In **Saved Types**, select .

The **Import Saved Types** window appears.

5. Select **Choose File**, and then select the CSV file as need.



Note:

If you import any irrelevant CSV file, the import will fail and you will be notified.

6. Select **Import**.

The user-defined types and their details are imported.

7. In the **Manage User-Defined Types: <system name>**, select **Done**.

Rename User-defined Types

You can rename a user-defined type as needed.

1. [Access Configuration Hub \(on page 336\)](#).

2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.

3. Select , and then select **Manage User-Defined Types**.

The **Manage User-Defined Types: <system name>** window appears.

4. In **Saved Types**, select the saved type as needed.

Details corresponding to the selected user-defined type are displayed.

5. Change the user-defined type name as needed.

6. Select **Save Type**.

The user-defined type name is renamed.

7. Click **Done**.

The changes are saved.

Delete a User-Defined Data Type

You cannot delete a user-defined data type (UDT) if it is assigned to a tag.

1. [Access Configuration Hub \(on page 336\)](#).

2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.

3. Select , and then select **Manage User-Defined Types**.

The **Manage User-Defined Types: <system name>** window appears.

4. Select the UDT that you want to delete, select , and then select **Delete**. Or, select  next to the UDT name.

A message appears, asking you to confirm that you want to delete the UDT.

5. Select **Delete**.

The UDT is deleted.

Managing Archives

About Archives

Historian archives are data files, each of which contains data gathered from all data sources during a specific period of time.

Types of Archive Files:

- **machine name_Config.ihc**: Contains information about the archiver, tag configuration, and collector configuration.
- **machine name_ArchiveXXX.iha**: Contains tag data, where x is a number indicating the place of the file in a time-based sequence.

Creation of Archive Files Automatically

Archive files grow to a user-configured maximum size as data is recorded by the server. When data starts loading into an archive file, Historian will automatically create a new blank archive file. When the current archive file becomes full, Historian will immediately serve data to the newly created archive file. This significantly reduces archive creation and transition time.

If, however, the option to automatically create archive files is not enabled, you must [create an archive file manually \(on page 868\)](#).



Note:

If the option to automatically create an archive is not enabled and you do not create a new archive manually, or if the available disk space is less than the required amount of free disk space, a new archive file will not be created.

Overriding Old Archive Files

If you enable the **Overwrite Old Archives** option, the system replaces the oldest archived data with new data when the latest archive default size has been reached. Since this action deletes historical data,

exercise caution in using this feature. Be sure that you have a backup of the archive so that you can restore it later. Best practice is to create an additional archive to prevent premature loss of data due to overwriting. For example, if you want to save 12 months of data into 12 archives, create 13 archives.

During archiver startup and every 60 seconds while the server is running, Historian verifies that you have configured enough free disk space to save the archives, buffer files, and log files. If there is insufficient disk space, the Data Archiver shuts down and a message is logged into the log file. By default, you can view the Historian archiver log file in `C:\Historian Data\LogFiles`.

```
[03/03/10 15:28:41.398] Insufficient space available in [d:\Historian\Archives\]
    [03/03/10 15:28:41.399] The server requires a minimum of [5000 MB] to continue
    [03/03/10 15:28:41.679] USER: DataArchiver TOPIC: ServiceControl MSG: DataArchiver(DataArchiver)
    Archiver shutdown at 03/03/10 15:28:41.653
    [03/03/10 15:28:41.807] DataArchiver Service Stopped.
    [03/03/10 15:28:41.809] [d:\Historian\LogFiles\DataArchiver-34.log] Closed.
```

Guidelines for Setting Archive Size

Since archived data files can become quite large, you must adjust system parameters carefully to limit data collection to meaningful data only and thus minimize the required size of system storage. You can allocate up to 256 GB per archive.

For each archive, you need approximately 1MB of archive space for every 1000 tags to store tag information. Archive size is a function of the rate at which you archive data and the time period you want the archive to cover. A typical user wants the archive to cover a time period of, say, 30 days.

The following factors affect the rate at which you archive data:

- Number of tags
- Polling frequency of each tag
- Compression settings
- Data types

Based on these parameters, the archive size is calculated as follows:

$$\#Tags \times \frac{Values}{Tag} \times \frac{Tags}{Second} \times \%PassComp \times \frac{Bytes}{Value} \times \frac{Seconds}{Hour} \times \frac{Hours}{Day} \times \frac{MB}{Bytes} = \frac{MB}{Day}$$

Calculating Archive Size

Suppose you want to store data, and you have the following parameters:

- Number of tags: 5000
- Polling rate: 1 value/5 seconds
- Pass compression: 5%.

Pass compression is the number of data values archived relative to the number of values read.

- Bytes/value: 4
- Duration: 30 days

Based on the preceding formula, for the given parameters, the archive size is calculated as follows:

$$5000 \times \frac{1}{1} \times \frac{1}{5} \times \frac{5}{100} \times \frac{4}{1} \times \frac{3600}{1} \times \frac{24}{1} \times \frac{1}{1024 \times 1024} \times 30 = 494 \frac{MB}{Month}$$

The calculation shows that a file size of 500 MB is adequate for archiving one month of data for this application.

Therefore, we recommend that you set the default archive size to 500 MB for systems with 1000 tags or more. If you believe the computed size is too large for your application, you can modify parameters as follows:

- Decrease the polling frequency.
- Increase compression deadband, reducing the pass percentage.
- Reduce the number of tags.
- Add more disk capacity to your computer.

Archive Size Calculator

An archive size calculator tool is available to estimate archive size and collector compression based on a tag that has already been configured or based on your inputs. Log on to <http://digitalsupport.ge.com> to download this tool and other GE Intelligent Platforms freeware product solutions.

Access an Archive

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Archives**. The **Archives** section appears. By default, only the archives of the default data store appear. If you want to access archives from another data store, select it in the **DATA STORE** field.


3. Select the archive whose details you want to access.

The **DETAILS** section displays the following information of the archive.

Field	Description
Status	Identifies the status of the archive. Contains one of the following values: <ul style="list-style-type: none"> ◦ Current: The archive is actively accepting data. ◦ Active: The archive contains data but is not currently accepting data. ◦ Empty: The archive was created but has never accepted data.
Start Time	The time at which writing data to the archive has begun.
End Time	The time at which writing data to the archive has ended.
Last Backup	The time at which the archive has been backed up last.
Backup User	The user who created the last backup of the archive.
File Name	The name and folder path of the archive file.
File Size (MB)	The size of the archive file.
File Attribute	Indicates whether the archive file is read-only or read/write.

4. If needed, change the values in the **Filename** and **File Attribute** fields. You cannot, however, change the file attribute for the current archive.

5. In the upper-left corner of the page, select **Save**.



The archive is modified.

Create Archives Automatically

Historian can automatically create archives for you if the current archive reaches a specific size or after a specific duration. This topic describes how to set these options. You can, however, choose to [create archives manually \(on page 728\)](#).


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Archives**. The **Data Stores** section appears.
3. Select the data store in which you want to create archives automatically. The **DETAILS** section displays the details of the data store.
4. Under **Archive Creation**, enter values as described in the following table.

Field	Description
Automatically Create Archives	Switch the toggle on to indicate that you want Historian to create archive files automatically when the current one is full.
Create Archive By	<p>Select whether you want to create a new archive automatically after the current one reaches a specific <i>size</i> or after a specific <i>duration</i>. This field is enabled only if you switch the Automatically Create Archives toggle on.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Size: Select this option if you want to create a new archive when the current one reaches a specific size. Specify the size in the Default Size (MB) field (which appears only if you select Size). ◦ Days or Hours: Select one of these options if you want to create a new archive after a specific duration. Specify the duration in the Archive Duration field (which appears only if you select Days or Hours).
Default Size (MB)	The default size of an archive after which a new one will be automatically created. This field

Field	Description
	appears only if you select Size in the Create Archive By field.
Archive Duration	The duration after which a new archive will be automatically created. This field appears only if you select Days or Hours in the Create Archive By field.

If needed, you can switch the **Overwrite Old Archives** toggle on. If you enable this option, the oldest archived data is replaced with the latest one when the latest archive default size is reached. Since this action deletes historical data, exercise caution in using this feature. Be sure that you have a backup of the archive so that you can restore it later. Best practice is to create an additional archive to prevent premature loss of data due to overwriting. For example, if you want to save 12 months of data into 12 archives, create 13 archives.

- In the upper-left corner of the page, select **Save**.



Archives will now be created automatically based on the criteria you specified.

Create Archives Manually

This topic describes how to create an archive file manually. You can create multiple archives at the same time. You can, however, choose to [create archives automatically \(on page 727\)](#).

- [Access Configuration Hub \(on page 336\)](#).
- In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Archives**.
The **Archives** section appears.
- In the upper-right corner of the section, select **+**.
The **Add Archives** window appears.
- Enter values as described in the following table.

Field	Description
ARCHIVE NAME	Identifies the name of the archive. A value is required. By default, it is in the following format: <code><data store name>_<system name>_Archive<number></code> . The number is used to name the archives sequentially. You can only add a suffix to the archive name.
DATA STORE	Select the data store in which you want to create the archives. A value is required.
FILE LOCATION	Enter the folder path in which you want to store the archives. A value is required. By default, it is <code>C:\Proficy Historian Data\Archives</code>
EACH ARCHIVE SIZE	Enter the size, in MB, that you want to allocate to each archive. A value is required. This field is populated with the value in the Default Size (MB) field in the data store (if applicable).
NUMBER OF ARCHIVES	Enter the number of archives that you want to create. A value is required. The default value is 1.
ALLOCATE SPACE	Specify the disk space that you want to allocate for archives. A value is required. <div data-bbox="862 1283 1419 1604" style="border: 1px solid #ffc107; border-radius: 10px; padding: 10px; background-color: #fff3cd;"> <p>! Important: If there is insufficient disk space, Data Archiver is shut down and a message is logged into the log file. By default, you can view the log file in <code>C:\Historian Data\LogFiles</code>.</p> </div>

5. Select **Add**.

The archives are created.

Back up an Archive

Ensure you have enough disk space.

You must back up archive files periodically to ensure that your data is protected. These backup files contain tag data as well as alarms and events data. You can send these files to a shared network location or to physical media.

Always back up archives before a planned Historian software product upgrade. Use Microsoft® Volume Shadow Copy Service when backing up archive files that are more than 2 GB in size or when backing up more than the last two archives. For more information, refer to [Back Up Archives with Volume Shadow Copy Service \(on page 731\)](#).

This topic describes how to back up an archive manually. You can also [back up an archive automatically \(on page 874\)](#).

Important points to remember:

- The .IHC file is automatically backed up when, and only when, you back up the current archive .IHA file. By default, the .IHC backup path is the same as the archives path.
- The .IHC backup file uses the following naming convention: `<system name>_Config-Backup.ihc`. If the default backup path is different from the archives counterpart, the .IHC file is copied to the backup folder with the standard .IHC naming convention: `ComputerName_Config.ihc`.
- In the mirroring system, Client Manager sends a backup message to Data Archiver located on the Client Manager node to which you are connected. The back up, then, happens in the specified location on that node. If that Data Archiver is not running, a NOT_CONNECTED error message appears, and the backup will not happen.
- If you back up an archive more than once, the backup tool will (by default) attempt to use the same name for the backup file and will detect that an archive with the same name already exists. Rename the backup archive file or move the original backup archive file to a different folder.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Archives**. The **Archives** section appears.
3. Right-click the archive that you want to back up (or select **☰**), and then select **Backup Archive**. The **Backup Archives** window appears. The **ARCHIVE NAME** field is disabled and populated. The **BACKUP FILE PATH** field is disabled and populated with the value in the **DEFAULT BACKUP PATH** field of the data store.

4. Select **OK**.

The archive file is backed up.

Back up Archives with Volume Shadow Copy Service

Use the Microsoft® Volume Shadow Copy Service to back up large archive files, or if you want to back up more than the last two archives, as it allows you to backup and restore archives reliably and in a short period of time without affecting the data collection.

The Volume Shadow Copy feature is provided by Windows Operating System, and the instructions to use backup and restore vary depending on the backup application that is used in the Windows operating system.

VSS provides fast volume capture of the state of a disk which is called a snapshot or shadow copy. When the snapshot is taken, disk writes are suspended for a brief period of time, typically on the order of milliseconds. After the snapshot, disk writes can resume, but the original state of the files are maintained by a difference file. The difference file allows the state of the original file at the time of the snapshot to be reconstructed. This behavior allows files to be backed up while new data is being written to files.

If you are using `ihArchiveBackup.exe` before the upgrade, your backup will continue to work in the same or similar manner as it did before the upgrade. There is no change in the backup procedure and the Auto Recovery Backup Files option remains unchanged.

**Note:**

Though you could use either `ihArchiveBackup.exe` or VSS for backup, VSS is a better choice for both larger archives or if you are backing up more than the last two archives to reduce the load on the Data Archiver service.

Microsoft uses a backup format called Virtual Hard Disk (VHD) to back up files.


When you create archives backup using Microsoft® Volume Shadow Copy Service, you must first restore the archives files (that is, `.bkf` or `.vhd` into `.iha`) using the Windows Restore wizard, and then restore the archives (`.iha`) into Historian. For more information on restoring an archive (`.iha`) into Historian, refer to the Restoring an Archive topic.

**Note:**

It is recommended that you:



- Use Microsoft® Volume Shadow Copy Service when you want to back up archive files that are more than 2 GB in size, or if you are backing up more than your last two archives.
- Ensure you have enough hard drive space on your default backup location before backing up your archives.



Important:

For optimum performance, it is recommended you to save paging file of the operating system, Historian archives, and scheduled backup directory on separate drives.

Restore an Archive

- Before restoring an archive from a removable disk, copy the archive file to the normal archive path and then restore the archive from that location. Leave the original backup file in the backup file folder.
- Ensure that the current archive is online.

Under certain circumstances, you may want to restore tag and alarms and events data to Historian. This may be after an unplanned shutdown, or you may need to retrieve data from an old, inactive archive.



Important:

Restoring an archive is a resource-intensive operation and should be scheduled for non-peak usage times.

Archives that have been previously removed from Historian can be found in the `\Archives\Offline` directory.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Archives**.
The **Archives** section appears.
3. In the upper-right corner of the section, select .
The **Restore Archives** window appears.
4. Enter values as described in the following table.

Field	Description
FILE LOCATION	This field is populated with the value in the DEFAULT BACKUP PATH field of the data store. Append the name of the .zip file of the archive that you want to restore. The ARCHIVE NAME field is populated with the .zip file name that you enter.
DATA STORE	Select the data store in which you want to restore the archive.

5. Select **Restore**.
The archive is restored; it is moved to the `Archive` folder and is made available for querying.

Close an Archive

By default, an archive is closed when it is full. However, you can manually close an archive before it is full.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Archives**.
The **Archives** section appears.
3. Right-click the archive that you want to back up (or select **☰**), and then select **Close Archive**.
A message appears, asking you to confirm that you want to close the archive.
4. Select **Yes**.
The archive file is closed, and another one is used for writing data.

Remove an Archive

When you remove an archive, it no longer appears in Configuration Hub. However, it exists in the Archives folder (by default, C:\Proficy Historian Data\Archives).

You cannot remove the current archive. If you want to remove it, you must first close it. When you do so, another archive is used for writing data.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Archives**.
The **Archives** section appears.
3. Right-click the archive that you want to remove (or select **☰**), and then select **Remove Archive**.
A message appears, asking you to confirm that you want to remove the archive.
4. Select **Yes**.
The archive file is removed.

Reading/Writing Data

Query Data

Using Configuration Hub, you can query the data of selected tags. This data is then plotted in a trend chart. You can also export this data into a PDF, SVG, PNG, or a JPEG file, or save it as favorites.

Querying data involves the following steps:

1. **Selecting the tags:** You can select tags from all the tags in the system. While selecting tags, you can view them in a hierarchical object model view or in a flat list.
2. **Applying conditions and filters:** You can select the sampling mode, size, query modifiers, and so on. You can also select the calculation modes for the calculated sampling mode.
3. **Generating the report:** You can plot the query results in a trend chart or view them in a table. You can also export the data.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data**. The **Data** section appears, displaying a list of object instances and the underlying variables and contained types hierarchically. If you want to view a flat list of all the tags, select .
3. Select the tags for which you want to query data, select Read data operation, and then select **Next**. You can select up to 10 tags.
4. Enter values as described in the following table.

Field	Description
START DATE/TIME	Enter the start date and time for the query.
END DATE/TIME	Enter the end date and time for the query.
SAMPLING MODES	Select the sampling mode for the query: <ul style="list-style-type: none"> ◦ Calculated (on page 1073): Returns the result of a calculation on tag values (for example, count, maximum, delta). ◦ Current Value (on page 1045): Returns a single sample containing the current value of the tag. Retrieves the timestamp, value, and quality. ◦ Interpolated (on page 1048): Returns the interpolated tag values. ◦ Interpolated to Raw ◦ Lab (on page 1047): Returns only collected values. Each collected value is repeated until the next collected value, resulting in a jagged step plot instead of a smooth curve. ◦ Lab to Raw ◦ Raw By Number (on page 1057): Returns the specified number of raw samples of all qualities beginning with the start time and moving in the specified direction.

Field	Description
	<ul style="list-style-type: none"> ◦ Raw By Time (on page 1057): Returns all raw samples of all qualities with a timestamp greater than the start time and less than or equal to the end time. It will not return a raw sample with same time stamp as the start time. ◦ Trend (on page 1065): Returns significant points, which are raw samples. These points are determined by finding the raw minimum and raw maximum values within each interval. ◦ Trend to Raw ◦ Trend to Raw2 ◦ Trend2 (on page 1069): Splits up a given time period into a number of intervals (using either a specified number of samples or specified interval length), and returns the minimum and maximum data values that occur within the range of each interval, together with the timestamps of the raw values. This sampling mode is suitable for analysis of minimum and maximum values and for plotting programs that can handle unevenly spaced data.
CALCULATION MODE	<p>Select the calculation mode that you want to use. This field appears only if you select Calculated in the SAMPLING MODES field. For information on calculation modes, refer to Calculation Modes (on page 1073).</p>
SAMPLING DIRECTION	<p>The direction in which you want to retrieve the query results:</p> <ul style="list-style-type: none"> ◦ Forward: Returns query results starting from the start data to the end date. ◦ Backward: Returns query results starting from the end date to the start data.
SAMPLE INCREMENT	<p>Identifies the amount of data samples in each sample:</p> <ul style="list-style-type: none"> ◦ By Size: Select this option if you want each sample to contain a specific number of data points, and then enter the number of data points. ◦ By Time: Select this option if you want each sample to contain data points collected for a specified duration, and then enter the duration.

Field	Description
QUERY MODIFIERS	Used for retrieving a specific set of data. For information, refer to Query Modifiers (on page 1159) .
Filters	<p>You can enter your filter conditions using the Filter tag, the Filter Condition, and the Filter Comparison Value.</p> <p>In the Filter Tag Name field, select the tag you want to enable filtering with.</p> <p>In the Condition field, select your comparison condition.</p> <p>In the Value field, enter your filter condition value.</p>

5. Select **Generate Report**.

The query results for the selected tags are plotted on a trend chart.




You can narrow down the start and end dates by dragging the timeline below the trend chart.

[Query_Results.mp4](#)

The Tags and query criteria appear in the **Summary** section; you can edit them if needed.

Select the Edit beside Tag Selection and Query Builder to modify tags and query criteria.



If you want to view the results in a table, select **Table**.



You can save the query if you may frequently use to read specific tags data with a specific query criteria. For more information, refer to [Save a query \(on page 741\)](#).

If you want to export the results into a .csv file, select . The results are exported.

If you want to print the trend, select , and then select **Print**.

To export into other formats (such as a .pdf, .svg, .png, or .jpeg), select , and then select the format.

Write Data

Using Configuration Hub, you can write data for selected tags. This helps you verify that data is being sent to Data Archiver.

Writing data involves the following steps:

1. **Selecting the tags:** You can select tags from all the tags in the system. While selecting tags, you can view them in a hierarchical object model view or in a flat list.
2. **Entering the data:** You can enter data for each selected tag, along with the data type and quality.
3. **Generating the report:** You can plot the query results in a trend chart or view them in a table. You can also export the data.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data**.
The **Data** section appears, displaying a list of object instances and the underlying variables and contained types hierarchically. If you want to view a flat list of all the tags, select .
3. Under **DATA OPERATION**, select **Write Data**.
4. Select the tags for which you want to write data, and then select **Next**.
5. For each tag that you have selected, enter values as described in the following table.

Column	Description
VALUE	Enter the value of the tag. A value is required.
DATA TYPE	If Hierarchical tags are selected, select the data type of the tag value. A value is required. If normal tags are selected, the data type will be automatically populated.
DATA QUALITY	Select the data quality of the tag value from Good or Bad from the list. A value is required.

6. Select **Write Data**, and then select **Next**.
7. Select **Generate Report**.
The query results for the selected tags are plotted on a trend chart.



You can narrow down the start and end dates by dragging the timeline below the trend chart.

[Query_Results.mp4](#)

The query criteria appear in the **Summary** section; you can edit them if needed.

The screenshot shows the 'Summary' section of the interface. It contains the same 'Tag Selection', 'Query Builder', 'QUERY MODIFIERS', and 'FILTER' sections as the previous image, providing a textual overview of the query configuration.

If you want to view the results in a table, select **Table**.



Timestamp	Value	Quality
> TAG NAME: MARUTHI>MILEAGE		
> TAG NAME: MARUTHI>SIDESTANDINDICATOR		
> TAG NAME: MARUTHI>SPEED		
> TAG NAME: SRINIVAS2020_SIMULATION.SIMULATION00002		

About Saved Query

About Saved Query

You can save queries that you use to read tags data. You can use this option to save queries that you may frequently use to read specific tags data with a specific query criteria. This will help you in the following:

- Quickly gather insights of specific tags.
- Create and save a predefined query only once and use it as needed.
- You can use the **Shared** option to make the query visible to the other users in the same network.



Note:

Once you share a query, all the other users will also be able to edit, and delete it. Be mindful about making a query as a shared query.

- Automate a monotonous query process through the saved queries.

What to do Next: You can [Save a query \(on page 741\)](#).


Save a Query

This topic describes how to save a Query to read tags data.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data**. The **Data** section appears, displaying a list of object instances and the underlying variables and contained types hierarchically. If you want to view a flat list of all the tags, select .

3. Select the tags for which you want to query data, select **Read Data** operation, and then select **Next**.
4. Enter the values as needed. For more information on the values, refer to [Query Data \(on page 738\)](#).
5. Select **Generate Report**.

The query results are plotted on a trend chart.



6. Select **Save Query**.

The **Save Query** window appears.

The 'Save Query' dialog box is shown. It has a title 'Save Query' and a 'NAME *' field containing 'My Interpolated Data'. Below this is a 'DESCRIPTION' field containing 'Interpolated data query.'. There is a checkbox labeled 'Shared' which is currently unchecked. At the bottom right, there are 'Cancel' and 'Save' buttons.

7. Enter values as described in the following table.

Field	Description
NAME	Enter a meaningful name for your query. You can enter alphanumeric values and also use special characters.
DESCRIPTION	This is optional. You can enter a description about the query you are creating. The description can help other users to get a quick overview of what this query is about.
Shared	<p>Select this check box to share this query with others.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Once you share a query, all the other users will also be able to edit, and delete it. Be mindful about making a query as a shared query.</p> </div>

8. Select **Save**.

The query is saved.

9. Select the **Saved Queries** tab.

The query you saved will be listed.

You can run or [edit \(on page 744\)](#) the query.

Run a Saved Query

After you create and save a query, you can run the query and see the query results.

This topic describes how to run a saved query.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data**.
The **Data** section appears, displaying a list of object instances and the underlying variables and contained types hierarchically.
3. Select the **Saved Queries** tab.
The list of all the saved queries appears.
4. Select a query as needed.

5. Select , and then select **Run**.



NAME	DESCRIPTION	SHARED	CREATEDBY	LAST MODIFIED BY
Filter	Filter	Filter	Filter	Filter
My Interpolated Data	Interpolated data query.	False		

SYSTEM

New Query **Saved Queries**

Last updated on 3/14/2024, 4:57:53 PM. 

Run
Delete

The query results are plotted on a trend chart.

Update a Saved Query

There can be changes in a process and so in the values. To update your saved queries, you can use the update option.

This topic describes how to edit and update a saved query.



Note:

If you are accessing a shared query, and if you did not create it, be mindful before you edit it. If possible, avoid editing the query.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data**.
The **Data** section appears, displaying a list of object instances and the underlying variables and contained types hierarchically.
3. Select the **Saved Queries** tab.
The list of all the saved queries appears.
4. Select a query as needed.
5. Select , and then select **Run**.

SYSTEM				
New Query Saved Queries				
				Last updated on 3/14/2024, 4:57:53 PM. 
NAME	DESCRIPTION	SHARED	CREATEDBY	LAST MODIFIED BY
<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>
My Interpolated Data	Interpolated data query.	False		
				<input type="button" value="Run"/> <input type="button" value="Delete"/>

The query results are plotted on a trend chart.

6. Select the **Edit** beside **Tag Selection** and **Query Builder** to edit tags and query criteria.

a. Edit the tag selections or query criteria as needed.

b. Select **Generate Report**.

The **Query Builder Summary** appears.

7. Select **Update**.

The screenshot displays a software interface for managing queries. At the top, there are tabs for 'Tags-dev_plugin' and 'Data-dev_plugin'. Below this, the 'SYSTEM' section is visible. The main area is titled 'New Query' and 'Saved Queries'. A breadcrumb trail shows '< Back My Interpolated Data'. The 'Query Builder Summary' section includes an 'Update' button (highlighted with a red box) and a 'Save as new Query' button. The 'Tag Selection' section shows two tags: '_Simulation_13.Constant' and '_Simulation_13.Constant_1%Noise'. The 'Query Builder' section provides details on the query configuration:

TIME	MODE
START DATE 2/21/2024, 11:11:46 AM	SAMPLING MODE Interpolated
END DATE 2/21/2024, 12:11:46 PM	SAMPLE DIRECTION Forward
	SAMPLES 1000

Below the table, the 'QUERY MODIFIERS' section shows 'NO MODIFIER'. The 'FILTER' section is empty. At the bottom, there are tabs for 'Trend' and 'Table', and a legend for the data series: '_Simulation_13.Constant_1%Noise' (blue) and '_Simulation_13.Constant' (red). A line graph shows the data trend over time, with values ranging from 505 to 510.

The **Update Query:<Query Name>** window appears.

Update Query : My Interpolated Data

DESCRIPTION

Enter Description

Shared

Cancel
Update

8. Update the description if needed
9. Select **Update**.
The query is updated.
10. To go back to the saved queries tab, in the top-left corner, select **<Back**

Update a Saved Query and Save it as a New Query

This topic describes how to update a saved query and save it as a new query.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data**.
The **Data** section appears, displaying a list of object instances and the underlying variables and contained types hierarchically.
3. Select the **Saved Queries** tab.
The list of all the saved queries appears.
4. Select a query as needed.
5. Select , and then select **Run**.

The screenshot shows a table with the following columns: NAME, DESCRIPTION, SHARED, CREATEDBY, and LAST MODIFIED BY. The table contains one entry: 'My Interpolated Data' with the description 'Interpolated data query.' and 'SHARED' set to 'False'. To the right of the table, there is a 'Last updated on 3/14/2024, 4:57:53 PM.' with a refresh icon. Below the table, there are 'Run' and 'Delete' buttons.

NAME	DESCRIPTION	SHARED	CREATEDBY	LAST MODIFIED BY
My Interpolated Data	Interpolated data query.	False		

The query results are plotted on a trend chart.

6. Select the **Edit** beside **Tag Selection** and **Query Builder** to edit tags and query criteria.

a. Edit the tag selections or query criteria as needed.

b. Select **Generate Report**.

The **Query Builder Summary** appears.

7. Select **Save as new Query**.

The screenshot shows the 'Query Builder Summary' window. It includes a 'Tag Selection' section with two tags: '_Simulation_13.Constant' and '_Simulation_13.Constant_1%Noise'. Below that is a 'Query Builder' section with a table of query parameters:

TIME	MODE	SAMPLE DIRECTION	SAMPLES
START DATE: 2/21/2024, 11:11:46 AM END DATE: 2/21/2024, 12:11:46 PM	SAMPLING MODE: Interpolated	Forward	1000

Below the table, there is a 'QUERY MODIFIERS' section with 'NO MODIFIER'. At the bottom, there is a 'FILTER' section and a 'Trend' chart showing two data series: '_Simulation_13.Constant_1%Noise' (blue) and '_Simulation_13.Constant' (red). The chart shows a noisy signal fluctuating between 505 and 510. There are 'Update' and 'Save as new Query' buttons at the top right of the window.

The **Save Query** window appears.

Save Query

NAME *

DESCRIPTION

Included additional Tags.

Shared

Cancel
Save

8. Enter a new name and description for the query.

9. Select **Save**.

The updated query is saved as a new query.

10. To go back to the saved queries tab, in the top-left corner, select **<Back**

Delete a Saved Query

This topic describes how to delete a saved query.



Note:

If you are accessing a shared query, and if you did not create it, be mindful before you delete it. Instead, kindly try to create a new query as needed.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data**.
The **Data** section appears, displaying a list of object instances and the underlying variables and contained types hierarchically.
3. Select the **Saved Queries** tab.
The list of all the saved queries appears.
4. Select a query as needed.

5. Select , and then select **Delete**.

The **Delete Query** window appears, prompting you whether to delete the saved query or not.

6. Select **Yes**.

The saved query is deleted.

Managing Alarms and Events

About Alarms and Events

Using Configuration Hub, you can manage alarms and events data from any OPC-compliant alarms and events server.



Note:

The Alarm Archiver must be available and running to access this feature.

Alarms: Alarms are generally defined as tags going into an abnormal condition. For example, you can set an alarm on a boiler when it reaches a specified temperature. Alarms usually have a well-defined life cycle, which is defined by the individual data sources from which the alarms data is collected. They enter an alarm state, are generally acknowledged, then return to normal.

To collect alarms and events data, you can use any of the following collectors:

- iFIX Alarms and Events collector
- OPC Classic Alarms and Events collector

Historian handles alarm data in two ways. You can view the entire Alarm as a single record that contains all information about the alarm, or you can view the Alarm History, which shows the transitions of the alarm as individual records.

Events: Events are generally defined as activities in a system that occur once only. For example, a user logging on to a device is an event. When viewing this data in Historian, each event is returned as a record.

Alarms and Events Requirements

To generate alarms and events data, you can use any OPC-compliant alarms and events server such as:

- CIMPLICITY
- iFIX

To collect alarms and events data, [install collectors \(on page 142\)](#), and then add any of the following collector instances:

- [iFIX Alarms and Events collector \(on page 505\)](#)
- [OPC Classic Alarms and Events collector \(on page 532\)](#)

To store alarms and events data, [install Historian Alarms and Events \(on page 140\)](#). During the installation, provide the credentials of Microsoft SQL server 2012 or later.

To view and analyze alarms and events data, you can use any of the following applications:

- Configuration Hub
- Historian Administrator
- Crystal Reports 11 or later
- The OLEDB Provider
- REST APIs



Note:

Before starting the Alarm Archive service, ensure that "NT AUTHORITY\SYSTEM" has "SysAdmin" privileges.

Create an Alarm

This topic describes how to create an alarm manually. You can use it to verify that Historian is collecting alarm data. You can then use the iFIX Alarms and Events collector or the OPC Classic Alarms and Events collector to collect alarm data and store it in Historian.

1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub for Historian, select **Alarms**. The **Alarms** section appears.
3. In the upper-right corner of the page, select .



Note:

To select hierarchical model tags you must need to have the valid license.

The **Add Alarm** window appears, displaying a list of tags in a hierarchical view. If you want to view a flat list of all the tags, select .

4. Select the check boxes corresponding to the tags for which you want to create an alarm, and then select **Next**.

The **Alarm Attributes** section appears, displaying the selected tags. The **TAG NAME** and **TIMESTAMP** columns are automatically populated.

5. For each tag, enter values as described in the following table.

Column	Description
SEVERITY	Specify whether you want to record high or low severity for the alarm.
DATA QUALITY	Specify whether you want to record good or bad quality for the alarm.
MESSAGE	Enter a message for the alarm.

6. Select **Write Alarm**.

The alarm is created.

Access/Filter Alarms

1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub for Historian, select **Alarms**.
The **Alarms** section appears.
3. To filter for alarms, enter values as described in the following table.

Field	Description
GENERATED FROM	Enter the start date and time for which you want to filter alarms. By default, ten minutes earlier than the current time is considered. A value is required.
GENERATED TO	Enter the end date and time for which you want to filter alarms. By default, the current time is considered. A value is required.
COLLECTOR NAME	Select the collector that collects the alarms and events data.

4. Select **Apply**.

The alarms and events data is filtered based on the criteria. To access the events data, select **Events**. The list of events is also filtered based on the criteria.



Tip:

You can show/hide/reorder columns in the table. For instructions, refer to [Common Tasks in Configuration Hub \(on page 353\)](#).

Back up Alarms Using Configuration Hub

1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub for Historian, select **Alarms**.
The **Alarms** section appears.
3. Select **☰**, and then select **Backup Alarms**.
The **Backup Alarms** window appears.
4. Enter values as described in the following table.

Field	Description
GENERATED FROM	Enter the start time for which you want to back up alarms.
GENERATED TO	Enter the end time for which you want to back up alarms.
PROVIDE FILE NAME	<p>Enter the file name and location of the back up file that you want to create. By default, the backup location of the default data store is considered. And, the file name is in the following format: <code>mm_dd_yyyy_hh_mm_ss</code>. For example: <code>11_25_2022_11_23_26.zip</code>. The time format followed is the 24-hour time notation.</p> <div data-bbox="678 1375 727 1423" data-label="Image"> </div> <p>Note: This file naming convention for alarm backup is standard to Historian. Even if you use other date settings such as <code>dd-mm</code>, the file name will still be saved in the <code>mm-dd</code> format.</p> <p>The end time stamp in the file name indicates the time at which the alarms have been backed up but not the time till when the alarms are backed up. For example, suppose, at 8.00 am, you back up alarms for the past two hours, the backup will contain alarms from 6:00 am to 8:00 am but may not contain an alarm</p>

Field	Description
	generated at 8:00 am. The last alarm may have been at 7:50 am. But the backup file name will have the time stamp of 8:00:00 along with the date.

5. Select **Backup**.

The alarms data is backed up.

Restore Alarms Using Configuration Hub

Restoring alarms to a running system makes them available for query and analysis. You can restore alarms that have been backed up or deleted previously.

1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub for Historian, select **Alarms**.
The **Alarms** section appears.
3. Select , and then select **Restore Alarms**.
The **Restore Alarms** window appears.
4. In the **PROVIDE FILE NAME** field, provide the backup file in the .zip format that you want to restore.



Note:

Remember to include .zip at the end of the file name.

5. Select **Restore**.

The alarm data is restored.

About Purging Alarms

Purging alarm data involves deleting the data from the database.



Note:

- Even after purging, the data is not lost; a backup is created to maintain an audit trail. You can restore the data if needed.
- When using circular archives (that is, archives that roll over), alarms are purged automatically.

You can choose to purge alarm data for any of the following reasons:

- To maintain alarm data efficiently
- The data is outdated or redundant
- The disk space is limited

Data in the following tables is purged:

- Alarm Attribute Values
- Alarm Attribute Value History
- Delete from Alarm History
- Delete from Alarm Table esignatures
- comments

You can purge data using one of the following methods:

- Purge data within a specified duration. You can do this [using Configuration Hub \(on page 756\)](#), [using the Proficy Historian Alarm and Event Data Migration utility \(on page 1221\)](#) or [at a command prompt \(on page 1223\)](#).
- Purge data related to a specific alarm ID. You can do this [using `Alarms.PurgeAlarmsById` \(on page 1604\)](#) to develop an SDK program.

Purging is performed in batches. You can check the log data in the `Proficy.Historian.AandE.Migration.log` file. By default, this file is located in the `C:\Program Files(x86)\Proficy` folder.

In the case of a failure:

- The batch size is changed to 10. That is, the collector receives an acknowledgement after sending 10 messages, thus reducing the load on the server.
- The waiting time for receiving an acknowledgement is automatically incremented after each failure per batch, starting from 90 seconds to 270 seconds. This gives more time for the server to respond.



Note:

After the acknowledgement is received, the batch size and the waiting time are reset for the subsequent batches.

If the time taken to purge exceeds the timeout limit, instead of reverting the entire purging operation, only the current batch, which is still under processing, is purged.

Best Practices:

- Restart the Alarms and Events services before purging data.

Purge Alarms Using Configuration Hub

1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub for Historian, select **Alarms**.
The **Alarms** section appears.
3. Select **☰**, and then select **Purge Alarms**.
The **Purge Alarms** window appears.
4. In the **PROVIDE FILE NAME** field, pro
5. Enter values as described in the following table.

Field	Description
GENERATED FROM	Enter the start time for which you want to purge alarms.
GENERATED TO	Enter the end time for which you want to purge alarms.
PROVIDE FILE NAME	<p>Enter the file name and location of the back up file that you want to create. This field is enabled only if you select the BACKUP ALARMS BEFORE PURGE? check box. By default, the backup location of the default data store is considered. And, the file name is in the following format: <code>mm_dd_yyyy_hh_mm_ss</code>. For example: <code>11_25_2022_11_23_26.zip</code>. The time format followed is the 24-hour time notation.</p> <div style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Note: This file naming convention for alarm backup is standard to Historian. Even if you use other date settings such as <code>dd-mm</code>, the file name will still be saved in the <code>mm-dd</code> format.</p> </div> <p>The end time stamp in the file name indicates the time at which the alarms have been backed up but not the time till when the alarms are backed up. For example, suppose, at 8.00 am, you</p>

Field	Description
	back up alarms for the past two hours, the backup will contain alarms from 6:00 am to 8:00 am but may not contain an alarm generated at 8:00 am. The last alarm may have been at 7:50 am. But the backup file name will have the time stamp of 8:00:00 along with the date.
BACKUP ALARMS BEFORE PURGE?	Select the check box if you want to back up alarms before purging.

6. Select **Purge**.

The alarms data is purged. A backup file is created if you have selected the **BACKUP ALARMS BEFORE PURGE?** check box.

Managing Configuration Templates

About Configuration Templates

A configuration template is a predefined set of common configuration options. You can create a configuration template for data stores and collectors separately and apply it to data stores and collectors as needed. This will help you save time by eliminating the need to configure common parameters manually and reduce monotonous tasks.



Note:

You can apply a data store configuration template to a user-created data store, provided they are not set as the default data store.

The following are some of the advantages of creating a configuration template:


- Update some common configurations of a data store or collector.
- Save time from configuring common parameters.

Create a Configuration Template for Collectors

This topic describes how to create a configuration template for collectors.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Configuration Templates**.

The **Collectors** tab appears, providing you to option to create template.



3. Select **+**.


The **Collectors:Configuration Template** window appears.

The screenshot shows the 'Collectors: Configuration Template' form. It has a title 'Collectors: Configuration Template'. Below the title are two input fields: 'TEMPLATE NAME*' with the value 'Python_Collector_Template' and 'DESCRIPTION' with the value 'This is a template for Python Collector with Unsolicited collection type.'. At the bottom right are two buttons: 'Cancel' and 'Add'.

4. In **TEMPLATE NAME**, enter a name for the template. You can enter any alphanumeric names and also use special characters.
5. In **DESCRIPTION**, enter a description for your template.

6. Select **Add**.

The configuration template is created.



7. Select the row that contains the created template.

The configuration details appear in the **DETAILS** section.

Table 47. The Template Section

Field	Description
Template Name	The name of the template. This field is read-only.
Description	The description of the template. You can edit the description if needed.

Table 48. The General Section

Field	Description
Memory Buffer Size (MB)	The size of the memory buffer currently assigned to the store-and-forward function. The memory buffer stores data during short-term or momentary interruptions of the server connection; the disk buffer handles long duration

Field	Description
	<p>outages. To estimate the size you need for this buffer, you need to know how fast the collector is trying to send data to the server and how long the server connection is likely to be down. With those values and a safety margin, you can compute the required size of the buffer.</p> <p>The default value is 20.</p>
Minimum Free Space (MB)	<p>The minimum free disk space that must be available on the computer. If the minimum space required is not available when the collector starts, the collector will shut down.</p>

Table 49. The Tags section

Field	Description
Tag Prefix	<p>The prefix that will be added to each tag that you configure for the collector instance. This field is disabled and populated with the name of the collector instance.</p> <p>This field applies to all collectors except File and Calculation collectors.</p>
Collection Interval Value	<p>The interval at which the collector collects data for all the tags configured in the collector instance.</p> <ul style="list-style-type: none"> ◦ For polled data collection, this value represents the time required to complete a poll of tags in the collector. ◦ For unsolicited data collection, it represents the frequency at which data is retrieved from tags in the collector. The collection interval can be individually configured for each tag. <p>You can set this value for each tag as well.</p>

Field	Description
	<div style="border: 1px solid orange; border-radius: 10px; padding: 10px; background-color: #fff9c4;"> <p>! Important:</p> <p>For an OPC collector, to avoid collecting redundant values when using device timestamps, specify a collection interval that is greater than the OPC server update rate.</p> </div>
Collection Interval	The units of measure for the collection interval value.
Collection Type	<p>The type of the data collection:</p> <ul style="list-style-type: none"> ◦ Polled: Data is collected based on a scheduled time interval. This type of data collection is supported only for: <ul style="list-style-type: none"> ▪ The Calculation collector ▪ The HAB collector ▪ The iFIX collector ▪ The OPC Classic DA collector ▪ The OPC UA DA collector ▪ The Python collector ▪ The Simulation collector ▪ The Windows Performance collector ◦ Unsolicited: Data is collected based on an event. This type of data collection is supported only for: <ul style="list-style-type: none"> ▪ The Calculation collector ▪ The HAB collector ▪ The MQTT collector ▪ The MQTT Sparkplug B collector ▪ The ODBC collector ▪ The OPC Classic DA collector ▪ The OPC Classic HDA collector ▪ The OPC UA DA collector ▪ The OSI PI collector ▪ The OSI PI distributor

Field	Description
	<ul style="list-style-type: none"> ▪ The Python collector ▪ The Server-to-Server collector ▪ The Server-to-Server distributor ▪ The Wonderware Collector

Table 50. The Collector Compression Section


Field	Description
Collector Compression	<p>Indicates whether you want to apply collector compression, which is a smoothing filter to data retrieved from the data source. By ignoring small changes in values that fall within a deadband centered around the last reported value, only significant changes are stored in Historian, thus consuming less archive storage space.</p> <p>For more information, refer to About Collector and Archive Compression (on page 660).</p>
Deadband	<p>Indicates whether you want to apply a deadband based on the percentage of values or on absolute values.</p> <p>For example, if you set the deadband to 20% for a range of 0 to 500 engineering units, the deadband value is 100 units, which is 50 units on each side. Therefore, only if the difference between two values is greater than 50, they are stored in Historian.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: If the data quality changes from good to bad or vice versa, the values are stored in Historian regardless of the deadband value.</p> </div>
Deadband Value	<p>The deadband value that you want to use for values collected by the collector. Depending on</p>

Field	Description
	<p>whether you have selected percent or absolute, the deadband value is determined.</p> <p>For example, if you want to set a deadband of 5 units on either side of a value (that is, value +/- 5), enter 10 in the Deadband Value field, and select Absolute in the Deadband field. Similarly, if you want to set a deadband of 5% on either side of a value, enter 10 in the Deadband Value field, and select Percent in the Deadband field.</p> <p>For more information, refer to About Collector and Archive Compression (on page 660).</p>
Compression Timeout	<p>The time for one poll cycle for which collector compression is not used, thus sending all the samples to Historian.</p> <p>This is used for a Calculation collector or Server-to-Server collector, when calculations fail, you may possibly observe collector compression (even if it is not enabled), thus producing no results or bad quality data. In such cases, you can use compression timeout, thus sending all the samples to Historian.</p> <p>For more information, refer to About Collector and Archive Compression (on page 660).</p>
Compression Timeout Interval	The units of measure for compression timeout.

Table 51. The Collector Options Section

Field	Description
Online Tag Configuration Changes	<p>Indicates whether you want tag configuration changes to reflect immediately. If you disable this option, any tag configuration changes will reflect only after you restart the collector instance.</p>

Field	Description
<p>Browse Source Address Space</p>	<p>Indicates whether you want to allow browsing for tags in the source. You may sometimes want to disable this option to reduce processing load on the collector.</p>
<p>Synchronize Timestamps to Server</p>	<p>Indicates whether you want to adjust the timestamp of data to align with the time setting in the Historian server. Note that this does not change the time setting in the collector machine; it only calculates the timestamp based on the difference between the time settings in the server machine and the collector machine, independent of time zone or daylight saving differences.</p> <div data-bbox="862 898 1419 1486" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <ul style="list-style-type: none"> ◦ This option is applicable only if the timestamp of the collector is considered (instead of that of the data source - as specified in the Time Assigned By field). ◦ If this option is disabled, and if the time in the collector machine is more than 15 minutes ahead of the time in the server machine, data will not be stored in Historian. </div>
<p>Delay Collection at Startup (sec)</p>	<p>The duration, in seconds, after which you want the data collection to begin post tag configuration.</p>



- After you edit the details as needed, in the upper-left corner, select **Save**.
The configuration details are saved.

You can select **⋮** and duplicate this template, edit, or delete it.

You can [apply the configuration template to a collector instance \(on page 650\)](#).

Apply Configuration Template to a Collector

You can apply the created template to collectors as needed. You will be prompted to confirm whether you want to overwrite few of the configuration values with the values in the template.

- Ensure that you have a [collector instance added \(on page 357\)](#).
- Ensure that you created a [configuration template for collectors \(on page 757\)](#).

This topic describes how to apply a configuration template to a collector.

- [Access Configuration Hub \(on page 336\)](#).
- In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors appears.
- Right-click the collector (or select **⋮**), and then select **Apply Configuration Template**.

The screenshot shows the 'Collectors-Historian' configuration page. At the top, there's a 'Configuration Template' tab and a 'Collectors-Historian' tab. Below the tabs, there's a 'SYSTEM' section and a 'Historian Collectors' section with a sub-tab for 'Offline Configuration Collectors'. A refresh button indicates the data was updated on 12/22/2023 at 9:29:36 AM. The main table has columns for Collector Name, Status, Configuration, Machine, and Version. The 'HistorianCollector' row is selected, and a context menu is open over it. The menu items include: Browse Tags (20), Add Tags (150), Recalculate (72,356), View Collector Performance (72,356), Start (CIFIC CONFIGURATION), Stop (10), Restart (4), Pause Data Collection (toggle), Resume Data Collection (toggle), Clear Buffer, Move Buffer, Change Destination Server, Reset Performance Counters, Reset Overruns (PythonSampleC...), Update Collector Credentials (1), Browse Activity Log (Seconds), **Apply Configuration Template** (Unsolicited), and Delete (Source).

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VER:
...ulation	Unknown	Historian		
...	Running	Historian		
...nCollector	Running	Historian		
..._Calculation	Running	Historian		
..._MQTTSparkplugB	Running	Historian		
..._Python	Unknown	Historian		
..._Python_1	Unknown	Historian		
..._Python_2	Unknown	Historian		
..._Simulation	Running	Historian		
..._Simulation_1	Running	Historian		

The **Apply Configuration Template** window appears, listing the available templates.

Apply Configuration Template

TEMPLATE NAME	TEMPLATE DESCRIPTION
<i>Filter</i>	<i>Filter</i>
Collector_Template	This is my sample template for collectors.
Python_Collector_Template	This is a template for Python Collector with Unsoli...

4. Select **Apply**.

A confirmation window appears, prompting you to confirm whether you want to overwrite few of the configuration values with the values in the template.

5. Select **Ok**.


6. In the upper-left corner, select **Save**.

The configurations in the template are applied to the collector.

Create a Configuration Template for Data Stores

This topic describes how to create a configuration template for data stores.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Configuration Templates**.
3. Select the **Data Stores** tab.



4. Select **+**.

The **Data Stores:Configuration Template** window appears.

Data Stores: Configuration Template

TEMPLATE NAME*

DataStore_Historical_Template

DESCRIPTION

This is a template for Data Store for historical data type.


Cancel
Add

5. In **TEMPLATE NAME**, enter a name for the template. You can enter any alphanumeric names and also use special characters.

6. In **DESCRIPTION**, enter a description for your template. The description box can do a spell check while you enter the description.

7. Select **Add**.

The configuration template is created.



- Select the row that contains the created template.
The data store details appear in the **DETAILS** section.

Table 52. The Template Section

Field	Description
Template Name	The name of the template. This field is read-only.
Description	The description of the template. You can edit the description if needed.

Table 53. Maintenance

Field	Description
Default Archive Path	The default folder in which you want to create archives.
Default Backup Path	The default folder in which you want to place the backup archives.
Free Space Required (MB)	Indicates the remaining disk space required after a new archive is created. If the available space is less than the requirement, a new archive is not created. The default value is 5000 MB. This field is not applicable to alarms and events archives. The alarms and events archiver will continue writing to the alarms and events archive until the drive is full. If this occurs, the alarms and events archiver will buffer incoming alarms and

Field	Description
	events data until the drive has free space. An error message is logged in the Historian message log.
Store OPC Quality	Indicates whether OPC data quality is stored.
Use Caching	Indicates whether caching is enabled. When reading data from the archiver, some data is saved in the system memory and retrieved using caching. This results in faster retrieval as the data is already stored in the buffer.


Table 54. Archive Creation

Field	Description
Create Archive by	<p>Indicates whether you want to create a new archive automatically after the current one reaches a specific size or after a specific duration. This field is enabled only if you switch the Automatically Create Archives toggle on.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Size: Select this option if you want to create a new archive when the current one reaches a specific size. Specify the size in the Default Size (MB) field (which appears only if you select Size). ◦ Days or Hours: Select one of these options if you want to create a new archive after a specific duration. Specify the duration in the Archive Duration field (which appears only if you select Days or Hours).
Default Size (MB)	The default size of an archive after which a new one will be automatically created if you switch the Automatically Create Archives toggle on. The Default Size (MB) field appears only if you select Size in the Create Archive By field.
Automatically Create Archives	Indicates whether you want to create an archive automatically (on page 727) after the current one is full. An archive file is considered full based on the size or duration you specify in the Create Archive By and the Archive Duration or Default Size fields.

Field	Description
Overwrite Old Archives	<p>Indicates whether you want to overwrite an old archive file when a new one is created.</p> <p>If you enable this option, the oldest archived data is replaced with the latest one when the latest archive default size is reached. Since this action deletes historical data, exercise caution in using this feature. Be sure that you have a backup of the archive so that you can restore it later. Best practice is to create an additional archive to prevent premature loss of data due to overwriting. For example, if you want to save 12 months of data into 12 archives, create 13 archives.</p>

Table 55. Security

Field	Description
Data is Read-Only After (Hours)	The number of hours for data to be stored in a read/write archive. After the time lapses, that portion of the archive file is automatically made read-only. Incoming data values with timestamps prior to this time are rejected. A single archive file, therefore, may have a portion made read-only, another portion that is read/write containing recently written data, and another that is unused free space.
Generate Message on Data Update	Indicates whether an audit log entry will be made any time the value of a previously archived data point is overwritten. This log entry will contain both the original and new values.



- After you edit the details as needed, in the upper-left corner, select **Save**. The configuration details are saved.

You can select  and duplicate this template, edit, or delete it.

You can [apply the configuration template to a data store \(on page 463\)](#).


Apply the Configuration Template to a Data Store

You can apply the created template to user-created data store as needed. You will be prompted to confirm whether you want to overwrite few of the configuration values with the values in the template.

- Ensure that you have a [data store created \(on page 370\)](#).
- Ensure that you have a [configuration template for data stores \(on page 767\)](#).

This topic describes how to apply a data store configuration template to a data store. You can apply a data store configuration template to a user-created data store, provided they are not the default data store.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Data Stores**. The **Data Stores** section appears.
3. Right-click the data store (or select **☰**), and then select **Apply Configuration Template**.



The **Apply Configuration Template** window appears, listing the available templates.

Apply Configuration Template

TEMPLATE NAME	TEMPLATE DESCRIPTION
<i>Filter</i>	<i>Filter</i>
DataStore_Historical_Template	This is a template for Data Store for historical data...

Cancel Apply

**Note:**

You can apply a data store configuration template to a user-created data store, provided they are not the default data store.

4. Select Apply.

A confirmation window appears, prompting you to confirm whether you want to overwrite few of the configuration values with the values in the template.

5. Select Ok.**6. In the upper-left corner, select Save.**

The configurations in the template are applied to the data store.

Managing Reports

About Reports

Reports provide you with a concise summary of tag-specific data of a specific collector.

You can select a report from the available predefined templates and generate a report to view categorized data. For example, you can generate a report that lists tags with aliases and view the needed information. You can also export the generated report as a CSV file or save it as a PDF file.

**Note:**

The reports are applicable only to the Historian destination collectors.


For more information on generating reports, refer to [generate reports \(on page 774\)](#).

Generate Reports

This topic describes how to generate report using a predefined template. You can select template from the available template options and generate a report.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Reports**.

A list of predefined templates appear.



3. Select a template as needed.

The corresponding input options appear, enabling you to select the collector and other options as needed. Based on your selections, you can generate the report.

4. Select the collector and other corresponding options.

**Note:**

To generate a report, you must select a collector.

The below table lists different reports and their corresponding input options.

Report	Description	Input Options	Data Available in the Report
Tag Aliases	This report displays tags that have aliases, along with the list of aliases for the selected collector instance.	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. 	<ul style="list-style-type: none"> ◦ TAG NAME
Invalid Source Tags	<p>This report displays tags with a collector name but no configured source address for the selected collector instance.</p> <div data-bbox="570 856 831 1121" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: This report is not applicable for a File collector. </div>	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. 	<ul style="list-style-type: none"> ◦ TAG NAME ◦ DESCRIPTION
Continuous Bad Value Tags	<p>This report displays tags that are continuously returning bad data for the selected Time Interval for the collector instance. You can carefully analyze those tags and make decisions.</p>	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. ◦ TIME INTERVAL- The duration based on which the report must be generated. The available options are, <ul style="list-style-type: none"> ▪ 1 hour ▪ 8 hours ▪ 1 day ▪ 1 week ▪ 1 month 	<ul style="list-style-type: none"> ◦ TAG NAME ◦ DESCRIPTION

Report	Description	Input Options	Data Available in the Report
		<ul style="list-style-type: none"> ▪ Custom- Selecting this option enables a custom start and end date/time selector. You can select or enter a custom start and end date/time based on which the report must be generated. 	
No Data Tags	This report displays tags that are not writing any data for the selected collector instance.	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. ◦ TIME INTERVAL- The duration based on which the report must be generated. The available options are, <ul style="list-style-type: none"> ▪ 1 hour ▪ 8 hours ▪ 1 day ▪ 1 week ▪ 1 month ▪ Custom- Selecting this option enables a cus- 	<ul style="list-style-type: none"> ◦ TAG NAME ◦ DESCRIPTION ◦ VALUE ◦ TIME STAMP ◦ DATA COLLECTION

Report	Description	Input Options	Data Available in the Report
		<p>tom start and end date/time selector. You can select or enter a custom start and end date/time based on which the report must be generated.</p>	
Soft Deleted Tags	<p>This report displays tags that were removed from the system but still exist in Historian and are not being used for the selected collector instance.</p>	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. ◦ TIME INTERVAL- The duration based on which the report must be generated. The available options are, <ul style="list-style-type: none"> ▪ 1 hour ▪ 8 hours ▪ 1 day ▪ 1 week ▪ 1 month ▪ Custom- Selecting this option enables a custom start and end date/time selector. You can select or 	<ul style="list-style-type: none"> ◦ TAG NAME ◦ DESCRIPTION ◦ DELETION TIME ◦ USER NAME

Report	Description	Input Options	Data Available in the Report
		<p>enter a custom start and end date/ time based on which the report must be generated.</p> <ul style="list-style-type: none"> ◦ USERNAME- The name of the user based on which the report must be generated. 	
Current Values	This report displays the current values of tags for the selected collector instance.	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. 	<ul style="list-style-type: none"> ◦ TAG ◦ ENGINEERING UNITS (DESCRIPTION) ◦ QUALITY ◦ VALUE ◦ TIME STAMP
Stale Tags	This report displays all the stale tags for the selected collector instance.	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. 	<ul style="list-style-type: none"> ◦ TAG NAME ◦ DESCRIPTION
Data Collection Status	This report displays the data collection status of tags for the selected collector instance.	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. ◦ DATA COLLECTION- The status of da- 	<ul style="list-style-type: none"> ◦ TAG NAME ◦ DESCRIPTION ◦ DATA COLLECTION

Report	Description	Input Options	Data Available in the Report
		ta collection based on which the report must be generated. The available options are, <ul style="list-style-type: none"> ▪ On ▪ Paused. 	
Tag Creation Audit Trail	This report displays information about tag creation time and created user.	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. ◦ TIME INTERVAL- The duration based on which the report must be generated. The available options are, <ul style="list-style-type: none"> ▪ 1 hour ▪ 8 hours ▪ 1 day ▪ 1 week ▪ 1 month ▪ Custom- Selecting this option enables a custom start and end date/time selector. You can select or enter a custom start and end date/ time based 	<ul style="list-style-type: none"> ◦ TAG NAME ◦ DESCRIPTION ◦ CREATION TIME ◦ CREATED BY

Report	Description	Input Options	Data Available in the Report
		<p>on which the report must be generated.</p> <ul style="list-style-type: none"> ◦ CREATION TIME- The time of creation based on which the report must be generated. ◦ CREATED USER- The name of the user based on which the report must be generated. 	
Collector Data Quality	This report displays the data quality of tags for the selected collector instance.	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. 	<ul style="list-style-type: none"> ◦ COLLECTOR NAME ◦ DESCRIPTION ◦ TOTAL TAG COUNT ◦ BAD TAGS COUNT ◦ BAD TAGS PERCENT ◦ GOOD TAGS COUNT ◦ GOOD TAGS PERCENT
No Data From Start Tags	This report displays tags that do not have data from the time they were created for the selected collector instance.	<ul style="list-style-type: none"> ◦ COLLECTOR NAME- Name of the collector instance based on which the report must be generated. 	<ul style="list-style-type: none"> ◦ TAG NAME ◦ DESCRIPTION

5. Click **Generate Report**.

The data corresponding to the selected report appears.

You can [export the generated report as a CSV file \(on page 781\)](#), or [save the generated report as a PDF file \(on page 781\)](#).

Export the Generated Report as a CSV File

This topic describes how to export and save a report as CSV file.


Ensure that you have the following:

- Microsoft Excel or any text editor is needed to view the exported CSV file.

1. [Generate the report \(on page 774\)](#) as needed.

2. To export the report as a CSV file, in the upper-right corner of the grid, select .

The report is exported as a CSV file.



The screenshot shows the 'Reports Historian' interface. At the top, there are search and filter options for predefined reports: 'Tag Aliases', 'Invalid Source Tags', 'Bad Value Tags', 'No Data Tags', and 'Soft Deleted Tags'. Below these, there are dropdown menus for 'COLLECTOR NAME' (set to 'Simul_DEMO') and 'MAX TAG COUNT' (set to '10'). A 'Generate Report' button is located in the top right corner of the report area. The main part of the interface is a table with 10 items, showing a list of simulation tags with their values, engineering units, quality, and time stamps.

TAG	VALUE	ENGINEERING UNITS/DESCRIPTION	QUALITY	TIME STAMP
Simul_DEMO.Simulation00001	0	Hz	Bad	11/17/2023, 12:47:46 PM
Simul_DEMO.Simulation00002	156981.1094	Hz	Good	11/17/2023, 1:52:54 PM
Simul_DEMO.Simulation00003	89168.98438		Good	11/17/2023, 1:52:54 PM
Simul_DEMO.Simulation00004	46693.32031		Good	11/17/2023, 1:52:54 PM

The file will be saved in the <System Name>_Reports_Export_Details_with_<ReportName> format. For example, **SYSTEMADMIN_Reports_Export_Details_with_CurrentValues**.

Save the Generated Report as a PDF File

This topic describes how to save the report as a PDF file.


Ensure that you have the following:

- A PDF reader is required to open and view the report saved as a PDF file.

1. [Generate the report \(on page 774\)](#) as needed.

2. To save the report as a PDF file, in the upper-right corner of the grid, select .

The report is saved as a PDF file.



The file will be saved in the Reports_<System Name>_<ReportName>_<MM_DD_YYYY, hh_mm_ss AM/PM> format. For example, **Reports_SYSTEMADMIN_CurrentValues_10_17_2023, 1_30_20 AM**.

Access Activity Logs

Activity logs are generated when activities are performed in the Historian system.

Examples:

- When a tag is created, modified, or deleted
- When a collector instance is created, modified, or deleted
- When data collection for a tag or a collector begins or ends
- When an archive is created or will be closed soon

You can access these logs for each tag/collector or for all the tags and collectors in a system. You can filter these logs based on the start and end dates, priority, topics, and the content in the logs. You can also export all the logs or selected ones.

1. [Access Configuration Hub \(on page 336\)](#).
2. If you want to access activity logs for all the tags and collectors in a system, in the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Activity Logs**.

A list of activity logs appears.

3. If you want to access the activity logs of a collector instance:
 - a. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.

A list of collectors in the system appears.

- b. Right-click the collector whose activity log you want to access (or select ) , and then select **Browse Activity Log**.

A list of activity logs for the collector appears.

4. If you want to access the activity logs of a tag:

- a. In the **NAVIGATION** section, select **Historian_<system_name> > Tags**.

A list of tags in the system appears.

- b. Right-click the tag whose activity log you want to access (or select ) , and then select **Browse Activity Log**.

A list of activity logs for the tag appears.

5. If you want to filter the list of activity logs:

- a. In the upper-right corner of the main section, select .

- b. Enter values as described in the following table.

Field	Description
START DATE/TIME	Select the start date and time for the activity logs.
END DATE/TIME	Select the end date and time for the activity logs.
PRIORITY	Specify whether you want to see only alerts or messages or both.
TOPIC	Select the topic based on which you want to filter the logs: <ul style="list-style-type: none"> ▪ Configuration: Includes modifying a collector instance or a tag configuration. ▪ Connections: Includes system connections and creating a collector interface.

Field	Description
	<ul style="list-style-type: none"> ▪ General: Includes pausing or resuming data collection. ▪ Performance: Includes creating or closing an archive and moving buffer files. ▪ ServiceControl: Includes starting or stopping a collector interface. <p>This list is not comprehensive.</p>
ACTIVITY CONTAINS	Enter the content of the logs based on which you want to filter them.

c. Select **Apply**.

The logs are filtered based on the criteria.

If you want to export the logs, select . The logs are exported into a CSV file.

Troubleshooting Configuration Hub

This topic contains solutions/workarounds to some of the common issues encountered with Configuration Hub. This list is not comprehensive. If the issue you are facing is not listed on this page, refer to [Troubleshooting Web-based Clients \(on page 300\)](#) and [Troubleshooting the Historian Server \(on page 298\)](#).

Unable to Access Configuration Hub After Upgrading Web-based Clients

Workaround: Clear your browser cache.

Even after installing Web-based Clients, you cannot access Configuration Hub.

Workaround: Start the Proficy Operations Hub Httpd Reverse Proxy and the Data Archiver services.

Unable to Access External Configuration Hub if Public Https Port is Different

Issue: During Web-based Clients installation, if you provide an existing Proficy Authentication and Configuration Hub details, and if the public https port numbers of these two machines do not match, you cannot access the external Configuration Hub from the current machine.

For example, suppose you have installed Web-based Clients on machine A, which points to the Proficy Authentication and Configuration Hub installed on machine B. If the public https port numbers of

machines A and B do not match, you cannot access Configuration Hub of machine B from machine A (although you can access it locally from machine B).

Workaround: Perform the following steps on the machine on which you have installed Configuration Hub (machine B):

1. Access the following folder: `C:\Program Files (x86)\GE\ConfigurationHub\Web\conf\confighub`
2. Access the file that contains the details of the machine from which you want to access external Configuration Hub (machine A). The file name begins with the host name of machine A.
3. In the line that contains the details of the Proficy Authentication server (for example, `proxy_pass https://machine_B.Domain.com:Port/uaa/`), change the port number to match the public https port number of machine B.
4. Save and close the file.
5. Restart the following services:
 - ConfigHubContainerService
 - ConfigHubNGINXService
 - ConfigHubStorageService

Error Occurs When Historian Plugin is Registered with an External Configuration Hub

Description: If you install Configuration Hub using iFIX, then install Web-based Clients on another machine with local Proficy Authentication, and then register the Historian plugin with Configuration Hub, testing the connection to Configuration Hub fails. Even after you add the IP addresses of both the machines to the hosts file, the issue is not resolved.

Error Message: Error while getting token in ConfigAuth App

Workaround: [Register the Historian plugin \(on page 186\)](#) on the machine on which you have installed Web-based Clients, [install the Proficy Authentication certificate \(on page 97\)](#), and then restart the browser.

Cannot Access the Collectors Section or Add a Collector Instance

Possible Cause: User credentials not provided while installing collectors or Remote Collector Manager:

If installing collectors and the Historian server on the same machine, the collectors installer does not mandate the entry of username and password because it not required for Remote Collector Management Agent to connect to a local Historian server. But if Historian security or strict authentication is enabled, it is mandatory to enter the username and password.

Workaround:

- **Option 1:** Disable the strict collector authentication using Historian Administrator, and then restart the Historian Remote Collector Management Agent service.
- **Option 2:** Reinstall Remote Management Agents, providing the user credentials.

Cannot Access or Add a System in Configuration Hub

Possible Causes:

- **User does not have security privileges:** During installation of the Historian server, if you have allowed the installer to create security groups, you must create a user with the name in the following format: <Proficy Authentication host name>.admin. Verify that this user has been created and added to the ihSecurityAdmins group.

If the Proficy Authentication server hostname is long, resulting in a username longer than 20 characters, Windows does not allow you to create the user. In that case, you can create a Proficy Authentication user, and then create the corresponding Windows user, using the Proficy Authentication Configuration utility:

1. Access the Proficy Authentication Configuration utility. By default, it is located at C:\Program Files\GE Digital\Historian Config\uaa_config_tool.
2. Run the following command: `uaa_config_tool add_user -u <username> -p <password> -s <the client secret you provided while installing the Historian server> -c`

Example: `uaa_config_tool add_user -u adminuser -p Password123 -s pwd@123 -c`

- **Incorrect Proficy Authentication details:** You must provide the host name of the Proficy Authentication server while installing the Historian server. In the Computer\HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\SecurityProviders\OAuth2 registry path, verify that the URI value is in the following format: `https://<Proficy Authentication host name>:<port number>/uaa/check_token.`

If needed, modify the value, and then restart the Data Archiver service.

Error Appears When Creating a Collector Instance

Description: When you add a collector instance, the following error message appears: `The server encountered an error processing the request. Please try again.` The collector instance is added successfully, but it does not appear in the **Collectors** section.

Possible causes: When you add a collector instance, the collector service is started and stopped so that it is connected to the Historian server. The collector then appears in the table in the **Collectors** section. Sometimes, however, the collector service does not respond to these commands on time, resulting in the

error message. If you attempt to add the same collector instance again, a message appears, stating that it exists.

Workaround: Select **Cancel**, and refresh the **Collectors** section. If the collector instance still does not appear, access the collector machine, and start the collector manually.

Data Archiver is Shut Down

Possible causes: If there is insufficient disk space, the Data Archiver shuts down and a message is logged into the log file. By default, you can view the Historian archiver log file in C:\Historian Data \LogFiles.

Workaround: Allocate more disk space for archives, or remove old archives. You can also configure Historian to overwrite old archives automatically by switching the **Overwrite Old Archives** toggle on. If you enable this option, the oldest archived data is replaced with the latest one when the latest archive default size is reached. Since this action deletes historical data, exercise caution in using this feature. Be sure that you have a backup of the archive so that you can restore it later. Best practice is to create an additional archive to prevent premature loss of data due to overwriting. For example, if you want to save 12 months of data into 12 archives, create 13 archives.

For instructions, refer to [Access a Data Store \(on page 453\)](#).

Proficy Authentication and other Configuration Hub Plugins are not Visible in Configuration Hub, but Historian Plugin is Visible

Description: Consider that you used the Proficy Installer and installed common components such as Proficy Authentication and Configuration Hub. Then, you installed Historian Web components and registered Historian Plugin during the installation process. When you try to access Configuration Hub, the Historian Plugin is visible. However, the Plugins like Proficy Authentication, Administrator, and others are not visible. To resolve this issue, perform the below workaround.

Workaround:

1. From your desktop, select **Setup Authentication**.

The **Configuration Hub Login** window appears.

2. In the bottom-right corner, select **Configure Confighub Authentication**.

The **Configuration Hub Administrator Credentials** window appears.

3. Enter the Configuration Hub Client ID and Secret that were created while installing Configuration Hub.

4. Select **Verify**.

On a successful verification, the **Register with Proficy Authentication** window appears.

5. In **SERVER NAME (FULLY QUALIFIED NAME)**, enter the server name in a Fully Qualified Domain (FQDN) format.

6. In **SERVER PORT**, enter the Proficy Authentication Server port, by default, it is 443.

7. Enter the Configuration Hub Client ID and Secret that were created while installing Configuration Hub.

8. Select **Register**.

9. Log in to Configuration Hub and see if the other Plugins are also displayed.

On a successful registration, you will see all the other Plugins that were registered.

Chapter 4. Remote Collector Management

Overview of Remote Collector Management

Many Historian users use collectors to collect data from data sources or servers. Typically, these collectors are distributed geographically, and so, accessing them can be challenging and not cost-effective. To overcome this challenge, Historian provides the Remote Collector Management agent, using which you can manage collectors remotely.

Advantages of using the Remote Collector Management agent:


- Accessing a collector machine physically to manage the collector is no longer required.
- Security is enabled. That is, only members of the iH Security Admins, iH Tag Admins, and the iH Collector Admins security groups can manage the collectors remotely.
- Works with the older versions of collectors as well (V5.5 and later).

Features

- [Add \(on page 797\)](#), [modify \(on page 799\)](#), or [delete \(on page 817\)](#) a collector instance.
- [Start \(on page 637\)](#), [stop \(on page 638\)](#), or [restart \(on page 639\)](#) a collector.
- [Pause \(on page 641\)](#) or [resume \(on page 642\)](#) the data collection of a collector.
- [Delete \(on page 643\)](#) or [move \(on page 644\)](#) the buffer files of a collector.
- [Change the destination server of a collector \(on page 645\)](#).

Workflow

The following diagram provides the workflow of Remote Collector Management when creating a collector instance. After the collector instance is created, the collector sends data to the configured destination. The green lines indicate the initial, one-time steps. The red lines indicate the steps performed every time you want to manage the collector remotely.



Limitations

- After installing Remote Management Agent, if you install a new collector, you must manually start it for the first time. This is to establish a connection between the collector and the Remote Collector Management agent. From the next time, you can manage the collector remotely.

Installing Remote Management Agents

Install Remote Management Agent Using the Installer

Ensure that all the collectors that you want to manage remotely are in the running state.

If the collectors that you have installed are earlier than version 9.0, you must install Remote Management Agent on each machine on which the collectors that you want to manage are installed. For collectors version 9.0 or later, Remote Management Agent are automatically installed when you install collectors.

This topic describes how to install Remote Management Agent using the installer. You can also [install them at a command prompt \(on page 190\)](#).

1. Run the `InstallLauncher.exe` file.
2. Select **Install Remote Management Agents**.


The welcome page appears.

3. Select **Next**.

The license agreement appears.

4. Select the **Accept** check box, and then select **Next**.

The default installation drive appears.



5. If needed, modify the installation drive, and then select **Next**.

The destination Historian server page appears.

Historian Server Details

Provide a valid windows user of the default Historian server to which the Remote Collector Manager will connect.

Historian Server:

User Name:


Password:

Confirm Password:

Note: If you have created security groups or enabled strict client/collector authentication, provide the destination Historian credentials. If the password changes, you must reinstall Remote Management Agents to reset the password.

6. Enter the details of the Historian server to which Remote Management Agent will connect, and then select **Next**.

The **Data Directory** page appears.



7. As needed, modify the location of the data directory, or leave the default value, and then select **Next**.

The **You are ready to install** page appears.

8. Select **Install**.

- Remote Collector Management is installed on your machine.
- A folder named `Historian Remote Management Agents` is created in the `GE Digital` folder in the installation location that you specified.
- Remote Collector Management is running, and a `.shw` file is created in the log folder. This file contains the details of the collectors that are running on the machine.
- For each collector that you manage using Remote Collector Management, a new entry named `ServiceName` is created in the collector registry. If the `ServiceName` key is not created or updated incorrectly, refer to [Troubleshooting Remote Collector Management Issues \(on page 820\)](#).

Install Remote Management Agent at a Command Prompt

Ensure that all the collectors that you want to manage remotely are in the running state.

If the collectors that you have installed are earlier than version 9.0, you must install Remote Management Agent on each machine on which the collectors that you want to manage are installed. For collectors version 9.0 or later, Remote Management Agent are automatically installed when you install collectors.

This topic describes how to install Remote Management Agent at a command prompt. You can also [install them using the installer \(on page 187\)](#).

1. Access the command prompt, and navigate to the RMA folder in the install media.
2. Run the following command, replacing the values in angular brackets with the appropriate values:

```
HistorianRMA_Install.exe -s RootDrive=<installation drive> DestinationServerName=<Destination Historian server name>
UserNamel=<Windows username> Password=<Windows password> DataPath="C:\Proficy Historian Data\LogFiles"

HistorianRMA_Install.exe -s RootDrive=C:\ UserNamel=Administrator Password=AdminPassword
DestinationServerName=VMHISTWEBAUTO DataPath="C:\Proficy Historian Data\LogFiles"
```

- Remote Collector Management is installed on your machine.
- A folder named `Historian Remote Management Agents` is created in the `GE Digital` folder in the installation location that you specified.
- Remote Collector Management is running, and a `.shw` file is created in the log folder. This file contains the details of the collectors that are running on the machine.
- For each collector that you manage using Remote Collector Management, a new entry named `ServiceName` is created in the collector registry. If the `ServiceName` key is not created or updated incorrectly, refer to [Troubleshooting Remote Collector Management Issues \(on page 820\)](#).

About Managing Collector Instances Using the RemoteCollectorConfigurator Utility

After you install Historian, you must install the collectors. These collectors are used to collect data from various sources and send it to Historian. For a list of collectors and their usage, refer to [About Historian Data Collectors \(on page 1990\)](#).

After you install collectors and Remote Management Agent, the following artefacts will be available:

- **Executable files:** These files are required to add a collector instance.
- **Instances of the following collectors:**
 - The iFIX collector
 - The iFIX Alarms & Events collector
 - The OPC Classic Data Access collector for CIMPLICITY
 - The OPC Classic Alarms and Events collector for CIMPLICITY

These instances will be created only if iFIX and/or CIMPLICITY are installed on the same machine as the collectors.

- **The Remote Collector Management agent:** Provides the ability to manage collectors remotely.

You can then add a collector instance. This section describes how to add, modify, or delete a collector instance using the RemoteCollectorConfigurator utility. It is a System-API-based tool, which connects to the destination Historian server, and allows you to add, modify, and delete a collector instance without the need to install Web-based Clients. You can also [perform these tasks using Configuration Hub \(on page 627\)](#).

You can use the RemoteCollectorConfigurator utility in one of the following ways:

- **Using Command Prompt:** In this method, you will enter a single command at a command prompt to run the RemoteCollectorConfigurator utility and provide values to all the required parameters.
- **Using the interactive UI of the RemoteCollectorConfigurator utility:** In this method, you will run the RemoteCollectorConfigurator utility, and use the on-screen instructions to manually provide values to all the required parameters. Interactive UI mode does not apply when Strict Authentication is enabled for Historian. Use the RemoteCollectorConfigurator.exe from the command-line in such cases. See the following example.

In both these methods, you can either enter the installation parameters and their values manually or provide a JSON file that contains them. The RemoteCollectorConfigurator utility can also [create sample JSON files \(on page 796\)](#), which you can use to create or modify collector instances. In addition, you can run the RemoteCollectorConfigurator utility without connecting to Historian or a data archiver. This section describes how to use each of these methods.



Tip:

You can access the Help for the RemoteCollectorConfigurator utility by running the following command:

```
RemoteCollectorConfigurator.exe --help
```

Example: RemoteCollectorConfigurator.exe from the Command line

```
RemoteCollectorConfigurator.exe "HistorianServerName" "Userid" "Password" InterfaceCreateViaCmd
{"\"CollectorDestination\": \"Historian\", \"CollectorSystemName\": \"HistorianServerName\",
\"DestinationHistorian\": \"Historianservername\", \"DestinationHistorianUserName\": \"userid\",
\"DestinationHistorianPassword\": \"Gei32litc\", \"DataPathDirectory\": \"<datadrive>:\\Proficy\",
\"InterfaceName\": \"collector_name\", \"Type\": \"2\", \"mode\": \"1\"}"
```

Or:

```
<installation drive>:\Program Files\GE Digital  
\NonWebCollectorInstantiationTool>RemoteCollectorConfigurator.exe "<<Historian Server>>"  
"<<Userid>>" "<<Userpassword>>" InterfaceCreateViaFile "Inputjsonfile.json"
```

Create a Sample JSON File

To add or modify a collector instance, you can provide a JSON file with the required details. Instead of manually creating the file, you can use the RemoteCollectorConfigurator utility to generate a sample JSON file. You can then modify the file as needed, and then use it to add or modify the collector instance.

1. Run the RemoteCollectorConfigurator.exe file. By default, it is located in the following folder: C:\Program Files\GE Digital\NonWebCollectorInstantiationTool\RemoteCollectorConfigurator.exe.
A list of options to manage collector instances appears.
2. Enter 7.
A list of collector types appears, along with a number assigned to each of them. You are prompted to enter the collector type.
3. Specify the collector type by entering the corresponding number. For example, if you want to add an instance of the Calculation collector, enter 1.
A list of destinations appears, along with a number assigned to each of them.
4. Specify the destination by entering the corresponding number. For example, if the destination is a Historian server, enter 1.
5. If needed, enter the folder path where you want the sample JSON file to be created. By default, the file will be created in the same folder in which the RemoteCollectorConfigurator utility is located.
A sample JSON file is created.
6. As needed, update the sample JSON file with the required [collector instance parameters \(on page 801\)](#). You can also specify values for the [general parameters \(on page 814\)](#).

[Add \(on page 797\)](#) or [modify \(on page 799\)](#) the collector instance using the sample JSON file that you have created.

Add a Collector Instance

- [Install collectors \(on page 142\)](#).
- For an iFIX collector, if iFIX is not running in a Windows-service mode, an error occurs when you add the collector instance. Refer to [About Adding an iFIX Collector Instance \(on page 501\)](#) for expected behaviour and configuration recommendations.
- If the destination of a collector is an Azure IoT Hub device, ensure that the device is running.

Before you begin using a collector, you must add an instance of the collector. You can add multiple instances of the same collector or instances of multiple collectors where you have installed the collectors.

For an ODBC collector, a single mapping file is used by multiple instances.



Note:

When you install collectors, if iFIX and/or CIMPLICITY is installed on the same machine as the collectors, instances of the following collectors are created automatically:

- The iFIX collector
- The iFIX Alarms & Events collector
- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

You can begin using these collectors, or create more instances as needed.

This topic describes how to add a collector instance using the RemoteCollectorConfigurator utility. You can also [add a collector instance using Configuration Hub \(on page 357\)](#). If you want to add an offline collector instance, refer to [Add an Offline Collector Instance \(on page 819\)](#).

1. If you want to use an interactive UI:
 - a. Run the RemoteCollectorConfigurator.exe file. By default, it is located in the following folder: C:\Program Files\GE Digital\NonWebCollectorInstantiationTool.
A list of options to manage collector instances appears.
 - b. Connect to the collector machine by entering 1 or 2, depending on whether collectors are installed locally or on a remote machine.
 - c. Enter 4.

You are prompted to choose between entering the installation parameters manually and providing a JSON file.

- d. If you want to manually enter the parameters and values, enter 1, and then run the following command:

```
{ "<parameter>": "<value>", "<parameter>": "<value>" }
```

If you want to use a JSON file containing the installation parameters and values, enter 2, and then enter the path to the JSON file that you have created. Instead of manually creating the JSON file, you can use the RemoteCollectorConfigurator utility to [generate it automatically \(on page 796\)](#).

You can leave the Historian username and password blank if there are no Historian security user groups.

For information on the parameters, refer to [Collector Instance Parameters \(on page 801\)](#).

2. If you want to use the Command Prompt window:

- a. Access the installation folder of the RemoteCollectorConfigurator utility. By default, it is C:\Program Files\GE Digital\NonWebCollectorInstantiationTool.
- b. Run Command Prompt in this location.
- c. If you want to manually enter the installation parameters and values, run the following command:

```
RemoteCollectorConfigurator.exe "<Destination Historian>" "<Destination Historian username>"
"<Destination Historian password>" InterfaceCreateViaCmd "{ \"<parameter>\": \"<value>\",
\"<parameter>\": \"<value>\"}"
```

If you want to use a JSON file containing the installation parameters and values, run the following command:

```
RemoteCollectorConfigurator.exe "<Destination Historian>" "<Destination Historian username>"
"<Destination Historian password>" InterfaceCreateViaFile "<path to the JSON file>"
```

Instead of manually creating the JSON file, you can use the RemoteCollectorConfigurator utility to [generate it automatically \(on page 796\)](#).

If ih security groups are available, you must enter the Windows username and password of the destination Historian. If you have enabled the **Enforce Strict Collector Authentication**

option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

For information on the parameters, refer to [Collector Instance Parameters \(on page 801\)](#).

The collector instance is added.

Specify the tags whose data you want to collect using the collector. For the CollectorDestination parameter:

- If you have entered Historian, access Historian Administrator, and manage the tag configuration. For information, refer to [About Tags \(on page 659\)](#).
- If you not entered a value, modify the offline configuration file of the collector. By default, this file is available in the following location: `<installation folder of Historian>\GE Digital \<collector name>`. For information, refer to [Creating Offline Configuration XML file \(on page 2040\)](#).

Modify a Collector Instance

[Stop the collector \(on page 1340\)](#) whose instance you want to modify.

This topic describes how to modify the destination details of a collector instance using the RemoteCollectorConfigurator utility. You can also [modify a collector instance using Configuration Hub \(on page 634\)](#).

1. If you want to use the Command Prompt window:

a. Run the RemoteCollectorConfigurator.exe file. By default, it is located in the following folder: `C:\Program Files\GE Digital \NonWebCollectorInstantiationTool`.

b. If you want to manually enter the installation parameters and values, run the following command:

```
RemoteCollectorConfigurator.exe "<Destination Historian>" "<Destination Historian username>"
"<Destination Historian password>" InterfaceEditDestinationViaCmd "{\"<parameter>\":\"<value>\",
\"<parameter>\":\"<value>\"}"
```

If you want to use a JSON file containing the installation parameters and values, run the following command:

```
RemoteCollectorConfigurator.exe "<Destination Historian>" "<Destination Historian username>"
"<Destination Historian password>" InterfaceEditDestinationViaFile "<path to the JSON file>"
```

Instead of manually creating the JSON file, you can use the RemoteCollectorConfigurator utility to [generate it automatically \(on page 796\)](#).

You can leave the Historian username and password blank if there are no Historian security user groups.

For information on the parameters, refer to [Collector Instance Parameters \(on page 801\)](#).

2. If you want to use an interactive UI:

- a. Run the RemoteCollectorConfigurator.exe file. By default, it is located in the following folder: C:\Program Files\GE Digital\NonWebCollectorInstantiationTool.
A list of options to manage collector instances appears.
- b. Connect to the collector machine by entering 1 or 2, depending on whether collectors are installed locally or on a remote machine.
- c. Enter 6.
You are prompted to choose between entering the installation parameters manually and providing a JSON file.
- d. If you want to manually enter the parameters and values, enter 1, and then run the following command:

```
{ "<parameter>": "<value>", "<parameter>": "<value>" }
```

If you want to use a JSON file containing the installation parameters and values, enter 2, and then enter the path to the JSON file that you have created. Instead of manually creating the JSON file, you can use the RemoteCollectorConfigurator utility to [generate it automatically \(on page 796\)](#).

You can leave the Historian username and password blank if there are no Historian security user groups.

For information on the parameters, refer to [Collector Instance Parameters \(on page 801\)](#).

The destination of the collector instance is modified.

Collector Instance Parameters

This topic provides a list of the parameters that you must provide when you add or modify a collector instance.

Table 56. Destination: Historian

Parameter	Description
CollectorDestination	<p>The type of the configuration to specify the tags whose data you want to collect.</p> <ul style="list-style-type: none"> • If you want to use Historian Administrator to specify the tags for data collection, enter <code>Historian</code>. For information, refer to About Tags (on page 659). • If you want to specify the tags using an offline tag configuration file, do not enter a value. By default, this file is available in the following location: <code><installation folder of Historian>\GE Digital\<collector name></code>. For information, refer to Creating Offline Configuration XML file (on page 2040).
winUserName	<p>The username to connect to the machine on which Historian Administrator is installed. A value is required only if:</p> <ul style="list-style-type: none"> • You want to use Historian Administrator to specify the tags for data collection. • Historian security groups are used. • The mode is set to 2.
winPassword	<p>The password to connect to the machine on which Historian Administrator is installed. A value is required only if:</p>

Table 56. Destination: Historian (continued)

Parameter	Description
	<ul style="list-style-type: none"> • You want to use Historian Administrator to specify the tags for data collection. • Historian security groups are used. • The mode is set to 2.
CollectorSystemName	The name of the machine on which you have installed the collectors. A value is required.
InterfaceName	<p>The interface name of the collector instance. A value is required and must be unique per destination. The following characters are not allowed in the interface name:</p> <ul style="list-style-type: none"> • < (less than) • > (greater than) • : (colon) • " (double quote) • / (forward slash) • \ (backslash) • (vertical bar or pipe) • ? (question mark) • * (asterisk)
InterfaceDescription	The description of the collector instance.
InterfaceSubType	The subtype of the collector. For information, refer to Collector Type and Subtype (on page 1339) .
Type	The type of the collector. For information, refer to Collector Type and Subtype (on page 1339) . A value is required.
DataPathDirectory	The folder in which you want to store the collector log files. If you do not enter a value, by default, C:\Proficiency Historian Data is considered.
mode	Identifies whether creating the collector instance requires a specific user account credentials. Enter one of the following values:

Table 56. Destination: Historian (continued)

Parameter	Description
	<ul style="list-style-type: none"> • 1: Creates the collector instance with the credentials of the local user. • 2: Creates the collector instance with the credentials of a specific user. If you choose this mode, you must enter values for the winUserName and winPassword parameters.

Installation parameters for an iFIX collector to send data to Historian

```

{
    "mode": 2,
    "CollectorSystemName": "<host name>",
    "InterfaceDescription": "iFIX collector for unit 1",
    "DataPathDirectory": "C:\\\\Proficy Historian Data",
    "CollectorDestination": "Historian",
    "winUserName": "<host name>\\<user name>",
    "winPassword": "<password>",
    "InterfaceSubType": "",
    "DestinationHistorianUserName": "<user name>",
    "DestinationHistorianPassword": "<password>",
    "DestinationHistorian": "<host name>",
    "General1": "",
    "General2": "",
    "General3": "FIX",
    "General4": "",
    "General5": "",
    "Type": 1,
    "InterfaceName": "collector_unique_name"
}

```

Table 57. Destination: Predix TimeSeries

Parameter	Description
ClientID	The collector when interacting with Predix Time Series. This is equivalent to the username in many authentication schemes. The client must exist in

Table 57. Destination: Predix TimeSeries (continued)

Parameter	Description
	the Proficy Authentication instance identified by the identity issuer, and the system requires that the <code>timeseries.zones. {ZoneId}.ingest</code> and <code>timeseries.zones. {ZoneId}.query</code> authorities are granted access to the client for the Predix Zone ID specified. Your Predix Time Series administrator can provide this information.
ClientSecret	The secret to authenticate the collector. This is equivalent to the password in many authentication schemes.
CloudDestinationAddress	The URL of a data streaming endpoint exposed by the Predix Time Series instance to which you want to send data. Typically, it starts with "wss://". This value is used as part of the interface name and default tag prefix of the collector. Your Predix Time Series administrator can provide this URL.
CollectorDestination	The type of the cloud destination. For Predix TimeSeries, enter <code>Predix</code> .
CollectorSystemName	The name of the machine on which you have installed the collectors. A value is required.
DataPathDirectory	The folder in which you want to store the collector log files. If you do not enter a value, by default, <code>C:\Proficy Historian Data</code> is considered.
DatapointAttribute<number>	The attributes for each data point whose values you want the collector to collect. You can specify maximum five attributes.
IdentityIssuer	The URL of an authentication endpoint for the collector to authenticate itself and acquire necessary credentials to stream to the Predix Time Series. In other words, this is the issuer ID of the Proficy Authentication instance that you want to use to con-

Table 57. Destination: Predix TimeSeries (continued)

Parameter	Description
	nect to Predix Time Series. Typically, it starts with https:// and ends with "/oauth/token".
InterfaceName	<p>The interface name of the collector instance. A value is required and must be unique per destination. The following characters are not allowed in the interface name:</p> <ul style="list-style-type: none"> • < (less than) • > (greater than) • : (colon) • " (double quote) • / (forward slash) • \ (backslash) • (vertical bar or pipe) • ? (question mark) • * (asterisk)
InterfaceDescription	The description of the collector instance.
InterfaceSubType	The subtype of the collector. For information, refer to Collector Type and Subtype (on page 1339) .
Proxy	Identifies the URL of the proxy server to be used for both the authentication process and for sending data. If the collector is running on a network where proxy servers are used to access web resources outside of the network, then you must provide the proxy server settings. However, it does not affect the proxy server used by Windows when establishing secure connections. As a result, you must still configure the proxy settings for the Windows user account under which the collector service runs.
ProxyUserName	The username to connect to the proxy server.
ProxyPassword	The password to connect to the proxy server.

Table 57. Destination: Predix TimeSeries (continued)

Parameter	Description
Type	The type of the collector. For information, refer to Collector Type and Subtype (on page 1339) . A value is required.
ZoneID	Unique identifier of the instance to which the collector will send data.
winUserName	<p>The username to connect to the machine on which Historian Administrator is installed. A value is required only if:</p> <ul style="list-style-type: none"> • You want to use Historian Administrator to specify the tags for data collection. • Historian security groups are used. • The mode is set to 2.
winPassword	<p>The password to connect to the machine on which Historian Administrator is installed. A value is required only if:</p> <ul style="list-style-type: none"> • You want to use Historian Administrator to specify the tags for data collection. • Historian security groups are used. • The mode is set to 2.
mode	<p>Identifies whether creating the collector instance requires a specific user account credentials. Enter one of the following values:</p> <ul style="list-style-type: none"> • 1: Creates the collector instance with the credentials of the local user. • 2: Creates the collector instance with the credentials of a specific user. If you choose this mode, you must enter values for the winUserName and winPassword parameters.

Installation parameters for an iFIX collector to send data to Predix TimeSeries

```
{  
  
    "ClientID": "HistQA",  
  
    "ClientSecret": "1234",  
  
    "CloudDestinationAddress": "wss://abcd.run.123.predix.io/v1/stream/messages",  
  
    "CollectorDestination": "Predix",  
  
    "CollectorSystemName": "<host name>",  
  
    "DataPathDirectory": "C:\\\\Proficy Historian Data",  
  
    "DatapointAttribute1": "\\site\\\\"site_1\\",  
  
    "DatapointAttribute2": "",  
  
    "DatapointAttribute3": "",  
  
    "DatapointAttribute4": "",  
  
    "DatapointAttribute5": "",  
  
    "DestinationHistorian": "<host name>",  
  
    "General1": "",  
  
    "General2": "",  
  
    "General3": "abc",  
  
    "General4": "",  
  
    "General5": "",  
  
    "IdentityIssuer": "https://1234567.predix-uaa.run.aws-usw02-pr.ice.predix.io/oauth/token",  
  
    "InterfaceDescription": "1234",  
  
    "InterfaceName": "123",  
  
    "InterfaceSubType": "",  
  
    "Proxy": "http://<host name>:<port number>",  
  
    "ProxyPassword": "",  
  
    "ProxyUserName": "",  
  
    "Type": 1,  
  
    "ZoneID": "123-456-789de-rft",  
  
    "winPassword": "",  
  
    "winUserName": "",  
  
    "mode": 1  
  
}
```

Table 58. Destination: MQTT

Parameter	Description
ClientID	The name of the MQTT client. A value is required and must be unique for an MQTT broker.
CollectorDestination	The type of the cloud destination. For MQTT, enter MQTT.
CollectorSystemName	The name of the machine on which you have installed the collectors. A value is required.
DataPathDirectory	The folder in which you want to store the collector log files. If you do not enter a value, by default, C:\Proficy Historian Data is considered.
DeviceSharedKey	The device shared key of the MQTT broker.
HostAddress	The host name of the MQTT broker to which you want the collector to send data. A value is required.
HostPort	The port number to connect to the MQTT broker to which you want the collector to send data.
InterfaceName	<p>The interface name of the collector instance. A value is required and must be unique per destination. The following characters are not allowed in the interface name:</p> <ul style="list-style-type: none"> • < (less than) • > (greater than) • : (colon) • " (double quote) • / (forward slash) • \ (backslash) • (vertical bar or pipe) • ? (question mark) • * (asterisk)
InterfaceDescription	The description of the collector instance.
InterfaceSubType	The subtype of the collector. For information, refer to Collector Type and Subtype (on page 1339) .

Table 58. Destination: MQTT (continued)

Parameter	Description
MQTTAutoRefresh	Indicates that the password is automatically generated on expiry; you are not required to provide the password.
MQTTCloudSubtype	The subtype of the MQTT broker.
MQTTUserName	Enter the username to connect to the MQTT broker.
MQTTPassword	Enter the password to connect to the MQTT broker.
Topic	The MQTT topic to which you want the collector to publish data.
Type	The type of the collector. For information, refer to Collector Type and Subtype (on page 1339) . A value is required.
winUserName	<p>The username to connect to the machine on which Historian Administrator is installed. A value is required only if:</p> <ul style="list-style-type: none"> • You want to use Historian Administrator to specify the tags for data collection. • Historian security groups are used. • The mode is set to 2.
winPassword	<p>The password to connect to the machine on which Historian Administrator is installed. A value is required only if:</p> <ul style="list-style-type: none"> • You want to use Historian Administrator to specify the tags for data collection. • Historian security groups are used. • The mode is set to 2.
mode	Identifies whether creating the collector instance requires a specific user account credentials. Enter one of the following values:

Table 58. Destination: MQTT (continued)

Parameter	Description
	<ul style="list-style-type: none"> • 1: Creates the collector instance with the credentials of the local user. • 2: Creates the collector instance with the credentials of a specific user. If you choose this mode, you must enter values for the winUserName and winPassword parameters.

**Tip:**

To establish an MQTT connection with Alibaba Cloud, refer to <https://www.alibabacloud.com/help/doc-detail/73742.htm>. To generate a password to connect to Alibaba Cloud, use the utility located [here](#).

Installation parameters for an iFIX collector to send data to Google Cloud

```
{
  "InterfaceName": "<unique collector name>",
  "InterfaceDescription": "collector for unit 3",
  "Type": 1,
  "mode": 2,
  "CollectorSystemName": "<host name>",
  "DataPathDirectory": "C:\\\\Proficy Historian Data",
  "CollectorDestination": "MQTT",
  "HostAddress": "mqtt.googleapis.com",
  "HostPort": "8883",
  "ClientID": "projects/mygcpproject/locations/asia-east1/registries/testmqttgcpilot/devices/testdevice",
  "Topic": "/devices/gcptesting/events",
  "DeviceSharedKey": "",
  "MQTTCloudSubtype": "GOOGLE",
  "MQTTUserName": "testusername",
  "MQTTPassword": "testGoogleConnectiionstringPassword",
  "MQTTAutoRefresh": "NO",
  "MQTTCAFile": "",
  "MQTTCertificateFile": "",
  "MQTTPrivateKeyFile": "",
  "MQTTPublicKeyFile": ""
}
```

```

"winUserName": "<host name>\\Admin",
"winPassword": "<password>",
"InterfaceSubType": "",
"DestinationHistorianUserName": "<Windows user name of the destination>",
"DestinationHistorianPassword": "<Windows password of the destination>",
"DestinationHistorian": "<host name>",
"General1": "",
"General2": "",
"General3": "FIX",
"General4": "",
"General5": ""
}

```

Table 59. Destination: Azure IoT Hub

Parameter	Description
CollectorDestination	The type of the cloud destination. For Azure IoT Hub, enter <i>Azure</i> .
CollectorSystemName	The name of the machine on which you have installed the collectors. A value is required.
DataPathDirectory	The folder in which you want to store the collector log files. If you do not enter a value, by default, C:\Proficiency Historian Data is considered.
DeviceConnectionString	Identifies the Azure IoT device to which you want to send data. Enter a value in the following format: HostName=<value>;DeviceId=<value>;SharedAccessKey=<value>
DeviceId	The ID of the Azure IoT device.
SharedAccessKey	The shared access key of the device.
InterfaceName	The interface name of the collector instance. A value is required and must be unique per destination. The following characters are not allowed in the interface name: <ul style="list-style-type: none"> • < (less than) • > (greater than)

Table 59. Destination: Azure IoT Hub (continued)

Parameter	Description
	<ul style="list-style-type: none"> • : (colon) • " (double quote) • / (forward slash) • \ (backslash) • (vertical bar or pipe) • ? (question mark) • * (asterisk)
InterfaceDescription	The description of the interface.
InterfaceSubType	The subtype of the collector. For information, refer to Collector Type and Subtype (on page 1339) .
Proxy	Identifies the URL of the proxy server to be used for both the authentication process and for sending data. If the collector is running on a network where proxy servers are used to access web resources outside of the network, then you must provide the proxy server settings. However, it does not affect the proxy server used by Windows when establishing secure connections. As a result, you must still configure the proxy settings for the Windows user account under which the collector service runs.
ProxyUserName	The username to connect to the proxy server.
ProxyPassword	The password to connect to the proxy server.
TransportProtocol	<p>The protocol that you want to use to send data to Azure IoT Hub. Enter one of the following values:</p> <ul style="list-style-type: none"> • HTTP • MQTT • AMQP • MQTT_OVER_WEBSOCKETS • AMQP_OVER_WEBSOCKETS

Table 59. Destination: Azure IoT Hub (continued)

Parameter	Description
	For information on which protocol to use, refer to Protocols and Port Numbers (on page 626) .
Type	The type of the collector. For information, refer to Collector Type and Subtype (on page 1339) . A value is required.
winUserName	<p>The username to connect to the machine on which Historian Administrator is installed. A value is required only if:</p> <ul style="list-style-type: none"> • You want to use Historian Administrator to specify the tags for data collection. • Historian security groups are used. • The mode is set to 2.
winPassword	<p>The password to connect to the machine on which Historian Administrator is installed. A value is required only if:</p> <ul style="list-style-type: none"> • You want to use Historian Administrator to specify the tags for data collection. • Historian security groups are used. • The mode is set to 2.
mode	<p>Identifies whether creating the collector instance requires a specific user account credentials. Enter one of the following values:</p> <ul style="list-style-type: none"> • 1: Creates the collector instance with the credentials of the local user. • 2: Creates the collector instance with the credentials of a specific user. If you choose this mode, you must enter values for the winUserName and winPassword parameters.

Installation parameters for an iFIX collector to send data to Azure IoT Hub

```
{
    "InterfaceName": "collector_unique_name",
    "InterfaceDescription": "iFIX collector for unit 2",
    "Type": 1,
    "mode": 2,
    "CollectorSystemName": "<host name>",
    "DataPathDirectory": "C:\\\\Proficy Historian Data",
    "CollectorDestination": "Azure",
    "DeviceConnectionString": "HostName=abc.azure-devices.net;DeviceId=Device1;SharedAccessKey=xxxxxxxxxx",
    "TransportProtocol": "AMQP_OVER_WEBSOCKETS",
    "Proxy": "<host name>:<port number>",
    "ProxyUserName": "",
    "ProxyPassword": "",
    "winUserName": "<host name>\\\\<user name>",
    "winPassword": "<password>",
    "InterfaceSubType": "",
    "DestinationHistorianUserName": "<user name>",
    "DestinationHistorianPassword": "<password>",
    "DestinationHistorian": "<host name>",
    "General1": "",
    "General2": "",
    "General3": "FIX",
    "General4": "",
    "General5": ""
}
```

General Parameters of a Collector

This topic provides a list of general parameters that are applicable to each type of collector.

Collector Type	Applicable General Parameters
The Calculation collector	<ul style="list-style-type: none"> • General1 - optional. Used for calculation timeout (sec). Default value: 10. • General2 - optional. Used for Max Recovery Time (hr). Default value: 4

Collector Type	Applicable General Parameters
The CygNet collector	<ul style="list-style-type: none"> • General2 - optional. Used for recovery time (hr). Default value: 0 • General3 - optional. Used for thread count. Default value: 5 • General4 - optional. Used for the Cygnet debug mode. Default value: 0 • General5 - optional. Used for optimization. Default value: 1
The iFIX Alarms and Events collector	General1 - optional. Used for ProgId. Default value: Proficy.OPCiFIXAE.1
The iFIX collector	<ul style="list-style-type: none"> • General3 - optional • General4 - optional. Used for blocks and fields for blocks. Default value: AI:F_CV,B_CUALM
The MQTT collector	<ul style="list-style-type: none"> • General1 - required. Used for the source host name. • General2 - required. Used for the source topic. • General3 - required. Used for the source port.
The ODBC collector	<ul style="list-style-type: none"> • General1 - required. Used for the ODBC server. • General2 - required. Used for the ODBC username. • General3 - required. Used for the ODBC password. • General4 - optional. Used for recovery time (hr). Default value: 0. • General5 - optional. Used for throttle (milliseconds). Default value: 100
The OPC Classic Alarms and Events collector	General1 - required. Used for the OPC source server progID.

Collector Type	Applicable General Parameters
The OPC Classic DA collector	General1 - required. Used for the OPC source server progID.
The OPC Classic HDA collector	<ul style="list-style-type: none"> • General1 - required. Used for the OPC HDA server. • General2 - optional. Used for recovery time (hr). Default value: 24
The OPC UA DA collector	<ul style="list-style-type: none"> • General1 - required. Used for the OPC UA server URI. • General2 - optional. Used for secured connectivity. Default value: false • General3 - optional. Used to enable user security. Default value: false • General4 - optional. Used for username when security is enabled. <p>General5 - optional. Used for password when security is enabled.</p>
The OSI PI collector	<ul style="list-style-type: none"> • General1 - required. Used for the OSI PI server name. • General2 - optional. Used for the OSI PI username. Default value: piadmin • General3 - optional. Used for the OSI PI password. • General4 - optional. Used for max recovery time (hr). Default value: 4 • General5 - optional. Used for the OSI PI source (archive or snapshot). Default value: Archive.
The OSI PI distributor	<ul style="list-style-type: none"> • General1 - optional. Used for the OSI PI server. <p>General2 - optional. Used for the OSI PI username. Default value: piadmin</p> <ul style="list-style-type: none"> • General3 - optional. Used for the OSI PI password.

Collector Type	Applicable General Parameters
	<ul style="list-style-type: none"> • General4 - optional. Used for max recovery time (hr). Default value: 4 • General5 - optional. Used for the OSI PI source (archive or snapshot). Default value: Archive.
The Python Collector	<ul style="list-style-type: none"> • General1 - optional. Used for calculation timeout (sec). Default value: 10 • General2 - optional. Used for max recovery time (hr). Default value: 4
The Server-to-Server distributor	<ul style="list-style-type: none"> • General1 - optional. Used for calculation timeout (sec). Default value: 10 • General2 - optional. Used for max recovery time (hr). Default value: 4 • General3 - required. Used for the source server name • General4 - optional. Used for message replication (0 or 1) and alarm replication (0 or 1). Enter 0 or 1 only for alarm replication. • General5 - optional. Used for prefix to messages.
The Windows Performance collector	None
The Wonderware collector	<ul style="list-style-type: none"> • General1 - required. Used for the Wonderware server. • General2 - required. Used for the Wonderware username. • General3 - required. Used for the Wonderware password. • General4 - optional. Used for the recovery time (hr). Default value: 0 • General5 - optional. Used for Throttle (milliseconds). Default value: 100

Delete a Collector Instance

Stop the collector ([on page 1340](#)) whose instance you want to delete.

If you no longer want to use a collector instance to collect data, you can delete it. When you delete a collector instance, the Windows service for the collector, the Registry folder, and the buffer files are deleted as well.

This topic describes how to delete a collector instance using the RemoteCollectorConfigurator utility. You can also [delete a collector instance using Configuration Hub \(on page 654\)](#). If you want to delete an offline collector, refer to [Delete an Offline Collector Instance \(on page 819\)](#).

1. If you want to use the Command Prompt window:

- a. Access the installation location of the RemoteCollectorConfigurator utility. By default, it is

```
C:\Program Files\GE Digital\NonWebCollectorInstantiationTool.
```

- b. Run the following command:

```
RemoteCollectorConfigurator.exe "<Destination Historian>" "<Destination Historian username>"  
"<Destination Historian password>" InterfaceDelete <interface name> ShouldDeleteTags[<0 or 1>]
```

You can leave the Historian username and password blank if there are no Historian security user groups.

2. If you want to use an interactive UI:

- a. Run the RemoteCollectorConfigurator.exe file. By default, it is

```
located in the following folder: C:\Program Files\GE Digital  
\NonWebCollectorInstantiationTool.
```

A list of options to manage collector instances appears.

- b. Connect to the collector machine by entering 1 or 2, depending on whether collectors are installed locally or on a remote machine.

- c. Enter 5.

You are prompted to enter the interface name of the collector whose instance you want to delete.

- d. Enter the interface name of the collector that you want to delete.

You are prompted to specify whether you want to delete the tag data as well.

- e. Enter 1 if you want to delete the tag data as well, or enter 0.

The collector instance is deleted.

Add an Offline Collector Instance

You can use an offline collector to send data directly to a cloud destination (without using a Historian server).

1. Access the installation folder of `ihCollectorManager_x64.exe`. By default, it is `C:\Program Files\GE Digital\Historian Remote Management Agents\Collector Manager`.
2. If you want to manually enter the installation parameters and values, run the following command:

```
ihCollectorManager_x64.exe InterfaceCreateViaCmd "{\"<parameter>\": \"<value>\",
\"<parameter>\": \"<value>\"}"
```

If you want to use a JSON file containing the installation parameters and values, run the following command:

```
ihCollectorManager_x64.exe InterfaceCreateViaFile "<path to the JSON file>"
```

Instead of manually creating the JSON file, you can use the `RemoteCollectorConfigurator` utility to [generate it automatically \(on page 796\)](#).

For information on the parameters, refer to [Collector Instance Parameters \(on page 801\)](#).

Delete an Offline Collector Instance

This topic describes how to delete an offline collector instance using the `RemoteCollectorConfigurator` utility.



Note:

When you delete an offline collector instance, the corresponding configuration file is not deleted. However, if another collector instance of the same interface name is created, the existing configuration file is replaced by a template configuration file.

1. Access the installation folder of `ihCollectorManager_x64.exe`. By default, it is `C:\Program Files\GE Digital\Historian Remote Management Agents\Collector Manager`.
2. Run the `ihCollectorManager_x64.exe` file.
3. Run the following command:

```
ihCollectorManager_x64.exe InterfaceDelete <interface name>
```

Manage a Collector Remotely

1. Ensure that the Historian server connected to the collectors that you want to manage is upgraded to Historian 8.1.
2. [Install Remote Management Agents \(on page 187\)](#).



Note:

Remote Collector Management will be installed as part of this installation.

3. Ensure that the Windows Task Scheduler service is running. This service is required to manage collectors in the command line mode. You can check the status of this service in the Microsoft Services Management console.
4. If you want to manage the iFIX collectors remotely, access the **SCU - FIX** window, and modify the task configuration such that the value in the **Command Line** field is **NOSERVICE**.

Perform any of the following tasks using Configuration Hub:

- [Start \(on page 637\)](#), [stop \(on page 638\)](#), or [restart \(on page 639\)](#) a collector.
- [Pause \(on page 641\)](#) or [resume \(on page 642\)](#) the data collection of a collector.
- [Delete \(on page 643\)](#) or [move \(on page 644\)](#) the buffer files of a collector.
- [Change the destination server of a collector \(on page 645\)](#).



Note:

You can also perform these tasks using [REST APIs \(on page 1254\)](#).

Troubleshooting Remote Collector Management Issues

Remote Collector Management does not work

Issue: If an iFIX collector instance created in version 9.0 exists, after you upgrade collectors, another instance of the iFIX collector is created. Because of this, the Remote Collector Manager (RCM) will not work correctly. This is applicable to the iFIX Alarms and Events collector as well.

Workaround: If you want to use RCM, you must delete one of the instances. If needed, you can manually create another instance of the iFIX collector using Configuration Hub or the RemoteCollectorConfigurator utility.

The ServiceName Registry Key is not Updated

Issue: When you attempt to manage collectors, sometimes, an error message appears in the `CollectorManager.shw` file.

Error message: Below are collectors in the registry without a service name. The String Registry value 'ServiceName' exists, but is blank. Collector Manager will not try to determine what the service name is. This will need to be manually configured.

Cause: When Remote Collector Management is started for the first time, the collector that you want to manage is not running. When this happens, the ServiceName registry key is not updated.

Workaround:

1. Stop the Remote Collector Management service.
2. Start the collector.
3. Start the Remote Collector Management service.

The ServiceName Registry key is Updated Incorrectly

Workaround:

1. Stop the Remote Collector Management service.
2. Access the registry folder of the collector.
3. Delete the ServiceName key.
4. Start the collector.
5. Start the Remote Collector Management service.
6. Access the `.shw` file to verify that the ServiceName key has been updated.

Chapter 5. Using Historian Administrator

Historian Administrator

Overview of Historian Administrator

Historian Administrator is a Windows-based application, which allows you to access administrative functions. Using Historian Administrator, you can monitor, supervise, archive, retrieve, and control data gathering functions from the server, a client, or one or more remote non-web-based nodes.

**Note:**

You can install multiple instances of Historian Administrator. Changes that you make to parameters on one instance are not automatically updated in other instances.

Historian Administrator communicates with the Historian server using the Historian API. You can install Historian Administrator on a local or a remote machine that has a TCP/IP connection to the Historian server.

Intended Audience

This guide is intended for people who need to:

- Retrieve and analyze archived information.
- Monitor Historian system performance.
- Set up and maintain configuration and other parameters for tags, collectors, and archives.
- Perform specific supervisory and security tasks for Historian.
- Maintain and troubleshoot Historian.

About Historian Administrator

Using Historian Administrator, you can:

- Examine key operating statistics for archives and collectors, and display or search system alerts and messages.
- Perform archive maintenance, including:
 - Setting archive size.
 - Selecting options and parameters.
 - Accessing security parameters.

- Adding and restoring archives.
- Performing backup and restoration tasks
- Perform tag maintenance, including:
 - Adding, deleting, and copying tags.
 - Searching for tags in a data source or in the Historian database.
 - Starting and stopping data collection for a tag.
 - Configuring, displaying, and editing tag parameters and options.
 - Displaying trend data for selected tags.
- Perform collector maintenance, including:
 - Adding or deleting collectors.
 - Configuring, displaying, and editing parameters for all types of collectors.
 - Creating calculation formulas.
 - Displaying performance trends for selected collectors.

Limitations

If the number of archives is large (that is, more than 5,000), Historian Administrator takes a long time to start.

Access Historian Administrator

- Install Historian Administrator (by installing Client Tools).
- Create a Windows user on the Historian server.
- Use a page with a resolution of 1024 x 768 or above.

From the Start menu, select **Historian Administrator**.



Note:

By default, The system attempts to connect to the default server using the username and password of the currently logged-in user. If you want to use a different server or user account:

- a. Select **Main**.

A login window appears.

- b. Provide the server name, username, password, and domain information, and then select **OK**.

The **Proficy Historian Administrator** window appears, displaying the following pages.

- **System Statistics:** Contains system status indicators, data collector performance indicators, system alerts and messages, with links to the data store maintenance, collector maintenance, tag maintenance, message search, and help pages.
- **Main:** Allows you to log in to a different Historian Server.
- **Tags:** Contains tag names, parameters, and controls.
- **Collectors:** Contains collector names, parameters, and controls.
- **DataStores:** Contains archive names, parameters, alarms, security, and controls.
- **Messages:** Contains alerts and messages selected by user-defined search parameters.

Historian in a Regulated Environment

Many FDA-regulated industries are required by the United States government to be compliant with regulations such as the [21CFR Part 11](#) regulation. If your industry is one of them, you will need software that allows you to build a compliant application or process. The flexibility and versatility of Historian lets you create a compliant process by:

- Providing limited system access to authorized individuals.
- Adding a timestamp to annotations, and displaying timestamps from the Historian archive.
- Requiring electronic signatures on annotations.



Note:

This option is available if the **Electronic Signatures/Records** option is enabled in the Historian Server.

- Supporting human-readable printouts and computer-readable format for audits (by exporting data to a CSV file that can be imported to a Microsoft Excel document or an SQL database).

Disabling Guest Accounts for a 21 CFR Part 11-Compliant Environment

If you want to use Historian in a 21 CFR Part 11-compliant environment, make sure that you disable guest accounts on your computer. This action applies whether or not you use Historian security.

Compliant Parameter Settings

You can set the following 21 CFR 11-compliant parameters in the **Security** section of the **Data Store** page.

Field	Description
Require Point Verification	Indicates whether you must enter identifying information whenever you attempt a restricted action. Whenever you attempt to change the system con-

Field	Description
	<p>figuration (for the tag, archive, or collector), a tag value, or another record, you must electronically sign the action with a username and password. If the user is authorized to make this change, the identity of the person, the action performed, and the time it was performed, are all recorded in the audit trail.</p> <div data-bbox="511 472 1421 850" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <ul style="list-style-type: none"> The audit features are not dependent on this feature being enabled. Historian audits all user actions regardless of whether this option is enabled. If you plan to create multiple archives at the same time, select the Disabled option. </div> <p>Enabling electronic signatures and electronic records also requires you to reverify your identity when you use the Historian Excel Add-in, modify or create a tag, or import data or messages.</p> <div data-bbox="511 1050 1421 1228" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <p>This feature is available only if you have purchased the Electronic Signatures and Electronic Records option.</p> </div>
Verification Message	When point verification is enabled, you are prompted to enter the username and password whenever you attempt to perform an action specified as requiring point verification.

High Availability

About High Availability

Historian supports high availability of the Historian server, archive files and configuration files. To facilitate this support, Historian uses Microsoft Cluster Server (MSCS) as well as an automated backup strategy. High availability decreases the likelihood of archive file corruption due to software or hardware failures. Implementing high availability ensures that collection of your data remains uninterrupted.

How it Works

If the primary Historian server fails due to software or hardware issues, MSCS replaces it with another Historian server. In addition, through the use of automated backups to a shared location, at least one known good Historian archive is maintained at all times. Older archives are replaced once per hour only if there is a more recent archive in place.

To provide high availability of Historian server for Client Manager, Configuration Manager, and Diagnostics Manager components of the distributed Historian service using Microsoft Failover Cluster Service, you must configure them as generic services in Failover Cluster. For information, refer to Microsoft documentation.

High availability is achieved by following these steps:

1. Every 5 seconds, MSCS monitors the health of all services and applications it is managing by performing a quick check of whether each service is in a running state.
2. Every 60 seconds, MSCS performs a more thorough test of the applications' health.
3. Server high availability logs are added to the server and queried.
4. If these steps fail, Historian assumes the server is no longer running, which causes the cluster to initiate failover of the application.



Note:

By default, MSCS monitors the health of all the services and applications every 5 seconds and 60 seconds. You can change this frequency using the cluster administrator.

For most failures, the cluster will detect a problem within 5 seconds of an application or service becoming unresponsive. In the case of a server hang, where the server process is still running but is otherwise unresponsive, it may take as many as 60 seconds to detect. The time to switch to another Historian server includes the time required for the cluster to re-start the Historian server. Server start-up time depends on the size and number of online archives.

Limitations

- Only a single Historian resource instance is supported per cluster.
- The Historian installation automatically registers Historian and AlarmArchiver resources with MSCS.
- Configuring an AlarmArchiver resource on MSCS requires a dependency on a Historian resource.

- Running collectors on a cluster is not recommended, as they are not supported on the cluster server. Therefore, failover cannot be performed if a cluster node goes offline. Historian offers a separate collector high availability feature.
- Historian local security with local users is not supported in cluster nodes.

High Availability of Archive and Configuration Files

Historian supports high availability of the latest archive (.iha) and configuration (.ihc) files. A copy of the latest .iha and .ihc file is created once every hour. If the latest archive files become corrupt, Historian will restore the files.

The following conditions apply when using this feature:

- Archive files are backed up only for tag data, not for alarms and events data.
- When using a cluster, this feature is automatically enabled; you cannot disable it.
- By default, this feature is disabled on a 64-bit Windows operating system.
- When you enable this feature, backup of all the current archive files is created. This will increase your storage overhead to twice that of the current archive. Therefore, for better performance, we recommend that you do not use this feature for a large-scale system.

Enable High Availability of Archive and Configuration Files

1. Install Historian on each node of the cluster. A hardware license key is required for each node of the cluster.
2. Configure a Historian resource on MSCS as follows:
 - Allow client access to the IP address and network name of the Historian server.
 - Ensure that a shared storage device or location is available to all the Historian cluster nodes in order to store the Historian archive files.
3. After you configure the components of the failover cluster, when configuring Client Manager, Configuration Manager and Diagnostics Manager, enable the **Use Network Name for Computer Name** option on the **General** section of the resource's properties.

1. Access Historian Administrator.
2. Select **Archives > Global Options**.
3. In the **Archive Maintenance** field, select the **Maintain Auto Recovery Backup Files** option.

Register Historian with a Windows 2012 Cluster

Before using later versions of Historian on Windows 2012 Cluster, you must register the `Historian.dll` file using PowerShell.

1. Open PowerShell in a Command prompt.
2. Enter the following command to register Data Archiver with the Cluster:

```
Add-clusterresourcetype Historian "C:\ProgramFiles\Proficy\Historian\x64\Server  
\Historian.dll" -DisplayName
```

3. Enter the following command to register AlarmArchiver with the Cluster:


```
Add-clusterresourcetype AlarmArchiver "C:\Program Files\Proficy\Historian\x64\Server  
\Historian.dll" -DisplayName
```

Historian Administrator - Pages

The Main Page

The **Main** page of Historian Administrator displays the system statistics, which contains the current system status and performance statistics. It provides an overall view of the system health. The page has the following sections:

- The **System Statistics** section (*on page 829*)
- The **Collectors** section (*on page 833*)
- The **Alerts** section (*on page 835*)



The System Statistics Section

The following table describes the fields in the **System Statistics** section.



Note:

The statistics displayed in this section are calculated independently on various time scales and schedules. As a result, they may be updated at different times.

Field	Description
Receive Rate (a time-based chart in events/minute)	Displays how busy the server is at a given instance and the rate at which the server is receiving data from collectors.
Archive Compression (% compression)	Displays the current effect of archive data compression. If the value is zero, it indicates that archive compression is either ineffective or turned off. To increase the effect of data compression, increase the value of archive compression deadbands on individual tags in the Tag Maintenance section to activate compression.

Field	Description
	<p>In calculating the effect of archive compression, Historian counts internal system tags as well as data source tags. Therefore, when working with a very small number of tags and with compression disabled on data source tags, this field may indicate a value other than zero. If you use a realistic number of tags, however, system tags will constitute a very small percentage of total tags and will therefore not cause a significant error in calculating the effect of archive compression on the total system.</p>
Write Cache Hit	<p>Displays the hit ratio of the write cache in percentage of total writes. It is a measure of how efficiently the system is collecting data. Typically, this value should range from 95 to 99.99%. If the data is changing rapidly over a wide range, however, the hit percentage drops significantly because current values differ from recently cached values. More regular sampling may increase the hit percentage. Out-of-order data also reduces the hit ratio.</p>
Failed Writes	<p>Displays the number of samples that failed to be written. Since failed writes are a measure of system malfunctions or an indication of offline archive problems, this value should be zero. If you observe a non-zero value, investigate the cause of the problem and take corrective action.</p> <p>Historian also generates a message if a write fails. Note that the message only appears once per tag, for a succession of failed writes associated with that tag. For example, if the number displayed in this field is 20, but they all pertain to one Historian tag, you will only receive one message until that Historian tag is functional again.</p>
Messages Since Startup	<p>Displays a count of system messages generated since the last startup. The system resets the value to zero on restart. The message database, however, may contain more messages than this value.</p>
Alerts Since Startup	<p>Displays a count of system warnings or alerts generated since the last startup. A high value here may indicate a problem of some kind. You should review the alerts and determine the probable cause. The count resets to zero on restart. The message database, however, may contain more alerts than this value.</p>

Field	Description
Calculations	Displays the value Enabled if the Calculation collector is licensed on the software key.
Server-to-Server	Displays the value Enabled if the Server-to-Server collector is licensed on the software key.
Alarms since Startup	Displays a count of alarms received by the data archiver since starting up.
Server Memory	Displays how much of the server memory the data archiver consumes.
Free Space (MB)	Displays how much disk space (in MB) is left in the current archive.
Consumption Rate (MB/day)	Displays how fast the archive disk space is consumed. If the value is too high, you can reduce it by slowing the poll rate on selected tags or data points or by increasing the filtering on the data (widening the compression deadband to increase compression).
Est. Days to Full (Days)	<p>Displays how much time is left before the archive is full, based on the current consumption rate. This value is dynamically calculated by the server and becomes more accurate as an archive file gets closer to completion. This value is only an estimate and will vary based on a number of factors, including the current compression effectiveness. The System sends messages notifying you at 5, 3, and 1 days until full. After the archive is full, a new archive must be created (could be automatic).</p> <p>To increase this value, you must reduce the consumption rate. To ensure that collection is not interrupted, make sure that the Automatically Create Archives option is enabled in the Data Store Maintenance section (under Global Options). You may also want to enable the Overwrite Old Archives option if you have limited disk capacity. Enabling overwrite, however, means that some old data will be lost when new data overwrites the data in the oldest online archive. Use this feature only when necessary.</p>
Active Tags	Displays number of tags in your configuration.
Licensed Tags	Displays the number of tags authorized for this Historian installation by the software key and license.

Field	Description
	<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If this field displays 100 tags and the licensed users field displays 1 client, you are likely running in demonstration mode and may have incorrectly installed your hardware key. </div>
Active Users	Displays the number of users currently accessing the Historian system.
Licensed Users	<p>Displays the number of users authorized to access Historian using the software key and license.</p> <p>The number of users that are authorized to access Historian is strictly based on the software key and license. However, if you have utilized your available Client Access Licenses (CAL) and need an additional one to administer the system in an emergency, you have an option to reserve a CAL. This reserved CAL allows you to access the server. To do so, provide the reserved CAL to the system administrators and add them to the <code>ih Security Admins</code> group. A system administrator can then connect to Historian in an emergency.</p> <p>This facility is optional and does not provide a guaranteed connection. It only eliminates the emergency situations when a CAL is preventing you from accessing the system and may not work if there are other conditions. For example, if the Historian server is busy, you will not be able to connect using this feature.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If this field displays 1 client and the Licensed Tags field displays 100 tags, you are likely running in demonstration mode and you may have incorrectly installed your hardware key. </div>
Alarm Rate	Displays the rate at which Historian is receiving alarms and events data.
SCADA Tags	Displays the number of CIMPLICITY or iFIX tags.
Tags Consumed by Arrays	Indicates the total number of Array tags consumed by Historian.

The Collectors Section

The **Collectors** section shows current statistics on the operation of all the connected collectors in the system. In this section, you can:

- Access the **Collector Maintenance** page of a collector by selecting the collector name. You can also access the **Collector Maintenance** page by selecting the collector link at the beginning of the **System Statistics** section.
- Automatically refresh the data every 45 seconds by selecting the **Auto** check box.
- Manually refresh the data by selecting **Refresh**.

The following table describes the fields in the **Collectors** section.

Field	Description
Collector	Displays the collector ID, which is used to identify the collector in Historian.
Status	Displays the current status of collection. This field contains one of the following values: <ul style="list-style-type: none"> • Running: Indicates that the collector is running. • Stopped: Indicates that the collector is not collecting data. • Unknown: Indicates that status information about the collector is unavailable, perhaps as a result of a lost connection between the collector and the server.
Computer	Displays the name of the computer on which the collector is running.
Report Rate	Displays the number of samples per minute that the server is receiving data from the collector. It is a measure of the collection rate and data compression. If the collector compression percent is zero, and if the value in this field is equal to the data acquisition rate, it indicates that every data point received from the collector is being reported to the server. This means that the collector is not performing any data compression. You can lower the report rate, and make the system more efficient, by increasing the data compression at the collector. To do this, widen the collection compression deadbands for selected tags.
Overruns	Displays the overruns in relation to the total events collected since startup. This value is calculated by using the following equation: $\text{OVERRUN_PCT} = \frac{\text{OVERRUNS}}{\text{OVERRUNS} + \text{TOTAL_EVENTS_COLLECTED}}$ Overruns are a count of the

Field	Description
	<p>total number of data events not collected on their scheduled polling cycle. In normal operation, this value should be zero.</p> <p>You may be able to reduce the number of overruns on the collector by increasing the tag collection intervals (per tag).</p>
Compression %	<p>Displays the percentage of how effective compression is at present for the specific collector since collector startup. A value of zero indicates that compression is either turned off or not effective. To increase the value, enable compression on the collector's associated tags and increase the width of the compression deadband on selected tags.</p> <p>The collector keeps track of how many samples it collected from the data source (for example, the OPC server) and keeps track of how many samples it reported to the Data Archiver (after collector compression is complete).</p> <p>A low number or zero means almost everything coming from the data source is being sent to the data archiver. The reason for the low number or zero is that too many samples are exceeding compression or you are not using collector compression.</p> <p>A high number or 100 means you are collecting a lot of samples, but they are not exceeding collector compression and therefore are not being sent to server.</p>
Out of Order	<p>Displays the number of samples within a series of timestamped data values normally transmitted in sequence that have been received out of sequence since collector startup. This field applies to all collectors. Even though events are still stored, a steadily increasing number of out-of-order events indicates a problem with data transmission that you must investigate.</p> <p>For instance, a steadily increasing number of out-of-order events when you are using the OPC collector means that there is an out-of-order connection between OPC Server and the OPC collector. This may also cause out-of-order connection between the OPC collector and the data archiver although that is not what this statistic indicates.</p>
Redundancy	<p>Displays the current redundancy status of the collector. This field contains one of the following values:</p>

Field	Description
	<ul style="list-style-type: none"> • Active: Indicates that the collector is currently collecting data. • Standby: Indicates that the collector is in the standby mode. This value appears only if the Collector Redundancy property of the collector is enabled.

The Alerts Section

The **Alerts** section displays all the alerts and warnings received or generated by the system. A total of up to 250 of the most recent messages appear in this section. In this section, you can:

- Stop automatic updating of the data by clearing the **Show Alerts** check box. However, the check box will be selected automatically when you restart Historian Administrator.
- Automatically refresh the data every 25 seconds by selecting the **Auto** check box.
- Manually refresh the data by selecting **Refresh**.

The following table describes the fields in the **Alerts** section.

Field	Description
Timestamp	The timestamp associated with the message or alert.
Topic	The type of alert message. Only the services and performance alerts appear in this field.
Message	The content of the message or alert.

The Data Store Page

Using the **Data Store** page, you can read and modify the parameters of archives, data stores, global options, security, and alarms.

The Archive Details Section

In the **Archive Details** section, a list of all the archives in your system appears. To access an archive, select it. In this section, you can:

- Close an archive by selecting **Close Archive**.
- Back up an archive by selecting **Backup**, and then providing the file name and path for the backup.
- Remove an archive by selecting **Remove**. The archive is then placed in the `\Archives\Offline` folder. However, the archive is not deleted.

This topic describes the fields in each subsection in the **Archive Details** section.

The Status Subsection

Field	Description
Status	The current operating state of the archive. This field contains one of the following values: <ul style="list-style-type: none"> • Current: Indicates that the archive is actively accepting data. • Active: Indicates that the archive contains data but is not currently accepting data. • Empty: Indicates that the archive has never accepted data.
Start Time	The time of the oldest sample in the archive.
End Time	The time the archive is closed (automatically or manually).

Table 60. The Backup Subsection

Field	Description
Last Backup	The date and time the last backup was performed on the archive.
Backup User	The username of the user who performed the last backup of the archive.

Table 61. Resources

Field	Description
File Location	The path and name of the archive file.
File Size	The size (in MB) of the archive file. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: Historian supports a maximum archive size of 256 GB per archive. </div>
File Attribute	The attribute to set a closed archive to read-only or read/write. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: To create multiple archives at the same time, set the value of this field to Read/Write. </div>

The Data Store Details Section

This topic describes the fields in each subsection in the **Data Store Details** section.

Data Store Settings

Archive Details | **Data Store Details** | Data Store Options | Global Options | Security | Alarms

Statistics

Archive Compression	0%
Write Cache Hit	0%
Receive Rate	(Events/Min)
Free Space	(MB)
Consumption Rate	(MB/Day)
Messages Since Startup	(Messages)
Failed Writes	(Events)
Est. Days to Full	(Days)
Alerts Since Startup	(Alerts)

User Details

Data Store State	Running
Is System	No
Number Of Tags	1
Is Default	<input checked="" type="radio"/> Yes <input type="radio"/> No
Storage Type	Historical Store
Description	The User Data Store.

Add Tags | Update | Delete

The Statistics Subsection

Field	Description
Archive Compression (% compression)	<p>Displays the current effect of archive data compression. If the value is zero, it indicates that archive compression is either ineffective or turned off. To increase the effect of data compression, increase the value of archive compression deadbands on individual tags in the Tag Maintenance section to activate compression.</p> <p>In calculating the effect of archive compression, Historian counts internal system tags as well as data source tags. Therefore, when working with a very small number of tags and with compression dis-</p>

Field	Description
	<p>abled on data source tags, this field may indicate a value other than zero. If you use a realistic number of tags, however, system tags will constitute a very small percentage of total tags and will therefore not cause a significant error in calculating the effect of archive compression on the total system.</p>
Write Cache Hit	<p>Displays the hit ratio of the write cache in percentage of total writes. It is a measure of how efficiently the system is collecting data. Typically, this value should range from 95 to 99.99%. If the data is changing rapidly over a wide range, however, the hit percentage drops significantly because current values differ from recently cached values. More regular sampling may increase the hit percentage. Out-of-order data also reduces the hit ratio.</p>
Receive Rate	<p>Displays how busy the server is at a given instance and the rate at which the server is receiving data from collectors.</p>
Free Space (MB)	<p>Displays how much disk space (in MB) is left in the current archive.</p>
Consumption Rate (MB/day)	<p>Displays how fast the archive disk space is consumed. If the value is too high, you can reduce it by slowing the poll rate on selected tags or data points or by increasing the filtering on the data (widening the compression deadband to increase compression).</p>
Messages Since Startup	<p>Displays a count of system messages generated since the last startup. The system resets the value to zero on restart. The message database, however, may contain more messages than this value.</p>
Failed Writes	<p>Displays the number of samples that failed to be written. Since failed writes are a measure of system malfunctions or an indication of offline archive problems, this value should be zero. If you observe a non-zero value, investigate the cause of the problem and take corrective action.</p> <p>Historian also generates a message if a write fails. Note that the message only appears once per tag, for a succession of failed writes associated with that tag. For example, if the number displayed in this field is 20, but they all pertain to one Historian tag, you will only receive one message until that Historian tag is functional again.</p>

Field	Description
Est Days to Full (Days)	<p>Displays how much time is left before the archive is full, based on the current consumption rate. This value is dynamically calculated by the server and becomes more accurate as an archive file gets closer to completion. This value is only an estimate and will vary based on a number of factors, including the current compression effectiveness. The System sends messages notifying you at 5, 3, and 1 days until full. After the archive is full, a new archive must be created (could be automatic).</p> <p>To increase this value, you must reduce the consumption rate. To ensure that collection is not interrupted, make sure that the Automatically Create Archives option is enabled in the Data Store Maintenance section (under Global Options). You may also want to enable the Overwrite Old Archives option if you have limited disk capacity. Enabling overwrite, however, means that some old data will be lost when new data overwrites the data in the oldest online archive. Use this feature only when necessary.</p>
Alerts Since Startup	<p>Displays a count of system warnings or alerts generated since the last startup. A high value here may indicate a problem of some kind. You should review the alerts and determine the probable cause. The count resets to zero on restart. The message database, however, may contain more alerts than this value.</p>

The User Settings Subsection

Field	Description
Data Store State	<p>The current state of the data store. The value in this field is Running until you delete the data store.</p>
Is System	<p>Indicates whether this data store is the system data store.</p> <div data-bbox="617 1627 1421 1837" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: By default, the Is System value of the system data store is set to yes. You cannot set the Is System value of any historical data store to yes.</p> </div>

Field	Description
Number of Tags	Displays the number of tags the data store contains.
Is Default (Yes/No)	Indicates whether the data store is the default store. Select Yes to set this data store as default one.
Storage Type	Indicates whether the storage type is historical or SCADA buffer.
Description	The description of the data store.

The Data Store Options Section

This topic describes the fields in each subsection in the **Data Store Options** section.

The screenshot shows the 'Data Store Options' configuration window. At the top, there are tabs: 'Archive Details', 'Data Store Details', 'Data Store Options' (active), 'Global Options', 'Security', and 'Alarms'. Below the tabs, the window is organized into three main sections:

- Archive Creation:**
 - 'Automatically Create Archives': Enabled, Disabled
 - 'Overwrite Old Archives': Enabled, Disabled
 - 'Default Size (MB)': Text box containing '100', followed by a dropdown menu set to 'BySize'.
- Maintenance:**
 - 'Default Archive Path': Text box containing 'C:\Proficy Historian Data\Archives\'
 - 'Default Backup Path': Text box containing 'C:\Proficy Historian Data\Archives\'
 - 'Base Archive Name': Text box containing 'User_IP-2UA3050GZC_Archive'
 - 'Free Space Required (MB)': Text box containing '5000'
 - 'Store OPC Quality': Enabled, Disabled
 - 'Use Caching': Enabled, Disabled
- Security:**
 - 'Data is Read-only After (Hours)': Text box containing '744'
 - 'Generate Message on Data Update': Enabled, Disabled

An 'Update' button is located at the bottom right of the window.

The Archive Creation or the SCADA Buffer Subsection

The **Archive Creation** subsection appears only if the data store type is historical. The **SCADA Buffer** subsection appears only if the data store type is SCADA buffer.

Field	Description
Automatically Create Archives	<p>Identifies whether the server must automatically create an archive file whenever the current archive file is full. The archive files are created in the default path directory.</p> <div data-bbox="511 430 1412 609" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If you plan to create multiple archives at the same time, select the Disabled option. </div>
Overwrite Old Archives	<p>When enabled, the system replaces the oldest archived data with new data when the default size has been reached. Since this action deletes historical data, exercise caution in using this feature. We recommend that you back up the archive so that you can restore it later.</p> <div data-bbox="511 829 1412 1102" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: To create multiple archives at the same time, select the Disabled option. If both the Automatically Create Archives and Overwrite Old Archives are enabled, set the ihArchiveFreeSpaceHardLimit parameter to TRUE using the Historian APIs. </div>
Default Size (MB)	<p>The default size of a newly created archive or the duration of a newly created archive in days or hours. Select one of the following options:</p> <ul style="list-style-type: none"> • BySize: A new archive file is created after the current archive reaches the default size. The recommended default archive size is at least 500 MB for systems with 1000 tags or more. • Days: A new archive file is created after the number of days that you specify in the Archive Duration field that will appear. • Hours: A new archive file is created after the number of hours that you specify in the Archive Duration field that will appear.
SCADA Buffer Duration (Days)	<p>Indicates the maximum number of days you want to store the trend data. The maximum number of days is equal to the value of the Rotational Buffer Duration shown in the GE Licence Client.</p>
Archive Duration (Days/Hours)	<p>Indicates the days or hours for which the duration of the archive is set.</p>

The Maintenance Subsection

Field	Description
Default Archive Path	<p>The folder path to store newly created archives.</p> <div data-bbox="513 415 1419 590" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: We recommend not to use a period in the default archive path field. If you do so, you will not be able to specify a default archive name.</p> </div>
Default Backup Path	The location to which the backup file will be saved.
Base Archive Name	A prefix that you want to add to all the archive files.
Free Space Required (MB)	<p>Indicates the remaining disk space required after a new archive is created. If the available space is less than the requirement, a new archive is not created. The default value is 5000 MB.</p> <p>This field is not applicable to alarms and events archives. The alarms and events archiver will continue writing to the alarms and events archive until the drive is full. If this occurs, the alarms and events archiver will buffer incoming alarms and events data until the drive has free space. An error message is logged in the Historian message log.</p>
Store OPC Quality	<p>Indicates whether to store the OPC data quality.</p> <div data-bbox="513 1213 1419 1388" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: To create multiple archives at the same time, select the Disabled option.</p> </div>
Use Caching	<p>Indicates whether caching must be enabled. When reading data from the archiver, some data is saved in the system memory and retrieved using caching. This results in faster retrieval as the data is already stored in the buffer.</p> <div data-bbox="513 1612 1419 1745" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: This option is not available for SCADA Buffer data stores.</p> </div>

The Security Subsection

Field	Description
Data is Read-only After (Hours)	<p>The number of hours for data to be stored in a read/write archive. After the time lapses, that portion of the archive file is automatically made read-only. Incoming data values with timestamps prior to this time are rejected. A single archive file, therefore, may have a portion made read-only, another portion that is read/write containing recently written data, and another that is unused free space.</p> <div data-bbox="511 640 1414 905" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: If an archive file is read-only, you cannot move the file in Windows File Explorer. To be able to move a read-only archive file, you must first remove the archive by selecting the file and selecting Remove in the Archive Maintenance page.</p> </div>
Generate Message on Data Update	<p>Indicates whether an audit log entry will be made any time the value of a previously archived data point is overwritten. This log entry will contain both the original and new values.</p> <div data-bbox="511 1087 1414 1262" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: To create multiple archives at the same time, select the Disabled option. This option is not available for SCADA Buffer data store.</p> </div>

The Global Options Section

This topic describes the fields in each subsection in the **Global Options** section.

Archive Details	Data Store Details	Data Store Options	Global Options	Security	Alarms
-----------------	--------------------	--------------------	-----------------------	----------	--------

Data Queries

Maximum Query Time (seconds)

Maximum Query Intervals

Memory/Recovery

Buffer Memory Max (MB)

Archiver Memory Size (MB)

Maintain Auto Recovery Files Enabled Disabled

Data Store

Default Data Store For Tag Add

The Data Queries Subsection

Field	Description
Maximum Query Time (seconds)	Specifies the maximum time that a data point or message query can take before it is terminated. Use this setting to limit query time and provide balanced read access to the archiver. This is applicable to all query types.
Maximum Query Intervals	Specifies the maximum number of samples per tag that Historian can return from a non-raw data query. Use this setting to throttle query results for non-raw data queries. This setting is not applicable to filtered data queries or raw data queries. If the number of returned samples exceeds the value in this field, the query fails and no data is returned.

The Memory/Recovery Subsection

Field	Description
Buffer Memory Max (MB)	The maximum memory buffer size that an archiver queue will use before starting to use disk buffering. The default value is 100 MB.

Field	Description
	<div data-bbox="834 275 1421 955" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <ul style="list-style-type: none"> • You can monitor your collector data write queue using the Perftag_CollectorDataWriteQueueSize tag. If you find that the queue is exceeding 10,000 items, such as during a store and forward flush, change the value of this field to 500 or more to maintain Historian performance. • If you are upgrading from a previous version of Historian, the value in this field remains the same. You can change the value as needed. </div>
Archiver Memory Size (MB)	<p>The target memory usage of the archive. The default value is 0, which indicates the system will manage the memory usage. If the archiver is running on a 32-bit operating system and you want to keep more data in memory, you can enter a value up to 1800 MB. If the archiver is running on a 64-bit operating system, we recommend that you use the default value.</p>
Maintain Auto Recovery Files	<p>Indicates whether high availability of the latest archive (.iha) and Historian configuration (.ihc) files must be enabled. When enabled, a copy of the latest .iha and .ihc file is made once every hour. These recovery files do not include alarms and events data.</p> <div data-bbox="834 1654 1421 1894" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <p>These files are managed internally by Historian, and should not be used as backup files. To create multiple archives at the same time, select the Disabled option. By</p> </div>


Field	Description
	 default, this field is set to Disabled on a 64-bit operating system. On a large-scale system, we recommend that you disable this option for better performance.

The Data Store Subsection

Field	Description
Default Data Store For Tag Add	The name of the default data store to which you want to add tags.

The Security Section

This topic describes the fields in each subsection in the **Security** section



The screenshot shows the 'Security' section of the Historian Administrator interface. At the top, there is a navigation bar with tabs for 'Archive Details', 'Data Store Details', 'Data Store Options', 'Global Options', 'Security', and 'Alarms'. The 'Security' tab is currently selected. Below the navigation bar, the 'Global Security' subsection is visible, containing three rows of radio button options: 'Security Groups' (Use Local selected, Use Domain), 'Enforce Strict Client Authentication' (Enabled selected, Disabled), and 'Enforce Strict Collector Authentication' (Enabled selected, Disabled). Below this is the 'Electronic Signatures / Records' subsection, which includes a 'Require Point Verification' option (Enabled, Disabled) and a 'Verification Message' text area containing the text: 'You Are Attempting To Perform An Audited Action. Please Confirm Your Username and Password to Continue'.

The Global Security Subsection

Field	Description
Security Groups	<p>Indicates whether to use the local security groups or the domain security groups.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: To ensure a secure environment when using Historian, do not create any local user accounts unless Historian is set up on a standalone computer and the guest account is disabled.</p> </div>
Enforce Strict Client Authentication	<p>Indicates whether to use strict client authentication. If you enable this option, only clients using the security-token-based authentication protocol can connect. Clients using Historian versions prior to 6.0 and other Proficy software they connect to may not be able to connect unless they have the latest updates for that version. If you disable this option, clients of any version can connect if they use a valid user name and password.</p>
Enforce Strict Collector Authentication	<p>Indicates whether to use strict collector authentication. If you enable this option, only collectors using the security-token-based authentication protocol can connect. Collectors using Historian versions prior to 6.0 and the other Proficy software they connect to may not be able to connect unless they have the latest updates for that version. If you disable this option, collectors of any version can connect.</p>

The Electronic Signatures / Records Subsection

The electronic signatures/records option assists users with government regulations such as the United States Food and Drug Administration's (FDA) 21 CFR Part 11 regulation or any site interested in added security by providing the ability to require a signature and password every time a change in data or configuration is requested. If you did not purchase the Electronic Signatures and Electronic Records option, the Electronic Signatures/Records field is disabled. For more information on Electronic Signatures and Records, refer to the [Using Historian in a Regulated Environment \(on page 824\)](#) section.

Field	Description
Require Point Verification	<p>Indicates whether you must enter identifying information whenever you attempt a restricted action. Whenever you attempt to change the system configuration (for the tag, archive, or collector), a tag value, or another record, you</p>

Field	Description
	<p>must electronically sign the action with a username and password. If the user is authorized to make this change, the identity of the person, the action performed, and the time it was performed, are all recorded in the audit trail.</p> <div data-bbox="511 426 1416 806" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <ul style="list-style-type: none"> • The audit features are not dependent on this feature being enabled. Historian audits all user actions regardless of whether this option is enabled. • If you plan to create multiple archives at the same time, select the Disabled option. </div> <p>Enabling electronic signatures and electronic records also requires you to reverify your identity when you use the Historian Excel Add-in, modify or create a tag, or import data or messages.</p> <div data-bbox="511 1005 1416 1178" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <p>This feature is available only if you have purchased the Electronic Signatures and Electronic Records option.</p> </div>
Verification Message	<p>When point verification is enabled, you are prompted to enter the username and password whenever you attempt to perform an action specified as requiring point verification.</p>

The **Alarms** Section

In the **Alarms** section, you can back up, purge, and restore alarms. This topic describes the fields in each subsection in the **Alarms** section.

Archive Details | Data Store Details | Data Store Options | Global Options | Security | **Alarms**

Backup / Purge Alarms

Start Time: 8 /23/2012 2 :34:02 PM

End Time: 8 /23/2012 4 :34:02 PM

Backup Alarms Purge Alarms

Restore Alarms

Select File: ...

Restore

The Alarms tab contains the following action buttons. Select a button to perform the action indicated by the name.

In the **Alarms**, you can set the following parameters:

The Backup / Purge Alarms Subsection

Table 62. Alarm Parameters

Field	Description
Start Time	The start time for backing up, purging, or restoring alarms. Enter a value in the following format: mm-dd-yyyy hh:mm:ss
End Time	The end time for backing up, purging, or restoring alarms. Enter a value in the following format: mm-dd-yyyy hh:mm:ss

The Restore Alarms Subsection

Field	Description
Select File	The backup file that you want to restore.


Searching in Message Panel

The **Message Search** page, shown in the following figure, lets you enter search parameters, such as start and end times, and to limit the search to alerts only or messages only. It further refines the search by topic and a text mask.

1. Enter a start time and end time (required).
If your start date and end date are identical, you must enter a timestamp with the date.
2. Select **All/ Alerts/ Messages**.
3. Select a **Topic** (optional).
4. Enter a text mask in the **Message Contains** field. (Optional).
If you do not specify a text mask, all items for the associated alert or message are returned. Use a text substring for a mask. The **Message Contains** field does not accept wildcard characters.
5. Select **Search**.
The search results are displayed in the **Search Results** panel.

Searching for Tags

1. Select the **Search Historian Tag Database** link in the **Tag Maintenance** page
The **Search Historian Tag Database** window in the following figure appears.



2. Enter a tag mask or a description mask in the appropriate fields, using standard Windows wildcard characters.
3. To limit the search to a specific collector, select a collector from the drop-down list in the **Collector** field.
4. Enter the maximum number of tags the search should return.
Entering 0 (zero) will return ALL tags available in the Historian Tag Database.
5. Select **OK** to execute the search.

Managing Data Stores

About Data Stores

A data store is a logical collection of tags. It is used to store, organize, and manage tags according to the data source and storage requirements. A data store can have multiple archive files (*.IHA), and includes both logical and physical storage definitions.

Tags can be segregated into separate archives through the use of data stores. The primary use of data stores is to segregate tags by data collection intervals. For example, you can put a name plate or static tags where the value rarely changes into one data store, and your process tags into another data store. This can improve query performance.

Historian data stores are stored as archive files that contain data gathered from all data sources during a specific period of time. You can write and read data from the archive files.

You can define two types of data stores:

- **Historical Data Store:** Tags stored under historical data store will store data as long as the disk space is available. Depending on your license, you may be able to create multiple historical data stores. The maximum number of historical data stores supported depends on the license.
- **SCADA Buffer Data Store:** Tags stored under the SCADA buffer data store will store data for a specific duration of time based on license.

When you install the Historian server, two historical data stores are installed by default.

- **System:** Stores Historian messages and performance tags. This is only for internal usage within Historian, and you cannot add tags to this data store. You cannot rename or delete the system data store.
- **User:** Stores tag data. This is a default data store. You can rename and delete a user data store as long as there is another default data store set for tag addition.

Based on your license, a SCADA Buffer data store may also be installed. It stores short-term tags and data.

Create a Data Store

Depending on your license, you can create or add multiple data stores.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **DataStores**.

The screenshot shows the Proficy Historian System Statistics page. The top navigation bar includes 'Main', 'Tags', 'Collectors', 'DataStores' (highlighted with a red box), 'Messages', and 'Help'. The main content area is divided into three sections: 'Receive Rate', 'Collectors', and 'Alerts'.

Receive Rate ? (Events/Min)

1
0 1 2 3 4 5 6 7 8 9 10

Archive Compression 0%
Write Cache Hit 0%
Failed Writes ? (Events)
Messages Since Startup ? (Messages)
Alerts Since Startup ? (Alerts)
Calculations (Enabled)
Server to Server (Enabled)
Max Scada Buffer Duration 201 (Days)

Server Memory 28%
Consumption Rate ? (MB/Day)
Historical Tags 8 (8 Used of 1,000,000 Licensed)
SCADA Tags 0 (0 Used of 2,400 Licensed)
Users 1 (15 Licensed)
Alarm Rate ? (Alarms/Min)
Alarms Since Startup ? (Alarms)
Data Stores 4 (20 Licensed)


Collectors Auto Refresh

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Show Alerts Auto Refresh

Timestamp	Topic	Message
-----------	-------	---------

3. Select **Add Data Store**.



The **Add New Data Store** window appears.

4. Enter values as described in the following table.

Field	Description
Data Store Name	Enter a unique name for the data store. The following characters are not allowed: <code>\/ \ * ? < > </code>
Default Data Store	Select this check box to set this data store as the default one for adding tags. A default data store is the one that is considered if you do not specify a data store while adding a tag. You can set only one data store as default.
Description	Enter a description for the data store.

5. Select **OK**.

The data store is created.

When you add tags to the data store, it will have its own set of .IHA (iHistorian Archive) files.

Ensure that you back up the new data store archives periodically.

Rename a Data Store

1. Access Historian Administrator (on page 823).
2. Select **DataStores**.


The screenshot shows the Proficy Historian System Statistics interface. The 'DataStores' menu item is highlighted with a red box. Below the navigation bar, there are several performance metrics and a table of collectors.

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

3. In the **Data Stores** field, select the data store that you want to rename.

The screenshot displays the Proficy Historian Data Store Maintenance interface. At the top, there are navigation tabs for Main, Tags, Collectors, DataStores, Messages, and Help. Below these are action buttons: Rename Data Store, Add Data Store, Add New Archive(s), and Restore an Archive from Backup. The main content area is titled 'Data Store Settings' and includes a 'Data Stores' dropdown menu (highlighted with a red box) showing 'User' selected. To the left is an 'Archives' table with columns 'Name' and 'Start Time', which is currently empty. The right side of the interface is divided into 'Statistics' and 'Details' sections. The 'Statistics' section includes metrics like Archive Compression (0%), Write Cache Hit (0%), Receive Rate, Free Space, Consumption Rate, Messages Since Startup, Failed Writes, Est. Days to Full, and Alerts Since Startup. The 'Details' section includes Data Store State (Running), Is System, Number Of Tags, Is Default (radio buttons for Yes/No), Storage Type (Historical Store), and Description (Text1). At the bottom right, there are buttons for 'Add Tags', 'Update', and 'Delete'.

4. Select **Rename Data Store**.



The **Rename New Data Store** window appears.

5. In the **New Data Store Name** field, enter the new name. The following special characters cannot be used in data store names: `/ \ * ? < > |`
6. Select **Rename**.

The data store is renamed.

Move a Tag to Another Data Store

You can move tags from one data store to another. However, moving a tag does not automatically move the data associated with it. If you want to retrieve the data stored before the tag was moved, you have to move the data manually using the migration utility tool.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

The screenshot shows the Proficy Historian System Statistics page. The 'Tags' menu item in the top navigation bar is highlighted with a red box. The page displays various system metrics and a table of collectors.

System Statistics:

- Receive Rate: ? (Events/Min)
- Archive Compression: 0%
- Write Cache Hit: 0%
- Failed Writes: ? (Events)
- Messages Since Startup: ? (Messages)
- Alerts Since Startup: ? (Alerts)
- Calculations: (Enabled)
- Server to Server: (Enabled)
- Max Scada Buffer Duration: 201 (Days)
- Server Memory: 28%
- Consumption Rate: ? (MB/Day)
- Historical Tags: 8 (8 Used of 1,000,000 Licensed)
- SCADA Tags: 0 (0 Used of 2,400 Licensed)
- Users: 1 (15 Licensed)
- Alarm Rate: ? (Alarms/Min)
- Alarms Since Startup: ? (Alarms)
- Data Stores: 4 (20 Licensed)

Collectors Table:

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Table:

Timestamp	Topic	Message
-----------	-------	---------

3. Select the tag that you want to move to a different data store.

Proficy Historian
Tag Maintenance

Main Tags Collectors DataStores Messages Help

Search Historian Tag Database Copy/Rename Tag Add Tag Manually Add Tags From Collector Define Enumerated Set Define User-Defined Types

Tags (1)

Tag Name
Tag322

Tag: Tag322

General | Collection | Scaling | Compression | Calculation | **Advanced**

Data Collection Options

Time Assigned By: Collector

Time Zone Bias (min): 0

Time Adjustment: Do Not Adjust For Source Time Difference

Data Store: User

Security

Read Group: []

Write Group: []

Administer Group: []

Audit


Last Modified: Never

Modified By: []

Update Delete

Right Mouse For Additional Options
* User-Defined and Array tags

4. Select **Advanced**.



5. In the **Data Store** field, select the data store to which you want to move the tag.

A message appears, asking you to confirm that the you want to move the tag.

6. Select **Yes**, and then select **Update**.

The tag has been moved. The new data for the tag will be stored in the new data store. However, if you want to store the old data as well in the new data store, you must manually migrate the tag data.

Delete a Data Store

You can delete a data store when it is no longer needed.



Note:

- You can only delete user data stores. You cannot delete the system data store.
- If you have only one user data store, you cannot delete it.

If there are any tags assigned to the data store, reassign them and manually move the data to another data store.

1. Access Historian Administrator (on page 823).
2. Select **DataStores**.

The screenshot shows the Proficy Historian System Statistics interface. The 'DataStores' tab is highlighted with a red box. The interface includes a navigation bar with 'Main', 'Tags', 'Collectors', 'DataStores', 'Messages', and 'Help'. Below the navigation bar, there are several performance metrics and a table of collectors.

System Statistics:

- Receive Rate: ? (Events/Min)
- Archive Compression: 0%
- Write Cache Hit: 0%
- Failed Writes: ? (Events)
- Messages Since Startup: ? (Messages)
- Alerts Since Startup: ? (Alerts)
- Calculations: (Enabled)
- Server to Server: (Enabled)
- Max Scada Buffer Duration: 201 (Days)
- Server Memory: 28%
- Consumption Rate: ? (MB/Day)
- Historical Tags: 8 (8 Used of 1,000,000 Licensed)
- SCADA Tags: 0 (0 Used of 2,400 Licensed)
- Users: 1 (15 Licensed)
- Alarm Rate: ? (Alarms/Min)
- Alarms Since Startup: ? (Alarms)
- Data Stores: 4 (20 Licensed)

Collectors Table:

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV_Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Section:

Alerts: Show Alerts Auto Refresh

Timestamp	Topic	Message
-----------	-------	---------

3. In the **Data Stores** field, select the data store that you want to delete.

Proficy Historian
DataStore Maintenance

Main Tags Collectors DataStores Messages Help

Rename Data Store Add Data Store Add New Archive(s) Restore an Archive from Backup

Data Stores
User

Archives

Name	Start Time
------	------------

Data Store Settings

Archive Details | Data Store Details | Data Store Options | Global Options | Security | Alarms

Statistics


Archive Compression	0%
Write Cache Hit	0%
Receive Rate	? (Events/Min)
Free Space	? (MB)
Consumption Rate	? (MB/Day)
Messages Since Startup	? (Messages)
Failed Writes	? (Events)
Est. Days to Full	? (Days)
Alerts Since Startup	? (Alerts)

Details

Data Store State	Running
Is System	IsSystem
Number Of Tags	NumberOfTags
Is Default	<input type="radio"/> Yes <input type="radio"/> No
Storage Type	Historical Store
Description	Text1

Add Tags Update Delete

4. Select **Delete**.



A message appears, asking you to confirm that you want to delete the data store.

5. Select **Yes**.

The data store is deleted.

Managing Archives

About Archives

Historian archives are data files, each of which contains data gathered from all data sources during a specific period of time.

Types of Archive Files:

- **machine name_Config.ihc**: Contains information about the archiver, tag configuration, and collector configuration.
- **machine name_ArchiveXXX.iha**: Contains tag data, where x is a number indicating the place of the file in a time-based sequence.

Creation of Archive Files Automatically

Archive files grow to a user-configured maximum size as data is recorded by the server. When data starts loading into an archive file, Historian will automatically create a new blank archive file. When the current archive file becomes full, Historian will immediately serve data to the newly created archive file. This significantly reduces archive creation and transition time.

If, however, the option to automatically create archive files is not enabled, you must [create an archive file manually \(on page 868\)](#).



Note:

If the option to automatically create an archive is not enabled and you do not create a new archive manually, or if the available disk space is less than the required amount of free disk space, a new archive file will not be created.

Overriding Old Archive Files

If you enable the **Overwrite Old Archives** option, the system replaces the oldest archived data with new data when the latest archive default size has been reached. Since this action deletes historical data, exercise caution in using this feature. Be sure that you have a backup of the archive so that you can restore it later. Best practice is to create an additional archive to prevent premature loss of data due to overwriting. For example, if you want to save 12 months of data into 12 archives, create 13 archives.

During archiver startup and every 60 seconds while the server is running, Historian verifies that you have configured enough free disk space to save the archives, buffer files, and log files. If there is insufficient disk space, the Data Archiver shuts down and a message is logged into the log file. By default, you can view the Historian archiver log file in `C:\Historian Data\LogFiles`.

```
[03/03/10 15:28:41.398] Insufficient space available in [d:\Historian\Archives\  
  
[03/03/10 15:28:41.399] The server requires a minimum of [5000 MB] to continue  
  
[03/03/10 15:28:41.679] USER: DataArchiver TOPIC: ServiceControl MSG: DataArchiver(DataArchiver)  
  
Archiver shutdown at 03/03/10 15:28:41.653  
  
[03/03/10 15:28:41.807] DataArchiver Service Stopped.  
  
[03/03/10 15:28:41.809] [d:\Historian\LogFiles\DataArchiver-34.log] Closed.
```

About Remote Storage of Archives

Historian can store current and backup archive files on remote storage devices. These remote storage devices can consist of network shares, Storage Area Networks (SAN), or Network Attached Storage (NAS)

devices. You can also employ a hybrid approach, by storing your current archive on the local disk and writing a script using the Historian SDK to migrate older archives to a remote storage device.

A SAN is a dedicated network apart from a LAN, specifically configured to allow servers to communicate with large storage arrays, usually over fibre-optic cables. The SAN is directly accessible as a disk device to Windows and does not operate through the slower network layer. NAS devices are similar to a SAN, but are directly attached to the LAN, appearing as a server.



Note:

Though NAS devices mapped to drives in Windows appear in Historian's Browse windows, they are not supported by the Data Archiver service. In order to access NAS devices in Historian, you must enter their UNC path (\\iHbackup\archive, for example).

If the Data Archiver service is not working, view the messages. Messages like these indicate that Historian is trying to use mapped drives: "Path N:\ not found." "Mapped drives unsupported as archive or backup file location" "UNC paths inaccessible when running as LocalSystem, configure other logon account for DataArchiver service". If these messages appear, find and change mapped drives to UNC paths.

Example: Migrating Non-Current Archives to a Remote Location

The following sample VBScript code will migrate non-current archive to a remote location by accessing the Historian SDK. This script could be run at specific intervals to migrate data from a local disk to a network share.

The Data Archiver service must have permission to write to the remote storage device. If you have configured alarms and events to use an SQL server, the SQL server must also have permissions to write to the remote storage device.

```
Dim FileSystem
set FileSystem = CreateObject("Scripting.FileSystemObject") Dim remoteLocation
remoteLocation = "\\StorageServer\Historian\Archives"
If InStrRev(remoteLocation, "\") Len(remoteLocation) Then remoteLocation = remoteLocation & "\"
' make sure we can access the remote storage before proceeding
Dim TestFile
set TestFile = FileSystem.OpenTextFile(remoteLocation & "Test.txt", 2, True, 0) If TestFile is Nothing Then
err.Raise 1, , "Unable to access remote storage location" End If
TestFile.Close
FileSystem.DeleteFile remoteLocation & "Test.txt" Dim Server
```

```

set Server = CreateObject("iHistorian_SDK.Server") If Server is Nothing Then
err.Raise 1, , "Unable to create iHistorian_SDK.Server object" End If

Dim archivesToMigrate(), i

If Server.Connect() Then

With Server.Archives

Dim backupPath

backupPath = .ArchivingOptions("ArchiveBackupPath")

If InStrRev(backupPath, "\") Len(backupPath) Then backupPath = backupPath & "\" ReDim archivesToMigrate(.Item.Count, 2)

For Each archive in .Item

If Not archive.IsCurrent Then

If UCase(Left(archive.FileName, InStrRev(archive.FileName, "\"))) UCase(remoteLocation) Then i = i + 1

archivesToMigrate(i, 0) = archive.Name

archivesToMigrate(i, 1) = backupPath & "Offline\" & cstr(archive.Name) & ".zip" archivesToMigrate(i, 2) =

archive.FileSizeTarget

End If

End If

Next

Dim j

For j = 1 To i

If .Delete(cstr(archivesToMigrate(j, 0))) Then FileSystem.MoveFile archivesToMigrate(j, 1), remoteLocation Dim archive

set archive = .Add(cstr(archivesToMigrate(j, 0)), cstr("%inplace%" & remoteLocation & archivesToMigrat

If Not (archive Is Nothing) Then

FileSystem.DeleteFile remoteLocation & archivesToMigrate(j, 0) & ".zip" End If

End If

Next End With Server.Disconnect

Else

err.Raise 1, , "Failed connecting to server"

End If

```

Guidelines for Setting Archive Size

Since archived data files can become quite large, you must adjust system parameters carefully to limit data collection to meaningful data only and thus minimize the required size of system storage. You can allocate up to 256 GB per archive.

For each archive, you need approximately 1MB of archive space for every 1000 tags to store tag information. Archive size is a function of the rate at which you archive data and the time period you want the archive to cover. A typical user wants the archive to cover a time period of, say, 30 days.

The following factors affect the rate at which you archive data:

- Number of tags
- Polling frequency of each tag
- Compression settings
- Data types

Based on these parameters, the archive size is calculated as follows:

$$\#Tags \times \frac{Values}{Tag} \times \frac{Tags}{Second} \times \%PassComp \times \frac{Bytes}{Value} \times \frac{Seconds}{Hour} \times \frac{Hours}{Day} \times \frac{MB}{Bytes} = \frac{MB}{Day}$$

Calculating Archive Size

Suppose you want to store data, and you have the following parameters:

- Number of tags: 5000
- Polling rate: 1 value/5 seconds
- Pass compression: 5%.

Pass compression is the number of data values archived relative to the number of values read.

- Bytes/value: 4
- Duration: 30 days

Based on the preceding formula, for the given parameters, the archive size is calculated as follows:

$$5000 \times \frac{1}{1} \times \frac{1}{5} \times \frac{5}{100} \times \frac{4}{1} \times \frac{3600}{1} \times \frac{24}{1} \times \frac{1}{1024 \times 1024} \times 30 = 494 \frac{MB}{Month}$$

The calculation shows that a file size of 500 MB is adequate for archiving one month of data for this application.

Therefore, we recommend that you set the default archive size to 500 MB for systems with 1000 tags or more. If you believe the computed size is too large for your application, you can modify parameters as follows:

- Decrease the polling frequency.
- Increase compression deadband, reducing the pass percentage.

- Reduce the number of tags.
- Add more disk capacity to your computer.

Archive Size Calculator

An archive size calculator tool is available to estimate archive size and collector compression based on a tag that has already been configured or based on your inputs. Log on to <http://digitalsupport.ge.com> to download this tool and other GE Intelligent Platforms freeware product solutions.

Create an Archive Automatically

When the current archive reaches a specified size or duration, you can configure Historian to create a new archive automatically. You can also [create an archive manually \(on page 870\)](#). When the current archive is full, the new one is used.


You can allocate maximum 256 GB for an archive.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **DataStores**.

The screenshot displays the Proficy Historian System Statistics interface. The 'DataStores' tab is highlighted with a red box. The interface includes a 'Receive Rate' graph, a list of system statistics, a 'Collectors' table, and an 'Alerts' section.

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV_Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

3. Select **Data Store Options**.



4. Enter values as described in the following table.

Field	Description
Automatically Create Archives	Select Enabled .
Overwrite Old Archives	Specify whether you want to overwrite old archives with new ones. Exercise caution in enabling this option. We recommend that you backup archives if you want to enable this option.
Default Size	Enter the size of the current archive after which you want to create a new archive. This field is available only if you have selected By Size in the adjacent drop-down list box. If, however, you want to create archives after a duration, select Days or Hours , and then enter the value in the Archive Duration field.

Field	Description
Archive Duration	Enter the duration after which you want to create a new archive. This field is available only if you select Days or Hours in the adjacent drop-down list box. If, however, you want to create an archive when the current one reaches a particular size, select By Size , and then enter the value in the Default Size field.
Default Archive Path	Enter the path to the folder in which you want to store the archive files.
Default Backup Path	Enter the path to the folder in which you want to store the backup files.
Base Archive Name	Enter the base name for the archive. This name will be appended with a number to identify the sequence of the archive.
Free Space Required	Enter the free space that is required to create the archives.
Store OPC Quality	Specify whether you want to store OPC quality in the archive.
Use Caching	Specify whether you want to use caching in the archive.
Data is Read-Only After (Hours)	Specify the duration, in hours, after which you want to archive to be read-only.
Generate Message on Data Update	Specify whether you want to generate a message when data is updated in the archive.

5. Select **Update**.

Archives will be created automatically when the current one reaches the size (or after the duration) that you have specified.

Create Archives Manually

If you want to create multiple archives at the same time, access Historian Administrator, and set values for the following fields:

Field	Value
The Details Section	
File Attribute	Read/Write

Field	Value
The Global Options Section	
Maximum Query Time (seconds)	60
Maximum Query Intervals	100000
Automatically Create Archives	Disabled
Overwrite Old Archives	Enabled
Maintain Auto Recovery Files	Enabled
Store OPC Quality	Disabled
The Security section	
Data is Readonly After (Hours)	1 month
Security Groups	Use local
Generate Message on Data Update	Disabled
Require Point Verification	Disabled

This topic describes how to create archives manually. You can also [create them automatically \(on page 868\)](#). When the current archive is full, a new archive is used (in a sequential order).

You can create multiple archives at the same time.



CAUTION:

If you want to creating multiple archives on a remote machine, you must ensure that you have enough hard disk space on that machine. The **Allocate Space** field does not display a remote machine's hard disk space; if you are creating multiple archives on a remote machine, you must ignore the "percentage of available disk space will be used" message displayed by the Allocate Space slider.

If you receive the error message "Runtime error 330 Invalid Property Value" while creating multiple archives on a remote machine, it is probably because you do not have enough hard disk space on that machine. When you select OK on the error message, Historian Administrator may disappear. You must now clean up the remote machine's hard disk space and restart Historian Administrator.

1. Access Historian Administrator (on page 823).
2. Select **DataStores**.

The screenshot shows the Proficy Historian System Statistics interface. The 'DataStores' tab is highlighted with a red box in the top navigation bar. The main content area is divided into three sections: a 'Receive Rate' graph, a 'System Statistics' table, and a 'Collectors' table.

Receive Rate ? (Events/Min)

1

0 1 2 3 4 5 6 7 8 9 10

System Statistics

Archive Compression	0%	Server Memory	28%
Write Cache Hit	0%	Consumption Rate	? (MB/Day)
Failed Writes	? (Events)	Historical Tags	8 (8 Used of 1,000,000 Licensed)
Messages Since Startup	? (Messages)	SCADA Tags	0 (0 Used of 2,400 Licensed)
Alerts Since Startup	? (Alerts)	Users	1 (15 Licensed)
Calculations	(Enabled)	Alarm Rate	? (Alarms/Min)
Server to Server	(Enabled)	Alarms Since Startup	? (Alarms)
Max Scada Buffer Duration	201 (Days)	Data Stores	4 (20 Licensed)


Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV_Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Select **Add New Archive(s)**.



The **Add New Archive(s)** window appears.

4. Enter values as described in the following table.

Field	Description
Archive Name	Enter a unique name for the archives. The value must be the same as the file name. When multiple archives are created, a number is appended to the name to make each name unique (and to maintain a sequence).
Data Store	Select the data store in which you want to create the archives.
File Location	Enter the path to the folder in which you want to store the archives, or specify a UNC path.
EachArchive Size (MB)	Enter the size, in MB, that you want to allocate to the archives.
Number of Archives	Enter the number of archives you want to create.

Field	Description
Allocate Space	<p>Specify the percentage of the disk space that you want to allocate for archives. As you increase the space, the number of archives increases accordingly.</p> <div data-bbox="669 430 1416 741" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px;"> <p> Note: The Allocate Space field does not display a remote machine's hard disk space; if you are creating multiple archives on a remote machine, you must ignore the "r;percentage of available disk space will be used" message displayed by the Allocate Space slider.</p> </div>

5. Select **OK**.

The archives are created.

Back up Archives Automatically

You must back up archive files periodically to ensure that your data is protected. These backup files contain tag data as well as alarms and events data. You can send these files to a shared network location or to physical media.

Planning for data recovery means always having up-to-date backup files for important information that you can call up and restore quickly when the need arises.

The .IHC file, which contains all configuration information, is an important file to back up. The .IHC file is automatically backed up when, and only when, you back up the current archive .IHA file. With the .IHC file, you can always restore the system configuration to the state it was in before the event occurred.

It is also important to backup the current online archive files *.IHA. If you restore the archive files, along with the configuration, you can quickly pick up where you left off when the event occurred with a minimum loss of data.

By default, the .IHC backup path is the same as the archives path. The .IHC uses the following naming convention: `ComputerName_Config-Backup.ihc`. If the default backup path is different than the archives path, the .IHC file is copied to the backup folder with the standard .IHC naming convention: `ComputerName_Config.ihc`.

Important points to remember:

- The .IHC file is automatically backed up when, and only when, you back up the current archive .IHA file. By default, the .IHC backup path is the same as the archives path.
- The .IHC backup file uses the following naming convention: `<system name>_Config-Backup.ihc`. If the default backup path is different from the archives counterpart, the .IHC file is copied to the backup folder with the standard .IHC naming convention: `ComputerName_Config.ihc`.
- In the mirroring system, Client Manager sends a backup message to Data Archiver located on the Client Manager node to which you are connected. The back up then happens in the specified location on that node. If that Data Archiver is not running, a NOT_CONNECTED error message appears, and the backup will not happen.
- If you back up an archive more than once, by default, the backup tool will attempt to use the same name for the backup file and will detect that an archive with the same name already exists. Rename the backup archive file or move the original backup archive file to a different folder.

1. Access the `ihArchiveBackup.exe` file. By default, it is located at `C:\Program Files\Proficy\Historian\Server`.

2. Run the following command if you want to back up multiple archives at the same time:

```
AT <time> /EVERY:<days of the week> "ihArchiveBackup.exe [-s <Historian server name>] [-u <Username>] [-p <Password>][-t <Timeout seconds>][-n <Number of archives>]
```

Run the following command if you want to back up a single archive file:

```
AT <time> /EVERY:<days of the week> "ihArchiveBackup.exe [-s <Historian server name>] [-u <username>] [-p <password>][-t <timeout seconds>] [-a <archive name>]"
```

The following table describes the parameters.

Switch	Parameter	Description
AT	Time	The time at which you want to back up the archives.
EVERY	Days of the week	The days of the week on which you want to back up the archives (for example, <code>EVERY:M,T,W,Th,F</code>).
-s	Historian server name	The IP address or the host name of the Historian server on which the archive is available.
-u	Username	The user name required to connect to the Historian server.

Switch	Parameter	Description
-p	Password	The password required to connect to the Historian server.
-t	Timeout seconds	The time, in seconds, to wait before the process times out.
-n	Number of archives	The number of archives to back up, counting backwards from the current archive.
-a	Archive name	The name of a specific archive to back up.
-c		Backs up only the Historian configuration (.ihc) file.
-d	Data store name	The name of the data store that stores the archive data. <div data-bbox="792 856 841 905" style="float: left; margin-right: 5px;"></div> <div data-bbox="857 867 1385 1073" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p>Note: Using one instance of ihArchiveBackup.exe you can point to one data store, and by using multiple instances you can point to multiple data stores.</p> </div>

If you do not provide any parameters, only the current archive file is backed up.

```
AT 23:59 /EVERY:M,T,W,Th,F "ihArchiveBackup.exe [-s MyHistorianServer] [-u User1] [-p password123][-t 10] [-a MyHistorianServer_DS1_Archive004]"
```

Back up an Archive Manually

- Ensure you have enough hard drive space on your default backup location before backing up your archives.
- Always back up archives before a planned Historian software product upgrade.
- Use Microsoft® Volume Shadow Copy Service when backing up archive files that are more than 2 GB in size or when backing up more than the last two archives. For more information, refer to [Back Up Archives with Volume Shadow Copy Service \(on page 731\)](#).

You must back up archive files periodically to ensure that your data is protected. These backup files contain tag data as well as alarms and events data. You can send these files to a shared network location or to physical media.

Planning for data recovery means always having up-to-date backup files for important information that you can call up and restore quickly when the need arises.

The .IHC file, which contains all configuration information, is an important file to back up. The .IHC file is automatically backed up when, and only when, you back up the current archive .IHA file. With the .IHC file, you can always restore the system configuration to the state it was in before the event occurred.

It is also important to backup the current online archive files *.IHA. If you restore the archive files, along with the configuration, you can quickly pick up where you left off when the event occurred with a minimum loss of data.

By default, the .IHC backup path is the same as the archives path. The .IHC uses the following naming convention: `ComputerName_Config-Backup.ihc`. If the default backup path is different than the archives path, the .IHC file is copied to the backup folder with the standard .IHC naming convention: `ComputerName_Config.ihc`.

Important points to remember:

- The .IHC file is automatically backed up when, and only when, you back up the current archive .IHA file. By default, the .IHC backup path is the same as the archives path.
- The .IHC backup file uses the following naming convention: `<system name>_Config-Backup.ihc`. If the default backup path is different from the archives counterpart, the .IHC file is copied to the backup folder with the standard .IHC naming convention: `ComputerName_Config.ihc`.
- In the mirroring system, Client Manager sends a backup message to Data Archiver located on the Client Manager node to which you are connected. The back up then happens in the specified location on that node. If that Data Archiver is not running, a NOT_CONNECTED error message appears, and the backup will not happen.
- If you back up an archive more than once, by default, the backup tool will attempt to use the same name for the backup file and will detect that an archive with the same name already exists. Rename the backup archive file or move the original backup archive file to a different folder.

1. [Access Historian Administrator \(on page 823\)](#).

2. Select **DataStores**.

Proficy Historian
System Statistics

[Main](#)
[Tags](#)
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

1 _____

0 1 2 3 4 5 6 7 8 9 10

Archive Compression	0%	Server Memory	28%
Write Cache Hit	0%	Consumption Rate	? (MB/Day)
Failed Writes	? (Events)	Historical Tags	8 (8 Used of 1,000,000 Licensed)
Messages Since Startup	? (Messages)	SCADA Tags	0 (0 Used of 2,400 Licensed)
Alerts Since Startup	? (Alerts)	Users	1 (15 Licensed)
Calculations	(Enabled)	Alarm Rate	? (Alarms/Min)
Server to Server	(Enabled)	Alarms Since Startup	? (Alarms)
Max Scada Buffer Duration	201 (Days)	Data Stores	4 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Select the archive that you want to back up.

The screenshot shows the Proficy Historian Data Store Maintenance interface. At the top, there are navigation links for Main, Tags, Collectors, DataStores, Messages, and Help. Below this, there are action buttons: Rename Data Store, Add Data Store, Add New Archive(s), and Restore an Archive from Backup. The main content area is divided into two sections: Archives and Data Store Settings.

Data Stores

User

Archives

Name	Start Time
------	------------

Data Store Settings

Archive Details | Data Store Details | Data Store Options | Global Options | Security | Alarms

Statistics

Archive Compression	0%
Write Cache Hit	0%
Receive Rate	? (Events/Min)
Free Space	? (MB)
Consumption Rate	? (MB/Day)
Messages Since Startup	? (Messages)
Failed Writes	? (Events)
Est. Days to Full	? (Days)
Alerts Since Startup	? (Alerts)

Details

Data Store State	Running
Is System	IsSystem
Number Of Tags	NumberOfTags
Is Default	<input type="radio"/> Yes <input type="radio"/> No
Storage Type	Historical Store
Description	Text1

Add Tags Update Delete

4. Select **Archive Details**, and then select **Backup**.

The screenshot displays the Proficy Historian DataStore Maintenance interface. At the top, there is a navigation bar with the Proficy Historian logo and menu items: Main, Tags, Collectors, DataStores, Messages, and Help. Below this is a secondary navigation bar with options: Rename Data Store, Add Data Store, Add New Archive(s), and Restore an Archive from Backup. The main content area is titled "Archive: User_System5_Archive002" and features a tabbed interface with "Archive Details" selected. On the left, a "Data Stores" dropdown menu is set to "User", and an "Archives" table lists "User_System5_Archive002" (28-01-2022 12:49:42) and "User_System5_Archive003" (Empty). The "Archive Details" tab shows sections for Status (Current, Start Time: 28-01-2022 12:49:42, End Time: Current Time), Backup (Last Backup: Never, Backup User:), and Resources (File Location: C:\Proficy Historian Data\Archives\User_System..., File Size (MB): 500, File Attribute: Read/Write). At the bottom, there are buttons for "Close Archive", "Backup", "Remove", and "Update".

Proficy Historian
DataStore Maintenance

Main | Tags | Collectors | DataStores | Messages | Help

Rename Data Store | Add Data Store | Add New Archive(s) | Restore an Archive from Backup

Data Stores: User

Name	Start Time
User_System5_Archive002	28-01-2022 12:49:42
User_System5_Archive003	Empty

Archive: User_System5_Archive002

Archive Details | Data Store Details | Data Store Options | Global Options | Security | Alarms

Status

Status: Current
Start Time: 28-01-2022 12:49:42
End Time: Current Time


Backup

Last Backup: Never
Backup User:

Resources

File Location: C:\Proficy Historian Data\Archives\User_System...
File Size (MB): 500
File Attribute: Read-only Read/Write

Close Archive | Backup | Remove | Update



The **Backing up Archive** window appears. The **Backup File** field is populated with the default folder path that you have specified while creating the data store and a default name.

5. If needed, change the folder path and name of the backup file.

The archive is backed up. If needed, you can close and remove it from the list of archives (but it will still remain in the disk).

Restore an Archive

- Before restoring an archive from a removable disk, copy the archive file to the normal archive path and then restore the archive from that location. Leave the original backup file in the backup file folder.
- Copy the backup archive file to the default archive path.

Under certain circumstances, you may want to restore tag data to Historian. This may be after an unplanned shutdown, or you may need to retrieve data from an old, inactive archive.



CAUTION:


- Restoring an archive is a resource-intensive operation and should be scheduled for non-peak usage times.
- Never restore an archive to a production Historian server without a current archive already online.

1. Access Historian Administrator (on page 823).
2. Select **DataStores**.

The screenshot displays the Proficy Historian System Statistics interface. At the top, navigation tabs include Main, Tags, Collectors, **DataStores** (highlighted with a red box), Messages, and Help. The main content area is divided into several sections:

- Receive Rate:** A line graph showing 1 event per minute over a 10-minute period.
- System Metrics:** A grid of status indicators including Archive Compression (0%), Write Cache Hit (0%), Failed Writes (?), Messages Since Startup (?), Alerts Since Startup (?), Calculations (Enabled), Server to Server (Enabled), Max Scada Buffer Duration (201 Days), Server Memory (28%), Consumption Rate (?), Historical Tags (8/1,000,000), SCADA Tags (0/2,400), Users (1/15), Alarm Rate (?), Alarms Since Startup (?), and Data Stores (4/20).
- Collectors Table:** A table with columns for Collector, Status, Computer, Report Rate, Overruns, Compression, Out Of Order, and Redundancy. One entry is visible: SAN-JAVA-DEV Simulation, Unknown, SAN-JAVA-DEV, 0, 0, %, 0.
- Alerts Section:** A section with a 'Show Alerts' checkbox (checked) and an 'Auto' checkbox (unchecked). Below it is a table with columns for Timestamp, Topic, and Message.

3. Select **Restore An Archive From Backup**.



The **Restore Archive** window appears.

4. Enter values as described in the following table.

Field	Description
Archive Name	Enter the name of the archive you want to restore.
File Location	Specify the location of the archive file.
Data Store	Select the data store to which you want to restore the archive. If the data store is not available, it is restored to the default data store.

5. Select **OK**.

The restored archive is moved to the \Archive directory and is made available for querying.

Configure System File Cache Memory

You can specify the maximum disk cache memory that an archiver can use. By default, Historian consumes 25% of system memory. If your computer has extra memory, you can increase the disk cache.

Increasing the disk cache memory optimizes the Historian performance. You should not increase system file caching cache memory if you do not have the necessary system resources.

1. Access Registry Editor.
2. Open the following key folder. `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\`
`\Services\DataArchiver\`
3. Create a new DWORD called `FileSystemMaxCacheMB`
4. Set the decimal value to a number. The value that you enter represents the maximum disk cache memory that an archiver can use.
5. Select **OK**, and then close the Registry Editor.
6. Restart the Data Archiver service.

Configure the Data Archiver Account for Remote Storage

By default, the Data Archiver service is installed under the LocalSystem account, which has no credentials to access network resources. In order to use Remote Storage, you must first configure the Data Archiver service to run under a user account that has read/write access to the network location.

1. Stop the Data Archiver service.
2. Open the Services Control Panel.
3. Right-click the **Historian Data Archiver** service, and select **Properties**
4. Select **Log On**.
5. In the **Log on as** field, select **This Account**.
6. Enter the user account using which you want to run the Data Archiver service. This account must have write privileges to your Storage Area Network.
7. Enter the password for the user account.
8. Restart the Data Archiver service.

Reuse an Archive Configuration File

You may want to reuse an existing archive configuration file (*.ihc) when a Historian installation uses the same archive configuration as another Historian installation or when renaming a machine and reusing the original .ihc file.

1. Retrieve a copy of the `<oldmachinename>_CentralConfig.ihc` file from the old machine. By default, this is located at `C:\Proficy Historian Data\Archives`
2. On the new machine, select and stop the following services:
 - Historian Client Manager
 - Historian Configuration Manager

- Data Archiver
 - Historian Diagnostics Manager
3. Copy the `<oldmachinename>_CentralConfig.ihc` file into the local folder on the new machine where the .ihc files are available.
 4. Look for a file in that folder on the new machine named `<newmachinename>_CentralConfig.ihc`. If there is a file with that name, delete it.
 5. Rename the copied .ihc file on the new machine to `<newmachinename>_CentralConfig.ihc`.
 6. Run a command prompt as an administrator.
 7. Go to `C:\Program Files\Proficy\Proficy Historian\x64\Server`, and run the following command: `ihConfigManager_x64.exe RenameDHSNode <old machine name> <new machine name>`

**Note:**

RenameDHSNode modifies only the local node name. The logical node name (service name) does not change.

RenameDHSNode will not alter service name `configmanager_<nodename>`

Reusing a Configuration File

Suppose you have a production Historian with a machine name "WaterSite" and want to load that configuration on a testbed Historian called "LabSite1". The testbed Historian is already running and already has a config file called "LabSite1_CentralConfig.ihc."

In this case:

1. Stop the services and delete `LabSite1_CentralConfig.ihc`.
2. Rename `WaterSite_CentralConfig.ihc` to `LabSite1_CentralConfig.ihc`.
3. At the command line, run the following:

```
ihConfigManager_x64.exe RenameDHSNode WaterSite LabSite1
```

Managing Tags

About Tags

A Historian tag is used to store data related to a property.

For example, if you want to store the pressure, temperature, and other operating conditions of a boiler, a tag will be created for each one in Historian.

When you collect data using a collector, tags are created automatically in Historian to store these values. These tags are mapped with the corresponding properties in the source.

For example, suppose you want to store OSI PI data in Historian. You will specify the OSI PI tags for which you want to collect data. The OSI PI collector creates the corresponding tags in Historian, and it stores the values in those tags.

You can also choose to create tags manually (for example, to store the result of a calculation performed by the Calculation collector).

About Array Tags

You can store a set of values with a single timestamp and single quality and then read the elements individually or as an array.

The following conditions apply when using an array tag:

- You need not specify the size of an array tag. Data Archiver will store the number of elements that were written.
- You can change a tag to an array tag later as well. However, when you do so, only the latest data is retrieved. If you want to get the old data, you must change the tag back to its previous type.
- The maximum number of elements that an array tag can store is 10,000.
- You cannot associate an enumerated set or a user-defined data type (UDT) with an array tag.
- Fixed String and Scaled data types are not supported.
- Scaling, collector compression, and archive compression do not apply to an array tag.
- You cannot use an array element as a calculation trigger.
- You cannot plot a trend chart for an array tag.
- TagStats calculation mode is not supported.

About Collector and Archive Compression

Collector Compression

Collector compression applies a smoothing filter to data retrieved from the data source. By ignoring small changes in values that fall within a deadband centered around the last reported value, only significant changes are reported to the archiver. Fewer samples reported yields less work for the archiver and less archive storage space used.

You can specify the deadband value. For convenience, if you enter a deadband percentage, Historian Administrator shows the deadband in engineering units. For example, if you specify a 20% deadband on 0

to 500 EGU span, it is calculated and shown as 100 engineering units. If you later change the limits to 100 and 200, the 20% deadband is now calculated as 20 engineering units.

The deadband is centered around the last reported sample, not simply added to it or subtracted. If your intent is to have a deadband of 1 unit between reported samples, you must enter a compression deadband of 2 so that it is one to each side of the last reported sample. In the previous example of 0 to 500 EGU range, with a deadband of 20%, the deadband is 100 units; This means that only if the value changes by more than 50 units, it is reported.

Changes in data quality from good to bad, or bad to good, automatically exceed collector compression and are reported to the archiver. Any data that comes to the collector out of time order will also automatically exceed collector compression.

It is possible for collected tags with no compression to appear in Historian as if the collector or archive compression options are enabled. If collector compression occurs, you will notice an increase in the percentage of the compression value in the **Collectors** section of the **System Statistics** page in Historian Administrator. When archive compression occurs, you will notice the archive compression value and status bar change on the **System Statistics** page.

For instructions on setting collector compression, refer to [Access/Modify a Tag \(on page 894\)](#).

Even if collector compression is not enabled, you may notice it in the following scenarios:

- When a succession of bad data quality samples appears, Historian collects only the first sample in the series. No new samples are collected until the data quality changes. Historian does not collect the redundant bad data quality samples, and this is reflected in the collector compression percentage.
- For a Calculation or Server-to-Server collector, when calculations fail, producing no results or bad quality data, collector compression is used. The effect of Collector Compression Timeout is to behave, for one poll cycle, as if the collector compression feature is not being used. The sample collected from the data source is sent to the archiver. Then the compression is turned back on, as configured, for the next poll cycle with new samples being compared to the value sent to the archiver.



Note:

Array tags do not support archive and collector compression. If the tag is an array tag, then the **Compression** tab is disabled.

Handling Value Step Changes with Collector Data Compression

If you enable collector compression, the collector does not send values to the archiver any new input values if the value remains within its compression deadband. Occasionally, after several sample intervals inside the deadband, an input makes a rapid step change in value during a single sample interval. Since there have been no new data points recorded for several intervals, an additional sample is stored one interval before the step change with the last reported value to prevent this step change from being viewed as a slow ramp in value. This value marks the end of the steady-state, non-changing value period, and provides a data point from which to begin the step change in value.



Note:

You can configure individual tags can be configured to retrieve step value changes.

The collector uses an algorithm that views the size of the step change and the number of intervals since the last reported value to determine if a marker value is needed. The following is an example of the algorithm:

```
BigDiff=abs(HI_EGU-LO_EGU)*(CompressionDeadbandPercent/(100.0*2.0))*4.0

If ( Collector Compression is Enabled )

If ( Elapsed time since LastReportedValue>=( SampleInterval * 5 ) )

If ( abs(CurrentValue-LastReportedValue) > BigDiff )

Write LastReportedValue,TimeStamp=(CurrentTime-SampleInterval)
```

In the example above, if a new value was not reported for at least the last 4 sample intervals, and the new input value is at least 4 deltas away from the old value (where a single delta is equal to half of the compression deadband), then a marker value is written.



Note:

These settings are also adjustable from the Registry. Please contact [technical support](#) for more information.

Value Spike with Collector Compression

For example, a collector reads a value X once per second, with a compression deadband of 1.0. If the value of X is 10.0 for a number of seconds starting at 0:00:00 and jumps to 20.0 at 0:00:10, the data samples read would be:

Time	X Value
0:00:00	10.0 (steady state value)

Time	X Value
0:00:01	10.0
0:00:02	10.0
0:00:03	10.0
0:00:04	10.0
0:00:05	10.0
0:00:06	10.0
0:00:07	10.0
0:00:08	10.0
0:00:09	10.0
0:00:10	20.0 (new value after step change)

To increase efficiency, the straightforward compression would store only 2 of these 11 samples.

Time	X Value
0:00:00	10.0 (steady state value)
0:00:10	20.0 (new value after step change)


However, without the marker value, if this data were to be put into a chart, it would look like the data value **ramped** over 10 seconds from a value of 10.0 to 20.0, as shown in the following chart.



The addition of a **marker value** to the data being stored results in the following data values:

Time	X Value
0:00:00	10.0 (steady state value)
0:00:09	10.0 (inserted Marker value)
0:00:10	20.0 (new value after step change)

If you chart this data, the resulting trend accurately reflects the raw data and likely real world values during the time period as shown in the following chart.



Evaluating and Controlling Data Compression

You can achieve optimum performance in Historian by carefully controlling the volume of dynamic data it collects and archives. You need enough information to tell you how the process is running, but you do not need to collect and store redundant or non-varying data values that provide no useful information.

Control Data Flow

You can control the amount of online or dynamic data the system handles at a given time by adjusting certain system parameters. The general principle is to control the flow of data into the archive either by adjusting the rate at which the collectors gather data or by adjusting the degree of filtering (compression) the system applies to the data collected.

Adjust the following parameters to *reduce* the rate of data flow into the server.

- Reduce the polling rate by increasing the collection interval for unsolicited and polled collection.
- Enable collector compression and optionally use compression timeout.
- Set the compression deadband on the collectors to a wider value.
- Use the collector compression timeout.

Adjust the following parameters to *increase the filtering* applied by the archiver in the server.

- Enable archive (trend) compression.
- Set the archive compression deadband to a wider value.
- Where possible, use the scaled data type and enable input scaling on selected tags.
- Where possible, select milliseconds or microseconds rather than seconds for time resolution.
Seconds is optimum for most common devices. This affects disk space.

Evaluate Data Compression Performance

You can determine how effectively data compression is functioning at any given time by examining the system statistics displayed on the **System Statistics** page of Historian Administrator.

The compression field at the top of the page shows the current effect of archive compression. Values for this parameter should typically range from 0 to 9%. If the value is zero, it indicates that compression is either ineffective or turned off. If it shows a value other than zero, it indicates that archive compression is operating and effective. The value itself indicates how well it is functioning. To increase the effect of data compression, increase the value of archive compression deadband so that compression becomes more active.

Archive Compression

Archive compression is used to reduce the number of samples stored when data values for a tag form a straight line in any direction. For a horizontal line (non-changing value), the behavior is similar to collector compression. But, in archive compression, it is not the *values* that are being compared to a deadband, but the *slope of line* those values produce when plotted value against time. Archive compression logic is executed in the data archiver and, therefore, can be applied to tags populated by methods other than collectors.

You can use archive compression on tags where data is being added to a tag by migration, or by the File collector, or by an SDK program for instance. Each time the archiver receives a new value for a tag, the archiver computes a line between this incoming data point and the last archived value.

The deadband is calculated as a tolerance centered about the slope of this line. The slope is tested to see if it falls within the deadband tolerance calculated for the previous point. If the new point does not exceed the tolerance, it is not stored in the archive. This process repeats with subsequent points. When an incoming value exceeds the tolerance, the value held by the archiver is written to disk and the incoming sample is withheld.

The effect of the archive compression timeout is that the incoming sample is automatically considered to have exceeded compression. The withheld sample is archived to disk and the incoming sample becomes the new withheld sample. If the Archive Compression value on the System Statistics page indicates that

archive compression is occurring, and you did not enable archive compression for the tags, the reason could be because of internal statistics tags with archive compression enabled.

For instructions on setting archive compression, refer to [Access/Modify a Tag \(on page 894\)](#).

About Scaling

Scaling converts a data value from a raw value expressed in an arbitrary range of units, such as a number of counts, to one in engineering units, such as gallons per minute or pounds per square inch. The scaled data type can serve as a third form of data compression, in addition to collector compression and archive compression, if it converts a data value from a data type that uses a large number of bytes to one that uses fewer bytes.

About Condition-Based Collection

Condition based collection is a method to control the storage of data for data tags by assigning a condition. Data is always collected but it is only written to the Data Archiver if the condition is true; otherwise, the collected data is discarded.

This condition is driven by a trigger tag; a tag collected by the collector evaluating the condition. Ideally, Condition based Collection should be used only with tags that are updating faster than the trigger tag. Condition based collection can be used to archive only the specific data which is required for analysis, rather than archiving data at all times, as the collector is running.

For example, if a collector has tags for multiple pieces of equipment, you can stop collection of tags for one piece of equipment during its maintenance. It is typically used on tags that use fast polled collection but you don't want to use collector compression. While the equipment is running, you want all the data but when the equipment is stopped, you don't want any data stored. The trigger tag would also typically use polled collection. But, either tag could use unsolicited collection.

The condition is evaluated every time data is collected for the data tag. When a data sample is collected, the condition is evaluated and data is either queued for sending to archiver, or discarded. If the condition cannot be evaluated as true or false, like if the trigger tag contains a bad data quality or the collector is not collecting the trigger tag, the condition is considered true and the data is queued for sending.

No specific processing occurs when the condition becomes true or false. If the condition becomes true, no sample is stored to the data tag using that condition, but the data tag will store a sample next time it collects. When the condition becomes false, no end of the collection marker is stored until the data tag is collected.

For example, if the condition becomes false at 1:15 and the data tag gets collected at 1:20, the end of collection marker will be created at 1:20 and have a timestamp of 1:20, not 1:15.

Condition based collection is supported by only archiver and collectors of Historian version 4.5 and above. Condition based collection does not apply to alarm collectors. This condition based collection is applicable to the following collectors only:

- Simulation Collector
- OPC Collector
- iFIX Collector
- PI Collector

For instructions on setting the condition-based collection, refer to [Access/Modify a Tag \(on page 894\)](#).

Access/Modify a Tag

Using Historian Administrator, you can access a list of tags in the Historian database by their name, description, or both.



Note:

By default, maximum one million tags are retrieved. If the Historian clients are configured to retrieve more than a million tags, to retrieve all of them, add the `MaxTagsToRetrieve` registry key under `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\DataArchiver\`, and then set the maximum number of tags that you want to retrieve. Restart the Historian Data Archiver service for the change to reflect.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

Proficy Historian
System Statistics

[Main](#)
Tags
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

1 _____

0 1 2 3 4 5 6 7 8 9 10

Archive Compression	0%	Server Memory	28%
Write Cache Hit	0%	Consumption Rate	? (MB/Day)
Failed Writes	? (Events)	Historical Tags	8 (8 Used of 1,000,000 Licensed)
Messages Since Startup	? (Messages)	SCADA Tags	0 (0 Used of 2,400 Licensed)
Alerts Since Startup	? (Alerts)	Users	1 (15 Licensed)
Calculations	(Enabled)	Alarm Rate	? (Alarms/Min)
Server to Server	(Enabled)	Alarms Since Startup	? (Alarms)
Max Scada Buffer Duration	201 (Days)	Data Stores	4 (20 Licensed)


Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Select **Search Historian Tag Database**.




The **Search Historian Tag Database** window appears.

4. Enter values in the available fields to search for the tag, and then select **OK**. You can use the wildcard character asterisk (*).

A list of tags that meet the search criteria appear in the **Tags** section.

5. Right-click the **Tags** section, and then select one of the following values:
 - **View By TagName**: Select this option to view only the names of the tags.
 - **View By Description**: Select this option to view only the descriptions of the tags.
 - **View Tagname and Description**: Select this option to view both the names and descriptions of the tags.



6. As needed, modify values as described in the following tables, and then select **Update**.

Table 63. The General Section

Field	Description
Description	The description of the tag.
EGU Description	The engineering units assigned to the tag.
Comment	Comments that apply to the tag.
StepValue	Indicates that the actual measured value changes in a sharp step instead of a smooth linear interpolation. This option is applicable only for numeric data. Enabling this option only affects data retrieval; it has no effect on data collection or storage.
Spare Configuration	The Spare 1 through Spare 5 fields list any configuration information stored in these fields.

Field	Description
	<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: Do not add or update the following spare configurations as data may get corrupted or overwritten: <ul style="list-style-type: none"> ◦ The Spare 1 field for OSI PI Distributor reads data from the Historian tag displayed in the Tag Source Address field and sends it to the OSI PI tag name displayed in the Spare 1 field. ◦ The Spare 5 field is used for a Server-to-Server collector and a Server-to-Server distributor for internal purposes. </div>

Table 64. The Collection Section

Field	Description
Collector	The name of the collector that collects data for the selected tag.
Source Address	<p>The address for the tag in the data source. Leave this field blank for tags associated with the Calculation or Server-to-Server collector.</p> <p>For Python Expression tags, this field contains the full applicable JSON configuration, which includes an indication of the source address.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: When exporting or importing tags using the EXCEL Add-In, the Calculation column, not the SourceAddress column, holds the formulas for tags associated with the Calculation or Server-to-Server collector. </div>
Data Type	<p>The data type of the tag.</p> <p>The main use of the scaled data type is to save space, but this results in a loss of precision. Instead of using 4 bytes of data, it only uses 2 bytes by storing the data as a percentage of the EGU limit. Changing the EGU limits will result in a change in the values that are displayed. For example, if the original EGU values were 0 to 100 and a value of 20 was stored using the scaled data type and if the EGUs are changed to 0 to 200, the original value of 20 will be represented as 40.</p>

Field	Description
	<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If you change the data type of an existing tag between a numeric and a string or binary data type (and vice versa), the tag's compression and scaling settings will be lost. </div>
Enumerated Set Name	The name of the enumerated set that you want to assign to the tag.
Data Length	The number of bytes for a fixed string data type. This field is enabled only for fixed string data types.
Is Array Tag	Indicates that the tag is an array tag.
Collection	Indicates whether data collection is enabled or disabled for the tag. If you disable collection for the tag, Historian stops collecting data for the tag, but does not delete the tag or its data.
Collection Type	The type of data collection used for this tag: <ul style="list-style-type: none"> ◦ Polled: The data collector requests data from the data source at the collection interval specified in the polling schedule. ◦ Unsolicited: The data source sends data to the collector whenever necessary (independent of the data collector polling schedule).
Collection Interval	The time interval between readings of data from this tag. For unsolicited collection type, this field defines the minimum interval at which unsolicited data should be sent by the data source.
Collection Offset	Used with the collection interval to schedule collection of data from a tag. For example, to collect a value for a tag every hour at thirty minutes past the hour (12:30, 1:30, 2:30, and so on), enter a collection interval of 1 hour and an offset of 30 minutes. Similarly, to collect a value each day at 8am, enter a collection interval of 1 day and an offset of 8 hours. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF; margin-top: 10px;">  Note: If you enter a value in milliseconds, the value must be in intervals of 1000 ms. For example, 1000, 2000, and 3000 ms are valid values, but 500 and 1500 ms are invalid. The minimum value is 1000 ms. </div>

Field	Description
Time Resolution	The precision for timestamps, which can be either seconds, milliseconds or microseconds.
Condition-Based	Indicates whether condition-based data collection (on page 666) is enabled.
Trigger Tag	The name of the trigger tag used in the condition.
Comparison	<p>The comparison operator that you want to use in the condition. This field is enabled only if you have enabled condition-based collection.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Undefined: Collection will resume only when the value of the triggered tag changes. This is considered an incomplete configuration, so condition-based collection is turned off and all the collected data is sent to archiver. ◦ < =: Setting condition as trigger tag value less than or equal to the compare value. ◦ > = Setting condition as trigger tag value greater than or equal to the compare value. ◦ <: Setting condition as trigger tag value less than the compare value. ◦ >: Setting condition as trigger tag value greater than the compare value. ◦ =: Setting condition as trigger tag value equals compare value. ◦ ! =: Setting condition as trigger tag value not the same as compare value.
Compare Value	A target value that you want to compare with the value of the trigger tag. If using = and != comparison parameters, ensure that the format of the compared value and triggered tag are the same. For example, for a float type trigger tag, the compare value must be a float value; otherwise, the condition result is an invalid configuration. When the configuration is invalid, condition-based collection is disabled and all data is sent to archiver.
End of Collection Markers	Indicates whether end-of-collection markers are enabled. This will mark all the tag's values as bad, and sub-quality as ConditionCollectionHalted when the condition becomes false. Trending and reporting applications can use this information to indicate that the real-world value was un-

Field	Description
	known after this time until the condition becomes true and a new sample is collected. If disabled, a bad data marker is not inserted when the condition becomes false.

Table 65. The Scaling Section

Field	Description
Hi Engineering Units	<p>The current value of the upper range limit of the span for this tag.</p> <p>Engineering Hi and Lo are retrieved automatically for F_CV fields for iFIX tags; all others are left at default settings. When adding tags from the server using an OPC Collector, the OPC Collector queries the server for the EGU units and EGU Hi/Lo limits. Not all OPC Servers make this information available, however. Therefore, if the server does not provide the limits when requested to do so, the collector automatically assigns an EGU range of 0 to 10,000.</p>
Lo Engineering Units	<p>The current value of the lower range limit of the span for this tag.</p>
Input Scaling	<p>Indicates whether input scaling is enabled, which converts an input data point to an engineering units value.</p> <p>For example, to rescale and save a 0 - 4096 input value to a scaled range of 0 - 100, enter 0 and 4096 as the low and high input scale values and 0 and 100 as the low and high engineering units values, respectively.</p> <p>If a data point exceeds the high or low end of the input scaling range, Historian logs a bad data quality point with a ScaledOutOfRange subquality. In the previous example, if your input data is less than 0, or greater than 4096, Historian records a bad data quality for the data point.</p> <p>OPC Servers and TRUE Values: Some OPC servers return a TRUE value as -1. If your OPC server is returning TRUE values as</p>

Field	Description
	<p>-1, modify the following scaling settings in the Tag Maintenance page of Historian Administrator:</p> <pre data-bbox="678 363 1421 598"> Hi Engineering Units = 0 Lo Engineering Units = 1 Hi Scale Value = 0 Lo Scale Value = - 1 Input Scaling = Enabled </pre>
Hi Scale Value	The upper limit of the span of the input value.
Lo Scale Value	The lower limit of the span of the input value.

Table 66. The Compression Section

Field	Description
Collector Compression	Indicates whether collector compression (on page 660) is enabled.
Collector Deadband	<p>The current value of the compression deadband. This value can be computed as a percent of the span, centered around the data value or given as an absolute range around the data value.</p> <div data-bbox="573 1144 1421 1459" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Some OPC servers add and subtract the whole deadband value from the last data value. This effectively doubles the magnitude of the deadband compared to other OPC servers. To determine how your specific server handles deadband, refer to the documentation of your OPC server.</p> </div> <p>Example:</p> <p>Suppose the engineering units are 0 to 200. Suppose the deadband value is 10%, which is 20 units. If the deadband value is 10% and the last reported value is 50, the value will be reported when the current value exceeds $50 + 10 = 60$ or is less than $50 - 10 = 40$. Note that the deadband (20 units) is split around the last data value (10 on either side.)</p>

Field	Description
	<p>Alternatively, you could specify an absolute deadband of 5. In this instance, if the last value was 50, a new data sample will be reported when the current value exceeds 55 or drops below 45.</p> <p>If compression is enabled and the deadband is set to zero, the collector ignores data values that do not change and records any that do change. If you set the deadband to a non-zero value, the collector records any value that lies outside the deadband. If the value changes drastically, a pre-spike point may be inserted. For information, refer to Enable Spike Logic (on page 970).</p>
Engineering Unit	<p>Converts the deadband percentage into engineering units and displays the result. This value establishes the deadband range that is centered around the new value.</p> <p>This field represents a calculated number created to give an idea of how large a deadband you are creating in engineering units. The deadband is entered in percentage and Historian converts the percentage in to engineering units.</p>
Collector Compression Timeout	<p>Indicates the maximum amount of time the collector will wait between sending samples for a tag to the archiver. This time is maintained per tag, as different tags report to the archiver at different times.</p> <p>For polled tags, this value should be in multiples of your collection interval. After the timeout value is exceeded, the tag stores a value at the next scheduled collection interval, and not when the timeout occurred. For example, if you have a 10-second collection interval, a 1-minute compression timeout, and a collection that started at 2:14:00, if the value has not changed, the value is logged at 2:15:10 and not at 2:15:00.</p> <p>For unsolicited tags, a value is guaranteed in, at most, twice the compression timeout interval.</p> <p>A non-changing value is logged on each compression timeout. For example, an unsolicited tag with a 1-second collection interval and a 30-second compression timeout is stored every 30 seconds.</p>

Field	Description
	<p>A changing value for the same tag may have up to 60 seconds between raw samples. In this case, if the value changes after 10 seconds, then that value is stored, but the value at 30 seconds (if unchanged) will not be stored. The value at 60 seconds will be stored. This leaves a gap of 50 seconds between raw samples which is less than 60 seconds.</p> <p>Compression timeout is supported in all collectors except the PI collector.</p>
Archive Compression	<p>Indicates whether archive compression (on page 660) is enabled. If enabled, Historian applies the archive deadband settings against all reported data from the collector.</p>
Archive Deadband	<p>The current value of the archive deadband, expressed as a percent of span or an absolute number.</p>
Engineering Unit	<p>Converts the deadband percentage into engineering units and displays the result. This value establishes the deadband range that is centered around the new value.</p>
Archive Compression Timeout	<p>The maximum amount of time from the last stored point before another point is stored, if the value does not exceed the archive compression deadband.</p> <p>The data archiver treats the incoming sample after the timeout occurs as if it exceeded compression. It then stores the pending sample.</p>

Table 67. The Advanced Section

Field	Description
Time Assigned By	<p>The source of the timestamp for a data value is either the collector or the data source.</p> <p>All tags, by default, have their time assigned by the collector. When you configure a tag for a polled collection rate, the tag is updated based on the collection interval. For example, if you set the collection interval to 5 seconds with no compression, then the archive will be updated with a new data point and timestamp every 5 seconds, even if the value is not changing.</p>

Field	Description
	<p>However, if you set the Time Assigned By field to Source for the same tag, the archive only updates when the device timestamp changes. For example, if the poll time is still 5 seconds, but if the timestamp on the device does not change for 10 minutes, no new data will be added to the archive for 10 minutes.</p> <div data-bbox="570 516 1419 646" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: This field is disabled for Calculation and Server-to-Server tags. </div>
Time Zone Bias	<p>The number of minutes from GMT that should be used to translate time-stamps when retrieving data from this tag. For example, the time zone bias for Eastern Standard time is -300 minutes (GMT-5).</p> <p>This field is not used during collection. Use this option if a particular tag requires a time zone adjustment during retrieval other than the client or server time zone. For example, you could retrieve data for two tags with different time zones by using the tag time zone selection in the iFIX chart.</p>
Time Adjustment	<p>If the Server-to-Server collector is not running on the source computer, select the Adjust for Source Time Difference option to compensate for the time difference between the source archiver computer and the collector computer.</p> <div data-bbox="570 1276 1419 1453" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: This field only applies to tags associated with the Server-to-Server collector that use a polled collection type. </div>
Data Store	Displays the data store to which the tag belongs.
Read Group	The Windows security group assigned to the selected tag.
Write Group	The Windows security group assigned to the selected tag.
Administer Group	The Windows security group assigned to the selected tag.

Field	Description
Last Modified	The date the last tag parameter modification was made.
Modified By	The name of the person who last modified the tag configuration parameters.

Add Tags from Source

Create a collector instance (on page 357) using which you want to browse the source for tags.

This topic describes how to browse for source tags and add them to Historian. These tags are then created automatically in the Historian database. You can also [create tags manually \(on page 909\)](#).


1. Access Historian Administrator (on page 823).
2. Select **Tags**.

The screenshot shows the Proficy Historian System Statistics interface. The 'Tags' tab is highlighted with a red box in the navigation menu. The main content area displays various system metrics:


- Receive Rate**: ? (Events/Min), 1
- Archive Compression**: 0%
- Write Cache Hit**: 0%
- Failed Writes**: ? (Events)
- Messages Since Startup**: ? (Messages)
- Alerts Since Startup**: ? (Alerts)
- Calculations**: (Enabled)
- Server to Server**: (Enabled)
- Max Scada Buffer Duration**: 201 (Days)
- Server Memory**: 28%
- Consumption Rate**: ? (MB/Day)
- Historical Tags**: 8 (8 Used of 1,000,000 Licensed)
- SCADA Tags**: 0 (0 Used of 2,400 Licensed)
- Users**: 1 (15 Licensed)
- Alarm Rate**: ? (Alarms/Min)
- Alarms Since Startup**: ? (Alarms)
- Data Stores**: 4 (20 Licensed)

Below the statistics, there are sections for **Collectors** and **Alerts**. The Collectors section shows a table with columns: Collector, Status, Computer, Report Rate, Overruns, Compression, Out Of Order, and Redundancy. The Alerts section shows a table with columns: Timestamp, Topic, and Message.

3. Select **Add Tags from Collector**.



The **Add Multiple Tags from Collector** window appears.



4. Enter values as described in the following table.

Field	Description
Collector	Select the collector instance using which you want to browse the source for tags.
Show Only	Specify whether you want to see all tags or only the ones that have not been added yet.
Source Tag Name	Enter the string to narrow down the search results based on the tag name. You can use wildcard characters.
Description	Enter the string to narrow down the search results based on the tag description. You can use wildcard characters.

5. Select **Browse**.

A list of tags based on the search criteria appear.

6. Select the tags that you want to add to Historian.

- Select a single tag by selecting the name of the tag.
- Select multiple tags by pressing the **Control** key and selecting the tags.

- Select a contiguous group by pressing the **Shift** key and selecting the first and last tag of the group.
 - Select all tags by selecting **Select All**.
7. Select **Add Selected Tags**.

The selected tags are added to the Historian database.

Create a Tag Manually

This topic describes how to create a tag manually. You can also [add tags from source \(on page 906\)](#); these tags are then automatically created in the Historian database.

Whenever you add tags, delete tags, or modify certain tag properties, the following collectors reload only the modified tags without restarting the collectors.

- OPC Collector
- iFIX Collector
- Calculation Collector
- Simulation Collector
- Server to Server Collector
- PI Collector
- PI Distributor

The dynamic collector update feature ensures that any modifications to the tag configuration do not affect all the tags in a collector. Tags that stop data collection may record zero data and bad quality without restarting the collector. Tags that do not stop data collection do not record bad data samples to the collection.

By default, the On-line Tag Configuration Changes option is enabled, which allows a tag to stop and restart data collection without restarting the collector. If you disable the On-line Tag Configuration Changes option, any changes you make to the tags do not affect collection until after you restart the collector. To enable or disable the On-line Tag Configuration Changes option, select **Advanced** on the **Collector Maintenance** page.

To restart the collector you must stop and start the collector service or executable. Restarting the collector stops and restarts the tag(s) collection and may record bad data samples to the collection. All the collector configuration changes done within a 30 second time frame are batched up together. To collect the modified data faster, update/modify a small set of tags at a time.



Note:


When updating large sets of tags at the same time, best practice is to disable the On-line Tag Configuration Changes option and restart the collector after modification.

1. Access Historian Administrator (on page 823).
2. Select **Tags**.

The screenshot shows the Proficy Historian System Statistics interface. The 'Tags' menu item is highlighted with a red box. The interface includes a 'Receive Rate' graph, a list of system statistics, a 'Collectors' table, and an 'Alerts' section.

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

3. Select **Add Tag Manually**.



The **Add Tag Manually** window appears.

4. Enter values as described in the following table.

Field	Description
Collector Name	Select the collector using which you want to collect data for the tag.
Source Address	Enter the source address for the tag.
Tag Name	Enter a unique name for the tag.
Data Store	Select the data store in which you want to store the tag data.
Data Type	Select the data type of the tag data.
Is Array Tag	Select this check box if the tag is an array tag. For fixed string data types only, enter a value in the field adjacent to the Data Type field.

Field	Description
	You can change a tag to an array tag later as well. However, when you do so, only the latest data is retrieved. If you want to get the old data, you must change the tag back to its previous type.
Time Resolution	Select the duration at which you want to collect data for the tag. For example, if you select Seconds , data is collected every second.

**Note:**

If you add a tag for a Server-to-Server collector, set the **Time Adjustment** field for the tag to **Adjust for Source Time Difference** after you add the tag. This field is available under **Tags > Advanced**. This is applicable only for polled data collection.

5. Select **OK**.

The tag is created.

Copy a Tag

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

Proficy Historian
System Statistics

[Main](#)
Tags
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

1 _____

0 1 2 3 4 5 6 7 8 9 10

Archive Compression	0%	Server Memory	28%
Write Cache Hit	0%	Consumption Rate	? (MB/Day)
Failed Writes	? (Events)	Historical Tags	8 (8 Used of 1,000,000 Licensed)
Messages Since Startup	? (Messages)	SCADA Tags	0 (0 Used of 2,400 Licensed)
Alerts Since Startup	? (Alerts)	Users	1 (15 Licensed)
Calculations	(Enabled)	Alarm Rate	? (Alarms/Min)
Server to Server	(Enabled)	Alarms Since Startup	? (Alarms)
Max Scada Buffer Duration	201 (Days)	Data Stores	4 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Select the tag that you want to copy.

The screenshot displays the Proficy Historian Tag Maintenance interface. At the top, the title bar reads "Proficy Historian Tag Maintenance" with navigation icons for Main, Tags, Collectors, DataStores, Messages, and Help. Below the title bar, a secondary menu contains icons and labels for "Search Historian Tag Database", "Copy/Rename Tag", "Add Tag Manually", "Add Tags From Collector", "Define Enumerated Set", and "Define User-Defined Types".


The main content area is divided into two sections. On the left, a "Tags (1)" list shows a table with the following data:

Tag Name
Tag322

The "Copy/Rename Tag" button in the secondary menu is highlighted with a red rectangular box. Below the list, a note states: "Right Mouse For Additional Options * User-Defined and Array tags".

On the right, the "Tag: Tag322" configuration panel is visible, featuring tabs for "General", "Collection", "Scaling", "Compression", "Calculation", and "Advanced". The "Data Collection Options" section includes fields for "Time Assigned By" (set to Collector), "Time Zone Bias (min)" (set to 0), "Time Adjustment" (set to Do Not Adjust For Source Time Difference), and "Data Store" (set to User). The "Security" section includes fields for "Read Group", "Write Group", and "Administer Group". The "Audit" section shows "Last Modified" as "Never" and "Modified By" as an empty field. "Update" and "Delete" buttons are located at the bottom right of the configuration panel.

4. Select **Copy/Rename Tag**.



The **Copy/RenameTag** window appears.

5. Select **Copy**.
 6. Enter a new tag name.
 7. Select **OK**.
- The tag is copied.

Rename a Tag

- You must be a member of the administrator's group with tag level security.
- If you want to rename a tag permanently, to avoid loss of data, stop the collector instance.

When you rename a tag, you can choose between the following options:

- **Rename using an alias:** In this case, the old name is called the tag alias. You can retrieve tag data using the tag alias as well. When you copy a tag, the tag alias is captured as well to aid in an audit trail.
- **Rename permanently:** In this case, the old name is no longer captured. Therefore, you can create another tag with this old name. You cannot store and forward data using the old name. This implies that data for the tag is collected separately for the new name.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

The screenshot shows the Proficy Historian System Statistics page. The 'Tags' menu item in the top navigation bar is highlighted with a red box. Below the navigation bar, there are several system statistics including Receive Rate, Archive Compression, Write Cache Hit, Failed Writes, Messages Since Startup, Alerts Since Startup, Calculations, Server to Server, Max Scada Buffer Duration, Server Memory, Consumption Rate, Historical Tags, SCADA Tags, Users, Alarm Rate, Alarms Since Startup, and Data Stores. Below these statistics are two tables: 'Collectors' and 'Alerts'.


Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV_Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Timestamp	Topic	Message

3. Select the tag that you want to rename.

The screenshot displays the Proficy Historian Tag Maintenance interface. At the top, the application title 'Proficy Historian' is shown with the subtitle 'Tag Maintenance'. A navigation bar includes icons for 'Main', 'Tags', 'Collectors', 'DataStores', 'Messages', and 'Help'. Below this, a secondary menu contains buttons for 'Search Historian Tag Database', 'Copy/Rename Tag', 'Add Tag Manually', 'Add Tags From Collector', 'Define Enumerated Set', and 'Define User-Defined Types'. The main content area is split into two panes. The left pane, titled 'Tags (1)', contains a table with one entry: 'Tag Name' and 'Tag322'. This pane is highlighted with a red border. The right pane, titled 'Tag: Tag322', shows configuration options for the selected tag, including 'Data Collection Options' (Time Assigned By, Time Zone Bias, Time Adjustment, Data Store), 'Security' (Read Group, Write Group, Administer Group), and 'Audit' (Last Modified, Modified By). At the bottom right of the right pane are 'Update' and 'Delete' buttons. A footer note at the bottom left of the interface reads: 'Right Mouse For Additional Options * User-Defined and Array tags'.

4. Select **Copy/Rename Tag** .



The **Copy/RenameTag** window appears.

5. If you want to rename the tag using an alias, select **Rename (Alias)**. If you want to rename the tag permanently, select **Permanent Rename**.
6. Select **OK**.

If you have renamed the tag permanently:

- If the tag is used as a trigger, reassign the trigger.
- Restart the collector instance.

View Tag Trends and Raw Data

This topic describes how to access the trend chart of tag data. Note that the tag trend should not be used for detailed data. And, trend data is not supported for array tags.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

Proficy Historian
System Statistics

[Main](#)
[Tags](#)
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

1 _____

0 1 2 3 4 5 6 7 8 9 10

Archive Compression	0%	Server Memory	28%
Write Cache Hit	0%	Consumption Rate	? (MB/Day)
Failed Writes	? (Events)	Historical Tags	8 (8 Used of 1,000,000 Licensed)
Messages Since Startup	? (Messages)	SCADA Tags	0 (0 Used of 2,400 Licensed)
Alerts Since Startup	? (Alerts)	Users	1 (15 Licensed)
Calculations	(Enabled)	Alarm Rate	? (Alarms/Min)
Server to Server	(Enabled)	Alarms Since Startup	? (Alarms)
Max Scada Buffer Duration	201 (Days)	Data Stores	4 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	


Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Right-click the tag whose trend chart you want to access, and then select **Trend**.

The screenshot shows the Proficy Historian Tag Maintenance interface. On the left, a list of tags includes 'Tag322'. A context menu is displayed over this tag, with the 'Trend' option highlighted in a red box. The main area shows the configuration for 'Tag: Tag322'. The 'Data Source' section includes fields for collector (SYSTEM4_IFX), source address, data type (Single Float), and enumerated set name. The 'Collection Options' section shows the collection type as 'Polled', a collection interval of 5 seconds, a collection offset of 0 seconds, and a time resolution of seconds. The 'Condition Based Collection' section is currently disabled, with fields for trigger tag, comparison operator (=), and compare value. 'Update' and 'Delete' buttons are visible at the bottom right.

The trend chart of the tag values appears.



**Note:**

To change the criteria, select **Criteria**, and then enter values as described in the following table.

Field	Description
Start Time	Select the start time of the trend chart.
End Time	Select the end time of the trend chart.
Sampling	Select the data type that you want to use.
Interval	Enter the interval at which you want to plot the tag data.
Criteria Strings	Enter the sampling mode, calculation mode, and/or query modifiers. Query modifiers are used to specify various ways of retrieving data from Historian. For example, you can request raw data with good quality only by specifying the criteria string as: <code>RAWBYTIME#ONLYGOOD</code> . The sampling mode specified with criteria strings takes precedence over the mode specified in the Sampling field.

You can also scroll back and forth on the x-axis time scale by selecting on the single and double left and right arrows at the bottom of the page.

View the Last 10 Raw Values of a Tag

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

Proficy Historian
System Statistics

[Main](#)
[Tags](#)
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

1 _____

0 1 2 3 4 5 6 7 8 9 10

Archive Compression	0%	Server Memory	28%
Write Cache Hit	0%	Consumption Rate	? (MB/Day)
Failed Writes	? (Events)	Historical Tags	8 (8 Used of 1,000,000 Licensed)
Messages Since Startup	? (Messages)	SCADA Tags	0 (0 Used of 2,400 Licensed)
Alerts Since Startup	? (Alerts)	Users	1 (15 Licensed)
Calculations	(Enabled)	Alarm Rate	? (Alarms/Min)
Server to Server	(Enabled)	Alarms Since Startup	? (Alarms)
Max Scada Buffer Duration	201 (Days)	Data Stores	4 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Right-click the tag whose last 10 values you want to access, and then select **Last 10 Values**.


The screenshot shows the Proficy Historian Tag Maintenance window for Tag322. The interface includes a navigation bar with options like Main, Tags, Collectors, DataStores, Messages, and Help. Below this are action buttons such as Search Historian Tag Database, Copy/Rename Tag, Add Tag Manually, Add Tags From Collector, Define Enumerated Set, and Define User-Defined Types. The main area is divided into a 'Tags (1)' list on the left and a configuration panel for 'Tag: Tag322' on the right. The configuration panel has tabs for General, Collection, Scaling, Compression, Calculation, and Advanced. The 'Collection' tab is active, showing settings for Data Source (SYSTEM4_IFX), Data Type (Single Float), Collection Options (Enabled), and Condition Based Collection (Disabled). A context menu is open over the 'Tags (1)' list, with 'Last 10 Values' highlighted in a red box. At the bottom of the configuration panel are 'Update' and 'Delete' buttons.

The last 10 values of the tag appear.

The screenshot shows the 'Historian Trend' window with a table of data. The table has four columns: Tagname, Timestamp, Value, and Quality. The data shows a sequence of values for 'DestAvgTag' over time, with values alternating between approximately 97.41665 and 47.41589. The quality is consistently 'Good'.

Tagname	Timestamp	Value	Quality
DestAvgTag	12/23/2002 2:11:50 PM	97.41665	Good
DestAvgTag	12/23/2002 2:11:49 PM	97.41665	Good
DestAvgTag	12/23/2002 2:11:48 PM	97.41665	Good
DestAvgTag	12/23/2002 2:11:47 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:46 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:45 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:44 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:43 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:42 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:41 PM	97.41665	Good

For an array tag, each element is displayed as a separate row with the tag name and the index.



The screenshot shows a window titled "Historian Trend" with a table of data. The table has four columns: Tagname, Timestamp, Value, and Quality. The data is as follows:

Tagname	Timestamp	Value	Quality
DestAvgTag	12/23/2002 2:11:50 PM	97.41665	Good
DestAvgTag	12/23/2002 2:11:49 PM	97.41665	Good
DestAvgTag	12/23/2002 2:11:48 PM	97.41665	Good
DestAvgTag	12/23/2002 2:11:47 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:46 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:45 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:44 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:43 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:42 PM	47.41589	Good
DestAvgTag	12/23/2002 2:11:41 PM	97.41665	Good

At the bottom of the window, there are navigation buttons: a double left arrow, a single left arrow, a text field containing "Criteria", a single right arrow, and a double right arrow.

Stop Data Collection

1. Access [Historian Administrator](#) (on page 823).
2. Select **Tags**.

Proficy Historian
System Statistics

[Main](#)
Tags
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

Archive Compression: 0%
 Write Cache Hit: 0%
 Failed Writes: ? (Events)
 Messages Since Startup: ? (Messages)
 Alerts Since Startup: ? (Alerts)
 Calculations: (Enabled)
 Server to Server: (Enabled)
 Max Scada Buffer Duration: 201 (Days)

Server Memory: 28%
 Consumption Rate: ? (MB/Day)
 Historical Tags: 8 (8 Used of 1,000,000 Licensed)
 SCADA Tags: 0 (0 Used of 2,400 Licensed)
 Users: 1 (15 Licensed)
 Alarm Rate: ? (Alarms/Min)
 Alarms Since Startup: ? (Alarms)
 Data Stores: 4 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV_Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Select the tag whose data collection you want to stop.

The screenshot displays the Proficy Historian Tag Maintenance interface. The top navigation bar includes 'Main', 'Tags', 'Collectors', 'DataStores', 'Messages', and 'Help'. Below this, a secondary navigation bar contains 'Search Historian Tag Database', 'Copy/Rename Tag', 'Add Tag Manually', 'Add Tags From Collector', 'Define Enumerated Set', and 'Define User-Defined Types'. The main content area is divided into two sections. On the left, a 'Tags (1)' list shows 'Tag322' under the 'Tag Name' column. This list is highlighted with a red border. On the right, the 'Tag: Tag322' configuration page is shown with tabs for 'General', 'Collection', 'Scaling', 'Compression', 'Calculation', and 'Advanced'. The 'Collection' tab is selected. The 'Data Collection Options' section includes dropdowns for 'Time Assigned By' (set to 'Collector'), 'Time Zone Bias (min)' (set to '0'), 'Time Adjustment' (set to 'Do Not Adjust For Source Time Difference'), and 'Data Store' (set to 'User'). The 'Security' section has dropdowns for 'Read Group', 'Write Group', and 'Administer Group'. The 'Audit' section shows 'Last Modified' as 'Never' and 'Modified By' as an empty field. At the bottom right, there are 'Update' and 'Delete' buttons. A red box highlights the 'Tags (1)' list and the 'Collection' tab.


4. Select **Collection**.

The screenshot shows the Proficy Historian Tag Maintenance interface. The main window is titled "Tag: Tag322" and has several tabs: "General", "Collection", "Scaling", "Compression", "Calculation", and "Advanced". The "Collection" tab is currently selected and highlighted with a red rectangular box. Below the tabs, there are several sections:

- Description:** Contains three text input fields for "Description", "EGU Description", and "Comment".
- StepValue:** Includes two radio buttons: "Enabled" (which is unselected) and "Disabled" (which is selected).
- Spare Configuration:** Contains five text input fields labeled "Spare 1" through "Spare 5".

At the bottom right of the main configuration area, there are two buttons: "Update" and "Delete". On the left side of the interface, there is a "Tags (1)" list showing "Tag322". At the bottom left, there is a note: "Right Mouse For Additional Options * User-Defined and Array tags".

5. For the **Collection** field, select **Disabled**.



6. Select **Update**.

7. To stop data collection on a tag:

- a. From the list in the left-hand window of the page, select a tag.
- b. In the window on the right side of the page, select **Collection**.
- c. For the **Collection** field, select the **Disabled** option.

d. Select **Update**.

The screenshot shows the Proficy Historian Tag Maintenance interface. The main window is titled "Tag: Tag322" and has several tabs: "General", "Collection", "Scaling", "Compression", "Calculation", and "Advanced". The "Collection" tab is selected. Under the "Data Source" section, the "Collector" is set to "SYSTEM4_IFX", "Source Address" is empty, "Data Type" is "Single Float", and "Enumerated Set Name" is empty. The "Is Array Tag" checkbox is unchecked. Under the "Collection Options" section, the "Collection" radio button is set to "Disabled". The "Collection Type" is "Polled", "Collection Interval" is "5" seconds, "Collection Offset" is "0" seconds, and "Time Resolution" is "Seconds". Under the "Condition Based Collection" section, the "Condition Based" radio button is set to "Disabled", "Trigger Tag" is empty, "Comparison" is "=", and "Compare Value" is empty. The "End of Collection Markers" radio button is set to "Enabled". A red text message at the bottom says "Collection is Currently Disabled". The "Update" button is highlighted with a red box.

The data collection for the tag is stopped.

Resume Data Collection

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

Proficy Historian
System Statistics

[Main](#)

[Tags](#)
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

Archive Compression: 0%
 Write Cache Hit: 0%
 Failed Writes: ? (Events)
 Messages Since Startup: ? (Messages)
 Alerts Since Startup: ? (Alerts)
 Calculations: (Enabled)
 Server to Server: (Enabled)
 Max Scada Buffer Duration: 201 (Days)

Server Memory: 28%
 Consumption Rate: ? (MB/Day)
 Historical Tags: 8 (8 Used of 1,000,000 Licensed)
 SCADA Tags: 0 (0 Used of 2,400 Licensed)
 Users: 1 (15 Licensed)
 Alarm Rate: ? (Alarms/Min)
 Alarms Since Startup: ? (Alarms)
 Data Stores: 4 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	


Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Select the tag whose data collection you want to resume.

The screenshot shows the Proficy Historian Tag Maintenance interface. The top navigation bar includes 'Main', 'Tags', 'Collectors', 'DataStores', 'Messages', and 'Help'. Below this, there are several action buttons: 'Search Historian Tag Database', 'Copy/Rename Tag', 'Add Tag Manually', 'Add Tags From Collector', 'Define Enumerated Set', and 'Define User-Defined Types'. The main content area is divided into two sections. On the left, a 'Tags (1)' list shows 'Tag322' under the 'Tag Name' column. This list is highlighted with a red border. On the right, the 'Tag: Tag322' configuration page is displayed, with tabs for 'General', 'Collection', 'Scaling', 'Compression', 'Calculation', and 'Advanced'. The 'Collection' tab is selected. Under 'Data Collection Options', there are dropdown menus for 'Time Assigned By' (set to 'Collector'), 'Time Zone Bias (min)' (set to '0'), 'Time Adjustment' (set to 'Do Not Adjust For Source Time Difference'), and 'Data Store' (set to 'User'). Below this is the 'Security' section with dropdowns for 'Read Group', 'Write Group', and 'Administer Group'. The 'Audit' section shows 'Last Modified' as 'Never' and 'Modified By' as an empty field. At the bottom right of the configuration area are 'Update' and 'Delete' buttons. A footer note at the bottom left of the interface reads: 'Right Mouse For Additional Options * User-Defined and Array tags'.


4. Select **Collection**.



5. For the **Collection** field, select **Enabled**.

The screenshot shows the Proficy Historian Tag Maintenance interface. The main window is titled "Tag: Tag322" and has several tabs: "General", "Collection", "Scaling", "Compression", "Calculation", and "Advanced". The "Collection" tab is selected. Under the "Data Source" section, the "Collector" is set to "SYSTEM4_IFX", "Data Type" is "Single Float", and "Is Array Tag" is unchecked. The "Collection Options" section has the "Collection" radio button selected and highlighted with a red box. Below it, "Collection Type" is "Polled", "Collection Interval" is "5" seconds, "Collection Offset" is "0" seconds, and "Time Resolution" is "Seconds". The "Condition Based Collection" section has "Condition Based" set to "Disabled", "Trigger Tag" is empty, "Comparison" is "=", and "End of Collection Markers" is "Enabled". At the bottom right, there are "Update" and "Delete" buttons. On the left, a "Tags (1)" list shows "Tag322".

6. Select **Update**.



The data collection for the tag is resumed.

Get all the Fields Related to a Tag

1. Access Registry Editor.
2. Create a DWORD (32-bit) registry entry named GetAllTagProps for the collector in the following registry path: `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\Services\OPCCollector*_OPC_Intellution_IntellutionGatewayOPCServer`
3. Provide the value 1 for the registry entry.

Remove A Tag

When you remove a tag, it is removed from the tag database, but all data for that tag is retained in the archive and the tag name cannot be reused. Since the tag data is still available from the archive, you can still reference that tag from within a calculation formula, for example, or by using the Excel Add-In.

If, however, you want to remove the tag data as well from the archive, you can [delete it permanently \(on page 938\)](#).

Whenever you delete/remove tags, the following collectors reload only the modified tag(s) without restarting the collectors.

- OPC Collector
- iFIX Collector
- Calculation Collector
- Simulation Collector
- Server to Server Collector
- PI Collector
- PI Distributor

By default, the On-line Tag Configuration Changes option is enabled, which allows a tag to stop and restart data collection without restarting the collector. If you disable the On-line Tag Configuration Changes option, any changes you make to the tags do not affect collection until you restart the collector. To enable or disable the On-line Tag Configuration Changes option, access Historian Administrator, and then select **Collectors > Advanced**.

Restarting the collector stops and restarts the tag(s) collection and may record bad data samples to the collection. All the collector configuration changes done within a 30-second time frame are batched up together. To collect the modified data faster, update/modify a small set of tags at a time. If the modified tags get zero bad markers and available runtime values at the same time, then precedence is given to available runtime values instead of zero bad markers.

**Tip:**

- To collect the modified data faster, update/modify a small set of tags at a time.
- When updating large sets of tags at the same time, the best practice is to disable the **On-line Tag Configuration Changes** option and restart the collector after modification.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

Proficy Historian
System Statistics

[Main](#)
Tags
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

1 _____

0 1 2 3 4 5 6 7 8 9 10

Archive Compression	0%	Server Memory	28%
Write Cache Hit	0%	Consumption Rate	? (MB/Day)
Failed Writes	? (Events)	Historical Tags	8 (8 Used of 1,000,000 Licensed)
Messages Since Startup	? (Messages)	SCADA Tags	0 (0 Used of 2,400 Licensed)
Alerts Since Startup	? (Alerts)	Users	1 (15 Licensed)
Calculations	(Enabled)	Alarm Rate	? (Alarms/Min)
Server to Server	(Enabled)	Alarms Since Startup	? (Alarms)
Max Scada Buffer Duration	201 (Days)	Data Stores	4 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Select the tag that you want to remove.

The screenshot displays the Proficy Historian Tag Maintenance interface. The top navigation bar includes 'Main', 'Tags', 'Collectors', 'DataStores', 'Messages', and 'Help'. The toolbar contains 'Search Historian Tag Database', 'Copy/Rename Tag', 'Add Tag Manually', 'Add Tags From Collector', 'Define Enumerated Set', and 'Define User-Defined Types'. The main area is titled 'Tag: Tag322' and features several tabs: 'General', 'Collection', 'Scaling', 'Compression', 'Calculation', and 'Advanced'. The 'Data Collection Options' section includes:

- Time Assigned By: Collector
- Time Zone Bias (min): 0
- Time Adjustment: Do Not Adjust For Source Time Difference
- Data Store: User

 The 'Security' section includes:


- Read Group: [Empty]
- Write Group: [Empty]
- Administer Group: [Empty]

 The 'Audit' section includes:

- Last Modified: Never
- Modified By: [Empty]

 At the bottom right, there are 'Update' and 'Delete' buttons. A red box highlights the 'Tags (1)' list on the left, which contains 'Tag322'. A tooltip at the bottom left of the list indicates 'Right Mouse For Additional Options * User-Defined and Array tags'.

4. Select **Delete**.



The **Delete Tags** window appears.

5. Select **Remove Tag from System**, and then select **OK**.

A message box appears, asking you to confirm that you want to remove the tag.

6. Select **Yes**.

The tag is removed.

Deleting Tags Permanently

When you delete a tag, the tag as well as all the data for that tag is removed from the archive and the tag name is available for reuse. You can no longer query the data for that tag. If, however, you want to just remove the tag, but retain the tag data, refer to [Remove A Tag \(on page 934\)](#).

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

Proficy Historian
System Statistics

[Main](#)
Tags
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

1 _____

0 1 2 3 4 5 6 7 8 9 10

Archive Compression	0%	Server Memory	28%
Write Cache Hit	0%	Consumption Rate	? (MB/Day)
Failed Writes	? (Events)	Historical Tags	8 (8 Used of 1,000,000 Licensed)
Messages Since Startup	? (Messages)	SCADA Tags	0 (0 Used of 2,400 Licensed)
Alerts Since Startup	? (Alerts)	Users	1 (15 Licensed)
Calculations	(Enabled)	Alarm Rate	? (Alarms/Min)
Server to Server	(Enabled)	Alarms Since Startup	? (Alarms)
Max Scada Buffer Duration	201 (Days)	Data Stores	4 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	


Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Select the tag that you want to delete.

The screenshot displays the Proficy Historian Tag Maintenance interface. At the top, the title bar reads "Proficy Historian Tag Maintenance" and includes navigation icons for Main, Tags, Collectors, DataStores, Messages, and Help. Below this is a secondary menu with options: Search Historian Tag Database, Copy/Rename Tag, Add Tag Manually, Add Tags From Collector, Define Enumerated Set, and Define User-Defined Types. The main content area is split into two panes. The left pane, titled "Tags (1)", contains a table with one entry: "Tag Name" and "Tag322". This pane is highlighted with a red border. The right pane, titled "Tag: Tag322", shows configuration tabs: General, Collection, Scaling, Compression, Calculation, and Advanced. The "General" tab is active, displaying sections for "Data Collection Options", "Security", and "Audit". The "Data Collection Options" section includes fields for "Time Assigned By" (set to "Collector"), "Time Zone Bias (min)" (set to "0"), "Time Adjustment" (set to "Do Not Adjust For Source Time Difference"), and "Data Store" (set to "User"). The "Security" section has fields for "Read Group", "Write Group", and "Administer Group". The "Audit" section shows "Last Modified" as "Never" and "Modified By" as an empty field. At the bottom right of the configuration pane are "Update" and "Delete" buttons. A footer note at the bottom left of the interface states: "Right Mouse For Additional Options * User-Defined and Array tags".

4. Select **Delete**.



The **Delete Tags** window appears.

5. Select **Permanently Remove Tags From System**, and then select **OK**.

A message box appears, asking you to confirm that you want to delete the tag.

6. Select **Yes**.

The tag is deleted.

About User-Defined Data Types

Sometimes, a single tag cannot store all the required details of a parameter. For example, if you want to store the name, address, and phone number of the manufacturer of a machine, it may not be feasible to store all these details in a single tag, which uses a single data type. In such cases, you can create a user-defined data type (UDT), which includes one or more fields, and then apply that type to Historian tags. Each of these fields in a UDT can contain a different data type based on your requirement.

The following conditions apply when working with a UDT:

- You must have appropriate security permissions to create, modify, and delete a UDT. The type can have its own Administrator security group.
- You cannot create an array tag that uses a UDT.
- UDTs cannot have fields of Scaled or FixedString data types.
- Scaling, collector compression, and archive compression do not apply to UDT tags.
- You cannot associate an enumerated set with a UDT tag.
- A UDT supports maximum 100 fields.

Manage User-Defined Data Types


You can create a [user-defined data type \(UDT\)](#) (on page 719) and assign it to multiple tags. A UDT can have up to 100 fields and must have at least one field.

1. [Access Historian Administrator](#) (on page 823).
2. Select **Tags**.

The screenshot shows the Proficy Historian System Statistics interface. The 'Tags' tab is highlighted with a red box. The interface displays various system metrics and status information.

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

3. Select **Define User-Defined Types**.



The **Define User-Defined Types** window appears.

4. To create a UDT:

- a. Select **Create New Type**.
- b. Enter values as described in the following table.

Field	Description
Type Name	Enter a unique name for the UDT.
Description	Enter a description for the UDT.
Store Individual Quality	Select the check box to store field-level quality. If this check box is cleared, the data sample will have a single quality similar to how an array tag works. Storing individual qualities consumes more disk space.

Field	Description
Administer Group	Specify the Windows Security Group that you want to assign to the UDT.

c. Add at least one **Field** to the UDT.

d. Select **Save Type**.

The UDT is created.

5. To add a field to a UDT:

a. Select **New Field**.

b. Enter values as described in the following table.

Field	Description
Field Name	Enter a name for the field.
Master Field	Select this check box if this field is a master field. Only one field can be the Master Field in a UDT.
Field Description	Enter a description for the field.
Field Data Type	Specify the data type of the field.

c. Select **Save Field**.

The field is added to the UDT.

6. To delete a field from a UDT:

a. Select the field that you want to delete.

b. Select **Delete Field**.

7. To delete a UDT, right-click the UDT that you want to delete, and then select **Delete Selected Type**.




Note:

You cannot delete a UDT if there are tags still using it.

8. To set a source address for a field:

- a. Select the field for which you want to set the source address.




- b. Browse and select the tag that you want to assign, and then select **Save Source Address > OK**.

The source address for the multifield tag is set.

9. To view the last 10 values of a tag:

- a. Right-click the tag (a tag indicated with *), and select **Last 10 values**.

The **List of Fields** window appears.



- b. Select the field from the list, and then select **OK**.

The last ten values of the field appear.

10. To view the trend chart of a tag:

- a. Right-click the tag, and then select **Trend**.

The trend chart of the tag values appears.

- b. If needed, modify the time period and other parameters by selecting **Criteria**. In the **criteria string** field, you can enter the sampling mode, calculation mode, and/or query modifiers.

Query modifiers are used to specify various ways of retrieving data from Historian. Sampling modes specified with criteria strings takes precedence over any mode specified in the Sampling field.

Request raw data with only good quality by specifying the criteria string: `RAWBYTIME#ONLYGOOD`

- c. Select **OK**.

The trend chart is plotted again with the new criteria. You can scroll back and forth on the x-axis time scale by selecting on the single and double left and right arrows at the bottom of the page.

Assign/Remove Tags from a User-Defined Data Type

There are two ways to assign tags to a user-defined types. This topic describes both these ways. User Defined tags are indicated with '*' in the Tags section. If the desired type is not already created, you can create it while assigning it. You can select multiple tags from the Tags list and assign the same UDT to all of them at once.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

The screenshot shows the Proficy Historian System Statistics interface. The 'Tags' tab is selected and highlighted with a red box. The interface displays various system metrics and sections:


- System Statistics:**
 - Receive Rate: ? (Events/Min)
 - Archive Compression: 0%
 - Write Cache Hit: 0%
 - Failed Writes: ? (Events)
 - Messages Since Startup: ? (Messages)
 - Alerts Since Startup: ? (Alerts)
 - Calculations: (Enabled)
 - Server to Server: (Enabled)
 - Max Scada Buffer Duration: 201 (Days)
 - Server Memory: 28%
 - Consumption Rate: ? (MB/Day)
 - Historical Tags: 8 (8 Used of 1,000,000 Licensed)
 - SCADA Tags: 0 (0 Used of 2,400 Licensed)
 - Users: 1 (15 Licensed)
 - Alarm Rate: ? (Alarms/Min)
 - Alarms Since Startup: ? (Alarms)
 - Data Stores: 4 (20 Licensed)
- Collectors:**

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN JAVA DEV Simulation	Unknown	SAN JAVA DEV	0	0	%	0	
- Alerts:**


Timestamp	Topic	Message
-----------	-------	---------

3. To assign a UDT to a tag from the **Collection** section:

a. Select **Collection**.



b. Select the tag for which you want to assign a UDT.



- c. In the **Data Type** field, select **MultiField**.
The **User Defined Type** field appears.
 - d. In the **User Defined Type** field, browse and select the UDT that you want to associate with the tag, and then select **OK**.
If the type has not already been created, create a type now and then continue associating it with the tag. For more information, refer to [Create a User Defined Type \(on page 942\)](#).
 - e. Select **Update**.
The UDT is assigned to the tag.
4. To assign a UDT to a tag from the **Add Tag Manually** window:
 - a. Select **Add Tag Manually**.
The **Add Tag Manually** window appears.
 - b. Enter values as described in the following table.


Field	Description
Collector Name	Select the collector instance in which the tag has been added.
Source Address	Browse and select the source address of the tag.
Data Type	Select MultiField .
User Defined Type	Browse and select the UDT that you want to assign the tag.
Time Resolution	Select the time resolution.

c. Select **OK**.

The UDT is assigned to the tag.

5. To remove a UDT from a tag:

a. Select the tag from which you want to remove the UDT.



b. Clear the value in the **User Defined Type** field.

c. In the **Data Type** field, select a data type.

d. Select **Update**.

The UDT is removed from the tag, and the new data type is assigned.

Managing Enumerated Data Sets

An enumerated data set provides an enhanced way of displaying data. It enables you to retrieve numeric data as string state values. You can use the string values in reports, charts, etc.

An enumerated set contains several states. A state is the number-string value pair in a set. It contains a set of numeric values and their corresponding string values. You can define an enumerated set for a single value or a range of values. These state values are defined for data states stored in Data Archiver. Data is retrieved using the value of the state. You have to define state values within a set to assign enumerated values.

Table 68. Example of a Single-Value Enumerated Set

State Name	State Value
Manual	0
Automatic	1

Table 69. Example of a Range-of-Values Enumerated Set:

State Name	State Value
ON	0 to 100
OFF	101 to 200

State names can be duplicated. If duplicated states exist, take precautions to avoid unpredictable results. For example, a tag is associated with an enumerated set defined as follows.

State Name	State Value
0	Open
1	Close
2	Close
2	Open

The server will return unpredictable results due to the State Name duplication for an input of 2.



Note:


You cannot assign an enumerated set to an array tag.

1. Access [Historian Administrator](#) (on page 823).
2. Select **Tags**.

The screenshot shows the Proficy Historian System Statistics page. The 'Tags' menu item is highlighted with a red box. Below the navigation bar, there are several performance metrics and a table of collectors.

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV_Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

3. Select **Define Enumerated Set**.



The **Define Enumerated Set** window appears.

4. To create a set:

- a. Select **Create New Set**.
- b. Enter values as described in the following table.

Field	Description
Set Name	Enter a name for the set.
Description	Enter a description for the set.
Enumerate By	Specify whether you want to define a single value or a range of values. A single value is best used with integer values because they match exactly. A range of values can be used with floating point val-

Field	Description
	ues because they may not match exactly due to rounding.

c. Add a state.

d. Select **Save Set**.

The enumerated set is created.

5. To create a state:

a. In the **State** section, select **New State**.

b. In the **Enumerate by** field, specify whether you want to use a single value or a range of values.

If you select **Single Value**, the **State Name**, **State Value**, and **Description** fields appear. If you select **Range**, the **State Name**, **Start Range**, **End Range**, and **Description** fields appear.

c. Enter values in the respective fields.

Enter only numeric values in the **State Values** field; string values such as ON/OFF are not supported.

d. Select **Save to List**.

The state is created and added to the enumerated set.

6. To delete a state:

a. To delete a *single* state, select the state and select **Delete State**. To delete *all* the states, select **Select All**, then select **Delete State**.

A message appears, asking you to confirm that you want to delete the state.

b. Select **Yes**.

The state is deleted.

7. To delete a set:

a. Right-click the set that you want to delete, and then select **Delete Selected Set**.

A message appears, asking you to confirm that you want to delete the set.

b. Select **Yes**.

The enumerated set is deleted.

Assign/Remove Tags from Enumerated Sets

To view data for a tag in an enumerated state value format, assign a set to the tag. You can remove an assigned set from a tag to assign a new tag or not assign any tag at all.



Note:

You cannot assign enumerated sets to array tags.

1. Access [Historian Administrator](#) (on page 823).
2. Select **Tags**.

Proficy Historian System Statistics

Main **Tags** Collectors DataStores Messages Help

Receive Rate ? (Events/Min)

1

0 1 2 3 4 5 6 7 8 9 10

Archive Compression 0%

Write Cache Hit 0%

Failed Writes ? (Events)

Messages Since Startup ? (Messages)

Alerts Since Startup ? (Alerts)

Calculations (Enabled)

Server to Server (Enabled)

Max Scada Buffer Duration 201 (Days)

Server Memory 28%

Consumption Rate ? (MB/Day)

Historical Tags 8 (8 Used of 1,000,000 Licensed)

SCADA Tags 0 (0 Used of 2,400 Licensed)

Users 1 (15 Licensed)

Alarm Rate ? (Alarms/Min)

Alarms Since Startup ? (Alarms)

Data Stores 4 (20 Licensed)

Collectors Auto Refresh

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	

Alerts Show Alerts Auto Refresh

Timestamp	Topic	Message
-----------	-------	---------

3. Select **Collection**.

The screenshot displays the Proficy Historian Tag Maintenance interface. The top navigation bar includes 'Main', 'Tags', 'Collectors', 'DataStores', 'Messages', and 'Help'. Below this, there are several action buttons: 'Search Historian Tag Database', 'Copy/Rename Tag', 'Add Tag Manually', 'Add Tags From Collector', 'Define Enumerated Set', and 'Define User-Defined Types'. The main area is divided into two sections. On the left, a 'Tags (1)' list shows 'Tag322' selected. On the right, the 'Tag: Tag322' configuration panel is shown with the 'Collection' tab selected. The 'Collection' tab contains the following settings:

- Data Source:** Collector (SYSTEM4_IFX), Source Address (empty), Data Type (Single Float), Enumerated Set Name (empty).
- Is Array Tag:**
- Collection Options:** Collection (Enabled), Collection Type (Polled), Collection Interval (5 Seconds), Collection Offset (0 Seconds), Time Resolution (Seconds).
- Condition Based Collection:** Condition Based (Disabled), Trigger Tag (empty), Comparison (=), Compare Value (empty), End of Collection Markers (Enabled).

Buttons for 'Update' and 'Delete' are located at the bottom right of the configuration panel. A note at the bottom left of the tag list states: 'Right Mouse For Additional Options * User-Defined and Array tags'.

4. Select the tag that you want to assign/remove.

The screenshot displays the Proficy Historian Tag Maintenance interface. The top navigation bar includes links for Main, Tags, Collectors, DataStores, Messages, and Help. Below this, there are several action buttons: Search Historian Tag Database, Copy/Rename Tag, Add Tag Manually, Add Tags From Collector, Define Enumerated Set, and Define User-Defined Types.

The main content area is divided into two sections. On the left, a table titled "Tags (1)" lists the tag "Tag322". This table is highlighted with a red border. Below the table, a note reads: "Right Mouse For Additional Options * User-Defined and Array tags".

On the right, the configuration page for "Tag: Tag322" is shown. It features several tabs: General, Collection, Scaling, Compression, Calculation, and Advanced. The "Data Collection Options" section includes:

- Time Assigned By: Collector
- Time Zone Bias (min): 0
- Time Adjustment: Do Not Adjust For Source Time Difference
- Data Store: User

 The "Security" section includes:

- Read Group: [Empty dropdown]
- Write Group: [Empty dropdown]
- Administer Group: [Empty dropdown]


 The "Audit" section shows:

- Last Modified: Never
- Modified By: [Empty field]

 At the bottom right of the configuration area, there are "Update" and "Delete" buttons.

5. To assign a set to a tag:

a. In the **Enumerated Set Name** field, select .



The **Define Enumerated Set** window appears.

b. From the **List of Enumerated Sets** section, select the enumerated set that you want to assign, select **Set**, and then select **OK**.

The **Enumerated Set** field is populated with the enumerated set that you have selected.

c. Select **Update**.

The set is now assigned to the tag and you can view the data in the enumerated state value format.

6. To remove an assigned set from a tag:

- a. Clear the value in the **Enumerated Set Name** field.

The screenshot shows the Proficy Historian Tag Maintenance interface. The 'Tag: Tag322' configuration window is open, showing the 'Data Source' section. The 'Enumerated Set Name' field is highlighted with a red box, indicating it should be cleared. The 'Collection Options' section shows 'Collection' is enabled and 'Collection Type' is 'Polled'. The 'Condition Based Collection' section shows 'Condition Based' is disabled.

- b. Select **Update**.

The enumerated set is no longer assigned to the tag.

Managing Collectors

About Collectors

Collectors are used to collect data from various data sources and send it to Historian. For a list of collectors and their usage, refer to [About Historian Data Collectors \(on page 1990\)](#).

After you install collectors and Remote Management Agent, the following artefacts will be available:

- **Executable files:** These files are required to add a collector instance.
- **Instances of the following collectors:**
 - The iFIX collector
 - The iFIX Alarms & Events collector

- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

These instances will be created only if iFIX and/or CIMPLICITY are installed on the same machine as the collectors.

- **The Remote Collector Management agent:** Provides the ability to manage collectors remotely.

To send data using a collector, you must:

1. [Install collectors \(on page 142\).](#)

You can install collectors on multiple Windows machines. These machines can be on-premises or on a virtual private cloud (VPC).

2. Create a collector instance.

Access/Modify a Collector

1. [Access Historian Administrator \(on page 823\).](#)
2. Select **Collectors**.

The screenshot displays the Proficy Historian System Statistics interface. At the top, there are navigation tabs: Main, Tags, **Collectors** (highlighted with a red box), DataStores, Messages, and Help. Below the tabs, there are several performance metrics and a line graph. The 'Receive Rate' is 155 (Events/Min). Other metrics include Archive Compression (39%), Write Cache Hit (100%), Failed Writes (0), Messages Since Startup (24), Alerts Since Startup (13), Calculations (Enabled), Server to Server (Enabled), Max Scada Buffer Duration (201 Days), Server Memory (32%), Consumption Rate (0.3 MB/Day), Historical Tags (5), SCADA Tags (0), Users (1), Alarm Rate (0), Alarms Since Startup (0), and Data Stores (3).

Below the metrics, there is a section for 'Collectors' with a table showing the status of collector instances. The table has columns for Collector, Status, Computer, Report Rate, Overruns, Compression, Out Of Order, and Redundancy. One instance is listed: 'SYSTEM4 #FX' with a status of 'Stopped'.


Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SYSTEM4 #FX	Stopped	System4	0	0	%	0	

At the bottom of the screenshot, there is an 'Alerts' section with a table showing the status of alerts. The table has columns for Timestamp, Topic, and Message. The 'Show Alerts' checkbox is checked.

Timestamp	Topic	Message
-----------	-------	---------

A list of collectors appears.

3. Select the collector whose details you want to access/modify.



4. As needed, modify values as described in the following tables, and then select **Update**.

Table 70. The General Section

Field	Description
Collection Status Field	The current operating status of the collector. Contains one of the following values: <ul style="list-style-type: none"> ◦ Running: The collector is operating and collecting data. ◦ Stopped: The collector is in pause mode and not collecting data. ◦ Unknown: The status information about the collector is unavailable at present, perhaps as a result of a lost connection between collector and server or because the collector was shut down improperly.

Field	Description
	You can specify whether you want to pause or resume data collection.
Total Events Collected	The total number of events collected from the data source by the collector.
Total Events Reported	The total number of events reported to the archive from the collector. This number may not match the Total Events Collected value due to collector compression.
Description	The name of the collector.
Collector Type	The type of the collector.
Computer Name	The machine name of the computer on which the collector is installed.
Memory Buffer Size (MB)	<p>The size of the memory buffer currently assigned to the store-and-forward function. The memory buffer stores data during short-term or momentary interruptions of the server connection; the disk buffer handles long duration outages. To estimate the size you need for this buffer, you need to know how fast the collector is trying to send data to the server and how long the server connection is likely to be down. With those values and a safety margin, you can compute the required size of the buffer.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: If you enter a new value for this parameter, the change is effective the next time you restart the collector.</p> </div>
Minimum Free Space (MB)	The minimum free disk space that must be available on the computer. If the minimum space required is not available when the collector starts, the collector will shut down.

Table 71. The Tags Section

Field	Description
Add Prefix to Tag	A prefix that is automatically added to all tag names when you add tags.
Naming Convention	When digital sets are automatically added via the OSI PI Collector:

Field	Description
	<ul style="list-style-type: none"> ◦ The enumerated set added to Historian is prefixed using the value configured here. For Example, if "IP- 4LJPD02." has been configured as the tag prefix value, then the digital set with name "SYSTEMSET" in PI Historian will be added as an enumerated set with name "IP-4LJPD02.SYSTEMSET" in Historian. ◦ If the value of the tag prefix is modified, then a new set of enumerated sets prefixed with the updated value will be added to Historian server. The enumerated sets prefixed with the old value will not be deleted and will not receive any later updates.
Collection Interval	<p>The time required to complete a poll of a given tag on the collector. It is also used in unsolicited collection. In effect, it specifies how frequently data can be read from a tag. The collection interval can be individually configured for each tag.</p> <div data-bbox="570 890 1419 1115" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: To avoid collecting repeat values with the OPC collector when using device timestamps, specify a collection interval that is greater than the OPC server update rate.</p> </div>
Collection Type	Indicates whether this collector is configured for polled or unsolicited data collection.
Time Assigned By	Indicates whether the timestamp for the data value is provided by the collector or the data source.
Collector Compression	Indicates whether collector compression (on page 660) is enabled as a default setting. This option is overridden by tag-level settings.
Deadband	The default setting of the collector compression deadband in absolute or percentage range values.
Compression Timeout	The default setting for the collector compression time-out for tags added through the Add Multiple Tags From Collector window. You must enable collector compression to use this field.
Spike Logic Control	Indicates whether incoming data samples for spikes are captured in tag values. If spike logic is enabled, a sample of equal value to the previous-

Field	Description
	ly archived sample is inserted into the archive in front of the spike value. For more information, refer to Enable Spike Logic (on page 970) .

Table 72. The Advanced Section

Field	Description
On-line Tag Configuration Changes	Indicates whether you can make changes to tags without having to restart the collector. If you disable this option, any changes you make to tags do not affect collection until you restart the collector.
Browse Source Address Space	Indicates whether you want the collector to respond to requests to browse the tags in the source. You may sometimes want to disable this feature to reduce processing load on the collector.
Synchronize Timestamps to Server Time	Adjusts all outgoing data timestamps to match the server clock. This option is not applicable when you configure timestamps to be provided by the data source. Note that this does not change collector times to match the server time; it adds or subtracts an increment of time to compensate for the relative difference between the clocks of the server and collector, independent of time zone or day light savings time (DST) differences. If the collector system clock is greater than 15 minutes ahead of the archiver system clock, and the Synchronize Timestamps to Server option is disabled, data will not be written to the archive.
Source/Device Timestamps	The time source for the timestamps. This field applies only if you are using source timestamps. The collector uses this field to determine whether the timestamps coming from the data source are in local machine time or UTC.
Delay Collection at Startup	The number of seconds to delay collection on startup (after loading its tag configuration).
Rate Output Address	Address in the source database into which the collector writes the current value of the events/minute output, letting an operator or the HMI/SCADA application know the performance of the collector. This should be connected to a writable analog field. The value is written once a minute.

Field	Description
	<p>For an iFIX collector, use an iFIX tag for the output address. Enter the address in the following format: NODE.TAG.FIELD (for example, MyNode.MySIM_AO.F_CV).</p> <p>For an OPC collector, use a writable OPC address in the server. Refer to your OPC documentation for more information.</p>
Status Output Address	<p>Address in the source database into which the collector writes the current value of the collector status, letting an operator or the HMI/SCADA application know the current status of the collector.</p> <p>This address should be connected to a writable text field of at least 8 characters. This value is only updated upon a change in status of the collector.</p> <p>For an iFIX collector, use TX tag for the output address. Enter the address in the following format: NODE.TAG.FIELD (for example, MyNode.MyCollector_TX.A_CV).</p> <p>For an OPC collector, use an OPC address in the server. Refer to your OPC documentation for more information.</p>
Heartbeat Output Address	<p>Address in the source database into which the collector writes the heartbeat signal output. This address should be connected to a writable analog field.</p> <p>For an iFIX collector, use an iFIX tag for the output address. Enter the address in the following format: NODE.TAG.FIELD (for example, MyNode.MyCollector_AO.F_CV).</p> <p>For an OPC collector, use the OPC address in the server. Refer to your OPC documentation for more information.</p> <p>The data collector writes the value of 1 to this location every 60 seconds while it is running. You can program the iFIX database to generate an alarm if the Heartbeat Output Address is not written once every 60 seconds, notifying you that the data collector has stopped.</p>

Table 73. The Performance Section

Section	Description
Report Rate	Displays the average rate at which data is coming into the server from the collector. This is a general indicator of load on the Historian collector. Since this chart displays a slow trend of compressed data, it may not always match the instantaneous value of report rate.
Compression	Displays the effectiveness of collector compression. If the chart displays a low current value, you can widen the compression deadbands to pass fewer values and increase the effect of compression.
Overruns	<p>Displays the value at which data overruns are occurring. This value is calculated by the following equation:</p> <div style="background-color: #f0f0f0; padding: 5px; margin: 5px 0;"> $\text{OVERRUN_PCT} = \text{OVERRUNS} / (\text{OVERRUNS} + \text{TOTAL_EVENTS_COLLECTED})$ </div> <p>Overruns are a count of the total number of data events not collected. In normal operation and under normal conditions, the current value should always be zero. If the current value is not zero, which indicates that data is being lost, you should take steps to reduce peak load on the system by increasing the collection interval.</p>

Table 74. The Redundancy Section

Field	Description
Redundant Collector	Indicates that this is a redundant collector.
Backup For	<p>The primary collector.</p> <div style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: This configuration will be preserved if you disable collector redundancy. This allows you to temporarily take a redundant collector offline without losing its configuration.</p> </div>
Backed Up By	The name of the collector providing redundancy for the primary collector.

Field	Description
Collector Status (Status)	The current status of the primary collector.
Redundancy Status	The current redundancy status of the collector. If a secondary collector has been activated, this field will appear.
Make Active Collector Now	Select this button to bring the selected collector online immediately. This is useful for testing, or in situations where the primary collector must be brought offline quickly.
Collector Status (Failover Triggers)	Indicates whether the collector will failover if the status changes to Unknown.
Watchdog Tag	The tag to use to determine the status of the collector. If the watchdog tag meets any of the conditions specified below, the secondary collector will be brought online to replace it.
Failover on Bad Quality	Indicates whether the secondary collector must be promoted when a data sample from the watchdog tag is received with bad quality. Failover happens on every write of a bad data sample to the watchdog, not just on the transition from good to bad quality.
Failover When Value Transitions from Zero	Indicates whether the secondary collector is promoted when a data sample from the watchdog tag with a non-zero value is received from the primary collector. Failure happens every time when a non-zero value is received, not just when the value promotes from zero to non-zero value.
Failover When No Value Changes for X Seconds	Indicates that the secondary collector is promoted when no data value changes have been received within the time period specified. This could be tied into a heartbeat status indicator. The value is checked every 5 seconds. To prevent failure, there must be a value change.

The Actions Buttons

All tabs in the Collector Maintenance screen contain action buttons. Click a button to perform the action indicated by the name.

Button	Function
Recalculate	Recalculate collector data for a specified period.
Add Tags	Browse and add tags from this collector to the archiver.
Update	Apply all parameter changes you have made on any tabs in this screen. To cancel changes and return to the original values or settings, open a different screen and then return to the Collector Maintenance screen.
Delete	Delete the selected collector. You can choose whether you want to delete only the collector or the collector and its tags.

Delete a Collector

When you delete a collector, all of its tags are deleted from the Historian database.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Collectors**.

Proficy Historian
System Statistics

Main Tags **Collectors** DataStores Messages Help

Receive Rate 155 (Events/Min)

Archive Compression 39%
 Write Cache Hit 100%
 Failed Writes 0 (Events)
 Messages Since Startup 24 (Messages)
 Alerts Since Startup 13 (Alerts)
 Calculations (Enabled)
 Server to Server (Enabled)
 Max Scada Buffer Duration 201 (Days)

Server Memory 32%
 Consumption Rate 0.3 (MB/Day)
 Historical Tags 5 (5 Used of 1,000,000 Licensed)
 SCADA Tags 0 (0 Used of 2,400 Licensed)
 Users 1 (15 Licensed)
 Alarm Rate 0 (Alarms/Min)
 Alarms Since Startup 0 (Alarms)
 Data Stores 3 (20 Licensed)

Collectors Auto Refresh

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SYSTEM4 #FX	Stopped	System4	0	0	%	0	

Alerts Show Alerts Auto Refresh

Timestamp	Topic	Message
-----------	-------	---------

A list of collectors appears.

3. Select the collector whose details you want to delete.

The screenshot shows the Proficy Historian Collector Maintenance interface. The 'Collectors' table on the left is highlighted with a red box, showing a single entry: 'SYSTEM4_IFX' on 'System4'. The right pane shows the configuration for 'Collector: SYSTEM4_IFX', including status (Stopped), description, and resource settings.

Name	Computer
SYSTEM4_IFX	System4

Collector: SYSTEM4_IFX

General | Configuration | Tags | Advanced | Performance | Redundancy

Status

Collection Status: Stopped
 Resume Collection Pause Collection

Total Events Collected: 0
 Total Events Reported: 0

Description

Description: SYSTEM4_IFX
 Collector Type: IFX

Resources

Computer Name: System4
 Memory Buffer Size (MB): 20
 Minimum Free Space (MB): 150

Recalculate | Add Tags | Update | Delete

4. Select **Delete**.

A message appears, asking you to confirm that you want to delete the collector.

5. Select **Yes**.


The collector is deleted.

Enable Spike Logic


When compression is enabled in the Historian archive, only the first instance in a series of data falling within a deadband range will be collected to the Historian archive. When that data is plotted using interpolation, false values are inserted into the chart to create a smooth trend between intervals in a given time period. In most cases, interpolation gives a reasonable portrayal of the actual data for a given time period.

Unfortunately, in the event of a spike in data values, an unrealistic set of samples is created when the data is plotted. Instead of showing the results of compression (the same values over a series of intervals), a rising or falling slope is created in the chart. This gives the impression that values for a given time stamp are higher or lower than they actually were. The figure below shows the difference between the raw

data for a series of samples, and how the samples would be plotted if data compression were enabled, assuming all values between 10 and 20 are in the deadband range.



Spike logic monitors incoming data samples for spikes in a tag's values. If spike logic is enabled, a sample of equal value to the previously archived sample is inserted into the archive in front of the spike value. The time stamp of the inserted value is determined by your polling interval. If samples are collected at one-second intervals, the inserted sample's time stamp will be one second before the spike. This helps identify the spike, and retains a more accurate picture of the data leading up to it, as shown in the following image.



1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Collectors**.

Proficy Historian
System Statistics

Main Tags **Collectors** DataStores Messages Help

Receive Rate 155 (Events/Min)

Archive Compression 39%
Write Cache Hit 100%
Failed Writes 0 (Events)
Messages Since Startup 24 (Messages)
Alerts Since Startup 13 (Alerts)
Calculations (Enabled)
Server to Server (Enabled)
Max Scada Buffer Duration 201 (Days)

Server Memory 32%
Consumption Rate 0.3 (MB/Day)
Historical Tags 5 (5 Used of 1,000,000 Licensed)
SCADA Tags 0 (0 Used of 2,400 Licensed)
Users 1 (15 Licensed)
Alarm Rate 0 (Alarms/Min)
Alarms Since Startup 0 (Alarms)
Data Stores 3 (20 Licensed)

Collectors Auto Refresh

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SYSTEM4 #FX	Stopped	System4	0	0	%	0	

Alerts Show Alerts Auto Refresh

Timestamp	Topic	Message
-----------	-------	---------

A list of collectors appears.

3. Select the collector to which you want to apply spike logic.

The screenshot displays the Proficy Historian Collector Maintenance interface. The top navigation bar includes links for Main, Tags, Collectors, DataStores, Messages, and Help. The main content area is divided into two sections. On the left, a table titled 'Collectors' lists the collector 'SYSTEM4_iFIX' associated with the computer 'System4'. This table is highlighted with a red border. On the right, the configuration page for 'Collector: SYSTEM4_iFIX' is shown, with tabs for General, Configuration, Tags, Advanced, Performance, and Redundancy. The 'Status' section indicates the collector is 'Stopped' and provides options to 'Resume Collection' or 'Pause Collection'. The 'Description' section shows the collector's name and type. The 'Resources' section specifies the computer name, memory buffer size, and minimum free space. At the bottom, there are buttons for 'Recalculate', 'Add Tags', 'Update', and 'Delete'.

Name	Computer
SYSTEM4_iFIX	System4

Collector: SYSTEM4_iFIX

General | Configuration | **Tags** | Advanced | Performance | Redundancy

Status

Collection Status: Stopped
 Resume Collection Pause Collection

Total Events Collected: 0
Total Events Reported: 0

Description


Description: SYSTEM4_iFIX
Collector Type: iFIX

Resources

Computer Name: System4
Memory Buffer Size (MB): 20
Minimum Free Space (MB): 150

Recalculate Add Tags Update Delete

4. Select **Tags**.



5. Under **Default Compression**, in the **Spike Logic Control** field, select **Enabled**, and then select one of the following options:
 - **Multiplier**: Specifies how much larger a spike value must be than the deadband range before spike logic will be invoked. For example, if you enter 3, and the deadband percentage was set to 5%, spike logic will not be invoked until the difference between the spike value and the previously archived data point is 15% of the EGU range.
 - **Interval**: Specifies how many samples must have been compressed before the spike logic will be invoked. For example, if you enter 4, and 6 values have been compressed since the last archived data sample, spike logic will be invoked.

6. Select **Update**.

The spike logic is enabled.

About Collector Redundancy

Collector redundancy decreases the likelihood of lost data due to software or hardware failures. It ensures that collection of your data remains uninterrupted. It uses two or more collectors that gather data from a single source.

**Note:**

Collector redundancy is not available and supported for the following collectors:

- File Collector.
- Calculation Collector.
- Python Collector.
- Server-to-Server Collector.
- Server-to-Server Distributor.
- OSI PI Collector.
- OSI PI Distributor.

All collectors in the group actively gather the same tags from a data source but only the *active* collector forwards its samples to the Historian server. The non-active (standby) collectors buffer their data against failover of the active collector. The Historian server actively monitors the health of the redundant collectors and will automatically switch to a backup if certain trigger conditions are met.

Trigger conditions: You can configure the following triggers:

- The collector is stopped.
- The collector sends bad quality data for a specified tag (called the watchdog tag).
- The values of the watchdog tag do not change for a specified duration.

If any of these trigger conditions are met, the primary collector goes into the standby mode, and the secondary collector becomes active. That means, data is then collected by the secondary collector. Similarly, if the secondary collector satisfies the trigger conditions, it goes into the standby mode, and the primary collector becomes active.

You can also manually trigger the failover.

For instructions on configuring collector redundancy, along with settings the triggers, refer to [Configure Collector Redundancy \(on page 651\)](#).

Synchronized Configuration: The configuration for each redundant collector is managed by the Historian server. If you change the configuration on one redundant collector, all other collectors will be updated automatically with the new configuration.

**Note:**

Redundant collectors must be of the same collector type.

Offline Collectors: To reduce the possibility of lost data, a collector will immediately send its buffered data to the Historian archiver when brought online. The Historian server will ignore any data that is already collected in the archive.

Adding Tags to a Redundant Collector: To add tags in a redundant collector system, you must add them to the primary collector. If tags are added to a redundant collector, data for these tags will not be collected until the redundant collector is taken out of the redundant system. If the primary collector is not available, you must add the tag manually.



Note:

- Use polled tags only as watchdog tags.
- Historian redundant collector configuration does not force the active Historian collector to run on the active iFIX SCADA, since both redundant collectors provide data. Also, when both iFIX SCADAS become active, they lose connection with each other.

Important information about the failover of redundant collectors:

- In the **Redundancy** section of the **Collectors** page, you can use the **Make Active Collector Now** button to manually force a failover to a backup collector.
- In an Enterprise system, collector redundancy failover happens only after 5 minutes after a tag change. You must select the **Make Active Collector Now** button after the first 5 minutes for the failover to happen.

Also, when you shut down an active collector, it does failover. However, if there was a tag change then shutting down the active collector does not cause failover immediately, it is just delayed by 5 minutes. There will not be any data loss since the backup collector sends data for the past 15 minutes when it becomes active.

- Failover precedent is cyclical; the last collector in a redundant group will automatically failover to the first collector in the group.
- Configuration Manager must be running for failover to happen in a mirrored environment.

Configure Redundant Collectors and Groups

1. [Create the collector instances \(on page 357\)](#) that you want to use for collector redundancy. All these collectors must be of the same type.



Note:

Collector redundancy is not available and supported for the following collectors:

- File Collector.
- Calculation Collector.
- Python Collector.
- Server-to-Server Collector.
- Server-to-Server Distributor.
- OSI PI Collector.
- OSI PI Distributor.

2. [Create tags \(on page 909\)](#) in the primary collector.
3. If you want to use the values of a watchdog tag as a failover trigger, [create the watchdog tag \(on page 909\)](#) in the primary collector.

Collector redundancy ensures that collection of your data remains uninterrupted. It uses two or more collectors that gather data from a single source. For more information, refer to [About Collector Redundancy \(on page 975\)](#)

This topic describes how to set up redundancy between two collectors - one primary and the other secondary. You can, however, set up multiple secondary collectors.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Collectors**.

Proficy Historian
System Statistics

[Main](#)
[Tags](#)
Collectors
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate 155 (Events/Min)

Archive Compression 39%
 Write Cache Hit 100%
 Failed Writes 0 (Events)
 Messages Since Startup 24 (Messages)
 Alerts Since Startup 13 (Alerts)
 Calculations (Enabled)
 Server to Server (Enabled)
 Max Scada Buffer Duration 201 (Days)

Server Memory 32%
 Consumption Rate 0.3 (MB/Day)
 Historical Tags 5 (5 Used of 1,000,000 Licensed)
 SCADA Tags 0 (0 Used of 2,400 Licensed)
 Users 1 (15 Licensed)
 Alarm Rate 0 (Alarms/Min)
 Alarms Since Startup 0 (Alarms)
 Data Stores 3 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SYSTEM4 #FX	Stopped	System4	0	0	%	0	

Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

A list of collectors appears.

3. Select the collector that you want to set as the first collector in your redundant group.

The screenshot displays the Proficy Historian Collector Maintenance interface. The top navigation bar includes links for Main, Tags, Collectors, DataStores, Messages, and Help. The main content area is divided into two sections. On the left, a table titled 'Collectors' lists the collector 'SYSTEM4_iFIX' associated with the computer 'System4'. This table is highlighted with a red border. On the right, the configuration page for 'Collector: SYSTEM4_iFIX' is shown, with tabs for General, Configuration, Tags, Advanced, Performance, and Redundancy. The 'Status' section indicates the collector is 'Stopped' and provides options to 'Resume Collection' or 'Pause Collection'. The 'Description' section shows the collector name 'SYSTEM4_iFIX' and type 'iFIX'. The 'Resources' section includes fields for 'Computer Name' (System4), 'Memory Buffer Size (MB)' (20), and 'Minimum Free Space (MB)' (150). At the bottom of the configuration page are buttons for 'Recalculate', 'Add Tags', 'Update', and 'Delete'.

4. Select **Redundancy**.

The screenshot shows the Proficy Historian Collector Maintenance interface. The top navigation bar includes links for Main, Tags, Collectors, DataStores, Messages, and Help. The main content area is divided into two sections. On the left, a table lists collectors with columns for Name and Computer. The table contains one entry: SYSTEM4_iFIX on computer System4. On the right, the configuration page for the selected collector, SYSTEM4_iFIX, is displayed. The Redundancy tab is highlighted with a red box. The configuration page includes sections for Status, Description, and Resources. The Status section shows the collection status as Stopped, with options to Resume Collection or Pause Collection. The Description section shows the collector type as iFIX. The Resources section shows the computer name as System4, memory buffer size as 20 MB, and minimum free space as 150 MB. At the bottom of the configuration page are buttons for Recalculate, Add Tags, Update, and Delete.

Name	Computer
SYSTEM4_iFIX	System4

Collector: SYSTEM4_iFIX

General | Configuration | Tags | Advanced | Performance | **Redundancy**

Status

Collection Status: Stopped
 Resume Collection Pause Collection

Total Events Collected: 0
Total Events Reported: 0

Description


Description: SYSTEM4_iFIX
Collector Type: iFIX

Resources

Computer Name: System4
Memory Buffer Size (MB): 20
Minimum Free Space (MB): 150

Recalculate Add Tags Update Delete

5. In the **Redundant Collector** field, select **Enabled**, and then select **Update**.
6. Select the collector that will be your second collector in your redundant group.



7. Select **Redundancy**, and then enter values as described in the following table.

Field	Description
Redundant Collector	Select Enabled .
Backup For	Select the collector that this collector will back up (in this case, it is the first collector in your redundant group).

8. Select **Update**.

A message appears, asking you to confirm that tags configured for the backup collector will no longer be collected.

9. Select **Yes**.

Redundancy is now configured for these two collectors. On the main page, the **Redundancy Status** of the first collector will be Active and the backup collector, Standby.

To add more collectors to the redundant group: Repeat steps 6 through 9. In the **Backup For** field, select the collector that backs up the last collector in the group. If you want to have collectors in

the redundant group failover when the active collector's status is unknown, select **Enabled** in the **Collector Status** field. Make sure you are browsing and defining the watchdog tag in the principal (or first) collector in your redundant group.

Maintaining, Operating, and Monitoring Historian

Maintain, Operate, and Monitor Historian

To ensure reliable, error-free operation over a long period of time, develop and execute a consistent maintenance program for the Historian system and the data it collects. The subsequent topics provide guidelines for setting up such a plan and for monitoring and interpreting system performance indicators.

Data Types

Historian uses the following data types.

Data Type	Size	Description	Valid Values
Single Float	4 bytes	Stores decimal values up to 6 places.	1.175494351e-38F to 3.402823466e+38F
Double Float	8 bytes	Stores decimal values up to 15 places.	2.2250738585072014e-308 to 1.7976931348623158e+308
Single Integer	2 bytes	Stores whole numbers.	-32767 to +32767
Double Integer	4 bytes	Stores whole numbers.	- 2147483648 to +2147483648
Quad Integer	8 bytes	Stores whole numbers.	-9,223,372,036,854,775,808 (negative 9 quintillion) to +9,223,372,036,854,775,807 (positive 9 quintillion)
Unsigned Single Integer	2 bytes	Stores whole numbers.	0 to 65535
Unsigned Double Integer	4 bytes	Stores whole numbers.	0 to 4,294,967, 295 (4.2 billion)
Unsigned Quad Integer	8 bytes	Stores whole numbers.	0 to 18,446,744,073,709,551,615 (19 quintillion)

Data Type	Size	Description	Valid Values
Byte	1 byte	Stores integer values.	-128 to +127
Boolean	1 byte	Stores boolean values.	0=FALSE and 1=TRUE (any value other than zero is treated as one)
Fixed String	Configured by user	Stores string data of a fixed size.	0 and 255 bytes
Variable String	No fixed size	Stores string values of undetermined size. This data type is useful if you cannot rely on a constant string length from your data source.	
Binary Object	No fixed size	Stores binary data. This is useful for capturing data that can not be classified by any other data type.	
Scaled	2 bytes	Stores a 4 byte float as a 2 byte integer. The scaled data type saves disk space but sacrifices data precision as a result.	

**Note:**

Tags associated with Quad Integer, Unsigned Double Integer, or Unsigned Quad Integer data types may suffer a loss of precision value due to a Visual Basic limitation.

**Note:**

The Calculation collector supports only calculations performed using the current value calculation. It does not support other calculations due to a Visual Basic script limitation.

Scaled Data Types

Historian uses the high and low EGU values to store and retrieve archived values for the scaled data type. This allows you to store 4 byte floats as 2 byte integers in the archive. Though this saves disk space, it sacrifices data precision. The smaller the span is between the high and low EGU limits, the more precise the retrieved value will be. When calculating the value of a scaled data type, you can use this formula:

```
ArchivedValue = ((RealWorldValue - EngUnits->Low) /
(EngUnits->High - EngUnits->Low) * (float) HR_SCALED_MAX_VALUE) + .5);
```

For example: A value of 12.345 was stored in a scaled tag whose high EGU was 200 and low EGU was 0. When later retrieved from the Historian archive, a value of 12.34473 will be returned.



Important:

Values that are outside of the EGU range of a scaled data type tag are stored as bad, scaledoutofrange in Historian. Changing either the High or Low EGU tags does not affect existing data, but only affects the new data with new timestamps. You cannot correct values for scaled data types that were inserted while EGUs were incorrect. If necessary, contact technical support for additional information.

Quad Integer Data Types: The high and low EGU limits for Quad Integer, Unsigned Single Integer, Unsigned Double Integer, Unsigned Quad Integer are between 2.2250738585072014e-308 to 1.7976931348623158e+308.

Set the Size of a Fixed String Data Type

Using the fixed string data type, you can store string data of a fixed size. This is useful when you know exactly what data will be received by Historian. If a value is larger than the size specified in the **Data Length** field, it will be truncated.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Tags**.

Proficy Historian
System Statistics

[Main](#)
Tags
[Collectors](#)
[DataStores](#)
[Messages](#)
[Help](#)

Receive Rate ? (Events/Min)

Archive Compression: 0%
 Write Cache Hit: 0%
 Failed Writes: ? (Events)
 Messages Since Startup: ? (Messages)
 Alerts Since Startup: ? (Alerts)
 Calculations: (Enabled)
 Server to Server: (Enabled)
 Max Scada Buffer Duration: 201 (Days)

Server Memory: 28%
 Consumption Rate: ? (MB/Day)
 Historical Tags: 8 (8 Used of 1,000,000 Licensed)
 SCADA Tags: 0 (0 Used of 2,400 Licensed)
 Users: 1 (15 Licensed)
 Alarm Rate: ? (Alarms/Min)
 Alarms Since Startup: ? (Alarms)
 Data Stores: 4 (20 Licensed)

Collectors Auto

Collector	Status	Computer	Report Rate	Overruns	Compression	Out Of Order	Redundancy
SAN-JAVA-DEV Simulation	Unknown	SAN-JAVA-DEV	0	0	%	0	


Alerts Show Alerts Auto

Timestamp	Topic	Message
-----------	-------	---------

3. Select the tag for which you want to set a fixed string data type.

The screenshot shows the Proficy Historian Tag Maintenance interface. The top navigation bar includes 'Main', 'Tags', 'Collectors', 'DataStores', 'Messages', and 'Help'. Below this, there are several action buttons: 'Search Historian Tag Database', 'Copy/Rename Tag', 'Add Tag Manually', 'Add Tags From Collector', 'Define Enumerated Set', and 'Define User-Defined Types'. The main content area is divided into two sections. On the left, a 'Tags (1)' list shows 'Tag322' under the 'Tag Name' column. On the right, the 'Tag: Tag322' configuration page is displayed with tabs for 'General', 'Collection', 'Scaling', 'Compression', 'Calculation', and 'Advanced'. The 'Collection' tab is active, showing 'Data Collection Options' with fields for 'Time Assigned By' (Collector), 'Time Zone Bias (min)' (0), 'Time Adjustment' (Do Not Adjust For Source Time Difference), and 'Data Store' (User). Below this are 'Security' options for 'Read Group', 'Write Group', and 'Administer Group', and an 'Audit' section with 'Last Modified' (Never) and 'Modified By'. 'Update' and 'Delete' buttons are at the bottom right. A red box highlights the 'Tags (1)' list and the 'Tag: Tag322' configuration page.

4. Select **Collection**.



5. In the **Data Type** box, select **Fixed String**.
 6. Enter a value in bytes in the adjacent field.
- The fixed string data type is set for the tag.

Plan for Data Recovery

Planning for data recovery means always having up-to-date backup files for important information that you can call up and restore quickly when the need arises.

The .IHC file, which contains all configuration information, is an important file to back up. The .IHC file is automatically backed up when, and only when, you back up the current archive .IHA file. With the .IHC file, you can always restore the system configuration to the state it was in before the event occurred.

It is also important to backup the current online archive files *.IHA. If you restore the archive files, along with the configuration, you can quickly pick up where you left off when the event occurred with a minimum loss of data.

By default, the .IHC backup path is the same as the archives path. The .IHC uses the following naming convention: `ComputerName_Config-Backup.ihc`. If the default backup path is different than the archives path, the .IHC file is copied to the backup folder with the standard .IHC naming convention: `ComputerName_Config.ihc`.

Develop a Maintenance Plan

The primary goal of a maintenance plan is to maintain integrity of the data collected. If you are successful in this regard, you will always be able to recover from a service interruption and continue operation with minimal or no loss of data. Since you can never ensure 100% system uptime, you must frequently and regularly back up current data and configuration files, and maintain non-current archive files in a read-only state, following the guidelines for backup and routine maintenance.

Daily Maintenance

On a daily schedule, perform the following backup operations, unless you use `ihArchiveBackup.exe` to back up archives automatically.

1. Use Historian Administrator to back up the current archive and most recent .IHA archived data file. This preserves data collected up to this moment in time. You do not need to back up any read-only archive files after they have been backed up once.
2. Use Windows Explorer to back up the .IHC file if it has been modified, unless it is backed up automatically. This file contains all current configuration information (tag configuration, archive configuration, and collector configuration). Using this file, you can restore the system configuration after an unplanned shutdown.

Routine Maintenance: On a regular schedule, examine and analyze the system performance indicators displayed on the System Statistics page of Historian Administrator as follows.

Table 75. System Statistics Performance Indicators

Field	Recommended Action
Est. Days to Full	If time is growing short, make sure that the server has sufficient unused storage capacity to open a new archive when the active one fills up. Verify that the Create New Archives Automatically function is enabled. If it is disabled, you must manually create a new archive before the active archive fills up.

Table 75. System Statistics Performance Indicators (continued)

Field	Recommended Action
	<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If you do not have enough unused storage capacity, you may have to enable the Overwrite Old Archives feature. Since this feature overwrites existing data, exercise caution in using it. </div>
Consumption Rate of Archive Storage	If the rate is excessively high, reduce the rate at which data flows into the system or increase the filtering applied to the data to lower the rate of archiving. To reduce the collection rate, slow the polling rate on some or all tags. To increase filtering, enable compression at the collector and/or archiver and widen the compression deadbands.
Failed Writes	If the display shows a significant number of failed writes, investigate the cause and take corrective action to eliminate the malfunctions. Refer to the <code>DataArchiver-XX.log</code> file or query the message database to determine the tags for which failed writes occurred. For example, trying to write values to a deleted archive causes failed writes. Trying to archive data with a timestamp that precedes the start time of the first archive, trying to write to a read-only archive, or trying to write a value with a timestamp more than 15 minutes ahead of the current time on an archiver will produce a failed write.
System Alerts	Examine the messages and alerts and take appropriate action to correct any problems.

On a regular schedule, examine and analyze the performance indicators displayed in the **Performance** section.

Table 76. Collector Performance Indicators

Field	Recommended Actions
Avg. Event Rate Chart	Is the rate at a normal level? Does the chart exhibit an acceptable trend line? If not, determine why. Balance polling schedules, adjust scan frequencies (collection intervals), and modify compression deadbands to lighten load.
Compression Chart	Is compression effectiveness acceptable?

Table 76. Collector Performance Indicators (continued)

Field	Recommended Actions
	If not, verify that compression is enabled and then widen the deadbands to increase the effect of compression.
Overruns Chart	If the value is anything other than zero, determine the severity and cause of the problem and take corrective action.

Evaluate and Control Data Compression

You can achieve optimum performance in Historian by carefully controlling the volume of dynamic data it collects and archives. You need enough information to tell you how the process is running, but you do not need to collect and store redundant or non-varying data values that provide no useful information. More information can be found in the Notes on Collector and Archive Compression reference.

Control Data Flow

You can control the amount of online or dynamic data the system handles at a given time by adjusting certain system parameters. The general principle is to control the flow of data into the archive either by adjusting the rate at which the collectors gather data or by adjusting the degree of filtering (compression) the system applies to the data collected.

This manual describes the detailed procedures for executing these adjustments in the sections: Configuring Archives, Configuring Tags, and Configuring Collectors.

Adjust the following parameters to **reduce** the rate of data flow into the server.

- Reduce the polling rate by increasing the collection interval for unsolicited and polled collection.
- Enable collector compression and optionally use compression timeout.
- Set the compression deadband on the collectors to a wider value.
- Use the collector compression timeout.

Adjust the following parameters to **increase the filtering** applied by the archiver in the server.

- Enable archive (trend) compression.
- Set the archive compression deadband to a wider value.
- Where possible, use the scaled data type and enable input scaling on selected tags.
- Where possible, select milliseconds or microseconds rather than seconds for time resolution. Seconds is optimum for most common devices. This affects disk space.

Evaluate Data Compression Performance

You can determine how effectively data compression is functioning at any given time by examining the system statistics displayed on the System Statistics page of Historian Administrator, as shown in Historian Administrator (System Statistics) Screen.

The compression field at the top of the page shows the current effect of archive compression. Values for this parameter should typically range from 0 to 9%. If the value is zero, it indicates that compression is either ineffective or turned off. If it shows a value other than zero, it indicates that archive compression is operating and effective. The value itself indicates how well it is functioning. To increase the effect of data compression, increase the value of archive compression deadband so that compression becomes more active.

Handle Value Step Changes with Collector Data Compression



Note:

Individual tags can be configured to retrieve step value changes.

If you enable collector compression, the collector does not send values to the archiver any new input values if the value remains within its compression deadband. Occasionally, after several sample intervals inside the deadband, an input makes a rapid step change in value during a single sample interval. Since there have been no new data points recorded for several intervals, an additional sample is stored one interval before the step change with the last reported value to prevent this step change from being viewed as a slow ramp in value. This value marks the end of the steady-state, non-changing value period, and provides a data point from which to begin the step change in value.

The collector uses an algorithm that views the size of the step change and the number of intervals since the last reported value to determine if a marker value is needed. The following is an example of the algorithm:

```
BigDiff=abs(HI_EGU-LO_EGU)*(CompressionDeadbandPercent/(100.0*2.0))*4.0
If ( Collector Compression is Enabled )
If ( Elapsed time since LastReportedValue>=( SampleInterval * 5 ) )
If ( abs(CurrentValue-LastReportedValue) > BigDiff )
Write LastReportedValue,Timestamp=(CurrentTime-SampleInterval)
```

In the example above, if a new value was not reported for at least the last 4 sample intervals, and the new input value is at least 4 deltas away from the old value (where a single delta is equal to half of the compression deadband), then a marker value is written.

**Note:**

These settings are also adjustable from the Registry. Please contact [technical support](#) for more information.

Value Spike with Collector Compression

For example, a collector reads a value X once per second, with a compression deadband of 1.0. If the value of X is 10.0 for a number of seconds starting at 0:00:00 and jumps to 20.0 at 0:00:10, the data samples read would be:

Time	X Value
0:00:00	10.0 (steady state value)
0:00:01	10.0
0:00:02	10.0
0:00:03	10.0
0:00:04	10.0
0:00:05	10.0
0:00:06	10.0
0:00:07	10.0
0:00:08	10.0
0:00:09	10.0
0:00:10	20.0 (new value after step change)

To increase efficiency, the straightforward compression would store only 2 of these 11 samples.

Time	X Value
0:00:00	10.0 (steady state value)
0:00:10	20.0 (new value after step change)


However, without the marker value, if this data were to be put into a chart, it would look like the data value **ramped** over 10 seconds from a value of 10.0 to 20.0, as shown in the following chart.



The addition of a **marker value** to the data being stored results in the following data values:

Time	X Value
0:00:00	10.0 (steady state value)
0:00:09	10.0 (inserted Marker value)
0:00:10	20.0 (new value after step change)

If you chart this data, the resulting trend accurately reflects the raw data and likely real world values during the time period as shown in the following chart.



Reviewing System Alerts and Messages

You can examine system alerts by scrolling through the Alerts panel of Historian Administrator System Statistics page or by examining the Message Search page for more detail. Refer to [Searching for Messages \(on page 850\)](#) for detailed instructions. You can diagnose most operating problems by examining the archiver LOG file.

You may also find the Windows Event Viewer to be useful in diagnosing a problem. To open the Event Viewer, use the following procedure.

1. Launch search.
2. Type `eventvwr.msc` and select **OK**.
The Event Viewer window appears.
3. Highlight an item.
A window appears with an explanation of the event.
4. Select **Previous** or **Next** to step through the messages.

Monitor Historian Health and Status

Historian provides extensive functionality to determine the health and status of both the data archiver and the collectors. You can access this information through Historian Administrator or set up your Historian

system to automatically alert you to any Historian change. The following sections describe procedures and hints for monitoring your Historian system, including:

- Monitor Operating System Event Files
- Monitor Collector Status Tags
- Monitor Historian Subscriptions
- Use Collector Status Tags
- Subscribe to Historian Alerts and Messages
- Create Subscriptions

Monitor Operating System Event Files

You can view the operating system event files through the Event Viewer. For more information on accessing the Event Viewer, refer to [Review System Alerts and Messages \(on page 995\)](#). The operating system event files contain the Historian Status messages found in the application log. Entries in that file are similar to those found in the Alerts panel, but may contain multiple entries for certain items. Multiple entries occur as a result of distributing the components of Historian. Each component logs its critical status changes to the local event log. For example, a collector and the data archive will both log a collector going off-line.

Monitor Collector Status Tags

The iFIX and OPC Collectors contain three status fields that you can write back to the data source for monitoring. Additionally, the iFIX Collectors allow you to display and alarm on the following three status fields.

- **Rate Output** - The number of events per minute the collector processes.
- **Status Output** - The status of the Collector as either Running or Stopped.
- **Heartbeat** - Allows the data source to verify that the collector is working. The collector writes a value of one to this address once a minute.

Other collectors allow you to define tags to record the status of the collector. These tags give an indication of the health of a collector, not the health of the Historian. The following figure displays the iFIX collector status tags.

Collector Status Outputs	
Rate Output Address	NodeName.HIST_RATE.F_CV
Status Output Address	NodeName.HIST_STATUS.A_CV
Heartbeat Output Address	NodeName.IHIST_HEARTBEAT.F_CV

The three tags referenced correspond to tag names within the SCADA node FIX.

- **nodeName.HIST_RATE.F_CV** – An AI block. The F_CV field gives the number of events per minute that the collector is reporting to the server.
- **nodeName.HIST_STATUS.A_CV** – A text block. The A_CV field displays a status such as Running or Stopped depending on the status on the collector. This field does not reflect whether or not the Collector program is running.
- **nodeName.HIST_HEARTBEAT.F_CV** – A digital alarm block that will alarm if the F_CV field remains OPEN for more than 60 seconds. The iFIX collector closes the F_CV field every 60 seconds. You must use a program block in conjunction with this block to automatically OPEN the block if it has been CLOSED. This provides for a momentary reset of the 60 second alarm timeout. Unlike the HIST_STATUS block that only updates the Collector status if the collection stops, the HIST_HEARTBEAT detects that the collection has stopped or that the Collector application is no longer running.

Monitor Historian Subscriptions

Certain objects in the Historian SDK allow you to create subscriptions that fire an event back to the calling application whenever the object's status updates. These subscriptions allow for exception-based monitoring of the Historian status without resorting to intensive polling of the server.

The following table displays the objects and their supported subscription events:

Table 77. Historian Objects with Subscription Events

Object	Subscription Events
Messages Object	AlertReceived and MessageReceived Events
Tags Object	ChangeReceived Event
Data Object	CurrentDataReceived Event
Archives Object	StatusReceived Event
Collectors Object	StatusReceived Event

Subscribing to any of these Object's events allows you to receive direct notification of status changes. For example, using iFIX scripting, you could route this notification to any alarm queue in iFIX.


Subscribe to Historian Alerts and Messages

You can obtain a complete picture of the Historian Server's status by monitoring the server's Alerts and Messages. Additionally, if you are using iFIX with Historian, you can capture these subscriptions and forward them to iFIX alarm queues to ensure operator notification.

You can also use scripting in iFIX to subscribe to the Historian message queues using VBA. If you write a script as part of an iFIX picture, you will need to either keep the picture with the scripts running at all times or run the scripts in the FIXBackground Server application.

Creating Subscriptions in iFIX

To subscribe to messages or alerts in Historian, you must reference the SDK from within the VBA project. To access the References window, shown in the following figure, use the Tools menu in the iFIX VBA Editor.



Once you reference a VBA project to the Historian SDK, you must define two module level objects: a Server Object and a Messages Object. Declare these Objects to remain in scope for the duration that the subscription is active.



Note:

You must declare the Messages Object using the WithEvents keyword. This keyword is only valid at the module or class level.

Typically, the Server and Messages Object are declared as private module level objects. Subscriptions are made during the module initialization or upon loading the method. You can subscribe to Alerts or Messages using either the `SubscribeAlerts` or `SubscribeMessages` Method of the Messages Object.

Specify Topics

When subscribing to Historian Messages you must specify which topics you are subscribing to. There are six topics.

- Message Topics: Configuration Audit, Connections, General
- Alert Topics: Performance, Security, ServiceControl

Once you make the subscription, the `AlertReceived` or `MessagesReceived` Event will fire when a new message is created on the Historian Server. The topic of the message determines which event fires. Additionally, the event receives a copy of the Message or Alert Object properties listed as follows:

- `MessageNumber` – The NLS string number.
- `MessageString` – Translated string, including substitutions for time stamp, user, or tag name.
- `Substitutions` – A collection of substitutions used to make the message string.
- `TimeStamp` – The time the message was created.
- `Topic` – The topic number of the message.
- `TopicName` – The string topic name of the message.
- `UserName` – The user name for the message.

You can also send Alerts and Messages to the iFIX Operator Message alarm queue using the `SendOperatorMessage` method of the System object. This method will send the alerts and messages to all alarm queues, but NOT the Alarm Summary queue. To send a message that will appear on an alarm summary, send the message to the Alarm Extension field of a digital alarm block and toggle the alarm state.

Monitor Historian Performance

Historian provides a variety of counters and tags that can be used to monitor how well the Historian components are performing. You can use performance tags or counters to determine the resource usage on the computer that runs the Historian application. Performance counters are also useful when Historian Administrator is not installed or cannot connect.

- Use performance **tags** to view information in an Excel report or SDK program, possibly along with other Historian tags.
- Use performance **counters** to view information using Windows Performance monitor, possibly along with non-Historian counter information.

Like any Windows performance counter, you must add the counters for collection to view history. Performance tags are always being collected and you can view past data any time.

Performance counters are updated in real time. Performance tags are updated once per minute with the activity over the last minute.

Performance counters contain more information than tags.

Any counter can be collected to a tag using the Historian Windows Performance Collector. Those tags will count against your licensed tag count.

For more information, refer to the following sections:

- Historian Server Performance Tags
- Historian Server Performance Counters

Historian Server Performance Tags

The following table provides information about the various Historian Server Performance tags.

Table 78. Server Performance Tags

Tag Name	Description
PerfTag_CompressionRatio	Specifies the current effect of archive data compression.
PerfTag_MinimumCompressionRatio	Specifies the minimum compression ratio.
PerfTag_MaximumCompressionRatio	Specifies the maximum compression ratio.
PerfTag_TotalEvents	Specifies the total number of data samples reported to the Historian archive from all sources.
PerfTag_TotalOutOfOrder	Specifies the total out of order data samples.
PerfTag_AverageEventRate	Specifies the average number of data samples per minute sent to archiver from all sources
PerfTag_MinimumEventRate	Specifies the minimum number of data samples per minute sent to archiver from all sources.

Table 78. Server Performance Tags (continued)

Tag Name	Description
PerfTag_MaximumEventRate	Specifies the maximum number of data samples per minute sent to archiver from all sources.
PerfTag_WriteCacheHitRatio	Specifies the hit ratio of the write cache in percent of the total writes.
PerfTag_TotalFailedWrites	Specifies the total number of samples since startup that failed to be written.
PerfTag_TotalMessages	Specifies the total messages (for example, connection or audit messages) received by the archiver since startup
PerfTag_TotalAlerts	Specifies the total number of alerts received by the data archiver since startup.
PerfTag_FreeSpace	Indicates the free disk space left in the current archive.
PerfTag_SpaceConsumptionRate	Specifies an archive disk space consumption rate in megabytes per day.
PerfTag_PredictedDaysToFull	Indicates the approximate number of days required for an archive to fill.
PerfTag_MemoryUsage	Specifies the amount of RAM used by the Data Archiver.
PerfTag_MemoryVMSize	Specifies the amount of virtual memory used by the Data Archiver.
PerfTag_TotalAlarms	Specifies the total number of alarms received by the Data Archiver since starting up.
PerfTag_AverageAlarmRate	Specifies the average alarm rate in alarms per minute received by Data Archiver.
PerfTag_TotalFailedAlarms	Specifies the total number of alarms since startup that failed to be written.
Perftag_ReadQueueSize	Specifies the total number of messages present in the Read queue.
Perftag_AverageReadRate	Specifies the total number of data samples per minute returned from the Data Archiver for all read requests.

Table 78. Server Performance Tags (continued)

Tag Name	Description
Perftag_ReadQueuePushRate	Specifies the number of read requests per minute that came into the archiver from all clients. A read request can return multiple data samples.
Perftag_WriteQueuePushRate	Specifies the number of write requests per minute that came into the archiver from all clients. A write request can contain multiple data samples.

View Data Trends for Tags

1. On the **Tag Maintenance** page, select a tag.
2. Right-select the tag and select **Trend**.
The trend for the selected tag displays.

Add a Performance Tag

1. In the **Tag Maintenance** page, select the **Tags** link on the toolbar.
The Tag Maintenance page appears.
2. Select the **Add Tag Manually** link on the toolbar.
The Add Tag window appears.
3. Enter the performance tag name.
4. Select **OK**
The Tag Maintenance page displays with the specified tag properties.

Historian Collector Performance Counters

The following table provides information about collector-specific performance counters.



Note:

Replace the placeholder value `%CollectorName%` with the actual name of the collector.

Table 79. Collector Performance Counters

Counter Name	Description
PerfTag_ <code>%CollectorName%</code> _InterfaceStatus	Specifies the status of an interface.

Table 79. Collector Performance Counters (continued)

Counter Name	Description
PerfTag_%CollectorName%_InterfaceTotalEventsCollected	Specifies the total number of events collected by an interface.
PerfTag_%CollectorName%_InterfaceTotalEventsReported	Specifies the total number of events reported by an interface.
PerfTag_%CollectorName%_InterfaceOutOfOrderEvents	Specifies the total out of order events.
PerfTag_%CollectorName%_InterfaceAverageEventRate	Specifies the average event rate of an interface.
PerfTag_%CollectorName%_InterfaceMinimumEventRate	Specifies the minimum event rate of an interface.
PerfTag_%CollectorName%_InterfaceMaximumEventRate	Specifies the maximum event rate of an interface.
PerfTag_%CollectorName%_InterfaceOverruns	Specifies the interface overruns.
PerfTag_%CollectorName%_InterfaceCompression	Specifies the compression of an interface.
PerfTag_%CollectorName%_InterfaceOverrunsPercent	Specifies the number of overruns in relation to the total events collected since startup.

Historian Server Performance Counters

The Windows performance counters are exposed as objects with counters. In the tables below, you can see each counter and the object to which it belongs.

Each object has one or more instances as shown in the Windows Performance Monitor. Counters belong to a specific instance of an object. For example, there is an instance of the Historian Archive object for each IHA in the system.

There is also a LatestArchive instance for each data store. The LatestArchive instance lets you collect the information from the newest archive even as archives become full and new archives are created. The LatestArchive is the newest archive receiving data, not the prepared archive.

To monitor performance counters, you must add the performance counter tags manually.

Table 80. Historian Archive Object

Archive Counter	Description
Cache Priority	Relative priority of items from the archive stored to the Windows Cache. A higher priority means the item is more likely to stay in cache. Disk Read Time (usec) Duration of last disk read in microseconds.
Disk Read Time (usec)	Duration of last disk read in microseconds.
Disk Read Time Max (usec)	Maximum duration across all disk reads from the archive in microseconds.
Disk Reads	Number of disk reads from archive.
Disk Write Time (usec)	Time of last disk write in microseconds.
Disk Write Time Max (usec)	Maximum duration of all disk writes to the archive in microseconds.
Disk Writes	Number of disk writes to archive.
File Size (MB)	Size of the archive file in MB.
Read Calls	Number of read calls to the archive since startup.
Read Rate (Calls/min)	Number of read calls to the archive per minute.
Write Count	Number of data samples written to archive since startup.
Write Count Rate	Number of data samples written to archive per minute.
Writes Compressed	Number of data samples since startup that were compressed writes to the archive.
Writes Expensive	Number of data samples since startup that were expensive or slow.
Writes Failed	Number of data samples that were failed writes to the archive.
Writes OutofOrder	Number of data samples that were out of time order writes to the archive.

Table 81. Historian Cache Object

Counter	Description
Hit Percentage	Hit rate percentage (0-100) for successful data retrieval calls to the cache. Higher numbers represent more efficiency.

Table 81. Historian Cache Object (continued)

Counter	Description
Hits	Number of hits in the cache since startup. To reset the count, restart the Archiver.
Misses	Number of misses in the cache.
Num Adds	Total number objects added to cache.
Num Deletes	Total number of objects deleted from cache.
Num High Prio Objs	Number high priority objects available for deletion.
Num Low Prio Objs	Number of low priority objects available for deletion.
Num Med Prio Objs	Number of medium priority objects available for deletion.
Obj Count	Number of objects in the cache.
Size (KB)	Size of cache in KB.

Table 82. Historian DataStores Object

Counter	Description
Compression Ratio (Max)	Archive compression ratio for this data store.
Compression Ratio (Max)	Maximum archive compression ratio for the data store.
Compression Ratio (Min)	Minimum archive compression ratio for the data store.
Messages (Total Alerts)	Total alerts since startup
Messages (Total)	Total messages since startup.
Read Calls	Number of read calls to the data store.
Read Rate (Calls/min)	Average read rate across all archives in the data store. (Read Calls/Minute)
Read Samp Rate (Samp/min)	Average read rate across all archives in the data store. (Samples/Minute)
Space (Consumption MB/day)	Disk space consumption rate. (MB/day)
Space (Days To Full)	Number of days until current archive is full.
Space (Free in MB)	Free disk space in the current archive.

Table 82. Historian DataStores Object (continued)

Counter	Description
Write Rate (Average)	Average event rate across all archives. (Samples/Minute)
Write Rate (Max)	Maximum event rate across all archives. (Samples/Minute)
Write Rate (Min)	Minimum event rate across all archives. (Samples/Minute)
Writes (Cache Hit Ratio)	Write Cache hit ratio.
Writes (Compressed)	Total number of compressed data samples since startup.
Writes (Total Failed)	Total failed data sample writes since startup.
Writes (Total OutOfOrder)	Total out of order data samples since startup.
Writes (Total)	Total data samples across all archives since startup.

Table 83. Historian Overview Object

Counter	Description
Compression Ratio (Average)	Average archive compression ratio of all data stores.
Compression Ratio (Max)	Average maximum compression ratio of all data stores.
Compression Ratio (Min)	Average minimum compression ratio of all data stores.
Memory Usage (KB)	Private bytes memory usage for Data Archiver.
Memory VM Size (KB)	Virtual Bytes memory usage for Data Archiver.
Messages (Total Alerts)	Sum of total alerts of all data stores since startup.
Messages (Total)	Sum of total messages of all data stores since startup.
Read Rate (Calls/min)	Sum of all average read rates of all data stores. (Samples/Minute)
Read Samp Rate (Samp/min)	Average read rate across all archives. (Samples/Minute)
Space (Consumption MB/day)	Sum of space consumption rate (MB/day) of all data stores.
Space (Days To Full)	Minimum number of days until current archive is full for all data stores.
Space (Free in MB)	Sum of all free space in the current archive of all data stores.
Write Rate (Average)	Sum of all average event rates of all data stores. (Samples/Minute)
Write Rate (Max)	Sum of all maximum event rates of all data stores.

Table 83. Historian Overview Object (continued)

Counter	Description
Write Rate (Min)	Sum of all minimum event rates of all data stores.
Writes (Cache Hit Ratio)	Average write Cache hit ratio of all data stores.
Writes (Compressed)	Sum of total number of compressed data samples of all data stores.
Writes (Expensive)	Sum of total number of expensive writes data samples of all data stores. One of the reasons for expensive writes is out-of-order data.
Writes (Total Failed)	Sum of total failed data sample writes of all data stores.
Writes (Total OutOfOrder)	Sum of total out of order data samples of all data stores.
Writes (Total)	Sum of total data samples across all archives of all data stores.

Table 84. Historian Queue Object

Counter	Description
ClientQueues with Msgs	The number of client queues with messages current on them. A lower number means all clients are up to date. A higher number means that the archiver is not up to date with incoming network traffic
Count (Max)	Maximum number of messages on the queue. (memory and disk)
Count (Total)	Number of messages on the queue. (memory and disk)
Disk Buf Msg Reads	Number of messages read from the disk buffer file.
Disk Buf Msg Writes	Number of messages written to the disk buffer file.
Processed Count	Number of messages processed from the queue since startup.
Processed Rate (msg/min)	Recent rate at which messages have been processed for the queue.
Processing Time (Ave)	Average time in milliseconds to process a message.
Processing Time (Last)	Time in milliseconds to process the last message.
Processing Time (Max)	Maximum time in milliseconds to process a message.
Recv Count (msgs)	Number of messages received into the queue.
Recv Rate (msgs/min)	Recent rate at which messages have been received for the queue.
Size Kb (Mem&Disk Max)	Max size of messages in Kb on the queue. (memory and disk).

Table 84. Historian Queue Object (continued)

Counter	Description
Size Kb (Mem&Disk)	Size of messages in Kb on the queue. (memory and disk)
Size Kb (Mem&Disk)	Size of messages in Kb on the queue. (memory only)
Threads	Number of worker threads allocated to process this queue. This is the number of created threads but they may be idle.
Threads Working	Number of queue processing worker threads currently processing messages.
Time in Queue (Ave)	Average time in milliseconds that a message was in the queue, waiting to be processed.
Time in Queue (Last)	Time in milliseconds that the last message was in the queue, waiting to be processed.
Time in Queue (Max)	Maximum time in milliseconds that a message was in the queue, waiting to be processed.

Table 85. Historian Config Counters

Counter	Description
File Size	The size of the Configuration File in MB
Hist Tags(Actual)	Number of the Historical tags in the system
Hist Tags (Licensed)	Total licensed Historian tags.
Hist Tags (Used)	Effective number of Historical Licensed Tags in the system. Can be greater than the number of tags because some tags count as more than one Licensed Tag.
Hist Tags (UsedByArrays)	Effective number of Historical Licensed Array Tags in the system (Not the raw tag count, the effective licensed count).
Hist Tags (UsedByUserDef)	Effective number of Historical Licensed User Defined Tags in the system (Not the raw tag count, the effective licensed count).
Number of Collectors	Number of collectors defined on the system.
Number of EnumSets	Number of enumerated sets defined on the system.
Number of UserDefTypes	Number of user defined types defined on the system.

Table 85. Historian Config Counters (continued)

Counter	Description
SCADA Tags (Actual)	Number of SCADA Tags in the system.
SCADA Tags (Licensed)	Total Licensed SCADA tags.
SCADA Tags (Used)	Effective number of SCADA Licensed Tags in the system. Can be greater than the number of tags because some tags count as more than one Licensed Tag.
SCADA Tags (UsedByArrays)	Effective number of SCADA Licensed Array Tags in the system (Not the raw tag count, the effective licensed count).
SCADA Tags (UsedByUserDef)	Effective number of SCADA Licensed User Defined Tags in the system (Not the raw tag count, the effective licensed count).

Troubleshooting

Solve Minor Operating Problems

The following is a table of troubleshooting tips for solving minor operating problems with Historian.

Issue	Suggested Action
After setting the system clock back, browsing the collector from Historian Administrator produces a Visual Basic script error.	Delete temporary Internet files and restart Internet Explorer.
With the Historian Administrator, switching usernames causes the system to reject the login if the User must change password at next login option is selected at time of user creation.	New users with this setting must log in to the appropriate Windows operating system at least once. If the login attempt fails, run Historian Administrator as an administrator, and log in with a new username and password.
A long error message from the File collector does not fit within the message field in the Historian File collector console window,	Open the File collector log file to see the complete text of the error message.

Issue	Suggested Action
resulting a partial display of the message.	
Excel Sample Reports do not display data.	When opening a Sample Excel report, you may receive a message prompting you to update all linked information in the workbook (Yes) or keep the existing information (No). It is recommended that you select No and keep the existing information. The links will be automatically updated for your worksheet. Save your worksheet after the links have been updated.
Need to connect an Historian Server to an Historian Client through a firewall.	Open port 14000 to enable client to server connection through a firewall.
Receiving archive offline failed writes messages.	These occur when the timestamps of data being sent to the archiver are not in the valid time range of any online archives. For example, failed writes occur when the timestamps appear <i>before</i> the oldest archive, the archive is offline, or timestamps are more than 15 minutes <i>past</i> the current time on another archiver.

FAQ: Run a Collector as a Service

The following list is frequently asked questions about running a collector as a service.

Can all collectors be run as a Windows service? If not, which ones cannot?

The OPC Collector, File collector, Simulation collector, Calculation collector, and Server-to-Server collector can be run as services. The iFIX collector run as a background task and cannot be run as a service.

Can all collectors be run as an application? If not, which ones cannot?

All collectors can run as applications (console programs). This includes the Simulation Collector. To make a collector run as a console program, pass a RUNASDOS command line parameter.

What does "running as a service" mean?

It means that the collector appears in the Control Panel list of services. It can run at system boot or be run with a different username and password from the currently logged-in user.

How can the iFIX collector be set up to run when no one is logged in?

It can be set up to run without a user login by adding it to the iFIX SCU task list as a background task and by configuring iFIX to continue running after logoff in local startup.

How do you shut down a collector running as console application?

Collectors started as console applications should be shut down by typing S at the command prompt in the DOS window and pressing Enter.

Can a collector be run as a Windows service and then stopped and restarted?

Yes. Collectors that can run as a service can be stopped and started in Control Panel Services. They can be paused/resumed through Historian Administrator.

What is the difference between running a collector to start as a service on boot up using the Services applet in Control Panel versus running iFIX as a service, which starts the collector through the startup task configuration in the SCU?

The collectors that can run as a service would not be started from iFIX. They can be started from the Control Panel start at system boot. Although you cannot run an iFIX collector as a service, you can log off and on while it is running.

Changing the Base Name of Automatically Created Archives

When the IHC file is created, it stores the name of the server inside the IHC file. Automatically created archives use that server name from the IHC file as a base name, not the Base Archive Name configured in Historian Administrator.

When you *manually* create an archive, however, the archive uses the Base Archive Name from Historian Administrator.

If you move an IHC file from one machine to another, you may want to change the default base archive name to match the new server. To change the default Base Archive Name, create a new .IHC file.

This topic describes how to change the base name of an archive using Excel Add-in. You can also [change the base name using Configuration Hub \(on page 441\)](#).

1. Export your tags using the Excel Add-in.
The Fields to Export window appears.
2. Select all tag attributes and select **OK**.
The data is exported to a new Excel worksheet.
3. Examine the **Comments** column in the new worksheet. To ensure a clean import, the Comments column must be completely full or completely empty. If no comments are found, this column must

be deleted to ensure a clean import. If only some comments are missing, the missing fields must be filled out with comments.

4. Save the Excel spreadsheet.
5. Stop the Data Archiver service.
6. Open the default archive path in Windows Explorer and rename the .IHC file.
Rename `MyMachine.IHC` to `MyMachine.OLD`.
7. Restart the Data Archiver service.
A new, blank IHC file is created for the machine.
8. Import your tags to this new configuration using the Excel Add-In.

Configuring the Inactive Timeout Value

Historian Administrator offers a configurable timeout. This configurable timeout determines how long Historian Administrator will wait before severing its connection to an inactive Historian archive. The default timeout value is 90 seconds.

1. Assuming Historian is already open, double-click on the **Main** button to open Historian Administrator Login window.
2. Select the **Browse for Server** button.
3. Select the Historian server you wish to configure from the **Servers** list.
4. In the **Connection Timeout** field, select the **Use Value** option and enter a timeout value in seconds.

Configuring Deep Data Tree Warnings

Reading and writing to deep trees with large time ranges can be very inefficient. Create a **MaxIndexRecursionDepth** registry key to configure the depth at which the archiver will warn about deep data trees.

1. From the **Start** menu, select **Run**, and then enter `regedit`.
2. Open the following key folder: `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\DataArchiver`
3. Create a value as DWORD called **MaxIndexRecursionDepth**.
4. Set **MaxIndexRecursionDepth** to a number higher or lower than the default value of 900.
To get more warning messages, set a smaller number if you have an archive which is 10 to 100 deep.
5. Select **OK**.
6. Close the Registry Editor.
7. Restart the archiver for the changes to take effect.

Control Data Flow Speeds

Configure buffer flush speed with the `BufferFlushMultiplier` key

Store-and-forward buffering is a key feature of Historian collectors. It prevents data loss during planned or unplanned network outages between a collector and Historian server.

If the collector is disconnected from the archiver for several hours or days, many megabytes of data can be buffered and must be delivered by the collector to the Data Archiver upon reconnect. Since all data is sent from the collector to the archiver in time order, the design goal has been to catch up to real time as quickly as possible by sending data as fast as possible.

If this is not the desired behavior because you want to limit the network load on a slow, shared Wide Area Network (WAN) or you want to limit the CPU load on the Data Archiver caused by the incoming data, you can configure the collector to throttle the data it is sending. Throttling Store and Forward does not affect the Alarms and Events collector.



Important:

Because data is sent in time order (oldest first), you will not be able to retrieve current historical data until the throttled flush is complete.

To configure the buffer flush speed using Configuration Hub:

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.

A list of systems appears in the main section.

3. Right-click the system associated with the collector whose buffer flush speed you want to configure, and then select **Advanced Settings**.

The advanced settings of the system appear, displaying the **Server** section by default.

4. Expand **Collector**, and then select the collector whose settings you want to configure.

The fields specific to the selected collector appear.

5. In the **BUFFER FLUSH MULTIPLIER** field, select the multiplier to the buffer flow speed while using the store-and-forward feature:

- **0**: Select this option if you want to disable throttling.
 - **1**: Select this option if you want normal speed.
 - **2**: Select this option if you want the collector to never send data faster than twice the normal speed.
6. Select **Save**.

A message appears, asking you whether you want to save and restart the collector as well.

7. If you want to save your changes and restart the collector as well, select **Save and Restart**. If you want to just save your changes, select **Save**. In that case, you must restart the collector later for the changes to reflect.

Your changes are saved. If you have selected **Save and Restart**, the collector is restarted.

To configure the buffer flush speed without using Configuration Hub: Configuring the throttle without using Configuration Hub requires modifying a registry key, so it should be done with caution.

A DWORD registry key called **BufferFlushMultiplier** is present under each collector. For Windows 32-bit, it is located under `HKey_Local_Machine\Software\Intellution, Inc.\iHistorian\Services\YOUR_COLLECTOR_TYPE`. For Windows 64-bit, it is located under `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\Services\YOUR_COLLECTOR_TYPE`.

- To **slow** the store and forward throttling, set the value of **BufferFlushMultiplier** to 2. The 2 means that the collector should never send data at more than 2 times its normal rate to limit network and CPU load.
- To **disable** throttling, set the value of **BufferFlushMultiplier** to 0 or delete the registry key.

Control archiver speed using Configuration Hub:

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.

A list of systems appears in the main section.

3. Right-click the system associated with the collector whose archive speed you want to configure, and then select **Advanced Settings**.

The advanced settings of the system appear, displaying the **Server** section by default.

4. Expand **Collector**, and then select the collector whose settings you want to configure.

The fields specific to the selected collector appear.

5. In the **NUM INTERVALS FLUSH** field, specify how quickly you want the collector to send data to Data Archiver. The value you enter in this field is multiplied by 100 milliseconds. For example, if you enter 5, the collector sends data to Data Archiver every 500 milliseconds. We recommend that you enter 5.
6. Select **Save**.

A message appears, asking you whether you want to save and restart the collector as well.

7. If you want to save your changes and restart the collector as well, select **Save and Restart**. If you want to just save your changes, select **Save**. In that case, you must restart the collector later for the changes to reflect.

Your changes are saved. If you have selected **Save and Restart**, the collector is restarted.

Configuring archiver speed without using Configuration Hub: The NumIntervalsFlush registry key controls how quickly the collector sends data to the archiver. The collector collects from the data source at the user configured rate, but for efficiency it bundles data samples in a single write to archive. By default, the collector will send data to archiver every 2 seconds or 10,000 samples, whichever happens first. Most often, it sends every 2 seconds because the collector is not collecting that many samples that fast.

If you need collected data sent to archiver right away, so that it is available for retrieval or for calculations, use the NumIntervalsFlush registry key.

You will have to create the registry key, as it does not exist by default. Create a DWORD value called **NumIntervalsFlush** under the collector, in the same place as HISTORIANNODENAME and INTERFACENAME. On a 64-bit Windows Operating System, all 32-bit component-related registry keys (such as collectors, Client Tools, and APIs) will be located under `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\`.

The preferred setting for **Num Intervals Before Flush** is 5. The intervals are 100 millisecond increments. The default of 20 means $(20 * 100\text{msec}) = 2000 \text{ msec} = 2 \text{ seconds}$. Set the value to 5 and the collector will send every 500msec.



Note:

Changes to the registry key do not take effect until the collector is restarted. This setting affects the sending of data whether it was collected polled or unsolicited.

Configure Inactive Server Reset Timeout

You can configure inactive server connections to reset automatically with the `SocketRecvTimeOut` registry key. `SocketRecvTimeOut` configures a timeout that forces the connection to drop and re-establish if no data is received during the specified time. Consider this configuration when your collector goes to status Unknown for long periods of time even when the connection between collector and archiver is good.

Create a DWORD registry key **SocketRecvTimeOut** under the collector where the problem is occurring and set to a value greater than 90 seconds. A typical value would be 300 seconds. If no bytes are received by the collector for 300 seconds, then the network connection will be closed and re-established.

Historian Errors and Message Codes

When you review errors and messages, for example, in an Historian archiver log file, full descriptions are usually included. If a number appears instead of a description, use the following table to determine the meaning of the error or message.

Table 86. Historian Error Codes and Messages

Number	Description
-32	Operation not permitted
-31	The requested data store was not found
-30	The requested Enumerated Set was not found
-29	A supplied argument is outside the valid range
-28	A supplied argument is NULL
-27	A supplied argument is invalid
-26	Alarms and Events subsystem unreachable
-25	Attempted data delete outside allowed modification interval
-24	Data Retrieval Count Exceeded
-23	Invalid Server Version
-22	Backup Exceeded Space
-21	Calculation Circular Reference
-20	Not Licensed
-19	Duplicate Interface

Table 86. Historian Error Codes and Messages (continued)

Number	Description
-18	No Value
-17	License: Invalid License DLL
-16	License: Too Many Users
-15	License: Too Many Tags
-14	Invalid Tagname
-13	Write No Archive Available
-12	Write Outside Active
-11	Archive Read Only
-10	Write Archive Offline
-9	Write in Future
-8	Access Denied
-7	Not Valid User
-6	Duplicate Data
-5	Not Supported
-4	Interface Not Found
-3	Not Connected
-2	API Timeout
-1	FAILED
0	OK
0	Undefined
1	Connection Successful
2	Connection Unsuccessful
3	Audited Write
4	Audited Write Update
5	Audited Write Out Of Order

Table 86. Historian Error Codes and Messages (continued)

Number	Description
6	Audited Write Update Out Of Order
7	Message On Update
8	Message On Update Out Of Order
9	License Library Function Missing
10	License Library Missing
11	Failed Write
12	Tag Added
13	Tag Modified
14	Tag Deleted
15	Interface Added
16	Interface Modified
17	Interface Deleted
18	Archive Added
19	Archive Add Failure Time Overlap
20	Archive Deleted
21	Archive Overwritten
22	Archive Backup Began
23	Archive Backup Failed
24	Archive Backup Completed
25	Archive Five Days Till Closing
26	Archive Three Days Till Closing
27	Archive One Day Till Closing
28	License Key Removed
29	License Max Tags Exceeded
30	License Max Users Exceeded

Table 86. Historian Error Codes and Messages (continued)

Number	Description
31	License Max Tags Exceeded Shutdown
32	License Max Users Exceeded Shutdown
33	License Library Invalid
34	Buffer Normal
35	Buffer On Disk
36	Buffer Out Of Space
37	Incomplete Shutdown
38	Archive Modified
39	License Expired
40	Buffer Could Not Create
41	Archiver Startup
42	Archiver Shutdown
43	Audit Status Changed
44	Option Modified
45	Write Processing Stopped
46	Write Processing Resumed
47	Interface Status Unknown
48	Archive Closed
49	Interface Stopped
50	Interface Started


Determining the Version of the Historian Server

The version of the Historian Server that Historian Administrator is connected to appears in the About window. If the version number is "Unknown", you are connected to an Historian v1.0 Server.

1. Open Historian Administrator.
2. Select the About link.

The About Historian window appears.

3. Note the version number that appear in Versions section of the About Historian window, as shown in the following figure.



Return a List of Valid Field Options

This topic describes how to determine the fields that are available for an SDK object.

1. Open Microsoft Visual Basic for Applications (VBA).
2. Ensure that you have selected the **Historian Software Kit** reference in the **References** window.
3. Select the **Object Browser** from the **View** menu.
4. Select **Historian_SDK** from the **Library** drop-down list.
5. Select an item in the **Classes** list to generate a list of valid fields for that item.
when you select **ihCollectionType**, you see a list of fields that includes **Polled** and **Unsolicited**.

Scheduled Software Performance Impact

Running continuous backup or disk scan software applications such as anti-virus scans, automated backup software, or any other software that accesses disk drives to a high degree may affect the overall performance of your Historian System by competing with Historian for disk resources.

If your Historian System requires that you need an extremely high throughput (20k/sec or greater), consider **disabling** the scheduled software execution.

Intellution 7.x Drivers as OPC Servers

The ABR and the ABC drivers are OPC v2.0 compliant. All other Intellution 7.x drivers, including the MB1, support OPC v1.0 compliance.

Version 7.x drivers also comply with the OLE for Process Control (OPC) v1.0a standard. Any 1.0-compliant OPC client application can access process hardware data through the I/O Server.

The ABC I/O Server also supports the v2.0 standard and with the OPC Alarms and Events v1.0 specification. Refer to Using OLE for Process Control (OPC) Functionality to learn more about the advantages of OPC.

Troubleshooting Failed Logins

The following is a table of error messages, possible causes, and recommended corrective actions for failed logins sometimes experienced with Historian Administrator.

Error Message	Suggested Action
User does not have authority to read messages.	The user is NOT a member of iH Readers nor a member of the iH Security Admins security groups. To access the Main Page, the user must have read access.
[07/18/2001 03:00:46.071 PM] USER: DOMAIN1\administrator TOPIC: Security MSG: DOMAIN1\administrator(administrator) unsuccessfully connected at 07/18/2001 03:00:46.071 PM. Not able to establish session to the server from a remote Web-based Clients. Page cannot be displayed.	Error in Internet Explorer. Check network connection or IIS on the server.
[07/17/2001 07:56:06.950 PM] USER: DataArchiver TOPIC: Security MSG: DataArchiver(DataArchiver) Exceeded number of licensed users at 07/17/2001 07:56:06.950 PM (NumUsers=0 MaxUsers=0)	Outdated or failed HASP key is attached. Obtain new key from technical support.
[07/17/2001 07:58:18.980 PM] USER: \baduser TOPIC: Security MSG: \baduser(baduser)	Bad password for user account. Enter correct password.

Error Message	Suggested Action
unsuccessfully connected at 07/17/2001 07:58:18.980 PM.	
[07/17/2001 07:58:48.712 PM] USER: \administrator TOPIC: Security MSG: \administra- tor(administrator) unsuccess- fully connected at 07/17/2001 07:58:48.712 PM.	DataArchiver service is not running. Results in a Failed to connect to server error. Make sure data archiver service is running and that the user did not enter a bad password.
[07/17/2001 07:23:44.397 PM] USER: DataArchiver TOPIC: Security MSG: DataArchiv- er(DataArchiver) Exceeded number of licensed tags at 07/17/2001 07:23:44.397 PM (NumTags=1021 MaxTags=0) Must Shutdown	Number of configured tags exceeds number of tags allowed by the key. Delete enough tags to meet the license limit or obtain a license for more tags from technical support.
[07/17/2001 07:35:32.134 PM] USER: DataArchiver TOPIC: Se- curity MSG: DataArchiver(Data- Archiver) Licensed expired. Must shutdown 07/17/2001 07:35:32.134 PM. To trou- bleshoot, refer to the DataArchiv- er.log file.	License on key has expired (archiver will not start). Obtain a new li- cense from technical support.

Troubleshoot Data Collector Configuration

Troubleshooting Data Collector configuration and/or performance requires a thorough understanding of how Historian works and how the various parameters affect system operation. Armed with this knowledge, you can usually localize a problem to one or more functions or parameter settings and take effective corrective action.

Historian offers several tools to help find the cause of an operating problem.

LOG files

The system creates a new log file each time an archiver or collector is started. You can open these files in Notepad or another text editor. The `-nn` suffix in the file name indicates the place of each log file in the time sequence.

The data collector log files, located in the `LogFiles` folder within the Historian program folder, are a historical journal of every event affecting operation of the collector.

The `DataArchiver-nn.LOG` files are sequential files for the archiver only.

The `iFIX collector-nn.LOG` files contain performance information on iFIX collector functioning.

SHW file

The Data Collector `.SHW` file shows configuration data for collectors and is also located in the `LogFiles` directory under Historian. Verify that the parameter and configuration settings match what you configured. You can open this file in Notepad or another text editor.

Collector Maintenance Performance Indicators

These performance and status indicators can be a major aid in identifying, localizing, and diagnosing a problem with a collector.

Collector Maintenance pages

The Collector Maintenance pages can provide useful information about settings and selections of various options and parameter values. Examine each field and verify that it is appropriate for the current application.

iHistorianSDKerrors.log

When performing any troubleshooting of the File collector Administrator or SDK program you should examine the `iHistorianSDKerrors.log` file, which is located in the `LogFiles` folder in your Historian program folder.

Troubleshoot Tags

Tag Configuration

To diagnose a problem in tag configuration, examine the `.LOG` and `.SHW` files in the `Historian/Logfiles` directory. Since these files are a journal record of all system events and parameter modifications important to a system administrator, they can be helpful in identifying and localizing the source of a system malfunction or data error.

You may also find the Windows Event Viewer helpful in troubleshooting. For more information on the Windows Event Viewer, refer to [Review System Alerts and Messages \(on page 995\)](#).

When troubleshooting SDK applications, such as Historian Administrator, the Excel Add-In, or File collector, examine the `iHistorianSDKerrors.log` file, located in the `LogFiles` folder in the Historian program folder.

Stale Tags

If you are not seeing all stale tags in the Historian Web Admin, the ClientManager service may be down. If so, the thread that processes stale tags is suspended until connection is restored.

If the connection to the ClientManager service is lost while processing a batch of 100 tags, that set of tags is skipped and a Tag Property Update error is logged. When the ClientManager service is back up again, the **next** set of 100 tags is considered for scanning. The skipped tags must wait until the Diagnostics Manager's next cycle. Until then, they are not marked as stale or not stale.

Alternately, the DataArchiver or ConfigManager services may be down. If so, all the remaining tags are skipped, and a DataOpenRecordset/Tag Update failure is logged. Even though the thread that processes stale tags is not suspended, all the remaining tags have to wait until the Diagnostics Manager's next cycle. Until then, they are not marked as stale or not stale.

Troubleshoot Historian Performance

There are many parameters that affect Historian Server performance and scalability. This topic emphasizes the parameters that help improve performance and scalability.

Buffer Memory Max

Buffer Memory Max allows you to specify the maximum memory buffer size that an archiver queue can take. Use this parameter to control memory allocation to the write queues. If you plan to collect large amounts of data with high update rates, increase the Buffer Memory Max size. Increasing the Buffer Memory Max size provides enough memory for write queues, thus increasing the Historian performance. Refer to [The Global Options Section \(on page 843\)](#) for more information.

Performance Counters

Historian provides a variety of performance counters that can be used to monitor how well the application is performing. Using the following performance counters you can determine the Historian Server performance and scalability:

- `Perftag_GenericWriteQueueSize`: displays the total number of messages present in the Generic Write queue.
- `Perftag_FastReadQueueSize`: displays the total number of messages present in the Fast Read queue.
- `Perftag_CollectorDataWriteQueueSize`: displays the total number of messages present in the Collector Data Write queue.
- `Perftag_EventMonitorQueueSize`: displays the total number of events present in the Event Monitor queue.
- `Perftag_DataWriteQueueSize`: displays the total number of messages present in the Data Write queue
- `Perftag_ReadQueueSize`: displays the total number of messages present in the Read queue

By monitoring the above performance counters, make sure that you manage application performance. Ideally, all write queues should be zero for optimum archiver performance. If you see an increase in back logs in write queues, then you can:

- Control archive transitions by having larger archive file size.
- Control update rate.
- Perform a backup when an archiver is in stable state.
- Control the caching evaluation period. Refer to [Historian Performance Counters \(on page 1002\)](#) for more information.

System File Cache Tuning

Historian allows you to specify the maximum disk cache memory that an archiver can use. Ideally, Historian consumes 25% of system memory. If your computer has extra memory, then you can increase the disk cache memory to optimize Historian performance.



Note:

You should not increase disk cache memory if you do not have the necessary system resources.

Troubleshoot the Archive Service

Archiver cannot create a new archive: If an archive is full and you have disabled Overwrite Old Archives in the **Global Options** section, Historian can only create a new archive if there is enough disk space available. If you do not have enough disk space to create a new archive, Historian does not generate an alert on the Main page, but instead adds the following messages to the Data Archiver log file: `Could`

```
not locate empty archive file, nor create one, nor use old one. Stopped processing data write requests. Free up disk space or enable Overwrite Old Archives to continue archiving your data.
```

Archive service not starting automatically: On some systems the Archiver does not start automatically after install. Start the Archiver manually through the Services window or restart the computer. The Archiver should start on all future restarts. The Archiver service may also fail to start if it is started by an improperly configured domain account. In order to add a user from the domain as the Archiver service start up account, the machine Historian is installed on must have joined the domain. The user changing the service log on account must also have administrative rights to the Historian machine. This user the service is configured with must be a member of the Domain Administrators group and have administrative rights to the Historian machine. The user also needs to be allowed to log on as a service and act as part of the operating system. This is configured in the local policy editor of the Historian machine.

Investigate failed backups: Refer to the `ArchiveBackup-XX.log` file to investigate failed backups. The backup can fail if the user does not have valid permissions or if the archive name supplied is not valid. For more information, refer to Knowledge Base article: i014491 at <http://iglobalcare.gefanuautomation.com>.

Chapter 6. Historian Advanced Topics

Historian Advanced Topics Overview

About Historian Advanced Topics

The intended audience for this content is a user with a high level of computing and technical skills, specifically with Microsoft Windows and associated networking products. It is also assumed that the user will have prior experience working with the Historian product.

This Help describes advanced content on the typical flow of data in a Historian system. It also describes advanced functions which you can run at the command line for data stores.

- **Data Input:** describes the time up until the data is sent over the network to the archiver.
- **Storage:** covers the time the archiver receives it until it is requested.
- **Retrieval:** covers the whole round trip from the client to the archiver and back with the requested data.

Because Historian can store and retrieve data, comments, and messages, the input, storage, and retrieval of each is discussed.

Buffering applies to both input and storage and is mentioned in those sections.

There are additional software tools introduced in this document that do not ship with the product.

Contact your technical support agent about such tools, should you require them.

Storage

Archive Compression

Archive Compression Overview


The Data Archiver performs archive compression procedures to conserve disk storage space. Archive compression can be used on tags populated by any method (collector, migration, File collector, SDK programs, Excel, etc.)

Archive compression is a tag property. Archive compression can be enabled or disabled on different tags and can have different deadbands.

Archive compression applies to numeric data types (scaled, float, double float, integer and double integer). It does not apply to string or blob data types. Archive compression is useful only for analog values, not digital values.

Archive compression can result in fewer raw samples stored to disk than were sent by collector.

If all samples are stored, the required storage space cannot be reduced. If we can safely discard any samples, then some storage space can be reduced. Briefly, points along a straight or linearly sloping line can be safely dropped without information loss to the user. The dropped points can be reconstructed by linear interpolation during data retrieval. The user will still retrieve real-world values, even though fewer points were stored.



Archive Compression uses a held sample. This is a sample held in memory but not yet written to disk. The incoming sample always becomes the held sample. When an incoming sample is received, the currently-held sample is either written to disk or discarded. If the currently-held sample is always sent to disk, no compression occurs. If the currently-held sample is discarded, nothing is written to disk and storage space is conserved.

In other words, collector compression occurs when the collected incoming value is discarded. Archive compression occurs when the currently-held value is discarded.

Held samples are written to disk when archive compression is disabled or the archiver is shut down.

Any sample written to disk is a true incoming sample. No timestamp or value or quality is ever changed or interpolated.



Note:

internal performance tags use an archive compression deadband of 0% or close to 0%.

Archive Compression Logic

The following describes the logic that is executed on every sample written to the archiver while archive compression is enabled for the tag:

```

IF the incoming sample data quality = held sample data quality

IF the new point is a bad

Toss the value to avoid repeated bads. Do we toss new bad or old bad?

ELSE

Decide if the new value exceeds the archive compression deadband/

ELSE//

data quality is changed, flush held to disk

IF we have exceeded deadband or changed quality

// Store the old held sample in the archive

// Set up new deadband threshold using incoming value and value written to disk.

// Make the incoming value the held value

```

Example: Change of data quality

The effect of archive compression is demonstrated in the following examples.

This example demonstrates that:

- A change in data quality causes held samples to be stored.
- Held samples are returned only in a current value sampling mode query.
- Restarting the archiver causes the held sample to be flushed to disk.

Normally, a flat straight line would never cause the held value to be written to disk. An important exception is that changes in data quality force the held value to be written to disk. Assume a large archive compression deadband, such as 75% on a 0 to 100 EGU span.

Time	Value	Quality
t)	2	Good
t1	2	Bad
t2	2	Good

The following SQL query lets you see which data values were stored:

```

Select * from ihRawData where samplingmode=rawbytime and tagname = t20.ai-1.f_cv and timestamp >
today

```

Notice that the value at t2 does not show up in a RawByTime query because it is a held sample. The held sample would appear in a current value query, but not in any other sampling mode:

```
select * from ihRawData where samplingmode=CurrentValue and tagname = t20.ai-1.f_cv
```

The points should accurately reflect the true time period for which the data quality was bad.

Shutting down and restarting the archiver forces it to write the held sample. Running the same SQL query would show that all 3 samples would be stored due to the change in data quality.

Archive Compression of Straight Line

In this case we have a straight flat line. Assume a small archive compression deadband, say 2% on a 0 to 100 EGU span. Since data occurs on a straight flat line, the deadband will never be exceeded.

Time	Value	Quality
t0	2	Good
t0+5	2	Bad
t0+10	2	Good
t0+15	2	Good
t0+20	2	Good

Shut down and restart the archiver, then perform the following SQL query:

```
select * from ihRawData where samplingmode=rawbytime and tagname = t20.ai-1.f_cv and timestamp > today
```

Only t0 and t0+20 were stored. T0 is the first point and T0+20 is the held sample written to disk on archiver shutdown, even though no deadband was exceeded.

Bad Data

This example demonstrates that repeated bad values are not stored. Assume a large archive compression deadband, such as, 75%.

Time	Value	Quality
t0	2	Good
t0+5	2	Bad

Time	Value	Quality
t0+10	2	Bad
t0+15	2	Bad
t0+20	2	Good
t0+25	3	Good

- The t0+5 value is stored because of the change in data quality.
- The t0+10 value is not stored because repeated bad values are not stored.
- The t0+15 value is stored when the t0+20 comes in because of a change of quality.

Disabling Archive Compression for a Tag

Assume a large archive compression deadband, such as 75%

Time	Value	Quality
t0	2	Good
t0+5	10	Good
t0+10	99	Good
t0+15	Archive compression disabled	

- The t0 value is stored because it is the first sample.
- The t0+5 is stored when the t0+10 comes in.
- The t0+10 is stored when archive compression is disabled for the tag.

Archive Compression of Good Data

This example demonstrates that the held value is written to disk when the deadband is exceeded.

In this case, we have an upward ramping line. Assume a large archive compression deadband, such as 75% on a 0 to 100 EGU span.

Time	Value	Quality
t0	2	Good
t0+5	10	Good
t0+10	10	Good

Time	Value	Quality
t0+15	10	Good
t0+20	99	Good

Shut down and restart the archiver, then perform the following SQL query:

```
select * from ihRawData where samplingmode=rawbytime and tagname = t20.ai-1.f_cv and timestamp >
today
```

Because of archive compression, the t0+5 and t0+10 values are not stored. The t0+15 value is stored when the t0+20 arrives. The t0+20 value would not be stored until a future sample arrives, no matter how long that takes.

Determining Whether Held Values are Written During Archive Compression

When archive compression is enabled for a tag, its current value is held in memory and not immediately written to disk. When a new value is received, the actual value of the tag is compared to the expected value to determine whether or not the held value should be written to disk. If the values are sufficiently different, the held value is written. This is sometimes described as "exceeding archive compression".

Archive compression uses a deadband on the slope of the line connecting the data points, not the value or time stamp of the points themselves. The archive compression algorithm calculates out the next expected value based on this slope, applies a deadband value, and checks whether the new value exceeds that deadband.

The "expected" value is what the value would be if the line continued with the same slope. A deadband value is an allowable deviation. If the new value is within the range of the expected value, plus or minus the deadband, it does not exceed archive compression and the current held value is not written to disk. (To be precise, the deadband is centered on the expected value, so that the actual range is plus or minus half of the deadband.)

Exceeding Archive Compression

EGUs are 0 to 200000 for a simulation tag.

Enter 2% Archive compression. This displays as 4,000 EGU units in the administration UI.

When a sample arrives, the archiver calculates the next expected value based on the slope and time since the last value was written. Let's say that the expected value is 17,000.

The deadband of 4,000 is centered, so the archiver adds and subtracts 2,000 from the expected value. Thus, the actual value must be from 15,000 to 19,000 inclusive for it to be ignored by the compression algorithm.

In other words, the actual value must be less than 15,000 or greater than 19,000 for it to exceed compression and for the held value to be written.

Determining Expected Value

The Archive Compression algorithm calculates the expected value from the slope, time, and offset (a combination of previous values and its timestamp):

```
ExpectedValue = m_CompSlope * Time + m_CompOffset;
```

Where

```
m_CompSlope = deltaValue / deltaT
m_CompOffset = lastValue - (m_CompSlope * LastTimeSecs)
```

Determining Expected Value

Values arriving into the archiver for tag1 are

Time	Value
t0	2
t0+5	10
t0+10	20

The expected value at time stamp t0+15 is calculated based on the samples at t0+5 and t0+10:

```
m_CompSlope = deltaValue / deltaTime m_CompSlope = (20-10) / 5
m_CompSlope = 2
m_CompOffset = lastValue - (m_CompSlope * LastTimeSecs)
m_CompOffset = 20 - (2 * 10)
m_CompOffset = 0
ExpectedValue = m_CompSlope * Time + m_CompOffset;
ExpectedValue = 2 * 15 + 0;
ExpectedValue = 30
```

The expected value at t0+15 is 30.

Archive Compression of a Ramping Tag

An iFIX tag is associated with an RA register. This value ramps up to 100 then drops immediately to 0.

Assume a 5-second poll time in Historian. How much archive compression can be performed to still "store" the same information?

With an archive compression of 75%, 25% or 5%, only the change in direction is logged:

```
11-Mar-2003 19:31:40.000 0.17 Good NonSpecific
11-Mar-2003 19:32:35.000 90.17 Good NonSpecific
11-Mar-2003 19:32:40.000 0.17 Good NonSpecific
11-Mar-2003 19:33:35.000 91.83 Good NonSpecific
11-Mar-2003 19:33:40.000 0.17 Good NonSpecific
```

An archive compression of 1% stores the most samples.

An archive compression of 0% logs every incoming sample. Even on a perfectly ramping signal with no deviations, 0% compression conserves no storage space and essentially disables archive compression.

Archive Compression of a Drifting Tag

A drifting tag is one that ramps up, but for which the value barely falls within the deadband each time. Even though a new held sample is created and the current one discarded, the slope is not updated unless the current slope exceeded. With a properly chosen deadband value, this is irrelevant: by specifying a certain deadband, the user is saying that the process is tolerant of changes within that deadband value and that they do not need to be logged.

Archive Compression of a Filling Tank

In the case of a filling tank, the value (representing the fill level) ramps up, then stops. In this case, the system also uses collector compression, so when the value stops ramping, no more data is sent to the archiver. At some point in the future, the value will begin increasing again.

As long as nothing is sent to the archiver, no raw samples are stored. During this flat time (or plateau), it will appear flat in an interpolated retrieval because the last point is stretched. This illustrates that you should use interpolated retrieval methods on archived compressed data.

How Archive Compression Timeout Works

The *Archive Compression Timeout value* describes a period of time at which the held value is written to disk. If a value is held for a period of time that exceeds the timeout period, the next data point is considered to exceed the deadband value, regardless of the actual data received or the calculated slope.

After the value is written due to an archive compression timeout period, the timeout timer is reset and compression continues as normal.

Archive De-fragmentation - An Overview

What is De-fragmentation? Having an IHA file with contiguous data values for a particular tag is called Archive De-fragmentation.

An Historian IHA (Historian Data Archive) file could contain data values for multiple tags and data written for a particular tag may not be in continuous blocks. This means data values in IHA files are fragmented.

Archive De-fragmentation improves the performance of reading and processing of archive data dramatically.

De-fragmentation of existing archives:

- An archive can be de-fragmented, when it is not active.
- A command line based tool can be used to run on any existing archive as needed.
- De-fragmentation can be done on all versions of archives, and the resulting archive will be the latest version.
- The de-fragmentation must be started manually.

De-fragmenting an existing archive

A command line based tool is available to de-fragment an existing archive. This tool can be run on any existing archive(s). After the de-fragmentation, the new archive will be slightly smaller in size than the original one.

To de-fragment an archive using the tool:

1. Select a read-only archive to backup.
2. Backup the archive.
3. Transfer the archive from the production machine to another machine.
4. Run the ihArchiveDefrag tool on the archive.

```
-----
Usage (Single File Mode): Operates on one archive at a time.

ihArchiveDefrag [-v][-d][-y][-h][-s] SrcArchive [DestArchive] [Config.ihc]
-----
```

Usage (Directory Mode): Processes all archives in the source directory.

```
ihArchiveDefrag [-v][-d][-y][-h][-s] SrcDir [DestDir] [Config.ihc]
```

```
[-v] Verbose logging to the logfile.
[-c] Skip the defrag step. Only compare/verify the archives.
[-d] Skip the verify step. Only defrag the archive.
[-h] Displays this help information.
[-s] Source is on a SSD. Skip the pre-read step as it is not needed.
[-y] Yes. Don't ask questions, answer YES. Just do the work.
```

* The Config.ihc is only needed for 4.0 or older archives

* If the DestArchive is not provided, a name will be generated.

* In directory mode, if the DestDir is not provided a new directory called 'DefragFiles' will be created under the SrcDir.

Examples:

```
ihArchiveDefrag User_Node_Archive001.iha
ihArchiveDefrag User_Node_Archive001.iha D:\Output\User_Node_Archive001.iha
ihArchiveDefrag -y c:\Historian\Archives\Backups
ihArchiveDefrag -y c:\Historian\Archives\Backups d:\DefragOutput
```



Note:

- As part of this process the source archive MAY be modified, It is HIGHLY recommended that this tool be run on a disposable copy of the archive just in case it is modified.
- De-fragmenting an archive is a disk intensive operation and can be slow (minutes to hours to run). Running on a machine with memory greater than twice the archive size is helpful.
- If the performance is not satisfactory it is recommended that the source archive be on an SSD when running ihArchiveDefrag.
- It is recommended that de-fragmentation should not be run on a production system as it can affect the performance of the production system.

5. Transfer the resulting new archive back to the production machine.
6. Unload the existing archive.
7. Load the new de-fragmented archive.

About Storing Future Data

You can store future data in Historian. This future data is the predicted data, which has a future timestamp. You can use this data to perform a predictive or forecast analysis, and revise the forecasting algorithms as needed.

The data is stored in the Historian Archiver. You can use it to analyse both the historical data and future data (for example, using trend charts), and take necessary actions. This allows you to refine the way the data to be stored in Historian is received and processed.

By default, Historian stores up to 1200 seconds of future data. However, if you enable storage of future data, you can store data up to the following timestamp: 03:14:07 on Tuesday, 19 January, 2038.

**Note:**

You can store future data beyond the license expiry date of Historian. For example, even if the license expires by May 31, 2022, you can store future data that is predicted till 19 January, 2038. However, after the license expires, you cannot use this feature.

You can store future data related to all the data types used in Historian. You can store future data for all the tags associated with a data store.

The following collectors support future data (that is, collect the future timestamp of the data):

- The OPC DA collector
- The OPCUA DA collector
- The OPCHDA collector

To use this feature, you must enable the storage of future data. You can do this using [sample programs \(on page 1039\)](#) or [Command Line \(on page 1039\)](#).

You can then retrieve and/or extract this data using any of the available options such as Historian Administrator, Rest APIs, Excel Add-In, and the Historian Interactive SQL application (ihsql.exe).

The following conditions apply when you store future data:

- You can enable the future data storage only for a data store.
- You can collect future data only using the OPC Data Access, OPCUA Data Access, and OPC HDA collectors. You cannot collect future data using collectors such as the Server-to-Server collector, the Server-to-Server distributor, and the Calculation collector.
- When you select the **Last 10 Values** option for a tag, the results include the last ten values till the current date and time; the results do not include future data. If you want to view future data, you can filter the data based on the start and end dates.
- Future data is stored till 19 January, 2038.



Note:

You can store future data beyond the license expiry date of Historian. For example, even if the license expires by May 31, 2022, you can store future data that is predicted till 19 January, 2038. However, after the license expires, you cannot use this feature.

Best practices:

- For a tag for which you want to store future data, do not store past data.
- As this feature can lead to out-of-order data, use this feature carefully to avoid load on the server. For example, store future data in the chronological order of time.

Known Issues:

- Data recalculation does not work for future data.

Suppose you have enabled the storage of future data for a data store named FDataStore.

Suppose the current time is 9.00 am, April 13, 2020. And, future data is stored from 11.00 am onwards, and a size-based archive is created to store the data.

Data can be stored in the archive file only from 11.00 am onwards.

Scenario 1: The timestamp of the data is in the past. For example: 11.00 am, April 12, 2020. A new archive file will be created to store this data. Therefore, to reduce load on the server, we strongly recommend that you store future data in the chronological order of time.

Scenario 2: The timestamp of the data is beyond the outside-active-hours of the archive file. For example: 11.00 am, December 12, 2020. Suppose the current archive file is active only for today. Data will not be stored in the archive file because the timestamp of the data falls beyond the outside-active-hours value of the archive file. To avoid this issue, a new archive file must be created in such scenarios. To do so, you must [enable offline archive creation \(on page 1043\)](#).

Scenario 3: The timestamp of the data is much further in the future. For example: 11.00 am, April 12, 2025. The current archive file may be used to store the data for this timestamp as well. This results in an optimum usage of the archive file instead of creating multiple archive files.

Enable Storing Future Data Using Configuration Hub

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Systems**.
A list of systems appears in the main section.
3. Right-click the system associated with the data store for which you want to enable storing future data, and then select **Advanced Settings**.
The advanced settings of the system appear, displaying the **Server** section by default.
4. Expand **Datastore**, and then, select the data store in which you want to store future data.
The fields specific to the selected data store appear.
5. Switch the **ALLOW FUTURE DATA** toggle on.
6. As needed, enter values in the remaining fields, and then select **Save**.
Storing future data is now enabled for the data store.

Enable Storing Future Data Using Command Line

Ensure that you have a mechanism to generate future data that you want to store in Historian.

By default, Historian stores up to 1200 seconds of future data. However, if you enable storage of future data, you can store data up to the following timestamp: 03:14:07 on Tuesday, 19 January, 2038. This topic describes how to enable storage of future data using Command Line. You can perform this task for any data store other than the default USER data store.

1. Stop the Historian DataArchiver service.
2. Open Command Prompt with elevated privileges or administrator privileges.
3. Navigate to the folder in which the `ihDataArchiver_x64.exe` file is located. By default, it is `C:\Program Files\Proficy\Proficy Historian\x64\Server`.
4. Run the following command: `ihDataArchiver_x64 OPTION.<data store name> ihArchiverAllowFutureDataWrites 1`
5. Run the following command: `ihDataArchiver_x64 OPTION.<data store name> ihArchiveActiveHours <number of active hours>`
6. Start the Historian DataArchiver service.

Enable Storage of Future Data

Ensure that you have a mechanism to generate future data that you want to store in Historian.

By default, Historian stores up to 1200 seconds of future data. However, if you enable storage of future data, you can store data up to the following timestamp: 03:14:07 on Tuesday, 19 January, 2038. This topic describes how to enable storage of future data.

1. For each data store for which you want to store future data:

a. Enable the `ihArchiverAllowFutureDataWrites` option.

**Tip:**

You can perform this step using the [sample programs \(on page 1040\)](#) or [Command Line \(on page 1039\)](#).

b. Enable the `ihArchiveCreateOfflineArchive` option.

This is to avoid receiving an outside-active-hours error. It happens if you attempt to store data when the current archive file is set to read-only.

**Tip:**

You can perform this step using [Command Line \(on page 1043\)](#).

2. For each collector that sends data to the data store, set the `Time Assigned By` property to `Source`.

**Note:**

You can perform this step only for the OPC Data Access, OPCUA Data Access, and OPC Classic HDA collectors.

Future data is now stored in Historian. You can retrieve the data using any of the available options such as Historian Administrator, Rest APIs, Excel Add-In, and the Historian Interactive SQL application (ihsql.exe).

Sample Program to Enable Future Data

Using C++

The following lines of code provide a sample program to enable the `ihArchiverAllowFutureDataWrites` option using C++:

```
void SetFutureDataWriteOptions(void)
{
```

```

ihChar enable[50];

printf("\n\n Please enter 1/0 for enable/disable future data write per data store: ");

_getws(enable);

ihChar dataStoreName[50];

printf("\n\n Please enter data store name to enable future data writes ");

_getws(dataStoreName);

ihAPIStatus Status;
ihOptionEx option;

option.Option = ihArchiverAllowFutureDataWrites;

option.DataStoreName = dataStoreName;

Status = ihArchiveSetOption(SrvHdl, &option,enable);

}

void GetFutureDataWriteOptions()
{
ihChar dataStoreName[50];

printf("\n\n Please enter the name of the data store Future Data write Option: ");

_getws(dataStoreName);

ihAPIStatus Status;

ihChar *Value;

ihOptionEx temp;

temp.Option = ihArchiverAllowFutureDataWrites;

temp.DataStoreName = dataStoreName;

Status = ihArchiveGetOption(SrvHdl,&temp,&Value);

printf("Archive Future Data Write Option ihArchiverAllowFutureDataWrites value is - [%s] for the data store
[%s]\n", (Value ? Value : L"NULL"), dataStoreName);

Pause();
}

```

Using C#

The following lines of code provide a sample program to enable the `ihArchiverAllowFutureDataWrites` option using C#:

```
static void Main(string[] args)
{
    string swtValue = "0";
    string dsName = "";
    ConsoleKeyInfo kInfo;
    connection = ClientConnect.NewConnection;
    do
    {
        Console.WriteLine("1 Set/Enable Data Store Create Offline Archives Option Value");
        Console.WriteLine("2 Set/Enable Data Store Allow Future Data Writes Option Value");
        Console.WriteLine("3 Get Data Store Create Offline Archives Option Value");
        Console.WriteLine("4 Get Data Store Allow Future Data Writes Option Value");
        Console.WriteLine("Enter Option Value");
        swtValue = Console.ReadLine();
        switch (swtValue)
        {
            case "1":
                Console.WriteLine("Enter Data Store Name");
                dsName = Console.ReadLine();
                connection.IServer.SetOption(HistorianOption.ServerCreateOfflineArchives, "1", dsName);
                Console.WriteLine("Option value set to " +
connection.IServer.GetOption(HistorianOption.ServerCreateOfflineArchives, dsName));
                Console.ReadKey();
                break;
            case "2":
                Console.WriteLine("Enter Data Store Name");
                dsName = Console.ReadLine();
                connection.IServer.SetOption(HistorianOption.ArchiverAllowFutureDataWrites, "1", dsName);
                Console.WriteLine("Option value set to " +
connection.IServer.GetOption(HistorianOption.ArchiverAllowFutureDataWrites, dsName));
                Console.ReadKey();
                break;
            case "3":
```

```

        Console.WriteLine("Enter Data Store Name");

        dsName = Console.ReadLine();

        Console.WriteLine("Option value is: " +
connection.IServer.GetOption(HistorianOption.ServerCreateOfflineArchives, dsName));

        Console.ReadKey();

        break;

    case "4":

        Console.WriteLine("Enter Data Store Name");

        dsName = Console.ReadLine();

        Console.WriteLine("Option value is: " +
connection.IServer.GetOption(HistorianOption.ArchiverAllowFutureDataWrites, dsName));

        Console.ReadKey();

        break;

    default:

        Console.WriteLine("Please enter valid number");

        Console.ReadKey();

        break;

    }

    Console.WriteLine("Please Enter X to exit");

    kInfo = Console.ReadKey();

    } while (kInfo.Key != ConsoleKey.X);

    }

}

```

Enable Offline Archive Creation

This topic describes how to enable offline archive creation. This is to avoid receiving an outside-active-hours error. It happens if you attempt to store data when the current archive file is set to read-only.

1. Stop the Historian DataArchiver service.
2. Open Command Prompt with elevated privileges or administrator privileges.
3. Navigate to the folder in which the `ihDataArchiver_x64.exe` file is located. By default, it is `C:\Program Files\Proficiency\Proficiency Historian\x64\Server`.
4. To enable the `ihArchiveCreateOfflineArchive` option for a data store, run the following command:

```
ihDataArchiver_x64 OPTION.<data store name> ihArchiveCreateOfflineArchive 1
```
5. Start the Historian DataArchiver service.

Retrieval

Retrieval

When retrieving data from Historian, you specify either a raw or non-raw sampling mode. Non-raw retrieval can include a calculation mode so that calculations are performed in the archiver before data is returned.

This is detailed in the following sections:

- Sampling Modes
- Hybrid Modes
- Filtered Data Queries

Some sampling and calculation modes are better suited to retrieving compressed data. Understanding the available modes helps you choose the best method for your archiving process.

The retrieval topics include descriptions of all methods of retrieval:

- API
- SDK
- OLE DB
- Charting
- Reporting via OLE DB and Excel Add In

Sampling Modes

Many different sampling and calculation modes can be used on retrieval of data that has already been collected in the archive. Available sampling modes in Historian include:



Note:

A filtered data query can be performed with each sampling mode except CurrentValue. Calculation modes are used when the sampling mode is set to "Calculated".

These topics explain some of these retrieval concepts. Each sampling mode (except calculated) is described with details and examples, including how sample attributes are determined. Each sample returned by Historian during data retrieval has the following properties:

- **Timestamp** – time stamp of the collected sample or an interval time stamp
- **Value** – The collected value or sampled value
- **Quality** – Each sample in Current Value and Raw retrieval has a quality of "good" or "bad". Interpolated and Lab Retrieval express quality as a "per cent good".

Current value sampling is the simplest retrieval mode. Raw data retrieval is the second simplest method of retrieval. Intervals and interpolation concepts are common to Interpolation and Lab sampling. Interpolation and lab sampling are presented together so that they can be contrasted for values and qualities returned from the same set of collected data.

Example Data: Each topic contains all necessary data for executing each example in the form of a CSV file that can be imported by the Historian File collector. You will have to copy and paste the appropriate data into a separate file with a CSV file name extension. Delete all archives before importing the data. You will not be able to import the data unless you adjust the active hours setting; this is true any time you import old data with the File collector. For details, see *Historian* documentation.

Current Value Sampling Mode

Current Value Sampling Mode retrieves the data sample value with newest timestamp of any quality that was received by the archiver. This is not the same as retrieving the newest raw sample stored in the archive, since archive compression sometimes discards raw samples sent by the collector during the compression process.

Current Value Sampling retrieves a single sample containing the current value of the tag, not a series of historical samples. The sample has a timestamp, value, and quality.

Timestamp

Returns the time stamp on the sample sent to the archiver. The time stamp is not necessarily the current time. If collector compression is enabled and the deadband on the collector has not been exceeded for some time, the time stamp may be much earlier than the current time.

If data is sent to the archiver out of order, the current value is always the newest timestamp, even when the most recent value received is older than previous samples.

Retrieving the current value of out of order data

1. Import this file that contains out of order data for a tag

```
* Example of Out Of Order data
* [Tags] Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
OUTOFORDERTAG,SingleFloat,60,0
[Data]
Tagname,TimeStamp,Value,DataQuality
OUTOFORDERTAG,29-Mar-2002 14:50:00.000,50.0,Good
OUTOFORDERTAG,29-Mar-2002 14:20:00.000,20.0,Good
```

```
OUTOFORDERTAG,29-Mar-2002 14:30:00.000,30.0,Good
OUTOFORDERTAG,29-Mar-2002 14:10:00.000,10.0,Good
```

2. Retrieve the data using current value sampling, using the following query:

```
select timestamp, tagname, value, quality from ihrawdata where samplingmode = CURRENTVALUE and
tagname = OUTOFORDERTAG
```

The time stamp of the current value should be the newest timestamp with the value and quality that was sent to the archiver, as shown here:

Timestamp	Tagname	Value	Quality
29-Mar-200214:50:00.000	OUTOFORDERTAG	50.00	GoodNonSpecific

- **Value:** Simply the value sent by the collector. The value is not interpolated to the current time or modified by the archiver during retrieval. The data type of the value will be the same data type as the tag's raw data.
- **Data Quality:** Returns the quality of the data sent by the collector. The current value can be of a bad data quality and will be flagged if the collector sends a sample with a bad data quality to the archiver. When the collector shuts down cleanly, it sends a bad data quality marker at shutdown time for all its tags. If the collector simply loses its connection to the archiver or crashes, the current value's quality will not automatically change to bad.

Retrieving the current value of a tag

The following sequence of steps displays the behavior of **Current Value** sampling mode. After each step, retrieve the tag current value using this query:

```
select timestamp, tagname, value, quality from ihrawdata where samplingmode = CURRENTVALUE and
tagname = IFIX.RAMP.F_CV
```

1. Configure the tag `IFIX.RAMP.F_CV` in an iFIX collector running on different PC than archiver. Configure it to have a one-second collection interval. The **Current Value** should be within one second of the value shown in a data link.
2. Stop the iFIX collector. The end-of-collection marker is sent to the data, so the **Current Value** quality should be marked as **bad** and its value set to zero.
3. Restart the iFIX collector. The **Current Value** quality should be marked as **good** and it should have a valid value.

4. Put the block off scan in the PDB. The **Current Value** quality should be marked as **bad**. (Put the block back on scan when you've verified this.)
5. Pull the network cable from the iFIX collector running on another machine. The current value remains unchanged as the value was good at the time the cable was pulled. To ensure that the **Current Value** is accurate, you would have to use the **Heartbeat Address** of the iFIX collector to verify that the collector is running.
6. Enable collector compression for the point and ensure that the tag's value does not change. The time stamp of the current value will stay the same until the collector reports a change.

Anticipated Usage

The current value can be used in any operator display. You should also display the data quality of the current value. You may choose to use the **Heartbeat** address of the collector so that you can confirm that the collector is running and that the current value is therefore up to date.

If the collector was shut down gracefully, then the current value would correctly display a bad data quality (and a value of 0). If the collector crashed or was disconnected from the server, then the current value will be the last value sent before the crash or disconnect.

Lab Sampling Mode

Lab Sampling is designed to duplicate the way iFIX classic Historian (HTA/HTC) returned data. This sampling mode returns only collected values. Each collected value is repeated until the next collected value, resulting in a jagged step plot instead of a smooth curve.

Interpolated values are used in other calculation modes. Lab sampling is never used by calculation modes. Each sample has the following attributes:

- **Timestamp** - Lab sampling determines intervals and timestamps the same as interpolated retrieval.
- **Value** - Any value returned is an actual collected raw value; the data value is never interpolated.
- **Data Quality** - Lab sampling uses the same logic as interpolated sampling to determine percent good quality.

Retrieving lab sample values of an interval with GOOD data

This sample uses exactly the same parameters as the interpolated sampling example, except that the sampling mode should be specified as `lab`.

```
select timestamp, value, quality from
    ihrawdata where samplingmode=lab and timestamp >= '29-Mar-2002 13:50' and
```

```
timestamp <= '29-Mar-2002 14:30' and tagname = tag1 and numberofsamples =
```

```
8
```

This supplies the following results:

Timestamp	Value	Quality
29-Mar-200213:55:00.000	0.00	0.00
29-Mar-200214:00:00.000	22.70	100.00
29-Mar-200214:05:00.000	22.70	100.00
29-Mar-200214:10:00.000	12.50	100.00
29-Mar-200214:15:00.000	7.00	100.00
29-Mar-200214:20:00.000	7.00	100.00
29-Mar-200214:25:00.000	4.80	100.00
29-Mar-200214:30:00.000	4.80	100.00

The value is never anything other than a collected value. This differs from interpolated sampling. A plot of this data would look like a series of steps, rather than a smooth, interpolated curve.

Anticipated Usage: Since lab sampling returns real, collected values, it is more accurate when a sufficient number of raw samples are stored. Use interpolated sampling for highly compressed data. It is generally not useful with archive compression. Collector compression can be used to filter out non-changing values, but a high deadband reduces the number of raw samples and therefore reduces the accuracy of lab sampling.

Interpolated Sampling Mode

This topic describes *interpolated retrieval mode*. It also presents concepts that are common to interpolated, lab, calculated, and trend retrieval modes. Interpolation is a separate sampling mode and is also used in the various calculation modes.

Data compression necessitates interpolation. A minimal number of real data points is stored in the archive. On retrieval, interpolation is performed to produce an evenly spaced list of the most likely real world values. Even if you are not using compression, you can use interpolation if you want samples spaced on intervals other than the "true" collection rate.

The following data is used in the examples below. You can import this data into Historian if you want to try the examples yourself:

*Example for Interpolated Data Documentation

*

[Tags]

Tagname,DataType,HiEngineeringUnits,

LoEngineeringUnits TAG1,SingleFloat,60,0

BADDQTAG,SingleFloat,60,0

[Data]

Tagname,TimeStamp,Value,DataQuality

TAG1,29-Mar-2002 13:59:00.000,22.7,Good

TAG1,29-Mar-2002 14:08:00.000,12.5,Good

TAG1,29-Mar-2002 14:14:00.000,7.0,Good

TAG1,29-Mar-2002 14:22:00.000,4.8,Good

BADDQTAG,29-Mar-200213:59:00.000,22.7,Good

BADDQTAG,29-Mar-2002 14:08:00.000,12.5,Bad

BADDQTAG,29-Mar-2002 14:14:00.000,7.0,Bad

BADDQTAG,29-Mar-2002 14:22:00.000,4.8,Good

Timestamp

All sampling and calculation modes (except raw sampling) use the same method for creating intervals from the start and end time. Raw retrieval has no intervals, only a start and end time. Each mode differs in how it arrives at the value to assign to that interval

The simplest case is when the interval is evenly divisible by the number of samples or by the interval in milliseconds. For example, the start and end times are one hour apart and you want data at ten-minute intervals, or 6 samples. The first time stamp occurs at the start time + one interval and represents the samples from a point greater than the start time to less than or equal to the interval time stamp.

Determining interval timestamps for evenly divisible duration

1. Import this data into the Historian. There is only a tag, with no data.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
c1,SingleFloat,100,0
```

2. Retrieve data for that tag over a 1-hour duration with a 10-minute interval. Use the following query:

```
select timestamp from ihrawdata where timestamp >= 14:00 and timestamp <= 15:00 and tagname = c1 and
numberofsamples = 6
```

or this query

```
select timestamp from ihrawdata where timestamp >= 14:00 and timestamp <= 15:00 and tagname = c1 and
Intervalmilliseconds = 10M
```

Both SQL queries result in the same intervals and interval timestamps

```
3/29/2002 14:10:00
3/29/2002 14:20:00 3/29/2002 14:30:00
3/29/2002 14:40:00
3/29/2002 14:50:00
3/29/2002 15:00:00
```

When the 1-hour duration is not evenly divisible, interval timestamps will include milliseconds even if the data samples do not use a resolution of milliseconds.

Example: Determining interval timestamps for a non-divisible duration

Divide the one hour duration from previous example into 7 intervals:

```
select timestamp from ihrawdata where timestamp >= 14:00 and timestamp <= 15:00 and tagname = c1 and
numberofsamples = 7
```

```
3/29/2002 14:08:34.285
3/29/2002 14:17:08.571
3/29/2002 14:25:42.857
3/29/2002 14:34:17.142
3/29/2002 14:42:51.428
3/29/2002 14:51:25.714
3/29/2002 14:59:59.999
```

**Note:**

Trend sampling determines intervals using a different method, described in the trend sampling topic.

Value

The logic for determining the value through interpolation is as follows:

Attribute samples to intervals

Any raw sample is attributed to exactly one interval based on the raw sample and interval time stamp. The rule is that the sample has to have a time stamp greater than the interval start time, but less than or equal to the end time. This is because the end timestamp of the interval is the start timestamp on the next interval.

Interpolate a value at each interval end time

For each interval end time, find the raw point before and after the end time. The interval time stamp is the interval end time; we can then interpolate the value at that time.

Determining interval interpolated value

This example shows how linear interpolation determines the most likely real world value at the interval timestamp.

Using the same data set as above, there are raw points at:

```
14:08:00.000,12.5,Good
14:14:00.000,7.0,Good
```

and you are trying to get an interpolated value at 14:10. The calculation used for linear interpolation would be:

```
interpolated value = previous raw sample + ((deltaY/deltaX) * offset)
```

Substituting the numbers for this example:

$\text{deltaY} = 7.0 - 12.5 = -5.5$

$\text{deltaX} = 14 - 8 = 6$

$\text{offset} = 2$ seconds (from 14:08 to 14:10)

$\text{Interpolated value} = 12.5 + ((-5.5/6)*2) = 10.67$

About Interpolated Data Type

When interpolating data, the data type of the value will be the same data type as that of the tag's raw data. Only floating point and double floating point values can be interpolated. Integers, strings, and blobs cannot be interpolated. When attempting to interpolate string and integer data, interpolation will simply repeat the collected value for each interval until the next collected value.

Retrieving interpolated values of an interval with GOOD data

The raw samples for TAG1 can be plotted as follows. The "G" indicates a good data quality raw sample.



Use this SQL query to retrieve the data:

```
select timestamp, value, quality from ihrawdata where samplingmode=interpolated and timestamp >=
'29-Mar-2002 13:50' and timestamp <= '29-Mar-2002 14:30' and tagname = tag1 and numberofsamples = 8
```

Timestamp	Value	Quality
29-Mar-2002 13:55:00.000	0.00	0.00
29-Mar-2002 14:00:00.000	21.57	100.00
29-Mar-2002 14:05:00.000	15.90	100.00
29-Mar-2002 14:10:00.000	10.67	100.00
29-Mar-2002 14:15:00.000	6.73	100.00
29-Mar-2002 14:20:00.000	5.35	100.00
29-Mar-2002 14:25:00.000	4.80	100.00
29-Mar-2002 14:30:00.000	4.80	100.00


**Note:**

The 13:50 to 13:55 interval is represented by the 13:55 timestamp.


There may be many raw points in an interval, but interpolation uses only the last one in the interval and the first one in the next interval. The sections below describe the interpolation behavior in the 3 possible cases.

Case 1: Good Data Samples Before and After the Interval Timestamp


This is the typical case when compression is not used. There are 2 good data quality raw points. With interpolation, calculate the slope and offset of this line and interpolate the value at the interval timestamp. The 14:10 interval has a sample at 14:08 and at 14:14.

**Case 1a: Good Data Samples between the Interval Timestamp and the Start and End Time**

In a similar case, there may be intervals with no raw samples, such as when data compression is used. Here, there is at least 1 good raw sample between the start time and interval, and at least 1 good raw sample between the interval and end time. The good raw samples are interpolated across intervals to determine values at the 14:00 and 14:05 intervals:


**Case 2: No Good Data between Start Time and Interval Timestamp**

If no or bad data occurs before the interval, then the interval is given a bad data quality. The 13:55 interval is an example of this. Note that bad data is treated identically to no data.



Case 3: No Good Data between Interval Timestamp and End Time

If no or bad data occurs after the interval then the interval is given a good data quality, but the value is simply stretched instead of interpolated. The 14:25 interval is an example of this. Note that bad data is treated identically to no data. Good data quality is attributed to the 14:30 interval



Data Quality

Unlike CurrentValue, RawByTime, and RawByNumber, Interpolated data does not assign an individual data quality to each returned sample. Since Interpolated, Lab, and Calculated retrieval modes can contain multiple samples in an interval, the data qualities of each point are combined and summarized as a percent good value.


Interpolated and Lab sampling determine the percent good using the same procedure, resulting in a value of either 100 or 0 (though the determined value may be different for each mode even with the same data). Intermediate percent good values are determined only for Calculated retrieval modes.

The following examples illustrate interpolated and lab sampling modes. For each example, you can see that the behavior is the same for lab and interpolated sampling by changing `samplingmode=Interpolated` to `samplingmode=lab`.

Interpolated and Lab retrieval resulting in percent good of 100

This example illustrates the effect of bad data quality samples on the percent good statistic for an interval. The start and end times vary so that bad samples are included or excluded, which affects the percent good statistic

The data for `BADDQTAG` can be plotted as follows. The `G` is used to indicate a good data quality raw sample and the `B` indicates a sample of bad data quality. A query of the whole data set is



Using this query for a period starting with good data quality:

```
select timestamp, value, quality from ihrawdata where samplingmode=interpolated and timestamp >=
'29-Mar-2002 13:55' and timestamp <= '29-Mar-2002 14:25' and tagname = baddqtag and numberofsamples = 1
```

This results in the following data quality:

Timestamp	Value	Quality
29-Mar-200214:25:00.000	4.80	100.00

The percent good is 100. Even though the interval contains bad data quality samples, the interval does not end with bad data quality. Percent good is determined this way because the purpose of interpolation and lab sampling is to determine the value and quality at the interval timestamp. On the other hand, Calculation modes operate on the full set of raw samples within an interval and therefore result in percent good values between 0 and 100.


This interval from 14:10 to 14:25 starts with a bad data quality sample but ends with a good sample, so the results are the same. That is, the query:

```
select timestamp, value, quality from ihrawdata where samplingmode=interpolated and timestamp >=
'29-Mar-2002 14:10' and timestamp <= '29-Mar-2002 14:25' and tagname = baddqtag and numberofsamples = 1
```

produces the same percent good result of 100.

Example: Interpolated and Lab retrieval resulting in percent good of 0


This example shows some data patterns that result in a percent good of 0. An interval ending with a bad data quality sample, always results in a percent good of 0 for the interval.



Timestamp	Value	Quality
29-Mar-2002 14:10:00.000	0.00	0.00


```
select timestamp, value, quality from ihrawdata where samplingmode=interpolated and timestamp >=
'29-Mar-2002 13:55' and timestamp <= '29-Mar-2002 14:10' and tagname = baddqtag and numberofsamples = 1
```

Timestamp	Value	Quality
29-Mar-2002 14:10:00.000	0.00	0.00




Example: Interpolated and Lab retrieval of an empty interval

The data quality of an empty interval depends on the previous and following raw samples. Intervals with a prior good data quality sample have a percent good of 100 and intervals preceded by a bad data quality sample (or no sample) have in a percent good of zero.



This query results in a percent good of 100:

```
select timestamp, value, quality from ihrawdata where samplingmode=interpolated and timestamp >=
'29-Mar-2002 14:00' and timestamp <= '29-Mar-2002 14:05' and tagname = baddqtag and numberofsamples = 1
```



Both of these queries produce a percent good of 0. The first has no preceding sample and the second is preceded by bad data:

```
select timestamp, value, quality from ihrawdata where samplingmode=interpolated and timestamp >=
'29-Mar-2002 13:50' and timestamp <= '29-Mar-2002 13:55' and tagname = baddqtag and numberofsamples = 1

select timestamp, value, quality from ihrawdata where samplingmode=interpolated and timestamp >=
'29-Mar-2002 14:15' and timestamp <= '29-Mar-2002 14:20' and tagname = baddqtag and numberofsamples = 1
```

The lab retrieval at 14:15 has a value of 7 but quality of 0. Note that you should almost always ignore specific values when the percent good is 0.

Raw Data Sampling Modes

To use raw data retrieval, you need only specify a start and end time, or a start time and number of samples. Any specified interval duration is ignored. Raw data may be retrieved using one of two methods:

- **RawByTime retrieval:** Specify a start and end time for data retrieval. RawByTime returns all raw samples of all qualities with a time stamp greater than the start time and less than or equal to the end time. It will not return a raw sample with same time stamp as the start time. NumberOfSamples is ignored and all raw samples will be returned.
- **RawByNumber Retrieval:** Specify a start time, a number of samples, and a direction (forward or backward). RawByNumber retrieval returns X raw samples of all qualities starting from a time stamp of the indicated start time, moving in the specified direction. It will return a raw sample with the same time stamp as the start time. If there is no sample at the specified start time, the retrieval count begins at the next sample.

Each sample has the following attributes:

- **Timestamp:** The time stamp sent by the collector along with the raw sample.
- **Value:** The value sent by the collector along with the raw sample.
- **Data Quality:** The quality of data sent by the collector, as set by the collector.

Archive compression can reduce the number of raw samples stored in the archive. Archive compression may discard raw samples sent by the collector; these are not stored as raw samples and would not be returned by raw data retrieval.

If the current value has not been stored as a raw sample, will not be returned by a raw data retrieval.

If they exist within the requested time period, collected samples with a bad data quality and collector startup and shutdown markers will be returned in a raw data query.

RawByTime retrieval of samples over a period of replaced data

1. Import this data into the Historian.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
RAWTAG,SingleInteger,100,0

[Data]
Tagname,TimeStamp,Value,DataQuality
RAWTAG,29-Mar-2002 13:59:00.000,7,Good
RAWTAG,29-Mar-2002 14:08:00.000,8,Bad
```

2. Import this data into the Historian so that there is replaced data:

```
[Data]
Tagname,TimeStamp,Value,DataQuality
```

```

RAWTAG,29-Mar-2002 13:59:00.000,22,Good
RAWTAG,29-Mar-2002 14:08:00.000,12,Bad
RAWTAG,29-Mar-2002 14:22:00.000,4,Good

```

3. Retrieve the data using this RawByTime query.

```

select timestamp, value, quality from ihrawdata where samplingmode=rawbytime and timestamp>='29-Mar-2002
13:59' and timestamp<='29-Mar-2002 14:22' and tagname=rawtag

```

The following results are obtained:

Timestamp	Value	Quality
29-Mar-200214:08:00.000	12	Bad NonSpecific
29-Mar-200214:22:00.000	4	Good NonSpecific

Note that the raw sample exactly at the start time is not returned and that the replaced value of 8 at 14:08 is not returned. If the start time is changed to 13:58:59, then all the samples are returned:

```

select timestamp, value, quality from ihrawdata where samplingmode=rawbytime and timestamp>='29-Mar-2002
13:58:59' and timestamp<='29-Mar-2002 14:22' and tagname=RAWTAG

```

Timestamp	Value	Quality
29-Mar-200213:59:00.000	22	Good NonSpecific
29-Mar-200214:08:00.000	12	Bad NonSpecific
29-Mar-200214:22:00.000	4	Good NonSpecific

RawByNumber retrieval over a period of replaced data

The RawByNumber sampling mode returns up to a specified number of raw samples beginning at the start time. The end time is ignored. Unlike the RawByTime, this can return a sample that has the same time stamp as the start time. You must specify a direction forward or backward from the start time to retrieve data.

- Using the data imported by the previous example, retrieve 10 samples going forward from 13:59:00.

```

select timestamp, value, quality from ihrawdata where samplingmode=rawbynumber and timestamp>='29-Mar-2002
13:59' and numberofsamples=10 and direction=forward and tagname=RAWTAG

```

The following results are obtained.

Timestamp	Value	Quality
29-Mar-200213:59:00.000	22	Good NonSpecific
29-Mar-200214:08:00.000	12	Bad NonSpecific
29-Mar-200214:22:00.000	4	Good NonSpecific

- Using the data imported by the previous example, retrieve 10 samples going backward from 14:22:00.

```
select timestamp, value, quality from ihrawdata where samplingmode=rawbynumber and timestamp<='29-Mar-2002
14:22' and numberofsamples=10 and direction=backward and tagname=RAWTAG
```

The following results are obtained.

Timestamp	Value	Quality
29-Mar-200214:22:00.000	4	Good NonSpecific
29-Mar-200214:08:00.000	12	Bad NonSpecific
29-Mar-200213:59:00.000	22	Good NonSpecific

Anticipated usage

You can use raw sampling to compute a raw minimum or raw maximum over a time period. `Raw Average` is already provided as a native calculation mode

You can also use raw sampling to analyze system efficiency. Count the number of raw samples per period of time, ignoring the values, then compare it to other periods of time.

If you have a high number of raw samples you may decide to implement collector or archive compression. If you have a different count of raw samples than another time period for the same point in your process, you should understand why the data is missing or why the extra data was logged.

You can use the `ihCount` calculation mode to easily count the number of raw samples between the start and end time.

RawByFilterToggle Sampling Mode

The `RawByFilterToggle` sampling mode is a form of filtered data query. A filtered data query returns data values for a particular time period whereas `RawByFilterToggle` sampling mode returns the time periods where the condition becomes TRUE or FALSE. The `RawByFilterToggle` sampling mode returns the

Timestamp, Value, and Data Quality for the matching entries. The data values returned will have the same tagname which you queried for.

RawByFilterToggle returns only 0 and 1. The value 1 is returned with a timestamp when the filter condition becomes TRUE, and the value 0 is returned with the timestamp when the filter condition becomes FALSE. You can have multiple pairs of 1 and 0 values if the condition becomes TRUE multiple times between the start and end time. If the condition never became TRUE between the start and end time, you will not get any values.

Timestamp

The RawByFilterToggle sampling mode returns 0 and 1 as values. The value 1 is returned with a timestamp when the filter condition becomes TRUE, and the value 0 is returned with the timestamp when the filter condition becomes FALSE. You can have multiple pairs of 1 and 0 values if the condition becomes TRUE multiple times between the start and end time. If the condition never became TRUE between the start and end time, you will not get any values. You can use a filterexpression to return the time ranges that match the criteria.

The RawByFilterToggle sampling mode can return any timestamp between the start and end time, depending on if and when the condition becomes TRUE or FALSE. The timestamps returned can be queried further using RawByTime, RawByNumber, Interpolated, or any other sampling or calculation mode.

Value

This sampling mode only returns 0 and 1 as values. The value 1 is returned with a timestamp where the filter condition is TRUE and 0 is returned with the timestamp where the filter condition is FALSE.

Data Quality

The RawByFilterToggle considers only Good quality data.

Retrieving Data Using RawByFilterToggle Sampling Mode

The following two examples use this data that is imported into Proficy Historian. This data will be used in the examples for retrieving data with the RawByFilterToggle sampling mode.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,
LoEngineeringUnits RAMP,SingleInteger,10,0

[Data]
Tagname,TimeStamp,Value,Data Quality
```

RAMP, 25-Feb-2013 07:00:00.000,0,Good,
RAMP, 25-Feb-2013 07:00:01.000,1,Good,
RAMP, 25-Feb-2013 07:00:02.000,2,Good,
RAMP, 25-Feb-2013 07:00:03.000,3,Good,
RAMP, 25-Feb-2013 07:00:04.000,4,Good,
RAMP, 25-Feb-2013 07:00:05.000,5,Good,
RAMP, 25-Feb-2013 07:00:06.000,6,Good,
RAMP, 25-Feb-2013 07:00:07.000,7,Good,
RAMP, 25-Feb-2013 07:00:08.000,8,Good,
RAMP, 25-Feb-2013 07:00:09.000,9,Good,
RAMP, 25-Feb-2013 07:00:10.000,10,Good,
RAMP, 25-Feb-2013 07:00:11.000,11,Good,
RAMP, 25-Feb-2013 07:00:12.000,12,Good,
RAMP, 25-Feb-2013 07:00:13.000,13,Good,
RAMP, 25-Feb-2013 07:00:14.000,14,Good,
RAMP, 25-Feb-2013 07:00:15.000,15,Good,
RAMP, 25-Feb-2013 07:00:16.000,16,Good,
RAMP, 25-Feb-2013 07:00:17.000,17,Good,
RAMP, 25-Feb-2013 07:00:18.000,18,Good,
RAMP, 25-Feb-2013 07:00:19.000,19,Good,
RAMP, 25-Feb-2013 07:00:20.000,20,Good,
RAMP, 25-Feb-2013 07:00:21.000,21,Good,
RAMP, 25-Feb-2013 07:00:22.000,22,Good,
RAMP, 25-Feb-2013 07:00:23.000,23,Good,
RAMP, 25-Feb-2013 07:00:24.000,24,Good,
RAMP, 25-Feb-2013 07:00:25.000,25,Good,
RAMP, 25-Feb-2013 07:00:26.000,26,Good,
RAMP, 25-Feb-2013 07:00:27.000,27,Good,
RAMP, 25-Feb-2013 07:00:28.000,28,Good,
RAMP, 25-Feb-2013 07:00:29.000,29,Good,
RAMP, 25-Feb-2013 07:00:30.000,30,Good,
RAMP, 25-Feb-2013 07:00:31.000,31,Good,
RAMP, 25-Feb-2013 07:00:32.000,32,Good,
RAMP, 25-Feb-2013 07:00:33.000,33,Good,
RAMP, 25-Feb-2013 07:00:34.000,34,Good,
RAMP, 25-Feb-2013 07:00:35.000,35,Good,
RAMP, 25-Feb-2013 07:00:36.000,36,Good,

```

RAMP,25-Feb-2013 07:00:37.000,37,Good,
RAMP,25-Feb-2013 07:00:38.000,38,Good,
RAMP,25-Feb-2013 07:00:39.000,39,Good,
RAMP,25-Feb-2013 07:00:40.000,40,Good,
RAMP,25-Feb-2013 07:00:41.000,41,Good,
RAMP,25-Feb-2013 07:00:42.000,42,Good,
RAMP,25-Feb-2013 07:00:43.000,43,Good,
RAMP,25-Feb-2013 07:00:44.000,44,Good,
RAMP,25-Feb-2013 07:00:45.000,45,Good,
RAMP,25-Feb-2013 07:00:46.000,46,Good,
RAMP,25-Feb-2013 07:00:47.000,47,Good,
RAMP,25-Feb-2013 07:00:48.000,48,Good,
RAMP,25-Feb-2013 07:00:49.000,49,Good,
RAMP,25-Feb-2013 07:00:50.000,50,Good,
RAMP,25-Feb-2013 07:00:51.000,51,Good,
RAMP,25-Feb-2013 07:00:52.000,52,Good,
RAMP,25-Feb-2013 07:00:53.000,53,Good,
RAMP,25-Feb-2013 07:00:54.000,54,Good,
RAMP,25-Feb-2013 07:00:55.000,55,Good,
RAMP,25-Feb-2013 07:00:56.000,56,Good,
RAMP,25-Feb-2013 07:00:57.000,57,Good,
RAMP,25-Feb-2013 07:00:58.000,58,Good,
RAMP,25-Feb-2013 07:00:59.000,59,Good,

```

Determining the Time Range After the Condition Became TRUE

An example of a Query using RawByFilterToggle sampling mode is as follows:

```

starttime='02/25/2013 07:00:00', endtime='02/25/2013 07:10:00'
select timestamp, value, quality from ihrawdata where tagname = RAMP and samplingmode= rawbyfiltertoggle
and filterexpression='(RAMP>50)' and filtermode=AfterTime

```

This query `set` would determine when the ramp value exceeded 50 and returns the time range after that.

The following results are obtained:

Timestamp	Value	Quality
02/25/201307:00:00	0	Good NonSpecific
02/25/201307:00:51	1	Good NonSpecific

Timestamp	Value	Quality
02/25/201307:10:00	1	Good NonSpecific

You can see in the raw data that the condition became true at 7:00:51 so the sample is returned with a value of 1. The 0 and 1 are bounding values that would make the data easier to plot. You cannot simply count the number of 1s returned to count the number of times the condition became true. You have to exclude the bounding values

Example 2: Determining the Time Range Before the Condition Became TRUE

An example of a query using RawByFilterToggle sampling mode is as follows

```
set starttime='02/25/2013 07:00:00', endtime='02/25/2013 08:00:00'

select timestamp, value, quality from ihrawdata where tagname = RAMP and samplingmode= rawbyfiltertoggle

and filterexpression='(RAMP>10)' and filtermode=BeforeTime
```

The following results are obtained

Timestamp	Value	Quality
02/25/201307:00:00	0	Good NonSpecific
02/25/201307:00:10	1	Good NonSpecific
02/25/201307:00:59	0	Good NonSpecific
02/25/201308:00:00	0	Good NonSpecific

You can see in the raw data that the condition became true at 7:00:10 so the sample is returned with a value of 1.

Anticipated Usage

This sampling mode can be used for the same reasons as filtered data queries. That is, when you want the Historian Data Archiver to determine the exact time(s) of the event and you have an approximate time range for an event of interest, such as:

- A batch starting or completing.
- A value exceeding a limit.
- A collected value matching a specified value.

Once you have the exact time range(s) as returned from `RawByFilterToggle`, you can use those time ranges in the subsequent data queries or in custom reporting or data analysis applications.

Trend Sampling Mode

The Trend Sampling mode maximizes performance when retrieving data specifically for plotting.

The Trend Sampling mode identifies significant points and returns them to the caller. These will be raw samples. Significant points are established by finding the raw minimum and raw maximum values within each interval. Note that this is not the same as finding the change in slope direction of a line, as archive compression does.

The Trend Sampling mode approximates a high resolution trend with only as much detail as could be drawn on the page. For example, say you are about to draw a trend on the page and you know that the area with the trend graph is only 100 pixels wide. You could not possibly represent any more than 100 points in those 100 pixels. By using the Trend sampling type, you can ensure you retrieve adjacent highs and lows to draw a visually accurate trend with only 100 points, regardless of whether the time period was one year or one hour.

Since the Trend Sampling mode does not need to acquire all data between the specified start and end times, it is a very efficient method of data retrieval, especially for large data sets. Depending on the requested start and end times (and the amount of data stored for that interval), it could be as much as 100 times faster than other methods.

When displaying data for reports or examination, this principle can be applied to other sampling types too. It is highly inefficient to trend data at a higher resolution than can be drawn on page or printed on hard copy. This is useful even for calculation modes like "Average value". It is not suitable for Interpolated mode, since this results in a loss of detail that ihTrend sampling attempts to recapture.

The `ihTrend` sampling type returns adjacent highs and lows within each interval. If you ask for 100 samples, you will effectively receive 50 high values and 50 low values over 100 intervals. The retrieval process works as follows:

1. Divide the query duration into even-length intervals, like other sampling modes.
2. Determine the raw minimum and raw maximum for each interval. If there is only one point, then that is both the minimum and maximum.
3. Since we want to return 2 samples per interval (a minimum and a maximum), we need twice as many intervals. Divide each interval in half. For example, a one hour interval of 01:00:00 to 02:00:00 becomes 2 intervals (01:00:00 to 01:30:00) and (01:30:00 to 02:00:00) .
4. Put the minimum in one half-interval and the maximum in the other. If minimum comes before maximum, put the minimum in the first half-interval and the maximum in second half-interval, and vice versa.

When doing filtered data queries, your maximum returned intervals must pass the throttle, even if only a few intervals actually match the filtered criteria.

Timestamp

There is no difference between full-interval timestamps and half-interval timestamps. Both are valid and all interval timestamps are in ascending order.

The Trend Sampling mode will always have an even number of samples, rounded up when necessary.

For example, if you request num samples = 7 or num samples = 8, you will get 8 samples.

If you request results by interval instead of number of samples, you will get back twice the number of results you expect.

For example, a 5-minute interval for a 40-minute duration is normally $40 / 5 = 8$ samples. But with trend sampling, you get 16 evenly-spaced intervals.

Value

The raw minimum or raw maximum of the full interval. There is no indication as to which one you are getting.

Data Quality

Trend sampling uses the same logic as interpolated sampling to determine the percent good quality.

Retrieving trend sample value

Using the data from the interpolated example, execute this query

```
select timestamp, value, quality from ihrawdata where samplingmode=trend and timestamp >=
'29-Mar-2002 13:50' and timestamp <= '29-Mar-2002 14:30' and tagname = tag1 and numberofsamples = 8
```

The following results are returned:

Timestamp	Value	Quality	Raw Samples
29-Mar-200213:55:00.000	22.70	100.00	None
29-Mar-200214:00:00.000	22.70	100.00	13:59:00.000,22.7, Good

Timestamp	Value	Quality	Raw Samples
29-Mar-2002 14:05:00.000	12.50	100.00	None
29-Mar-2002 14:10:00.000	12.50	100.00	14:08:00.000,12.5, Good
29-Mar-2002 14:15:00.000	7.00	100.00	14:14:00.000,7.0, Good
29-Mar-2002 14:20:00.000	7.00	100.00	

The interval timestamps are the same as for interpolated. The raw minimum and raw maximum are determined for each interval.

For example, a tag has data every second for 1 year (around 31 million data points). We want to perform a query using `ihTrend` with `StartTime = LastYear`, `EndTime = now`, and `NumSamples = 364`.

The `StartTime` to `EndTime` is broken down into `NumSamples/2` pseudo-intervals (182). For each pseudo-interval, the min and max value is found. These will be the first two data points. With two data points per pseudo-interval multiplied by `NumSamples/2` gives us the desired `NumSamples`. If the minimum occurs before the maximum, it will be the first of the two samples, and vice versa.

The query:

```
select timestamp, value, quality from ihrawdata where samplingmode=lab and timestamp >=
'29-Mar-2002 13:50' and timestamp <= '29-Mar-2002 14:30' and tagname = tag1 and numberofsamples = 8
```

The following results are returned:

Timestamp	Value	Quality
29-Mar-2002 13:55:00.000	0.00	0.00
29-Mar-2002 14:00:00.000	22.70	100.00
29-Mar-2002 14:05:00.000	22.70	100.00
29-Mar-2002 14:10:00.000	12.50	100.00
29-Mar-2002 14:15:00.000	7.00	100.00
29-Mar-2002 14:20:00.000	7.00	100.00

Timestamp	Value	Quality
29-Mar-200214:25:00.000	4.80	100.00
29-Mar-200214:30:00.000	4.80	100.00

Trend Data returned in the wrong interval

Note that, with trend sampling, data can be returned using an interval timestamp that does not contain the sample. A CSV file includes three values for each of 9 days.

```
[Data]
Tagname,TimeStamp,Value
Dfloattag5,01/05/03 8:00,95.00
Dfloattag5,01/05/03 15:00,88.00
Dfloattag5,01/05/03 16:00,80.00
Dfloattag5,01/06/03 7:00,11.00
Dfloattag5,01/06/03 10:00,13.00
Dfloattag5,01/06/03 13:00,93.00
Dfloattag5,01/07/03 8:00,99.0
Dfloattag5,01/07/03 11:00,86.0
Dfloattag5,01/07/03 12:00,16.0
Dfloattag5,01/08/03 8:00,0.00
Dfloattag5,01/08/03 12:00,99.00
Dfloattag5,01/08/03 14:00,100.00
```

If you use the following query:

```
Select timestamp,tagname,value Quality from ihrawdata where tagname =dfloattag5
And samplingmode= trend and intervalmilliseconds =24h
And timestamp> '1/02/2003 07:00:00' and timestamp<= '01/10/2003 12:00:00'
```

then the results include:

Timestamp	Tag Name	Value	Quality
6-Jan-200319:00:00	Dfloattag5	13.00	100
7-Jan-200307:00:00	Dfloattag5	93.00	100
7-Jan-200319:00:00	Dfloattag5	99.00	100
8-Jan-200307:00:00	Dfloattag5	16.00	100

It is expected that the value 93 is listed for 1/6/03 19:00:00, since that is where the timestamp of the raw sample occurs. However, the maximum of 1/6/03 07:00:00 to 1/7/03 07:00:00 is:

```
Dfloattag5,01/06/03 13:00,93.00
```

which comes after the minimum of:

```
Dfloattag5,01/06/03 10:00,13.00
```

Hence, it is placed in the second half-interval, even though its timestamp does not fall into the time range for that half-interval. Raw samples will never be placed in the wrong "real" interval, but may be placed in the wrong "fake" interval.

Anticipated Usage: Trend sampling is designed only for graphical plotting applications.

Trend2 Sampling Mode

The Trend2 sampling mode is a modified version of the Trend sampling mode.

The Trend2 sampling mode splits up a given time period into a number of intervals (using either a specified number of samples or specified interval length), and returns the minimum and maximum data values that occur within the range of each interval, together with the timestamps of the raw values.

The key differences between Trend and Trend2 sampling modes are in:

- How they treat a sampling period that does not evenly divide by the interval length:
 - For the Trend sampling mode, Historian ignores any leftover values at the end, rather than putting them into a smaller interval.
 - For the Trend2 sampling mode, Historian creates as many intervals of the interval length as will fit into the sampling period, and then creates a remainder interval from whatever time is left.
- Spacing of timestamps returned:
 - For the Trend sampling mode, Historian returns evenly-spaced interval timestamps.
 - For the Trend2 sampling mode, Historian returns raw sample timestamps. These timestamps can be unevenly spaced, since raw data can be unevenly spaced.
- Inclusion of start and end times entered:
 - The Trend sampling mode is start time exclusive and end time inclusive.
 - The Trend2 sampling mode is start time inclusive and end time inclusive.

The Trend sampling mode is more suitable for plotting applications that prefer evenly-spaced data.

The Trend2 sampling mode is more suitable for analysis of mins and maxes and for plotting programs that can handle unevenly spaced data.

Table 87. Parameters

Name	Description
Tagname(s)	Specify all of the tag(s) on which to perform Trend2 sampling.
Starting time	<p>Specify when the time period starts.</p> <p>Values in the raw data whose timestamps fall on the starting time will be included in the results, if they are the minimum or the maximum in the interval.</p>
Ending time	<p>Specify when the time period ends.</p> <p>Values in the raw data whose timestamps fall on the ending time will be included in the results, if they are the minimum or the maximum in the interval.</p>

The following determine the size of the intervals:

Name	Description
Interval length	<p>If you specify the interval length, then Historian splits the time period between start and end into as many intervals of that length as will fit in the period.</p> <p>For example, if you have a 30 second time period, and you request intervals of 5 seconds, Historian will break the time period into 6 intervals, each of which covers 5 seconds.</p> <p>If the sampling period does not evenly divide by the interval length, then Historian creates as many intervals of that length as will fit, and then create a remainder interval from whatever time is left. So, if we request intervals of 7 seconds for a 30 second time period, Historian splits the sampling period into 4 intervals of 7 seconds each, and one remainder interval of 2 seconds.</p> <p>This behavior is in contrast to the original Trend sampling, which would simply ignore any leftover values at the end, rather than putting them into a smaller interval.</p>

Name	Description
Number of samples	<p>If you specify the number of samples to return, Historian determines the number of intervals to return. Each interval returns 2 samples, so Historian divides the time period between start and end into half as many intervals as there are specified samples.</p> <p>For example, if you specify 12 samples, Historian will divide the time period into 6 intervals, because $12/2 = 6$.</p> <p>If the number of samples specified is odd, then it is rounded up to the nearest even number. So, if you ask for 7 samples, Historian rounds up to 8 samples, from $8/2 = 4$ intervals. All intervals are of the same length.</p> <p>If the time period from start to finish is 60 seconds and we request 10 intervals, then each interval will be 6 seconds long.</p>

About Retrieving Data from Historian

After data collection, the Historian server compresses and stores the information in an .iha file in Data Archive. Any client application can retrieve archived data through the Historian API. The Historian API is a client/server programming interface that maintains connectivity to the Historian Server and provides functions for data storage and retrieval in a distributed network environment.

You can retrieve data from Historian using any number of clients, including but not limited to:

- Configuration Hub
- Historian Analysis
- Knowledge Center
- iFIX
- CIMPPLICITY
- Real-Time Information Portal
- Dream Reports
- Excel Add-In
- Custom SDK Applications
- OLE DB

Historian exposes various sampling and calculation modes that are used on retrieval of data that has already been collected to the archive. These modes do not effect data collection. Some sampling modes

are suited to compressed data and should be used when collector compression or archive compression is used.

Sampling Modes

Sampling modes are used to specify how the data will be retrieved from Historian. Several modes are available, such as CurrentValue, Interpolated, Calculated and RawByTime. Sampling modes are specified in the client you use to retrieve data from Historian.

For more information, refer to the *Advanced Topics* section in the online help.

- For the Trend sampling mode, Historian ignores any leftover values at the end, rather than putting them into a smaller interval.
- For the Trend2 sampling mode, Historian creates as many intervals of the interval length as will fit into the sampling period, and then creates a remainder interval from whatever time is left.
- Spacing of timestamps returned:
 - For the Trend sampling mode, Historian returns evenly-spaced interval timestamps.
 - For the Trend2 sampling mode, Historian returns raw sample timestamps. These timestamps can be unevenly spaced, since raw data can be unevenly spaced.
- Inclusion of start and end times entered:
 - The Trend sampling mode is start time exclusive and end time inclusive.
 - The Trend2 sampling mode is start time inclusive and end time inclusive.

Trend sampling mode is more suitable for plotting applications that prefer evenly-spaced data.

Trend2 sampling mode is more suitable for analysis of mins and maxes and for plotting programs that can handle unevenly spaced data.

TrendtoRaw2: The TrendtoRaw2 sampling mode is a modified version of the TrendtoRaw sampling mode.

The TrendtoRaw2 sampling mode almost always produces the same results as the Trend2 sampling mode. The exception is that, when more samples are requested than there are raw data points, the TrendtoRaw2 sampling mode returns all of the available raw data points with no further processing.

Calculated: Returns samples based on a selected Calculation mode.

RawByFilterToggle: RawByFilterToggle returns filtered time ranges. The values returned are 0 and 1. If the value is 1, then the condition is true and 0 means false.

This sampling mode is used with the time range and filter tag conditions. The result starts with a starting time stamp and ends with an ending timestamp

Calculation Modes

Calculation modes are used when the sampling mode is set to Calculated. The data type of all calculated values will be DoubleFloat except for MinimumTime, MaximumTime, FirstRawTime and LastRawTime which will be a Date. The data type of the values of FirstRawValue and LastRawValue will be the same as that of the selected tag.

Calculation Mode	Results
Count	<p>Displays the number of raw samples in the specified interval. This only indicates the count and does not display the actual values or qualities of the samples.</p> <p>The Count calculation mode is useful for analyzing the distribution of raw data samples. If you have a higher number of raw samples than expected, you may decide to implement collector or archive compression. If samples are missing, then you may want to slow your collection rates.</p>
State Count	Displays the number of times a tag has transitioned to another state from a previous state. A state transition is counted when the previous good sample is not equal to the state value and the next good sample is equal to state value.
State Time	Displays the duration that a tag was in a given state within an interval.
Minimum	<p>Displays the minimum value in a specified interval with good data quality. This value may be raw or interpolated.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: The Minimum and MinimumTime calculation retrieve two additional samples per interval; one is interpolated at the interval start time and the other is interpolated at the interval end time. These samples are used to determine the min or max just like any raw value.</p> </div>
MinimumTime	<p>Displays the time stamp of the minimum value in a specified interval.</p> <p>See the note in Minimum for additional information.</p>
Maximum	Displays the maximum value in a specified interval.

Calculation Mode	Results
	<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: The Maximum and MaximumTime calculation internally retrieve two additional samples per interval; one is interpolated at the interval start time and the other is interpolated at the interval end time. These samples are used in the min or max just like any raw or interpolated value. </div>
MaximumTime	Displays the time stamp of the maximum value in a specified interval. See the note in Maximum for additional information.
RawAverage	Displays the arithmetic average of the raw values in a specified interval with good data quality. This is useful only when a sufficient number of raw data values are collected.
Average	Similar to RawAverage, but performs a special logic for time weighting and for computing the value at the start of the interval. This is useful for computing an average on compressed data.
OPCQOr and OPCQAnd	The OPCQOr is a bit wise OR operation of all the 16 bit OPC qualities of the raw samples stored in the specified interval. The OPCQAnd is a bit wise AND operation of all the 16 bit OPC qualities of the raw samples stored in the specified interval.
Total	Retrieves the time-weighted total of raw and interpolated values for each calculation interval. The collected value must be a rate per 24 hours. This calculation mode determines a count from the collected rate.
Delta Queries	Historian offers the following delta queries to determine the delta over a time interval: <ul style="list-style-type: none"> • DELTAPOS (on page 1116) • DELTANEG (on page 1132) • DELTA (on page 1141)
RawTotal	Displays the arithmetic sum of raw values in a specified interval.
StandardDeviation	Displays the time-weighted standard deviation of raw values for a specified interval.

Calculation Mode	Results
RawStandardDeviation	Displays the arithmetic standard deviation of raw values for a specified interval.
TimeGood	Displays the amount of time (in milliseconds) during an interval when the data is of good quality and matches filter conditions if the filter tag is used.
FirstRawValue	Returns the first good raw value for a specified time interval.
FirstRawTime	Returns the timestamp of the first good raw for a specified time interval.
LastRawValue	Returns the last good raw value for a specified time interval.
LastRawTime	Returns the timestamp of the last good raw for a specified time interval.
TagStats	Allows you to return multiple calculation modes for a tag in a single query.

**Note:**

You can also use INCLUDEBAD or FILTERINCLUDEBAD as query modifiers to include bad quality data. For more information, refer INCLUDEBAD and FILTERINCLUDEBAD sections in Advanced Topics.

Query Modifiers

Query Modifiers are used for retrieving data that has been stored in the archive. They are used along with sampling and calculation modes to get a specific set of data.

- The time interval is great than 1 minute.
- The collection interval is greater than 1 second.
- The data node size is greater than the default 1400 bytes.
- The data type of the tags is String or Blob.

Query performance varies depending on all of the above factors.

Use this query modifier only with FirstRawValue, FirstRawTime, LastRawValue, and LastRawTime calculation modes.

EXCLUDESTALE:

- Stale tags are tags that have no new data samples within a specified period of time, and which have the potential to add to system overhead and slow down user queries.
- The EXCLUDESTALE query modifier allows for exclusion of stale tags in data queries.

- Unless permanently deleted, stale tags from the archiver are not removed but are simply marked as stale. Use the query without this query modifier to retrieve the sample values.
- Data is not returned for stale tags. An `ihSTATUS_STALED_TAG` error is returned instead.

Filtered Data Queries

Filtered data queries enhance Historian by adding filter tags and additional filtering criteria to standard queries. Unfiltered data queries in Historian allow you to specify a start and end time for the query, then return all data samples within that interval. A filtered data query, however, will allow you to specify a condition to filter the results by, as well as calculation modes to perform on the returned data. Filtered data queries are performed on the Historian server.

For example, a filtered data query is useful when trying to retrieve all data for a specific Batch ID, Lot Number, or Product Code and for filtering data where certain limits were exceeded, such as all data where a temperature exceeded a certain value. Rather than filtering a full day's worth of process data in the client application, you can filter data in the Historian archiver, and only return the matching results to the client application. The result is a smaller, more relevant data set.

You can use filter criteria with raw, interpolated, and calculated sampling modes. You cannot use it with current value sampling. The logic of selecting intervals is always interpolated, even when the data retrieval is raw or calculated. The value that triggers a transition from false to true can be a raw value or interpolated value.

You cannot use a filtered data query in an iFIX chart. For more information, refer to Advanced Topics section in the online help.

Filter Parameters for Data Queries

Use of filter parameters with a data query is optional.

- AND Condition
- OR Condition
- Combination of both AND and OR

Filter Expression can be used instead of `FilterTag`, `FilterComparisonMode` and `FilterValue` parameters. While using `FilterExpression`, the expression is passed within single quotes and for complex expressions we write the conditions within a parenthesis. There is no maximum length for a filter expression, but if it is called using OLE DB or Excel, they may have their own limitations.

Filter Mode: The type of time filter.

The Filter Mode defines how time periods before and after transitions in the filter condition should be handled.

For example, `AfterTime` indicates that the filter condition should be True starting at the timestamp of the archive value that triggered the True condition and leading up to the timestamp of the archive value that triggered the False condition.

ExactTime

Retrieves data for the exact times that the filter condition is True (only True).

BeforeTime

Retrieves data from the time of the last False filter condition up until the time of the True condition (False until True).

AfterTime

Retrieves data from the time of the True filter condition up until the time of next False condition (True until False).

BeforeAndAfterTime

Retrieves data from the time of the last False filter condition up until the time of next False condition (While True).

Filter Comparison Mode: Filter Comparison Mode is only used if Filter Tag is filled in. The Filter Comparison Mode defines how archive values for the Filter Tag should be compared to the Filter Value to establish the state of the filter condition. If a Filter Tag and Filter Comparison Value are supplied, time periods are filtered from the results where the filter condition is False.

The type of comparison to be made on the filter comparison value:

Equal

Filter condition is True when the Filter Tag is equal to the comparison value.

EqualFirst

Filter condition is True when the Filter Tag is equal to the first comparison value.

EqualLast

Filter condition is True when the Filter Tag is equal to the last comparison value.

NotEqual

Filter condition is True when the Filter Tag is NOT equal to the comparison value.

LessThan

Filter condition is True when the Filter Tag is less than the comparison value.

GreaterThan

Filter condition is True when the Filter Tag is greater than the comparison value.

LessThanEqual

Filter condition is True when the Filter Tag is less than or equal to the comparison value.

GreaterThanEqual

Filter condition is True when the Filter Tag is greater than or equal to the comparison value.

AllBitsSet

Filter condition is True when the binary value of the Filter Tag is equal to all the bits in the condition. It is represented as \wedge to be used in Filter Expression.

AnyBitSet

Filter condition is True when the binary value of the Filter Tag is equal to any of the bits in the condition. It is represented as \sim to be used in Filter Expression.

AnyBitNotSet

Filter condition is True when the binary value of the Filter Tag is not equal to any one of the bits in the condition. It is represented as $!\sim$ to be used in Filter Expression.

AllBitsNotSet

Filter condition is True when the binary value of the Filter Tag is not equal to all the bits in the condition. It is represented as $!\wedge$ to be used in Filter Expression.

Alarm Condition

Specifies an alarm condition to filter data by. For example, Level.

Alarm SubCondition

Specifies an alarm sub-condition to filter data by. For example, HHHI.

Filter Comparison Value: Filter Comparison Value is only used if Filter Tag is filled in. The value to compare the filter tag with when applying the appropriate filter to the data record set query (to determine the appropriate filter times).

Filtered Queries in the Excel Add-in Example

This example shows how a filtered data query returns specific data from the Historian archive. The example uses two tags: `batchid` and `ramp`. The `batchid` tag is updated before a new batch is produced with the new batch's ID. The `ramp` tag contains raw data sent by a device in the process. In this example, it

is requested that Historian return data samples at ten second intervals for the `ramp` tag during the period that the `batchid` tag is set to B1.

A standard query in Historian for the ramp tag's values between 08:00 and 08:01, at ten second intervals, would look like this:

Time Stamp	Value	Data Quality
07/30/2003 08:00:00	B0	Good
07/30/2003 08:00:20	B1	Good
07/30/2003 08:00:45	B2	Good

Filtering Data Queries in the Excel Add-in

You can enter your filter conditions using Filter tag, Filter Comparison Mode, and Filter Comparison Value or you can put that all that information in a single FilterExpression. You can enter the filter conditions in the FilterExpression field of the **Historian Data Query** window. The filter conditions are passed within single quotes.

To find the values of the `ramp` tag for the B1 batch, enter the following values into the **Historian Filtered Data Query** window:

1. In the `Tag Name(s)` field, enter the tag you want to receive results from - the `ramp` tag in this example.
2. Select a start and end time for your query.
3. In the `Filter Tag` field, enter the tag you want to enable filtering with - `batchid` in this example.
4. In the `Filter Comparison` field, select your comparison condition.
5. In the `Include Data Where Value Is` field, enter your filter condition value.
6. In the `Include Times` field, select your filter mode.
7. In the `Sampling Type` field, select your sampling mode.
8. In the `Calculation` field, select your calculation mode.
9. Select your `Sampling Interval`.
10. In the `Output Display` field, select the tag values you want to display.

Hybrid Modes

Hybrid mode is an advanced method of sampling collected data for trending. This mode of sampling has the ability to switch between sampled (like interpolated or trend) and raw data based on the actual and

requested number of samples or a specified time interval. The purpose of these modes is to return the minimum number of points to speed and simplify trending .

Hybrid mode is available for Interpolated, Lab, Trend, and Trend2 modes of sampling.

In these hybrid modes, the behavior is as follows

- If the actual number of stored samples is fewer than requested you will receive the raw data samples.
- If the actual number of stored samples is fewer than requested you will receive the raw data samples.

Data for Examples

All queries in this section use this set of data. The data here can be entered into Historian as a CSV file using the File collector. The queries can all be run in Historian Interactive SQL.

```
[Tags]
Tagname,DataType
TagA,DoubleInteger

[Data]
Tagname,Timestamp,Value,Quality
TagA,01/06/2014 12:00:01 PM,40000000,Good
TagA,01/06/2014 12:00:02 PM,30696808,Good
TagA,01/06/2014 12:00:03 PM,1952308224,Good
TagA,01/06/2014 12:00:04 PM,672641664,Good
TagA,01/06/2014 12:00:05 PM,636126336,Good
TagA,01/06/2014 12:00:06 PM,1826624640,Good
TagA,01/06/2014 12:00:07 PM,838753408,Good
TagA,01/06/2014 12:00:08 PM,520660896,Good
TagA,01/06/2014 12:00:09 PM,1293350272,Good
TagA,01/06/2014 12:00:10 PM,1959451264,Good
TagA,01/06/2014 12:00:11 PM,89220576,Good
TagA,01/06/2014 12:00:12 PM,1951745280,Good
TagA,01/06/2014 12:00:13 PM,888276160,Good
TagA,01/06/2014 12:00:14 PM,1031795200,Good
TagA,01/06/2014 12:00:15 PM,1449288960,Good
TagA,01/06/2014 12:00:16 PM,1516603392,Good
TagA,01/06/2014 12:00:17 PM,1843676544,Good
TagA,01/06/2014 12:00:18 PM,1672796672,Good
```

TagA,01/06/2014 12:00:19 PM,1533833984,Good
TagA,01/06/2014 12:00:20 PM,1697586560,Good
TagA,01/06/2014 12:00:21 PM,1647121280,Good
TagA,01/06/2014 12:00:22 PM,543921472,Good
TagA,01/06/2014 12:00:23 PM,1141920768,Good
TagA,01/06/2014 12:00:24 PM,540008448,Good
TagA,01/06/2014 12:00:25 PM,731087232,Good
TagA,01/06/2014 12:00:26 PM,631079296,Good
TagA,01/06/2014 12:00:27 PM,1160291968,Good
TagA,01/06/2014 12:00:28 PM,1324413696,Good
TagA,01/06/2014 12:00:29 PM,1875167744,Good
TagA,01/06/2014 12:00:30 PM,390197280,Good
TagA,01/06/2014 12:00:31 PM,192162736,Good
TagA,01/06/2014 12:00:32 PM,646106624,Good
TagA,01/06/2014 12:00:33 PM,210439200,Good
TagA,01/06/2014 12:00:34 PM,675144064,Good
TagA,01/06/2014 12:00:35 PM,1421636224,Good
TagA,01/06/2014 12:00:36 PM,537191872,Good
TagA,01/06/2014 12:00:37 PM,492214752,Good
TagA,01/06/2014 12:00:38 PM,1376227840,Good
TagA,01/06/2014 12:00:39 PM,1085046656,Good
TagA,01/06/2014 12:00:40 PM,924105984,Good
TagA,01/06/2014 12:00:41 PM,1294991488,Good
TagA,01/06/2014 12:00:42 PM,1737416960,Good
TagA,01/06/2014 12:00:43 PM,582910848,Good
TagA,01/06/2014 12:00:44 PM,1745973760,Good
TagA,01/06/2014 12:00:45 PM,1607484928,Good
TagA,01/06/2014 12:00:46 PM,2005492352,Good
TagA,01/06/2014 12:00:47 PM,746677184,Good
TagA,01/06/2014 12:00:48 PM,2143539456,Good
TagA,01/06/2014 12:00:49 PM,2009761664,Good
TagA,01/06/2014 12:00:50 PM,640139968,Good
TagA,01/06/2014 12:00:51 PM,990464704,Good
TagA,01/06/2014 12:00:52 PM,109999792,Good
TagA,01/06/2014 12:00:53 PM,1269805568,Good
TagA,01/06/2014 12:00:54 PM,1111627520,Good
TagA,01/06/2014 12:00:55 PM,60175184,Good

Historian | 6 - Historian Advanced Topics | 1082

TagA,01/06/2014 12:00:56 PM,1407366400,Good
TagA,01/06/2014 12:00:57 PM,928761280,Good
TagA,01/06/2014 12:00:58 PM,1666397696,Good
TagA,01/06/2014 12:00:59 PM,438304832,Good
TagA,01/06/2014 12:01:00 PM,1179844864,Good
TagA,01/07/2014 06:00:01 PM,9000,Good
TagA,01/07/2014 06:00:02 PM,5,Good
TagA,01/07/2014 06:00:03 PM,8,Good
TagA,01/07/2014 06:00:04 PM,-1,Good
TagA,01/07/2014 06:00:05 PM,4,Good
TagA,01/07/2014 06:00:06 PM,485,Good
TagA,01/07/2014 06:00:07 PM,-30000,Good
TagA,01/07/2014 06:00:08 PM,2,Good
TagA,01/07/2014 06:00:09 PM,4,Good
TagA,01/07/2014 06:00:10 PM,-60000,Good
TagA,01/07/2014 06:00:11 PM,60000,Good
TagA,01/07/2014 06:00:12 PM,1,Good
TagA,01/07/2014 06:00:13 PM,1,Good
TagA,01/07/2014 06:00:14 PM,30,Good
TagA,01/07/2014 06:00:15 PM,-70000,Good
TagA,01/07/2014 06:00:16 PM,-70000,Good
TagA,01/07/2014 06:00:17 PM,5,Good
TagA,01/07/2014 06:00:18 PM,1,Good
TagA,01/07/2014 06:00:19 PM,8,Good
TagA,01/07/2014 06:00:20 PM,220,Good
TagA,01/07/2014 06:00:21 PM,45,Good
TagA,01/07/2014 06:00:22 PM,44,Good
TagA,01/07/2014 06:00:23 PM,12,Good
TagA,01/07/2014 06:00:24 PM,13,Good
TagA,01/07/2014 06:00:25 PM,-5600,Good
TagA,01/07/2014 06:00:26 PM,15,Good
TagA,01/07/2014 06:00:27 PM,0,Good
TagA,01/07/2014 06:00:28 PM,25000,Good
TagA,01/08/2014 09:00:01 AM,1400,Good
TagA,01/08/2014 09:00:02 AM,0,Good
TagA,01/08/2014 09:00:03 AM,16,Good
TagA,01/08/2014 09:00:04 AM,-1400,Good

```
TagA,01/08/2014 09:00:05 AM,-12,Good
TagA,01/08/2014 09:00:06 AM,125,Good
TagA,01/08/2014 09:00:07 AM,150,Good
TagA,01/08/2014 09:00:08 AM,13,Good
TagA,01/08/2014 09:00:09 AM,-56,Good
TagA,01/08/2014 09:00:10 AM,12,Good
TagA,01/08/2014 09:00:11 AM,45,Good
```

The following examples provide various cases of the InterpolatedtoRaw hybrid mode illustrating the switching of data between raw and calculated data.

The following data is used in the example below. You can import this data into Historian if you want to try the example yourself:

```
Tag1 5/16/2011 15:52:24 1,000.0000000 100.0000000
Tag1 5/16/2011 15:52:25 1,001.0000000 100.0000000
Tag1 5/16/2011 15:52:26 1,002.0000000 100.0000000
Tag1 5/16/2011 15:52:27 1,003.0000000 100.0000000
Tag1 5/16/2011 15:52:28 1,004.0000000 100.0000000
Tag1 5/16/2011 15:52:29 1,005.0000000 100.0000000
Tag1 5/16/2011 15:52:30 1,006.0000000 100.0000000
```

Case 1

Use the following query to retrieve data for Tag 1 where it requests for 5 samples using InterpolatedtoRaw mode.

```
SET starttime= '5/16/2011 15:52:05 PM', endtime= '5/16/2011 15:52:47 PM', numberofsamples = 5, samplingmode=
Interpolatedtoraw SELECT * FROM ihrawdata where tagname = "TAG1"
```

The query will return interpolated data as shown below because the actual number of raw samples (7) is greater than the requested number of samples (5):

tagname	timestamp	value	quality	samplingmode	numberof-samples
Tag1	5/16/2011 15:52:13	0.0000000	0.0000000	InterpolatedtoRaw	5
Tag1	5/16/2011 15:52:21	0.0000000	0.0000000	InterpolatedtoRaw	5

tagname	timestamp	value	quality	samplingmode	numberof-samples
Tag1	5/16/2011 15:52:30	1,006.0000000	100.0000000	InterpolatedtoRaw	5
Tag1	5/16/2011 15:52:38	1,006.0000000	100.0000000	InterpolatedtoRaw	5
Tag1	5/16/2011 15:52:47	1,006.0000000	100.0000000	InterpolatedtoRaw	5

Case 2

Use the following query to retrieve data for Tag 1 where it requests for 50 samples using InterpolatedtoRaw mode.

```
starttime= '5/16/2011 3:52:05 PM', endtime= '5/16/2011 3:52:47 PM', numberofsamples = 50, sampling- mode=
Interpolatedtoraw SELECT & FROM ihrawdata where tagname = "TAG1"
```

The query will return raw data as shown below because the actual sample count(7) is less than the requested sample count (50):

tagname	timestamp	value	quality	samplingmode	numberof-samples
Tag1	5/16/2011 15:52:24	1,000.0000000	100.0000000	InterpolatedtoRaw	50
Tag1	5/16/2011 15:52:25	1,001.0000000	100.0000000	InterpolatedtoRaw	50
Tag1	5/16/2011 15:52:26	1,002.0000000	100.0000000	InterpolatedtoRaw	50
Tag1	5/16/2011 15:52:27	1,003.0000000	100.0000000	InterpolatedtoRaw	50
Tag1	5/16/2011 15:52:28	1,004.0000000	100.0000000	InterpolatedtoRaw	50
Tag1	5/16/2011 15:52:29	1,005.0000000	100.0000000	InterpolatedtoRaw	50

tagname	timestamp	value	quality	samplingmode	numberof-samples
Tag1	5/16/2011 15:52:30	1,006.0000000	100.0000000	InterpolatedtoRaw	50

Case 3

Use the following query to retrieve data for Tag 1 where it requests for samples in a time interval (milliseconds), using InterpolatedtoRaw mode.

```
SET starttime= '5/16/2011 3:52:05 PM', endtime= '5/16/2011 3:52:25 PM', intervalmilliseconds=10s , samplingmode=
Interpolatedtoraw

Tag1 5/16/2011 15:52:24 1,000.0000000 100.0000000
Tag1 5/16/2011 15:52:25 1,001.0000000 100.0000000
```

The query will return interpolated data as shown below because the actual number of raw samples (7) is greater than the requested number of samples (5):

Tagname	Timestamp	Value	Quality	Sampling MOde
Tag1	5/16/2011 15:52:24	1,000.0000000	1,000.0000000	InterpolatedtoRaw
Tag1	5/16/2011 15:52:25	1,001.0000000	1,000.0000000	InterpolatedtoRaw

Calculation Modes

This information is intended to supplement the information in the Historian product documentation and the SDK Help File.

Sampling and calculation modes are used on retrieval of data that has already been collected to the archive. Calculation modes are used when the sampling mode is set to "Calculated". It is helpful to separate the many modes into 3 main categories from simplest to most complex. A detailed explanation of the calculation modes with examples are discussed in following topics:

Raw Calculation Modes: Easiest to understand. Only raw points are used to determine calculated value.

- Count
- RawTotal
- RawAverage

- RawStandardDeviation
- FirstRawValue
- FirstRawTime
- LastRawValue
- LastRawTime

Interpolated Calculation Modes – both raw and interpolated points are used to determine a value.

- Minimum
- MinimumTime
- Maximum
- MaximumTime
- TimeGood

Delta Query Calculation Modes - Determine the delta over a time interval.

- DELTAPOS ([on page 1116](#))
- DELTANEG ([on page 1132](#))
- DELTA ([on page 1141](#))

Time Weighted Calculation Modes – Most complicated. Time weighting on raw and interpolated points is used to determine a value.

- Average
- Total
- StandardDeviation

Other Calculation Modes

- STATECOUNT
- STATETIME
- OPCQOR and OPCQAND
- TagStats

Each sample retrieved from Historian has a timestamp, value, and quality.

- **Timestamp** - the same logic as for interpolated values. It is covered in detail in the Understanding Sampling Modes document and not covered at all in this document.
- **Value** – depends entirely on the calculation mode being used
- **Quality** - Depending on the calculation mode, this either means:

- The percent of raw samples vs. total raw samples in the interval that were of good data quality.
- The percent of time in the interval that the data was of good data quality

Filtered data queries are described in the **Filtered data Queries** section.



Note:

This document intentionally contains all necessary data for executing the examples and reproducing the results. The tags and data are in the form of a CSV to be imported with the Historian File collector. You will not be able to import the data unless you adjust the active hours setting and possibly the Create Offline Archives setting of the archiver. This is true any time you are importing old data with the File collector.

Raw Calculation Modes

The calculation modes use only collected raw samples to determine the value for each interval.

Count Mode:

- **Value:** The count of raw samples with good quality in the interval. The values of the each sample are ignored. The Count does not include any samples with bad quality, including the start and end of collection markers.
- **Quality:** Percent good is always 100, even if the interval does not contain any raw samples or contains only bad quality samples.
- **Anticipated Usage:** Count is useful for analyzing the distribution of the raw data samples to determine the effect of compression deadbands. It is also useful to determine which tags are consuming the most archive space.

RawTotal Mode: Retrieves the arithmetic total (sum) of sampled values for each interval.

- **Value:** The sum of the good quality values of all raw samples in the interval. All bad quality samples are ignored.
- **Quality:** Percent good is always 100, even if the interval does not contain any raw samples or it contains only bad quality samples.
- **Anticipated Usage:** RawTotal mode is useful for calculating an accurate total when a sufficient number of raw samples are collected. Note that unlike ihTotal, this is a simple sum with no assumption that the values are rate values.

RawAverage Mode: The arithmetic average (mean) of all good quality raw samples in the interval.

- **Value:** The sum of all good quality samples in the interval, divided by the number of good quality samples in the interval. All bad quality samples are ignored. That is, RawAverage is equivalent to the RawTotal divided by Count.
- **Quality:** If there are no raw samples in the interval or they all have bad quality, then the percent good is 0. Otherwise, percent good is always 100, even if the interval contains bad quality samples.

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated
and calculationmode=rawaverage and timestamp >= '29-Mar-2002 13:30' and
timestamp <= '29-Mar-2002 14:30' and tagname = counttag and intervalmilliseconds = 10M
```

- **Anticipated Usage:** The RawAverage mode is useful for calculating an accurate average when a sufficient number of raw samples are collected.

RawAverage Mode:

- **Value:**
- **Quality:**
- **Anticipated Usage:**

RawStandardDeviation Mode: Retrieves the arithmetic standard deviation of raw values for each calculation interval.

- **Value:** Any raw point of bad data quality is ignored.
- **Quality:** If there are no raw samples in the interval or they all have bad quality, then the percent good is 0. Otherwise, percent good is always 100, even if the interval contains bad quality samples.
- **Anticipated Usage:** The RawStandardDeviation mode is useful for calculating an accurate standard deviation when a sufficient number of raw samples are collected.

FirstRawValue/FirstRawTime Modes: Retrieve the first good raw sample value and timestamp for a given time interval, respectively.

- **Value:** The value of the raw sample or zero if there are no good raw samples in the interval. The timestamp of the sample or the year 1969 if there are no good raw samples in the interval.
- **Quality:** The quality is the same for FirstRawValue and First RawTime. If there are no good raw samples in the interval, then the percent good is 0. Otherwise, the percent good is always 100, even if the interval contains bad quality samples.

The Raw sample has a quality of Good, Bad or Uncertain, and that is converted to a 0 or 100 percent.

- **Anticipated Usage:**

LastRawValue/LastRawTime Modes: Retrieve the last good raw sample value and timestamp for a given time interval, respectively.

- **Value:** The value of the raw sample or zero if there are no good raw samples in the interval. The timestamp of the sample or the year 1969 if there are no good raw samples in the interval.

- **Quality:**

The quality is the same for LastRawValue and LastRawTime. If there are no good raw samples in the interval, then the percent good is 0. Otherwise, percent good is always 100, even if the interval contains bad quality samples.

The Raw sample has a quality of Good, Bad or Uncertain, and that is converted to a 0 or 100 percent.

- **Anticipated Usage:**

Calculating the count of raw samples

The following example demonstrates that only good samples are counted. Importing the following data ensures that at least one interval has 0 samples.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
COUNTTAG,SingleInteger,100,0

[Data]
Tagname,TimeStamp,Value,DataQuality
COUNTTAG,29-Mar-2002 13:59:00.000,22,Good
COUNTTAG,29-Mar-2002 14:08:00.000,12,Bad
COUNTTAG,29-Mar-2002 14:22:00.000,4,Good
```

The following query retrieves data with a start time of 14:00 and an end time of 14:30 with a 10-minute interval.

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated and calculationmode=count and timestamp
>='29-Mar-2002 14:00' and timestamp <= '29-Mar-2002 14:30' and tagname = counttag and intervalmilliseconds = 10M
```

Time Stamp	Value	Quality
29-Mar-200214:10:00.000	0.00	100.00
29-Mar-200214:20:00.000	0.00	100.00
29-Mar-200214:30:00.000	1.00	100.00



Note:

The bad raw sample at 14:08 is not counted, but the good sample at 14:22 is counted. The 14:11 to 14:20 interval has no raw samples, but still has a percent good of 100 percent.

Calculating the Raw Total

The following example demonstrates that only good quality samples are included in the sum. Perform the following query on the same data set as that in the Count example above:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated and calculationmode=rawtotal and
timestamp >= '29-Mar-2002 13:30' and timestamp <= '29-Mar-2002 14:30' and tagname = counttag and intervalmilliseconds
= 10M
```

Time Stamp	Value	Quality
29-Mar-200213:40:00.000	0.00	100.00
29-Mar-200213:50:00.000	0.00	100.00
29-Mar-200214:00:00.000	22.00	100.00
29-Mar-200214:10:00.000	0.00	100.00
29-Mar-200214:20:00.000	0.00	100.00
29-Mar-200214:30:00.000	4.00	100.00

If the same start and end time are used, but the time span is treated as a single interval, then all values are added together:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated and calculationmode=rawtotal and
timestamp >= '29-Mar-2002 13:30' and timestamp <= '29-Mar-2002 14:30' and tagname = counttag
and numberofsamples=1
```

Time Stamp	Value	Quality
29-Mar-200214:30:00.000	26.00	100.00

Even though the time span covers all raw samples, only the two good quality samples are used in the calculation: $26 = 22 + 4$

Calculating RawAverage

The following example demonstrates that only good quality samples are included in RawAverage. Perform the following query on the same data set as that in the Count example above. This query retrieves data using RawAverage, with a start time of 13:30 and an end time of 14:30 at 10-minute intervals.

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated and calculationmode=rawaverage and
timestamp >= '29-Mar-2002 13:30' and timestamp <= '29-Mar-2002 14:30' and tagname = counttag and intervalmilliseconds
= 10M
```

Time Stamp	Value	Quality
29-Mar-200213:40:00.000	0.00	0.00
29-Mar-200213:50:00.000	0.00	0.00
29-Mar-200214:00:00.000	22.00	100.00
29-Mar-200214:10:00.000	0.00	0.00
29-Mar-200214:30:00.000	4.00	100.00

The interval from 14:11 to 14:20 has no raw samples. The percent good quality of 0.

The interval from 14:01 to 14:10 has 0 good and 1 bad samples. It also has a percent good quality of 0.

The interval from 14:21 to 14:30 has 1 good and 0 bad samples. It has a percent good quality of 100.

If the same start and end time are used, but the time span is treated as a single interval, then all values are averaged together:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated and calculationmode=rawaverage
and timestamp >= '29-Mar-2002 13:30' and timestamp <= '29-Mar-2002 14:30' and tagname = counttag and
numberofsamples=1
```

Time Stamp	Value	Quality
29-Mar-200214:30:00.000	13.00	100.00

Even though the time span covers all raw samples, but only the two good samples are used in the calculation: $13 = (22+4)/2$ Since the interval includes at least one good quality sample, percent good for the interval is 100, even though 33% of the samples are of bad quality.

Calculating the Raw Standard Deviation

The following example demonstrates that only good samples are included in the standard deviation. Perform the following query on the same data set as that in the Count example above:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated and calculationmode=rawstandarddeviation
and
timestamp >= '29-Mar-2002 13:30' and timestamp <= '29-Mar-2002 14:30' and tagname = counttag and numberofsamples=1
```

Time Stamp	Value	Quality
29-Mar-200214:30:00.000	12.73	100.00

Retrieving the FirstRawValue/FirstRawTime Values

Import this data to Historian:

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
Tag1,SingleFloat,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
Tag1,07-05-2011 17:24:00,29.72,Bad
Tag1,07-05-2011 17:25:00,29.6,Good
Tag1,07-05-2011 17:26:00,29.55,Good
Tag1,07-05-2011 17:27:00,29.49,Bad
Tag1,07-05-2011 17:28:00,29.53,Bad
Tag1,07-05-2011 17:29:00,29.58,Good
Tag1,07-05-2011 17:30:00,29.61,Bad
Tag1,07-05-2011 17:31:00,29.63,Bad
Tag1,07-05-2011 18:19:00,30,Good
Tag1,07-05-2011 18:20:00,29.96,Good
Tag1,07-05-2011 18:21:00,29.89,Good
```

```
Tag1,07-05-2011 18:22:00,29.84,Good
Tag1,07-05-2011 18:23:00,29.81,Bad
```

Using FirstRawValue Calculation Mode

```
set starttime='07-05-2011 16:00:00', endtime='07-05-2011 19:00:00'

select timestamp,value,quality from ihrawdata where tagname like 'Tag1' and samplingMode=Calculated and
CalculationMode=FirstRawValue and intervalmilliseconds=1h
```

The output is as follows:

Time Stamp	Value	Quality
07-05-201117:00:00	0.0000000	0.0000000
07-05-201118:00:00	29.6000000	100.0000000
07-05-201119:00:00	30.0	100.0000000

For the time interval 16:00 to 17:00 there are no raw values so a value and quality of 0 is returned for both FirstRawValue and FirstRawTime. The first raw sample from 17:00 to 18:00 is 29.72 but it is a bad data quality so it is skipped and the 29.6 is returned and its timestamp of 17:25 is returned in FirstRawTime. FirstRawValue calculation mode considers only good quality data. In the last interval the first good raw sample is 30 and is returned and its timestamp is returned as FirstRawTime.

Retrieving the LastRawValue/LastRawTime Values

Import this data into Historian

```
[Tags]Tagname,DataType
DecimatedOneHour,DoubleInteger

[Data]
Tagname,TimeStamp,Value,DataQuality
Tag1,07-05-2011 17:29:00,29,Good
Tag1,07-05-2011 20:00:00,0,Good
Tag1,07-05-2011 20:12:00,12,Good
Tag1,07-05-2011 20:15:00,0,Bad
```

Using LastRawValue Calculation Mode

```
set starttime='07-05-2011 17:00:00',endtime=' 07-05-2011 21:00:00'

select timestamp,value,quality from ihrawdata where tagname like Tag1 and samplingmode=Calculated and
CalculationMode=LastRawValue and Intervalmilliseconds=1h
```

The output is as follows:

Time Stamp	Value	Quality
07-05-201118:00:00	29	100.0000000
07-05-201119:00:00	0	0.0000000
07-05-201120:00:00	0	100.0000000
07-05-201121:00:00	12	100.0000000

In the interval from 17:00 to 18:00 the last good value is 29. The 18:00 to 19:00 has no raw samples so the quality is bad. The 20:00 sample is returned as the last good value in the 19:00 to 20:00. In the final interval, the last raw sample is bad quality so it is ignored and the previous sample is returned.

Using LastRawTime Calculation Mode

```
set starttime='07-05-2011 17:00:00',endtime=' 07-05-2011 21:00:00'
select timestamp,value,quality from ihrawdata where tagname like Tag1 and samplingmode=Calculated and CalculationMode=
LastRawTime and Intervalmilliseconds=1h
```

The output is as follows:

Time Stamp	Value	Quality
07-05-201117:00:00	07-05-201117:29:00	100.0000000
07-05-201118:00:00	01-01-197005:30:00	0.0000000
07-05-201119:00:00	07-05-201120:00:00	100.0000000
07-05-201120:00:00	07-05-201120:12:00	100.0000000



Note:

You can also use the INCLUDEBAD query modifier to include bad quality data.

Interpolated Calculation Modes

Interpolation is used in many calculation modes. When using interpolated data, it is possible that there are no raw samples in the interval (such as with highly-compressed data) so the archiver requires additional samples to perform calculations.

The Minimum, MinimumTime, Maximum, and MaximumTime all use interpolation to arrive at two additional samples per interval. One is interpolated at the interval start time and one is interpolated at the interval end time. The interpolated samples are used in calculations just like raw, collected samples within the interval. In particular, the minimum or maximum calculated value can be a raw or interpolated value.

All described rules for interpolating a value at an interval's end time also apply to the interval's start time. There is no raw maximum or raw minimum sampling mode. To acquire these values, you must retrieve the raw samples using RawByTime or RawByNumber and compute the minimum or maximum yourself.

Similarly, you must also manually calculate a minimum or maximum when using values acquired through lab sampling.

Minimum/Maximum and MinimumTime/MaximumTime Modes: The minimum (or maximum) value in the interval and the time stamp of that value.

- **Value:**

Maximum returns the raw or interpolated value with the greatest value and good data quality in the interval. Minimum returns the raw or interpolated value with the lowest value and good data quality in the interval

MaximumTime returns the time stamp of the Maximum value. MinimumTime returns the time stamp of the Minimum value.

In all cases, all raw samples of bad quality is ignored, both during interpolation and when calculating the maximum.

- **Quality:** If the raw samples in the interval all have bad quality, or if the sample before the interval has bad quality, then percent good is 0. Otherwise, percent good is always 100, even if the interval does not contain any raw samples or contains both good and bad quality samples.

TimeGood Mode: The TimeGood mode calculates the amount of time for which the data was of good quality.

The TimeGood mode is most useful when combined with filtered data queries. You can use a filter condition to acquire samples for which a specific condition was true, then calculate for how long that data was of a good quality. For example, you could use a filter condition to determine the amount of time a pump was activated, then calculate for how much of that time the data was of a good quality.

To get the most use out of the TimeGood mode, you should understand how filtered data queries work.

- **Value:** The TimeGood mode retrieves the total number of milliseconds during the interval for which the data is good AND for which the filter condition is true. If there is no filter tag or condition, then TimeGood is the total number of milliseconds in the interval that the data is good.
- **Quality:** The TimeGood mode always has a percent good of 100, even if there are no raw samples or if all samples have bad quality. In the latter case, the Value will be 0, but the percent good is still 100.

Finding minimum and maximum of Downward Sloping Data

The following example demonstrates how a raw sample is interpolated at the interval's start and end time and how this interpolation is used with raw samples when calculating minimum and maximum values.

Import the following data:

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
DOWNSLOPE,SingleFloat,100,0

[Data]
Tagname,TimeStamp,Value,DataQuality
DOWNSLOPE,29-Mar-2002 13:59:00.000,22,Good
DOWNSLOPE,29-Mar-2002 14:08:00.000,12,Good
DOWNSLOPE,29-Mar-2002 14:22:00.000,4,Good
```

The following query retrieves the Maximum value:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated
and calculationmode=Maximum and timestamp >= '29-Mar-2002 13:50' and
timestamp <= '29-Mar-2002 14:30' and tagname = DOWNSLOPE and numberofsamples = 8
```

The following query retrieves the MaximumTime:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated
and calculationmode=MaximumTime and timestamp >= '29-Mar-2002 13:50' and
timestamp <= '29-Mar-2002 14:30' and tagname = DOWNSLOPE and numberofsamples = 8
```

The following query retrieves the Minimum:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated
and calculationmode=Minimum and timestamp >= '29-Mar-2002 13:50' and
timestamp <= '29-Mar-2002 14:30' and tagname = DOWNSLOPE and numberofsamples = 8
```

The following query retrieves the MaximumTime value:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated
and calculationmode=MinimumTime and timestamp >= '29-Mar-2002 13:50' and
timestamp <= '29-Mar-2002 14:30' and tagname = DOWNSLOPE and numberofsamples = 8
```

The following query retrieves the Minimum value:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated
and calculationmode=Min
```

The following query retrieves the MinimumTime value:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated
and calculationmode=MinimumTime and timestamp >= '29-Mar-2002 13:50' and
timestamp <= '29-Mar-2002 14:30' and tagname = DOWNSLOPE and numberofsamples = 8
```

Interval Time Stamp	Maximum	Maximum Time	Minimum	Minimum Time	Quality
13:55:00.000	0.00	31-Dec-1969 19:00:00.000	0.00	31-Dec-1969 19:00:00.000	0.00
14:00:00.000	22.00	13:59:00.000	20.89	14:00:00.000	100.00
14:05:00.000	20.89	14:00:00.000	15.33	14:05:00.000	100.00
14:10:00.000	15.33	14:05:00.000	10.86	14:10:00.000	100.00
14:15:00.000	10.86	14:10:00.000	8.00	14:15:00.000	100.00
14:20:00.000	8.00	14:15:00.000	5.14	14:20:00.000	100.00
14:25:00.000	5.14	14:20:00.000	4.00	14:25:00.000	100.00
14:30:00.000	4.00	14:30:00.000	4.00	14:30:00.000	100.00

The value is 4 for the entire interval of 14:26:00 to 14:30:00. However, the newest value is always returned for MinimumTime and MaximumTime for an interval, so the values instead are calculated as 14:30.

All modes have the same quality. A MaximumTime or MinimumTime of 1969 means there is no value in that interval.

Maximum always begins at the start of the interval because the data forms this is a downwards-sloping line. The Maximum takes the sample interpolated at the interval start time. The timestamp is still the interval end time.

When an interval has no raw samples, such as in the 14:05 interval, samples are interpolated at the beginning and the end of the interval. This means that the 14:05 interval has 2 samples to example at when calculating the Minimum or Maximum.

Finding Minimum and Maximum of Changing Data

The following example uses a value that continually changes, rather than one that simply slopes upwards or downwards. Any Minimum or Maximum within an interval is necessarily a raw sample. If the minimum or maximum occurred as raw samples in the middle of the interval, these are also detected.

Import the following data:

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
SAWTOOTH,SingleFloat,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
SAWTOOTH,29-Mar-2002 13:59:00.000,22.7,Good
SAWTOOTH,29-Mar-2002 14:01:00.000,12.5,Good
SAWTOOTH,29-Mar-2002 14:02:00.000,47.0,Good
SAWTOOTH,29-Mar-2002 14:03:00.000,2.4,Good
SAWTOOTH,29-Mar-2002 14:04:00.000,9.5,Good
SAWTOOTH,29-Mar-2002 14:08:00.000,12.5,Good
SAWTOOTH,29-Mar-2002 14:14:00.000,7.0,Good
SAWTOOTH,29-Mar-2002 14:22:00.000,4.8,Good
```

The following query retrieves the Maximum value:

```
select timestamp, value, quality from ihrawdata where
samplingmode=calculated and calculationmode=Maximum and timestamp >= '29-Mar-2002 13:50'
and timestamp <= '29-Mar-2002 14:30' and tagname = SAWTOOTH and numberofsamples = 8
```

The following query retrieves the MaximumTime value:

```
select timestamp, value, quality from ihrawdata where
samplingmode=calculated and calculationmode=MaximumTime and timestamp >= '29-Mar-2002 13:50'
and timestamp <= '29-Mar-2002 14:30' and tagname = SAWTOOTH and numberofsamples = 8
```

The following query retrieves the Minimum value:

```
select timestamp, value, quality from ihrawdata where
samplingmode=calculated and calculationmode=Minimum and timestamp >= '29-Mar-2002 13:50'
and timestamp <= '29-Mar-2002 14:30' and tagname = SAWTOOTH and numberofsamples = 8
```

The following query retrieves the MinimumTime value:

```
select timestamp, value, quality from ihrawdata where
samplingmode=calculated and calculationmode=MinimumTime and timestamp >= '29-Mar-2002 13:50'
and timestamp <= '29-Mar-2002 14:30' and tagname = SAWTOOTH and numberofsamples = 8
```

Interval Time Stamp	Maximum	Maximum Time	Minimum	Minimum Time	Quality
13:55:00.000	0.00	31-Dec-1969 19:00:00.000	0.00	31-Dec-1969 19:00:00.000	0.00
14:00:00.000	22.70	13:59:00.000	17.60	14:00:00.000	100.00
14:05:00.000	47.00	14:02:00.000	2.40	14:03:00.000	100.00
14:10:00.000	12.50	14:08:00.000	10.25	14:03:00.000	100.00
14:15:00.000	10.67	14:10:00.000	6.73	14:15:00.000	100.00
14:20:00.000	6.73	14:15:00.000	5.35	14:20:00.000	100.00
14:25:00.000	4.80	14:20:00.000	4.80	14:25:00.000	100.00
14:30:00.000	4.80	14:30:00.000	4.80	14:30:00.000	100.00

Querying with a single interval so that all samples are included results in the following:

Interval Time Stamp	Maximum	Maximum Time	Minimum	Minimum Time	Quality
14:30:00.000	47.00	14:02:00.000	2.40	14:03:00.000	100.00

Finding the Minimum and Maximum with Bad Quality Data and Repeated Values

Import the following data:

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
MINMAXBAD,SingleFloat,60,0
```

```
[Data]
Tagname,TimeStamp,Value,DataQuality
MINMAXBAD,29-Mar-2002 13:59:00.000,22.7,Good
MINMAXBAD,29-Mar-2002 14:01:00.000,12.5,Good
MINMAXBAD,29-Mar-2002 14:02:00.000,47.0,Bad
MINMAXBAD,29-Mar-2002 14:03:00.000,2.4,Bad
MINMAXBAD,29-Mar-2002 14:04:00.000,9.5,Good
MINMAXBAD,29-Mar-2002 14:08:00.000,12.5,Good
MINMAXBAD,29-Mar-2002 14:14:00.000,7.0,Good
MINMAXBAD,29-Mar-2002 14:22:00.000,4.8,Good
```

Querying with a single interval so that all samples are included results in the following:

Interval Time Stamp	Maximum	Maximum Time	Minimum	Minimum Time	Quality
14:30:00.000	22.70	13:59:00.00	4.80	14:30:00.000	100.00



Note:

MinimumTime is not 14:22 but 14:30. When multiple values within an interval have the same Minimum or Maximum value, (such as here, where two samples have a minimum of 4.8), the newest time stamp is always taken.

Finding the amount of time the collector was running

The following example uses multiple intervals without a filter condition. If the data is good for the entire interval, the returned Value would be the length of the interval in milliseconds.

Import the following data (identical to that used in the examples for Interpolated Data)

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
BADDQTAG,SingleFloat,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
BADDQTAG,29-Mar-2002 13:59:00.000,22.7,Good
BADDQTAG,29-Mar-2002 14:08:00.000,12.5,Bad
```

```
BADDQTAG,29-Mar-2002 14:14:00.000,7.0,Bad
BADDQTAG,29-Mar-2002 14:22:00.000,4.8,Good
```

The following SQL query retrieves data with a start time of 14:00 and an end time of 14:30 in 5-minute intervals:

```
select timestamp,value,intervalmilliseconds from ihRawData where
tagname = baddqtag and samplingmode=calculated and calculationmode=timegood
and timestamp > '29-mar-2002 13:55:00' and timestamp < '29-mar-2002 14:30:00'
and intervalmilliseconds=5m
```

Time Stamp	Value	Intervalmilliseconds
29-Mar-2002 14:00:00.000	60,000.00	300,000
29-Mar-2002 14:05:00.000	300,000.00	300,000
29-Mar-2002 14:10:00.000	180,000.00	300,000
29-Mar-2002 14:15:00.000	0.00	300,000
29-Mar-2002 14:20:00.000	0.00	300,000
29-Mar-2002 14:25:00.000	180,000.00	300,000

The percent quality for each returned interval is 100.00 and is not shown. By including the intervalmilliseconds column, you can compare the returned milliseconds to the total milliseconds for the interval.

- *When data is good for the whole interval:* From 14:01 to 14:05 the data is good, though no raw samples are contained. The value is equal to intervalmilliseconds (300,000).
- *When data starts bad while entering the interval and then turns good:* The data is bad going into the 14:21 to 14:25 interval, resulting in a value of 180,000 (out of 300,000).
- *When data is bad from the middle of the interval to the end the interval:* The data in the 14:06 to 14:10 interval starts with good quality and changes to bad quality. The value is therefore less than the calculated intervalmilliseconds (180,000 out of 300,000).
- *When there are no raw samples in an interval:* The number of raw samples has no effect on the Value; it only affects the percent quality

The interval from 14:01 to 14:05 contains no raw samples. The data quality throughout the entire interval is good. Therefore, for this interval, the Value is 300,000 (the length of the entire interval).

The interval from 14:16 to 14:20 contains no raw samples. The data quality throughout the entire interval is bad. At no time in this interval is there good data, so for this interval, the Value is 0.

The following example demonstrates the case of bad data throughout a section in the middle of an interval. The following query retrieves data from a larger interval that has a section of bad quality in the middle of 2 periods of good quality.

```
select timestamp,value,intervalmilliseconds from ihRawData where
tagname = baddqtag and samplingmode=calculated and calculationmode=timegood and
timestamp >= '29-mar-2002 14:05:00' and timestamp <= '29-mar-2002 14:25:00' and
intervalmilliseconds=20m
```

Time Stamp	Value	Intervalmilliseconds
29-Mar-2002 14:25:00.000	360,000.00	1,200,000

A value of 360,000 milliseconds corresponds to 3 minutes of good quality at the beginning of the interval and 3 minutes of good quality at the end of the interval.

Time Weighted Calculation Modes

The ihAverage and ihTotal and ihStandardDeviation modes use time-weighted calculations of interpolated and raw samples. The following example illustrates this concept using the ihAverage mode.

Import the following data:

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
TAG2,SingleFloat,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
TAG2,29-Mar-2002 14:00:00.000,30.0,Good
TAG2,29-Mar-2002 14:01:00.000,40.0,Good
TAG2,29-Mar-2002 14:01:10.000,50.0,Good
TAG2,29-Mar-2002 14:01:15.000,20.0,Bad
TAG2,29-Mar-2002 14:01:45.000,25.0,Good
```

Attributes for each data sample are Tagname, TimeStamp, Value, and DataQuality. The data can also be organized by duration:

Value	Duration
30	60 seconds
40	10 seconds
50	5 seconds
20	30 seconds
25	15 seconds

We want to analyze the data over the following interval. The time begins at the timestamp for the first sample and ends 15 seconds after the timestamp of the last sample.

```
3/29/2002 14:00:00 - start time
3/29/2002 14:02:00 - end time
```

Calculating a raw average over these two minutes produces the following:

```
(40 + 50 + 25) / 3 = 38.33
```

You can also calculate it with the following query:

```
select timestamp, value, quality from ihrawdata where
samplingmode=calculated and calculationmode=RawAverage and timestamp >= '29-Mar-2002 14:00'
and timestamp <= '29-Mar-2002 14:02' and tagname = tag2 and numberofsamples = 1
```

Time Stamp	Value	Quality
29-Mar-200214:02:00.000	38.33	100.00

The value of 30 is not used because the RawAverage mode uses only samples whose timestamps are greater than the interval's start time. A value whose timestamp is 14:00 would be associated with the previous interval.

In a time-weighted average, the values are multiplied by the durations. The two-minute time weighted average is:

```
((30 * 59.999) + (40 * 10) + (50 * 5) + (25*15)) / (60 + 10 + 5 + 15) = 31.38
```

You can calculate this with the following query:

```
select timestamp, value, quality from ihrawdata where
samplingmode=calculated and calculationmode=Average and timestamp >= '29-Mar-2002 14:00'
and timestamp <= '29-Mar-2002 14:02' and tagname = tag2 and numberofsamples = 1
```

This more closely describes the real situation, the value was 30 during most of the queried interval. The value of 30 is assigned to a timestamp of 14:00:00.001, which is the first possible timestamp greater than the interval start time (up to a resolution of milliseconds).



Note:

The bad quality sample (whose value was 20) is ignored when calculating the time-weighted average. The quality was bad for 30 seconds out of the 2 minutes, so the percent good quality is 75. When performing time-weighted calculations, percent good represents the percentage of time within the interval that had data with good quality: (90 seconds of good data quality / 120 seconds of the total interval duration) = 75%

Computing an Average Without A Raw Sample At Start Time

There is rarely a raw sample available at the interval start time. However, the archiver needs to know the value at the start of an interval before it can perform time-weighted calculations. The archiver uses interpolation to get values it needs for which no raw samples are available.

For example, if we set the start time for the query to 14:05, then the archiver will interpolate a value at the timestamp of 14:05.

The RawAverage would then be calculated as follows:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated and
calculationmode=RawAverage and timestamp >= '29-Mar-2002 14:00:05' and
timestamp <= '29-Mar-2002 14:02' and tagname = tag2 and numberofsamples = 1
```

Time Stamp	Value	Quality
29-Mar-200214:02:00.000	38.33	100.00

Similarly, the time-weighted average would be calculated as follows:

```
select timestamp, value, quality from ihrawdata where samplingmode=calculated
and calculationmode=Average and timestamp >= '29-Mar-2002 14:00:05' and
timestamp <= '29-Mar-2002 14:02' and tagname = tag2 and numberofsamples = 1
```

Time Stamp	Value	Quality
29-Mar-2002 14:02:00.000	32.01	73.91

Average and Step Values

The average of the raw samples is the interval, but there is special logic for time weighting and for computing the value at the start of the interval.

Averages are computed differently depending on the value of the Tag.StepValue property. If `StepValue=FALSE` then the average works as it always did in 2.0 and 3.0. A value at the start of the interval is determined via interpolation.

If `StepValue=TRUE` then lab sampling, not interpolation, is used to determine the value at interval start time. This would more accurately reflect a value that steps or a value that uses collector compression and did not change for a long period of time.

ihTotal Mode

The ihTotal mode retrieves the time weighted rate total for each calculation interval.

A rate total is considered for totalizing a continuous measurement. A factor is applied to the totalized value to convert into the appropriate engineering units. Since this is a rate total, a base rate of Units/Day is assumed. If the actual units of the continuous measurement is Units/Minute, multiply the results by 1440 Minutes / Day to convert the totalized number into the appropriate engineering units.

The formula for total is `total = average * (interval in milliseconds / 1000) / 86400`. The 86400 is number of seconds in a day. This formula takes the average, which is assumed to be already in units per day, and divides it into "units per interval".

Collecting a Rate from a Data Source

Assume an average of 240 barrels per day.

If your interval is one day, then the "units per interval" is units per DAY. Since the average was already assumed to be in units per day, you just get back the average.

$$240 = 240 * (86400000/1000) / 86400$$

$$240 = 240 * 1$$

If your interval is 1 hour, you should get back 1/24 of the average.

$$\text{total} = 240 * (3600000/1000) / 86400$$

total = 240 * 0.0417

total = 10

Ten is 1/24 of 240 and tells you 10 units were produced that hour.

Filtered Data Queries

You can retrieve data using an optional filter tag or filter expression if the client program or API you are using supports it.

Normally, a data query specifies a start and an end time for the query. Data is returned for `ALL` intervals between the start and end times. A filtered data query allows you to specify a filter tag or expression with additional criteria so that only some of those intervals which match the filter conditions are returned. The method of calculating the value attributed to the interval can be different from a non-filtered query, since the filter criteria can exclude raw samples inside an interval as well as exclude intervals themselves.

The value that triggers a transition from `FALSE` to `TRUE` can be a raw value or interpolated value. If a FilterTag or expression is supplied, the Data Archiver attempts to filter time periods from the results.

The filter data query parameters include:

- FilterTag or FilterExpression
- FilterMode
- FilterComparisonMode
- FilterComparisonValue

Each parameter is described in the following table with examples that demonstrate common usages.

Internally to the Data Archiver, the filter condition is evaluated to get zero or more time ranges. For example, if you query from 1pm to 2pm and the filter condition was never `TRUE` during that time, nothing is returned.

If the condition was `TRUE` from 1:40 to 1:45 then only the data for that time range is queried and returned.

Together the Filter Tag, Filter value, and Filter Comparison Mode define the criteria to apply to each interval to determine inclusion or exclusion. You can optionally use Filter Expression to include all the above parameters in one condition.

The Include Times defines how the time periods before and after transitions in the filter condition should be handled. An example with actual data and a graphic to clarify the behavior of each of the IncludeTime options is provided in the following topics.

You can retrieve data using a filtered data query or filter expressions.

Using a Filtered Data Query

The filter query logic has two problems to solve:

- *Which time ranges should be included?* In the following example, you see that No Filter mode returns all intervals. Each mode has its own logic to determine if an interval passes the filter or not.
- *What value and quality should be attributed to the interval?* If the filter condition is TRUE for the whole interval, then this is just like the non-filtered result. When the filter condition is TRUE only for part of the interval, raw samples get filtered out, changing the values returned.

For the following example, we know that we want to use AfterTime since the batch ID is written to the PLC at the start of the batch. The intervals included are the ones for the times the batch is running. You would use the BeforeTime if the batch ID was written at the end. Use the ExactTime if you are comparing 2 or more values at a single point in time.

```
* Example for Filtered Data Documentation
*
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
BATCHID,VariableString,10,0
RAMP,SingleInteger,60,0
ONOFF,SingleInteger,60,0
HAS SPACE,SingleInteger,60,0
[Data]
Tagname,TimeStamp,Value,DataQuality
BATCHID,30-Jul-2002 07:00:00.000,B1,Good
BATCHID,30-Jul-2002 07:00:20.000,B2,Good
BATCHID,30-Jul-2002 07:00:34.000,B3,Good
BATCHID,30-Jul-2002 07:00:52.000,B1,Good
RAMP,30-Jul-2002 07:00:00.000,0,Good
RAMP,30-Jul-2002 07:00:01.000,1,Good
RAMP,30-Jul-2002 07:00:02.000,2,Good
RAMP,30-Jul-2002 07:00:03.000,3,Good
RAMP,30-Jul-2002 07:00:04.000,4,Good
RAMP,30-Jul-2002 07:00:05.000,5,Good
RAMP,30-Jul-2002 07:00:06.000,6,Good
RAMP,30-Jul-2002 07:00:07.000,7,Good
```

RAMP, 30-Jul-2002 07:00:08.000, 8, Good
RAMP, 30-Jul-2002 07:00:09.000, 9, Good
RAMP, 30-Jul-2002 07:00:10.000, 10, Good
RAMP, 30-Jul-2002 07:00:11.000, 11, Good
RAMP, 30-Jul-2002 07:00:12.000, 12, Good
RAMP, 30-Jul-2002 07:00:13.000, 13, Good
RAMP, 30-Jul-2002 07:00:14.000, 14, Good
RAMP, 30-Jul-2002 07:00:15.000, 15, Good
RAMP, 30-Jul-2002 07:00:16.000, 16, Good
RAMP, 30-Jul-2002 07:00:17.000, 17, Good
RAMP, 30-Jul-2002 07:00:18.000, 18, Good
RAMP, 30-Jul-2002 07:00:19.000, 19, Good
RAMP, 30-Jul-2002 07:00:20.000, 20, Good
RAMP, 30-Jul-2002 07:00:21.000, 21, Good
RAMP, 30-Jul-2002 07:00:22.000, 22, Good
RAMP, 30-Jul-2002 07:00:23.000, 23, Good
RAMP, 30-Jul-2002 07:00:24.000, 24, Good
RAMP, 30-Jul-2002 07:00:25.000, 25, Good
RAMP, 30-Jul-2002 07:00:26.000, 26, Good
RAMP, 30-Jul-2002 07:00:27.000, 27, Good
RAMP, 30-Jul-2002 07:00:28.000, 28, Good
RAMP, 30-Jul-2002 07:00:29.000, 29, Good
RAMP, 30-Jul-2002 07:00:30.000, 30, Good
RAMP, 30-Jul-2002 07:00:31.000, 31, Good
RAMP, 30-Jul-2002 07:00:32.000, 32, Good
RAMP, 30-Jul-2002 07:00:33.000, 33, Good
RAMP, 30-Jul-2002 07:00:34.000, 34, Good
RAMP, 30-Jul-2002 07:00:35.000, 35, Good
RAMP, 30-Jul-2002 07:00:36.000, 36, Good
RAMP, 30-Jul-2002 07:00:37.000, 37, Good
RAMP, 30-Jul-2002 07:00:38.000, 38, Good
RAMP, 30-Jul-2002 07:00:39.000, 39, Good
RAMP, 30-Jul-2002 07:00:40.000, 40, Good
RAMP, 30-Jul-2002 07:00:41.000, 41, Good
RAMP, 30-Jul-2002 07:00:42.000, 42, Good
RAMP, 30-Jul-2002 07:00:43.000, 43, Good
RAMP, 30-Jul-2002 07:00:44.000, 44, Good

```
RAMP,30-Jul-2002 07:00:45.000,45,Good
RAMP,30-Jul-2002 07:00:46.000,46,Good
RAMP,30-Jul-2002 07:00:47.000,47,Good
RAMP,30-Jul-2002 07:00:48.000,48,Good
RAMP,30-Jul-2002 07:00:49.000,49,Good
RAMP,30-Jul-2002 07:00:50.000,50,Good
RAMP,30-Jul-2002 07:00:51.000,51,Good
RAMP,30-Jul-2002 07:00:52.000,52,Good
RAMP,30-Jul-2002 07:00:53.000,53,Good
RAMP,30-Jul-2002 07:00:54.000,54,Good
RAMP,30-Jul-2002 07:00:55.000,55,Good
RAMP,30-Jul-2002 07:00:56.000,56,Good
RAMP,30-Jul-2002 07:00:57.000,57,Good
RAMP,30-Jul-2002 07:00:58.000,58,Good
RAMP,30-Jul-2002 07:00:59.000,59,Good
ONOFF,30-Jul-2002 07:00:00.000,0,Good
ONOFF,30-Jul-2002 07:00:01.000,1,Good
ONOFF,30-Jul-2002 07:01:01.000,0,Good
ONOFF,30-Jul-2002 07:01:16.000,0,Good
ONOFF,30-Jul-2002 07:01:17.000,1,Good
ONOFF,30-Jul-2002 07:01:18.000,1,Good
ONOFF,30-Jul-2002 07:02:01.000,1,Good
ONOFF,30-Jul-2002 07:03:01.000,0,Good
HAS SPACE,30-Jul-2002 07:00:00.000,0,Good
HAS SPACE,30-Jul-2002 07:00:01.000,1,Good
HAS SPACE,30-Jul-2002 07:01:01.000,0,Good
HAS SPACE,30-Jul-2002 07:01:16.000,0,Good
HAS SPACE,30-Jul-2002 07:01:17.000,1,Good
HAS SPACE,30-Jul-2002 07:01:18.000,1,Good
HAS SPACE,30-Jul-2002 07:02:01.000,1,Good
HAS SPACE,30-Jul-2002 07:03:01.000,0,Good
```

The key to understanding this example is that the batch ID is written to the text tag at the start of the batch, and only at the start. It is not repeated during the batch. Other systems may write the batch ID at the end of the interval. You can tell the time period of a batch by looking at the raw samples of the batch ID tag.

```
BATCHID,30-Jul-2002 07:00:00.000,B1,Good
BATCHID,30-Jul-2002 07:00:20.000,B2,Good
BATCHID,30-Jul-2002 07:00:34.000,B3,Good
BATCHID,30-Jul-2002 07:00:52.000,B1,Good
```

In this system, since the batch ID is written at the start of the batch, you can tell that batch B1 ran from 07:00:01 to 07:00:19 and then batch B2 ran. This assumes that all time is attributable to some batch and there is no dead time between batches. If there is equipment downtime after a batch, you need to write some other value to the batch ID tag to indicate the end time of the batch.

The query parameters are given below:

Query Parameter	Value
Start Time	07/30/2002 07:00:00
End Time	07/30/2002 07:01:00
Interval	10 seconds

Using Filter Expressions

You can enter filter expressions in filtered data queries to indicate the desired time range. A Filter Expression has one or more filter conditions.

A filter condition has:

1. A Historian tag
2. A comparison (=, !=, >, <, <=, >=, ^, ~, !~, !^)
3. A value

For example: mytag < 7

You can add more than one filter condition in a filter expression using AND, OR within a parenthesis. For example: (mytag > 3) and (mytag < 7).

You can use bitwise comparison for a tag. By using bitwise comparison you can compare the binary values of the given filter tag with the bits specified in the condition. The Bitwise comparison modes are:

1. AllBitssSet (^)
2. AnyBitSet (~)
3. AnyBitNotSet (!~)
4. AllBitsNotSet (!^)

While using filter expression you should remember the following things:

- You cannot use a NOT operator; you can use != instead.
- You cannot do mathematical operations such as (mytag1+7) > 15.
- You cannot compare two tags such as mytag1 > mytag2.

Your conditions can only include values and not qualities. Values are used only if they are of good quality so you need not check the quality separately. As with any filtered data query, the filter expression determines the time ranges of the data returned. There is no maximum length for an expression but a typical expression will be have 1 or 3 conditions.

Import this data to Historian:

```
*
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
BATCHID,VariableString,10,0
RAMP,SingleInteger,60,0
ONOFF,SingleInteger,60,0
HAS SPACE,SingleInteger,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
BATCHID,30-Jul-2002 07:00:00.000,B1,Good
BATCHID,30-Jul-2002 07:00:20.000,B2,Good
BATCHID,30-Jul-2002 07:00:34.000,B3,Good
BATCHID,30-Jul-2002 07:00:52.000,B1,Good
RAMP,30-Jul-2002 07:00:00.000,0,Good
RAMP,30-Jul-2002 07:00:01.000,1,Good
RAMP,30-Jul-2002 07:00:02.000,2,Good
RAMP,30-Jul-2002 07:00:03.000,3,Good
RAMP,30-Jul-2002 07:00:04.000,4,Good
RAMP,30-Jul-2002 07:00:05.000,5,Good
RAMP,30-Jul-2002 07:00:06.000,6,Good
RAMP,30-Jul-2002 07:00:07.000,7,Good
RAMP,30-Jul-2002 07:00:08.000,8,Good
RAMP,30-Jul-2002 07:00:09.000,9,Good
RAMP,30-Jul-2002 07:00:10.000,10,Good
RAMP,30-Jul-2002 07:00:11.000,11,Good
RAMP,30-Jul-2002 07:00:12.000,12,Good
```

RAMP, 30-Jul-2002 07:00:13.000, 13, Good
RAMP, 30-Jul-2002 07:00:14.000, 14, Good
RAMP, 30-Jul-2002 07:00:15.000, 15, Good
RAMP, 30-Jul-2002 07:00:16.000, 16, Good
RAMP, 30-Jul-2002 07:00:17.000, 17, Good
RAMP, 30-Jul-2002 07:00:18.000, 18, Good
RAMP, 30-Jul-2002 07:00:19.000, 19, Good
RAMP, 30-Jul-2002 07:00:20.000, 20, Good
RAMP, 30-Jul-2002 07:00:21.000, 21, Good
RAMP, 30-Jul-2002 07:00:22.000, 22, Good
RAMP, 30-Jul-2002 07:00:23.000, 23, Good
RAMP, 30-Jul-2002 07:00:24.000, 24, Good
RAMP, 30-Jul-2002 07:00:25.000, 25, Good
RAMP, 30-Jul-2002 07:00:26.000, 26, Good
RAMP, 30-Jul-2002 07:00:27.000, 27, Good
RAMP, 30-Jul-2002 07:00:28.000, 28, Good
RAMP, 30-Jul-2002 07:00:29.000, 29, Good
RAMP, 30-Jul-2002 07:00:30.000, 30, Good
RAMP, 30-Jul-2002 07:00:31.000, 31, Good
RAMP, 30-Jul-2002 07:00:32.000, 32, Good
RAMP, 30-Jul-2002 07:00:33.000, 33, Good
RAMP, 30-Jul-2002 07:00:34.000, 34, Good
RAMP, 30-Jul-2002 07:00:35.000, 35, Good
RAMP, 30-Jul-2002 07:00:36.000, 36, Good
RAMP, 30-Jul-2002 07:00:37.000, 37, Good
RAMP, 30-Jul-2002 07:00:38.000, 38, Good
RAMP, 30-Jul-2002 07:00:39.000, 39, Good
RAMP, 30-Jul-2002 07:00:40.000, 40, Good
RAMP, 30-Jul-2002 07:00:41.000, 41, Good
RAMP, 30-Jul-2002 07:00:42.000, 42, Good
RAMP, 30-Jul-2002 07:00:43.000, 43, Good
RAMP, 30-Jul-2002 07:00:44.000, 44, Good
RAMP, 30-Jul-2002 07:00:45.000, 45, Good
RAMP, 30-Jul-2002 07:00:46.000, 46, Good
RAMP, 30-Jul-2002 07:00:47.000, 47, Good
RAMP, 30-Jul-2002 07:00:48.000, 48, Good
RAMP, 30-Jul-2002 07:00:49.000, 49, Good

```
RAMP,30-Jul-2002 07:00:50.000,50,Good
RAMP,30-Jul-2002 07:00:51.000,51,Good
RAMP,30-Jul-2002 07:00:52.000,52,Good
RAMP,30-Jul-2002 07:00:53.000,53,Good
RAMP,30-Jul-2002 07:00:54.000,54,Good
RAMP,30-Jul-2002 07:00:55.000,55,Good
RAMP,30-Jul-2002 07:00:56.000,56,Good
RAMP,30-Jul-2002 07:00:57.000,57,Good
RAMP,30-Jul-2002 07:00:58.000,58,Good
RAMP,30-Jul-2002 07:00:59.000,59,Good
ONOFF,30-Jul-2002 07:00:00.000,0,Good
ONOFF,30-Jul-2002 07:00:01.000,1,Good
ONOFF,30-Jul-2002 07:01:01.000,0,Good
ONOFF,30-Jul-2002 07:01:16.000,0,Good
ONOFF,30-Jul-2002 07:01:17.000,1,Good
ONOFF,30-Jul-2002 07:01:18.000,1,Good
ONOFF,30-Jul-2002 07:02:01.000,1,Good
ONOFF,30-Jul-2002 07:03:01.000,0,Good
HAS SPACE,30-Jul-2002 07:00:00.000,0,Good
HAS SPACE,30-Jul-2002 07:00:01.000,1,Good
HAS SPACE,30-Jul-2002 07:01:01.000,0,Good
HAS SPACE,30-Jul-2002 07:01:16.000,0,Good
HAS SPACE,30-Jul-2002 07:01:17.000,1,Good
HAS SPACE,30-Jul-2002 07:01:18.000,1,Good
HAS SPACE,30-Jul-2002 07:02:01.000,1,Good
HAS SPACE,30-Jul-2002 07:03:01.000,0,Good
```

For the following scenarios, import the data tags provided.

Counter Delta Queries

A delta counter measures the change in tag values that increase steadily over a time interval and then reset to a minimum value (for example, the electricity meter of a household).

Historian offers the following delta queries to determine the delta over a time interval:

- [DELTAPOS \(on page 1116\)](#)
- [DELTANEG \(on page 1132\)](#)
- [DELTA \(on page 1141\)](#)

Advantages of using delta queries:

- Simplified visualization and analysis of counter data.
- Returns the delta over a period rather than the exact value at the end of each counter.
- Handles counter resets and counter wrap around.

Delta counters are useful when you are monitoring data from multiple sources. The following terms are used in a delta counter:

Counter Reset

A point where data points are reset to the minimum value. For example, the electricity meter of a household is reset to 0 at the beginning of every month or when a meter is replaced with a new one.

Counter Wrap Around

A point where data in an increasing trend suddenly drops to a value less than a specified value. This happens when the reading goes beyond the maximum value that the meter can read. For example, if a meter can read from 0 to 255, any reading greater than 255 is set to 0. This is called a counter wrap around.

Delta Max Value

The maximum value that a tag can have. It also called the rollover point of the counter or totalizer. If the tag values exceed MaxValue, the counter is reset to the minimum value. If you do not provide MaxValue, the delta query cannot check for a positive counter wrap. You can set this value while [specifying tags for data collection \(on page 357\)](#) in Configuration Hub.

Delta Min Value

The minimum value that a tag can have. If the tag values are less than MinValue (and the counter is going in the negative direction), the tag values are reset to MaxValue. If you do not provide MinValue, 0 is considered. You can set this value while [specifying tags for data collection \(on page 357\)](#) in Configuration Hub.

Delta Max Positive RPH

The maximum rate per hour between two consecutive data points in the positive direction. If two consecutive data points exceed this value, they are not considered in a delta query. You can set this value while [specifying tags for data collection \(on page 357\)](#) in Configuration Hub.

Delta Max Negative RPH


The maximum rate per hour between two consecutive data points in the negative direction. If two consecutive data points exceed this value, they are not considered in a delta query. You can set this value while [specifying tags for data collection \(on page 357\)](#) in Configuration Hub.

The Delta Max Positive RPH and Delta Max Negative RPH values are used to determine if a counter wrap has occurred or if the counter has been manually reset. They help ignore data points whose values increase or decrease drastically.

Suppose a tag stores the readings of an electricity meter. And you have provided the following values:

Field	Value
Delta Max Value	255
Delta Min Value	5
Delta Max Positive RPH	10
Delta Max Negative RPH	10


Suppose the following data points are received for the tag:



After 35, the value increases to 47. Since the difference is greater than MaxPositiveRPH, the data points 35 and 47 will not be considered in a delta query.

Similarly, the difference between 55 and 40 is greater than MaxNegativeRPH; therefore, these two data points will not be considered in a delta query.

After 55, the counter has been reset to its minimum value.



DELTAPOS Calculation

The following diagrams show how DELTAPOS is calculated. If Delta Min is not considered, 0 is considered.

Figure 2. DELTAPOS Calculation When Delta Max Positive RPH is not Provided





Figure 3. DELTAPOS Calculation When Delta Max Positive RPH is Provided



Note:

Delta Max Negative RPH is not used to calculate DELTAPOS.

Calculating DELTAPOS When Delta Max Positive RPH is Not Provided and Data is in the Increasing Trend

Suppose you have received the following tag data:

TimeStamp	Tag Value	Data Quality
19-Dec-2021 14:01:10	0	Good
19-Dec-2021 14:01:20	5	Good
19-Dec-2021 14:01:30	10	Good
19-Dec-2021 14:01:40	15	Good
19-Dec-2021 14:01:50	20	Good
19-Dec-2021 14:02:00	25	Good
19-Dec-2021 14:02:10	30	Good
19-Dec-2021 14:02:20	35	Good
19-Dec-2021 14:02:30	40	Good

TimeStamp	Tag Value	Data Quality
19-Dec-2021 14:02:40	45	Good
19-Dec-2021 14:02:50	50	Good
19-Dec-2021 14:03:00	55	Good
19-Dec-2021 14:03:10	60	Good
19-Dec-2021 14:03:20	65	Good
19-Dec-2021 14:03:30	70	Good
19-Dec-2021 14:03:40	75	Good
19-Dec-2021 14:03:50	80	Good
19-Dec-2021 14:04:00	85	Good
19-Dec-2021 14:04:10	90	Good
19-Dec-2021 14:04:20	95	Good
19-Dec-2021 14:04:30	100	Good
19-Dec-2021 14:04:40	105	Good
19-Dec-2021 14:04:50	110	Good
19-Dec-2021 14:05:00	115	Good
19-Dec-2021 14:05:10	120	Good
19-Dec-2021 14:05:20	125	Good
19-Dec-2021 14:05:30	130	Good
19-Dec-2021 14:05:40	135	Good
19-Dec-2021 14:05:50	140	Good
19-Dec-2021 14:06:00	145	Good

Suppose you have run the following query:

```
Select timestamp,value,quality from IHrawdata
where tagname=BasicTestPos and samplingmode=calculated and
timestamp>='19-Dec-2021 14:00:00.000' and timestamp<='19-Dec-2021 14:06:00.000'
and calculationmode=DeltaPos and intervalmilliseconds=1M
```

Regardless of whether you have provided Delta Min and Delta Max, since you have not provided Delta Max Positive RPH, and since the data points are in the increasing trend, DELTAPOS is calculated as the difference between consecutive data points:

TimeStamp	DELTAPOS Value	Data Quality
19-Dec-2021 14:00:00	0	100
19-Dec-2021 14:01:00	0	100
19-Dec-2021 14:02:00	25.00	100
19-Dec-2021 14:03:00	30.00	100
19-Dec-2021 14:04:00	30.00	100
19-Dec-2021 14:05:00	30.00	100
19-Dec-2021 14:06:00	30.00	100

Calculating DELTAPOS When Data Quality is Bad

Suppose you have received the following data:

Time Stamp	Value	Data Quality
19-Dec-2021 14:01:10	0	Good
19-Dec-2021 14:01:20	5	Bad
19-Dec-2021 14:01:30	10	Good
19-Dec-2021 14:01:40	15	Bad
19-Dec-2021 14:01:50	20	Good
19-Dec-2021 14:02:00	25	Bad
19-Dec-2021 14:02:10	30	Good
19-Dec-2021 14:02:20	35	Bad
19-Dec-2021 14:02:30	40	Good
19-Dec-2021 14:02:40	45	Bad
19-Dec-2021 14:02:50	50	Good
19-Dec-2021 14:03:00	55	Bad

Time Stamp	Value	Data Quality
19-Dec-2021 14:03:10	60	Good
19-Dec-2021 14:03:20	65	Bad
19-Dec-2021 14:03:30	70	Good
19-Dec-2021 14:03:40	75	Bad
19-Dec-2021 14:03:50	80	Good
19-Dec-2021 14:04:00	85	Bad
19-Dec-2021 14:04:10	90	Good
19-Dec-2021 14:04:20	95	Bad
19-Dec-2021 14:04:30	100	Good
19-Dec-2021 14:04:40	105	Bad
19-Dec-2021 14:04:50	110	Good
19-Dec-2021 14:05:00	115	Bad
19-Dec-2021 14:05:10	120	Good
19-Dec-2021 14:05:20	125	Bad
19-Dec-2021 14:05:30	130	Good
19-Dec-2021 14:05:40	135	Bad
19-Dec-2021 14:05:50	140	Good
19-Dec-2021 14:06:00	145	Bad

Suppose you have run the following query:

```
Select timestamp,value,quality from IHrawdata
where tagname=BasicTestWithBad and samplingmode=calculated
and timestamp>='19-Dec-2021 14:00:00.000' and timestamp<='19-Dec-2021 14:06:00.000'
and calculationmode=DeltaPos and intervalmilliseconds=1M
```

Data with bad quality is not considered in the calculation. Therefore, DELTAPOS is the difference between consecutive data points with good quality.

Time Stamp	Val- ue	Data Quality	DELTAPOS
19-Dec-2021 14:01:10	0	Good	0
19-Dec-2021 14:01:20	5	Bad	0
19-Dec-2021 14:01:30	10	Good	10
19-Dec-2021 14:01:40	15	Bad	0
19-Dec-2021 14:01:50	20	Good	10
19-Dec-2021 14:02:00	25	Bad	0
19-Dec-2021 14:02:10	30	Good	10
19-Dec-2021 14:02:20	35	Bad	0
19-Dec-2021 14:02:30	40	Good	10
19-Dec-2021 14:02:40	45	Bad	0
19-Dec-2021 14:02:50	50	Good	10
19-Dec-2021 14:03:00	55	Bad	0
19-Dec-2021 14:03:10	60	Good	10
19-Dec-2021 14:03:20	65	Bad	0
19-Dec-2021 14:03:30	70	Good	10
19-Dec-2021 14:03:40	75	Bad	0
19-Dec-2021 14:03:50	80	Good	10
19-Dec-2021 14:04:00	85	Bad	0
19-Dec-2021 14:04:10	90	Good	10
19-Dec-2021 14:04:20	95	Bad	0
19-Dec-2021 14:04:30	100	Good	10
19-Dec-2021 14:04:40	105	Bad	0
19-Dec-2021 14:04:50	110	Good	10
19-Dec-2021 14:05:00	115	Bad	0
19-Dec-2021 14:05:10	120	Good	10
19-Dec-2021 14:05:20	125	Bad	0

Time Stamp	Value	Data Quality	DELTAPOS
19-Dec-2021 14:05:30	130	Good	10
19-Dec-2021 14:05:40	135	Bad	0
19-Dec-2021 14:05:50	140	Good	10
19-Dec-2021 14:06:00	145	Bad	0

DELTAPOS for a given duration is calculated as the sum of the individual DELTAPOS values in that duration as shown in the following table.

Time Stamp	Value	Data Quality
19-Dec-2021 14:00:00	0.00	100
19-Dec-2021 14:01:00	0.00	100
19-Dec-2021 14:02:00	20.00	100
19-Dec-2021 14:03:00	30.00	100
19-Dec-2021 14:04:00	30.00	100
19-Dec-2021 14:05:00	30.00	100
19-Dec-2021 14:06:00	30.00	100

Calculating DELTAPOS When Rate of Increase is Greater than Delta Max Positive RPH

Suppose you have provided the following data:

Delta Max	265
Delta Min	50
Delta Max Positive RPH	10
Delta Max Negative RPH	10

Suppose you have received the following data:

TimeStamp	Tag Value	Data Quality
19-Dec-2021 14:01:10	55	Good
19-Dec-2021 14:01:20	65	Good
19-Dec-2021 14:01:30	80	Good
19-Dec-2021 14:01:40	85	Good
19-Dec-2021 14:01:50	95	Good
19-Dec-2021 14:02:00	105	Good
19-Dec-2021 14:02:10	120	Good
19-Dec-2021 14:02:20	125	Good
19-Dec-2021 14:02:30	140	Good
19-Dec-2021 14:02:40	145	Good
19-Dec-2021 14:02:50	155	Good
19-Dec-2021 14:03:00	165	Good
19-Dec-2021 14:03:10	175	Good
19-Dec-2021 14:03:20	185	Good
19-Dec-2021 14:03:30	195	Good
19-Dec-2021 14:03:40	205	Good
19-Dec-2021 14:03:50	215	Good
19-Dec-2021 14:04:00	225	Good
19-Dec-2021 14:04:10	235	Good
19-Dec-2021 14:04:20	245	Good
19-Dec-2021 14:04:30	255	Good
19-Dec-2021 14:04:40	265	Good
19-Dec-2021 14:04:50	55	Good
19-Dec-2021 14:05:00	65	Good
19-Dec-2021 14:05:10	75	Good

TimeStamp	Tag Value	Data Quality
19-Dec-2021 14:05:20	85	Good
19-Dec-2021 14:05:30	95	Good
19-Dec-2021 14:05:40	105	Good
19-Dec-2021 14:05:50	115	Good
19-Dec-2021 14:06:00	125	Good

Suppose you have run the following query:

```
Select timestamp,value,quality from IHrawdata
where tagname=DeltaPosSample4 and samplingmode=calculated
and timestamp>='19-Dec-2021 14:00:00.000' and timestamp<='19-Dec-2021 14:06:00.000'
and calculationmode=DeltaPos and intervalmilliseconds=1M
```

In the cases where the rate of increase is greater than Delta Max Positive RPH, DELTAPOS = 0. For the other values, DELTAPOS is the difference between the consecutive values (highlighted in bold formatting):

Time Stamp	Val- ue	Data Quality
19-Dec-2021 14:00:00	0.00	100
19-Dec-2021 14:01:00	0.00	100
19-Dec-2021 14:02:00	50.00	100
19-Dec-2021 14:03:00	60.00	100
19-Dec-2021 14:04:00	60.00	100
19-Dec-2021 14:05:00	55.00	100
19-Dec-2021 14:06:00	60.00	100

Calculating DELTAPOS When Delta Max is not Provided and Data does not Follow a Trend

Suppose you have received the following data:

Time Stamp	Val- ue	Data Quality
19-Dec-2021 14:01:10	0	Good

Time Stamp	Value	Data Quality
19-Dec-2021 14:01:20	5	Good
19-Dec-2021 14:01:30	10	Good
19-Dec-2021 14:01:40	8	Good
19-Dec-2021 14:01:50	20	Good
19-Dec-2021 14:02:00	25	Good
19-Dec-2021 14:02:10	30	Good
19-Dec-2021 14:02:20	19	Good
19-Dec-2021 14:02:30	40	Good
19-Dec-2021 14:02:40	45	Good
19-Dec-2021 14:02:50	50	Good
19-Dec-2021 14:03:00	55	Good
19-Dec-2021 14:03:10	60	Good
19-Dec-2021 14:03:20	38	Good
19-Dec-2021 14:03:30	70	Good
19-Dec-2021 14:03:40	75	Good
19-Dec-2021 14:03:50	80	Good
19-Dec-2021 14:04:00	85	Good
19-Dec-2021 14:04:10	90	Good
19-Dec-2021 14:04:20	95	Good
19-Dec-2021 14:04:30	100	Good
19-Dec-2021 14:04:40	105	Good
19-Dec-2021 14:04:50	110	Good
19-Dec-2021 14:05:00	115	Good
19-Dec-2021 14:05:10	120	Good
19-Dec-2021 14:05:20	125	Good

Time Stamp	Value	Data Quality
19-Dec-2021 14:05:30	130	Good
19-Dec-2021 14:05:40	135	Good
19-Dec-2021 14:05:50	140	Good
19-Dec-2021 14:06:00	145	Good

Suppose you have run the following query:

```
Select timestamp,value,quality from IHrawdata
where tagname=DeltaPosSample1 and samplingmode=calculated
and timestamp>='19-Dec-2021 14:00:00.000' and timestamp<='19-Dec-2021 14:06:00.000'
and calculationmode=DeltaPos and intervalmilliseconds=1M
```

Since you have not provided Delta Max Positive RPH, for data points that are in the increasing trend, the difference is used. For data points that are in the decreasing trend, DELTAPOS is calculated as the difference between the latest value and Delta Min (highlighted in bold formatting). Since Delta Min is not provided, it is considered as 0.

Time Stamp	Value	DELTAPOS
19-Dec-2021 14:01:10	0	0
19-Dec-2021 14:01:20	5	5
19-Dec-2021 14:01:30	10	5
19-Dec-2021 14:01:40	8	8
19-Dec-2021 14:01:50	20	12
19-Dec-2021 14:02:00	25	5
19-Dec-2021 14:02:10	30	5
19-Dec-2021 14:02:20	19	19
19-Dec-2021 14:02:30	40	21
19-Dec-2021 14:02:40	45	5
19-Dec-2021 14:02:50	50	5

Time Stamp	Value	DELTAPOS
19-Dec-2021 14:03:00	55	5
19-Dec-2021 14:03:10	60	5
19-Dec-2021 14:03:20	38	38
19-Dec-2021 14:03:30	70	32
19-Dec-2021 14:03:40	75	5
19-Dec-2021 14:03:50	80	5
19-Dec-2021 14:04:00	85	5
19-Dec-2021 14:04:10	90	5
19-Dec-2021 14:04:20	95	5
19-Dec-2021 14:04:30	100	5
19-Dec-2021 14:04:40	105	5
19-Dec-2021 14:04:50	110	5
19-Dec-2021 14:05:00	115	5
19-Dec-2021 14:05:10	120	5
19-Dec-2021 14:05:20	125	5
19-Dec-2021 14:05:30	130	5
19-Dec-2021 14:05:40	135	5
19-Dec-2021 14:05:50	140	5
19-Dec-2021 14:06:00	145	5

DELTAPOS for a given duration is calculated as the sum of the individual DELTAPOS values in that duration as shown in the following table.

Time Stamp	DELTAPOS Value	Data Quality
19-Dec-2021 14:00:00	0.00	100
19-Dec-2021 14:01:00	0.00	100

Time Stamp	DELTAPOS Value	Data Quality
19-Dec-2021 14:02:00	35.00	100
19-Dec-2021 14:03:00	60.00	100
19-Dec-2021 14:04:00	90.00	100
19-Dec-2021 14:05:00	30.00	100
19-Dec-2021 14:06:00	30.00	100

Calculating DELTAPOS When Delta Max is Provided and Data does not Follow a Trend

Suppose you have provided the following values:

Delta Max	265
Delta Min	50

Suppose you have received the following data:

Time Stamp	Value	Data Quality
19-Dec-2021 14:01:10	50	Good
19-Dec-2021 14:01:20	60	Good
19-Dec-2021 14:01:30	55	Good
19-Dec-2021 14:01:40	80	Good
19-Dec-2021 14:01:50	90	Good
19-Dec-2021 14:02:00	100	Good
19-Dec-2021 14:02:10	110	Good
19-Dec-2021 14:02:20	80	Good
19-Dec-2021 14:02:30	130	Good
19-Dec-2021 14:02:40	110	Good
19-Dec-2021 14:02:50	150	Good
19-Dec-2021 14:03:00	160	Good

Time Stamp	Value	Data Quality
19-Dec-2021 14:03:10	170	Good
19-Dec-2021 14:03:20	180	Good
19-Dec-2021 14:03:30	190	Good
19-Dec-2021 14:03:40	200	Good
19-Dec-2021 14:03:50	210	Good
19-Dec-2021 14:04:00	220	Good
19-Dec-2021 14:04:10	230	Good
19-Dec-2021 14:04:20	240	Good
19-Dec-2021 14:04:30	250	Good
19-Dec-2021 14:04:40	260	Good
19-Dec-2021 14:04:50	50	Good
19-Dec-2021 14:05:00	60	Good
19-Dec-2021 14:05:10	70	Good
19-Dec-2021 14:05:20	80	Good
19-Dec-2021 14:05:30	90	Good
19-Dec-2021 14:05:40	100	Good
19-Dec-2021 14:05:50	110	Good
19-Dec-2021 14:06:00	120	Good

Suppose you have run the following query:

```
Select timestamp,value,quality from IHrawdata  
where tagname=DeltaPosSample3 and samplingmode=calculated  
and timestamp>='19-Dec-2021 14:00:00.000' and timestamp<='19-Dec-2021 14:06:00.000'  
and calculationmode=DeltaPos and intervalmilliseconds=1M
```

Since you have not provided Delta Max Positive RPH, for data points that are in the increasing trend, the difference is used. For data points that are in the decreasing trend, DELTAPOS is calculated as follows:

$$\text{DELTAPOS} = \text{Delta Max} - \text{Previous Value} + \text{Current Value} - \text{Delta Min}$$

These values as highlighted in bold formatting in the following table.

Time Stamp	Value	DELTAPOS Value
19-Dec-2021 14:01:10	50	0
19-Dec-2021 14:01:20	60	10
19-Dec-2021 14:01:30	55	210
19-Dec-2021 14:01:40	80	25
19-Dec-2021 14:01:50	90	10
19-Dec-2021 14:02:00	100	10
19-Dec-2021 14:02:10	110	10
19-Dec-2021 14:02:20	80	185
19-Dec-2021 14:02:30	130	50
19-Dec-2021 14:02:40	110	195
19-Dec-2021 14:02:50	150	40
19-Dec-2021 14:03:00	160	10
19-Dec-2021 14:03:10	170	10
19-Dec-2021 14:03:20	180	10
19-Dec-2021 14:03:30	190	10
19-Dec-2021 14:03:40	200	10
19-Dec-2021 14:03:50	210	10
19-Dec-2021 14:04:00	220	10
19-Dec-2021 14:04:10	230	10
19-Dec-2021 14:04:20	240	10
19-Dec-2021 14:04:30	250	10
19-Dec-2021 14:04:40	260	10
19-Dec-2021 14:04:50	50	5
19-Dec-2021 14:05:00	60	10
19-Dec-2021 14:05:10	70	10

Time Stamp	Value	DELTAPOS Value
19-Dec-2021 14:05:20	80	10
19-Dec-2021 14:05:30	90	10
19-Dec-2021 14:05:40	100	10
19-Dec-2021 14:05:50	110	10
19-Dec-2021 14:06:00	120	10

DELTAPOS for a given duration is calculated as the sum of the individual DELTAPOS values in that duration as shown in the following table.

Time Stamp	Value	Data Quality
19-Dec-2021 14:00:00	0.00	100
19-Dec-2021 14:01:00	0.00	100
19-Dec-2021 14:02:00	265.00	100
19-Dec-2021 14:03:00	490.00	100
19-Dec-2021 14:04:00	60.00	100
19-Dec-2021 14:05:00	55.00	100
19-Dec-2021 14:06:00	60.00	100

DELTANEG Calculation

The following diagrams show how DELTANEG is calculated. If Delta Min is not considered, 0 is considered.

Figure 4. DELTANEG Calculation When Delta Max Negative RPH is not Provided





Figure 5. DELTANEG Calculation When Delta Max Negative RPH is Provided



Note:

Delta Max Positive RPH is not used to calculate DELTANEG.

Calculating DELTANEG When Delta Max Negative RPH is Not Provided and Data is in the Decreasing Trend

Suppose you have received the following tag data:

TimeStamp	Tag Value	Data Quality
19-Dec-2021 14:01:10	265	Good
19-Dec-2021 14:01:20	260	Good
19-Dec-2021 14:01:30	255	Good
19-Dec-2021 14:01:40	250	Good
19-Dec-2021 14:01:50	245	Good
19-Dec-2021 14:02:00	240	Good
19-Dec-2021 14:02:10	235	Good
19-Dec-2021 14:02:20	230	Good
19-Dec-2021 14:02:30	225	Good

TimeStamp	Tag Value	Data Quality
19-Dec-2021 14:02:40	220	Good
19-Dec-2021 14:02:50	215	Good
19-Dec-2021 14:03:00	210	Good
19-Dec-2021 14:03:10	205	Good
19-Dec-2021 14:03:20	200	Good
19-Dec-2021 14:03:30	195	Good
19-Dec-2021 14:03:40	190	Good
19-Dec-2021 14:03:50	185	Good
19-Dec-2021 14:04:00	180	Good
19-Dec-2021 14:04:10	175	Good
19-Dec-2021 14:04:20	170	Good
19-Dec-2021 14:04:30	165	Good
19-Dec-2021 14:04:40	160	Good
19-Dec-2021 14:04:50	155	Good
19-Dec-2021 14:05:00	150	Good
19-Dec-2021 14:05:10	145	Good
19-Dec-2021 14:05:20	140	Good
19-Dec-2021 14:05:30	135	Good
19-Dec-2021 14:05:40	130	Good
19-Dec-2021 14:05:50	125	Good
19-Dec-2021 14:06:00	120	Good

Suppose you have run the following query:

```
Select timestamp,value,quality from IHrawdata
where tagname=BasicTest and samplingmode=calculated
and timestamp>='19-Dec-2021 14:00:00.000' and timestamp<='19-Dec-2021 14:06:00.000'
and calculationmode=DeltaNeg and intervalmilliseconds=1M
```

Regardless of whether you have provided Delta Min and Delta Max, since you have not provided Delta Max Negative RPH, and since the data points are in the decreasing trend, DELTANEG is calculated as the difference between consecutive data points:

TimeStamp	DELTANEG Value	Data Quality
19-Dec-2021 14:00:00	0	100
19-Dec-2021 14:01:00	0	100
19-Dec-2021 14:02:00	-25.00	100
19-Dec-2021 14:03:00	-30.00	100
19-Dec-2021 14:04:00	-30.00	100
19-Dec-2021 14:05:00	-30.00	100
19-Dec-2021 14:06:00	-30.00	100

Calculating DELTANEG When Data Quality is Bad

Suppose you have received the following data:

Time Stamp	Value	Data Quality
19-Dec-2021 14:01:10	265	Good
19-Dec-2021 14:01:20	260	Bad
19-Dec-2021 14:01:30	255	Good
19-Dec-2021 14:01:40	250	Bad
19-Dec-2021 14:01:50	245	Good
19-Dec-2021 14:02:00	240	Bad
19-Dec-2021 14:02:10	235	Good
19-Dec-2021 14:02:20	230	Bad
19-Dec-2021 14:02:30	225	Good
19-Dec-2021 14:02:40	220	Bad
19-Dec-2021 14:02:50	215	Good
19-Dec-2021 14:03:00	210	Bad

Time Stamp	Value	Data Quality
19-Dec-2021 14:03:10	205	Good
19-Dec-2021 14:03:20	200	Bad
19-Dec-2021 14:03:30	195	Good
19-Dec-2021 14:03:40	190	Bad
19-Dec-2021 14:03:50	185	Good
19-Dec-2021 14:04:00	180	Bad
19-Dec-2021 14:04:10	175	Good
19-Dec-2021 14:04:20	170	Bad
19-Dec-2021 14:04:30	165	Good
19-Dec-2021 14:04:40	160	Bad
19-Dec-2021 14:04:50	155	Good
19-Dec-2021 14:05:00	150	Bad
19-Dec-2021 14:05:10	145	Good
19-Dec-2021 14:05:20	140	Bad
19-Dec-2021 14:05:30	135	Good
19-Dec-2021 14:05:40	130	Bad
19-Dec-2021 14:05:50	125	Good
19-Dec-2021 14:06:00	120	Bad

Suppose you have run the following query:

```
Select timestamp,value,quality from IHrawdata
where tagname=BasicTestWithBad and samplingmode=calculated
and timestamp>='19-Dec-2021 14:00:00.000' and timestamp<='19-Dec-2021 14:06:00.000'
and calculationmode=DeltaNeg and intervalmilliseconds=1M
```

Data with bad quality is not considered in the calculation. Therefore, DELTANEG is the difference between consecutive data points with good quality.

Time Stamp	Value	Data Quality	DELTANEG
19-Dec-2021 14:01:10	265	Good	0
19-Dec-2021 14:01:20	260	Bad	0
19-Dec-2021 14:01:30	255	Good	-10
19-Dec-2021 14:01:40	250	Bad	0
19-Dec-2021 14:01:50	245	Good	-10
19-Dec-2021 14:02:00	240	Bad	0
19-Dec-2021 14:02:10	235	Good	-10
19-Dec-2021 14:02:20	230	Bad	0
19-Dec-2021 14:02:30	225	Good	-10
19-Dec-2021 14:02:40	220	Bad	0
19-Dec-2021 14:02:50	215	Good	-10
19-Dec-2021 14:03:00	210	Bad	0
19-Dec-2021 14:03:10	205	Good	-10
19-Dec-2021 14:03:20	200	Bad	0
19-Dec-2021 14:03:30	195	Good	-10
19-Dec-2021 14:03:40	190	Bad	0
19-Dec-2021 14:03:50	185	Good	-10
19-Dec-2021 14:04:00	180	Bad	0
19-Dec-2021 14:04:10	175	Good	-10
19-Dec-2021 14:04:20	170	Bad	0
19-Dec-2021 14:04:30	165	Good	-10
19-Dec-2021 14:04:40	160	Bad	0
19-Dec-2021 14:04:50	155	Good	-10
19-Dec-2021 14:05:00	150	Bad	0
19-Dec-2021 14:05:10	145	Good	-10
19-Dec-2021 14:05:20	140	Bad	0

Time Stamp	Value	Data Quality	DELTANEG
19-Dec-2021 14:05:30	135	Good	-10
19-Dec-2021 14:05:40	130	Bad	0
19-Dec-2021 14:05:50	125	Good	-10
19-Dec-2021 14:06:00	120	Bad	0

DELTANEG for a given duration is calculated as the sum of the individual DELTANEG values in that duration as shown in the following table.

Time Stamp	DELTANEG	Data Quality
19-Dec-2021 14:00:00	0.00	100
19-Dec-2021 14:01:00	0.00	100
19-Dec-2021 14:02:00	-20.00	100
19-Dec-2021 14:03:00	-30.00	100
19-Dec-2021 14:04:00	-30.00	100
19-Dec-2021 14:05:00	-30.00	100
19-Dec-2021 14:06:00	-30.00	100

Calculating DELTANEG When Delta Max Negative RPH is not Provided and Data is in the Increasing Trend

Suppose you have received the following data:

TimeStamp	Tag Value	Data Quality
19-Dec-2021 14:01:10	265	Good
19-Dec-2021 14:01:20	260	Good
19-Dec-2021 14:01:30	262	Good
19-Dec-2021 14:01:40	250	Good
19-Dec-2021 14:01:50	245	Good
19-Dec-2021 14:02:00	240	Good

TimeStamp	Tag Value	Data Quality
19-Dec-2021 14:02:10	235	Good
19-Dec-2021 14:02:20	230	Good
19-Dec-2021 14:02:30	231	Good
19-Dec-2021 14:02:40	233	Good
19-Dec-2021 14:02:50	215	Good
19-Dec-2021 14:03:00	210	Good
19-Dec-2021 14:03:10	205	Good
19-Dec-2021 14:03:20	220	Good
19-Dec-2021 14:03:30	195	Good
19-Dec-2021 14:03:40	190	Good
19-Dec-2021 14:03:50	185	Good
19-Dec-2021 14:04:00	180	Good
19-Dec-2021 14:04:10	175	Good
19-Dec-2021 14:04:20	170	Good
19-Dec-2021 14:04:30	165	Good
19-Dec-2021 14:04:40	160	Good
19-Dec-2021 14:04:50	155	Good
19-Dec-2021 14:05:00	150	Good
19-Dec-2021 14:05:10	145	Good
19-Dec-2021 14:05:20	140	Good
19-Dec-2021 14:05:30	135	Good
19-Dec-2021 14:05:40	130	Good
19-Dec-2021 14:05:50	125	Good
19-Dec-2021 14:06:00	120	Good

Suppose you have run the following query:

```
Select timestamp,value,quality from IHrawdata
where tagname=DeltaNegSample1 and samplingmode=calculated
and timestamp>='19-Dec-2021 14:00:00.000' and timestamp<='19-Dec-2021 14:06:00.000'
and calculationmode=DeltaNeg and intervalmilliseconds=1M
```


For data that is in the increasing trend, since you have not provided values for Delta Max, Delta Min, and Delta Max Negative RPH, DELTANEG = 0. For the other cases, DELTANEG is the difference between the values.

Time Stamp	DELTANEG Value	Data Quality
19-Dec-2021 14:00:00	0.00	100
19-Dec-2021 14:01:00	0.00	100
19-Dec-2021 14:02:00	-27.00	100
19-Dec-2021 14:03:00	-33.00	100
19-Dec-2021 14:04:00	-45.00	100
19-Dec-2021 14:05:00	-30.00	100
19-Dec-2021 14:06:00	-30.00	100

DELTA Calculation

The following diagram shows how DELTA is calculated.

Figure 6. DELTA Calculation



Note:

To calculate Delta, all of these values are required: Delta Max, Delta Min, Delta Max Positive RPH, and Delta Max Negative RPH.

Other Calculation Modes

STATECOUNT

The STATECOUNT calculation mode counts the number of times a tag has transitioned to another state from a previous state. A state transition is counted when the previous good sample is not equal to the state value and the next good sample is equal to state value.

The STATECOUNT calculation mode cannot be used on tags of BLOB data type.

- **Value:** The number of transitions into the state in a given time interval.
- **Quality:** The percent good is 100 if there are no bad samples within the time interval. Otherwise, the percent good is the percent of interval time that the value was of good quality.
- **Anticipated usage:** The STATECOUNT calculation mode is useful to determine the number of times a value transitioned to a certain state such as when a digital state was turned on or the enumerated value was of certain value. It should mostly be used with integer values because it may not exactly match a float state value due to rounding.

STATETIME Calculation Mode: The STATETIME calculation mode retrieves the duration that a tag was in a given state within an interval.

- **Value:** The STATETIME calculation mode retrieves the total number of milliseconds during the interval for which the data was in the state value.
- **Quality:**

The percent good is 100 if the data is good quality for the entire the time interval.

Import this data to use in the examples.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
STATECOUNTTAG,SingleInteger,60,0
STATEBADTAG,SingleInteger,60,0
STATEBADTAG2,SingleInteger,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
STATECOUNTTAG,06-Aug-2012 8:59:00.000,2,Good
STATECOUNTTAG,06-Aug-2012 9:08:00.000,4,Good
STATECOUNTTAG,06-Aug-2012 9:14:00.000,4,Good
STATECOUNTTAG,06-Aug-2012 9:22:00.000,2,Good
STATEBADTAG,06-Aug-2012 8:59:00.000,2,Good
STATEBADTAG,06-Aug-2012 9:08:00.000,0,Bad
STATEBADTAG,06-Aug-2012 9:14:00.000,2,Good
STATEBADTAG,06-Aug-2012 9:22:00.000,4,Good
STATEBADTAG2,06-Aug-2012 8:59:00.000,2,Good
STATEBADTAG2,06-Aug-2012 9:08:00.000,0,Bad
```

```
STATEBADTAG2,06-Aug-2012 9:14:00.000,4,Good
```

```
STATEBADTAG2,06-Aug-2012 9:22:00.000,2,Good
```

- **Anticipated usage:** The STATETIME calculation mode is useful to determine the duration the tag was in a particular state. For example, if a tag records the state of a motor you can use state count to determine the duration a motor was in **idle** state.

OPCQOR and OPCQAND Calculation Modes:

The OPCQOR calculation mode is a bit-wise OR operation of all the 16 bit OPC qualities of the raw samples stored in the specified interval. This calculation mode can be used only if you have set the "Store OPC Quality" to "Enabled" in Historian Administrator and your data is coming from an OPC Collector.

The OPCQAND calculation mode is a bit wise AND operation of all the 16 bit OPC qualities of the raw samples stored in the specified interval. This calculation mode can be used only if you have set the "Store OPC Quality" to Enabled in Historian Administrator and your data is coming from an OPC Collector.

When collecting data from OPC servers, the Historian OPC collector will convert the 16 bits of OPC quality to a Historian quality and subquality. When "Store OPC Quality" is enabled, the 16 bits are also stored with the data and can be retrieved here.

Use the returned value from OPCQOR like a data quality. By using OPCQOR and OPCQAND values, you can see if a condition occurred during an interval and therefore know how trustworthy your returned data is.

- **Value:** The 16 bits are in the following format: VVVVVVVVQQSSSSSS

The first 16 bits are for vendor to fill in. The next two are the actual quality, good, bad,uncertain.

The rest of the bits are subquality.

- OPC good is a decimal 192 which is binary 0000000011000000.
- OPC bad is all zeros 0000000000000000.

- **Quality:** The percent good is 100 if all the samples have good Historian quality. The Historian quality is based on the OPC quality but both the qualities are not the same.

- **Anticipated usage:**

The OPCQOR and OPCQAND calculation modes are useful if you want to the know the quality of your samples between a time interval. For example,if you want to know how many of your samples from 3pm to 4pm had the following quality:

- All good - If you do an OPCAND from 3 P.M. to 4 P.M and get the result as 0000000011000000 which is 192 decimal, it means that the value was good for the whole time.
- All bad - If OPCOR returns 0, then the data was bad the whole time.
- Some bad - If you do a OPCOR and get the result as 0000000011000000 which is 192 decimal, it means that there were at least some good values. If you do an OPCAND and get the result as 0000000000000000, it means that at least some data was bad.

TagStats Calculation Mode: The TagStats calculation mode returns multiple values for a tag in a single query. The TagStats calculation mode returns the values by appending the calculation mode to the tagname. For example, when you query `tag1` the result will be `tag1.Min` which is the result of the minimum calculation mode and `tag1.Max`, the result of the maximum calculation mode. The calculation mode is appended to the tagname.

- **Value:** A query will return multiple values for the same timestamp. They are the results of each individual calculation mode. For more information on different Calculation Modes, refer to the corresponding sections
- **Quality:** There is no single overall quality for the query, only a quality per calculation mode.

Calculating the state count of good quality data

This example shows a simple case of counting state transitions. In this example, the value 4 means that a machine is running so we want to count the number of times the tag transitioned from some other value to 4.

Import the following data.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
STATECOUNTTAG,SingleInteger,60,0
STATEBADTAG,SingleInteger,60,0
STATEBADTAG2,SingleInteger,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
STATECOUNTTAG,06-Aug-2012 8:59:00.000,2,Good
STATECOUNTTAG,06-Aug-2012 9:08:00.000,4,Good
STATECOUNTTAG,06-Aug-2012 9:14:00.000,4,Good
STATECOUNTTAG,06-Aug-2012 9:22:00.000,2,Good
STATEBADTAG,06-Aug-2012 8:59:00.000,2,Good
```

```
STATEBADTAG,06-Aug-2012 9:08:00.000,0,Bad
STATEBADTAG,06-Aug-2012 9:14:00.000,2,Good
STATEBADTAG,06-Aug-2012 9:22:00.000,4,Good
STATEBADTAG2,06-Aug-2012 8:59:00.000,2,Good
STATEBADTAG2,06-Aug-2012 9:08:00.000,0,Bad
STATEBADTAG2,06-Aug-2012 9:14:00.000,4,Good
STATEBADTAG2,06-Aug-2012 9:22:00.000,2,Good
```

Execute the following query in Historian Interactive SQL:

```
set starttime='08/06/2012 8:00:00',endtime='08/06/2012 10:00:00'

select timestamp,value,quality from ihrawdata where tagname = STATECOUNTTAG and samplingmode=Calculation and
CalculationMode=StateCount and IntervalMilliseconds=20m and statevalue=4
```

The following results are returned:

Time Stamp	Value	Quality
8/6/2012 08:20:00	0.000000000000	0.0000000
8/6/2012 08:40:00	0.000000000000	0.0000000
8/6/2012 09:00:00	0.000000000000	5.0000000
8/6/2012 09:40:00	1.000000000000	100.0000000
8/6/2012 09:40:00	0.000000000000	100.0000000
8/6/2012 10:00:00	0.000000000000	100.0000000

Note that the transition from 2 to 4 (machine started running) happened at 9:08, so it is included in the 9:00 to 9:20 interval.

The data was of bad quality until 8:59:00 which is for 1 minute of the 20 minute interval. The percent good for that interval is 5.

There are two samples with the value 4. We do not count the number of times the statevalue occurred, but the number of transitions from some other value to the state value.

We only count transitions into the state value not out of the state value. So, the transition from 4 to 2 is not counted.

Calculating the state count of bad quality data

Note that this tag had a bad data sample when the collector was restarted. This does not, however, affect the state count.

Run the following query:

```
set starttime='08/06/2012 8:00:00',endtime='08/06/2012 10:00:00'

select timestamp,value,quality from ihrawdata where tagname = STATEBADTAG and samplingmode=Calculation and
CalculationMode=StateCount and IntervalMilliseconds=20m and statevalue=4
```

The following results are returned:

Time Stamp	Value	Quality
8/6/2012 08:20:00	0.000000000000	0.0000000
8/6/2012 08:40:00	0.000000000000	0.0000000
8/6/2012 09:00:00	0.000000000000	5.0000000
8/6/2012 09:20:00	0.000000000000	70.0000000
8/6/2012 09:40:00	1.000000000000	100.0000000
8/6/2012 10:00:00	0.000000000000	100.0000000

Note that the bad value is ignored and the state change that happened at 9:22 is counted. We do not know if the machine had started and stopped while the collector was shutdown.

If the value did change to running while the collector was shut down then that change is counted as in shown in the following example:

```
set starttime='08/06/2012 8:00:00',endtime='08/06/2012 10:00:00'

select timestamp,value,quality from ihrawdata where tagname = STATEBADTAG2 and samplingmode=Calculation and
CalculationMode=StateCount and IntervalMilliseconds=20m and statevalue=4
```

Time Stamp	Value	Quality
8/6/2012 08:20:00	0.000000000000	0.0000000
8/6/2012 08:40:00	0.000000000000	0.0000000
8/6/2012 09:00:00	0.000000000000	5.0000000
8/6/2012 09:20:00	1.000000000000	70.0000000

Time Stamp	Value	Quality
8/6/2012 09:40:00	0.000000000000	100.0000000
8/6/2012 10:00:00	0.000000000000	100.0000000



Note:

The state change at 9:14 is counted and returned in the 9:20 interval.

Calculating the state count of enumerated set data

When querying a tag that uses enumerated sets, use the string state name as the state value.

Using the data from previous example, assume that the STATECOUNTTAG had an enumerated set with the values as 2=Stopped and 4=Running.

You should use this query with statevalue of Running instead of the native value 4.

```
set starttime='08/06/2012 8:00:00',endtime='08/06/2012 10:00:00'

select timestamp,value,quality from ihrawdata where tagname = STATECOUNTTAG and samplingmode=Calculation and
CalculationMode=StateCount and IntervalMilliseconds=20m and statevalue='Running'
```

The results match with the results when statevalue=4 is used.

Time Stamp	Value	Quality
8/6/2012 08:20:00	0.000000000000	0.0000000
8/6/2012 08:40:00	0.000000000000	0.0000000
8/6/2012 09:00:00	0.000000000000	5.0000000
8/6/2012 09:20:00	1.000000000000	100.0000000
8/6/2012 09:40:00	0.000000000000	100.0000000
8/6/2012 10:00:00	0.000000000000	100.0000000

Calculating the state time of good quality data

Run this query in the Historian Interactive SQL:

```
set starttime='08/06/2012 8:00:00',endtime='08/06/2012 10:00:00'

select timestamp,value,quality from ihrawdata where tagname = STATECOUNTTAG and samplingmode=Calculation and
CalculationMode=StateTime and IntervalMilliseconds=20m and statevalue=4
```

The following results are returned:

Time Stamp	Value	Quality
8/6/2012 08:20:00	0.000000000000	0.0000000
8/6/2012 08:40:00	0.000000000000	0.0000000
8/6/2012 09:00:00	0.000000000000	5.0000000
8/6/2012 09:20:00	720,000.000000000000	100.0000000
8/6/2012 09:40:00	120,0.000000000000	100.0000000
8/6/2012 10:00:00	0.000000000000	100.0000000

A 20 minute interval is $20 \times 60 \times 1000 = 1200000$ milliseconds. In the 9:00 to 9:20 interval the value was in state 4 from 9:08 to 9:20 which is 12 minutes * 60 * 1000 = 720000 milliseconds.

In the 9:20 to 9:40 interval the value was in state 4 from 9:20 to 9:22 which is $2 \times 60 \times 1000 = 120000$ milliseconds.

Calculating the state time of bad quality data

This tag has a bad data sample such as when the collector was restarted. A new value is recorded when the collector is started.

```
set starttime='08/06/2012 8:00:00',endtime='08/06/2012 10:00:00'

select timestamp,value,quality from ihrefdata where tagname = STATEBADTAG2 and samplingmode=Calculation and
CalculationMode=StateTime and IntervalMilliseconds=20m and statevalue=4

Tagname,TimeStamp,Value,DataQuality
STATEBADTAG2,06-Aug-2012 8:59:00.000,2,Good
STATEBADTAG2,06-Aug-2012 9:08:00.000,0,Bad
STATEBADTAG2,06-Aug-2012 9:14:00.000,4,Good
STATEBADTAG2,06-Aug-2012 9:22:00.000,2,Good
```

The following results are returned:

Time Stamp	Value	Quality
8/6/2012 08:20:00	0.000000000000	0.0000000
8/6/2012 08:40:00	0.000000000000	0.0000000

Time Stamp	Value	Quality
8/6/2012 09:00:00	0.000000000000	5.0000000
8/6/2012 09:20:00	360,000.000000000000	70.0000000
8/6/2012 09:40:00	120,000.000000000000	100.0000000
8/6/2012 10:00:00	0.000000000000	100.0000000

In the interval between 9:00 to 9:20, the value was in state 4 from 9:14 to 9:20 = 6 minutes * 60 * 1000 = 360000 milliseconds.

In the interval between 9:20 to 9:40, the value was in state 4 from 9:20 to 9:22 = 2 minutes * 60 * 1000 = 120000 milliseconds.

Calculating the OPCQOR

The following is the data set used to run the query on.

```

TagName, Timestamp, Value
DATA1:Bad-0 OPC-(60)(08/09/12 18:00:01.000),Val=10
DATA2:Bad-0 OPC-(59)(08/09/12 18:00:02.000),Val=10
DATA3:Bad-0 OPC-(58)(08/09/12 18:00:03.000),Val=10
DATA4:Bad-0 OPC-(57)(08/09/12 18:00:04.000),Val=10
DATA5:Bad-0 OPC-(56)(08/09/12 18:00:05.000),Val=10
DATA6:Bad-0 OPC-(55)(08/09/12 18:00:06.000),Val=10
DATA7:Bad-0 OPC-(54)(08/09/12 18:00:07.000),Val=10
DATA8:Bad-0 OPC-(53)(08/09/12 18:00:08.000),Val=10
DATA9:Bad-0 OPC-(52)(08/09/12 18:00:09.000),Val=10
DATA10:Bad-0 OPC-(51)(08/09/12 18:00:10.000),Val=10
DATA11:Bad-0 OPC-(50)(08/09/12 18:00:11.000),Val=10
    
```

The following query retrieves the OPCQOR data with a start time of 18:00:00 and end time of 18:00:10 with a 2 second time interval.

```

set starttime='08/09/2012 18:00:00',endtime='08/09/2012 18:00:10'

select tagname,timestamp,value,Quality from ihrawdata where tagname like OPCQualityDataTag and samplingmode=Calculated
and calculationmode=OPCQOR and IntervalMilliseconds=2S
    
```

The following output is retrieved.

Tag Name	Time Stamp	Value	Quality
OPCQualityDataTag	8/9/2012 18:00:02	63.0000000000000	50.0000000
OPCQualityDataTag	8/9/2012 18:00:04	59.0000000000000	100.0000000
OPCQualityDataTag	8/9/2012 18:00:06	63.0000000000000	100.0000000
OPCQualityDataTag	8/9/2012 18:00:08	55.0000000000000	100.0000000
OPCQualityDataTag	8/9/2012 18:00:10	55.0000000000000	100.0000000

Calculating the OPCQAND

The following query retrieves the OPCQAND data with a start time of 18:00:00 and end time of 18:00:10 with a 2 second time interval.

```
set starttime='08/09/2012 18:00:00',endtime='08/09/2012 18:00:10'

select tagname,timestamp,value,Quality,opcquality from ihrawdata where tagname like OPCQualityDataTag and
samplingmode=Calculated and calculationmode=OPCQAND and IntervalMilliseconds=2S
```

The following output is retrieved.

Tag Name	Time Stamp	Value	Quality
OPCQualityDataTag	8/9/2012 18:00:02	50.0000000	0
OPCQualityDataTag	8/9/2012 18:00:04	100.0000000	0
OPCQualityDataTag	8/9/2012 18:00:06	100.0000000	0
OPCQualityDataTag	8/9/2012 18:00:	100.0000000	0
OPCQualityDataTag	8/9/2012 18:00:10	100.0000000	0

Using TagStats Calculation Mode

This image displays the TagStats calculation mode example in the Proficy Historian Interactive SQL Application.

In this example we perform the calculations for a single interval by giving `numberofsamples=1`.

```



set starttime='07-05-2011 16:00:00', endtime='07-05-2011 21:00:00'
select tagname,timestamp,value,quality from ihrawdata where tagname like 'Tag1' and
samplingMode=Calculated and CalculationMode=TagStats and numberofsamples = 1
    
```

	tagname	timestamp	value	quality
1	Tag1.MIN	7/5/2011 21:00:00	29.549999237061	100.0000000
2	Tag1.MAX	7/5/2011 21:00:00	30.000000000000	100.0000000
3	Tag1.COUNT	7/5/2011 21:00:00	7.000000000000	100.0000000
4	Tag1.MINTIME	7/5/2011 21:00:00	7/5/2011 17:26:00	100.0000000
5	Tag1.MAXTIME	7/5/2011 21:00:00	7/5/2011 18:19:00	100.0000000
6	Tag1.RAWSTDEV	7/5/2011 21:00:00	0.192167984773	100.0000000
7	Tag1.RAWAVG	7/5/2011 21:00:00	29.774285452707	100.0000000
8	Tag1.RAWTOT	7/5/2011 21:00:00	208.419998168945	100.0000000
9	Tag1.AVG	7/5/2011 21:00:00	29.774285452707	2.3333330
10	Tag1.TIMEGOOD	7/5/2011 21:00:00	420,000.000000000000	100.0000000
11	Tag1.TOT	7/5/2011 21:00:00	6.202976135981	2.3333330
12	Tag1.STDEV	7/5/2011 21:00:00	0.105273135692	2.3333330
13	Tag1.STATECNT	7/5/2011 21:00:00	0.000000000000	2.3333330
14	Tag1.STATETIME	7/5/2011 21:00:00	0.000000000000	2.3333330
15	Tag1.OPCQAND	7/5/2011 21:00:00	0.000000000000	0.0000000
16	Tag1.OPCQOR	7/5/2011 21:00:00	0.000000000000	0.0000000
17	Tag1.FIRSTRAWVALUE	7/5/2011 21:00:00	29.6000000	100.0000000
18	Tag1.FIRSTRAWTIME	7/5/2011 21:00:00	7/5/2011 17:25:00	100.0000000
19	Tag1.LASTRAWVALUE	7/5/2011 21:00:00	29.8400000	100.0000000
20	Tag1.LASTRAWTIME	7/5/2011 21:00:00	7/5/2011 18:22:00	100.0000000

Query Completed in 0 seconds 5/14/2013 6:28 PM

StepValue Tag Property

Retrieval generally does not take into account how a value changes. When retrieving data from the archive, Historian will attempt to interpolate it, which may result in an inaccurate representation of the data's real world changes, such as that shown in the following figure.



In order for Historian to know that a tag did not ramp down between reported values, the StepValue tag property must be applied. This tag property is used to indicate that the value in the real world changes in a sharp step instead of a smooth linear interpolation. An example would be a digital signal that quickly goes 0 to 1. Or, a flow rate that goes 5 to 25 when an upstream valve is opened.



Note:

The StepValue tag property only affects retrieval of Average values in Historian. It does not affect data collection or storage.

Example: Reporting Step Change

Copy and paste the following into an empty CSV file and import the file with the File collector.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
TAG1,SingleFloat,100,0

[Data]
Tagname,TimeStamp,Value,DataQuality
tag1,9/19/05 05:15:00,26.41,Good
tag1,9/19/05 06:15:00,26.45,Good
tag1,9/19/05 07:15:00,26.59,Good
tag1,9/19/05 08:15:00,26.58,Good
tag1,9/19/05 09:15:00,26.36,Good
tag1,9/19/05 10:15:00,10.74,Good
tag1,9/19/05 11:15:00,11.00,Good
tag1,9/19/05 12:15:00,10.94,Good
tag1,9/19/05 13:15:00,11.03,Good
```

Set the StepValue=TRUE in Historian Administrator. Then, use the following query to retrieve data using Average with a 15 minute interval.

```
select * from ihrawdata where tagname=TAG1 and timestamp > '9/19/05 09:30:00'
and timestamp <= '9/19/05 11:30:00' and calculationmode=average and
intervalmilliseconds=15m
```

You will see the following results, which show two distinct steps:

Value	Quality
09:45:00	26.36
10:00:00	26.36
10:15:00	26.36

Value	Quality
10:30:00	10.74
10:45:00	10.74
11:00:00	10.74
11:15:00	10.74
11:30:00	11.00

If you set the `StepValue=FALSE` and run the same query, you will see the following results, which reflect interpolated values.

Value	Quality
09:45:00	22.46
10:00:00	18.55
10:15:00	14.64
10:30:00	10.74
10:45:00	10.80
11:00:00	10.87
11:15:00	10.93
11:30:00	11.00

Example: No raw sample at start time

Copy and paste these lines into an empty CSV file and import the file with the File collector

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits,StepValue
TAG2,SingleFloat,100,0,TRUE

[Data]
Tagname,TimeStamp,Value,DataQuality
TAG2,9/19/05 13:59:00.000,22,Good
TAG2,9/19/05 14:08:00.000,12,Good
TAG2,9/19/05 14:22:00.000,4,Good
```

Use the following query to retrieve the data using Average with a 30 minute interval

```
select * from ihrawdata where tagname=tag2 and timestamp >
'9/19/05 14:00:00' and timestamp <= '9/19/05 14:30:00' and
calculationmode=average and intervalmilliseconds=30m
```

You will see the following results.

Time Stamp	Value	Quality
14:30:00	12.53	100.00

The following table is another way to look at the data as values and durations.

Point	Value	Duration (Seconds)
Point 1	22.00	480 (lab sampled at start)
Point 3	12	1320
Point 4	4	480

The step value average would be:

$$((22.00 * 480) + (12 * 840) + (4 * 480)) / (480 + 840 + 480) = 12.53$$

The percent good is 100 since it was good the whole time.

The interpolated average is 12.24 because the first sample is different.

Point	Value	Duration (Seconds)
Point 1	20.88	480 (lab sampled at start)
Point 3	12	1320
Point 4	4	480

The lab average would be:

$$((20.88 * 480) + (12 * 840) + (4 * 480)) / (480 + 840 + 480) = 12.24$$

Example: Raw sample at end time

The point of this example is that if you have a raw sample on the interval end time then it is ignored because of the time weighting.

Copy and paste these lines into an empty CSV file and import the file with the File collector.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits,StepValue
TAG5,SingleFloat,100,0,TRUE

[Data]
Tagname,TimeStamp,Value,DataQuality
TAG5,9/19/05 13:10:00.000,22,Good
TAG5,9/19/05 14:18:00.000,12,Good
TAG5,9/19/05 14:30:00.000,1,Good
```

Use the following query to retrieve the data using Average with a 30 minute interval.

```
select * from ihrawdata where tagname=tag5 and timestamp >
'9/19/05 14:00:00' and timestamp <= '9/19/05 14:30:00' and
calculationmode=average and intervalmilliseconds=30m
```

You will see the following results.

Time Stamp	Value
14:30:0	18.00

See that the last raw sample is ignored

Point	Value	Duration (Seconds)
Point 1	22.00	1080 (lab sampled at start)
Point 3	12.00	720
Point 4	1.00	0

The lab sampled average is:

```
((22.00 * 1080) + (12 * 720) + (1 * 0)) / (1080 + 720) = 18.0
```

- The interpolated average gives 13.59 because of the different interpolated value at interval start.
- The percent good is 100 since it was good the whole time.

Example: No raw samples in interval

This case shows the biggest difference between averages of step value and non step value tags. In this case we lab sample a value at the start time and that is the average.

Copy and paste these lines into an empty CSV file and import the file with the File collector.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits,StepValue
TAG4,SingleFloat,100,0,TRUE

[Data]
Tagname,TimeStamp,Value,DataQuality
TAG4,9/19/05 13:55:00.000,99,Good
TAG4,9/19/05 14:40:00.000,10,Good
```

Use the following query to retrieve the data using Average.

```
select * from ihrawdata where tagname=tag4 and timestamp >
'9/19/05 14:00:00' and timestamp <= '9/19/05 14:30:00' and
calculationmode=average and intervalmilliseconds=30m
```

You will see the following results.

Time Stamp	Value	Quality
14:30:00	99	100



Note:

The single lab sampled value at interval start time is the average.

Retrieving the data when StepValue=FALSE gives the following:

Time Stamp	Value	Quality
14:30:00	89.11	100



Note:

The single interpolated sample at interval start time is the average of the interval.

Comment Retrieval Mode

The Comment Retrieval Mode returns any comments or annotations that have been stored with the data between the start time and end time of the query.

However, some Sampling and Calculation modes use raw samples beyond the start and end time to interpolate a value. An average will interpolate a value at the start of each interval and this will likely use raw samples outside the interval.

To retrieve the comments from raw values that were used beyond the interval, you can define a registry key on a computer running the Data Archiver.

Create a DWORD value under:

```
HKEY_LOCAL_MACHINE\Software\Intellution, Inc.\iHistorian\Services\DataArchiver
```

- If you have the Data Archiver installed, the registry key should already exist and you are just adding a DWORD value.
- Set `CommentRetrievalMode` to 1.

**Note:**

- You do not have to restart the Archiver for the changes to the registry to take place. The changes to registry setting take effect immediately
- Raw data queries are not affected with this change.
- Any application can be used to query the data
- The Comment Retrieval Mode may result in many comments being returned for a query. Therefore, it is not recommended for users who want to plot the data via the Proficy Real Time Information Portal (RTIP) Chart as it may cause slower performance.

Query Modifiers

Query Modifiers are used for retrieving data that has been stored in the archive. They are used along with sampling and calculation modes to get a specific set of data. The following sections describe the Query Modifiers in **Historian**.

- **ONLYGOOD**

The ONLYGOOD modifier excludes bad and uncertain data quality values from retrieval and calculations. Use this modifier with any sampling or calculation mode but it is most useful with Raw and CurrentValue queries.

All the calculation modes such as minimum or average exclude bad values by default, so this modifier is not required with those.

Example 1: Demonstrating the Behavior

Import the following data to demonstrate the behavior of ONLYGOOD

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
BADDQTAG,SingleFloat,60,0

[Data]
Tagname,TimeStamp,Value, DataQuality
BADDQTAG,12-Jul-2012 8:59:00.000,22.7,Good
BADDQTAG,12-Jul-2012 9:08:00.000,12.5,Bad
BADDQTAG,12-Jul-2012 9:14:00.000,7.0,Bad
BADDQTAG,12-Jul-2012 9:22:00.000,4.8,Good
```

Example 2: Excluding bad data from raw data query

Without any query modifier, all raw samples are returned from a RawByTime query.

```
select timestamp,value,quality
from ihrawdata
where tagname = BADDQTAG and samplingmode=Rawbytime and timestamp < now
```

Time Stamp	Value	Quality
7/12/2012 08:59:00	22.7000000	Good, NonSpecific
7/12/2012 09:08:00	12.5000000	Bad, NonSpecific
7/12/2012 09:14:00	7.0000000	Bad, NonSpecific
7/12/2012 09:22:00	4.8000000	Good, NonSpecific



Note:

The above results have both good and bad samples:

Now by using the ONLYGOOD modifier, you can exclude the bad quality values:

```
select timestamp,value,quality
from ihrawdata
where tagname = BADDQTAG and samplingmode=Rawbytime and timestamp < now and
criteriastring="#ONLYGOOD"
timestamp          value          quality
```

Time Stamp	Value	Quality
7/12/2012 08:59:00	22.7000000	Good, NonSpecific
7/12/2012 09:22:00	4.8000000	Good, NonSpecific

**Note:**

Only the good samples have been retrieved.

Example 3: Retrieving the last known value**Value**

You can use the ONLYGOOD query modifier to show the last known good value for a tag. If the collector loses communication with the data source or has shut down, you can ignore the bad data that is logged.

The following examples demonstrate the ways to retrieve the last known values:

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnit
EXAMPLETAG,SingleInteger,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
EXAMPLETAG,06-Aug-2012 8:59:00.000,2,Good
EXAMPLETAG,06-Aug-2012 9:02:00.000,0,Bad
```

Without any query modifier, the newest raw sample is returned in a current value query as retrieved with the following query.

```
select timestamp,value,quality
from ihrawdata
where tagname = EXAMPLETAG and samplingmode=CurrentValue
```

Time Stamp	Value	Quality
8/6/2012 09:02:00	Bad	NonSpecific

The bad data could be a communication error or collector shutdown marker

When the ONLYGOOD modifier is used, the bad quality value is ignored and last known good value is returned as per the query here.

```
select timestamp,value,quality
from ihrawdata
where tagname = EXAMPLETAG and samplingmode=CurrentValue and
criteriastring="#ONLYGOOD"
```



Note:

Only the Good value has been retrieved as following. timestamp value quality.

Time Stamp	Value	Quality
8/6/201208:59:00	2 Good	NonSpecific

Anticipated Usage

You can use the ONLYGOOD modifier to exclude end of collection markers but understand that it excludes all bad data, even communication errors, and out of range errors.

If you want to bring data into Microsoft Excel for further analysis, you can use ONLYGOOD so that good values are brought into a spreadsheet.

• INCLUDEREPLACED

Normally, when you query raw data from Historian, any values that have been replaced with a different value for the same timestamp are not returned. The INCLUDEREPLACED modifier helps you to indicate that you want replaced values to be returned, in addition to the currently retrievable data. However, you cannot query only the replaced data and the retrievable values that have replaced. You can query all currently visible data and get the data that has been replaced.

This modifier is only useful with rawbytime or rawbynumber retrieval. Do not use it with any other sampling or calculation mode.

Example

Import this data to demonstrate the behavior of the INCLUDEDLETED query modifier.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
DELETEDDATA,SingleInteger,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
DELETEDDATA,06-Aug-2012 9:01:00.000,1,Good
DELETEDDATA,06-Aug-2012 9:02:00.000,2,Good
DELETEDDATA,06-Aug-2012 9:04:00.000,4,Good
```

Delete the raw sample at 9:02 and query the raw data without any modifier and you will get only the non-deleted values.

Run the following query:

```
select timestamp,value,quality
from ihrawdata
where tagname = DELETEDDATA and samplingmode=RawByTime and timestamp < now
```

Time Stamp	Value	Quality
8/6/2012 09:01:00	1	Good NonSpecific
8/6/2012 09:04:00	4	Good NonSpecific

Query with the INCLUDEDELETED modifier and you will get the deleted sample together with the non-deleted data.

```
select timestamp,value,quality
from ihrawdata
where tagname = DELETEDDATA and samplingmode=RawByTime and timestamp < now and
criteriastring="#INCLUDEDELETED"
```

Time Stamp	Value	Quality
8/6/2012 09:01:00	1 Good	NonSpecific
8/6/2012 09:02:00	2 Good	NonSpecific
8/6/2012 09:04:00	4 Good	NonSpecific

Anticipated Usage

The INCLUDEDELETED modifier can be used to detect and recover deleted data. Perform a query without the modifier and with the modifier and compare the results. You will detect the deleted samples. You can also determine the deleted samples with a User API program.

ONLYIFCONNECTED and ONLYIFUPTODATE

The ONLYIFCONNECTED and ONLYIFUPTODATE modifiers can be used on any sampling or calculation mode to retrieve bad data if the collector is not currently connected and sending data to the archiver. The bad data is not stored in the IHA file but is only returned in the query. If the collector reconnects and flushes data and you run the query again, the actual stored data is returned in the following situations:

- Collector loses connection to the Archiver
- Collector crashes
- Collector compression is used and no value exceeds the deadband

Any data query will return the last known value repeated till the current time with the quality of data as good. But the information could have changed in the real world and has yet to reach the archiver.

Repeating the last known good value data can be misleading. Data should be returned as bad quality if no data is coming in from a collector.

The Data Archiver keeps track of the newest raw sample received for any tag for each collector. If no data is received for any tag, the collector is considered to be idle. If the collector is idle for more than 270 seconds, then either the data is heavily compressed or the collector is crashed or has lost connection. The collector idle time defaults to 270 seconds and this current setting appears in the *dataarchiver.shw* file. You can change the value using an SDK program. The setting applies to all collectors.

Use the ONLYIFUPTODATE modifier to return bad data from the time of the newest raw sample to the current time. However, if there is an unlikely chance that all tags are heavily compressed, then use the ONLYIFCONNECTED modifier. The difference in the behavior of the two modifiers is given in the following examples:

When you add an ONLYIFCONNECTED or ONLYIFUPTODATE modifier to the query, and the collector is disconnected from the archiver, bad values are returned from the time of the disconnect until the current time. Queries of data before the disconnect time are unaffected.

**Note:**

- The ONLYIFCONNECTED and ONLYIFUPTODATE modifiers are applicable to tags that are collected by data collectors.
- For raw by number, if the number of samples collected are greater or equal to the number of samples, bad data quality is not added.
- For raw by time, if the endtime is less than maximum data received time, bad data quality is not added.
- For raw by number backward, bad data quality is added at the beginning.

Example 1: Using ONLYIFCONNECTED to detect connection loss

To demonstrate the behavior of ONLYIFCONNECTED, you need to query data currently being collected.

1. Configure the Simulation collector to collect any tag once per second with no compression. For example, collect the simulation RAMP tag.
2. Let the collector run for at least 5 minutes of collection.
3. Disconnect the collector but leave it running. In this test, the collector was disconnected at 20:55:00.
4. After about 5 minutes, query the data without ONLYIFCONNECTED and the last known value repeated with good quality to the current time, even though the collector is not connected.

```
set starttime='22-Aug-2012 20:53:00',endtime='now'

select timestamp,value,quality

from ihrawdata

where tagname = RAMP and samplingmode=Interpolated and intervalmilliseconds=5s order by

timestamp asc
```

Time Stamp	Value	Quality
8/22/2012 20:54:55	166.6666666666667	100.0000000
8/22/2012 20:55:00	0.0000000000000	100.0000000
8/22/2012 20:55:05	166.6666666666667	100.0000000
8/22/2012 20:55:10	333.3333333333333	100.0000000

Time Stamp	Value	Quality
8/22/2012 20:55:15	500.000000000000	100.0000000
8/22/2012 20:55:20	533.333333333333	100.0000000
8/22/2012 20:55:25	533.333333333333	100.0000000
8/22/2012 20:55:30	533.333333333333	100.0000000
8/22/2012 20:55:35	533.333333333333	100.0000000

5. Run the query again with ONLYIFCONNECTED and the data is marked bad at the time of the collector disconnect:

```
set starttime='22-Aug-2012 20:53:00',endtime='now'

select timestamp,value,quality

from ihrawdata

where tagname = RAMP and samplingmode=Interpolated and intervalmilliseconds=5s and

criteriastring=#onlyifconnect
```

Time Stamp	Value	Quality
8/22/2012 20:54:55	166.666666666667	100.0000000
8/22/2012 20:55:00	0.000000000000	100.0000000
8/22/2012 20:55:05	166.666666666667	100.0000000
8/22/2012 20:55:10	333.333333333333	100.0000000
8/22/2012 20:55:15	500.000000000000	100.0000000
8/22/2012 20:55:20	0.000000000000	0.0000000
8/22/2012 20:55:25	0.000000000000	0.0000000
8/22/2012 20:55:30	0.000000000000	0.0000000
8/22/2012 20:55:35	0.000000000000	0.0000000

6. Reconnect the collector and once the collector reconnects and flushes its buffered data run the query again with ONLYIFCONNECTED and the period of bad data is filled in with ramping values:

Time Stamp	Value	Quality
8/22/2012 20:54:55	166.6666666666667	100.0000000
8/22/2012 20:55:00	0.0000000000000	100.0000000
8/22/2012 20:55:05	166.6666666666667	100.0000000
8/22/2012 20:55:10	333.3333333333333	100.0000000
8/22/2012 20:55:15	500.0000000000000	100.0000000
8/22/2012 20:55:20	569.696969985962	100.0000000
8/22/2012 20:55:25	615.151515960693	100.0000000
8/22/2012 20:55:30	660.606061935425	100.0000000
8/22/2012 20:55:35	706.060606002808	100.0000000

Example 2: Querying Compressed Data

If all tags for a collector are compressed, then the newest raw sample across all tags can easily be older than 270 seconds even when the collector is connected to archiver. It is unlikely in a real system that a collector will send 0 raw samples for 270 seconds, but it is possible.

1. Use the simulation collector and collect the constant tag as 1 second polled with a small deadband such as 1. In the example below, the newest raw sample is at 17:27:31 and the current time is 5 minutes or more.
2. Query the data as interpolated with a 5 second interval and no modifier.

```
set starttime='23-Aug-2012 17:00:30',endtime='now',rowcount=0
select timestamp,value,quality
from ihrawdata
where tagname = CONSTANT and samplingmode=Interpolated and intervalmilliseconds=5s order by
timestamp asc
```

Time Stamp	Value	Quality
8/23/2012 17:27:20	500.0000000000000	100.0000000
8/23/2012 17:27:25	500.0000000000000	100.0000000
8/23/2012 17:27:30	500.0000000000000	100.0000000

Time Stamp	Value	Quality
8/23/2012 17:27:35	0.000000000000	100.0000000
8/23/2012 17:27:40	0.000000000000	100.0000000


Note:
 The newest sample is repeated to the current time

3. Query with ONLYIFCONNECTED and you get the same results even when the newest raw sample is more than 270 seconds old. The data is old but the collector is currently connected.

```

set starttime='23-Aug-2012 17:00:30',endtime='now',rowcount=0

select timestamp,value,quality

from ihrawdata

where tagname = CONSTANT and samplingmode=Interpolated and intervalmilliseconds=5s and

criteriastring=#onlyifcon
    
```

Time Stamp	Value	Quality
8/23/2012 17:27:20	500.000000000000	100.0000000
8/23/2012 17:27:25	500.000000000000	100.0000000
8/23/2012 17:27:30	500.000000000000	100.0000000
8/23/2012 17:27:35	500.000000000000	100.0000000
8/23/2012 17:27:40	500.000000000000	100.0000000

4. Query with ONLYIUPTODATE and the data is considered bad quality after the newest raw sample.

```

set starttime='23-Aug-2012 17:00:30',endtime='now',rowcount=0

select timestamp,value,quality

from ihrawdata

where tagname = CONSTANT and samplingmode=Interpolated and intervalmilliseconds=5s and

criteriastring=#onlyifupt
    
```

Time Stamp	Value	Quality
8/23/2012 17:27:20	500.000000000000	100.0000000

Time Stamp	Value	Quality
8/23/2012 7:27:25	500.000000000000	100.0000000
8/23/2012 7:27:30	500.000000000000	100.0000000
8/23/2012 7:27:35	0.000000000000	0.0000000
8/23/2012 7:27:40	0.000000000000	0.0000000

**Note:**

If your collector can possibly have no data for any tag due to compression, use ONLYIFCONNECTED. Otherwise, if you want to detect data being old due to collector crash or disconnect, then use ONLYIFUPTODATE and optionally adjust the collector idle time.

Anticipated Usage

Use the ONLYIFCONNECTED and ONLYIFUPTODATE modifiers so that your trend lines stop plotting when the collector loses connection.

Use the ONLYIFCONNECTED and ONLYIFUPTODATE modifiers with CurrentValue retrieval so that the current value turns to bad quality if the collector is disconnected. This way you are not misled by looking at an outdated value that does not match the real world.

ONLYRAW

The ONLYRAW modifier retrieves only the raw stored samples. It does not add interpolated or lab sampled values at the beginning of each interval during calculated retrieval such as average or minimum or maximum.

Normally, a data query for minimum value will interpolate a value at the start of each interval and use that together with any raw samples to determine the minimum value in the interval. Interpolation is necessary because some intervals may not have any raw samples stored.

**Note:**

Use the ONLYRAW modifier with Calculation modes only, not with raw or sampled retrieval like interpolated modes.

Example

Import this data to demonstrate the behavior of the ONLYRAW query modifier.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
RAMPUP,SingleFloat,100,0

[Data]
Tagname,TimeStamp,Value,DataQuality
RAMPUP,06-Aug-2012 9:01:00.000,1,Good
RAMPUP,06-Aug-2012 9:02:00.000,2,Good
RAMPUP,06-Aug-2012 9:03:00.000,3,Good
RAMPUP,06-Aug-2012 9:04:00.000,4,Good
RAMPUP,06-Aug-2012 9:05:00.000,5,Good
RAMPUP,06-Aug-2012 9:06:00.000,6,Good
```

When you query the minimum without any modifier, you see that the minimum value may not be one of the stored values.

```
set starttime='06-Aug-2012 09:02:30',endtime='06-Aug-2012 09:05:30'
select timestamp,value,quality
from ihrawdata
where tagname = RAMPUP and samplingmode=Calculated and CalculationMode=minimum and numberofsamples=3
```

Time Stamp	Value	Quality
8/6/2012 09:03:30	2.500000000000	100.0000000
8/6/2012 09:04:30	3.500000000000	100.0000000
8/6/2012 09:05:30	4.500000000000	100.0000000

```
set starttime='06-Aug-2012 09:02:30',endtime='06-Aug-2012 09:05:30'
select timestamp,value,quality
from ihrawdata
where tagname = RAMPUP and samplingmode=Calculated and CalculationMode=minimum and numberofsamples=3
and criteriastring='#onlyraw'
```

Time Stamp	Value	Quality
8/6/2012 09:03:30	3.000000000000	100.0000000
8/6/2012 09:04:30	4.000000000000	100.0000000
8/6/2012 09:05:30	5.000000000000	100.0000000

Anticipated Usage

Use the ONLYRAW modifier to query the minimum and maximum values of stored data samples, similar to the RawAverage Calculation mode. A minimum or maximum of raw samples is more like doing a MIN() or MAX () in an Excel spreadsheet. Realize that if you use the ONLYRAW modifier, there may be intervals with no raw samples. The ONLYRAW modifier is useful for Calculation modes and not the Sampling modes.

LABSAMPLING

The LABSAMPLING modifier affects the calculation modes that interpolate a value at the start of each interval. Instead of using interpolation, lab sampling is used. When querying highly compressed data you may have intervals with no raw samples stored. An average from 2 P.M to 6 P.M on a one hour interval will interpolate a value at 2 P.M., 3 P.M., 4 P.M, and 5 P.M and use those in addition to any stored samples to compute averages. When you specify LABSAMPLING, then lab sampling mode is used instead of interpolated sampling mode to determine the 2 P.M., 3 P.M., 4 P.M., and 5 P.M., values.

A lab sampled average would be used when querying a tag that never ramps but changes in a step pattern such as a state value or setpoint.



Note:

Use the LABSAMPLING modifier with calculation modes only, not raw or sampled retrieval like interpolated modes.

Example

Import this data to demonstrate the behavior of the LABSAMPLING query modifier.

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
RAMPUP,SingleFloat,100,0

[Data]
Tagname,TimeStamp, Value,DataQuality
RAMPUP,06-Aug-2012 9:01:00.000,1,Good
RAMPUP,06-Aug-2012 9:02:00.000,2,Good
RAMPUP,06-Aug-2012 9:03:00.000,3,Good
RAMPUP,06-Aug-2012 9:04:00.000,4,Good
RAMPUP,06-Aug-2012 9:05:00.000,5,Good
RAMPUP,06-Aug-2012 9:06:00.000,6,Good
```

Run this query without a modifier to see the minimum values using the interpolated values:

```
set starttime='06-Aug-2012 09:02:30',endtime='06-Aug-2012 09:05:30'

select timestamp,value,quality

from ihrawdata

where tagname = RAMPUP and samplingmode=Calculated and CalculationMode=minimum and numberofsamples=3
```

Time Stamp	Value	Quality
8/6/2012 09:03:30	2.500000000000	100.0000000
8/6/2012 09:04:30	3.500000000000	100.0000000
8/6/2012 09:05:30	4.500000000000	100.0000000

The returned minimum values are stored values but sampled forward to each interval timestamp. This is the behavior of lab sampling and is applied here to calculated values.

Anticipated Usage

Use the LABSAMPLING modifier to query the minimum, maximum, and average values of tags that change in a step fashion and never ramp. For example, you may want to retrieve the minimum of a set point. This tag would change from one value directly to another without ramping. And the value may not change in a long period. A minimum should not return a value that ramps over a long period of time from one set point value to the next. The LABSAMPLING modifier is useful for Calculation modes and not the Sampling modes.

ENUMNATIVEVALUE

The ENUMNATIVEVALUE modifier retrieves the native, numeric values such as 1 or 2 instead of string values such as on/off for the data that has enumerated states associated with it.



Note:

You can use the ENUMNATIVEVALUE modifier with any sampling or calculation mode.

Example

Import this data to demonstrate the use of ENUMNATIVEVALUE:

```
[Tags]

Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits

STATETAG,SingleInteger,60,0

[Data]
```

```

Tagname,TimeStamp,Value,DataQuality
STATETAG,06-Aug-2012 9:08:00.000,4,Good
STATETAG,06-Aug-2012 9:14:00.000,4,Good
STATETAG,06-Aug-2012 9:22:00.000,2,Good

```

Assume the tag has an enumerated set associated where 2=Stopped and 4=Running. When you do the interpolated query you get the string value:

```

set starttime='06-Aug-2012 09:10:00',endtime='06-Aug-2012 09:30:00'

select timestamp,value,quality

from ihrawdata

where tagname = STATETAG and samplingmode=Interpolated and numberofsamples=6

```

Time Stamp	Value	Quality
8/6/2012 09:13:20	running	100.0000000
8/6/2012 09:16:40	running	100.0000000
8/6/2012 09:20:00	running	100.0000000
8/6/2012 09:23:20	stopped	100.0000000
8/6/2012 09:26:40	stopped	100.0000000
8/6/2012 09:30:00	stopped	100.0000000

Using the ENUMNATIVEVALUE query modifier, you can get the numeric value suitable for plotting

```

set starttime='06-Aug-2012 09:10:00',endtime='06-Aug-2012 09:30:00'

select timestamp,value,quality

from ihrawdata

where tagname = STATETAG and samplingmode=Interpolated and numberofsamples=6 and
criteriastring='#enumnativevalue'

```

Time Stamp	Value	Quality
8/6/2012 09:13:20	4	100.0000000
8/6/2012 09:16:40	4	100.0000000
8/6/2012 09:20:00	4	100.0000000
8/6/2012 09:23:20	2	100.0000000

Time Stamp	Value	Quality
8/6/2012 09:26:40	2	100.0000000
8/6/2012 09:30:00	2	100.0000000

**Note:**

For bad data, the values are returned as string values based on the Enumerated State table though the enumerative value is set to FALSE.

Anticipated Usage

Use the ENUMNATIVEVALUE query modifier to plot tags that use enumerated values. You can put the string value in a data link and put the native value in a chart.

INCLUDEBAD

The INCLUDEBAD modifier directs the Data Archiver to consider raw samples of bad data quality when computing calculation modes. Use INCLUDEBAD modifier to consider both good and bad quality values.

You can use the INCLUDEBAD modifier with any Sampling or Calculation mode only if you want to include bad quality data.

Use the INCLUDEBAD modifier only if you believe the bad quality data has meaningful values and are useful as input to calculations. Most bad data quality values do not have meaningful values; they show 0 or unpredictable numbers. But in some cases, if the data is being written using a user program instead of a collector, you can use this query modifier.

Bad data always has a sub quality such as Comm Error or Configuration Error. When you use the INCLUDEBAD modifier any end of collection raw samples or calculation error raw samples are still ignored because they are not process data, just data markers that are inserted by collectors.

Example

Import this data to demonstrate the behavior of the INCLUDEBAD query modifier:

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
Tag1,SingleFloat,60,0
[Data]
Tagname,TimeStamp,Value,DataQuality
Tag1,07-05-2011 17:24:00,29.72,Bad
```

```
Tag1,07-05-2011 17:25:00,29.6,Good
Tag1,07-05-2011 17:26:00,29.55,Good
Tag1,07-05-2011 17:27:00,29.49,Bad
Tag1,07-05-2011 17:28:00,29.53,Bad
```

**Note:**

The given sample contains three bad quality data.

Run the following query

```
set starttime='07-05-2011 16:00:00', endtime='07-05-2011 21:00:00'
select timestamp,value,quality from ihrawdata where tagname like 'Tag1' and samplingMode=calculated and
CalculationMode=count and Numberofsamples=1
```

Time Stamp	Value	Quality
7/5/201121:00:00	2.000000000000	100.0000000

The count is 2 because only good quality data is considered. If you want to consider bad quality use the INLCUDEBAD query modifier as given in the following example.

```
set starttime='07-05-2011 16:00:00', endtime='07-05-2011 21:00:00'
select timestamp,value,quality from ihrawdata where tagname like 'Tag1' and samplingMode=calculated and
CalculationMode=count and criteriastring="#INCLUDEBAD" and Numberofsamples=1
```

Time Stamp	Value	Quality
7/5/201121:00:00	5.000000000000	100.0000000

**Note:**

When we use INCLUDEBAD query modifier all the values are considered and the count is 5.

Anticipated Usage

The INCLUDEBAD modifier can be used to force the Data Archiver to consider every raw sample collected from a field device while still excluding Proficy Historian collection markers or calculation errors and timeouts.

The INCLUDEBAD modifier is usually used if you are writing data with a custom program and not a collector and your program stores meaningful values with bad quality.

FILTERINCLUDEBAD

The FILTERINCLUDEBAD modifier directs the Data Archiver to consider the values of bad quality data when determining the time ranges that match the filter condition. This modifier is similar to the INCLUDEBAD but that modifier applies to the data tag and this modifier applies to the FilterTag.

You can use the FILTERINCLUDEBAD modifier if you are also using INCLUDEBAD because your application data of bad quality has meaningful values then you can also consider this modifier but, you do not need to use both modifiers at the same time.

Example: Filtered Data Query containing Bad Quality Filter Values

Import this data to demonstrate the behavior of the FILTERINCLUDEBAD query modifier:

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
ExcelTag1,SingleFloat,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
ExcelTag1,07-05-2011 17:24:00,29.72,Bad
ExcelTag1,07-05-2011 17:25:00,29.6,Good
ExcelTag1,07-05-2011 17:26:00,29.55,Good
ExcelTag1,07-05-2011 17:27:00,29.49,Bad
ExcelTag1,07-05-2011 17:28:00,29.53,Bad
```

The given sample contains three bad quality data samples. Run the following query:

```
set starttime='07-05-2011 16:00:00', endtime='07-05-2011 21:00:00'
select timestamp,value,quality from ihrawdata where tagname=ExcelTag1 and samplingMode=Calculated and
calculationmode=rawtotal and FilterExpression ='ExcelTag1>29.5' and numberofsamples=1
```

In this query, we use a filtered expression where the filter condition is ExcelTag1>29.5, and the result is as follows because it adds the two good values to compute the RawTotal:

Time Stamp	Value	Quality
7/5/201121:00:00	59.149999618530	100.0000000

Bad quality data is not considered while filtering. If you want to consider bad quality data then use the FILTERINLCUDEBAD query modifier together with the INCLUDEBAD query modifier as in the following query:

```
set starttime='07-05-2011 16:00:00', endtime='07-05-2011 21:00:00'

select timestamp,value,quality from ihrawdata where tagname=ExcelTag1 and samplingMode=Calculated and
calculationmode=rawtotal and FilterExpression ='ExcelTag1>29.5' and numberofsamples=1 and
CriteriaString='#FilterIncludeBad#IncludeBad'
```

The result is as follows

Time Stamp	Value	Quality
7/5/201121:00:00	118.399999618530	100.0000000



Note:

The value is 118 because all the values that are greater than 29.5 are added together, not just the good quality values.

Anticipated Usage

The FILTERINCLUDEBAD modifier can be used to force the Data Archiver to consider every raw sample collected from a field device when determining the time ranges while still excluding Historian injected end of collection markers or calculation errors and timeouts.

USEMASTERFIELDTIME

The USEMASTERFIELDTIME query modifier is used only for the MultiField tags. It returns the value of all the fields at the same timestamp of the master field time, in each interval returned.

The following are the points to remember while using the USEMASTERFIELDTIME query modifier:

1. In your user defined data type, you have to indicate which field is the master field. You can define a master field when you define the type.
2. When you use the USEMASTERFIELDTIME query modifier, the query returns raw values of all the field elements at the timestamp determined by the MasterField.
3. When you use the USEMASTERFIELDTIME query modifier in Excel Add-in, the percentage good value displayed will be incorrect. It is recommended to use this query modifier using APIs.
4. Only a few calculation modes are supported by the USEMASTERFIELDTIME query modifier. The supported calculation modes are:

- Minimum Value
- Maximum Value
- Minimum Time
- Maximum Time
- FirstRawValue
- FirstRawTime
- LastRawValue
- LastRawTime

The supported modes will examine the raw samples for the master field of a Multi Field tag. For each raw sample in the interval, the minimum or maximum or first or last sample is determined depending on the mode. The timestamp of that raw sample is the master field time.

For example you have a multi-field tag called `mytag` with 3 fields and field3 is the master field.

1. You do a LastRawValue query on `mytag` and pass the USEMASTERFIELDTIME query modifier.
2. The Data Archiver determines the last raw sample for `mytag.field3` between 3pm and 4pm is at 3:42pm. That is the master field time for this interval. Each interval has a master field time.
3. The Data Archiver gets the values for field1 and field2 at 3:42 so now you have a value for all 3 fields at 3:42.



Note:

When there is no raw sample for a field in the given interval then there is no master time for that interval. Most of the calculation modes will then return a 0 Value and Quality Bad for that interval.

Example

Import this data to demonstrate the behavior of the USEMASTERFIELDTIME query modifier.

```
[Data]
Tagname,TimeStamp,Value,DataQuality
MUser1.F1,05-22-2013 14:15:00,4,Good
MUser1.F1,05-22-2013 14:15:01,7,Good
MUser1.F1,05-22-2013 14:15:02,9,Good
MUser1.F2,05-22-2013 14:15:00,241,Good
MUser1.F2,05-22-2013 14:15:01,171,Good
MUser1.F2,05-22-2013 14:15:02,191,Good
```

**Note:**

In this sample the MUser1 tag has two fields F1 and F2 and F2 is marked as the MasterField.

Run the following query:

```
set starttime = '5/22/2013 14:15:00', endtime = '5/22/2013 14:15:02'

select tagname, timestamp, value, quality from iohrawdata where tagname = 'MUser1' and

samplingmode = calculated and calculationmode = minimum and

criteriastring = '#USEMASTERFIELDTIME' and numberofsamples = 1
```

The output is as follows:

Tag Name	Time Stamp	Value	Quality
MUser1.F1	05-22-201314:15:02	7	0.0000000
MUser1.F2	05-22-201314:15:02	171.000000000000	100.0000000

Here the minimum value for the Master Field tag F2 is 171 at 14:15:01 timestamp. That is the master time. Then the master time is used to get the value of F1 at the same timestamp which is 7 and this is returned even as the minimum value of F1 is 4.

In a multi field tag it is possible that some fields may be NULL at a given timestamp. In this case if F1 was a NULL value at 14:15:01 you would get a value of null and bad quality.

HONORENDTIME

Normally, a query keeps searching through archives until the desired number of samples has been located, or until it gets to the first or last archive. However, there are cases where you would want to specify a time limit as well. For example, you may want to output the returned data for a RawByNumber query in a trend page, in which case there is no need to return data that would be off page.

In cases where you want to specify a time limit, you can do this by specifying an end time in your RawByNumber query and including the HONORENDTIME query modifier. Since RawByNumber has direction (backwards or forwards), the end time must be older than the start time for a backwards direction or newer than the start time for a forwards direction.

**Note:**

Use the HONORENDTIME modifier only with the RawByNumber sampling mode.

Example using HONORENDTIME with RawByNumber Sampling Mode

Import this data to Historian:

```
[Tags]
Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits
TAG1,SingleInteger,60,0

[Data]
Tagname,TimeStamp,Value,DataQuality
TAG1,09/18/2015 14:00:00.000,00,Good
TAG1,09/18/2015 14:05:00.000,5,Good
TAG1,09/18/2015 14:10:00.000,10,Good
TAG1,09/18/2015 14:15:00.000,15,Good
TAG1,09/18/2015 14:20:00.000,20,Good
TAG1,09/18/2015 14:25:00.000,25,Good
TAG1,09/18/2015 14:30:00.000,30,Good
TAG1,09/18/2015 14:35:00.000,35,Good
TAG1,09/18/2015 14:40:00.000,40,Good
TAG1,09/18/2015 14:45:00.000,45,Good
TAG1,09/18/2015 14:50:00.000,50,Good
TAG1,09/18/2015 14:55:00.000,55,Good
TAG1,09/18/2015 15:00:00.000,60,Good
```

Without HONORENDTIME Query Modifier

```
set starttime='9/18/2015 14:00:00',endtime='9/18/2015 14:15:00'

select Timestamp,Value,Quality from ihrawdata where tagname like TAG1 and

samplingmode=rawbynumber and

direction=forwardand numberofsamples=6
```

The output is as follows:

Time Stamp	Value	Quality
9/18/2015 14:00:00	0	Good NonSpecific
9/18/2015 14:05:00	5	Good NonSpecific
9/18/2015 14:10:00	10	Good NonSpecific
9/18/2015 14:15:0	15	Good NonSpecific
9/18/2015 14:20:00	20	Good NonSpecific

Time Stamp	Value	Quality
9/18/2015 14:25:00	25	Good NonSpecific

In the above query, the endtime specified is ignored and 6 values are returned.

With HONORENDTIME Query Modifier

```
set starttime='9/18/2015 14:00:00',endtime='9/18/2015 14:15:00'

select TagName,Timestamp,Value,Quality from ihrawdata where tagname like TAG1 and

samplingmode=rawbynumber and

direction=forward and numberofsamples=6 and criteriastring=#honorendtime
```

The output is as follows:

Time Stamp	Value	Quality
9/18/2015 14:00:00	0	Good NonSpecific
9/18/2015 14:05:00	5	Good NonSpecific
9/18/2015 14:10:00	10	Good NonSpecific
9/18/2015 14:15:0	15	Good NonSpecific

In the above query, the endtime specified is used and only 4 values are returned.

Anticipated Usage

Use the HONORENDTIME modifier when you would want to specify a time limit to a query. For example, you may want to output the returned data for a RawByNumber query in a trend page, in which case there is no need to return data that would be offpage.

EXAMINEFEW

Queries using calculation modes normally loop through every raw sample, between the given start time and end time, to compute the calculated values.

When using FirstRawValue, FirstRawTime, LastRawValue, and LastRawTime calculation modes, we can use only the raw sample near each interval boundary and achieve the same result. The EXAMINEFEW query modifier enables this. If you are using one of these calculation modes you may experience better read performance using the EXAMINEFEW query modifier.



Note:

Use the EXAMINEFEW query modifier only with FirstRawValue, FirstRawTime, LastRawValue, and LastRawTime calculation modes.

Examples using EXAMINEFEW with FirstRawValue and FirstRawTime Calculation Modes

Import this data to Historian:

```
[Tags]

Tagname,DataType,HiEngineeringUnits,LoEngineeringUnits

Tag1,SingleFloat,60,0

[Data]

Tagname,TimeStamp,Value,DataQuality

Tag1,07-05-2011 17:24:00,29.72,Bad

Tag1,07-05-2011 17:25:00,29.6,Good

Tag1,07-05-2011 17:26:00,29.55,Good

Tag1,07-05-2011 17:27:00,29.49,Bad

Tag1,07-05-2011 17:28:00,29.53,Bad

Tag1,07-05-2011 17:29:00,29.58,Good

Tag1,07-05-2011 17:30:00,29.61,Bad

Tag1,07-05-2011 17:31:00,29.63,Bad

Tag1,07-05-2011 18:19:00,30,Good

Tag1,07-05-2011 18:20:00,29.96,Good

Tag1,07-05-2011 18:21:00,29.89,Good

Tag1,07-05-2011 18:22:00,29.84,Good

Tag1,07-05-2011 18:23:00,29.81,Bad
```

Using FirstRawValue Calculation Mode

```
set starttime='07-05-2011 16:00:00', endtime='07-05-2011 19:00:00'

select timestamp,value,quality from ihrawdata where tagname like 'Tag1' and

samplingMode=Calculated and

CalculationMode=FirstRawValue and criteriastring="#EXAMINEFEW" and

intervalmilliseconds=1h
```

The output is as follows:

Time Stamp	Value	Quality
07-05-2011 17:00:00	00.0000000	0.0000000

Time Stamp	Value	Quality
07-05-2011 18:00:00	29.6000000	100.0000000
07-05-2011 19:00:00	30.0	100.0000000

**Note:**

The EXAMINEFEW query modifier does not affect query results, but may improve read performance.

Using FirstRawTime Calculation Mode

```
set starttime='07-05-2011 16:00:00', endtime='07-05-2011 19:00:00'

select timestamp,value,quality from ihrawdata where tagname like 'Tag1' and

samplingMode=Calculated and

CalculationMode=FirstRawTime and criteriastring="#EXAMINEFEW" and

intervalmilliseconds=1h
```

The output is as follows:

Time Stamp	Value	Quality
07-05-2011 17:00:00	01-01-1970 05:30:00	0.0000000
07-05-2011 18:00:00	07-05-2011 17:25:00	100.0000000
07-05-2011 19:00:00	07-05-2011 18:20:00	100.0000000

**Note:**

The EXAMINEFEW query modifier does not affect query results, but may improve read performance.

Anticipated Usage

Using the EXAMINEFEW modifier is recommended when:

- The time interval is greater than 1 minute.
- The collection interval is greater than 1 second.
- The data node size is greater than the default 1400 bytes.
- The data type of the tags is String or Blob.

**Note:**

Query performance varies depending on all of the above factors.

EXCLUDESTALE

Stale tags are tags that have no new data samples within a specified period of time, and which have the potential to add to system overhead and slow down user queries.

The EXCLUDESTALE query modifier allows for exclusion of stale tags in data queries.

Unless permanently deleted, stale tags from the archiver are not removed but are simply marked as stale. Use the query without the EXCLUDESTALE query modifier to retrieve the sample values.

**Note:**

Data is not returned for stale tags. An ihSTATUS_STALED_TAG error is returned instead.

Example**Data**

In this example, the data below is for the last raw samples for Tag1 to Tag7:

```
Tag, Timestamp, Value
Tag1, 9/25/2015 10:00:00, 10
Tag2, 9/18/2015 10:00:00, 20
Tag3, 9/25/2015 10:00:00, 30
Tag4, 9/25/2015 10:00:00, 40
Tag5, 9/18/2015 10:00:00, 50Tag6, 9/25/2015 10:00:00, 60
Tag7, 9/18/2015 10:00:00, 70
```

Further Assumptions

- Current System Time: 9/26/2015 11:00:00
- Server configuration
 - Stale Period: 7 Days
 - Stale Period Check: 1 Day

In this case, Tag2, Tag5, and Tag7 were logged more than 7 days ago. They are therefore considered stale.

Query without EXCLUDESTALE

The following query is run at 9/26/2015 11:00:00:

```
set StartTime='9/17/2015 10:00:00',EndTime='9/26/2015 11:00:00'
select TagName,Timestamp,Value from ihrawdata where tagname like Tag* and
Samplingmode=RawByTime and
CriteriaString="#ExcludeStale"
```

Output is returned for the following tags:

```
Tag, Timestamp, Value
Tag1, 9/25/2015 10:00:00, 10
Tag3, 9/25/2015 10:00:00, 30
Tag4, 9/25/2015 10:00:00, 40
Tag6, 9/25/2015 10:00:00, 60
```

In the above query, the stale tags (Tag 2, Tag5, and Tag7) are excluded from the results.

Query with EXCLUDESTALE:

The following query is run at 9/26/2015 11:00:00:

```
set StartTime='9/17/2015 10:00:00',EndTime='9/26/2015 11:00:00'
select TagName,Timestamp,Value from ihrawdata where tagname like Tag* and
Samplingmode=RawByTime and
CriteriaString="#ExcludeStale"
```

Output is returned for the following tags:

```
Tag, Timestamp, Value
Tag1, 9/25/2015 10:00:00, 10
Tag3, 9/25/2015 10:00:00, 30
Tag4, 9/25/2015 10:00:00, 40
Tag6, 9/25/2015 10:00:00, 60
```

In the above query, the stale tags (Tag 2, Tag5, and Tag7) are excluded from the results.

Anticipated Usage

Stale tags have the potential to add to system overhead and slow down user queries, without adding new data. The EXCLUDESTALE modifier can be used to exclude such tags, thereby speeding up query time.

Work with Data Stores from the Command Line

Using the Command Line to Work with Data Stores

You can create new data stores or delete existing ones from the command line. Before you can work with data stores from the command line, you must follow these steps.

1. Stop all Historian services.
2. Open a command prompt, or shell, and switch to the directory where `ihConfigManager.exe` is located.
By default, this folder is located in: `C:\Program Files\Proficy\Historian\x64\Server`.
3. Run `ihConfigureManager.exe` with the options you choose.

Related reference

[Examples \(on page 1187\)](#)

Related information

[Creating a Data Store \(on page 1186\)](#)

[Deleting a Data Store \(on page 1186\)](#)

Creating a Data Store

To create a new data store, run the following:

```
ihConfigManager_x64.exe CreateDataStore DataStoreName [StoreType: Historical = 0, Scada = 1]
[DefaultStore: NotADefault=0, Default = 1] ["OptionalDataStoreDescription"]
```

Where `DataStoreName` is the name of the data store you want to create.

Deleting a Data Store

To delete an existing data store, run the following:

```
ihConfigManager_x64.exe DeleteDataStore MyStore [NoConfirm]
```

Where:

- MyStore is the name of the data store you want to delete, and
- NoConfirm allows you delete a data store without a validation message appearing.

**CAUTION:**

Exercise extreme care in using the NoConfirm option, as it will delete an entire data store without a prompt. This is sometimes helpful in scripting, but it is a dangerous option otherwise.

Examples

Example 1: Create a new historical data store, but do not change my default data store

```
C:\Program Files\Proficy\Historian\x64\Server\ihConfigManager_x64.exe CreateDataStore MyStore 0 0
```

Example 2: Create a new historical data store and make it a default data store

```
C:\Program Files\Proficy\Historian\x64\Server\ihConfigManager_x64.exe CreateDataStore MyStore 0 1 "This
is my default historical store"
```

Example 3: Delete a data store, and display a validation message after it is removed

```
C:\Program Files\Proficy\Historian\x64\Server\ihConfigManager_x64.exe DeleteDataStore MyStore
```

Example 4: Delete a data store, but suppress any validation messages

```
C:\Program Files\Proficy\Historian\x64\Server\ihConfigManager_x64.exe DeleteDataStore MyStore NoConfirm
```

Measuring Historian Performance

About Measuring Performance of Proficy Historian

You can use the Windows Performance Counters to measure activity and performance of the Data Archivers. The Counters are more familiar to the system administrators and monitors the following Historian information.

- Read rates
- Side by side with non-Historian counters such as CPU usage or handle
- Thread counts

The following topics provide the objects and counters most useful for measuring and describing the system activity. The counters that are specified in the following topics are a subset of all the available counters.



Note:

- The Historian Advanced Topics documentation is not a replacement of the documentation for the full set of counters. Examples contained in each topic of this documentation use the counters to produce other measurements. Sometimes, the measurement number that you want is not exposed as a single counter. However, the number can be a combination of counters or a comparison of two counters.
- The counters only describe the behavior of the Data Archiver. For more information about troubleshooting and optimizing performance using the Historian and Windows counters, refer to the appropriate Historian documentation.

About the Proficiency Historian Overview Objects

The Overview objects are the counters that measure the samples collected and sent by the Data Archiver. You cannot use the counters to perform the following actions:

- Measure the performance of a specific read.
- Track the reads of a specific client or program.

The Overview objects are preferred to measure and describe a system. It is calculated as the sum total of the numbers in each instance of a data store. After you understand the Overview object, you can identify the most active data store by using the associated counters.

The performance counters are more useful because:

- You cannot access the read rates in the administrator UI.
- The write rate is updated only once in a minute. The counters are updated in real time making it much easier to see exactly when a problem began.
- The administrator UI shows only the data in the last 10 minutes but the counters are displayed over a longer time period to locate active times.
- You can access the counters in relation to the non-historian counters in the same trend.
- The counters are accessible when you cannot access the administrator UI due to performance or security reasons.

The reads vary based on the load on the Data Archiver.

**Note:**

The load on the Data Archiver does not depend only on the number of read calls. The load increases with the increased number of tags, archives, and the raw samples. You can monitor some of these activities using the counters.

You can use the Overview object to measure the following:

- Number of samples examined internally with respect to the number of samples returned to a user at a given time
- Inconsistency of reads and writes in a day, week, or month
- The number of out-of-order writes during a given time range
- The average number of samples examined per read call

Counter Name	Description
Read Rate (Calls/min)	The number of user or program initiated read calls processed over the last minute
Read Raw Rate (Samp/min)	The number of raw data samples examined internally over the last minute in response to read calls
Read Samp Rate (Samp/min)	The number of raw data samples returned to external programs over the last minute in response to read calls

**Note:**

The counts and rates provided in the above table are generic across the Data Archiver. The counts and rates do not provide detailed information, such as the reason of the time taken by a read (for example, 8 seconds) and the activities where the time was spent. However, the counts and rates can describe the reason of a scenario, when the same read criteria takes different time frames in two different days. If there are more reads or writes happening in the Data Archiver, the read criteria takes more time.

Comparing Read Raw Rate and Read Samp Rate

Run a query for a month average of 200 tags that have collected data in every second. Assume that you stored the data in one day archives. The Data Archiver has to examine a large number (200 tags x 60 seconds x 24 hours x 30 days) of raw samples that are spread across 30 one day archives to produce only

200 returned samples. If the query is run in 1 minute without any error, the Read Raw Rate value is a large number and the Read Samp Rate value is 200.

Run the same query with `samplingmode Raw By Time`. The Read Raw Rate shows the same value because the same number of raw samples were examined. As the query results returned to the caller, the `Read Samp Rate = Read Raw Rate`.



Note:

The number of archives examined is not reflected for the counter. You will get the same Read Raw Rate and Read Samp Rate if you have a 30 days archive instead of a 31 days archive.

You cannot only look at the number of write calls with reads. A write can have samples for multiple tags and the timestamps on the data can affect the number of archives accessed by a write. A collector can typically write data for all its tags, but with the same timestamp and the write call can access the same archive. A migration program can write two years of data for a tag, which can access many archives.

The following table provides the counters that have a rate over the last minute. These counters describe the data write activity in the Data Archiver.

Counter Name	Description
Write Rate (Average)	The number of raw samples received from the external programs in the last minute
Write Rate (Max)	The highest number of Write Rates (average) after starting the Data Archiver

The following table provides the total counters after starting the Data Archiver. If the Data Archiver runs for a long time, the counters are set to zero.

Counter Name	Description
Writes (Expensive)	The total number of raw samples that are expensive writes after the Data Archiver started
Writes (Total Failed)	The total number of data samples that failed to be stored after the Data Archiver started
Writes (Total)	The total number data samples stored to IHA files after the Data Archiver started

Counter Name	Description
Writes (Total OutOfOrder)	The total number of data samples written out of time order after the Data Archiver started. The number only includes the successful writes, and performs slower than when the data is in time order.

**Note:**

Although some counters are rates and some are totals, all the counters are in units of data samples.

Comparing the number of Raw Samples Read and Written

The Write Rate (Average) is the write equivalent to the Read Samp Rate. You can compare the two counters to see if more reads or writes per minute are created in your Data Archiver.

Understanding the varying load on the Data Archiver

Trend the Write Rate (Average) and Read Samp Rate over a 24 hour period. You may see certain times of the day where the load varies, such as when reports are run, or a collector has a store and forward flush, or data is recalculated with Calculation collector. Access the data available for a month. A system used for compliance or billing will have a very low read rate until you run the report till the end of month. Compare the value to a system used for real time, auto updating trending. That system will have a more consistent read load throughout the month.

Calculating the rate of out of order writes during a given time range

Out of order data writes are only exposed as a count, not a rate.

You can compute the number of out of order writes between a specific time (for example, between 3:15pm and 3:25pm) by getting the value of Total Out of Order at each timestamp and subtracting the value. You can convert the value to a rate per minute by dividing the value by 10 minutes.

The measurement is necessary because there are occurrences of out of order data in many systems. There is a base rate of out of order data for the system. If the system has intermittent changes in write performance, you can calculate the out of order rate during those times and compare the data to the base rate.

Calculating samples examined per read

As both the number of read calls and number of samples examined are exposed, you can divide to get the number of samples examined per read. In some systems, the number is near one, which indicates many small reads while the Calculation collector does many current value reads that examine one sample and return it. The samples per read will also be one, if you query raw data, such as when replicating data. An analytic program can summarize the data into 5 minute averages. For one second uncompressed data, the value is 300 samples examined per read. The number is an overall system wide number so it will not be useful to troubleshoot one read.

About Proficy Historian Message Queue Object

In any server software, there will be a number of queues. Most of the time, and all the queues should ideally have 0 items. This implies that the server is keeping up with the workload. The read and write counters of the overview object tell you how many read and write operations were performed. However, the queue counters can tell you how many actions are expected to happen, and if the user had to wait for a response.

Measuring the system performance through queues is an excellent way to determine if the server has reached the steady state performance limit. It can also tell you if the usage comes in bursts and needs to be more spread out over time.

When using the queues for measurement, you should think about what are the “items” on that queue. The “items” or “messages” here are read calls or write calls. One read call can have multiple tag names and one write call can have multiple data samples.

There are 3 queue instances exposed by counters

- Write Queue: Data writes from collectors and non-collectors.
- Read Queue: Anything for data that is not a write. It is not just data reads, it can also be tag browses.
- Msgs Queue: Anything other than read queue and write queue. You can practically ignore this queue as it is only a tiny part of the activity and it is not considered in this document.

You can get basic or very detailed information from the queue counters. At a basic level, if the queues are non-zero at a point in time, you are doing too much work at that point in time. If your queues are always non zero, then you are always expecting too much and have reached your performance limit.

Use the Queue Counters on the Read and Write queues to measure the following parameters as explained in the sections that follow:

- Last Read time vs Average Read Time
- Variability of the current queue counts
- Variability of the processed rate of read or write queue
- Number of samples per write

Basic Queue Counters

These counters represent concepts that apply to any queue usage in any server software. There is a set of these for the read queue and set for the write queue.

Counter Name	Description
Count (Max)	The highest number reached by the Count (Total).
Count (Total)	Number of messages currently on the queue.
Processed Count	Number of messages processed from the queue since Data Archiver startup. This number will wrap around and reset to zero if the Data Archiver runs for a long time.
Processed Rate (msg/min)	Number of messages processed from the queue in the last minute.
Processing Time (Ave)	Average time (in milliseconds) since the Data Archiver startup to process a message.
Processing Time (Last)	Time (in milliseconds) to process the most recently processed message.
Processing Time (Max)	Highest number the Processing Time (Last) reached since the Data Archiver startup.
Recv Count (msgs)	Number of messages received into the queue since the Data Archiver startup.
Recv Rate (msgs/min)	Rate at which messages are received in the last minute.

If your Processed Rate (msgs/min) is more than your Recv Rate (msgs/min), then your Count (Total) will be zero as the Data Archiver will be keeping up with the incoming requests.

The current value of these counters in report view is displayed at all times in the Performance Monitor. You can log these counters to a Performance Monitor group file so that the times can be matched up with periods of slow performance.

Detailed Queue Counters

These counters require a detailed understanding of how the queues are used.

There is no single read or write queue in memory. They are a virtual queue that is the sum total of all the client queues. Each connection from a client uses a socket. Each socket is monitored by a thread called a client thread. A queue is used between one client thread and the pool of threads that access the IHA files. This can be called as a client queue. No client thread goes directly to the IHA files. There are a fixed number of threads that monitor all client queues and read and write the IHA files.

A default system has one write thread and four read threads. You may have 20 collectors and 35 clients connected to the data archiver, that is, $20+35=55$ client threads. That is, $55 \times 2 = 110$ client queues as each client thread has one read and one write queue.

The four read threads will monitor the 55 client read queues, most of which are empty most of the time. The one write thread monitors the 55 client write queues.

The Count (Total) on the Read Queue instance or the Write Queue instance is the sum total of all the items on the 55 read queues.

Counter Name	Description
Threads	Number of configured threads that go to the IHAs. This number will not change at runtime. It defaults to one write thread and four read threads.
Threads Working	Number of configured queue processing worker threads that are currently working on processing a message. If there is not much work to do, there will be idle threads and which will be much less than the Threads counter, possibly zero.
Time In Queue (Ave)	The average time since the Data Archiver startup of the "Time In Queue (Last)".
Time In Queue (Last)	Time (in milliseconds) that the last message waited in the queue before a thread started processing

Counter Name	Description
	it. This should be near zero, meaning the archiver is keeping up with the requests and writes.
Time In Queue (Max)	The max time since the Data Archiver startup of the Time In Queue (Last).
ClientQueues with Msgs	<p>The number of client queues with messages on them. In the previous example, this is how many of the 55 read client queues have at least one item on it. It doesn't matter how many items are on the client queue, only that it has at least one item. The number would be between 0 and 55.</p> <p>This number gives some idea about how balanced the incoming load is and how balanced the servicing of the clients is. You don't want any single client doing too many reads or write causing other clients to have to wait.</p>

The time to process one read or one write would be the Time In Queue (Last) + the Processing Time (Last). But these are not visible as these are overall system wide counters, and not the way to troubleshoot one read or one client. The Time in Queue (Last) increases when the Threads Working equals Threads meaning all threads are busy.

Example: Comparing current to average processing time

Every system is different and has its own "normal" data rate. You can measure it if your current rate is above or below normal. To determine if the Recv Rate or Processed Rate is above or below normal, you must look at the number over a longer period of time, maybe 1 hour or 24 hours.

To determine if the processing time is taking longer than normal, you can trend the Processing Time (Last) to the Processing Time (Average) at the same time range. One line will be above the other to show if the range is above or below normal.

Example: Measuring the variability of Queue Count Total

This demonstrates that the Count (Total) can change. The number will change based on the Recv Count and the Processed Count.

The Write Queue Recv Rate is usually consistent. But you may see the Write Queue Recv Rate increase during a Store and Forward flush of a collector. The Write Queue Processed Count will vary more, and that will cause the Write Queue Count (Total) to vary as well. Consider an archive backup done at midnight each day. During a backup, the writes have to stop. The Write Queue Recv Rate will stay the same because collectors are still writing. The Processed Count will be zero during the backup so the Write Count (Total) will grow.

The same happens if there are long reads happening. If there are any reads, then the writes will have to wait and the Write Count (Total) will grow. But the Overview object Read Raw Rate should be busy, indicating the Data Archiver is busy doing some work, but not the writes.

If the writes are out of time order, the exact same number and bundle size of the raw samples can take longer to write. The exact same number of raw samples can take longer to read if there are cache misses and the data archiver does file I/O.

Reads are unlike writes because collectors will keep sending writes, even if they don't get responses. A client that does a read will wait for the response before sending the next read. The reads will not queue up in the Data Archiver. In general, the Read Queue Count (Total) will not grow as high as the Write Queue Count (Total) unless you have many read clients.

You can measure how much your Read and Write Queue Count (Total) vary over a 24 hour period, and understand that Count (Total) variability is caused by the variability of the Recv Rate and Processed Rate. The variability of those is caused by the variability of the sizes of the reads and writes combined with whatever else is happening on the machine.

Example: Computing the number of samples per write

The Overview object has a Read Calls counter but does not have a Write calls counter. You don't know the number of write calls nor can you compute a number of samples per write call. But, since one Write Queue Recv Count is one write call, you can use that number.

About Proficy Historian Cache Object

Caching is used in many kinds of server software. You may have a basic idea of the concept and terminology of caching and just need to know how Historian makes use of a cache to give improved performance. The Historian Data Archiver is used to store and retrieve data from gigabytes of archives on disk. All those raw samples can not be kept in memory. For performance reasons, the Data Archiver will attempt to keep the most recently used information in memory. Cache hits avoid file I/O which is the number one negative performance factor in any server software.

As with multiple queues, there are multiple caches in the Data Archiver, each holding a different type of object. As with “items” in queues you want to understand what “objects” are in a cache. One Read Call in the overview object becomes one Recv Count in the Queue object which becomes one or more cache hits or misses in the Archive Data Cache. This is because one read may span the raw samples stored in multiple data nodes. Some of those data nodes may be in cache and some may not.

There are four caches within the Data Archiver: ArchiveDataCache, ArchiveIndexCache, ArchiveTagCache, and ConfigTagCache. You can ignore three of them and only monitor the Archive Data Cache. These are raw samples. So, this cache is the simplest to understand and has the biggest effect on performance.

The Archive Data Cache starts empty at Data Archiver startup and fills as data is read and written.

Cache counters, like Queue counts are best viewed as current values in the report view of Performance monitor. These are displayed on the Archive Data Cache instance.

Counter Name	Description
Hits	When a program is queried or re-queried a tag and time range, and it was found in the cache.
Misses	Data reads where the requested information was either never in cache or had to be removed to make room for more recently accessed data.
Hit Percentage	Hits divided by Misses expressed as a percent. A high percentage means most data requests are being satisfied without having to access the disk.

The objects in the Archive Data Cache are the data nodes. One data node is about 250 consecutive raw samples for one tag.

Counter Name	Description
Obj Count	Number of objects (data nodes containing raw samples) in the cache.
Num Adds	Total number objects added to cache since Data Archiver startup. This number will always be increasing as new data is collected and queried.
Num Deletes	Total number of objects deleted from cache. Deletes will not happen until the cache has reached its maximum size.

Counter Name	Description
Size (MB)	The amount of memory used by the cache to contain the raw samples.

Possible uses of the counters are demonstrated in the sections that follow.

Example: Computing the cache hits for a specific time range

All the counters are numbers since Data Archiver startup, which means it is hard to detect a period of time that had many cache misses. If you know that the read was run at 4pm and took 1 minute, you can get the hits and miss counts at 3:59 and 4:02 and subtract them to know what the hit percentage was at the time the read was done. This is more useful than the hit percentage since startup. When subtracting, verify if the counter had rollover and went back to zero.

Example: Best Case Archive Data Cache hit percentage

Run the exact same SQL query 10 times with fixed start and end times. Your hits would be nine and misses would be one, that is, the first read. This is a cache hit percent of 90%. If you keep doing the read you will keep hitting the same raw samples in the same data nodes.

You must have an auto updating chart that always shows the data up to current time. You will have a high but not 100% cache hit percentage. This is because, as new data is added, you will have one cache miss accessing that newly created data node.

Example: Diagnosing Data Archiver memory growth due to cache

The overall Data Archiver memory usage consists of multiple kinds of objects. But you can monitor the memory usage due to caching in detail.

There are memory usage numbers on the cache and another way to do it is look at the object count in the cache. If Data Archiver Virtual Memory use is increasing, look at the Object Count over the same time period to see if it is also increasing.

Example: Removing items from cache to limit memory usage

There is no maximum reserved size for the cache. If adding more objects would put you past the configured Archiver Memory Usage, then adding one object will delete another object. Or, if the archiver memory is used for non-cache reasons like large tag browses, then the Data archiver cache will remove items to meet the target memory usage.

Example: Monitoring the size in bytes of the cache

Configure the Archiver Memory Size (MB) in the Admin UI to 100 meg and in the Report View of Performance Monitor look at the Size(MB) counter of the ArchiveDataCache instance. It is zero. Now change the Archiver Memory Size to 1700 and restart the data Archiver. The number is still zero.

This is because the counter measures how much space the cache is currently using, not a configured size nor maximum size. If you start reading and writing data, the Size (MB) will grow.

Chapter 7. Historian Alarms and Events

Overview of Alarms and Events

Using Historian, you can archive alarms and events data from any OPC-compliant alarms and events server.

Alarms: Alarms are generally defined as tags going into an abnormal condition. For example, you can set an alarm on a boiler when it reaches a specified temperature. Alarms usually have a well-defined life cycle, which is defined by the individual data sources from which the alarms data is collected. They enter an alarm state, are generally acknowledged, then return to normal.

To collect alarms and events data, you can use any of the following collectors:

- iFIX Alarms and Events collector
- OPC Classic Alarms and Events collector

Historian handles alarm data in two ways. You can view the entire Alarm as a single record that contains all information about the alarm, or you can view the Alarm History, which shows the transitions of the alarm as individual records.

Events: Events are generally defined as activities in a system that occur once only. For example, a user logging on to a device is an event. When viewing this data in Historian, each event is returned as a record.



Note:

If you have configured Historian to use the SQL Server, you must ensure that both Historian and SQL Servers have write access to Default Archive Path and Default Backup Path. (By default, Archive and Backup path is `C:\Proficy Historian Data\Archives\.`) Also, make sure that the SQL service user account has permission to create a new database in the SQL Server.

Alarms and Events Requirements

To generate alarms and events data, you can use any OPC-compliant alarms and events server such as:

- CIMPLICITY
- iFIX

To collect alarms and events data, [install collectors \(on page 142\)](#), and then add any of the following collector instances:

- [iFIX Alarms and Events collector \(on page 505\)](#)
- [OPC Classic Alarms and Events collector \(on page 532\)](#)

To store alarms and events data, [install Historian Alarms and Events \(on page 140\)](#). During the installation, provide the credentials of Microsoft SQL server 2012 or later.

To view and analyze alarms and events data, you can use any of the following applications:

- Configuration Hub
- Historian Administrator
- Crystal Reports 11 or later
- The OLEDB Provider
- REST APIs

**Note:**

Before starting the Alarm Archive service, ensure that "NT AUTHORITY/SYSTEM" has "SysAdmin" privileges.

Install Alarms and Events

- You must install Historian Alarms and Events on the same machine as the data archiver.
- If you have chosen to connect Historian to a remote SQL server, the following conditions must be satisfied:
 - The Historian Alarm Archiver service must be run on a user account that has privileges to log in to the SQL server using Windows authentication.
 - The default backup path, which you can set on the Archive page, must be a shared directory that is accessible to both the Historian Data Archiver and the remote SQL server. It is recommended that this shared directory be placed on the same computer as the Historian Data Archiver service.

1. Run the `InstallLauncher.exe` file.
2. Select **Install Alarms and Events**.
The **Alarms and Events Archiver** page appears.

3. If needed, change the values in the **Server Name** and **Database Name** fields to provide the name of the SQL server and the name of the database where the alarms and events data is archived.
4. If you want to use the SQL server credentials, clear the **Use Windows Authentication** check box, and then enter the SQL server login credentials in the **Admin User** and **Password** fields. If you want to use Windows authentication, select the **Use Windows Authentication** check box. When you do so, the **Admin User** and **Password** fields are disabled.
5. Select **Next**.
6. When prompted to restart your system, select **Yes**.

Historian Alarms and Events is installed in the following folder: *<installation drive>*:
 \Program Files\Proficy\Proficy Historian\x86\Server, and the following registry path is created: HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\ Intellution, Inc.
 \iHistorian\Services\AlarmArchiver

- To verify that the Alarms service has started, access the **Services** window, and check the status of the Historian Alarm Archiver service.

If the **Startup Type** field is set to **Automatic**, the service is started automatically when the system is started or restarted.

Upgrade Alarms and Events

- If Alarms and Events were installed prior to Historian 7.0, you must install them separately.
- If you want to upgrade from Historian 4.5, since the database schema are different, if you select the same database name that is pre-populated by default, you will get an error message: `Later or Higher version of Alarms and Events database is already installed. Hence, you cannot proceed further.` You need to enter a different database name and then proceed with the upgrade.

[Install Alarms and Events \(on page 140\).](#)

Alarms and Events are upgraded to the latest version.

Change the SQL Server to Store Alarms and Events Data

If you have chosen to connect Proficy Historian to a remote SQL server:

- The Historian Alarm Archiver service must be run on a user account that has privileges to log into the SQL Server using Windows Authentication.
- The Default Backup Path, found on the Archive page, must be a shared directory that is accessible to both the Historian Data Archiver and the remote SQL Server. It is recommended that this shared directory be placed on the same computer as the Historian Data Archiver service.

- Run the `Proficy.Historian.AandE.Migration.exe` file. By default, it is located at `C:\Program Files (x86)\Proficy\Proficy DataBase.`

The **Proficy Historian Alarm and Event Data Migration** window appears.

- Select **Specify SQL Server Instance**.
- In the **Server Name**, **Database Name**, **Admin User**, and **Admin User Password** fields, enter values.
- Select **Use default SQL path as data and log path** if you want to place the data and log files at the default location as the SQL server.

If you want to install the data and log files in a different location, cancel the selection and in the **Alarms Data Path** and **Alarms Log Path** fields, and provide the path to place the data and log files.

About Backing up Alarms

It is a good practise to back up alarm data periodically. It helps restore the data if you accidentally delete it. In addition, if you want to migrate alarms and events data from one version of Historian to another, you must first back up the data.

When you back up alarms, a copy of the alarm data is created on your machine, which you can [restore \(on page 1209\)](#) later.

You can back up alarm data using any of the following methods:

- [Using Configuration Hub \(on page 753\)](#)
- [Using the Proficy Historian Alarm and Event Data Migration utility \(on page 1205\)](#)
- [Using Historian Administrator \(on page 1206\)](#)
- [At a command prompt \(on page 1208\)](#)

Back up Alarms Using Configuration Hub

1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub for Historian, select **Alarms**.
The **Alarms** section appears.
3. Select , and then select **Backup Alarms**.
The **Backup Alarms** window appears.
4. Enter values as described in the following table.

Field	Description
GENERATED FROM	Enter the start time for which you want to back up alarms.
GENERATED TO	Enter the end time for which you want to back up alarms.
PROVIDE FILE NAME	<p>Enter the file name and location of the back up file that you want to create. By default, the backup location of the default data store is considered. And, the file name is in the following format: <code>mm_dd_yyyy_hh_mm_ss</code>. For example: 11_25_2022_11_23_26.zip. The time format followed is the 24-hour time notation.</p> <div style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note: This file naming convention for alarm backup is standard to Historian. Even if you use other date settings</p> </div>

Field	Description
	<div data-bbox="669 268 1421 373" style="border: 1px solid #00a0e3; border-radius: 10px; padding: 5px; background-color: #e6f2ff;">  such as dd-mm, the file name will still be saved in the mm-dd format. </div> <p>The end time stamp in the file name indicates the time at which the alarms have been backed up but not the time till when the alarms are backed up. For example, suppose, at 8:00 am, you back up alarms for the past two hours, the backup will contain alarms from 6:00 am to 8:00 am but may not contain an alarm generated at 8:00 am. The last alarm may have been at 7:50 am. But the backup file name will have the time stamp of 8:00:00 along with the date.</p>

5. Select **Backup**.

The alarms data is backed up.

Back Up Alarms and Events Using the Utility

1. Run the `Proficy.Historian.AandE.Migration.exe` file. By default, it is located at `C:\Program Files (x86)\Proficy\Proficy DataBase`.
The **Proficy Historian Alarm and Event Data Migration** window appears.
2. Select **Backup Existing Alarms and Events**.
3. Enter values as described in the following table.

Field	Description
Time Range	Enter the duration in which you want to back up alarms.
SQL Server Instance Name	Enter the SQL server instance name in which the alarms are stored.
Database Name	Enter the name of the database from which you have to backup the data. Typically, this will be the same as the SQL Server you are currently using.
Use Windows Authentication or Use SQL Authentication	Select either of these options to specify the type of authentication you want to use.
User Id	Depending on whether you have selected Use Windows Authentication or Use SQL Authentication , enter the Windows or SQL

Field	Description
	server username to connect to the SQL server. Ensure that this user has the permission to back up alarms.
Password	Depending on whether you have selected Use Windows Authentication or Use SQL Authentication , enter the Windows or SQL server password to connect to the SQL server.
Backup Folder Path	Enter the absolute path, including file name, to store the backed up alarms (for example, c:\temp\March2010.bak). If the SQL server is on a remote machine, enter a path that exists on the remote machine.

4. Select **Test Connection** to verify that the source database is active and the information is accurate.
The **Begin Backup** button is enabled after the connection is successful.
5. Select **Begin Backup**.
The alarm data is backed up.

Back Up Alarms Using Historian Administrator

When you back up alarms, a copy of the alarm data is created on your machine, which you can restore later.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Data Stores > Alarms**.

The screenshot shows the Proficy Historian DataStore Maintenance interface. The top navigation bar includes 'Main', 'Tags', 'Collectors', 'DataStores' (highlighted in red), 'Messages', and 'Help'. Below the navigation bar, there are buttons for 'Rename Data Store', 'Add Data Store', 'Add New Archive(s)', and 'Restore an Archive from Backup'. The main content area is divided into two sections: 'Data Stores' and 'Alarms Maintenance'. The 'Data Stores' section shows a dropdown menu with 'User' selected. The 'Alarms Maintenance' section has tabs for 'Archive Details', 'Data Store Details', 'Data Store Options', 'Global Options', 'Security', and 'Alarms' (highlighted in red). Under 'Alarms Maintenance', there are two sub-sections: 'Backup / Purge Alarms' and 'Restore Alarms'. The 'Backup / Purge Alarms' section has 'Start Time' and 'End Time' fields, both set to '08-06-2022' and '07:47:45'. Below these fields are 'Backup Alarms' and 'Purge Alarms' buttons. The 'Restore Alarms' section has a 'Select File' field and a 'Restore' button.

3. In the **Start Time** and **End Time** fields, enter the duration in which you want to back up alarms.
4. Select **Backup Alarms**, provide a name for the backup file, and then save the file. If the SQL server is on a different machine, ensure that you specify a path available to the SQL server.
By default, the file name is in the following format: `mm-dd-yyyy hh:mm:ss`. The time format followed is the 24-hour time notation.

**Note:**

This file naming convention for alarm backup is standard to Historian. Even if you use other date settings such as `dd-mm`, the file name will still be saved in the `mm-dd` format.

The end time stamp in the file name indicates the time at which the alarms have been backed up but not the time till when the alarms are backed up. For example, suppose, at 8:00 am, you back up alarms for the past two hours, the backup will contain alarms from 6:00 am to 8:00 am but may not contain an alarm generated at 8:00 am. The last alarm may have been at 7:50 am. But the backup file name will have the time stamp of 8:00:00 along with the date.

The alarms data is backed up.

Back up Alarms at a Command Prompt

When you back up alarms, a copy of the alarm data is created on your machine, which you can restore later.

1. Run the `ihBackupAlarms.exe` file. By default, it is located at `C:\Program Files\Proficiency\ProficiencyHistorian\Server\ihBackupAlarms.exe`
2. Use the following parameters to back up alarms data:

Parameter	Description
<code>-s <Historian server></code>	The Historian server containing the alarm data that you want to back up. If you do not provide this parameter, the local machine is considered.
<code>-u <username></code>	The username to connect to the archiver.
<code>-p <password></code>	The password to connect to the archiver.
<code>-b "<file path>"</code>	<p>The file path where you want to place the backup file. If the path is not specified, the default backup path of the archive is considered.</p> <div style="border: 1px solid #00a0c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;">  Note: You must enter the file path in double quotes (for example, "C:\\backup\\"). </div>
<code>-d <number of Days prior to the current time></code>	<p>Indicates the time in days till the current date for which you want to back up alarms. For example, to back up alarms of the past seven days, enter:</p> <pre style="background-color: #f0f0f0; padding: 5px;">-d 7</pre>
<code>-h <number of hours prior to the current time></code>	<p>Indicates the time in hours till the current time for which you want to back up alarms. For example, to back up alarms of the past two and half days, enter:</p> <pre style="background-color: #f0f0f0; padding: 5px;">-d 2 -h 12</pre>
<code>-m <number of minutes prior to the current time></code>	<p>Indicates the time in minutes till the current time for which you want to back up alarms. For example, to back up alarms of the past 3 hours 15 minutes, enter:</p>

Parameter	Description
	<code>-h 3 -m 15</code>
<code>-sec <number of seconds prior to the current time></code>	Indicates the time in seconds till the current time for which you want to back up alarms. For example, to back up alarms of the past 30 seconds, enter: <code>-sec 30</code>

The alarm data is backed up.

Restoring Data

Restore Alarms Using Configuration Hub

Restoring alarms to a running system makes them available for query and analysis. You can restore alarms that have been backed up or deleted previously.

1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub for Historian, select **Alarms**.
The **Alarms** section appears.
3. Select , and then select **Restore Alarms**.
The **Restore Alarms** window appears.
4. In the **PROVIDE FILE NAME** field, provide the backup file in the .zip format that you want to restore.



Note:

Remember to include .zip at the end of the file name.

5. Select **Restore**.
The alarm data is restored.

Restore Alarms Using Historian Administrator

Restoring alarms to a running system makes them available for query and analysis. You can restore alarms that have been backed up or deleted previously.

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Data Stores > Alarms**.

The screenshot shows the Proficy Historian DataStore Maintenance interface. The top navigation bar includes 'Main', 'Tags', 'Collectors', 'DataStores' (highlighted in red), 'Messages', and 'Help'. Below this, there are buttons for 'Rename Data Store', 'Add Data Store', 'Add New Archive(s)', and 'Restore an Archive from Backup'. The main content area is divided into two sections: 'Data Stores' on the left and 'Alarms Maintenance' on the right. The 'Data Stores' section shows a dropdown menu with 'User' selected and a table of archives. The 'Alarms Maintenance' section has tabs for 'Archive Details', 'Data Store Details', 'Data Store Options', 'Global Options', 'Security', and 'Alarms' (highlighted in red). Under 'Alarms Maintenance', there are two sub-sections: 'Backup / Purge Alarms' and 'Restore Alarms'. The 'Backup / Purge Alarms' section has fields for 'Start Time' (08-06-2022 07:47:45) and 'End Time' (08-06-2022 09:47:45), with 'Backup Alarms' and 'Purge Alarms' buttons. The 'Restore Alarms' section has a 'Select File' field and a 'Restore' button.

3. In the **Select File** field, provide the backup file in the .zip format that you want to restore.

4. Select **Restore**.

The alarm data is restored.

About Migrating Alarms and Events Data

If you are upgrading to the latest version of Historian, and you have already collected alarms, you can migrate the alarms and events data after upgrading to latest version of Historian. Only after you migrate the data, you can retrieve alarms.



Note:

Before migrating alarms and events data, ensure that you have [backed up the data \(on page 1205\)](#).

To migrate your alarms into the new alarm database, you must back up the old alarms, and restore them into the new database. You can back up the data before the upgrade using Configuration Hub or Historian

Administrator, or you can back up the data after the upgrade using the Proficy Alarms Database Migration Tool.

You may need to migrate small time periods if you have many alarms. If you need to migrate the alarms in blocks of time, do the oldest alarms first.

Migrate Alarms and Events Using the Utility

[Back up the alarms and events data \(on page 1205\).](#)

1. Run the `Proficy.Historian.AandE.Migration.exe` file. By default, it is located at `C:\Program Files (x86)\Proficy\Proficy DataBase`.
The **Proficy Historian Alarm and Event Data Migration** window appears.
2. Select **Migrate Alarms and Events Backup**.
3. Enter values as described in the following table.

Field	Description
Backup File Path	Enter the location of the backup file. If your server is running on a remote computer, enter a path that exists on the remote computer.
SQL Server Instance Name	Enter the SQL server instance name in which the backup file is stored.
Database Name	Enter the name of the database using which you have backed up the data. Typically, this will be the same as the SQL Server you are currently using.
Use Windows Authentication or Use SQL Authentication	Select either of these options to specify the type of authentication you want to use.
User Id	Depending on whether you have selected Use Windows Authentication or Use SQL Authentication , enter the Windows or SQL server username to connect to the SQL server. Ensure that this user has the permission to restore alarms.
Password	Depending on whether you have selected Use Windows Authentication or Use SQL Authentication , enter the Windows or SQL server password to connect to the SQL server.

4. Select **Test Connection** to verify that the source database is active and the information is accurate.

**Note:**

You can find this information in the registry under: `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\AlarmArchiver.`

The **Begin Migration** is activated and the alarm data is restored.

5. Select **Begin Migration**.

The data is migrated.

Migrate Alarms and Events at a Command Prompt

[Back up the alarms and events data \(on page 1205\).](#)

1. Run the `ihBackupAlarms.exe` file. By default, it is located at `C:\Program Files\Proficy\ProficyHistorian\Server\ihBackupAlarms.exe`
2. Use the following parameters to migrate data:

parameter	Description
<code>/TASK</code>	Specify whether you want to back up or restore data. Enter one of the following values: <ul style="list-style-type: none"> ◦ BACKUP ◦ RESTORE This parameter is required.
<code>/SERVER</code>	Enter the SQL server instance name in which the backup file is stored. This parameter is required.
<code>/DBNAME</code>	Enter the name of the database using which you have backed up the data. Typically, this will be the same as the SQL Server you are currently using. This parameter is required.
<code>/SDATETIME</code>	Enter the start time from which you want to migrate alarms. Enter a value in the following format: <code>mm/dd/yyyy HH:MM:ss</code> (for example <code>5/21/2023 10:20:30</code>). Alarms and events data collected from this time will be considered. This parameter is mandatory if you are backing up alarms.
<code>/EDATETIME</code>	Enter the end time up to which you want to migrate alarms. Enter a value in the following format: <code>mm/dd/yyyy HH:MM:ss</code> (for example <code>5/21/2023 10:20:30</code>). Alarms and events data collect-

Parameter	Description
	ed from this time will be considered. This parameter is mandatory if you are backing up alarms.
/BKPPATH	Fully qualified path of the .dat file where the backup of the database will be taken. This parameter is mandatory if you are backing up alarms.
/RSTPATH	Fully qualified path of the .dat file from where the database will be restored. This parameter is mandatory if you are restoring alarms.
/USERNAME	Enter the Windows or SQL server username to connect to the SQL server. If you do not provide this parameter, Windows authentication is used.
/PWD	Enter the Windows or SQL server password to connect to the SQL server. By default, the password is blank, but we recommend that you enter a password.

To back up using SQL authentication:

```
Proficy.Historian.AandE.Migration.exe /TASK=Backup
/SERVER=CPHIST45\PROFICYHIST /DBNAME=CPHIST45_plantdatabase
/SDateTime="3/9/2013 21:00:00" /EDateTime="3/9/2013 23:59:59"
/BKPPATH=C:\temp\PDB_0309.dat /USERNAME=sa /PWD=Pr0f1cyhist
```

To back up using Windows authentication:

```
Proficy.Historian.AandE.Migration.exe /TASK=Backup
/SERVER=Domain\Node /DBNAME=AEEDB /SDateTime="5/10/2012 10:20:30"
/EDateTime="6/10/2012 10:20:30" /BKPPATH=E:\DBBkpPath\AEEDB_1.dat
```

To restore using SQL authentication:

```
Proficy.Historian.AandE.Migration.exe /TASK=Restore
/SERVER=CPHIST45\PROFICYHIST /DBNAME=CPHIST45_AEDatabase
/RSTPATH=C:\temp\PDB_0309.dat /USERNAME=sa /PWD=Pr0f1cyhist
```

To restore using Windows Authentication:

```
Proficy.Historian.AandE.Migration.exe /TASK=RESTORE
/SERVER=Domain\Node /DBNAME=AEEDB /RSTPATH=E:\DBBkpPath\AEEDB_1.dat
```

To perform multiple back ups using a batch file:

```
cd C:\Program Files\Proficy\Proficy DataBase

start/b/wait Proficy.Historian.AandE.Migration.exe /TASK=Backup

/SERVER=CPHIST45\PROFICYHIST /DBNAME=CPHIST45_plantdatabase

/SDateTime="3/9/2013 21:00:00" /EDateTime="3/9/2013 23:59:59"

/BKPPATH=C:\temp\PDB_0309.dat /USERNAME=sa /PWD=Pr0f1cyhist

start /b /wait Proficy.Historian.AandE.Migration.exe /TASK=Backup

/SERVER=CPHIST45\PROFICYHIST /DBNAME=CPHIST45_plantdatabase

/SDateTime="3/10/2013 00:00:00" /EDateTime="3/10/2013 02:00:00"

/BKPPATH=C:\temp\PDB_0310_1.dat /USERNAME=sa /PWD=Pr0f1cyhist

start /b /wait Proficy.Historian.AandE.Migration.exe /TASK=Backup

/SERVER=CPHIST45\PROFICYHIST /DBNAME=CPHIST45_plantdatabase

/SDateTime="3/10/2013 02:00:00" /EDateTime="3/10/2013 04:00:00"

/BKPPATH=C:\temp\PDB_0310_2.dat /USERNAME=sa /PWD=Pr0f1cyhist
```

To perform multiple restores using a batch file:

Multiple Restores Using a Batch File:

```
cd C:\Program Files\Proficy\Proficy DataBase

start/b/wait Proficy.Historian.AandE.Migration.exe /TASK=Restore

/SERVER=CPHIST45\PROFICYHIST /DBNAME=CPHIST45_AEDatabase

/RSTPATH=C:\temp\PDB_0309.dat /USERNAME=sa /PWD=Pr0f1cyhist

start /b /wait Proficy.Historian.AandE.Migration.exe /TASK=Restore

/SERVER=CPHIST45\PROFICYHIST /DBNAME=CPHIST45_AEDatabase

/RSTPATH=C:\temp\PDB_0310_1.dat /USERNAME=sa /PWD=Pr0f1cyhist

start /b /wait Proficy.Historian.AandE.Migration.exe

/TASK=Restore /SERVER=CPHIST45\PROFICYHIST /DBNAME=CPHIST45_AEDatabase

/RSTPATH=C:\temp\PDB_0310_2.dat /USERNAME=sa /PWD=Pr0f1cyhist
```



Note:

Parameter values with spaces must be enclosed within quotation marks.

Query Alarms and Events Data Using the Excel Add-In

Querying Alarms and Events data in the Excel Add-In retrieves alarms and events data according to your Query Criteria. Three query types are available: Alarm, Alarm history, and Events.



Note:

You cannot use an OPC alarms and events server with FIX32 SCADA systems. To collect alarm data from these systems, you can use a proxy for alarms through an iFIX node with an OPC alarms and events server. The OPC Classic Alarms and Events collector of Proficy Historian can then collect the data. For more information, refer to [Using the OPC AE Collector with FIX32 SCADA Systems \(on page 1225\)](#).

1. Open an Excel worksheet.
2. Select **Historian > Query Alarms & Events**.
The **Query Alarms & Events** window appears.
3. Enter values as described in the following table.

Field	Description
Server	Select the SQL server that contains the alarms and events data.
Query Type	Select one of the following values: <ul style="list-style-type: none"> ◦ Alarms: In Historian, an alarm's entire life cycle is stored as a single record in the alarm archive. Thus, when retrieving from the archive, the entire life cycle of an alarm will be returned in a single record. ◦ Alarm History: Each change in the alarm's state will be returned in a single record. ◦ Events: One row per event is returned.
Query Criteria	Enter the criteria that you want to use in the query. For example, you may want to include alarms where the Alarm ID is equal to a specific Alarm ID occurring after a specific start time. In addition, you can specify which attributes must be displayed and how the results must be sorted in the spreadsheet.
Output Range	Select a range of cells in a single row or column to determine where the returned data must be placed.
Output Orientation	Select either Columns or Rows for the output display. Selecting Columns displays a table of values with parameters arranged in

Field	Description
	columns with header labels at the top. Selecting Rows rotates the table 90 degrees.
Maximum Results	Enter the maximum number of results for the query to return. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: An Excel spreadsheet can display up to 255 columns and 32,767 rows. </div>
Output Display	Specify the attributes that you want to display in the spreadsheet.
Output Sorting	Select the parameter using which you want to sort the results: <ul style="list-style-type: none"> ◦ Alarm Time: Sorts the data by the start time. The results appear in the reverse chronological order. ◦ Custom Sort: Allows you to select the field using which you want to sort the results. ◦ None: The results are not sorted at all. They are returned in the order they are received from the alarms and events database.

4. Select **OK**.

The query results appear.

Import Alarms and Events Data into a Spreadsheet

Using the Historian Excel add-in, you can import alarms and events data into a spreadsheet. It helps you include alarms and events data into the Historian archive that is not normally collected by Historian or when you are migrating data from an older system into Historian.

**Note:**

- The Excel worksheet must contain at least the source and timestamp columns.
- If an error occurs while importing data, the whole operation is aborted.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Import Alarms**.

The alarms and events data is imported.

Export Alarms and Events Data from a Spreadsheet

Using the Historian Excel add-in, you can export alarms and events data into a new worksheet or into a CSV or an XML file.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Export Alarms**.

The **Historian Alarm Export** window appears.

3. Enter values as described in the following table.

Field	Description
Server	Select the SQL server that contains the alarms and events data.
Query Type	Select one of the following values: <ul style="list-style-type: none"> ◦ Alarms: In Historian, an alarm's entire life cycle is stored as a single record in the alarm archive. Thus, when retrieving from the archive, the entire life cycle of an alarm will be returned in a single record. ◦ Alarm History: Each change in the alarm's state will be returned in a single record. ◦ Events: One row per event is returned.
Query Criteria	Enter the criteria that you want to use in the query. For example, you may want to include alarms where the Alarm ID is equal to a specific Alarm ID occurring after a specific start time. In addition, you can specify which attributes must be displayed and how the results must be sorted in the spreadsheet.
Output Range	Select a range of cells in a single row or column to determine where the returned data must be placed.
Output Orientation	Select either Columns or Rows for the output display. Selecting Columns displays a table of values with parameters arranged in columns with header labels at the top. Selecting Rows rotates the table 90 degrees.
Maximum Results	Enter the maximum number of results for the query to return.

Field	Description
	 Note: An Excel spreadsheet can display up to 255 columns and 32,767 rows.
Output Display	Specify the attributes that you want to display in the spreadsheet.
Output Sorting	Select the parameter using which you want to sort the results: <ul style="list-style-type: none"> ◦ Alarm Time: Sorts the data by the start time. The results appear in the reverse chronological order. ◦ Custom Sort: Allows you to select the field using which you want to sort the results. ◦ None: The results are not sorted at all. They are returned in the order they are received from the alarms and events database.
Export Options	Select the format in to which you want to export the data: <ul style="list-style-type: none"> ◦ To New Worksheet: Exports the data to a new Excel worksheet. ◦ To CSV File: Exports the data with comma separated values to a new file. ◦ To XML File: Exports the data to a new XML file.

4. Select **OK**.

The data is exported.

About Purging Alarms

Purging alarm data involves deleting the data from the database.



Note:

- Even after purging, the data is not lost; a backup is created to maintain an audit trail. You can restore the data if needed.
- When using circular archives (that is, archives that roll over), alarms are purged automatically.

You can choose to purge alarm data for any of the following reasons:

- To maintain alarm data efficiently
- The data is outdated or redundant
- The disk space is limited

Data in the following tables is purged:

- Alarm Attribute Values
- Alarm Attribute Value History
- Delete from Alarm History
- Delete from Alarm Table esignatures
- comments

You can purge data using one of the following methods:

- Purge data within a specified duration. You can do this [using Configuration Hub \(on page 756\)](#), [using the Proficy Historian Alarm and Event Data Migration utility \(on page 1221\)](#) or [at a command prompt \(on page 1223\)](#).
- Purge data related to a specific alarm ID. You can do this [using `Alarms.PurgeAlarmsById` \(on page 1604\)](#) to develop an SDK program.

Purging is performed in batches. You can check the log data in the `Proficy.Historian.AandE.Migration.log` file. By default, this file is located in the `C:\Program Files(x86)\Proficy` folder.

In the case of a failure:

- The batch size is changed to 10. That is, the collector receives an acknowledgement after sending 10 messages, thus reducing the load on the server.
- The waiting time for receiving an acknowledgement is automatically incremented after each failure per batch, starting from 90 seconds to 270 seconds. This gives more time for the server to respond.



Note:

After the acknowledgement is received, the batch size and the waiting time are reset for the subsequent batches.

If the time taken to purge exceeds the timeout limit, instead of reverting the entire purging operation, only the current batch, which is still under processing, is purged.

Best Practices:

- Restart the Alarms and Events services before purging data.

Purge Alarms Using Configuration Hub

1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub for Historian, select **Alarms**.
The **Alarms** section appears.
3. Select **☰**, and then select **Purge Alarms**.
The **Purge Alarms** window appears.
4. In the **PROVIDE FILE NAME** field, pro
5. Enter values as described in the following table.

Field	Description
GENERATED FROM	Enter the start time for which you want to purge alarms.
GENERATED TO	Enter the end time for which you want to purge alarms.
PROVIDE FILE NAME	<p>Enter the file name and location of the back up file that you want to create. This field is enabled only if you select the BACKUP ALARMS BEFORE PURGE? check box. By default, the backup location of the default data store is considered. And, the file name is in the following format: <code>mm_dd_yyyy_hh_mm_ss</code>. For example: <code>11_25_2022_11_23_26.zip</code>. The time format followed is the 24-hour time notation.</p> <div data-bbox="669 1444 1421 1711" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: This file naming convention for alarm backup is standard to Historian. Even if you use other date settings such as <code>dd-mm</code>, the file name will still be saved in the <code>mm-dd</code> format.</p> </div> <p>The end time stamp in the file name indicates the time at which the alarms have been backed up but not the time till when the alarms are backed up. For example, suppose, at 8.00 am, you</p>

Field	Description
	back up alarms for the past two hours, the backup will contain alarms from 6:00 am to 8:00 am but may not contain an alarm generated at 8:00 am. The last alarm may have been at 7:50 am. But the backup file name will have the time stamp of 8:00:00 along with the date.
BACKUP ALARMS BEFORE PURGE?	Select the check box if you want to back up alarms before purging.

6. Select **Purge**.


The alarms data is purged. A backup file is created if you have selected the **BACKUP ALARMS BEFORE PURGE?** check box.

Purge Data Using the Utility

This topic describes how to purge alarms using the Proficy Historian Alarm and Event Data Migration utility. You can also [purge them at a command prompt \(on page 1223\)](#).

Ensure that you are a member of the ihsecurityAdmins security group.

1. Run the `Proficy.Historian.AandE.Migration.exe` file. By default, it is located at `C:\Program Files (x86)\Proficy\Proficy DataBase`.
The **Proficy Historian Alarm and Event Data Migration** window appears.
2. Select **Purge Alarms**.



The **Purge Alarms** section appears.

3. Enter values as described in the following table.

Field	Description
SQL Instance Name	Enter the Microsoft SQL server instance that contains the data that you want to purge.
Database Name	Enter the name of the database that contains the data that you want to purge.
Authentication	Select Windows or SQL depending on whether you want to provide credentials of the Windows machine or the SQL server, respectively.
User Id	Enter the User ID of the Windows user or the SQL user (depending on whether you have selected Windows or SQL).
Password	Enter the password of the Windows or SQL user account (depending on whether you have selected Windows or SQL).

4. Select **Connect**.

A message appears, specifying that a connection to the Microsoft SQL database is established. The **Space Consumed (MB)** and the **Alarms and Events count** fields are populated with the appropriate values.

5. If you want to purge data within a time range, provide the start time and end time in the **From** and **To** fields, respectively.

6. If you want to purge data for a certain duration till the current date and time, enter a value in the **Retention** field, and then select the units of measurement. The default value is 1 minute.

If you want to purge data until last week, enter 7, and then select **Days**. Data from the beginning until seven days prior to the current date and time is purged.

7. Select **Begin Purge**.

The data received within the specified duration is purged. You can check the log data in the `Proficy.Historian.AandE.Migration.log` file. By default, this file is located in the `C:\Program Files(x86)\Proficy` folder.

In addition, an audit log is created at `..\Proficy Historian Data\LogFiles` folder.

Purge Alarms at a Command Prompt

This topic describes how to purge alarms at a command prompt. You can also [purge them using the Proficy Historian Alarm and Event Data Migration utility \(on page 1221\)](#).

Ensure that you are a member of the `ihsecurityAdmins` security group.

1. Run the `ihPurgeAlarms.exe` file. By default, it is located at `C:\Program Files\Proficy\ProficyHistorian\Server\ihPurgeAlarms.exe`.
2. Use the following parameters to purge alarms.

Parameter	Description
<code>-s <Historian server></code>	The Historian server on which you want to access archive data. If you do not provide this parameter, the local machine is considered.
<code>-u <username></code>	The username to connect to the archiver.
<code>-p <password></code>	The password to connect to the archiver.
<code>-b "<file path>"</code>	The file path where you want to place the backup file of the purged alarms. If the path is not specified, the default backup path of the archive is considered.

Parameter	Description
	<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: You must enter the file path in double quotes (for example, "C:\\\\backup\\"). </div>
<p><code>-z 1 <file name></code></p>	<p>The name of the backup file in the .zip file format. For example, if you want to purge alarms older than 36 hours, but want to back up the data in a .zip file format, enter:</p> <pre style="background-color: #f0f0f0; padding: 5px;">ihPurgeAlarms.exe -h 36 -z 1</pre> <p>If you run this command, the backup file will be created in the default archive backup folder.</p>
<p><code>-d <number of Days prior to the current time></code></p>	<p>Indicates the time in days till the current date for which you want to purge alarms. For example, to purge alarms older than seven days, enter:</p> <pre style="background-color: #f0f0f0; padding: 5px;">-d 7</pre>
<p><code>-h <number of hours prior to the current time></code></p>	<p>Indicates the time in hours till the current time for which you want to purge alarms. For example, to purge alarms older than two and half days, enter:</p> <pre style="background-color: #f0f0f0; padding: 5px;">-d 2 -h 12</pre>
<p><code>-m <number of minutes prior to the current time></code></p>	<p>Indicates the time in minutes till the current time for which you want to purge alarms. For example, to purge alarms older than 3 hours 15 minutes, enter:</p> <pre style="background-color: #f0f0f0; padding: 5px;">-h 3 -m 15</pre>
<p><code>-sec <number of seconds prior to the current time></code></p>	<p>Indicates the time in seconds till the current time for which you want to purge alarms. For example, to purge alarms older than 30 seconds, enter:</p> <pre style="background-color: #f0f0f0; padding: 5px;">-sec 30</pre>

The alarms are purged, and an audit log is created at `..\Proficiency Historian Data \LogFiles` folder.

Close an Alarm


1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Collectors**.
3. From the list of collectors, select the alarms and events collector that you want to close.
4. Select **Close Alarms**.
The **Close Alarms** window appears.
5. In the **End Date/Time** field, enter the duration for which you want to close alarms.
6. Select **Show Alarms**.
A list of open alarms in the duration appear.
7. Select the alarms that you want to close, and then select **Close Alarms**.

Using the OPC AE Collector with FIX32 SCADA Systems

You cannot use an OPC alarms and events server with FIX32 SCADA systems. To collect alarm data from these systems, you can use a proxy for alarms through an iFIX node with an OPC alarms and events server. The OPC Classic Alarms and Events collector of Proficy Historian can then collect the data.


There are two different configurations that can occur in this instance:

1. A single proxy in which only one FIX32 system forwards its alarms through a particular iFIX node.



In this case, you can link the OPC Classic Alarms and Events collector to the FIX32 data collector. Refer to [Configure the OPC Alarms and Events Collector \(on page 2392\)](#). You can then query the data using clients such as Configuration Hub, Historian Excel add-in, and so on.

2. Multiple FIX32 system proxy alarms through a single iFIX node.



In this case, you cannot set the `Link To Data Collector` parameter to both FIX32 data collectors. As a result, it is not possible to create a relationship between alarm and tag data. Therefore, you cannot link the data using Historian Excel add-in.

To link the alarm and tag data in this scenario, perform an OLE DB query with a join between the `ItemID` column of the `ihAlarms` database and the `TagName` column of the `ihRawData` database. You can do this only if `No Prefix` has been added to the tagname.

The following example shows a parametrized query that uses the `AlarmID` property to find all values read from the corresponding tag for that alarm during the duration of the alarm.

```

SELECT  ihRawData.'Value', ihRawData.Tagname, ihRawData.'TimeStamp'
FROM    ihRawData, ihAlarms
WHERE   ihRawData.Tagname = ihAlarms.ItemID
AND     ( ihRawData.'TimeStamp' >= ihAlarms.Starttime )
AND     ( ihRawData.'TimeStamp' <= ihAlarms.'Timestamp' )
AND     ( ihAlarms.AlarmID = 13240 )
AND     ( ihRawData.SamplingMode = 'RawByTime' )
  
```

Chapter 8. Historian REST APIs

Introduction to Historian REST APIs

Historian APIs

Historian is a high performance data archiving system designed to collect, store, and retrieve time-based information at extremely high speed efficiently. The Historian environment provides a set of REST APIs to query data from the archives.

This document provides links for setting up your development environment, as well as information for getting started with the Historian services and their associated APIs.

Starting Historian 8.0, the default https port is 443. If you use the default port, you need not include it in the Rest API calls.

Also, the default admin client name is changed from admin to hostname.admin, and it is case-sensitive.

Example:

```
curl -u admin:adminsecret https://<nodename>:443/uaa/oauth/token -d  
'grant_type=client_credentials'
```

should be replaced with

```
curl -u hostname.admin:adminsecret https://<nodename>/uaa/oauth/token -d  
'grant_type=client_credentials'
```

See the following topics for more information:

- [About Security and Authentication \(on page 1227\)](#)
- [Standards \(on page 1229\)](#)
- [API Methods \(on page 1230\)](#)
- [API Status Messages \(on page 1230\)](#)


About Security and Authentication

For security purposes, Historian uses the Proficy Authentication service as a trusted source of tokens issued for authentication. It is a multi-tenant identity management service, used in Cloud Foundry, but also available as a standalone OAuth2 server. Its primary role is as an OAuth2 provider, issuing tokens for client applications to use when they act on behalf of Cloud Foundry users. It can also authenticate users with Cloud Foundry credentials, and can act as an SSO service using those credentials, or others.

It contains endpoints for managing user accounts, registering OAuth2 clients, and other management functions.

The following diagram shows how the Proficy Authentication server functions with a Python REST client:

Figure 7. Proficy Authentication Server and Python REST Client



Authorization

For exchanging data between the client-server system, user authentication is required. Once you have provided your client credentials, an access or bearer token is generated. This token is used for the REST APIs.

cURL command format for generating an oauth token for clients: `curl -u <client ID>:<client secret> https://<node name>:443/uaa/oauth/token -d 'grant_type=client_credentials'`

Example: `curl -u server1.admin:adminsecret https://server1:443/uaa/oauth/token -d 'grant_type=client_credentials'`

cURL command format for generating an oauth token for Proficiency Authentication users: `curl -d`

```
"client_id=<value>&client_secret=<value>&grant_type=password&username=<value>&password=<value>&token_format=opaque"
https://<node name>:8080/uaa/oauth/token
```

Example: `curl -d`

```
"client_id=historian_public_rest_api&client_secret=publicapisecret&grant_type=password&username=<value>&password=<value>"
https://<nodename>/uaa/oauth/token
```

In the following image, the actual token text is blurred for security concerns.

Figure 8. OAuth Access Token Sample



Client applications can access data using service REST API endpoints. Your application makes an HTTP request and parses the response. You can use any web-development language to access the APIs.

Standards

Historian APIs use a REST application architecture constrained by Hypermedia as the Engine of Application State (HATEOAS) that distinguishes it from most other network application architectures. Therefore, a client interacts with a network application entirely through hypermedia provided dynamically by application servers. The REST client doesn't need prior knowledge about how to interact with a particular application or server beyond a basic understanding of hypermedia.

As defined by the query parameters, the Historian APIs use "search" functions to access raw data using cURL and HTTP, while responses are in JSON format.

cURL is a command-line utility used to transfer data from or to a server, using one of the supported protocols, such as DICT, FILE, FTP, FTPS, GOPHER, HTTP, HTTPS, IMAP, IMAPS, LDAP, LDAPS, POP3, POP3S, RTMP, RTSP, SCP, SFTP, SMTP, SMTPS, TELNET and TFTP. The command is designed to work without user interaction.

cURL offers many useful functions such as proxy support, user authentication, FTP upload, HTTP post, SSL connections, cookies, file transfer resume, user and password authentication, and more.

You can run the sample commands provided in this document from Bash on Windows in the Windows operating system, and also in Linux Shell in the Linux operating system.

As a prerequisite, make sure you install cURL on your system, if it is not already installed. Run the `curl --version` command on Windows Bash or Linux shell to check if cURL is installed on your system.



Important:

Do not create your own URIs. Instead, use the links in this document and in the responses to navigate between resources.

API Methods

The Historian APIs use GET, POST, PUT, and DELETE methods.

Method	Usage
GET	Retrieves a resource.
POST	Creates (or adds) a resource.
PUT	Updates a resource.
DELETE	Removes a resource.

API Status Messages

In its use of the following HTTP status codes, the Historian API services adhere as closely as possible to standard HTTP and REST conventions.

Status Code	Usage
200 OK	Success message. The request has completed.
201 Created	Success message. A new resource has been created. The resource URI is available from the location header in the response.
204 No Content	Success message. An update to an existing resource has been applied.
400 Bad Request	Error message. The request was malformed. The response body provides additional information.

Status Code	Usage
401 Unauthorized	Error message. Either you are not authenticated, or the authentication is incorrect. You must re-authenticate and try again.
403 Forbidden	Error message. You do not have permission to access this resource.
404 Not Found	Error message. The requested resource does not exist.
500 Internal Error	Error message. The server encountered an unexpected condition that prevented it from fulfilling the request.

Common API Parameters

Overview of Commonly Used API Parameters

The Historian REST service provides various REST API calls to retrieve the current tags list and query data with different sampling modes. Most of these API calls use the following common parameters:

- [tagNames \(on page 1231\)](#)
- [Start and End timestamps \(on page 1232\)](#)
- [TagSamples \(on page 1232\)](#)
- [DataSamples \(on page 1234\)](#)
- [SamplingModeType \(on page 1235\)](#)
- [Direction \(on page 1237\)](#)
- [CalculationModeType \(on page 1237\)](#)
- [FilterModeType \(on page 1243\)](#)
- [ReturnDataFields \(on page 1244\)](#)
- [Payload \(on page 1245\)](#)
- [Error Code Definitions \(on page 1251\)](#)

TagNames Parameter

By default, the Historian REST service provides support to read samples for multiple tags. Multiple tag names are separated by semicolons (;). For example, "tagname1;tagname2;tagname3".

```
https://<historianservername>:443/historian-rest-api
/v1/datapoints/currentvalue?tagNames=tagName1;tagName2;tagName3

https://RestTestsNode/historian-rest-api/v1/datapoints/currentvalue?tagNames=TAG01;TAG02
```

Encode the semicolon as %3B if using the URI format, as the semicolon is also a valid character for a Historian name, and the web service parses the tag names incorrectly if a tag name contains a semicolon.

Start and End Timestamps Parameter

For the Start and End Timestamps parameter, the Timestamp format in the URI must be in ISO data format, such as `YYYY-MM-DDTHH:mm:ss.SSSZ`.

EPOCH time (standard base time) is only valid in the JSON-format request body or response body, such as `\Date(928167600000-0500)\`. If you use the same timestamp for start and end timestamps, the request returns a single result.

All timestamps passed to the REST service must be formatted as UTC timestamps.

Object Name	Description
StartTime	Start time of the query. This represents the earliest timestamp for any tag contained in the query. If no StartTime is specified, the start time is two hours prior to running the query.
EndTime	End time of the query. This represents the latest timestamp for any tag contained in the query. If no EndTime is specified, the end time is the time that the query runs.

TagSamples Parameter

The TagSamples parameter is the output from the REST API calls.

Property Name	Property Type	Description
TagName	String	Name of the tag.
DataType	String	Tag Data Type Value:

Property Name	Property Type	Description
		<ul style="list-style-type: none"> • Blob – Stores tags as binary large objects. The Blob datatype generally refers to undetermined binary data types, such as an Excel spreadsheet, a PDF file, or a Word file. • Boolean (one byte) – Stores boolean values. Valid values for the boolean data type are 0=FALSE and 1=TRUE. If the user sends zero, the value is taken as zero. Anything other than zero, the value is treated as one. • Byte (one byte) – Stores integer values. Valid values for the byte data type are -128 to +127. • SingleFloat (four bytes) – Stores decimal values up to six places. Valid ranges for the single float data type are 1.175494351e-38F to 3.402823466e+38F • DoubleFloat (eight bytes) – Stores decimal values up to 15 places. Valid values for the double float data type are 2.2250738585072014e-308 to 1.7976931348623158e+308. • SingleInteger (two bytes) – Stores whole numbers, without decimal places. Valid values for the single integer data type are -32767 to +32767. • DoubleInteger (four bytes) – Stores whole numbers, without decimal places. Valid values for the double integer data type are -2147483648 to +2147483648. • FixedString (Configured by user) – Stores string data of a fixed size. Valid values are between 0 and 255 bytes. • Float – Single float. • Integer – Single integer. • MultiField – Stores string data that has multiple words. • QuadInteger (eight bytes) – Stores whole numbers without decimal places. Valid values for the quad integer data type are -9,223,372,036,854,775,808 (negative nine quintillion) to +9,223,372,036,854,775,807 (positive nine quintillion). • Scaled (two bytes) – Lets you store a four-byte float as a twobyte integer in the Historian archive. The scaled data type saves disk space but sacrifices data precision as a result. • Time – Returns or sets the type of time stamping applied to data at collection time.

Property Name	Property Type	Description
		<ul style="list-style-type: none"> • UDoubleInteger (Unsigned Double Integer) (four bytes) – Stores whole numbers without decimal places. Valid values for the unsigned double integer data type are 0 to 4,294,967, 295 (4.2 billion). • Undefined – Data type is not defined. • UQuadInteger (Unsigned Quad Integer) (eight bytes) – Stores whole numbers without decimal places. Valid values for the unsigned quad integer data type are 0 to 18,446,744,073,709,551,615 (19 quintillion). • USingleInteger (Unsigned Single Integer) (two bytes) – Stores whole numbers without decimal places. Valid values for the unsigned single integer data type are 0 to 65535. • VariableString (No fixed size) – Stores string values of undetermined size. This data type is useful if you cannot rely on a constant string length from your data source. • Array – Returns an array of tags from your data source. You can specify orientation, size, and number of rows returned in the array.
ErrorCode	Error Code	<p>Error Code Definition</p> <p>See Error Code Definition (on page 1251) for more information.</p>
Samples	Data Sample	See DataSample Parameter (on page 1234) for more information.

DataSample Parameter

The DataSample Parameter specifies the number of data samples to retrieve from the archive. Samples are evenly spaced within the time range defined by start time and end time for most sampling modes.

Property Name	Property Type	Description
Value	String	<p>Format for a multi-field tag like</p> <pre>{ "field1": "1", "field2": "1000.0" }</pre> <p>(user-defined type tag).</p>

Property Name	Property Type	Description
		JavaScript code can parse the value string as a JSON object. All field values are string.
TimeStamp	DateTime	Start and end times of the query. If no start time is specified, the start time is two hours prior to running the query. If no EndTime is specified, the end time is the time the query runs.
Quality	Integer (Enumerated value of DataQuality.StatusType)	Data type consisting of a set of named values called elements, members or enumerators of the type. Property values reflect quality as "quality is good" or " quality is bad". Value and Status <ul style="list-style-type: none"> • 0 – Bad • 1 – Uncertain • 2 – NA • 3 – Good

SamplingModeType Parameter

The SamplingModeType parameter is the mode of sampling data from the archive. The default setting for the Sampling Mode is `Calculated`.

Properties	Description	Value
Undefined	Sampling mode is not defined.	0
CurrentValue	Retrieves the current value. The time- interval criteria are ignored.	1
Interpolated	Retrieves evenly-spaced, interpolated values based on interval or NumberOf-Samples and the time-frame criteria.	2
Trend	Returns the raw minimum and raw maximum value for each specified interval.	3

Properties	Description	Value
	Use the Trend sampling mode to maximize performance when retrieving data points for plotting. For the Trend sampling mode, if the sampling interval does not evenly divide by the interval length, Historian ignores any leftover values at the end, rather than putting them into a smaller interval.	
RawByTime	Retrieves raw archive values based on time-frame criteria.	4
RawByNumber	Retrieves raw archive values based on the StartTime criteria, the NumberOfSamples, and Direction criteria. The End-Time criteria is ignored for this sampling mode.	5
Calculated	Retrieves evenly spaced calculated values based on NumberOfSamples, interval, the time frame criteria, and the CalculationMode criteria.	6
Lab	Returns actual collected values without interpolation.	7
InterpolatedtoRaw	Provides raw data in place of interpolated data when the number of samples are fewer than the available samples.	8
TrendtoRaw	The TrendtoRaw sampling mode almost always produces the same results as the Trend sampling mode. However, when more samples are requested than there are raw data points, the TrendtoRaw sampling mode returns all available raw data points with no further processing. Use TrendtoRaw in place of Trend when this condition exists.	9

Properties	Description	Value
LabtoRaw	Provides raw data for the selected calculated data, when NumberOfSamples is less than the available samples.	10
RawByFilterToggle	Returns filtered time ranges using the following values: <ul style="list-style-type: none"> • 1 – true • 0 – false <p>This sampling mode is used with the time range and filter tag conditions. The response string starts with a starting time stamp and ends with an ending timestamp.</p>	11

Direction Parameter

The Direction Parameter specifies the direction (Forward or Backward from the starting time) of data sampling from the archive. The default value is Forward.

Direction	Value
Forward	1
Backward	0

CalculationModeType Parameter

The CalculationModeType parameter is only applied if the Sampling Mode is set to Calculated. It represents the type of calculation to use on the archive data. The default Calculation Mode, if none is specified, is Average.

Calculation Mode Type	Description	Value
Undefined	Calculation mode is not defined.	0
Average	Retrieves the time-weighted average for each calculation interval.	1

Calculation Mode Type	Description	Value
StandardDeviation	Retrieves the time-weighted standard deviation for each calculation interval.	2
Total	<p>Retrieves the time-weighted rate total for each calculation interval.</p> <p>Use rate totals when working with a continuous measurement. Time weighting takes into account that compressed data is not evenly spaced in time. A factor must be applied to the total value to convert into appropriate engineering units. As a rate total, the default is Units/Day. If the actual units of the continuous measurement are Units/Minute, you would multiply the results by 1440 (minutes per day) to convert the total into appropriate engineering units.</p>	3
Minimum	Retrieves the minimum value for each calculation interval.	4
Maximum	Retrieves the maximum value for each calculation interval.	5
Count	<p>Counts the number of raw samples found with good quality in the interval.</p> <p>Value is the count of raw samples with good quality in the interval. The values of each sample are ignored. The Count does not include any samples of bad quality, including the start and end of collection markers.</p> <p>For Quality, the percentage of good samples is always 100, even if the interval does not contain any raw samples, or contains only bad quality samples.</p> <p>Count is useful for analyzing the distribution of the raw data samples to determine the ef-</p>	6

Calculation Mode Type	Description	Value
	<p>fect of compression deadbands. It is also useful to determine which tags are consuming the most archive space.</p>	
RawAverage	<p>Retrieves the arithmetic average of all good quality raw samples for each calculation interval.</p> <p>Value is the sum of all good quality samples in the interval, divided by the number of good quality samples in the interval. All bad quality samples are ignored. That is RawAverage is equivalent to RawTotal divided by the Count.</p> <p>For Quality, if there are no raw samples in the interval or if they all are bad quality, then the percentage of good is 0. Otherwise, the percentage of good is always 100, even if the interval contains bad quality samples.</p> <p>RawAverage is useful for calculating an accurate average when a sufficient number of raw samples are collected.</p>	7
RawStandardDeviation	<p>Retrieves the arithmetic standard deviation of raw values for each calculation interval.</p> <p>For Value, any raw point of bad data quality is ignored.</p> <p>For Quality, if there are no raw samples in the interval or they all have bad quality, then the percentage of good is 0. Otherwise, the percentage of good is always 100, even if the interval contains bad quality samples.</p> <p>RawStandardDeviation is useful for calculating an accurate standard deviation when</p>	8

Calculation Mode Type	Description	Value
	a sufficient number of raw samples are collected.	
RawTotal	<p>Retrieves the arithmetic total (sum) of sampled values for each interval.</p> <p>Value is the sum of the good quality values of all raw samples in the interval. All bad quality samples are ignored.</p> <p>For Quality, the percentage of good samples is always 100, even if the interval does not contain any raw samples or it contains only bad quality samples.</p> <p>If the same start and end times are used, and the time span is treated as a single interval, then all values are added together.</p> <p>RawTotal is useful for calculating an accurate total when a sufficient number of raw samples are collected. Note that unlike ihTotal, this is a simple sum with no assumption that the values are rate values.</p>	9
MinimumTime	Retrieves the timestamp of the minimum value found within each calculation interval. It can be a raw or an interpolated value. The minimum must be a good data quality sample.	10
MaximumTime	Retrieves the timestamp of the maximum value found within each calculation interval. It can be a raw or an interpolated value. The maximum must be a good data quality sample.	11
TimeGood	Retrieves the amount of time (milliseconds) during the interval when the data is of good quality and the filter condition is met.	12

Calculation Mode Type	Description	Value
StateCount	Retrieves the amount of time a tag uses to transition to another state from a previous state during a time interval.	13
StateTime	Retrieves the duration that a tag stayed in a given state within an interval.	14
OPCQAnd	Retrieves the OPCQAND, bit-wise AND operation of all the 16-bit OPC qualities of the raw samples stored in the specified interval. Note that OPC Quality is a subfield for Quality-Value-Timestamp (QVT), so when this calculation mode is used, OPC Quality is considered for calculation.	15
OPCQOr	Retrieves the OPCQOR, bit-wise OR operation of all the 16-bit OPC qualities of the raw samples stored in the specified interval. Note that OPC Quality is a subfield for Quality-Value-Timestamp (QVT), so when this calculation mode is used, OPC Quality is considered for calculation.	16
FirstRawValue	Retrieves the first good raw sample value for a given interval. Value is the value of the raw sample, or zero if there are no good raw samples in the interval. For Quality, if there are not good raw samples in the interval, then the percentage of good is 0. Otherwise, the percentage of good is always 100, even if the interval contains bad quality samples. Note that Quality is the same for FirstRawValue and FirstRawTime.	17

Calculation Mode Type	Description	Value
	<p>The Raw sample has a quality of Good, Bad, or Uncertain, and that is converted to a 0 or 100 percent.</p>	
<p>FirstRawTime</p>	<p>Retrieves the first good raw timestamp for a given interval.</p> <p>Value is the timestamp of the sample or the year 1969 if there are no good raw samples in the interval.</p> <p>For Quality, if there are not good raw samples in the interval, then the percentage of good is 0. Otherwise, the percentage of good is always 100, even if the interval contains bad quality samples. Note that Quality is the same for FirstRawValue and FirstRawTime.</p> <p>The Raw sample has a quality of Good, Bad, or Uncertain, and that is converted to a 0 or 100 percent.</p>	<p>18</p>
<p>LastRawValue</p>	<p>Retrieves the last good raw sample value for a given time interval.</p> <p>Value is the value of the raw sample or zero if there are no good raw samples in the interval.</p> <p>For Quality, if there are no good raw samples in the interval, the percentage of good samples is 0. Otherwise, the percentage of good is always 100, even if the interval contains bad samples. Note that Quality is the same for LastRawValue and LastRawTime.</p> <p>The Raw sample has a quality of Good, Bad, or Uncertain, and that is converted to a 0 or 100 percent.</p>	<p>19</p>

Calculation Mode Type	Description	Value
LastRawTime	<p>Retrieves the last good timestamp of the last value for a given time interval.</p> <p>Value is the timestamp of the sample or the year 1969 if there are no good raw samples in the interval.</p> <p>For Quality, if there are no good raw samples in the interval, the percentage of good samples is 0. Otherwise, the percentage of good is always 100, even if the interval contains bad samples. Note that Quality is the same for LastRawValue and LastRawTime.</p> <p>The Raw sample has a quality of Good, Bad, or Uncertain, and that is converted to a 0 or 100 percent.</p>	20
TagStats	Retrieves the statistics for a tag from the archive stored in the specified interval.	21

FilterModeType Parameter

The FilterModeType parameter defines how time periods before and after transitions in the filter condition should be handled.

When the FilterModeType parameter is applied, then the Start time and End time are specified as:

- ExactTime
- BeforeTime
- AfterTime
- BeforeAndAfterTime

For example, AfterTime indicates that the filter condition should be True starting at the timestamp of the archive value that triggered the True condition, and leading up to the timestamp of the archive value that triggered the False condition.

Properties	Description	Value
ExactTime	Retrieves data for the exact times that the filter condition is True.	1
BeforeTime	Retrieves data from the timestamp of the last False filter condition to the timestamp of the next True condition.	2
AfterTime	Retrieves data from the timestamp of the True filter condition to the timestamp of the next False condition.	3
BeforeAndAfterTime	Retrieves data from the timestamp of the last False filter condition to the timestamp of the next False condition.	4

ReturnDataFields Parameter

The ReturnDataFields bitwise parameter specifies which data fields are returned in a query. Using it in a query returns data such as TimeStamp, and each field returns a Boolean value.

Each time-series data sample contains QVT (quality, value, and timestamp) values. If ReturnDataFields is not provided, then the default value of 0 is considered, and all QVT values are returned for each data sample. To return one of the data field properties, such as TimeStamp, use the TimeStamp option as shown in the table.

Properties	Description	Field value (Boolean)
All Fields	Specifies that all data fields are returned in the query.	0 (0000)
TimeStamp	The time stamp of the collected sample or an interval time stamp. When specified in the query, returns the TimeStamp property.	1 (0001)
Value	The collected value or sampled value; the data type of the value will be the same	2 (0010)

Properties	Description	Field value (Boolean)
	data type as the tag's raw data.	
Quality	<p>When specified in the query, returns the Quality property. Each sample in Current Value and Raw query retrieval has a quality of:</p> <ul style="list-style-type: none"> • Good (3) • Not Available (2) • Uncertain (1) • Bad (0) <p>Interpolated and Lab Retrieval express quality as "percent good".</p>	4 (0100)

Payload Parameter

This parameter queries for the tag properties requested from the server.

Use the Payload parameter to query for all the tag properties to return from the server. In the Update Tag Configuration API, you must provide the actual tag property value. However, in the Get Tag Properties API, you must provide the property name and value of 1 (true), so the property can be read from the server and returned.

The properties listed in the following table are valid in APIs that use the Payload parameter, unless otherwise specified. For Property Names used in the Get Tag Properties API, the property name is always a Boolean (true/false) value, while it can be a string or integer for other APIs.

Property Name	Property Type	Description
AllFields	Boolean	Used for Get Tag Properties API.
Name	Boolean, String	Used for the Get Tag Properties API, Add Single Tag API, and Add Bulk Tags API.
Description	String	
EngineeringUnits	String	

Property Name	Property Type	Description
Comment	String	
DataType : ihDataType	SignedInteger	Type definition is an enumerated type "ihDataType". <pre> { ihDataTypeUndefined = 0, ihScaled, ihFloat, ihDoubleFloat, ihInteger, ihDoubleInteger, ihFixedString, ihVariableString, ihBlob, ihTime, ihInt64, ihUInt64, ihUInt32, ihUInt16, ihByte, ihBool, ihMultiField, ihArray, ihMaxDataType } ihDataType;</pre>
FixedStringLength	UnsignedChar	
CollectorName	String	
SourceAddress	String	
CollectionType : ihCollectionType	SignedInteger	Type definition is an enumerated type "ihCollectionType". <pre> { ihUnsolicited = 1, ihPolled } ihCollectionType;</pre>

Property Name	Property Type	Description
CollectionInterval	SignedIntegral	
CollectionOffset	UnsignedLong	
LoadBalancing	Boolean	
TimeStampType : ihTimeStampType	SignedIntegral	Type definition is an enumerated type "ihTimeStampType". <pre>{ ihSource = 1, ihInterface, } ihTimeStampType;</pre>
HiEngineeringUnits	Double	
LoEngineeringUnits	Double	
InputScaling	Boolean	
HiScale	Double	
LoScale	Double	
CollectorCompression	Boolean	
CollectorDeadbandPercentRange	Float	
ArchiveCompression	Boolean	
ArchiveDeadbandPercentRange	Float	
General1	String	
General2	String	
General3	String	
General4	String	
General5	String	
ReadSecurityGroup	String	
WriteSecurityGroup	String	

Property Name	Property Type	Description
AdministratorSecurityGroup	String	
LastModified	Boolean	Used for Get Tag Properties API.
LastModifiedUser	Boolean	Used for Get Tag Properties API.
InterfaceType	Boolean	Used for Get Tag Properties API.
CollectorType : ihInterfaceType	SignedIntegral	Type definition is an enumerated type "ihInterfaceType". <pre>{ ihInterfaceUndefined = 0, ihIFix, ihRandom, ihOPC, ihFile, ihIFixLabData, ihManualEntry, ihOther, ihCalcEngine, ihServerToServer, ihPI, ihOPCAE, ihCIMPE, ihPIDistributor, ihCIMME, ihPerfTag, ihCustom, ihServerToServerDistributor, ihWindowsPerfMon, } ihInterfaceType;</pre>
UTCBias	SignedIntegral	
AverageCollectionTime	Boolean	Used for Get Tag Properties API.
CalculationDependencies	StringArray	
CollectionDisabled	Boolean	

Property Name	Property Type	Description
ArchiveCompressionTimeout	Unsigned-Long	
CollectorCompressionTimeout	Unsigned-Long	
SpikeLogic	Boolean	
SpikeLogicOverride	Boolean	
CollectorAbsoluteDeadbanding	Boolean	
CollectorAbsoluteDeadband	Double	
ArchiveAbsoluteDeadbanding	Boolean	
ArchiveAbsoluteDeadband	Double	
StepValue	Boolean	
TimeResolution : ihTimeResolution	SignedIntegral	Type definition is an enumerated type "ihTimeResolution". <pre>{ ihSeconds = 0, ihMilliseconds, ihMicroseconds, ihNanoseconds } ihTimeResolution;</pre>
ConditionCollectionEnabled	Boolean	
ConditionCollectionTriggerTag	String	
ConditionCollectionComparison : ihConditionCollectionComparison	SignedIntegral	Type definition is an enumerated type "ihConditionCollectionComparison". <pre>{ ihConditionComparisonUndefined = 0, ihConditionComparisonEqual, ihConditionComparisonLessThan, ihConditionComparisonLessThanEqual, ihConditionComparisonGreaterThan, ihConditionComparisonGreaterThanEqual,</pre>

Property Name	Property Type	Description
		<pre>ihConditionComparisonNotEqual } ihConditionCollectionComparison;</pre>
ConditionCollectionCompareValue	String	
ConditionCollectionMarkers	Boolean	
Calculation	String	When the Calculation field is used, then two more conditions are required. Calculation is not a specific field for a tag property. If the tag's collector or interface type is Server-to-server and the Calculation field is set (not Null), then the field value is set to the source address.
TagId	Boolean	Used for Get Tag Properties API.
EnumeratedSetName	String	
DataStoreName	String	
DefaultQueryModifiers	Long Long	
UserDefinedTypeName	String	
NumberOfElements	SignedIntegral	
DataDensity : ihTagDataDensity	SignedIntegral	<p>Type definition is an enumerated type "ihTagDataDensity".</p> <pre>{ ihDataDensityUndefined = 0, ihDataDensityMinimum = 1, ihDataDensityMedium = 4, ihDataDensityMaximum = 7 } ihTagDataDensity;</pre>
CalcType : ihTagCalcType	SignedIntegral	<p>Type definition is an enumerated type "ihCalcType".</p> <pre>{ ihRawTag = 0, ihAnalyticTag = 1,</pre>

Property Name	Property Type	Description
		<pre>ihPythonExprTag = 2 } ihTagCalcType;</pre>
HasAlias	Boolean	Used for Get Tag Properties API.
IsStale	Boolean	Used for Get Tag Properties API.

Error Code Definitions

The following table provides the values and definitions for the ErrorCode parameter.

Table 88. Error Code Definitions

Error Code Value:	Error Code Definition
Success = 0	Operation successful.
Failed = -1	Operation failed.
Timeout = -2	Operation failed due to timeout.
NotConnected = -3	Not connected to Historian server.
CollectorNotFound = -4	The given collector does not exist on the server.
NotSupported = -5	Operation not supported.
DuplicateData = -6	Attempt to overwrite an existing data sample.
InvalidUsername = -7	Bad user name or password.
AccessDenied = -8	Insufficient permissions for operation.
WriteInFuture = -9	Attempted data write too far in the future.
WriteArchiveOffline = -10	Attempted data write to an offline archive.
WriteArchiveReadOnly = -11	Attempted data write to a read-only archive.
WriteOutsideActiveRange = -12	Attempted data write beyond the configured active range.
WriteNoArchiveAvailable = -13	Attempted data write with no available archives.
InvalidTagName = -14	The requested tag was not found.
LicensedTagCountExceeded = -15	Number of licensed tags exceeded.

Table 88. Error Code Definitions (continued)

Error Code Value:	Error Code Definition
LicensedConnectionCountExceeded = -16	Number of licensed server connections exceeded.
InternalLicenseError = -17	Internal license error.
NoValue = -18	No available tag data.
DuplicateCollector = -19	The given collector name already exists on the server.
NotLicensed = -20	Server or feature is not licensed.
CircularReference = -21	Circular reference detected in calculation.
BackupInsufficientSpace = -22	Insufficient disk space to perform backup.
InvalidServerVersion = -23	Operation unsupported due to server version.
QueryResultSizeExceeded = -24	Upper limit on query results exceeded.
DeleteOutsideActiveRange = -25	Attempted data delete outside allowed modification interval.
AlarmArchiverUnavailable = -26	Alarms and Events subsystem unreachable.
ArgumentException = -27	A supplied argument is invalid.
ArgumentNullException = -28	A supplied argument is NULL.
ArgumentOutOfRangeException = -29	A supplied argument is outside the valid range.
InvalidEnumeratedSet = -30	The requested Enumerated Set was not found.
InvalidDataStore = -31	The requested data store was not found.
NotPermitted = -32	Operation not permitted.
InvalidCustomDataType = -33	The Custom data type is not supported.
ihSTATUS_EXISTING_USERDEF_REFERENCES = -34	N/A
ihSTATUS_INVALID_TAGNAME_DELETEDTAG = -35	N/A
ihSTATUS_INVALID_DHS_NODENAME = -36	N/A
ihSTATUS_DHS_SERVICE_IN_USE = -37	N/A

Table 88. Error Code Definitions (continued)

Error Code Value:	Error Code Definition
ihSTATUS_DHS_STORAGE_IN_USE = -38	N/A
ihSTATUS_DHS_TOO_MANY_NODES_IN_MIRROR = -39	N/A
ihSTATUS_ARCHIVE_IN_SYNC = -40	N/A
InvalidArchiveName= -41	N/A
InvalidSession = 1	Session id is invalid.
SessionExpired = 2	Session has expired.
UnknownError = 3	Unknown error, please check server log.
NoValidClientBufferManager= 4	No valid client buffer manager.
NoValueInDataSet = 5	No value in returned data set.
TagNotExisting = 6	Tag doesn't exist.
ClientBufferManagerCommunicationError = 7	Service call to central buffer server fail.
TagTypeNotSupported=8	Tag type is not supported.
ValueTypeNotMatchTagDataType = 9	Value type doesn't match tag data type.
InvalidParameter=10	Invalid query parameter.
TagSearchResultIsHuge = 11	Tag Search Criteria result was more than 5000.
InvalidHistorianServer=12	No valid server or historian server name isn't in the server list.
ihSTATUS_INVALID_INTERFACETYPE = -49	The collector type is not valid. For a list of collector types, refer to Collector Type and Subtype (on page 1339) .
ihSTATUS_INTERFACE_START_FAIL = -50	Starting the collector has failed.
ihSTATUS_INTERFACE_STOP_FAIL = -51	Stopping the collector has failed.

Historian REST APIs

Overview of the Historian REST APIs

Historian provides REST APIs to manage Historian systems, collectors, data stores, and tags. In addition, it provides APIs to install and manage collector instances.



Important:

Port 443 is used in examples and sample code. If you copy and paste the sample code from Help, you must change this port to your installed port.

Managing Systems

The Get DHS Machines API

Using the Get DHS Machines API, you can view the list of DHS machines in a location.

METHOD	GET
URI	<code>https://<historianservername>/historian-rest-api/v1/dhsmachines?storageName=</code>
SAMPLE QUERY PARAM GET URL	<code>https://<historianservername>/historian-rest-api/v1/dhsmachines?storageName=xx</code>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": [{ "NodeName": "xyz", "IsAlreadyAdded": true }] }</pre>

	<pre>] } } } </pre>
SAMPLE cURL COMMAND	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/dhsmachines?storageName=xxx </pre>

Table 89. Query Parameters

Parameter	Description	Required?	Values
storageName	The value of the location whose DHS machines you want to view.	Yes	String

Table 90. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Get DHS Services API

Using the Get DHS Services API, you can view the list of DHS services in a data store.

METHOD	GET
URI	<pre> https://<historianservername>/historian-rest-a pi/v1/dhsservices?dhSServiceMask=&withReason=fa lse </pre>
SAMPLE QUERY PARAM GET URL	<pre> https://<historianservername>/historian-rest-a pi/v1/dhsservices?dhSServiceMask =*&withReason=false </pre>

SAMPLE RESPONSE

```
{

  "ErrorCode": 0,

  "ErrorMessage": null,

  "Data": [

    {

      "LogicalName":

"ConfigManager_NPI212611749M1",

      "NodeName": "NPI212611749M1",

      "ServiceType": 4,

      "Status": 1,

      "TCPPort": 14002

    },

    {

      "LogicalName":

"DataArchiver_NPI212611749M1",

      "NodeName": "NPI212611749M1",

      "ServiceType": 2,

      "Status": 1,

      "TCPPort": 14001

    },

  ],

}
```

```
{  
  
  "LogicalName":  
  "ClientManager_NPI212611749M1",  
  
  "NodeName": "NPI212611749M1",  
  
  "ServiceType": 3,  
  
  "Status": 1,  
  
  "TCPPort": 14000  
  
},  
  
{  
  
  "LogicalName":  
  "DiagnosticsManager_NPI212611749M1",  
  
  "NodeName": "NPI212611749M1",  
  
  "ServiceType": 5,  
  
  "Status": 1,  
  
  "TCPPort": 14003  
  
},  
  
{  
  
  "LogicalName":  
  "DataArchiver_distmachine2",  
  
  "NodeName": "distmachine2",
```

```
        "ServiceType": 2,

        "Status": 0,

        "TCPPort": 14001

    },

    {

        "LogicalName":

        "DataArchiver_distmachine1",

        "NodeName": "distmachine1",

        "ServiceType": 2,

        "Status": 1,

        "TCPPort": 14001

    },

    {

        "LogicalName":

        "ClientManager_distmachine1",

        "NodeName": "distmachine1",

        "ServiceType": 3,

        "Status": 1,

        "TCPPort": 14000

    }

}
```

	<pre> }, { "LogicalName": "DiagnosticsManager_distmachine1", "NodeName": "distmachine1", "ServiceType": 5, "Status": 0, "TCPPort": 14003 }] } </pre>
<p>SAMPLE cURL COMMAND</p>	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/dhsservices?dhSServiceMask=*&withReason=fa lse </pre>

Table 91. Query Parameters

Parameter	Description	Required?	Values
withReason	Indicates whether the reason must be retrieved in the API response.	Yes	Boolean
dhSServiceMask	The value of the DHS service mask.	Yes	String

Table 92. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Get Server Properties API

Using the Get Server Properties API, you can view the list of properties of a server.

METHOD	GET
URI	<code>https://<historianservername>/historian-rest-api/v1/serverproperties</code>
SAMPLE QUERY PARAM GET URL	<code>https://<historianservername>/historian-rest-api/v1/serverproperties</code>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": { "Storages": [{ "StorageName": "System Storage", "StorageType": 2, "NumberOfDataStores": 1, "NumberOfArchivers": 0, "DataStores": [</pre>

```
        "System"

    ],

    "Id":
"861C2743-72E0-46FC-9B31-90E28CC39B8D",

    "IsDefault": false,

    "LastModifiedUser": null,

    "LastModifiedTime":
"1970-01-01T00:00:00.000Z",

    "ArchiverServices": []

},

{

    "StorageName": "xyz",

    "StorageType": 0,

    "NumberOfDataStores": 3,

    "NumberOfArchivers": 1,

    "DataStores": [

        "ScadaBuffer",

        "DHSSystem",

        "User"
```

```
    ],  
  
    "Id":  
    "5F267DF3-879A-4222-8A0E-D31EDEA83C14",  
  
    "IsDefault": true,  
  
    "LastModifiedUser": null,  
  
    "LastModifiedTime":  
    "1970-01-01T00:00:00.000Z",  
  
    "ArchiverServices": [  
  
        {  
  
            "LogicalName":  
            "DataArchiver_xyz",  
  
            "NodeName": "xyz",  
  
            "ServiceType": 2,  
  
            "IsAlreadyAdded": true,  
  
            "TCPPort": 14001  
  
        }  
  
    ]  
  
    }  
  
    ],  
  
    "Servers": [  

```

```
{  
  
  "LogicalName":  
"DataArchiver_xyz0",  
  
  "NodeName": "xyz",  
  
  "ServiceType": 2,  
  
  "Status": 1,  
  
  "TCPPort": 14001,  
  
  "MemoryVMSize": "4778",  
  
  "TotalFailedWrites": "0",  
  
  "WriteCacheHitRatio": "0.748",  
  
  "TotalOutOfOrder": "3",  
  
  "CompressionRatio": "0.321",  
  
  "ReadQueueSize": "0",  
  
  "WriteQueueSize": "0",  
  
  "MsgQueueSize": "0",  
  
  "ReadQueueProcessingRate": "1",  
  
  "WriteQueueProcessingRate":  
"31",  
  
  "MsgQueueProcessingRate": "0"  
  
}
```

	<pre>] } } </pre>
SAMPLE cURL COMMAND	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/serverproperties </pre>

Table 93. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Get System Statistics API

Using the Get System Statistics API, you can view the statistics of a system.

METHOD	GET
URI	<pre> https://<historianservername>/historian-rest-a pi/v1/systemstats </pre>
SAMPLE QUERY PARAM GET URL	<pre> https://<historianservername>/historian-rest-a pi/v1/systemstats </pre>
SAMPLE RESPONSE	<pre> { "ErrorCode": 0, "ErrorMessage": null, "Data": { "Utilization": { </pre>

```
"WriteCacheHitRatio": "0.499",

"SpaceConsumptionRate": "",

"CompressionRatio": "0.199",

"ReadQueueSize": "0",

"WriteQueueSize": "0",

"MsgQueueSize": "0",

"ReadQueueProcessRate": "3",

"WriteQueueProcessRate": "0",

"MsgQueueProcessRate": "0",

"MemoryVMUsage": "62",

"OutOfOrderRate": "0",

"ReadThreadUsage": "0",

"WriteThreadUsage": "0",

"FailedWriteRate": "0",

"DiskFreeSpace": "59828"

},

"AlarmEvents": {

"AverageAlarmRate": ""
```

```
    },  
  
    "TotalCollectors": {  
  
        "TotalCollectors": 1,  
  
        "RunningCollectors": 1,  
  
        "StoppedCollectors": 0,  
  
        "UnknownCollectors": 0  
  
    },  
  
    "Licence": {  
  
        "ActualDataStores": 3,  
  
        "MaxDataStores": 200,  
  
        "ActualTags": 0,  
  
        "MaxTags": 2147483647,  
  
        "ActualUsers": 0,  
  
        "MaxUsers": 1000  
  
    }  
  
    }  
  
}
```

SAMPLE cURL COMMAND

```
curl -i -H "Accept: application/json" -H  
"Authorization: Bearer <TOKEN>"
```

	<pre>https://<historianservername>/historian-rest-api/systemstats</pre>
--	---

Table 94. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Get Read Sample and Receive Rate API

Using the Get Read Sample and Receive Rate API, you can view the read rate and receive rate of a system.

METHOD	GET
URI	<p>Read Sample Rate</p> <pre>https://<historianservername>/historian-rest-api/v1/performancecounter/perftagdata/PerfTag_AverageEventRate/--/starttime/endtime/interval</pre> <p>Receive Rate</p> <pre>https://<historianservername>/historian-rest-api/v1/performancecounter/perftagdata/PerfTag_AverageReadRawRate/--/starttime/endtime/interval</pre>
SAMPLE GET URI	<pre>https://<historianservername>/historian-rest-api/v1/performancecounter/perftagdata/PerfTag_AverageEventRate/--/2020-12-15T11:19:01.719Z/2020-12-15T12:19:01.719Z/360000</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0,</pre>

```
"ErrorMessage": null,  
  
"Data": [  
  
  {  
  
    "TagName":  
"PerfTag_AverageEventRate",  
  
    "ErrorCode": 0,  
  
    "DataType": "DoubleFloat",  
  
    "Samples": [  
  
      {  
  
        "TimeStamp":  
"2020-11-18T05:35:22.612Z",  
  
        "Value": "0",  
  
        "Quality": 0  
  
      },  
  
      {  
  
        "TimeStamp":  
"2020-11-18T05:47:22.612Z",  
  
        "Value": "0",  
  
        "Quality": 0  
  
      },  
  
    ]  
  
  }  
  
]
```

```
{  
  
    "TimeStamp":  
    "2020-11-18T05:53:22.612Z",  
  
    "Value": "0",  
  
    "Quality": 0  
  
},  
  
{  
  
    "TimeStamp":  
    "2020-11-18T06:11:22.612Z",  
  
    "Value": "0",  
  
    "Quality": 0  
  
},  
  
{  
  
    "TimeStamp":  
    "2020-11-18T06:29:22.612Z",  
  
    "Value": "0",  
  
    "Quality": 0  
  
}  
  
]  
  
}
```

	<pre> } } </pre>
SAMPLE cURL COMMAND	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/performancecounter/perftagdata/ PerfTag_AverageEventRate/--/2020-12-15T11:19:01 .719Z/2020-12-15T12:19:01.719Z/360000 </pre>

Table 95. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Get Storages API

Using the Get Storages API, you can view the list of locations in a system.

METHOD	GET
URI	<pre> https://<historianservername>/historian-rest-a pi/v1/storages?storageMask= </pre>
SAMPLE QUERY PARAM GET URL	<pre> https://<historianservername>/historian-rest-a pi/v1/storages?storageMask=* </pre>
SAMPLE RESPONSE	<pre> { "ErrorCode": 0, "ErrorMessage": null, "Data": [{ </pre>

```
    "StorageName": "System Storage",

    "StorageType": 2,

    "NumberOfDataStores": 1,

    "NumberOfArchivers": 0,

    "DataStores": [

        "System"

    ],

    "Id":

    "861C2743-72E0-46FC-9B31-90E28CC39B8D",

    "IsDefault": false,

    "LastModifiedUser": null,

    "LastModifiedTime":

    "1970-01-01T00:00:00.000Z",

    "ArchiverServices": []

},

{

    "StorageName": "srinivaswin10",

    "StorageType": 0,

    "NumberOfDataStores": 3,
```

```
"NumberOfArchivers": 1,

"DataStores": [

  "ScadaBuffer",

  "DHSystem",

  "User"

],

"Id":

"5F267DF3-879A-4222-8A0E-D31EDEA83C14",

"IsDefault": true,

"LastModifiedUser": null,

"LastModifiedTime":

"1970-01-01T00:00:00.000Z",

"ArchiverServices": [

  {

    "LogicalName":

    "DataArchiver_xyz",

    "NodeName": "xyz",

    "ServiceType": 2,

    "TCPPort": 14001

  }

]
```

	<pre>] }] } </pre>
SAMPLE cURL COMMAND	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/storages?storageMask=* </pre>

Table 96. Query Parameters

Parameter	Description	Required?	Values
storageMask	The value of the location mask.	No	String

Table 97. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Add Machine API

Using the Add Machine API, you can add a server in a Historian system.

METHOD	POST
URI	<pre> https://<historianservername>/historian-rest-a pi/v1/machine </pre>
SAMPLE URI	<pre> https://<historianservername>/historian-rest-a pi/v1/machine Payload { </pre>

	<pre>"nodeName": "node1" }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"nodeName\": \"name\"}" -X POST https://<historianservername>/historian-rest-a pi/v1/machine</pre>

Table 98. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the machine name of the server that you want to add.	Yes	Multiple

Table 99. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Delete Machine API

Using the Delete Machine API, you can remove a server from a Historian system.

METHOD	DELETE
URI	<pre>https://<historianservername>/historian-rest-a pi/v1/machine</pre>

<p>SAMPLE URI</p>	<pre>https://<historianservername>/historian-rest-api/v1/machine Payload { "nodeName": "", }</pre>
<p>SAMPLE RESPONSE</p>	<pre>{ "ErrorCode": 0, "ErrorMessage": null }</pre>
<p>SAMPLE cURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"nodeName \": \"name\"}" -X DELETE https://<historianservername>/historian-rest-api/v1/machine</pre>

Table 100. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the name of the machine that you want to remove.	Yes	Multiple

Table 101. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Create Mirror Group API

Using the Create Mirror Group API, you can create a mirror group.

METHOD	POST
URI	<code>https://<historianservername>/historian-rest-api/v1/mirrorgroup</code>
SAMPLE URI	<code>https://<historianservername>/historian-rest-api/v1/mirrorgroup</code>
SAMPLE RESPONSE	<pre>Payload { "mirrorStorageName": "storagename", "nodes": "node1;node2" }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \" mirrorStorageName \": \"name\", \" nodes \": \"xx;yy\"}" -X POST https://<historianservername>/historian-rest-api/v1/mirrorgroup</pre>

Table 102. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the mirror group name and the servers you want to add to the group.	Yes	Multiple

Table 103. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Add Mirror Machine API

Using the Add Mirror Machine API, you can add a server to a mirror group.

METHOD	POST
URI	<code>https://<historianservername>/historian-rest-api/v1/mirrormachine</code>
SAMPLE URI	<pre>https://<historianservername>/historian-rest-api/v1/mirrormachine Payload { "mirrorStorageName": "Mirror2", "mirrorMachineName": "distmachine1" }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null</pre>

	<pre> }</pre>
SAMPLE cURL COMMAND	<pre> curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \" mirrorStorageName \": \"name\", \" nodes \": \"xx;yy\"}" -X POST https://<historianservername>/historian-rest-a pi/v1/mirrormachine</pre>

Table 104. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the machine name of the server that you want to add.	Yes	Multiple

Table 105. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Mirror Group Update API

Using the Mirror Group Update API, you can update the name of a mirror group.

METHOD	PUT
URI	<pre> https://<historianservername>/historian-rest-a pi/v1/mirrorsgroup</pre>
SAMPLE URI	<pre> https://<historianservername>/historian-rest-a pi/v1/mirrorsgroup Payload { "mirrorStorageName": "Mirror2",</pre>

	<pre>"mirrorStorageNewName": "Mirror3" } </pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null } </pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"mirrorStorageName \": \"name\", \" mirrorStorageNewName \": \"sname\"}" -X PUT https://<historianservername>/historian-rest-a pi/v1/mirrorsgroup </pre>

Table 106. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the existing and new names of the mirror group that you want to rename.	Yes	Multiple

Table 107. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Delete Mirror Machine API

Using the Delete Mirror Machine API, you can remove a server from a mirror group.

METHOD	DELETE
URI	<code>https://<historianservername>/historian-rest-api/v1/mirrormachine</code>
SAMPLE URI	<pre>https://<historianservername>/historian-rest-api/v1/mirrormachine Payload { "mirrorStorageName": "Mirror 2", "mirrorMachineName": "dismachine1" }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"mirrorStorageName \": \"name\", \" mirrorMachineName\": \"name\"}" -X DELETE https://<historianservername>/historian-rest-api/v1/mirrormachine</pre>

Table 108. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the name of the machine that you want to remove	Yes	Multiple

Table 108. Query Parameters (continued)

Parameter	Description	Required?	Values
	and the name of the mirror group.		

Table 109. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Delete Mirror Group API

Using the Delete Mirror Group API, you can delete a mirror group.

METHOD	DELETE
URI	<code>https://<historianservername>/historian-rest-api/v1/mirrorsgroup</code>
SAMPLE URI	<code>https://<historianservername>/historian-rest-api/v1/mirrorsgroup</code> Payload <pre>{ "mirrorStorageName": "Mirror3", }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null }</pre>

<p>SAMPLE cURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"mirrorStorageName \": \"name\"}" -X DELETE https://<historianservername>/historian-rest-a pi/v1/mirrorgroup</pre>
----------------------------	--

Table 110. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the name of the machine that you want to remove.	Yes	Multiple

Table 111. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Local OPC Servers API

Using the Local OPC Servers API, you can view the list of OPC servers installed on a specified machine.

METHOD	GET
URI	http://<historianservername>/v1/localopcserve rs/<machine name>
SAMPLE QUERY PARAM GET URL	http://<historianservername>/v1/localopcserve rs/<machine name>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "ServerIDs": ["ID1", "ID2"] }</pre>

	} }
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/localopcservers/xyz</pre>

Table 112. Query Parameters

Parameter	Description	Required?	Values
machine name	The machine name of the OPC server.	Yes	String

Table 113. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Local OPC AE Servers API

Using the Local OPC AE Servers API, you can view the list of OPC Alarms and Events servers installed on a specified machine.

METHOD	GET
URI	<pre>http://<historianservername>/v1/localopcaeserve rs/<machine name></pre>
SAMPLE QUERY PARAM GET URL	<pre>http://<historianservername>/v1/localopcaeserve rs/<machine name></pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "ServerIDs": ["ID1", "ID2"] }</pre>

	} }
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/localopcaeservers/abc</pre>

Table 114. Query Parameters

Parameter	Description	Required?	Values
machine name	The machine name of the OPC Alarms and Events server.	Yes	String

Table 115. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Local OPC HDA Servers API

Using the Local OPC HDA Servers API, you can view the list of OPC HDA servers installed on a specified machine.

METHOD	GET
URI	<pre>http://<historianservername>/v1/localopchdaserve rs/<machine name></pre>
SAMPLE QUERY PARAM GET URL	<pre>http://<historianservername>/v1/localopchdaserve rs/<machine name></pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "ServerIDs": ["ID1", "ID2"] }</pre>

	}
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/localopchdaservers/xyz</pre>

Table 116. Query Parameters

Parameter	Description	Required?	Values
machine name	The machine name of the OPC HDA server.	Yes	String

Table 117. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The DHS Service Port Update API

Using the DHS Service Port Update API, you can change the port and other details of a DHS service.

METHOD	PUT
URI	<pre>https://<historianservername>/historian-rest-a pi/v1/dhsservice/<DHS service name></pre>
SAMPLE URI	<pre>https://<historianservername>/historian-rest-a pi/v1/dhsservice/ DataArchiver_xxx { "LogicalName": "DataArchiver_xxx", "NodeName": "xxx",</pre>

	<pre>"ServiceType": 2, "Status": 1, "TCPPort": 14005 }</pre>
<p>SAMPLE RESPONSE</p>	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": { "LogicalName": "DataArchiver_xxx", "NodeName": "xxx", "ServiceType": 2, "Status": 1, "TCPPort": 14005 } }</pre>
<p>SAMPLE cURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \" LogicalName \":\": \" DataArchiver_xxx \", \" NodeName \": \"xxx\"\", \" ServiceType \": 2, \" Status\": 1, \" TCPPort \": 14005}" -X PUT https://<historianservername>/historian-rest-a pi/v1/dhsservice/DataArchiver_xxx</pre>

Table 118. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the values of the attributes of the data store that you want to change.	Yes	Multiple

Table 119. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

Managing Historian Model

The Add Object Type API

Using this API, you can create an object type.

METHOD	POST
URI	<code>https://<historianservername>/historian-model/v2/objectTypes</code>
SAMPLE QUERY PARAM POST URL	<code>https://localhost:443/historian-model/v2/objectTypes</code>
SAMPLE PAYLOAD	<pre>[{ "name": "Vehicle", "description": "Vehicle description", "dataVariables": [], "containedObjectTypes": [], "objectTypeTemplates": [], "lastModifiedUser": "", "lastmodifiedTime": "", "versionNumber": 0 }]</pre>

Table 120. Payload Parameters

Parameter	Description	Required?	Data Type
name	The object type name (must be unique).	Yes	String
description	The description of the object type.	No	String
containedObjectTypes	The list of contained types with details	No	Array
objectTypeTemplates	The list of object type templates, along with their details.	No	Array
lastModifiedUser	The username of the user who created the object type.	Yes	String
lastModifiedTime	The current time.	Yes	String
versionNumber	The version number of the object type. Start with 1 and increment by 1 each time you want to modify the object type.	Yes	Number

Table 121. Response Parameters

Parameter	Data Type	Description
detail	String	Description of the error.
error_code	Integer	The error code. A value of 0 indicates that the operation was successful.
status	String	The http request status.
title	String	The title of the error.
type	String	The type of the error.

The View Object Type API

Using this API, you can access an object type.

METHOD	POST
--------	------

URI	<code>https://<historianservername>/historian-model/v2/objectTypes/info</code>
SAMPLE QUERY PARAM POST URL	<code>https://localhost:443/historian-model/v2/objectTypes/info</code>
SAMPLE RESPONSE	<pre>{ "containedObjectTypes": [], "dataVariables": [], "description": "Vehicle description", "lastModifiedUser": "XYZ.admin", "lastmodifiedTime": "2022-01-21 08:58:20", "name": "Vehicle", "objectTypeTemplates": [{"containedObjectTypes": [], "dataVariables": [], "defaultTemplate": true, "description": "Default_Template_Vehicle", "lastModifiedUser": "XYZ.admin", "lastmodifiedTime": "2022-01-21 08:58:20", "name": "Default_Template_Vehicle", "objectType": "Vehicle", "substituteParameters": [], "versionNumber": 3}], "versionNumber": 3 }</pre>
SAMPLE PAYLOAD	<code>{"databaseName": "XYZ", "name": "Vehicle"}</code>

Table 122. Payload Parameters

Parameter	Description	Required?	Data Type
<code>name</code>	The object type name (must be unique).	Yes	String
<code>databaseName</code>	The name of the Historian server.	Yes	String

Table 123. Response Parameters

Parameter	Data Type	Description
name	String	The object type name (must be unique).
description	String	The description of the object type.
containedObject-Types	Array	The list of contained types with details
dataVariables	Array	The list of variables (with details) in the object type.
objectTypeTemplates	Array	The list of object type templates, along with their details.
lastModifiedUser	String	The username of the user who created the object type.
lastModifiedTime	String	The current time.
versionNumber	Number	The version number of the object type. Start with 1 and increment by 1 each time you want to modify the object type.

Table 124. objectTypeTemplates Array Parameters

Parameter	Data Type	Description
name	String	The object type name (must be unique).
description	String	The description of the object type.
containedObject-Types	Array	The list of contained types with details
dataVariables	Array	The list of variables (with details) in the object type.
lastModifiedUser	String	The username of the user who created the object type.
lastModifiedTime	String	The current time.
versionNumber	Number	The version number of the object type. Start with 1 and increment by 1 each

Table 124. objectTypeTemplates Array Parameters (continued)

Parameter	Data Type	Description
		time you want to modify the object type.
objectType	String	The object type name.
substituteParameters	Array	Blank (not applicable)

The Update Object Type API

Using this API, you can modify an object type.

METHOD	PUT
URI	<code>https://<historianservername>/historian-model/v2/objectTypes</code>
SAMPLE QUERY PARAM POST URL	<code>https://localhost:443/historian-model/v2/objectTypes</code>
SAMPLE RESPONSE	Error code and message, specifying whether the object type has been modified (200 for success and other codes for failure).
HEADER	<ul style="list-style-type: none"> • Content type: multipart/form-data • Boundary: ---WebKitFormBoundary-KeyName
SAMPLE PAYLOAD	<pre> -----WebKitFormBoundaryViBtYYvOfWhTYyhH Content-Disposition: form-data; name="objectTypeInfo"; filename="blob" Content-Type: application/json { "containedObjectTypes": [], "dataVariables": [{ "baseType": "NUMBER", "description": "", </pre>

```
"name": "Speed",
"variableType": "Direct"
},
{
"baseType": "STRING",
"description": "",
"name": "Type",
"variableType": "Indirect"
}
],
"description": "Vehicle description",
"lastModifiedUser": "XYZ.admin",
"lastmodifiedTime": "2022-01-21 11:37:56",
"name": "Vehicle",
"objectTypeTemplates":
[
{
"containedObjectTypes": [],
"dataVariables":
[
{
"baseType": "NUMBER",
"description": "",
"name": "Speed",
"properties":
{"blockType": "AI",
"propertyDefinition": []
},
"required": true,
"templateTagName": "",
"variableType": "DIRECT"
},
{
"baseType": "STRING",
"description": "",
"name": "Type",
"properties":
```

```
{
  "blockType": "AI",
  "propertyDefinition": []
},
"required": true,
"templateTagName": "",
"variableType": "INDIRECT"
}
],
"defaultTemplate": true,
"description": "Default_Template_Vehicle",
"lastModifiedUser": "XYZ.admin",
"lastmodifiedTime": "2022-01-21 11:37:56",
"name": "Default_Template_Vehicle",
"objectType": "Vehicle",
"substituteParameters": [],
"versionNumber": 5
}
],
"versionNumber": 5,
"databaseName": "XYZ",
"containedObjectTypesChanges":
[
{
  "newName": "",
  "oldName": "Engine"
}
],
"dataVariablesChanges":
[
{
  "newName": "",
  "oldName": "Color"
}
],
"objectTypeTemplatesChanges":
[
```

```

{
  "newName": "",
  "oldName": "Car"
}
]
}
-----WebKitFormBoundaryViBtYYvOfWhTYyhH--
    
```

Table 125. Payload Parameters

Parameter	Description	Required?	Data Type
name	The object type name (must be unique).	Yes	String
description	The description of the object type.	No	String
dataVariables	The list of variables in the object type.	No	Array
containedObjectTypes	The list of contained types with details	No	Array
objectTypeTemplates	The list of object type templates, along with their details.	No	Array
lastModifiedUser	The username of the user who created the object type.	Yes	String
lastModifiedTime	The current time.	Yes	String
versionNumber	The version number of the object type. Start with 1 and increment by 1 each time you want to modify the object type.	Yes	Number

Table 126. Response Parameters

Parameter	Data Type	Description
name	String	The object type name (must be unique).
description	String	The description of the object type.

Table 126. Response Parameters (continued)

Parameter	Data Type	Description
<code>containedObject-Types</code>	Array	The list of contained types with details.
<code>dataVariables</code>	Array	The list of variables (with details) in the object type.
<code>objectTypeTemplates</code>	Array	The list of object type templates, along with their details.
<code>lastModifiedUser</code>	String	The username of the user who created the object type.
<code>lastModifiedTime</code>	String	The current time.
<code>versionNumber</code>	Number	The version number of the object type. Start with 1 and increment by 1 each time you want to modify the object type.
<code>databaseName</code>	The name of the Historian server.	Yes
<code>containedObject-TypeChanges</code>	The list of changes in the contained type.	No
<code>dataVariables-Changes</code>	The list of changes in the object type variables.	No
<code>objectTypeTemplatesChanges</code>	The list of changes in the object type templates.	No

Table 127. objectTypeTemplates Array Parameters

Parameter	Description	Data Type
<code>name</code>	The object type name (must be unique).	String
<code>description</code>	The description of the object type.	String
<code>containedObject-Types</code>	The list of contained types with details	Array

Table 127. objectTypeTemplates Array Parameters (continued)

Parameter	Description	Data Type
<code>dataVariables</code>	The list of variables (with details) in the object type.	Array
<code>lastModifiedUser</code>	The username of the user who created the object type.	String
<code>lastModifiedTime</code>	The current time.	String
<code>versionNumber</code>	The version number of the object type. Start with 1 and increment by 1 each time you want to modify the object type.	Number
<code>ObjectType</code>	The object type name.	String
<code>substituteParameters</code>	Blank (not applicable)	Array

Table 128. dataVariables Array Parameters

Parameter	Description	Re-quired?	Data Type
<code>name</code>	The name of the object type name (must be unique).	Yes	String
<code>description</code>	The description of the object type.	No	String
<code>variableType</code>	The type of the variable (direct, indirect, or static).	No	String
<code>baseType</code>	Not applicable	No	String
<code>dbTagName</code>	Not applicable	No	String

Table 129. containedObjectTypes Array Parameters

Parameter	Description	Re-quired?	Data Type
<code>name</code>	The name of the object type (must be unique).	Yes	String
<code>description</code>	The description of the object type).	No	String
<code>containedObjectType</code>	The name of the object type that you want to use as a contained type.	No	String

Table 129. containedObjectTypes Array Parameters (continued)

Parameter	Description	Re-quired?	Data Type
<code>baseType</code>	The type of the contained type (ThingName indicates a contained type).	No	String

Table 130. Response Parameters

Parameter	Data Type	Description
<code>detail</code>	String	The description of the error.
<code>error_code</code>	Integer	The error code. A value of 0 indicates that the operation was successful.
<code>status</code>	String	The http request status.
<code>title</code>	String	The title of the error.
<code>type</code>	String	The type of the error.

The Contained Type List API

Using this API, you can get a list of contained types in each object type.

METHOD	GET
URI	<code>https://<historianservername> /historian-model/v2/ containedObjectTypesMap</code>
SAMPLE QUERY PARAM GET URL	<code>https://localhost:443/historian-model/v2/containedObjectTypesMap</code>

Table 131. Response Parameters

Parameter	Description	Data Type
<code>containedObjectTypes</code>	The list of contained types.	Array
<code>name</code>	The object type in which the contained type is used.	String

The Create Object Instance API

Using this API, you can create an object instance.

METHOD	POST
URI	https://<historianservername> /historian-model/v2/objects
SAMPLE QUERY PARAM POST URL	https://localhost:443/historian-model/v2/objects
SAMPLE PAYLOAD	<pre>[{ "containedObjects":[], "containedType":false, "dataVariables":[], "databaseName":"XYZ", "description":"", "fullName":"", "name":"Audi", "objectDataValueChanges":[], "objectDataValues":[], "objectType":"Vehicle", "objectTypeTemplate":"Car", "override":false, "parentName":"", "substituteParameters":[], "v1Type":false, "versionNumber":0 }]</pre>

Table 132. Payload Parameters

Parameter	Description	Required?	Data Type
containedObjects	The list of contained object types.	No	Array
containedType	Indicates whether the object type is used as a contained type (by default, False).	Yes	Boolean

Table 132. Payload Parameters (continued)

Parameter	Description	Required?	Data Type
data-Variables	The list of variables with details.	No	Array
description	The description of the object instance.	No	String
fullName	The full name of the object instance, which contains the name of the original object type, followed by the contained type name (as applicable).	No	String
name	The name of the object instance.	Yes	String
object-Data-Value-Changes	The list of changes in the object instance.	No	Array
Object-Type	The object type from which this instance must be created.	Yes	String
object-TypeTemplate	The name of the template you want to use in the object instance.	Yes	String
Override	True or false (required, but not used in Historian).	No	Boolean
parent-Name	The name of the object type.	No	String
substi-tutePa-rameters	Not applicable	No	String
v1Type	Indicates whether it is an Operations Hub model or a Historian model (by default, False, indicating a Historian model).	Yes	Boolean
version-Number	The version number of the object instance.	Yes	Number

Table 132. Payload Parameters (continued)

Parameter	Description	Required?	Data Type
data-baseName	The name of the Historian system.	Yes	String

Table 133. Response Parameters

Parameter	Data Type	Description
detail	String	Description of the error.
error_code	Integer	The error code. A value of 0 indicates that the operation was successful.
status	String	The http request status.
title	String	The title of the error.
type	String	The type of the error.

The Object Instance Info API

Using this API, you can view an object instance.

METHOD	POST
URI	<code>https://<historianservername>/historian-model/v2/objects/info</code>
SAMPLE QUERY PARAM POST URL	<code>https://localhost:443/historian-model/v2/objects/info</code>
SAMPLE RESPONSE	<pre>{ "containedObjects": [{ "alias": "Engine", "baseType": "THINGNAME", "containedObjectType": "Engine", "containedObjectTypeTemplate": "Default_Template_Engine", "description": "Engine", "fullName": "Audi1>Engine", </pre>

```
"name": "Engine",
"variableType": "ContainedAsset"
}
],
"containedType": false,
"dataVariables":
[
{
"baseType": "NUMBER",
"blockType": "AI",
"dbTagName": "Speed",
"description": "",
"name": "Speed",
"properties": [],
"required": true,
"variableType": "Direct"
},
{
"baseType": "STRING",
"blockType": "AI",
"dbTagName": "Type",
"description": "",
"name": "Type",
"properties": [],
"required": true,
"variableType": "InDirect"
},
{
"baseType": "NUMBER",
"blockType": "AI",
"dbTagName": "Color",
"description": "",
"name": "Color",
"properties": [],
"required": true,
"variableType": "Static"
}
]
```

	<pre>], "databaseName": "XYZ", "description": "", "lastModifiedUser": "XYZ.admin", "lastmodifiedTime": "2022-01-21 11:38:59", "name": "Audi1", "objectType": "Vehicle", "objectTypeTemplate": "Car", "override": false, "parentName": ">", "substituteParameters": [], "vlType": false, "versionNumber": 3 } </pre>
SAMPLE PAYLOAD	<pre> {"name": "Audi1", "databaseName": "XYZ"} </pre>

Table 134. Payload Parameters

Parameter	Description	Re-quired?	Data Type
name	The name of the object instance.	Yes	String
databaseName	The name of the Historian server.	No	String

Table 135. Response Parameters

Parameter	Description	Data Type
contained-Objects	The list of contained object types.	Array
contained-Type	Indicates whether the object type is used as a contained type.	Boolean
dataVariables	The list of variables with details.	Array
description	The description of the object instance.	String
fullName	The full name of the object instance.	String

Table 135. Response Parameters (continued)

Parameter	Description	Data Type
name	The name of the object instance.	String
object-DataValue-Changes	The list of changes in the object instance.	Array
ObjectType	The name of the object instance from which this instance is created.	String
objectType-Template	The name of the object type template used in the object instance.	String
Override	True or false.	Boolean
parentName	The name of the parent.	String
substitute-Parameters	Not applicable	String
v1Type	Indicates whether it is an Operations Hub model or a Historian model (by default, False, indicating a Historian model).	Boolean
versionNumber	The version number of the object instance.	Number
database-Name	The name of the Historian server.	String

Table 136. containedObjectTypes Array Parameters

Parameter	Description	Re-quired?	Data Type
alias	The name of the variable.	No	String
variableType	The type of the variable (direct, indirect, or static).	No	String
name	The name of the object type (must be unique).	Yes	String
description	The description of the object type).	No	String

Table 136. containedObjectTypes Array Parameters (continued)

Parameter	Description	Re-quired?	Data Type
<code>containedObject- Type</code>	The name of the object type that you want to use as a contained type.	No	String
<code>containedObject- TypeTemplate</code>	The template in the contained type that you want to use.	No	String
<code>baseType</code>	The type of the contained type (ThingName indicates a contained type).	No	String

Table 137. Data Variables Parameters

Parameter	Description	Re-quired?	Data Type
<code>baseType</code>	The type of the contained type (ThingName indicates a contained type).	No	String
<code>blockType</code>	Not applicable	No	String
<code>dbTagName</code>	The tag mapped with the variable (in the case of a direct or indirect variable).	No	String
<code>descrip- tion</code>	The description of the object instance.	No	String
<code>name</code>	The name of the variable.	No	String
<code>proper- ties</code>	Not applicable	No	Array
<code>required</code>	Indicates whether this variable is included in the object instance.	No	String
<code>variable- Type</code>	The data type of the variable (direct, indirect, or static).	No	String

The Object Instance with Contained Type Variables API

Using this API, you can view the contained type variables in an object instance.

METHOD	POST
--------	------

URI	https://<historianservername>/historian-model/v2/types-InstancesList/objects
SAMPLE QUERY PARAM POST URL	https://localhost:443/historian-model/v2/typesInstancesList/objects
SAMPLE RESPONSE	<pre>[{ "hasItems":true, "id":"Instances_Audil_V_", "loaded":false, "parentId":"Instances_Audil", "text":"Variables", "type":"objectInstanceVariableRootNode" }, { "hasItems":false, "id":"Instances_Audil_V_0", "loaded":false, "objectFullName":"Audil", "parentId":"Instances_Audil_V_", "parentObjectName":"Audil", "text":"Speed", "type":"objectInstanceVariableNode" }, { "hasItems":false, "id":"Instances_Audil_V_1", "loaded":false, "objectFullName":"Audil", "parentId":"Instances_Audil_V_", "parentObjectName":"Audil", "text":"Type", "type":"objectInstanceVariableNode" }, { "hasItems":false, "id":"Instances_Audil_V_2",</pre>

	<pre> "loaded":false, "objectFullName":"Audil", "parentId":"Instances_Audil_V_", "parentObjectName":"Audil", "text":"Color", "type":"objectInstanceVariableNode" }, { "hasItems":true, "id":"Instances_Audil0", "loaded":false, "objectFullName":"Audil>Engine", "objectType":"Engine", "objectTypeTemplate":"Default_Template_Engine", "parentId":"Instances_Audil", "parentObjectName":"Audil", "status":"state_new", "text":"Engine", "type":"objectInstanceContainedAssetNode" }, { "hasItems":false, "id":"Instances_Audil0_V_", "loaded":false, "parentId":"Instances_Audil0", "text":"Variables", "type":"objectInstanceVariableRootNode" }] </pre>
SAMPLE PAYLOAD	<pre> {"name":"Audil","databaseName":"XYZ"} </pre>

Table 138. Payload Parameters

Parameter	Description	Re-quired?	Data Type
name	The name of the object instance.	Yes	String

Table 138. Payload Parameters (continued)

Parameter	Description	Re-quired?	Data Type
databaseName	The name of the Historian system.	Yes	String

Table 139. Response Parameters

Parameter	Description	Data Type
hasItems	Indicates whether the variable is a static text or a variable (be default, false, indicating that it is static text).	Boolean
id	The sequence ID to render the model tree.	String
loaded	Not applicable	Boolean
parentId	The ID of the parent.	String
text	Contains the static text value or, in the case of variables, contains the text <code>Variables</code> .	String
type	The type of the variable: <ul style="list-style-type: none"> • objectInstanceVariableRootNode: Indicates static text. • objectInstanceVariableNode: Indicates direct, indirect, or a static variable. • objectInstanceContainedAssetNode: Indicates a variable in a contained type. 	String

The Object Instance - Variable Information API

Using this API, you can view the variable details of an object instance.

METHOD	POST
URI	<code>https://<historianservername> /historian-model/v2/ objects/variables/info</code>
SAMPLE QUERY PARAM POST URL	<code>https://localhost:443/historian-model/v2/objects/variables/info</code>

SAMPLE RESPONSE	<pre>{ "blockType": "AI", "variableName": "Speed", "variableTagName": "Audil>Speed", "variableType": "Direct", "variableValue": "Audil>Speed" }</pre>
SAMPLE PAYLOAD	<pre>{"databaseName": "XYZ", "name": "Audil>Speed" }</pre>

Table 140. Payload Parameters

Parameter	Description	Re-quired?	Data Type
name	The name of the object instance.	Yes	String
databaseName	The name of the Historian system.	Yes	String

Table 141. Response Parameters

Parameter	Description	Data Type
blockType	Not applicable	String
variableName	The name of the variable.	String
variableTagName	The name of the tag associated with the variable (not applicable for a static variable).	String
variableType	The type of the variable (static, direct, or indirect).	String
variableValue	The value of the variable (in case of a static variable) or the associated tag (in case of a direct or indirect variable).	String

The Historian Model API

Using this API, you can view the Historian model of a Historian system.

METHOD	POST
URI	<code>https://<historianservername>/historian-model/v2/typesObjectsList</code>
SAMPLE QUERY PARAM POST URL	<code>https://localhost:443/historian-model/v2/typesObjectsList</code>
SAMPLE PAYLOAD	<code>{"databaseName": "XYZ" }</code>

Table 142. Payload Parameters

Parameter	Description	Re-quired?	Data Type
<code>databaseName</code>	The name of the Historian system.	Yes	String

Table 143. Response Parameters

Parameter	Description	Data Type
<code>assetTemplates</code>	List of all the templates in the Historian model.	Array
<code>assetTemplatesInfo</code>	List of the details of all the templates in the Historian model.	Array
<code>assetTypes</code>	List of all the object types in the Historian model.	Array
<code>assetTypesInfo</code>	List of the details of all the object types in the Historian model.	Array
<code>assets</code>	List of all the object instances in the Historian model.	Array
<code>assetsInfo</code>	List of the details of all the object types in the Historian model.	Array

Table 144. assetTemplates Parameters

Parameter	Description	Data Type
<code>defaultTemplate</code>	Indicates whether it is the default template.	Boolean
<code>description</code>	The description of the template.	String

Table 144. assetTemplates Parameters (continued)

Parameter	Description	Data Type
lastModified-User	The username of the user who last modified the template.	String
lastmodified-Time	The date and time when the template was last modified.	Date and time
name	The name of the template.	String
objectType	The name of the object type associated with the template.	String
versionNumber	The version number of the template.	Integer

Table 145. assets Parameters

Parameter	Description	Data Type
assetFullName	The full name of the object instance.	Array
assetName	The name of the object instance.	String
lastModified-User	The username of the user who last modified the object instance.	String
lastmodified-Time	The date and time when the object instance was last modified.	Date and time
assetParent-Name	The parent name of the asset.	String
containedAssets	List of all the contained types in the object type.	Array
versionNumber	The version number of the object instance.	Integer

Table 146. assetsInfo Parameters

Parameter	Description	Data Type
containedType	Indicates whether the object type is a contained type.	Boolean
databaseName	The name of the Historian system.	String

Table 146. assetsInfo Parameters (continued)

Parameter	Description	Data Type
lastModified-User	The username of the user who last modified the object instance.	String
lastmodified-Time	The date and time when the object instance was last modified.	Date and time
description	The description of the object instance.	String
name	The name of the object instance.	String
objectType	The name of the object type associated with the object instance.	String
objectTypeTemplate	The name of the template used in the object instance.	String
Override	Updated or not.	Boolean
ParentName	The parent name of the asset.	String
status	Not applicable	String
v1Type	Not applicable	Boolean
versionNumber	The version number of the object instance.	number

The Export Historian Model API

When you create an object type or an object instance, you can use it only in the Historian system in which you have created it. If, however, you want to use the object type/instance in a different Historian system, you can export it and then import it into the other Historian system.

Using this API, you can export a Historian model, along with the object types, object instances, variables, templates, and contained types, into another Historian system.

METHOD	GET
URI	<code>http://<historianservername>/historian-model/v2/export?type-s=<true/false>&templates=<true/false>&instances=<true/false>&databaseName=<encrypted Historian system name></code>

SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/v2/export?types=true&templates=true&instances=true&databaseName=KNQWYA</code>
SAMPLE RESPONSE	<pre>{ "admissionTime": 1642600209, "jobId": 0 }</pre>

Table 147. Query Parameters

Parameter	Description	Required?	Data Type
<code>types</code>	Indicates whether you want to include object types while exporting the Historian model.	Yes	Boolean
<code>templates</code>	Indicates whether you want to include templates while exporting the Historian model.	No	Boolean
<code>instances</code>	Indicates whether you want to include object instances while exporting the Historian model.	No	Boolean
<code>databaseName</code>	The Historian system from which you want to export the Historian model.	Yes	String (Encrypted)

Table 148. Response Parameters

Parameter	Description	Data Type
<code>admissionTime</code>	The timestamp in Epoch time format when the model is exported.	Unix Time Stamp
<code>jobId</code>	The job id with which the operation started.	Integer

The Export Historian Model to Historian - Job Status API

Using this API, you can view the status of exporting a Historian model to another Historian system.

METHOD	GET
URI	<code>http://<historianservername>/historian-model/import-export/status/?jobId=<jobId></code>

SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/import-export/status/?jobId=1</code>
SAMPLE RESPONSE	<pre>{ "admissionTime": 1642601025, "completionTime": 1642601025, "isRunning": 0, "processing": "Completed", "processingElement": 14, "startTime": 1642601025, "statusPercentage": 100 }</pre>

Table 149. Query Parameters

Parameter	Description	Required?	Data Type
<code>jobId</code>	The job created when the export command is run.	Yes	Integer

Table 150. Response Parameters

Parameter	Description	Data Type
<code>admissionTime</code>	The timestamp in Epoch time format when the model is exported.	Unix Time Stamp
<code>completionTime</code>	The completing time of the job.	Unix Time Stamp
<code>isRunning</code>	The status of the job.	String
<code>processing</code>	Indicates whether the elements are being processed.	String
<code>processingElement</code>	The element that is being processed.	String
<code>startTime</code>	The start time of the job.	Unix Time Stamp
<code>statusPercentage</code>	The percentage of job completion.	Integer

The Historian Model to Historian - Job Log API

Using this API, you can view the job log of exporting a Historian model to another Historian system.

METHOD	GET
URI	<code>http: //<historianservername>/historian-model/import-export/log/?jobId=<jobId></code>
SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/import-export/log/?jobId=1</code>
SAMPLE RESPONSE	<pre>[{ "Elements": ["2022-01-19T08-08-43\t"], "LogStringCode": 12304 }, { "Elements": ["2022-01-19T08-08-43\t","3"], "LogStringCode": 12309 }, { "Elements": ["2022-01-19T08-08-43\t","2.1"], "LogStringCode": 12310 }]</pre>

Table 151. Query Parameters

Parameter	Description	Required?	Data Type
<i>jobId</i>	The job created when you run the export command.	Yes	Integer

Table 152. Response Parameters

Parameter	Description	Data Type
Array of Elements	List of elements that are processed.	Array
LogStringCode	The processing code.	Integer

The Export Historian Model to Historian - Job Result API

Using this API, you can export and retrieve a Historian model in a CSV file. You can then import it into another Historian model.

METHOD	GET
URI	<code>http://<historianservername>/historian-model/import-export/result/?jobId=<jobId></code>
SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/import-export/result/?jobId=1</code>

Table 153. Query Parameters

Parameter	Description	Required?	Data Type
jobId	The job created when you run the export command.	Yes	Integer

Table 154. Response Parameters

Parameter	Description	Data Type
CSV file	Contains the exported model	file

The Export Historian Model to Operations Hub API

When you create an object type or an object instance, you can use it only in the Historian system in which you have created it. If, however, you want to use the object type/instance in Operations Hub, you can export it and then import it into Operations Hub.

Using this API, you can export a Historian model to Operations Hub.

METHOD	GET
URI	<code>http://<historianservername>/historian-model/v2/export?type-s=<true/false>&instances=<true/false>&forOpsHub=<true/false>&databaseName=<encrypted Historian system name></code>
SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/v2/export?types=true&instances=true&forOpsHub=true&databaseName=KNOGEYA</code>
SAMPLE RESPONSE	<pre>{ "admissionTime": 1642600209,</pre>

```

{
  "jobId": 0
}
    
```

Table 155. Query Parameters

Parameter	Description	Required?	Data Type
types	Indicates whether you want to include object types while exporting the Historian model.	Yes	Boolean
in- stances	Indicates whether you want to include object instances while exporting the Historian model.	No	Boolean
data- base- Name	The Historian system from which you want to export the Historian model.	Yes	String (Encrypted)

Table 156. Response Parameters

Parameter	Description	Data Type
admission- Time	The timestamp in Epoch time format when the model is exported.	Unix Time Stamp
jobId	The job id with which the operation started.	Integer

The Export Historian Model to Operations Hub Job Status API

Using this API, you can get the job status of exporting a Historian model to Operations Hub.

METHOD	GET
URI	<code>http://<historianservername>/historian-model/import-export/status/?jobId=<jobId></code>
SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/import-export/status/?jobId=1</code>
SAMPLE RESPONSE	<pre> { "admissionTime": 1642601025, "completionTime": 1642601025, "isRunning": 0, "processing": "Completed", "processingElement": 14, </pre>

	<pre>"startTime": 1642601025, "statusPercentage": 100 }</pre>
--	---

Table 157. Query Parameters

Parameter	Description	Required?	Data Type
jobId	The job created when you run the export command.	Yes	Integer

Table 158. Response Parameters

Parameter	Description	Data Type
admissionTime	The timestamp in Epoch time format when the model is exported.	Unix Time Stamp
completionTime	The completion time of the job.	Unix Time Stamp
isRunning	The status of the job.	String
processing	Indicates whether the elements are being processed.	String
processingElement	The element which is being processed.	String
startTime	The start time of the job.	Unix Time Stamp
statusPercentage	The percentage of job completion.	Integer

The Export Historian Model to Operations Hub Job Log API

Using this API, you can get the log of the job when exporting a Historian model to Operations Hub.

METHOD	GET
URI	<code>http: //<historianservername>/historian-model/import-export/log/?jobId=<jobId></code>
SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/import-export/log/?jobId=1</code>

SAMPLE RESPONSE	<pre>[{ "Elements": ["2022-01-19T08-08-43\t", "LogStringCode": 12304 }, { "Elements": ["2022-01-19T08-08-43\t", "3"], "LogStringCode": 12309 }, { "Elements": ["2022-01-19T08-08-43\t","2.1"], "LogStringCode": 12310 }]</pre>
-----------------	---

Table 159. Query Parameters

Parameter	Description	Required?	Data Type
jobId	The job created when you run the export command.	Yes	Integer

Table 160. Response Parameters

Parameter	Description	Data Type
Array of Elements	List of elements that are processed.	Array
LogStringCode	The processing code.	Integer

The Export Historian Model to Operations Hub Job Result API

Using this API, you can export and retrieve a Historian model in a CSV file. You can then import it into Operations Hub.

METHOD	GET
URI	<code>http://<historianservername>/historian-model/import-export/result/?jobId=<jobId></code>

SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/import-export/re- sult/?jobId=1</code>
-------------------------------	---

Table 161. Query Parameters

Para- meter	Description	Re- quired?	Data Type
<code>jobId</code>	The job created when you run the export command.	Yes	Integer

Table 162. Response Parameters

Para- meter	Description	Data Type
<code>CSV file</code>	Contains the exported model.	file

The Import Model to Historian API

Using this API, you can import a Historian model from one system to another.



Important:

If the name of a tag associated with a variable in a model contains a period (.), you cannot import the tag while importing the model into a Historian system.

METHOD	POST
URI	<code>http://<historianservername>/historian-model/v2/import?type- s=<true/false>&templates=<true/false>&instances=<true/ false>&databaseName=<encrypted Historian system name></code>
SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/v2/import?types=true&tem- plates=true&instances=true&databaseName=KGEYA</code>
SAMPLE RESPONSE	<pre>{ "admissionTime": 1642600209, "jobId": 0 }</pre>

Table 163. Payload Parameters

Pay-load	Description	Re-quired?	Data Type
body	CSV file that you want to import	Yes	file

Table 164. Query Parameters

Para-meter	Description	Re-quired?	Data Type
types	Indicates whether you want to import object types.	Yes	Boolean
templates	Indicates whether you want to import templates.	No	Boolean
instances	Indicates whether you want to import object instances.	No	Boolean
database-Name	The Historian system name in to which you want to import the model.	Yes	String (Encrypted)

Table 165. Response Parameters

Parameter	Description	Data Type
admission-Time	The timestamp in Epoch time format when the model is imported.	Unix Time Stamp
jobId	The job id with which the operation started.	Integer

The Import Historian Model to Historian - Job Status API

Using this API, you can view the job status of importing a Historian model to another Historian system.

METHOD	GET
URI	<code>http://<historianservername>/historian-model/import-export/status/?jobId=<jobId></code>
SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/import-export/status/?jobId=1</code>
SAMPLE RESPONSE	<pre>{ "admissionTime": 1642601025,</pre>

	<pre> "completionTime": 1642601025, "isRunning": 0, "processing": "Completed", "processingElement": 14, "startTime": 1642601025, "statusPercentage": 100 } </pre>
--	---

Table 166. Query Parameters

Parameter	Description	Required?	Data Type
<code>jobId</code>	The job created when the import command is run.	Yes	Integer

Parameter	Description	Data Type
<code>admissionTime</code>	The error in text format.	Unix Time Stamp
<code>completionTime</code>	The completed time of the job.	Unix Time Stamp
<code>isRunning</code>	The status of the job.	String
<code>processing</code>	Indicates whether the elements are processed.	String
<code>processingElement</code>	The element that is being processed.	String
<code>startTime</code>	The start time of the job.	Unix Time Stamp
<code>statusPercentage</code>	The percentage of job completion.	Integer

The Import Historian Model to Historian - Job Log API

Using this API, you can view the job log of importing a Historian model into another Historian model.

METHOD	GET
URI	<code>http://<historianservername>/historian-model/import-export/log/?jobId=<jobId></code>
SAMPLE QUERY PARAM GET URL	<code>http://localhost:443/historian-model/import-export/log/?jobId=1</code>
SAMPLE RESPONSE	<pre> { { </pre>

```

"Elements": ["2022-01-19T08-08-43\t"],
"LogStringCode": 12304
},
{
"Elements": ["2022-01-19T08-08-43\t","3"],
"LogStringCode": 12309
},
{
"Elements": ["2022-01-19T08-08-43\t","2.1"],
"LogStringCode": 12310
}
]
    
```

Table 167. Query Parameters

Parameter	Description	Required?	Data Type
jobId	The job created when the import command is run.	Yes	Integer

Table 168. Response Parameters

Parameter	Description	Data Type
Array of Elements	The list of elements that are processed.	Array
LogStringCode	The processing code.	Integer

The Import Historian Model to Historian - Result API

Using this API, you can view the result of importing a Historian model into another Historian system.

METHOD	GET
URI	http://<historianservername>/historian-model/import-export/result/?jobId=<jobId>
SAMPLE QUERY PARAM GET URL	http://localhost:443/historian-model/import-export/result/?jobId=1

SAMPLE RESPONSE	<pre>[{ "Elements":["2022-01-19T08-06-59\t","72","Contained Asset","Engine1"], "LogStringCode":12214 }, { "Elements":["2022-01-19T08-06-59\t","73","Contained Asset","cylinder1"], "LogStringCode":12214 }, { "Elements":["2022-01-19T08-06-59\t","74","Contained Asset","piston1"], "LogStringCode":12214 }]</pre>
-----------------	---

Table 169. Payload Parameters

Parameter	Description	Required?	Data Type
jobId	The job created when the import command is run.	Yes	Integer

Table 170. Response Parameters

Parameter	Description	Data Type
Array of Elements	The list of elements that are processed.	Array
LogStringCode	The processing code.	Integer

The Duplicate Object Instance API

Using this API, you can copy an object instance.

METHOD	POST
URI	http: //<historianservername>/historian-mod-el/v2/objects/clone

SAMPLE QUERY PARAM POST URL	<code>http://localhost:443/historian-model/v2/objects/clone</code>
SAMPLE PAYLOAD	<pre>{ "databaseName": "XYZ", "source": "Vehicle", "destination": "Audi", "description": "the new object" }</pre>

Table 171. Payload Parameters

Parameter	Description	Re-quired?	Data Type
database-Name	The name of the Historian system.	Yes	String
source	The name of the object instance that you want to copy.	Yes	String
destina-tion	The name that you want to provide for the copied object instance.	Yes	String
descrip-tion	The description of the new object instance.	No	String

The Duplicate Object Type API

Using this API, you can copy an object type. When you copy an object type, all the templates and variables are copied too.

METHOD	POST
URI	<code>http://<historianservername>/historian-model/v2/objectTypes/clone</code>
SAMPLE QUERY PARAM POST URL	<code>http://localhost:443/historian-model/v2/objectTypes/clone</code>
SAMPLE PAYLOAD	<pre>{ "source": "Vehicle", "destination": "Audi", }</pre>

	<pre>"description": "the new object" }</pre>
--	--

Table 172. Payload Parameters

Parameter	Description	Re-quired?	Data Type
source	The name of the object type that you want to copy.	Yes	String
destina- tion	The name that you want to provide for the copied object type.	Yes	String
descrip- tion	The description of the new object type.	No	String

The Export Object Instance API

Using this API, you can export an object instance into another Historian system.

METHOD	POST
URI	http: //<historianservername>/historian-mod- el/v2/export/objects
SAMPLE QUERY PARAM POST URL	http://localhost:443/historian-model/v2/export/ob- jects
SAMPLE PAYLOAD	<pre>{ "objects": ["object_Instance_1", "Object_Instance_2"], "objectType": "Audi", "objectTypeTemplate": "Vehicle", "databaseName": "XYZ" }</pre>

Table 173. Payload Parameters

Parameter	Description	Re-quired?	Data Type
<code>objects</code>	The list of the object instances that you want to export.	Yes	Array
<code>objectType</code>	The object type associated with the object instances that you want to export.	Yes	String
<code>objectType-Template</code>	The template type of the object instances that you want to export.	No	String
<code>database-Name</code>	The name of the Historian system.	Yes	String

The Export Object Type API

Using this API, you can export an object type into another Historian system.

METHOD	POST
URI	<code>http://<historianservername>/historian-model/export/objectTypes</code>
SAMPLE QUERY PARAM POST URL	<code>http://localhost:443/historian-model/export/objectTypes?databaseName= KOGEYA</code>
SAMPLE PAYLOAD	<pre>{ "objectType": ["object_type_1", "object_type_2"] }</pre>

Table 174. Payload Parameters

Parameter	Description	Re-quired?	Data Type
<code>objectType</code>	The list of object types that you want to export.	Yes	Array

Table 175. Query Parameters

Parameter	Description	Required?	Data Type
<code>data-baseName</code>	The name of the Historian system from which you want to export the object type.	Yes	String (encrypted)

The Delete Object Instance API

Using this API, you can delete an object instance. If there are direct variables in the object type, you can also choose to delete the tags associated with these variables (along with their data).

METHOD	DELETE
URI	<code>http://<historianservername>/historian-model/v2/objects</code>
SAMPLE QUERY PARAM DELETE URL	<code>http://localhost:443/historian-model/v2/objects</code>
SAMPLE PAYLOAD	<pre>{ "databaseName": "XYZ", "name": "Vehicle1", "permanentDelete": true }</pre>

Table 176. Payload Parameters

Parameter	Description	Required?	Data Type
<code>data-baseName</code>	The name of the Historian system.	Yes	String
<code>name</code>	The name of the object instance that you want to delete.	Yes	String
<code>permanentDelete</code>	Indicates whether you want to permanently delete the object instance. If you do so, the tags are deleted as well.	Yes	Boolean

The Incoming Dependencies API

Using this API, you can view a list of object instances associated with an object type. This is used to check if an object type contains object instances before you delete the object type.

METHOD	POST
URI	<code>http://<historianservername>/historian-model/v2/object-Types/IncomingDependencies</code>
SAMPLE QUERY PARAM POST URL	<code>http://localhost:443/historian-model/v2/objectTypes/IncomingDependencies</code>
SAMPLE PAYLOAD	<pre>{ "name": "Vehicle", "databaseName": "XYZ" }</pre>

Table 177. Payload Parameters

Parameter	Description	Re-quired?	Data Type
<code>name</code>	The name of the object type that you want to delete.	Yes	String
<code>database-Name</code>	The name of the Historian system associated with the object type.	Yes	String

The Delete Object Type API

Using this API, you can delete an object type. You can delete multiple object types together; however, all the object types must belong to the same Historian system. You cannot delete an object type if it is used in an object instance; you must first delete the object instance.

METHOD	DELETE
URI	<code>http://<historianservername>/historian-model/v2/objectTypes</code>
SAMPLE QUERY PARAM DELETE URL	<code>http://localhost:443/historian-model/v2/objectTypes</code>
SAMPLE PAYLOAD	<pre>{ "databaseName": "XYZ", "objectTypes": ["Vehicle", "Engine"] }</pre>

Table 178. Payload Parameters

Parameter	Description	Re-quired?	Data Type
object-Types	The list of object types that you want to delete.	Yes	Array
database-Name	The name of the Historian system associated with the object types.	Yes	String

Managing Collector Instances

The Create Collector Instance API

Using the Create Collector Instance API, you can create a collector instance.

METHOD	POST
URI	<code>https://<historianservername>/historian-rest-api/v1/collector/createnewinstance</code>
SAMPLE URI	<p><code>https://<historianservername>/historian-rest-api/v1/collector/createnewinstance</code></p> <p>Payload</p> <pre>{ "mode":1, "CollectorSystemName":"xyz", "InterfaceDescription":"xyz_Simulation_<IP address>_2", "DataPathDirectory":"C:\\Proficy Historian Data", "CollectorDestination":"Historian", "winUserName":"","winPassword":"", "InterfaceSubType":"", "DestinationHistorianUserName":"abc", "DestinationHistorianPassword":"password", "DestinationHistorian":"<IP address>", "General1":"","", "General2":"","", "General3":"123",</pre>

	<pre> "General4":""," "General5":""," "Type":2, "InterfaceName":"<source server>_<type of the collector>_<destination server>" } </pre> <div data-bbox="820 499 1341 1060" style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note:</p> <ul style="list-style-type: none"> • The DestinationHistorian parameter will not have a value for offline collector configuration. • To connect to MQTT destinations such as AWS IoT and Google Cloud Platform (GCP), you must provide an encrypted password. </div>
<p>SAMPLE RESPONSE</p>	<pre> { "ErrorCode": 0, "ErrorMessage": null } </pre>
<p>SAMPLE cURL COMMAND</p>	<pre> curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"mode\":1,\"CollectorSystemName\": \"xyz\", \"InterfaceDescription\": \"xyz_Simulation_<IP address>_2\", \"DataPathDirectory\": \"C:\ \Proficy Historian Data\", \"CollectorDestination\": \"Historian\", \"winUserName\": \"\", \"winPassword\": \"\", </pre>

```

\"InterfaceSubType\":
\\\", \"DestinationHistorianUserName\": \"abc\",
\"DestinationHistorianPassword\": \"password\",
\"DestinationHistorian\": \"<IP
address>\", \"General1\": \"\",
\"General2\": \"\", \"General3\": \"xyz\",
\"General4\": \"\", \"General5\": \"\",
\"Type\": 2, \"InterfaceName\": \"<source
server>_<type of the collector>_<destination
server>\"}\" -X POST
https://<historianservername>/historian-rest-a
pi/v1/collector/createnewinstance
    
```

Table 179. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Get Collector Instance Details API

Using the Get Collector Instance Details API, you can view the details of a collector instance.

METHOD	GET
URI	https://<historianservername>/historian-rest-api/v1/collector/instancedetails/<interface name>
SAMPLE QUERY PARAM GET URL	https://<historianservername>/historian-rest-api/v1/collector/instancedetails/<interface name>
SAMPLE RESPONSE	<pre> { "ErrorCode": 0, "ErrorMessage": null, "Data": { "CloudDestination": "", "InterfaceSubType": "", "CollectorSystemName": "xyz", </pre>

	<pre>"Type":2, "DefaultCompression":false, "CloudInformationLogLevel":0, "InterfaceDataDir":"C:\\Proficy Historian Data", "SourceServer":"", "Username":"", "Password":"", "DestinationType":"Historian", "DestinationServer":"abc", "DebugLogLevel":0, "InterfaceInstallDrive":"C", "ConnectionString":"xyz" } }</pre>
<p>SAMPLE cURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/collector/instancedetails/xyz_Simulation_ <IP address>_2</pre>

Table 180. Query Parameters

Parameter	Description	Required?	Values
<code>interface name</code>	The interface name of the collector whose details you want to view.	Yes	String

Table 181. Response Parameters

Parameter	Data Type	Required?	Description
<code>ErrorCode</code>	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
<code>ErrorMessage</code>	String	Yes	For example, NULL.

The Edit Collector Instance API

Using the Edit Collector Instance API, you can modify the cloud parameters of a collector instance. The collector instance will be restarted after you make changes.

METHOD	PUT
URI	<pre>https://<historianservername>/historian-rest-api/v1/collector/editInstance</pre>
SAMPLE URI	<pre>https://<historianservername>/historian-rest-api/v1/collector/editInstance</pre> <p>Payload</p> <pre>{ "InterfaceName": "<source server>_<type of the collector>_<destination server>", "messageCompression": 0, "azureLogLevel": 1, "debugMode": 0, "CollectorDestination": "Predix", "DestinationHistorian": "abc", "mode": 1, "CloudDestinationAddress": "wss://def.run.abc.ice.predix.io/v1/stream/messages", "IdentityIssuer": "https://1234.predix-uaa.run.abc.ice.predix.io/oauth/token", "ClientID": "xyz", "ClientSecret": "123", "ZoneID": "1234", "Proxy": "http://1.2.3.4:80", "ProxyUserName": "", "ProxyPassword": "", "DatapointAttribute1": "", "DatapointAttribute2": "", "DatapointAttribute3": "", "DatapointAttribute4": "" }</pre> <div data-bbox="820 1575 1341 1852" style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note:</p> <ul style="list-style-type: none"> • The DestinationHistorian parameter will not have a value for offline collector configuration. </div>

	 <ul style="list-style-type: none"> To connect to MQTT destinations such as AWS IoT and Google Cloud Platform (GCP), you must provide an encrypted password.
<p>SAMPLE RESPONSE</p>	<pre>{ "ErrorCode": 0, "ErrorMessage": null }</pre>
<p>SAMPLE cURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"InterfaceName\": \"<source server>_<type of the collector>_<destination server>\", \"InterfaceName\": \"<source server>_<type of the collector>_<destination server>\", \"messageCompression\": 0, \"azureLogLevel\": 1, \"debugMode\": 0, \"CollectorDestination\": \"Predix\", \"DestinationHistorian\": \"abc\", \"mode\": 1, \"CloudDestinationAddress\": \"wss://wss://def.run.abc.ice.predix.io/v1/strea m/messages\", \"IdentityIssuer\": \"https://1234.predix-uaa.run.abc.ice.predix. io/oauth/token\", \"ClientID\": \"HistQA\", \"ClientSecret\": \"Gei321itc\", \"ZoneID\": \"1234\", \"Proxy\": \"http://1.2.3.4:80\", \"ProxyUserName\": \"\", \"ProxyPassword\": \"\"\",</pre>

```

\DatapointAttribute1\":"\","DatapointAttribut
e2\":"\","DatapointAttribute3\":"\","
\DatapointAttribute4\":"\"}" -X PUT
https://<historianservername>/historian-rest-a
pi/v1/collector/editInstance
    
```

Table 182. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Azure Log Level API

Using the Azure Log Level API, you can set the debug information log level for destination - Azure IoT Hub. You can set a value ranging from 0 to 4.

METHOD	PUT
URI	https://<historianservername>/historian-rest-api/v1/collector/azureloglevel
SAMPLE URI	<p>https://<historianservername>/historian-rest-api/v1/collector/azureloglevel</p> <p>Payload</p> <pre> {"InterfaceName": "<InterfaceName>:<source server>_<type of the collector>_<destination server>", "azureLogLevel":1,} </pre>
SAMPLE RESPONSE	<pre> { "ErrorCode": 0, "ErrorMessage": null } </pre>

<p>SAMPLE cURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{\"InterfaceName\": \"<source server>_<type of the collector>_<destination server>\", \"azureLogLevel\": 1}" -X PUT https://<historianservername>/historian-rest-a pi/v1/collector/azureloglevel</pre>
-----------------------------------	---

Table 183. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Install Component Details API

Using the Install Component Details API, you can view the install component details from the collector machine.

<p>METHOD</p>	<p>GET</p>
<p>URI</p>	<pre>https://<historianservername>/historian-rest-a pi/v1/ installcomponentdetails/collectorType/collectorS ubType/machine</pre>
<p>SAMPLE URI</p>	<pre>https://<historianservername>/historian-rest-a pi/v1/installcomponentdetails/2/-/abc</pre>
<p>SAMPLE RESPONSE</p>	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": { "InterfaceInstallDrive": "C", "InterfaceDataDir": "C:\\Proficiency Historian Data", "CertPathDir": "NONE"</pre>

	<pre>} }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/installcomponentdetails/2/-/abc</pre>

Table 184. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Message Compression API

Using the Message Compression API, you can enable or disable message compression.

METHOD	PUT
URI	<pre>https://<historianservername>/historian-rest-a pi/v1/collector/messagecompression</pre>
SAMPLE REQUEST	<pre>{ "InterfaceName": "<source server>_<type of the collector>_<destination server>", "messageCompression": 1 }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d {"\InterfaceName\":"<source server>_<type of the collector>_<destination server>\", \messageCompression\":1}" -X PUT</pre>

	<pre>https://<historianservername>/historian-rest-api/v1/collector/messagecompression</pre>
--	---

Table 185. Query Parameters

Parameter	Description	Required?	Values
<code>interface name</code>	The interface name of the collector whose message compression you want to enable or disable.	Yes	String
<code>messagecompression</code>	Identifies whether you want to enable or disable message compression. The valid values are 0 and 1.	Yes	

Table 186. Response Parameters

Parameter	Data Type	Required?	Description
<code>ErrorCode</code>	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
<code>ErrorMessage</code>	String	Yes	For example, NULL.

The Delete Instance API

Using the Delete Instance API, you can delete a collector instance.

<p>METHOD</p> <p>URI</p> <p>SAMPLE REQUEST</p>	<p>PUT</p> <pre>https://<historianservername>/historian-rest-api/v1/collector/deleteinstance</pre> <pre>https://<historianservername>/historian-rest-api/v1/collector/deleteinstance</pre> <p>Payload</p> <pre>{ "InterfaceName": "<source server>_<type of the collector>_<destination server>", "deleteTags": true }</pre>
---	---

<p>SAMPLE RESPONSE</p>	<pre>{ "ErrorCode":0, "ErrorMessage":null, }</pre>
<p>SAMPLE cURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{\"InterfaceName\":\"<source server>_<type of the collector>_<destination server>\", \"deleteTags\":true}" -X PUT https://<historianservername>/historian-rest-a pi/v1/collector/deleteinstance</pre>

Table 187. Query Parameters

Parameter	Description	Required?	Values
interface name	The interface name of the collector whose details you want to delete.	Yes	String
deleteTags	Identifies whether you want to delete the tags. The valid values are true and false.	Yes	Boolean

Table 188. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

Collector Type and Subtype

The following table provides a list of collector type and subtype for each collector, which you will provide in APIs.

Collector	Collector Type	Collector Subtype
The Calculation collector	8	
The CygNet collector	16	Cygnnet
The File collector	4	
The HAB collector	16	HAB
The iFIX Alarms and Events collector	11	iFixAE
The iFIX collector	1	
The MQTT collector	16	MQTT
The ODBC collector	16	ODBC
The OPC Classic Alarms and Events collector	11	
The OPC Classic DA collector	3	
The OPC Classic HDA collector	16	OPCHDA
The OPC UA DA collector	16	OPCUA
The OSI PI collector	10	
The OSI PI distributor	13	
The Server-to-Server collector	9	
The Server-to-Server distributor	17	
The Simulation collector	2	
The Windows Performance collector	18	
The Wonderware collector	16	Wonderware

Managing Collectors

The Start Collector API

Using the Start Collector API, you can start a collector.

METHOD	PUT
URI	<pre>https://<historianservername>/historian-rest-api/v1/collector/start</pre>
SAMPLE URI	<p>Sample URI for the service mode:</p> <pre>https://<historianservername>/historian-rest-api/v1/collector/start</pre> <p>Payload</p> <pre>{ "interfaceName": "<source server>_<type of the collector>_<destination server>", "mode": 1 }</pre> <p>Sample URI for the command line mode:</p> <pre>https://<historianservername>/historian-rest-api/v1/collector/start</pre> <p>Payload</p> <pre>{ "interfaceName": "<source server>_<type of the collector>_<destination server>", "mode": 2, "winUserName": "", "winPassword": "" }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": "", "Data": "Collector Start Initiated" }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json"</pre>

```
-H "Authorization: Bearer <TOKEN>" -d
"{ \"interfaceName\": \"<source server>_<type of
the collector>_<destination server>\",
\"mode\": 1}" -X PUT
https://<historianservername>/historian-rest-api/v1/collector/start
```

Query parameters include the Payload parameter, which is a JSON file, which contains the following properties.

Table 189. Query Parameters

Parameter	Description	Required?	Values
interfaceName	The interface name of the collector.	Yes	String
mode	The mode to use to manage the collector.	Yes	<ul style="list-style-type: none"> • 1: service mode • 2: command-line mode
winUserName	The Windows username.	Yes (only if you want to use the command-line mode)	String
winPassword	The Windows password	Yes (only if you want to use the command-line mode)	String

Table 190. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.
Data	String	No	Indicates if the task has been initiated.

The Stop Collector API

Using the Stop Collector API, you can stop a collector.

METHOD	PUT
URI	<code>https://<historianservername>/historian-rest-api/v1/collector/stop</code>
SAMPLE URI	<pre>https://<historianservername>/historian-rest-api/v1/collector/stop Payload { "interfaceName": "<source server>_<type of the collector>_<destination server>" "winUserName": "TestAdmin", "winPassword": "TestAdminPassword" }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": "Collector Stop Initiated" }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"interfaceName\": \"<source server>_<type of the collector>_<destination server>\"}" -X PUT https://<historianservername>/historian-rest-api/v1/collector/stop</pre>

Query parameters include the Payload parameter, which is a JSON file, which contains the following properties.

Table 191. Query Parameters

Parameter	Description	Required?	Values
<code>interfaceName</code>	The interface name of the collector.	Yes	String
<code>winUserName</code>	The Windows username.	Yes (only if you want to use the command-line mode)	String
<code>winPassword</code>	The Windows password	Yes (only if you want to use the command-line mode)	String

Table 192. Response Parameters

Parameter	Data Type	Required?	Description
<code>ErrorCode</code>	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
<code>ErrorMessage</code>	String	Yes	For example, NULL.
<code>Data</code>	String	No	Indicates if the task has been initiated.

The Restart Collector API

Using the Restart Collector API, you can restart a collector.

METHOD	PUT
URI	<code>https://<historianservername>/historian-rest-api/v1/collector/restart</code>
SAMPLE URI	<code>https://<historianservername>/historian-rest-api/v1/collector/restart</code> Payload <pre>{</pre>

	<pre>"interfaceName": "<source server>_<type of the collector>_<destination server>" "winUserName": "", "winPassword": "" }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": "Collector Restart Initiated" }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"interfaceName\": \"<source server>_<type of the collector>_<destination server>\"}" -X PUT https://<historianservername>/historian-rest-a pi/v1/collector/restart</pre>

Query parameters include the Payload parameter, which is a JSON file, which contains the following properties.

Table 193. Query Parameters

Parameter	Description	Required?	Values
interfaceName	The interface name of the collector.	Yes	String
winUserName	The Windows username.	Yes	String
winPassword	The Windows password	Yes	String

Table 194. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

Table 194. Response Parameters (continued)

Parameter	Data Type	Required?	Description
Data	String	No	Indicates if the task has been initiated.

The Pause Data Collection API

Using the Pause Data Collection API, you can pause the data collection of a collector.

METHOD	PUT
URI	<code>https://<historianservername>/historian-rest-api/v1/collector/pausecollection/{interfaceName}</code>
SAMPLE URI	<code>https://<historianservername>/historian-rest-api/v1/collector/pausecollection/RSSERVER2012-02_Simulation</code>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": "" }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -X PUT https://<historianservername>/historian-rest-api/v1/collector/pausecollection/RSSERVER2012-02_Simulation</pre>

Table 195. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.
Data	String	No	Indicates if the task has been initiated.

The Resume Data Collection API

Using the Resume Data Collection API, you can resume the data collection of a collector.

METHOD	PUT
URI	<code>https://<historianservername>/historian-rest-api/v1/collector/resumecollection/{interfaceName}</code>
SAMPLE URI	<code>https://<historianservername>/historian-rest-api/v1/collector/resumecollection/RSSERVER2012-02_Simulation</code>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": "" }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -X PUT https://<historianservername>/historian-rest-api/v1/collector/resumecollection/RSSERVER2012-02_Simulation</pre>

Table 196. Response Parameters

Parameter	Data Type	Required?	Description
<code>ErrorCode</code>	Integer	Yes	For example, <code>ErrorCode = 0</code> implies the operation was successful.
<code>ErrorMessage</code>	String	Yes	For example, NULL.
<code>Data</code>	String	No	Indicates if the task has been initiated.

The Add Tag Comment API

Using the Add Tag Comment API, you can add a comment to a tag.

METHOD	POST
URI	<code>https://<historianservername>/historian-rest-api/v1/tags/addcomment</code>

<p>SAMPLE URI</p>	<pre>https://<historianservername>/historian-rest-api/v1/tags/addcomment Payload { "tagName": "rserver2012-02.Simulation00003", "comment": "Retest", "timeStamp": "2020-04-22T00:00:00.000Z" }</pre>
<p>SAMPLE RESPONSE</p>	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": "" }</pre>
<p>SAMPLE cURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"tagName\": \" rserver2012-02.Simulation00003\", \"comment\": \Test10\", \"timeStamp\": \"2020-04-22T00:00:00.000Z \"}" -X POST https://<historianservername>:443/historian-rest-api/v1/tags/addcomment</pre>

Query parameters include the Payload parameter, which is a JSON file, which contains the following properties.

Table 197. Query Parameters

Parameter	Description	Required?	Values
tagName	The name of the tag.	Yes	String
timestamp	The timestamp of the comment.	Yes	String
comment	The comment.	Yes	String

Table 198. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Get Tag Comment API

Using the Get Tag Comment API, you can view the comments added to a tag.

METHOD	GET
URI	<pre>https://<historianservername>/historian-rest-api/v1/tags/comments/{tagNames}/{start}/{end}</pre>
SAMPLE QUERY PARAM GET URI	<pre>https://<historianservername>/historian-rest-api/v1/tags/comments/?tagNames=rserver2012-02.Simulation00003;rserver2012-02.Simulation00004&start=2020-04-19T00:00.000Z&end=2020-04-24T00:00.000Z</pre> <div style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: The query parameter supports multiple tags. </div>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": [{ "TagName": "Motor Temperature", "ErrorCode": 0, "Comments": [{</pre>

```

        "TimeStamp":
        "2020-04-22T00:00:00.000Z",
        "Comment": "Heat run test:
Starting temperature"
    },
    {
        "TimeStamp":
        "2020-04-22T00:00:00.000Z",
        "Comment": "Heat run test:
Temperature of the stator"
    },
    {
        "TimeStamp":
        "2020-04-22T00:00:00.000Z",
        "Comment": "Heat run test:
Temperature of the rotor"
    },
    {
        "TimeStamp":
        "2020-04-22T00:00:00.000Z",
        "Comment": "Heat run test:
Temperature of the shaft"
    },
    {
        "TimeStamp":
        "2020-04-22T00:00:00.000Z",
        "Comment": "Heat run test:
Temperature of the endshield"
    }
]
}
]
}

```

SAMPLE cURL COMMAND

```

curl -i -H "Accept: application/json" -H
"Authorization: Bearer <TOKEN>"
http://<historianservername>

```

```
/historian-rest-api/v1/tags/comments/<tagName>
s>/<start>/<end>
```

Query parameters include the Payload parameter, which is a JSON file, which contains the following properties.

Table 199. Query Parameters

Parameter	Description	Required?	Values
tagNames	The names of the tag as a semi-colon-separated list. For example: HISTWIN20161.ctag1; HISTWIN20161.ctag2	Yes	String
start	The start time of the query, in ISO data format (YYYY-MM-DDTHH:mm:ss.SSSZ).	Yes	DateTime
end	The end time of the query, in ISO format (YYYY-MM-DDTHH:mm:ss.SSSZ).	Yes	DateTime

Table 200. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Set Debug Mode API

Using the Set Debug Mode API, you can set the debug mode of a collector.

METHOD	PUT
URI	https://<historianservername>/historian-rest-api/v1/collector/setdebugmode
SAMPLE URI	https://<historianservername>/historian-rest-api/v1/collector/setdebugmode

	<pre>Payload { "interfaceName": "<source server>_<type of the collector>_<destination server>", "debugMode": 255 }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": "" }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"interfaceName\": \"<source server>_<type of the collector>_<destination server>\", \"debugMode\": \"}\"" -X PUT https://<historianservername>/historian-rest-api/v1/collector/setdebugmode</pre>

Query parameters include the Payload parameter, which is a JSON file, which contains the following properties.

Table 201. Query Parameters

Parameter	Description	Required?	Values
interfaceName	The interface name of the collector.	Yes	String
debugMode	The debug log level for the collector.	Yes	<ul style="list-style-type: none"> • 0: Normal log level • 255: Debug log level

Table 202. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.

Table 202. Response Parameters (continued)

Parameter	Data Type	Required?	Description
ErrorMessage	String	Yes	For example, NULL.

The Buffer File Control API

Using the Buffer File Control API, you can delete or move the buffer files. It is recommended to move the buffer files to a new folder within the same drive.



Note:
Moving files to a network shared drive is not supported.

METHOD	PUT
URI	<pre>https://<historianservername>/historian-rest-api/v1/collector/buffercontrol</pre>
SAMPLE URI	<p>Sample URI for moving buffer files:</p> <pre>https://<historianservername>/historian-rest-api/v1/collector/buffercontrol</pre> <p>Payload</p> <pre>{ "interfaceName": "<source server>_<type of the collector>_<destination server>", "bufferMode": 2, "winUserName": "Administrator", "winPassword": "xxxxxxx", "bufferPath": "C:\\Users\\bufffiles" }</pre> <p>Sample URI for deleting buffer files:</p> <pre>https://<historianservername>/historian-rest-api/v1/collector/buffercontrol</pre> <p>Payload</p> <pre>{</pre>

	<pre> "interfaceName": "<source server>_<type of the collector>_<destination server>", "bufferMode": 1 "winUserName": "Administrator", "winPassword": "xxxxxxx", } </pre>
<p>SAMPLE RESPONSE</p>	<p>Sample response for moving buffer files:</p> <pre> { "ErrorCode": 0, "ErrorMessage": null, "Data": "BufferFiles Move Initiated. Collector is in the Stopped state." } </pre> <p>Sample response for deleting buffer files:</p> <pre> { "ErrorCode": 0, "ErrorMessage": null, "Data": "BufferFiles Delete Initiated. Collector is in the Stopped state." } </pre>
<p>SAMPLE cURL COMMAND</p>	<pre> curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"interfaceName\": \"<source server>_<type of the collector>_<destination server>\", \"bufferMode \": 1, \"bufferPath \": \" C:\\Users\\bufffiles\"}" -X PUT https://<historianservername>/historian-rest-a pi/v1/collector/buffercontrol </pre>

Query parameters include the Payload parameter, which is a JSON file, which contains the following properties.

Table 203. Query Parameters

Parameter	Description	Required?	Values
<code>interfaceName</code>	The interface name of the collector.	Yes	String
<code>bufferMode</code>	Indicates whether you want to move or delete the files.	Yes	<ul style="list-style-type: none"> • 1: Indicates that the buffer files will be deleted. • 2: Indicates that the buffer files will be moved to the location specified in the <code>bufferPath</code> parameter.
<code>bufferPath</code>	<p>The directory to which you want to move the buffer files. For example: <code>C:\\Data\\New-BufferFilesLocation</code> or <code>C:/Data/NewBufferPathLocation</code></p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: The double slash (\\) is required in the JSON format.</p> </div>	Yes (only if you want to move the buffer files)	String
<code>winUserName</code>	The Windows username.	Yes (only if you want to use the command-line mode)	String
<code>winPassword</code>	The Windows password	Yes (only if you want to use the com-	String

Table 203. Query Parameters (continued)

Parameter	Description	Required?	Values
		mand-line mode)	

Table 204. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.
Data	String	No	Indicates if the task has been initiated (and if the collector is in the stopped state).

The Server Node Change API

Using the Server Node Change API, you can change the server node of a collector to a machine that has Historian 8.1 installed on it.

METHOD	PUT
URI	<code>https://<historianservername>/historian-rest-api/v1/collector/historiannodechange</code>
SAMPLE URI	<pre> https://<historianservername>/historian-rest-api/v1/collector/historiannodechange Payload { "interfaceName":"<source server>_<type of the collector>_<destination server>", "mode":2, "winUserName":"TestAdministrator", "winPassword":"TestPassword", "historianNode":"VMHISTWEBAUTO", "historianUserName":" TestAdministrator2 ", "historianpassword":" TestPassword2" </pre>

	<pre>} </pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": "" }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"interfaceName\": \"<source server>_<type of the collector>_<destination server>\", \"userName winUserName\": \"tesrt\", \"winpPassword \": \"password\", \"historianNode \": \"nodename\", \" historianUserName \": \"husername\", \" historianpassword \": \"hpassword\"}" -X PUT https://<historianservername>/historian-rest-a pi/v1/collector/ historiannodechange</pre>

Query parameters include the Payload parameter, which is a JSON file, which contains the following properties.

Table 205. Query Parameters

Parameter	Description	Required?	Values
interfaceName	The interface name of the collector.	Yes	String
mode	The mode to use to manage the collector.	Yes	<ul style="list-style-type: none"> • 1: service mode • 2: command-line mode
winUserName	The Windows username.	Yes (only if you want to use the command-line mode)	String

Table 205. Query Parameters (continued)

Parameter	Description	Required?	Values
<code>winPassword</code>	The Windows password.	Yes (only if you want to use the command-line mode)	String
<code>historianNode</code>	The host name of the new Historian destination machine. The destination machine must have Historian 8.1.	Yes	String
<code>historian-UserName</code>	The Windows username of the new Historian destination machine.	Yes (only if you want to use the command-line mode)	String
<code>historian-Password</code>	The Windows password of the new Historian destination machine.	Yes (only if you want to use the command-line mode)	String

Table 206. Response Parameters

Parameter	Data Type	Required?	Description
<code>ErrorCode</code>	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
<code>ErrorMessage</code>	String	Yes	For example, NULL.

The Get Collector Version API

Using the Get Collector Version API, you can view the version number of a collector.

METHOD	GET
--------	-----

URI	<code>https://<historianservername>/historian-rest-api/v1/collector/version/{interfaceName}</code>
SAMPLE QUERY PARAM GET URL	<code>https://<historianservername>/historian-rest-api/v1/collector/version/?interfaceName=<source server>_<type of the collector>_<destination server></code>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": { "Version": "8.1.2068.0" } }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" http://<historianservername>/historian-rest-api/v1/collector/version/RSSERVER2012-02_Simulation</pre>

Table 207. Query Parameters

Parameter	Description	Required?	Values
<code>interfaceName</code>	The interface name of the collector.	Yes	String

Table 208. Response Parameters

Parameter	Data Type	Required?	Description
<code>ErrorCode</code>	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
<code>ErrorMessage</code>	String	Yes	For example, NULL.
<code>Data</code>	String	Yes	Returns the version of the collector.

The Get Collector Status API

Using the Get Collector Status API, you can view the status of a collector.

METHOD	GET
URI	<code>https://<historianservername>/historian-rest-api/v1/collector/status/{interfaceName}</code>
SAMPLE GET URI	<code>https://<historianservername>/historian-rest-api/v1/collector/status/RSSERVER2012-02_Simulation</code>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": "null" "Data":{ "Status": "Running" } }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-api/v1/collector/status/RSSERVER2012-02_Simulation</pre>

Table 209. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.
Data	String	Yes	Returns the status of the collector.

The Collector Manager List API

Using the Collector Manager List API, you can view the list of collector agents machines associated with the Historian server.

METHOD	GET
--------	-----

<p>URI</p>	<p>https://<historianservername>/historian-rest-api/v1/collectormanagerlist</p>
<p>SAMPLE QUERY PARAM GET URL</p>	<p>https://<historianservername>/historian-rest-api/v1/collectormanagerlist</p>
<p>SAMPLE RESPONSE</p>	<pre> { "ErrorCode": 0, "ErrorMessage": null, "Data": [{ "Name": "CollectorManager::abc", "IPAddress": "[::ffff:<IP address>]", "Status": 1, "ComputerName": "abc " }, { "Name": "CollectorManager::xyz", "IPAddress": "[::ffff:<IP address>]", "Status": 1, "ComputerName": "xyz" }, { "Name": "CollectorManager::abc", "IPAddress": "[::ffff:<IP address>]", "Status": 1, "ComputerName": "abc" }, { "Name": "CollectorManager::123", "IPAddress": "[::ffff:<IP address>]", "Status": 1, "ComputerName": "123" }] } </pre>

	<pre>] } } } } </pre>
SAMPLE cURL COMMAND	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/collectormanagerlist </pre>

Table 210. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Collector Mode API

Using the Collector Mode API, you can view the running mode of a collector.

METHOD	GET
URI	<pre> https://<historianservername>/historian-rest-a pi/v1/collector/mode/<collector interface name> </pre>
SAMPLE QUERY PARAM GET URL	<pre> https://<historianservername>/historian-rest-a pi/v1/collector/mode/<collector interface name> </pre>
SAMPLE RESPONSE	<pre> { "ErrorCode": 0, "ErrorMessage": null, "Data": { "RunningMode": "Service Mode" } } </pre>
SAMPLE cURL COMMAND	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/collector/mode/<host name>_Simulation_<IP address>_2 </pre>

Table 211. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Collector Details API

Using the Collector Details API, you can view the details of a collector.

METHOD	GET
URI	<code>https://<historianservername>/historian-rest-api/v1/collector/details</code>
SAMPLE QUERY PARAM GET URL	<code>https://<historianservername>/historian-rest-api/v1/collector/details</code>
SAMPLE RESPONSE	<pre>{ "ErrorCode":0, "ErrorMessage":null, "Data": [{ "Name":"<value>", "ComputerName":"<value>", "Status":"Running", "ReportRate":0, "MaximumEventRate":0, "MinimumEventRate":0, "OutOfOrderEvents":0, "Overruns":0, "OverrunsPercent":0, "TotalEventsCollected":0, "TotalEventsReported":0, "LastDataValue":"\\\"1970-01-01T00:00:00.000Z\\\" }], "Redundancy":"" }</pre>

	<pre>"Comments": "<username>--test2--\\ \"2020-12-15T07:19:42.000Z\\\"";", "Version": "9.0.4326.0", "CollectorCompression": 0, "TagsCount": 0 }] }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/collector/details</pre>

Table 212. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Offline Collectors API

Using the Offline Collectors API, you can view a list of offline collectors.

METHOD	GET
URI	<pre>https://<historianservername>/historian-rest-a pi/v1/offlinecollectors</pre>
SAMPLE QUERY PARAM GET URL	<pre>https://<historianservername>/historian-rest-a pi/v1/offlinecollectors</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": [{ "Name": "DISTMACHINE1_Simulation", "ComputerName": "DISTMACHINE1",</pre>

	<pre> "Status": "Stopped" }, { "Name": "NPI212611749M1_Simulation", "ComputerName": "NPI212611749M1", "Status": "Stopped" }, { "Name": "NPI212611749M1_Mqtt", "ComputerName": "NPI212611749M1", "Status": "Stopped" }] } </pre>
SAMPLE cURL COMMAND	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/offlinecollectors </pre>

Table 213. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

Managing Data Stores

The Get Data Stores API

Using the Get Data Stores API, you can view the list of data stores in a system.

METHOD	GET
URI	<pre> https://<historianservername>/historian-rest-a pi/v1/datastores?dataStoreMask= </pre>

<p>SAMPLE QUERY PARAM GET URL</p>	<pre>https://<historianservername>/historian-rest-api/v1/datastores?dataStoreMask=*</pre>
<p>SAMPLE RESPONSE</p>	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": [{ "Description": "The System Data Store.", "Id": "D3C23639-81CD-40F7-9CB0-37484FC5190D", "IsDefault": false, "IsSystem": true, "Name": "System", "NumberOfTags": 0, "State": 2, "DHSStorageName": "System Storage", "StorageType": 0, "Links": [{</pre>

```
        "Rel": "self",

        "Href": "/datastore/System"

    }

]

},

{

    "Description": "The Scada Buffer
Data Store.",

    "Id":
"39B39D42-DC7A-4048-9BA8-E4BAB4644B0C",

    "IsDefault": false,

    "IsSystem": false,

    "Name": "ScadaBuffer",

    "NumberOfTags": 0,

    "State": 2,

    "DHSStorageName": "xyz",

    "StorageType": 1,

    "Links": [

        {

            "Rel": "self",
```

```
        "Href":  
        "/datastore/ScadaBuffer"  
    }  
]  
},  
{  
    "Description": "The DHS System Data  
Store.",  
    "Id":  
    "56C1DFE9-D0BF-427F-B5D8-B127E38B5C11",  
    "IsDefault": false,  
    "IsSystem": false,  
    "Name": "DHSSystem",  
    "NumberOfTags": 0,  
    "State": 2,  
    "DHSSStorageName": "xyz",  
    "StorageType": 0,  
    "Links": [  
    {  
        "Rel": "self",
```

```
        "Href":  
        "/datastore/DHSSystem"  
    }  
]  
},  
{  
    "Description": "The User Data  
Store.",  
    "Id":  
    "33BA016D-B005-4702-96DB-42CF7238C8FF",  
    "IsDefault": true,  
    "IsSystem": false,  
    "Name": "User",  
    "NumberOfTags": 5,  
    "State": 2,  
    "DHSSStorageName": "xyz",  
    "StorageType": 0,  
    "Links": [  
    {  
        "Rel": "self",
```

	<pre> "Href": "/datastore/User" }] } } } } } } </pre>
<p>SAMPLE cURL COMMAND</p>	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/datastores?dataStoreMask=* </pre>

Table 214. Query Parameters

Parameter	Description	Required?	Values
dataStoreMask	The value of the data store mask.	No	String

Table 215. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Get Data Stores of Storage API

Using the Get Data Stores of Storage API, you can view the list of data stores in a location.

METHOD	GET
URI	<pre>https://<historianservername>/historian-rest-api/v1/storage/datastores?storageName=</pre>
SAMPLE QUERY PARAM GET URL	<pre>https://<historianservername>/historian-rest-api/v1/storage/datastores?storageName=xx</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": [{ "Description": "The Scada Buffer Data Store.", "Id": "39B39D42-DC7A-4048-9BA8-E4BAB4644B0C", "IsDefault": false, "IsSystem": false, "Name": "ScadaBuffer", "NumberOfTags": 0, "State": 2, "DHSStorageName": "xyz", "StorageType": 1, "Links": [</pre>

```
{
    "Rel": "self",
    "Href":
"/datastore/ScadaBuffer"
}
],
{
    "Description": "The DHS System Data
Store.",
    "Id":
"56C1DFE9-D0BF-427F-B5D8-B127E38B5C11",
    "IsDefault": false,
    "IsSystem": false,
    "Name": "DHSSystem",
    "NumberOfTags": 0,
    "State": 2,
    "DHSSStorageName": "xyz",
    "StorageType": 0,
    "Links": [
```

```
{
  "Rel": "self",
  "Href":
"/datastore/DHSSystem"
}
],
{
  "Description": "The User Data
Store.",
  "Id":
"33BA016D-B005-4702-96DB-42CF7238C8FF",
  "IsDefault": true,
  "IsSystem": false,
  "Name": "User",
  "NumberOfTags": 5,
  "State": 2,
  "DHSSStorageName": "xyz",
  "StorageType": 0,
  "Links": [
```

	<pre> { "Rel": "self", "Href": "/datastore/User" }] }] } </pre>
<p>SAMPLE cURL COMMAND</p>	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<historianservername>/historian-rest-a pi/v1/storage/datastores?storageName=xx </pre>

Table 216. Query Parameters

Parameter	Description	Required?	Values
storageName	The name of the location whose data stores you want to view.	Yes	String

Table 217. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Add Datastore API

Using the Add Datastore API, you can create a data store in a Historian server.



Note:

This API is applicable only to an Enterprise Historian.

METHOD	POST
URI	<pre>https://<historianservername>/historian-rest-api/v1/datastorestorage</pre>
SAMPLE PATH PARAM GET URI	<pre>https://<historianservername>/historian-rest-api/v1/datastorestorage Payload { "dataStoreName": "abc", "storageName": "storage1", "description": "test", "isDefault": true }</pre>
SAMPLE RESPONSE	<pre>{ "ErrorCode": 0, "ErrorMessage": null }</pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"dataStoreName \": \"name\", \" storageName \": \"sname\", \"description</pre>

```

\":" des\"," isDefault \":false}"
-X POST
https://<historianservername>/historian-rest-a
pi/v1/datastorestorage
    
```

Table 218. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the details of the data store in the JSON format.	Yes	Multiple

Table 219. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Delete Data Store API

Using the Delete Data Store API, you can delete a data store.

METHOD	DELETE
URI	https://<historianservername>/historian-rest-api/v1/datastore
SAMPLE URI	https://<historianservername>/historian-rest-api/v1/datastore
	Payload <pre> { "dataStoreName": "testdatastore" } </pre>
SAMPLE RESPONSE	<pre> { </pre>

<p>SAMPLE cURL COMMAND</p>	<pre>"ErrorCode": 0, "ErrorMessage": null } curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"dataStoreName \": \"name\"}" -X DELETE https://<historianservername>/historian-rest-a pi/v1/datastore</pre>
----------------------------	---

Table 220. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Data Store Update API

Using the Data Store Update API, you can modify a data store.

METHOD	PUT
URI	https://<historianservername>/historian-rest-api/v1/dataStore/<data store name>
SAMPLE URI	<pre>https://<historianservername>/historian-rest-a pi/v1/dataStore/mirror1DS1 Payload { "Description": "testing", "IsDefault": true,</pre>

	<pre> "IsSystem": false, "Name": "mirror1DS1", "NumberOfTags": 0, "State": 2, "DHSSStorageName": "mirror1", "StorageType": 0, } </pre>
<p>SAMPLE RESPONSE</p>	<pre> { "ErrorCode": 0, "ErrorMessage": null } </pre>
<p>SAMPLE cURL COMMAND</p>	<pre> curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \" Description\": \"des\", \"IsDefault \": true, \" IsSystem \": false, \" Name\": \" mirror1DS1\", \"NumberOfTags \": 0, \"State\": 2, \"DHSSStorageName\": \"mirror1\", \"StorageType \": 0, \}" -X PUT https://<historianservername>/historian-rest-a pi/v1/dataStore/mirror1DS1 </pre>

Table 221. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the values of the attributes of the data store that you want to change.	Yes	Multiple

Table 222. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Default Data Store Update API

Using the Default Data Store Update API, you can change the default data store.

METHOD	PUT
URI	<code>https://<historianservername>/historian-rest-api/v1/storage/<location name></code>
SAMPLE URI	<pre> https://<historianservername>/historian-rest-api/v1/storage/NPI212611749M1 Payload { "StorageName": "NPI212611749M1", "StorageType": 0, "NumberOfDataStores": 5, "NumberOfArchivers": 1, "DataStores": [</pre>

	<pre> "User", "testDS1", "ScadaBuffer", "testDS2", "DHSSystem"], "Id": "9CD06AFB-1566-4CE6-99D4-B2F65857F33A", "IsDefault": true, "LastModifiedUser": null, "LastModifiedTime": "1970-01-01T00:00:00.000Z", "ArchiverServices": ["DataArchiver_NPI212611749M1", "DataArchiver_distamchine1"] } </pre>
<p>SAMPLE RESPONSE</p>	<pre> { "ErrorCode": 0, "ErrorMessage": null, </pre>

	<pre>} </pre>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"StorageName\": \"name\", \"StorageType\": 0, \"NumberOfDataStores\": 5, \" NumberOfArchivers\": 1, \"IsDefault\": true, \"ArchiverServices\": [\"DataArchiver_NPI212611749M1\", \"DataArchiver_distamchine1\"]}" -X PUT https://<historianservername>/historian-rest-a pi/v1/storage/NPI212611749M1 </pre>

Table 223. Query Parameters

Parameter	Description	Required?	Values
Payload	Contains the values of the attributes of the default data store that you want to change.	Yes	Multiple

Table 224. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

Managing Tags

The Tags API

The Tags API retrieves the qualified tag name list by a given `nameMask`.



Note:

URI format supports asterisks (*) and question marks (?).

METHOD	GET
URI	https://<historianservername>:443/historian-rest-api/v1/tags/{nameMask}/{maxNumber}
SAMPLE URI	https://<historianservername>:443/historian-rest-api/v1/tags?nameMask=*&maxNumber=100
SAMPLE cURL COMMAND	curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<nodename>:443/historian-rest-api/v1/tags?nameMask=*&maxNumber=<Number_Of_Tags>

Table 225. Query Parameters

Parameter	Description	Required?	Values
nameMask	Tagmask that searches for all tags that match the mask and applies the remaining criteria to retrieve data. The mask can include wildcards, such as asterisks (*).	Optional	String
maxNumber	<p>Maximum tag number provides the limit while returning the results (0 by default). This means that for a query, if using 0, all tags are returned.</p> <p>If a negative number is used, then 0 is used for the maxNumber.</p> <p>If a positive number is used, then that number of tags is returned. In addition, an error number of +14 notifies the user that there are more than the requested number of tags in the system.</p>	Optional	<p>Integer</p> <p>0 by default</p>

Table 226. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Number	Yes	For example, ErrorCode = 0, which means the operation was successful.
ErrorMessage	String	Yes	For example, NULL.
tags	String	Yes	Includes the following: <ul style="list-style-type: none"> • ALT_SENSOR • tagName1 • tagName2

The Taglist API

The Tags List API `GET` method retrieves the list of tags.

When retrieving large tag lists from Historian, you can paginate the response, allowing you to get the next page, go the end, go back one page, and go to the beginning.

Request Parameters

You can use wildcards (*, &?) with string parameters for pattern matching. Results are sorted in ascending tag names. All parameters use the `AND` operator. The `OR` operator is not supported.

All request parameters are optional.

When there are NO wildcard characters (*, &?) with string parameters for pattern matching, then search would be a `contains` search

Example: "dog" pattern will match "dog1", "dog2","dogs", "dogx", "dog12", "dogs are faithful", "1dog1" and so on. When wildcards (*,& ?) are used in the search string parameters for pattern matching, then they work as per the wildcard character definition.

? - Single character matching

* - Multi character matching

Eg1: "dog?" pattern will match: "dog1", "dog2","dogs", "dogx" and so on but not "dog12" or "dogs are faithful"

Eg2: “dog*” pattern will match “dog1”, “dog2”, “dogs”, “dogx”, “dog12”, “dogs are faithful” and so on but not “1dog1”

Parameter Name	Data Type	Default	Description
<code>calctype</code>	Integer	-1	Returns exact match of calc type (0,1,2).
<code>collectiondisabled</code>	Boolean	If ignored, all types considered.	Must be only true / false, else error out.
<code>collectioninterval</code>	Integer	0 – means all intervals	If <code>collectorinterval</code> = 0 consider all intervals, else exact match.
<code>collectorcompression</code>	Boolean	*	Returns exact match of collector compression (true/false).
<code>collectorname</code>	String	*	Default * means consider all.
<code>collectortype</code>	Integer	0 – means consider all collector types	Returns exact match of collector type.
<code>comment</code>	String	*	Default * means consider all.
<code>data storename</code>	String	*	Default * means consider all.
<code>datatype</code>	Integer	0 – means consider all data types	Returns exact match of data type.
<code>description</code>	String	*	Default * means consider all.
<code>egudescription</code>	String	*	Default * means consider all.
<code>enumeratedset</code>	String	*	Default * means consider all.
<code>hasalias</code>	Boolean	If ignored, all types considered.	Must be only true / false, else error out.
<code>isstale</code>	Boolean	If ignored, all types considered.	Must be only true / false, else error out.

Parameter Name	Data Type	Default	Description
lastmodified	String	1970-01-01T00:00:00Z	is applied so that last modified tag is returned in the result set.
lastmodifieduser	String	*	Default * means consider all.
numberofelements	Integer	0	If 0, ignore this parameter else returns exact match of number of elements.
pageno	Integer	1 Must be > 1	If invalid, no data is returned.
pagesize	Integer	128 Max 512 Min 2	If out of range, returns error. Provide 0 to return all tags at once without any pagination.
sourceaddress	String	*	Default * means consider all.
tagname	String	*	Default * means consider all.
userdefinedtypename	String	*	Default * means consider all.

The Tags List Pagination Parameters

When retrieving large tag lists from Historian, you can paginate the response, allowing you to get the next page, go the end, and go back on page and to the beginning. Results with no errors return these pagination parameters:

Parameter	Value
pagesize	Current page size.
pageno	Current page number
totalcount	Total result other than current page.
Links to URLs	All URLs are part of the HTTP response headers.

Parameter	Value
	<ul style="list-style-type: none"> • <code>first</code> – First page <code>tags list</code> URL (can be null if count is 0). • <code>last</code> - Last page <code>tags list</code> URL (can be null if count is 0). • <code>prev</code> – Previous page <code>tags list</code> URL (can be null if current page is 1). • <code>Next</code> - Next page <code>tags list</code> URL (can be null if current page is last page).

Table 227. Sample cURL commands

METHOD	GET
SAMPLE cURL COM- MAND: [lastmodi- fied]	curl -i -H "Accept: application/json" -H "Authorization:Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/tagslist?lastmodified=2017-05-01T00:00:00.00Z
SAMPLE cURL COM- MAND: [pageno=0]	curl -i -H "Accept: application/json" -H "Authorization:Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/tagslist?pageno=0
SAMPLE cURL COM- MAND: [pageno=1]	curl -i -H "Accept: application/json" -H "Authorization:Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/tagslist?pageno=1
SAMPLE cURL COM- MAND: [complete tagslist]	curl -i -H "Accept: application/json" -H "Authorization:Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/tagslist

Example Queries

The following request returns first page as `pageno` is ignored and `pagesize` is defaulted to 128, all tags are considered:

```
<baseurl>/v1/tagslist
```

The following request returns first page as `pageno` is ignored and `pagesize` is defaulted to 128, all tags are considered that are modified after `2017-05-01T00:00:00.00Z`.

```
<baseurl>/v1/tagslist?lastmodified=2017-05-01T00:00:00.00Z
```

Example Results

The following info is returned for each tag from the criteria provided in the request as an array of tag info.

- `tagid` - String
- `tagname` - String
- `description` - String
- `datatype` - Integer
- `collectorname` - String
- `collectortype` - Integer
- `data storename` - String
- `egudescription` - String
- `comment` - String
- `sourceaddress` - String
- `sourceaddress` - String
- `collectioninterval` - Integer
- `collectorcompression` - Boolean
- `lastmodifieduser` - String
- `enumeratedset` - String
- `userdefinedtypename` - String
- `calctype` - Integer
- `isstale` - Boolean
- `lastmodified` - Long
- `lastmodified` - Long
- `lastmodifiedString` - String - In readable format
- `has alias` - Boolean
- `numberofelements` - Integer
- `collectiondisabled` - Boolean

Example:

```
{
  "TotalCount": 1031,
  "Page": 1,
  "PageSize": 4,
  "Tags": [
    {
      "Tagid": "adb70ebf-978f-46dd-ac6f-5e863cdb0739",
      "Tagname": "-anilgwxb.Constant",
```

```

    "Description": "anilgwx.Constant",
    "DataType": 3,
    "CollectorName": "ANILGWXB_Simulation",
    "CollectorType": 2,
    "DataStoreName": "User",
    "EngineeringUnits": "",
    "Comment": "",
    "SourceAddress": "$Constant",
    "CollectionInterval": 1000,
    "CollectorCompression": false,
    "LastModifiedUser": null,
    "EnumeratedSetName": "",
    "UserDefinedTypeName": "",
    "CalcType": 0,
    "IsStale": false,
    "HasAlias": false,
    "NumberOfElements": 0,
    "CollectionDisabled": false,
    "LastModified": 1496992712,
    "LastModifiedString": "2017-06-09T07:18:32Z"
  },
  {
    "Tagid": "88elf448-643f-465a-95c2-d2bd08870547",
    "TagName": "anilgwx.Constant_1%Noise",
    "Description": "anilgwx.Constant_1%Noise",
    "DataType": 3,
    "CollectorName": "ANILGWXB_Simulation",
    "CollectorType": 2,
    "DataStoreName": "User",
    "EngineeringUnits": "",
    "Comment": "",
    "SourceAddress": "$Constant_1%Noise",
    "CollectionInterval": 1000,
    "CollectorCompression": false,
    "LastModifiedUser": null,
    "EnumeratedSetName": "",
    "UserDefinedTypeName": "",

```

```

"CalcType": 0,

"IsStale": false,

"HasAlias": false,

"NumberOfElements": 0,

"CollectionDisabled": false,

"LastModified": 1496992712,

"LastModifiedString": "2017-06-09T07:18:32Z"

},

<SNIP>

},

"Links": {

"first": "https://anilgwx:443/historian-rest-api/v1/tagslist?pageno=1&pagesize=4",

"last": "https://anilgwx:443/historian-rest-api/v1/tagslist?pageno=258&pagesize=4",

"prev": null,

"next": "https://anilgwx:443/historian-rest-api/v1/tagslist?pageno=2&pagesize=4"

}

}

```

The Raw Data API

The Raw Data API queries raw data, such as a number of samples or the time range for a list of tags. If the count is not zero, then the API service returns the number of raw samples taken beginning from the start time. If the count is zero, then the service returns the raw samples taken between the start time and the end time.

METHOD:	GET, POST
URI:	<p>GET</p> <p>https://<historianservername>:443/historian-rest-api/v1/datapoints/raw/{tagNames}/{start}/{end}/{direction}/{count}</p> <p>POST</p> <p>https://<historianservername>:443/historian-rest-api/v1/datapoints/raw/{start}/{end}/{direction}/{count}</p>
SAMPLE GET URI:	Raw By Number

	<p>Count value is a non-zero positive number, and end time is greater than start time.</p> <pre>https://<historianservername>:443/historian-rest-api/datapoints/raw/tagName1/2013-10-02T11:30:00.111Z/2013-10-02T11:31:11.111Z/0/100https://<historianservername>:443/historian-rest-api/datapoints/raw/tagNames=tagName1&start=2013-10-02T11:30:00.111Z&end=2013-10-02T11:31:11.111Z&count=100&direction=0</pre> <p>Raw By Time</p> <p>The count value equals 0.</p> <pre>https://<historianservername>:443/historian-rest-api/datapoints/raw/tagName1/2013-10-02T11:30:00.111Z/2013-10-02T11:31:11.111Z/0/0https://<historianservername>:443/historian-rest-api/datapoints/raw/tagNames=tagName1&start=2013-10-02T11:30:00.111Z&end=2013-10-02T11:31:11.111Z&count=0&direction=0</pre>
<p>SAMPLE POST URI:</p>	<p>Raw By Number</p> <p>Count value is a non-zero positive number, and end time is greater than start time.</p> <pre>https://<historianservername>:443/historian-rest-api/datapoints/raw/2013-10-02T11:30:00.111Z/2013-10-02T11:31:11.111Z/0/100https://<historianservername>:443/historian-rest-api/datapoints/raw/start=2013-10-02T11:30:00.111Z&end=2013-10-02T11:31:11.111Z&count=100&direction=0</pre> <p>Raw By Time</p> <p>The count value equals 0.</p> <pre>https://<historianservername>:443/historian-rest-api/datapoints/raw/2013-10-02T11:30:00.111Z/2013-10-02T11:31:11.111Z/0/0https://<historianservername>:443/historian-rest-api/datapoints/raw/</pre>

	<code>start=2013-10-02T11:30:00.111Z&end=2013-10-02T11:31:11-111Z&count=0&direction=0</code>
SAMPLE cURL COMMAND (GET): [Raw By Number]	<code>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/ datapoints/raw/<tagName>/<start time>/<end time>/<direction>/<count></code>
SAMPLE cURL COMMAND (GET): [Raw By Time]	<code>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/ datapoints/raw/<tagName>/<start time>/<end time>/<direction>/0</code>
SAMPLE cURL COMMAND (POST): [Raw By Number]	<code>curl -X POST -i -H "Content-Type: application/json" -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" -d "{\"tagNames\": \"<tagName>;<tagName>\"}" http:// <nodename>/ historian-rest-api/v1/ datapoints/raw/ <start time>/<end time>/<direction>/<count></code>
SAMPLE cURL COMMAND (POST): [Raw By Time]	<code>curl -X POST -i -H "Content-Type: application/json" -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" -d "{\"tagNames\": \"<tagName>;<tagName>\"}" http:// <nodename>/ historian-rest-api/v1/ datapoints/raw/ start=<start time>&end=<end time>&direction=<direction>&count=<count></code>

Table 228. Query Parameters

Parameter	Description	Required?	Values
TagNames	Queries the specified tag names.	Yes	String
Start	Start time of the query, in ISO data format (such as YYYY-MM-DDTHH:m:m:ss.SSSZ).	Yes	DateTime
End	End time of the query, in ISO data format (such as YYYY-MM-DDTHH:m:m:ss.SSSZ).	Yes	DateTime
Direction	Specifies the direction (Forward or Backward	Yes	Integer, with a value such as 1.

Table 228. Query Parameters (continued)

Parameter	Description	Re-quired?	Values
	from the starting time) of data sampling from the archive. The default value is Forward (1).		
Count	Count of archive values within each calculation interval.	Yes	Integer, with a value such as 100.

Table 229. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, 0.
ErrorMessage	String	Yes	For example, NULL.
Data	String	Yes	<p>The object container for the following parameters:</p> <p>DataType</p> <p>DoubleFloat, which stores decimal values up to 15 places.</p> <p>ErrorCode</p> <p>Value is 0, which means the operation was successful.</p> <p>TagName</p> <p>Example: TagName1.</p> <p>Samples</p> <p>Provides TimeStamp, Value, Quality, and DtatAttributes for each sample. Where, DataAttributes is</p>

Table 229. Response Parameters (continued)

Parameter	Data Type	Required?	Description
			<p>the detailed information regarding the Quality.</p> <p>For example,</p> <pre> "TimeStamp": "2013-10-02T11:30:00.111Z", "Value": 34.26155", "Quality": 3, "DataAttributes": [] </pre>

The Interpolated Data API

The Interpolated Data API queries interpolated values for a list of tags. If the start time equals the end time, the request returns one sample.

METHOD:	GET, POST
URI:	<p>GET</p> <pre> https://<historianservername>:443/historian-rest-api/v1/datapoints/interpolated/{tag-Names}/{start}/{end}/{count}/{intervalMs} </pre> <p>POST</p> <pre> https://<historianservername>:443/historian-rest-api/v1/datapoints/interpolated/{start}/{end}/{count}/{intervalMs} </pre>
SAMPLE GET URI:	<pre> https://<historianservername>:443/historian-rest-api/v1/datapoints/interpolated/tag-Name1/2013-10-02T11:30:00.111111Z/2013-10-02T11:31:11.111Z/100/10000 </pre>
SAMPLE POST URI:	<pre> https://<historianservername>:443/historian-rest-api/v1/datapoints/interpolated/2013-10-02T11:30:00.111111Z/2013-10-02T11:31:11.111Z/100/10000 </pre>
SAMPLE cURL COMMAND (GET):	<pre> curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/ </pre>

	datapoints/interpolated/<tagName>/<start time>/<end time>/<count>/<intervalMS>
SAMPLE cURL COMMAND (POST):	curl -i -X POST -H "Content-Type: application/json" -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" -d "{\"tagNames\": \"<tagName>\"}" http://<nodename>:443/historian-rest-api/v1/datapoints/interpolated/<start time>/<end time>/<count>/<intervalMS>

Table 230. Query Parameters

Parameter	Description	Required?	Values
TagName	Queries the tag names specified.	Yes	String
Start	Start time of the query, in ISO data format (such as YYYY-MM-DDTHH:m-m:ss.SSSZ).	Yes	DateTime
End	End time of the query, in ISO data format (such as YYYY-MM-DDTHH:m-m:ss.SSSZ).	Yes	DateTime
Count	Count of archive values within each calculation interval.	Yes	Integer, with a value such as 100.
intervalMS	Interval in milliseconds.	Yes	64-bit signed integer, with a value such as 10000.

Table 231. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, 0.
ErrorMessage	String	Yes	For example, NULL.
Data	String	Yes	The object container for the following parameters:

Table 231. Response Parameters (continued)

Parameter	Data Type	Required?	Description
			<p>Data Type</p> <p>DoubleFloat, which stores decimal values up to 15 places.</p> <p>Error Code</p> <p>Value is 0, which means the operation was successful.</p> <p>TagName</p> <p>Example is TagName1.</p> <p>Samples</p> <p>Provides TimeStamp, Value and Quality for each sample. For example, TimeStamp = 2013-10-02T11:30:00.111Z, Value = 34.26155, and Quality = 3.</p>

The Current Value API

The Current Value API queries the current value data and reads the current values for a list of tags. If the start time is equal to end time, the request returns one sample.

METHOD:	GET, POST
URI:	<p>GET</p> <p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/raw/{tagNames}/{start}/{end}/{direction}/{count}</code></p> <p>POST</p> <p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/currentvalue</code></p>

SAMPLE GET URI:	<code>https://<historianservername>:443/historian-rest-api/v1/datapoints/currentvalue?tagNames=tagName1</code>
SAMPLE POST URI:	<code>https://<historianservername>:443/historian-rest-api/v1/datapoints/currentvalue</code>
SAMPLE cURL COMMAND (GET):	<code>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/datapoints/currentvalue/<tagName></code>
SAMPLE cURL COMMAND (POST):	<code>curl -i -X POST -H "Content-Type: application/json" -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" -d "{\"tagNames\": \"<tagName>\"}" http://<nodename>:443/historian-rest-api/v1/datapoints/currentvalue</code>

Table 232. Query Parameters

Parameter	Description	Required?	Values
TagNames	Queries the specified tag names.	Yes	String

Table 233. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, 0.
ErrorMessage	String	Yes	For example, NULL.
Data	String	Yes	<p>The object container for the following parameters:</p> <p>DataType</p> <p>DoubleFloat, which stores decimal values up to 15 places.</p> <p>ErrorCode</p> <p>Value is 0, which means the operation was successful.</p>

Table 233. Response Parameters (continued)

Parameter	Data Type	Required?	Description
			<p>TagName</p> <p>Example is TagName1.</p> <p>Samples</p> <p>Provides TimeStamp, Value and Quality for each sample. For example, TimeStamp = 2014-01-01T12:00:00Z, Value = 34.26155, and Quality = 3.</p>

The Calculated Data API

The Calculated Data API queries the calculated data for a list of tags. Data can be requested using a number of samples or a time range for a list of tags. If the count is not zero, the service returns the number of raw samples beginning from the start time. If the count is zero, the services uses the interval, start time, and end time to calculate the required sample number.

METHOD:	GET, POST
URI:	<p>GET</p> <p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/calculated/{tagNames}/{start}/{end}/{calculationMode}/{count}/{intervalMs}</code></p> <p>POST</p> <p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/calculated/{start}/{end}/{calculationMode}/{count}/{intervalMs}</code></p>
SAMPLE GET URI:	<p>Number of Samples</p> <p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/calculated/tagName1/2013-10-02T11:30:00.111Z/2013-10-02T11:31:11.111Z/1/100/1000</code></p>

	<p>Time Range for List of Tags</p> <pre>https://<historianservername>:443/historian-rest-api/v1/datapoints/calculated?tagNames=tagName1&start=2013-10-02T11:30:00.111Z&end=2013-10-02T11:31:11.111Z&count=100&calculationMode=1&intervalMs=1000</pre>
<p>SAMPLE POST URI:</p>	<p>Number of Samples</p> <pre>https://<historianservername>:443/historian-rest-api/v1/datapoints/calculated/2013-10-02T11:30:00.111Z/2013-10-02T11:31:11.111Z/1/100/1000</pre> <p>Time Range for List of Tags</p> <pre>https://<historianservername>:443/historian-rest-api/v1/datapoints/calculated?start=2013-10-02T11:30:00.111Z&end=2013-10-02T11:31:11.111Z&count=100&calculationMode=1&intervalMs=1000</pre>
<p>SAMPLE cURL COMMAND (GET):</p>	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" http://<nodename>:8843/historian-rest-api/v1/datapoints/calculated/<tagName>/<start time>/<end time>/<count>/<calculation mode>/<intervalMS></pre>
<p>SAMPLE cURL COMMAND (POST):</p>	<pre>curl -i -X POST -H "Content-Type: application/json" -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" -d "{\"tagNames\": \"<tagName>\"}" http://<nodename>:8843/historian-rest-api/v1/datapoints/calculated/<start time>/<end time>/<count>/<calculationmode>/<intervalMS></pre>

Table 234. Query Parameters

Parameter	Description	Required?	Values
TagNames	GE identifier for a location.	Yes	1000000106
Start	Start time of the query, in ISO data format (such as YYYY-MM-DDTHH:m-m:ss.SSSZ).	Yes	DateTime

Table 234. Query Parameters (continued)

Parameter	Description	Re-quired?	Values
End	End time of the query, in ISO data format (such as YYYY-MM-DDTHH:m-m:ss.SSSZ).	Yes	DateTime
Count	Count of archive values within each calculation interval.	Yes	Integer, with a value such as 100.
Calculation Mode		Yes	Integer, with a value such as 1. For more information on the calculation modes, refer to calculation modes for REST API.
IntervalMS	Interval in milliseconds.		64-bit signed integer, with a value such as 1000.

Table 235. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, 0.
ErrorCode	String	Yes	For example, NULL.
Data	String	Yes	<p>The object container for the following parameters:</p> <p>DataType</p> <p>DoubleFloat, which stores decimal values up to 15 places.</p> <p>ErrorCode</p> <p>Value is 0, which means the operation was successful.</p> <p>TagName</p>

Table 235. Response Parameters (continued)

Parameter	Data Type	Required?	Description
			<p>Example is TagName1.</p> <p>Samples</p> <p>Provides TimeStamp, Value and Quality for each sample. For example, TimeStamp = 2013-10-02T11:30:00.111Z, Value = 34.26155, and Quality = 3.</p>

The Sampled Data API

The Sampled Data API queries the sampled data for a list of tags. Data can be requested using a number of samples or a time range for a list of tags. If the count is not zero, the service returns the number of raw samples beginning from the start time. If the count is zero, the services uses the interval, start time, and end time to calculate the required sample number.



Note:

For the query, you can also use optional parameters such as FilterMode and ReturnDataFields. Unused parameters can be omitted.

METHOD:	GET, POST
URI:	<p>GET</p> <p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/sampled</code></p> <p>POST</p> <p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/sampled</code></p>
SAMPLE GET URI:	<code>https://<historianservername>:443/historian-rest-api/v1/datapoints/sampled?tagNames=tagName1&start=2013-10-02T11:30:00.111Z&end=2013-10-02T11:31:11-</code>

	<code>.111Z&samplingMode=1&calculationMode=1&direction=0&count=0&intervalMs=1000</code>
SAMPLE POST URI:	<code>https://<historianservername>:443/historian-rest-api/v1/datapoints/sampled</code>
SAMPLE cURL COMMAND (GET):	<code>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/datapoints/sampled/<tagName>/<start time>/<end time>/<direction>/<count>/<intervalMS></code>
SAMPLE cURL COMMAND (POST):	<code>curl -i -X POST -H "Content-Type: application/json" -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"tagNames\": \"<tagName>\", \"start\": \"<start>\", \"end\": \"<end>\", \"samplingMode\": <samplingMode>, \"calculationMode\": <calculationMode>, \"direction\": <direction>, \"count\": <count>, \"returnDataFields\": <returnDataFields>, \"intervalMs\": <intervalMs>, \"queryModifier\": <queryModifier>, \"filterMode\": <filterMode>, \"filterExpression\": \"<filterExpression>\"}" http://<nodename>:443/historian-rest-api/v1/datapoints/sampled</code>

Table 236. Query Parameters

Parameter	Description	Required?	Values
TagNames	Queries the tag names specified.	Yes	String
Start	Start time of the query, in ISO data format (such as YYYY-MM-DDTHH:m-m:ss.SSSZ).	Yes	DateTime
End	End time of the query, in ISO data format (such as YYYY-MM-DDTHH:m-m:ss.SSSZ).	Yes	DateTime
Sampling-Mode	Also known as SamplingModeType.	Optional	Integer, with a value such as 1.

Table 236. Query Parameters (continued)

Parameter	Description	Re-quired?	Values
Calculation-Mode	Also known as CalculationModeType.	Optional	Integer, with a value such as 1.
Direction	Specifies the direction (Forward or Backward from the starting time) of data sampling from the archive. The default value is Forward (1).	Optional	Integer, with a value such as 1.
Count	The count of archive values within each calculation interval.	Optional	Integer, with a value such as 0.
IntervalMS	Interval in milliseconds.	Optional	64-bit signed integer, with a value such as 1000.

Table 237. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, 0.
ErrorCode	String	Yes	For example, NULL.
Data	String	Yes	<p>The object container for the following parameters:</p> <p>DataType</p> <p>DoubleFloat, which stores decimal values up to 15 places.</p> <p>ErrorCode</p> <p>Value is 0, which means the operation was successful.</p> <p>TagName</p>

Table 237. Response Parameters (continued)

Parameter	Data Type	Required?	Description
			<p>Example is TagName1.</p> <p>Samples</p> <p>Provides TimeStamp, Value and Quality for each sample. For example, TimeStamp = 2013-10-02T11:30:00.111Z, Value = 34.26155, and Quality = 3.</p>

The Trend Data API

The Trend Data API queries the trend data for a list of tags.

 **Note:**
 For the query, you can also use optional parameters such as FilterMode and StatisticsItemFilter. Unused parameters can be omitted.

METHOD:	GET, POST
URI:	<p>GET</p> <p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/trend</code></p> <p>POST</p> <p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/trend</code></p>
SAMPLE GET URI:	<p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/trend?tagNames=tagName1&start=2013-10-02T11:30:00.111Z&end=2013-10-02T11:31:11.111Z&samplingMode=1&calculationMode=1&direction=0&count=0&intervalMs=1000</code></p>
SAMPLE POST URI:	<p><code>https://<historianservername>:443/historian-rest-api/v1/datapoints/trend</code></p>

SAMPLE cURL COMMAND (GET):	<pre>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" http://<nodename>:443/historian-rest-api/v1/datapoints/trend/<tagName>/<start time>/<end time>/<samplingMode>/<calculationMode>/<direction>/<count>/<intervalMS></pre>
SAMPLE cURL COMMAND (POST):	<pre>curl -i -X POST -H "Content-Type: application/json" -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"tagNames\": \"<tagName>\", \"start\": \"<start>\", \"end\": \"<end>\", \"samplingMode\": <samplingMode>, \"calculationMode\": <calculationMode>, \"direction\": <direction>, \"count\": <count>, \"returnDataFields\": <returnDataFields>, \"intervalMs\": <intervalMs>, \"queryModifier\": <queryModifier>, \"filterMode\": <filterMode>, \"filterExpression\": \"<filterExpression>\"}" http://<nodename>:443/historian-rest-api/v1/datapoints/trend</pre>

Table 238. Query Parameters

Parameter	Description	Required?	Values
TagNames	Queries the tag names specified.	Yes	String
Start	Start time of the query, in ISO data format (such as YYYY-MM-DDTHH:m-m:ss.SSSZ).	Yes	DateTime
End	End time of the query, in ISO data format (such as YYYY-MM-DDTHH:m-m:ss.SSSZ).	Yes	DateTime
Sampling-Mode	Also known as SamplingModeType.	Optional	Integer, with a value such as 1.
Calculation-Mode	Also known as CalculationModeType.	Optional	Integer, with a value such as 1.
Direction	Specifies the direction (Forward or Backward	Optional	Integer, with a value such as 1.

Table 238. Query Parameters (continued)

Parameter	Description	Re-quired?	Values
	from the starting time) of data sampling from the archive. The default value is Forward (1).		
Count	The count of archive values within each calculation interval.	Optional	Integer, with a value such as 0.
IntervalMS	Interval in milliseconds.	Optional	64-bit signed integer, with a value such as 1000.

Table 239. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, 0.
ErrorMessage	String	Yes	For example, NULL.
Data	String	Yes	<p>The object container for the following parameters:</p> <p>TagName</p> <p>Name of the tag, such as ahistfile.Simulation00001.</p> <p>TagSource</p> <p>Location where tags are being searched for.</p> <p>Data Type</p> <p>Float, which stores decimal values up to 6 places.</p> <p>Trend</p> <p>Provides TimeStamp, Value and Quality for each sample. For ex-</p>

Table 239. Response Parameters (continued)

Parameter	Data Type	Required?	Description
			ample, TimeStamp = 2016-03-15T04:53:17.000Z, Value = 170903.6563, and Quality = True.

The Add Single Tag API

For the Add Single Tag API, you can add a new tag to Historian, and the tag name and data type must be provided in the payload (parameter) of the method. All other tags are optional. If a property is provided, the respective validation is performed at the server end. If the tag exists, then any new properties provided in the payload are applied to the existing tag.

METHOD:	POST
URI:	https://<historianservername>:443/historian-rest-api/v1/tags/addtag
SAMPLE URI:	<pre>https://<historianservername>:443/historian-rest-api/v1/tags/addtag Payload: { "Name" : "SampleTag", "DataType" : 3 }</pre>
SAMPLE cURL COMMAND:	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"Name\": \"Sampletag\", \"DataType\": 3}" -X POST https://<historianservername>:443/historian-rest-api/v1/tags/addtag</pre>

Table 240. Query Parameters

Parameter	Description	Required?	Values
Payload	JSON array of PropertyName and PropertyValue.	Yes. "Name" and "DataType" properties are required.	Multidata types. See Payload Parameter (on page 1245) for a list of tag prop-

Table 240. Query Parameters (continued)

Parameter	Description	Required?	Values
		All other properties are optional.	Properties used to update a tag configuration.

Sample Response

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, 0.
ErrorMessage	String	Yes	For example, NULL.

The Add Bulk Tags API

For the Add Bulk Tags API, you can add new tags to Historian using an array, and the tag names and data types must be provided in the payload (parameter) of the method. All other tags are optional. If a property is provided, the respective validation is performed at the server end. If the tags exist, then any new properties provided in the payload are applied to the existing tags. The payload is be an array of tags defined.

METHOD:	POST
URI:	<code>https://<historianservername>:443/historian-rest-api/v1/tags/addtags</code>
SAMPLE URI:	<pre>https://<historianservername>:443/historian-rest-api/v1/tags/addtags Payload: [{ "Name" : "SampleTag1", "DataType" : 3 }, { "Name" : "SampleTag2", "DataType" : 3 }]</pre>

SAMPLE cURL COMMAND:	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "[{ \"Name\": \"Sampletag1\"}, { \"Name\": \"Sampletag2\"}]" -X POST https://<historianservername>:443/historian-rest-api/v1/tags/addtags</pre>
-----------------------------	---

Table 241. Query Parameters

Parameter	Description	Required?	Values
Payload	JSON array tags with individual tags of PropertyName and PropertyValue.	Yes. "Name" and "DataType" properties are required. All other properties are optional.	Multidata types. See Payload Parameter (on page 1245) for a list of tag properties used to update a tag configuration.

Table 242. Response Parameters

Parameter	Data Type	Exists?	Description
TagName	String	Yes	Tag name.
ErrorCode	Integer	Yes	For example, 0.
ErrorMessage	String	Yes	For example, NULL.

The Update Tag Configuration API

The Update Tag Configuration API allows you to set or modify any tag property values. You cannot, however, rename a tag using this API.

METHOD:	PUT
URI:	https://<historianservername>:443/historian-rest-api/v1/tags/properties/tagName
SAMPLE DELETE URI:	<pre>https://<historianservername>:443/historian-rest-api/v1/tags/properties/tagName</pre> <p>Payload:</p> <pre>{ "PropertyName" : "PropertyValue" }</pre>

SAMPLE cURL COMMAND:	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"Description\": \"SampleDesc\"}" -X PUT https://<historianservername>:443/historian-rest-api/v1/tags/properties/tagName</pre>
-----------------------------	---

Table 243. Query Parameters

Parameter	Description	Required?	Values
tagName	Tag name for which properties need to be set or modified.	Yes	String
Payload	JSON array of Property-Name and Property-Value.	At least one property must be provided.	Multidata types. See Payload Parameter (on page 1245) for a list of tag properties used to update a tag configuration.

Table 244. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, 0.
ErrorMessage	String	Yes	For example, NULL.

The Get Tag Properties API

You can use this API to specify which properties are required for retrieval. If no property names are provided, then all properties are retrieved. When using the Get Tag Properties method, requesting a non-existent tag name returns an error.

METHOD:	GET / POST
URI: (GET)	<pre>https://<historianservername>:443/historian-rest-api/v1/tags/properties/tagName</pre> This URI returns all tag properties.
URI: (POST)	<pre>https://<historianservername>:443/historian-rest-api/v1/tags/properties/tagName</pre>

	<pre>Payload { "PropertyName1" : 1, "PropertyName2" : 1 }</pre>
SAMPLE GET URI:	<code>https://<historianservername>:443/historian-rest-api/v1/tags/properties/tagName</code>
SAMPLE POST URI:	<pre>https://<historianservername>:443/historian-rest-api/v1/tags/properties/tagName Payload: { "Description" : 1 }</pre>
SAMPLE cURL GET COMMAND:	<code>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -X GET https://<historianservername>:443/historian-rest-api/v1/tags/properties/tagName</code>
SAMPLE cURL POST COMMAND:	<code>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"Description\": 1}" -X POST https://<historianservername>:443/historian-rest-api/v1/tags/properties/tagName</code>

Table 245. Query Parameters

Parameter	Description	Required?	Values
tagName	Tag name for which properties need to be retrieved.	Yes	String
Payload	JSON array of Property-Name and boolean (true/false).	At least one property must be provided.	Multi data types. See Payload Parameter (on page 1245) for a list of tag properties used to update a tag configuration.

**Note:**

The query payload contains all the tag properties you want returned from the server. In the Update Tag Config method, you need to provide the actual tag property value. However, in the Get Tag Properties method, you need to provide the property and a value of 1 (true), to allow it to be read from the server and returned.

Table 246. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, 0.
ErrorMessage	String	Yes	For example, NULL.
Name	String	Optional	If no error, then the tag name of query is returned and all requested parameters.

The Delete Tag API

The Delete Tag API provides the ability to delete an existing tag from the Historian server.

Its URI format supports question marks (?).

METHOD:	DELETE
URI:	<code>https://<historianservername>:443/historian-rest-api/v1/tags/tag-Name?{permanentDelete}</code>
SAMPLE DELETE URI:	<code>https://<historianservername>:443/historian-rest-api/v1/tags/tag-Name?permanentDelete=true</code>
SAMPLE CURL COMMAND:	<code>curl -i -H "Authorization: Bearer <TOKEN>" -X DELETE https://<historianservername>:443/historian-rest-api/v1/tags/tagName?permanentDelete=<true false></code>

Table 247. Query Parameters

Parameter	Description	Re-quired?	Values
tagName	Name of the tag to be deleted.	Yes	String

Table 247. Query Parameters (continued)

Parameter	Description	Re-quired?	Values
permanent-Delete	Deletes the tag permanently from the Historian server if the value passed in is true. If the parameter is not provided, then permanent-Delete is assumed to be false.	Optional (false is default)	Boolean, true or false

Table 248. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Number	Yes	For example, ErrorCode=0, which means the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

The Query Results API

The Query Results API enables you to include the number of samples required, by providing an end point to configure query results.

The minimum number of samples should be 1000.

METHOD:	PUT
URI:	<code>https://<historianservername>:443/historian-rest-api/v1/data-points/ configuration/{maxDataQueryResultSize}</code>
SAMPLE URI:	<code>https://<historianservername>:443/historian-rest-api/v1/data-points/ configuration?maxDataQueryResultSize=6000</code>
SAMPLE CURL COMMAND:	<code>curl -i -H "Accept: application/json" -H "Authorization: Bearer <TOKEN>" https://<nodename>:443/ historian-rest-api/v1/data-points/configuration? maxDataQueryResultSize=<Number_Of_Query_Results></code>

Table 249. Query Parameters

Parameter	Description	Re-quired?	Values
maxDataQueryResultSize	Maximum samples that should be configured as part of Query Results.	Yes	Integer

Table 250. Response Parameters

Parameter	Data Type	Required?	Description
Error Code	Integer	Yes	For example, 0.
Error Message	String	Yes	For example, NULL.
Maximum DataQueryResultSize	Integer	Yes	Returns the number of samples that were configured as part of query. For example, based on the sample URI, this parameter will be 6000.

The Tag Rename API

This API allows the administrator to rename tags.

METHOD:	PUT
URI	<code>https://<historianservername>:443/historian-rest-api/v1/tags/tagrename/oldtagname/newtagname?truerename</code>
SAMPLE URI	<code>https://<historianservername>:443/historian-rest-api/v1/tags/tagrename/GDW14NV2E.Simulation0000101/GDW14NV2E.Simulation0000101new-name?truerename= <true false></code>
SAMPLE CURL COMMAND	<code>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json"-H "Authorization: Bearer <TOKEN> -X PUT https://<historianservername>:443/historian-rest-api/v1/tags/tagrename/<oldtagname>/<newtagname>?truerename=<true false></code>

Table 251. Query Parameters

Parameter	Description	Required?	Values
oldtagname	Tag which is to be re-named.	Yes	String
newtagname	New name for the selected tag.	Yes	String
truerename	Renames the tag permanently if the value entered is true. Creates an alias if the value entered is false.	Optional (false is default)	Boolean (true or false)

Table 252. Response Parameters

Parameter	Data Type	Required?	Description
Error Code	Integer	Yes	For example, 0.
Error Message	String	Yes	For example, NULL.
Data	List	Yes	Returns all the properties of the tag.

The Write Tag API

Write Tag Data API enables you to create data for tags. You can write data to a tag for different data types such as integer, float, array, multifield and so on. Once created, you can view the data using other end points. Only REST API Administrator and users with write permission can perform this operation.

Method	POST
URI	<code>https://<historianservername>:443/historian-rest-api /v1/datapoints/create</code>
SAMPLE URI	<code>https://<historianservername>:443/historian-rest-api /v1/datapoints/create</code>

Method	POST
	<pre> Payload { "TagName": "GDW14NV2E.Simulation00015", "samples": [{ "TimeStamp": "2019-09-17T15:58:00.000Z", "Value": "1", "Quality": 3 }] } </pre>
<p>SAMPLE RESPONSE</p>	<pre> { "ErrorCode": 0, "ErrorMessage": "" } </pre>
<p>SAMPLE CURL COMMAND</p>	<pre> curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer <TOKEN>" -d "{ \"TagName\": \"GDW14NV2E.Simula- tion00015\", \"samples\": [{\"TimeStamp\": \" 2019-09-17T15:58:00.000Z\", \"Val- ue\": \"1\", \"Quality\": 3}]}\" -X POST https://<historianservername>:443/histo- rian-rest-api/v1/datapoints/create </pre>

Table 253. Query Parameters

Parameter	Description	Required?	Values
Payload	JSON format of Property Name and Property Value.	Yes	Multi-data types. It can have integer, float, array, multifield data types.

Table 254. Response Parameters

Parameter	Data Type	Required?	Description
Error Code	Integer	Yes	For example, ErrorCode = 0, which means the operation was successful.
Error Message	String	Yes	For example, NULL.

Calculation Modes for REST API

Calculation modes are used on retrieval of data that has already been collected to the archive. Calculation modes are used when the sampling mode is set to "Calculated". The table below lists the different calculation modes and their corresponding value that you can pass as part of the query parameters to manage tags.

Calculation Mode	Value
Average	1
StandardDeviation	2
Total	3
Minimum	4
Maximum	5
Count	6
RawAverage	7
RawStandardDeviation	8
RawTotal	9

Calculation Mode	Value
MinimumTime	10
MaximumTime	11
TimeGood	12
StateCount	13
StateTime	14
OPCAnd	15
OPCOr	16
FirstRawValue	17
FirstRawTime	18
LastRawValue	19
LastRawTime	20
TagStats	21
DeltaPos	22
DeltaNeg	23
Delta	24

Managing Alarms and Events

Overview

Historian includes Alarms and Events (A&E) archiving to provide the ability to retrieve and store Alarms and Events Data from any OPC-compliant A&E server through the OPC Classic Alarms and Events collector.

Alarms are generally defined as tags going into an abnormal condition. For example, an alarm could be set on a boiler when it reaches a specified temperature. Alarms usually have a well-defined life cycle, which is defined by the individual data sources the alarms are collected from (iFIX, for example). They enter an alarm state, are generally acknowledged, and then return to normal.

Events are generally defined as activities in a system that occur only once. For example, a user logging on to a device is an event. When viewing this data in Historian, each event is

returned as a record. The Historian REST API provide API's to store, retrieve, backup, restore, and delete alarms and events data.

Add Alarm or Event

Add alarm API allows you to create alarm in Historian Server.

METHOD	POST
URI	<pre>https://<historianservername>:443/historian-rest-api/v1/alarms/create</pre>
SAMPLE URI	<pre>https://<historianservername>:443/historian-rest-api/v1/alarms/create</pre> <p>Payload</p> <pre>{ "DataSource": "Simulation", "AlarmsInfo": [{ "ItemId": "GF7DQL63E_Simulation.Simulation00001", "Source": "Simulation", "DataSourceName": "Simulation", "Tagname": "GF7DQL63E_Simulation.Simulation00001", "AlarmType": 4, "EventCategory": "SimCategory", "ConditionName": "Simulation", "SubConditionName": "Simulation", "StateTransitionTime": "2022-09-21T5:58:00.000Z", "StartTime": "2022-09-21T5:58:00.000Z", "EndTime": "2022-09-21T6:58:00.000Z", "AckTime": "2022-09-21T6:58:00.000Z", "TimeStamp": "2022-09-21T5:58:00.000Z", "Message": "This is simulation alarm",</pre>

	<pre> "Severity":100, "Actor":"Simulator", "Quality":3 }] } </pre>
<p>SAMPLE CURL COMMAND</p>	<pre> curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer " -d "{ \"DataSource\": \"Simulation\", \"AlarmsInfo\": [{ \"ItemId\": \"GF7DQL63E_Simulation.Simulation00001\", \"Source\": \"Simulation\", \"DataSourceName\": \"Simulation\", \"Tagname\": \"GF7DQL63E_Simulation.Simulation00001\", \"AlarmType\": 4, \"EventCategory\": \"SimCategory\", \"ConditionName\": \"Simulation\", \"SubConditionName\": \"Simulation\", \"StateTransitionTime\": \"2022-09-21T5:58:00.000Z\", \"StartTime\": \"2022-09-21T5:58:00.000Z\", \"EndTime\": \"2022-09-21T6:58:00.000Z\", \"AckTime\": \"2022-09-21T6:58:00.000Z\", \"TimeStamp \": \"2022-09-21T5:58:00.000Z\", \"Message\": \"This is simulation alarm\", </pre>

```

        \Severity\":100,
        \Actor\": \"Simulator\",
        \Quality\":3
    }
}
} -X PUT https://:443/historian-rest-api/v1/
alarms/create
    
```

Table 255. Query Parameters

Parameter	Data Type	Description
DataSource	VT_- BSTR	The collector interface name associated with the alarm or event.
ItemId	VT_- BSTR	The OPC <code>ItemID</code> of the alarm. This contains the source address of the data access tag with which the alarm is associated. This can contain a <code>NULL</code> value if an alarm is not associated with a tag.
Source	VT_- BSTR	The unique identifier used by the OPC A&E Collector for the alarm or event.
Data- SourceName	VT_- BSTR	The collector interface name associated with the alarm or event.
Tagname	VT_- BSTR	The Historian tag name associated with the alarm. This value is <code>NULL</code> unless the tag is also collected by Historian
AlarmType	VT_- BSTR	The alarm type: <ul style="list-style-type: none"> • <code>Alarms</code>: In Historian, the full life cycle of an alarm is stored as a single record in the alarm archive. • <code>Alarm_History</code>: The separate transitions for all alarms. One row per transition is returned. • <code>Events</code>: The simple and tracking events.
EventCate- gory	VT_- BSTR	The OPC event category of the alarm or event.
Condition- Name	VT_- BSTR	The OPC condition of the alarm. Does not apply to event data. This value combined with the Source value comprises an alarm.

Table 255. Query Parameters (continued)

Parameter	Data Type	Description
SubConditionName	VT_- BSTR	The OPC subcondition of the alarm. Does not apply to event data. This value represents the state of the alarm.
StateTransitionTime	VT_- DB- Time- S- tamp	The time the state of the tag was generated.
StartTime	VT_- DB- Time- S- tamp	The start time or timestamp of the alarm or event.
EndTime	VT_- DB- Time- S- tamp	The end time of the alarm. Does not apply to event data.
AckTime	VT_- DB- Time- S- tamp	The time the alarm was acknowledged. Does not apply to event data.
TimeStamp	VT_- DB- Time- S- tamp	The time the alarm was generated.
Message	VT_- BSTR	The message attached to the alarm or event.

Table 255. Query Parameters (continued)

Parameter	Data Type	Description
Severity	VT_- I4	The severity of the alarm or event. Stored as an integer value with a range of 1–1000.
Actor	VT_- BSTR	The operator who acknowledged the alarm, or caused the tracking event.
Quality	VT_- I4	The quality of the alarm or event.

Table 256. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

Query Alarm or Event

The following table contains the query parameters for alarms and events data.

METHOD	POST
URI	<code>https://<historianservername>:443/historian-rest-api/v1/alarms/query</code>
SAMPLE URI	<p><code>https://<historianservername>:443/historian-rest-api/v1/alarms/query</code></p> <p>Payload:</p> <pre>{ "AlarmType": "4", "StartTime": "2022-10-30T3:30:00.000Z", "EndTime": "2022-10-31T4:30:00.000Z", "DataSourceName": "GF7DQL63E_Simulation", "MaxRecords": 50 }</pre> <p>Response:</p>

	<pre>{ "ErrorCode": 0, "ErrorMessage": null, "Data": [{ "Description": "This is a simulated alarm.", "Source": "Simulation00001_ALM", "StartTime": "2022-10-30T03:30:00.000Z", "EndTime": "2022-10-30T03:30:02.000Z", "Condition": "Simulated", "Sub Condition": "OK", "EventCategory": "SimCategory", "Severity": 0, "ModifiedTime": "2022-10-30T03:30:02.000Z", "Quality": 3 }] }</pre>
<p>SAMPLE CURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer " -d "{ \"AlarmType\": \"4\", \"StartTime\": \"2022-10-30T3:30:00.000Z\", \"EndTime\": \"2022-10-31T4:30:00.000Z\", \"DataSourceName\": \"GF7DQL63E_Simulation\", \"MaxRecords\": 50 }" -X PUT https://:443/historian-rest-api/v1/alarms/ query</pre>

Table 257. Query Parameters

Parameter	Description	Required?	Values
DataSourceName	The collector interface name associated with the alarm or event.	false	
AlarmType	Classifies this AlarmInfo as an alarm or an event. Enter 1 for an event and 4 for an alarm.	yes	
StartTime	The start time or time stamp of the alarm or event.	yes	
EndTime	The end time of the alarm. This does not apply to event data.	yes	
MaxRecords	Maximum records returned	false	

Table 258. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, ErrorCode = 0 implies the operation was successful.
ErrorMessage	String	Yes	For example, NULL.

Delete Alarms or Events

This REST API allows to purge the alarms between time frame.

METHOD	POST
URI	<code>https://<historianservername>:443/historian-rest-api/v1/alarms/delete</code>
SAMPLE URI	<p><code>https://<historianservername>:443/historian-rest-api/v1/alarms/delete</code></p> <p>Payload</p> <pre> https://<historianservername>:443/historian-rest-api/v1/alarms/delete Payload: { "StartTime": "2022-09-21T5:58:00.000Z", "EndTime": "2022-09-21T6:58:00.000Z" } </pre>
SAMPLE CURL COMMAND	<pre> curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer " -d "{ \"StartTime\": \"2022-09-21T5:58:00.000Z\", \"EndTime\": \"2022-09-21T6:58:00.000Z\" }" -X PUT https://:443/historian-rest-api/v1/alarms/delete </pre>

Table 259. Query Parameters

Parameter	Description	Required?	Values
StartTime	The start time or time stamp of the alarm or event.	Yes	
EndTime	The end time of the alarm or event.	Yes	

Table 260. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, -26 A&E Server not connected
ErrorMessage	String	Yes	For example, NULL.

Backup Alarms or Events

This REST API allows to create a copy of the alarm data in an offline file that can be restored later. The alarms are not removed from the online system.

METHOD	POST
URI	<code>https://<historianservername>:443/historian-rest-api/v1/alarms/backup</code>
SAMPLE URI	<p><code>https://<historianservername>:443/historian-rest-api/v1/alarms/backup</code></p> <p>Payload</p> <pre>{ "BackupFileName": "C:\\Proficy Historian Data\\Archives\\abc.zip, "StartTime": "2022-09-21T5:58:00.000Z", "EndTime": "2022-09-21T6:58:00.000Z" }</pre>

<p>SAMPLE CURL COMMAND</p>	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer " -d "{ \"BackupFileName\": \"C:\\Proficy Historian Data\\Archives\\abc.zip\", \"StartTime\": \"2022-09-21T5:58:00.000Z\", \"EndTime\": \"2022-09-21T6:58:00.000Z\" }" -X PUT https://:443/historian-rest-api/v1/alarms/ backup</pre>
-----------------------------------	---

Table 261. Query Parameters

Parameter	Description	Required?	Values
BackupFileName	Path of the backup file.	Yes	C:\\Proficy Historian Data\\Archives\\abc.zip
StartTime	The start time or time stamp of the alarm or event.	Yes	
EndTime	The end time of the alarm or event.	Yes	

Table 262. Response Parameters

Parameter	Data Type	Required?	Description
ErrorCode	Integer	Yes	For example, -26 A&E Server not connected.
ErrorMessage	String	Yes	For example, NULL.

Restoring Alarms or Events

Restoring alarms to a running system makes them available for query and analysis. You can restore alarms that have been backed up previously..

METHOD	POST
--------	------

URI	<code>https://<historianservername>:443/historian-rest-api/v1/alarms/restore</code>
SAMPLE URI	<p><code>https://<historianservername>:443/historian-rest-api/v1/alarms/restore</code></p> <p>Payload:</p> <p><code>C:\\Proficy Historian Data\\Archives\\abc.zip</code></p>
SAMPLE cURL COMMAND	<pre>curl -i -H "Accept: application/json" -i -H "Content-Type: application/json" -H "Authorization: Bearer " -d "C:\\Proficy Historian Data\\Archives\\abc.zip" -X PUT https://:443/historian-rest-api/v1/alarms/ restore</pre>

Table 263. Query Parameters

Parameter	Description	Required?	Values
<code>C:\\Proficy Historian Data\\Archives\\abc.zip</code>	Path of the restore file.	Yes	<code>C:\\Proficy Historian Data\\Archives\\abc.zip</code>

Table 264. Response Parameters

Parameter	Data Type	Required?	Description
<code>ErrorCode</code>	Integer	Yes	For example, 10 invalid parameter.
<code>ErrorMessage</code>	String	Yes	For example, NULL.

Swagger Documentation

You can now access Historian REST APIs using Swagger UI. This tool enables you to visualize and interact with the API's resources without having any of the implementation logic in place establishing a fully interactive documentation experience using Swagger.

Install web-based clients or ensure web-based clients are installed.

This topic describes how to access the Historian REST APIs.

1. Access a node on which Historian web-based clients are installed.
2. Access the following URL: `https://<web-based client machine name>/historian-rest-api/swagger-ui.html`



Note:

To access the link, you must provide the machine name where web-based clients are installed. `https://<machinename>/historian-rest-api/swagger-ui.html`

The Swagger UI appears.

3. Select **Authorize**. The Available authorizations window appears.
4. In the Available authorizations window, scroll down to the **oauth2schema** (OAuth2, password) section, enter the following values, and then select **Authorize**:

Field	Description
username	Enter the web-based client login username. Default <machinename>.admin
password	Enter the web-based client login password.
client_id	Enter client id: historian_public_rest_api
client_secret	Enter publicapisecret as client secret.

5. You can now access the REST APIs for Historian.

Chapter 9. Historian System API

Overview of the Historian System API

Overview of the Historian System API

This document is intended to help in the development of C and C++ programs that interact with Historian at the System API level. With the System API you can develop programs that perform the following functions:

- Create, browse, and modify tags of any data type including User Defined Data Types and array data types.
- Read data as raw samples or using any sampling or calculation mode or filter condition or query modifier.
- Write, delete, and replace data samples.
- Get and Set server properties such as product version, archive size, or data store configuration.

Historian has different APIs based on the programming languages. Both the System API and the User API can be called using C or C++. The System API is used only when the User API does not meet your needs. The User API is more widely used and has greater version compatibility.

System API programs are fully capable but they are subject to Proficy Historian security so you will need to have an understanding of security within Historian.

Message and Alarm functions are not documented. However, for more information you can contact the Technical Support team at GE Intelligent Platforms.

The information that you need to write a collector is not included in the System API, but you can create programs that write data. Refer to the Collector Toolkit documentation if you need to write a collector.

Prerequisites

Programs created with the Historian System API must be run on a computer with at least the following software installed and configured:

- Historian 5.5 Client Tools
- Visual Studio .NET 2010

The Historian Client Tools are installed when the product is installed. You will be able to install the updates and bug fixes along with the product installation. Do not distribute Historian DLLs directly.

You will need a Data Archiver running locally or on another machine. That Data Archiver can be of any version of Historian. The Historian System API has been tested with Visual Studio .NET 2010. The Historian System API has no additional hardware requirements.



Note:

The Historian version where your program is running should be the same as the version of the program you developed.

ihapi.h File Overview

ihapi.h File Overview

All technical information for the System API is included in a single `ihapi.h` header file. This document highlights the areas of `ihapi.h` that might affect your programs.

System API Functions and Data Structures

```
#pragma pack(push,BeforeihAPI)
#pragma pack(1)
```

The System API uses 1 byte packing for structures:

```
// Setup a link dependency on the ihAPI lib
#define ihAPILIB_NAME "ihAPI55.lib"
#define ihAPIDLL_NAME L"ihAPI55.dll"
#define ihAPIDLL_VERSION 550
```

The version specified in the given example changes for each version of Historian. The version of your program should match the version of Historian installed.

```
#ifndef _WCHAR_T_DEFINED
typedef ihPUBLIC wchar_t ihChar;
#else
typedef ihPUBLIC unsigned short ihChar;
#endif
```

The System API uses Unicode. Your program should use `ihChar` for all strings and you can find the correct data type from `ihapi.h` file.

```
typedef struct ihTimeStruct {
MSO_ULONG Seconds;
```

```
MSO_ULONGLONG Nanoseconds;

} ihTimeStruct; // (Must match MSOTimeStruct)
```

Timestamps are nanosecond resolution in the System API. However, only microseconds are exposed to users.

```
// Error Statuses typedef enum
ihStatus { ihSTATUS_OK = 0,
...
} ihStatus;
```

There is a fixed set of error codes and you cannot add new ones. Your program can receive errors on reads or writes or tag adds and those errors will be described with the function documentation.

```
typedef enum ihQualityStatus {
ihOPCBad = 0,
...
} ihQualityStatus;

typedef enum ihQualitySubStatus {
ihOPCNonspecific = 0,
...
} ihQualitySubStatus;
```

Historian uses a fixed set of quality and subquality data and you cannot add new ones.

```
typedef enum ihDataType {
ihDataTypeUndefined = 0,
... } ihDataType;
```

There are a fixed set of data types and user-defined data types. You cannot add new native data types.

```
typedef enum ihSamplingMode {
ihSamplingModeUndefined=0,
...
} ihSamplingMode;

typedef enum ihCalculationMode {
ihCalculationModeUndefined=0,
...
} ihCalculationMode;
```

To read data you should specify a sampling mode, calculation mode, a filter condition (optional), and a query modifier (optional).

```
typedef ihHIDDEN struct ihBlobData {
    ihVoidPtr Blob;
    MSO_ULONG BlobSize;
} ihBlobData;
```

The blob data type is a size and a pointer in the System API

```
typedef struct ihTagProperties {
    ihString Tagname;
    ...
} ihTagProperties;
```

A tag has a fixed set of properties as listed in this structure. Some tag properties may not exist in the earlier versions of Historian and new properties may be added in the future. You are limited to the set of properties available in the version of the ihapi.h shipped with this SDK and you cannot add new tag properties.

```
typedef struct ihDataProperties {
    ihTimeStruct TimeStamp;
    ihDataType ValueDataType;
    ihValue Value;
    ihQuality Quality;
    unsigned char NumberOfComments;
    ihCommentsPtr Comments;
    ihGeoLocation Unsupported;
} ihDataProperties;
```

The given prototype is the structure for one raw data sample and it has timestamp, data type, value, and quality. It can optionally have comments. This structure is used on both data reads and data writes.

```
typedef struct ihDataRecordset {
    ihDataFields Fields;
    ihDataCriteria Criteria;
    ihUNSIGNED long NumberOfResults; // (Num items in results)
    ihDataResultPtr Results; // (array. One for each matching tag)
} ihDataRecordset;
```

The given prototype is a collection of data samples that you get back from a data read or subscription.

Callback Prototypes/typedefs

```
typedef void (__stdcall *ihInterfaceGetCurrentValueCallbackFunction) (ihServerHandle hServer, void *UserParameter,
ihUNSIGNED long NumberOfSourceAddresses,
ihString *SourceAddresses, ihCallbackId CallbackId);
```

A lot of information can be communicated to your program using callback if you subscribe to changes which is optional. The following sections describe this in more detail.

ihConfiguration Functions

```
extern ihC_DEC ihAPIStatus __stdcall ihConfigurationGetProperties
(ihServerHandle hServer, ihConfigurationProperties *Properties);
extern ihC_DEC void __stdcall ihConfigurationFreeProperties
(ihConfigurationProperties *Properties);
```

You can get information about the Data Archiver in addition to reading and writing data.

ihServer Function

```
extern ihC_DEC ihAPIStatus stdcall ihServerConnect(ihString ServerName, ihString Username, ihString Password,
ihString BufferFileName, ihServerHandle *hServer);
extern ihC_DEC ihAPIStatus stdcall ihServerConnectClient(ihString ServerName, ihString Username, ihString
Password, ihString BufferFileName, ihServerHandle *hServer, ihString ClientName);
extern ihC_DEC ihAPIStatus stdcall ihServerDisconnect(ihServerHandle hServer);
extern ihC_DEC ihBoolean stdcall ihServerIsConnected(ihServerHandle hServer);
```

You need to connect to the server before you start working.

```
extern ihC_DEC ihAPIStatus stdcall ihServerAdd(ihString ServerName, ihString Username, ihString Password,
ihBoolean IsDefault, ihString BufferFileName, ihServerHandle *hServer, ihULONG ConnectionTimeout);
extern ihC_DEC ihAPIStatus stdcall ihServerDelete(ihString ServerName);
extern ihC_DEC ihAPIStatus stdcall ihServerOpenRecordset(ihString ServerNameMask, ihServerRecordset
*ServerRecordset);
extern ihC_DEC void stdcall ihServerCloseRecordset(ihServerRecordset *ServerRecordset);
```

You can set up a collection of servers with their timeouts and usernames. However, you can simply call connect to establish a connection.

ihTag Functions

```
extern ihC_DEC ihAPIStatus stdcall ihTagAdd(ihServerHandle hServer, ihTagFields *hFields, ihTagProperties
*hTag);

extern ihC_DEC ihAPIStatus stdcall ihTagOpenRecordset(ihServerHandle hServer, ihTagFields *RequestedFields,
ihTagCriteria *Criteria, ihTagFields *CriteriaFields, ihTagRecordset *TagRecordset);

extern ihC_DEC ihAPIStatus stdcall ihTagGetProperties(ihServerHandle hServer, ihString Tagname, ihTagFields
*hFields, ihTagProperties *hTag);
```

You can add and browse tags using these functions

ihData Functions

```
extern ihC_DEC ihAPIStatus stdcall ihDataAdd(ihServerHandle hServer, ihUNSIGNED long NumberOfTags, ihString
*TagNames, ihDataProperties *DataValues, ihAPIStatus *ErrorStatuses, ihBoolean WaitForReply, ihBoolean ErrorOnRep
```

You can add and delete data and subscribe to data changes

ihDataStore Functions

```
extern ihC_DEC ihAPIStatus stdcall ihDataStoreOpenRecordset(ihServerHandle hServer, ihString
DataStoreMask, ihDataStoreRecordset *Recordset);
```

You need not configure data stores, the defaults should be fine.

ihComment Functions

```
extern ihC_DEC ihAPIStatus stdcall ihCommentAdd (ihServerHandle hServer, ihString Tagname, ihTimeStruct
*CommentAdd, ihCommentData *ihCommentData, ihString SuppliedUser, ihString SuppliedPassword);
```

You can add comments to data and get them back when you read the data but this is not commonly used.

ihTime Functions

```
extern ihC_DEC void stdcall ihTimeLCLPartsToUTCStruct(int Year, int Month, int Day, int Hour, int Minute,
int MilliSecond, ihTimeStruct *UTCTime);

extern ihC_DEC void stdcall ihTimeUTCStructToLCLParts(int *Year, int *Month, int *Day, int *Hour, int
*Minute, int *Second, int *MilliSecond, ihTimeStruct *UTCTime);
```

The System API has utility functions for working with time zones and daylight saving time.

ihUtil Functions

```
extern ihC_DEC void stdcall ihUtilAnsiToUnicode(char *MBStr, ihChar *WCStr);
extern ihC_DEC void stdcall ihUtilUnicodeToAnsi(char *MBStr, ihChar *WCStr);
```

The System API has utility functions for converting between Unicode and ANSI strings.

System API Programming

System API Programming

To use System API you should be an experienced programmer. The section that follow list general topics that will help you understand the best use of the System API.

Unicode

String tag names, string tag properties such as description, and string data values are all Unicode strings.

Memory

You should never free memory allocated in the API. The API provides many functions to free memory or clear record sets and structures and you should use them as demonstrated in sample programs.

String Length

In the API you will notice that most string fields such as tag names or descriptions are just pointers and this is because they do not have a maximum length. They must be allocated and freed.

Networking between the System API and the Data Archiver

The communication between the `ihapi` DLL and the Data Archiver is TCP/IP networking which sends proprietary packet streams via Winsock calls. The details are not documented.

Multithread Programming

You can have multiple threads reading and writing data, even sharing the same connection.

Multitag Functions

In most cases you can simply act on one tag at a time when reading data or adding tags. These calls are less frequent than writing data. But there are API calls that can handle multiple tags in one round trip and your design should decide if they are needed for performance reasons.

Timestamps

You will see that the timestamp structure is in seconds and subseconds. It is implied that the time zone of the seconds is in GMT+0 Universal Time Coordinated time zone. The System API gives utility functions to convert timestamps to and from local time zones.

Running as a Service

You can develop programs that run as GUI programs, console programs, or services.

Timeouts and Throttles in the System API and the Data Archiver

The Data Archiver will try to protect the system against unintentional large data queries. There are Data Archiver enforced, configurable throttles for queries that return too many samples or take too long to execute. Use the `ihArchiverMaxIntervalRetrievalCount` and `ihArchiverMaxQueryTime` archiver options to increase the limits if you occasionally get the `ihSTATUS_DATA_RETRIEVAL_COUNT_EXCEEDED` error from intentional large queries.

On the System API side there is a configurable timeout set via `ihServerSetTimeout()` and defaults to 90 seconds. Data writes and setting of options must complete within this time period or the API will return an error to the application. The Data Archiver may have queued the work and will still perform the request even if a timeout is returned to the application.

Reads and tag browses can take longer than 90 seconds and this is because the API needs to receive only a partial response every 90 seconds. Large reads and tag browses are streamed back to the API in pieces as the read or browse is still being performed in the Data Archiver. If we do not receive at least one piece every 90 seconds, a timeout error is returned to application but the Data Archiver will continue working until it hits the limit in `ihArchiverMaxQueryTime` archiver option.

System API Functions

System API Connect Functions

This section provides detailed information about each available System API function. Use this information together with the sample programs provided to develop your own applications. The System API functions are grouped as follows:

- [Connect Functions \(on page 1437\)](#)
- [System API Tag Functions \(on page 1443\)](#)
- [Read and Write Functions \(on page 1455\)](#)
- [Archiver Configuration Functions \(on page 1469\)](#)

- [User Defined Type Functions \(on page 1488\)](#)
- [Utility Factors \(on page 1495\)](#)

Not every function and structure in the `ihapi.h` is documented or available for use in user written programs. Please limit your programs to the documented functions or contact the Technical Support team at GE Intelligent Platforms for additional clarifications.

Connect Functions

To perform a connection you need to just use the connect functions. The API will complete the connection and do further necessary reconnects when the Data Archiver is restarted. Your program does not need to manage and monitor connections as it is done by the API.

Connections are subjected to Historian security, which is based on Microsoft Windows Security.

It is expected that user written programs will connect a minimal number of times for staying connected and using that connection for all read and write calls. Connecting and disconnecting rapidly is not efficient. The connect functions are:

ihServerConnect

This function establishes the connection with the Historian server.

```
ihServerConnect(

ihString ServerName, // the computer name or IP address of the Machine running the Data Archiver. You can pass
NULL or the empty string &quot;&rdquo; to attempt connection to a Data Archiver on your local machine.

ihString Username, // The windows username to use when connecting or NULL if you want to connect as the process
owner of your program, typically the logged in user. You would specify a username if the process owner was unable to
connect or did not have sufficient Historian Security permissions.

ihString Password, // if you passed a Username you can pass the password or &rdquo; if there is no password or
otherwise just pass NULL

ihString BufferFileName, // an optional bufferfilename if your program will be using store and forward to
deliver written data

ihServerHandle *hServer // this is an output parameter that will contain the server handle that you would use in
later read and write calls

);
```

Remarks

A server is a computer running a Data Archiver. You can specify a server by including the computer name or IP address.

`ihServerConnect()` will initiate a connection, but you should really use `ihServerIsConnected()` (on page 1439) to determine if the connect actually completed.

If you setup a connection callback function with `ihServerRegisterConnectionCallback()` you will be notified of connection changes. Your security permissions for reads and writes will be established at connect time and are based on the user name and password provided.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the server name or IP address provided cannot be located.
<code>ihSTATUS_LIC_TOO_MANY_USERS</code>	If this connection would exceed your licensed number of connections.
<code>ihSTATUS_NOT_VALID_USER</code>	If the user is not allowed to connect. This can happen whether you provided a username or connected as the process owner. Consult the Historian documentation for security behavior.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihServerDisconnect

Use this function to disconnect from the Historian server.

Prototype

```
ihServerDisconnect {
    ihServerHandle hServer // the handle returned by a previous call to ihServerConnect
};
```

Remarks

You should call `ihServerDisconnect()` function even if the connection attempt returned an error.

Returns

Returns Status	Message
ihSTATUS_OK	On success.

ihServerIsConnected

This function returns whether the Historian server is currently connected or not. It is an indication that if you try to read and write data the call should be successful.

Prototype

```
ihServerIsConnected {
    ihServerHandle hServer // a server handle returned from ihServerConnect
};
```

Returns

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_FAILED	On failure.

ihServerSetTimeout

This function is used to configure the timeout of the server connection.

Prototype

```
TihServerSetTimeout {
    ihServerHandle hServer, // a server handle returned from ihServerConnect
    int Timeout // the timeout, in seconds, to use
};
```

Use this to configure the timeout to a larger or smaller value. If the System API does not receive any response, even a partial response, during the timeout value, a `ihSTATUS_API_TIMEOUT` will be returned from the API call.

Set the timeout any time after connecting and the timeout stays in effect until it is changed or disconnect is issued.

Returns

Returns Status	Message
TRUE	if you are currently successfully connected.
FALSE	if you were never connected or if the connection is currently down and being re-established.

ihServerGetTimeout

This function is used to return the messaging timeout value of the server connection identified by ihServer.

```
ihServerGetTimeout {
    ihServerHandle hServer, ihULONG *timeout
};
```

Remarks

Call `ihServerConnect()` to make a connection, then `ihServerSetTimeout()` to set the timeout if you want a non default value. You can use the `ihServerGetTimeout()` function to determine the timeout value that is being used.

The returned timeout value is in seconds.

Returns

Returns Status	Message
ihSTATUS_OK	On success
ihSTATUS_FAILED	On failure

ihServerGetVersion

This function returns the Historian server version and connection status.

Prototype

```
ihServerGetVersion {
    ihServerHandle hServer, // a serverhandle returned from a previous call to ihServerConnect
    int *Major, // output parameter to contain the major version of the Data Archiver.
    // For example 4 when the Data Archiver version is 4.5.
    int *Minor, // output parameter to contain the minor version of the Data Archiver.
    // For example 5 when the Data Archiver version is 4.5.
```

```
int *Build, // output parameter to contain the build number of the Data Archiver. This is typically not used.
int *Revision // output parameter to contain the revision number of the Data Archiver. This is typically not used

};

You will not receive an immediate callback with the current connection status. You will be notified of the next change
in status
```

Remarks

You will not receive an immediate callback with the current connection status. You will be notified of the next change in status.

Returns

Returns Status	Message
ihSTATUS_OK	On success and the desired information can be read from the output parameters.
ihSTATUS_FAILED	On failure.

ihSecurityGetMembership

This function returns your membership list. Your group memberships determine your security permissions and what calls you can make on this Proficy Historian server connection.

Prototype

```
ihSecurityGetMembership {
    ihServerHandle hServer, // handle from previous call to ihServerConnect
    ihSecurityGrpMembership *Memberships // output parameter to contain the group membership list
};
```

Remarks

You can optionally use this call after a successful connect to determine whether the Data Archiver considers your membership list. You need to be completely connected, not just initiate a connection, before this call can be used. The best way is to use [ihServerIsConnected\(\) \(on page 1439\)](#) after [ihServerConnect\(\) \(on page 1437\)](#) to determine that the connection completed.

Returns

Returns Status	Message
ihSTATUS_OK	On success and the desired information can be read from the output parameter.
ihSTATUS_API_TIMEOUT	If the call could not be completed.
ihSTATUS_NOT_CONNECTED	When not currently connected to the Data Archiver.
ihSTATUS_FAILED	When the other three return options otherwise do not apply.

ihServerOpenRecordset

This function returns the list of Historian servers that exist in the Windows registry.

Prototype

```

ihServerOpenRecordset {
    ihString ServerNameMask, // typically NULL to get all servers but could be a mask

    ihServerRecordset *ServerRecordset // output parameter containing the recordset
};
    
```

Remarks

Use this function to get the list of servers that exist in the Registry. This is a local call and does not need the Data Archiver.

The default server is stored in the Registry and can be used to query instead of hardcoding a server name in your program or prompting the user. The default server is established during product install and can be changed anytime later

Returns

Returns Status	Message
ihSTATUS_OK	On success and the desired information can be read from the output parameter.
ihSTATUS_FAILED	On failure

ihServerCloseRecordset

This function is used to free any memory such as server names that were allocated in the System API.

Prototype

```
void ihServerCloseRecordset {
    ihServerRecordset *ServerRecordset // recordset returned from ihServerOpenRecordset
};
```

Use this function to free any memory such as server names that were allocated in the System API in the `ihServerOpenRecordset()` call.

Returns

void

System API Tag Functions

You need tags to exist in Historian in order to write and read data samples. A read or write call requires a tagname as a parameter. The tag must exist before the data samples are written, the tag is not created automatically.

You can refer to a tag in the following ways:

- A tag has a `tagname`.
- A tag may have aliases which are previously used names left over from tag renames.
- A tag has a `tagid` which is a long number and does not change. If you convert this number to a string you can pass it in place of a `tagname`. If your tagnames are typically longer than 128 characters then using the `tagid` would be shorter.

A tagname can contain any character except the two wild card characters * and ?.

There are many tag properties as listed in the `ihTagProperties` data structures in the `ihapi.h`. All properties are available to your application and are documented in the Historian product documentation. A subset of important properties are given in the following table. This list that applies to tags being written to by user programs. All of the properties related to collectors are not documented in the following table.

ihTagProperties

Property	Type	Description
Tagname	ihString	The tag name that shows in the tag browse.
Description	ihString	The description of the tag that shows in the tag browse.
DataType	ihData- Type	The data type of the tag. This can be a custom type also.
FixedStringLength	Un- signed- Char	Used only if data type is FixedString.
HiEngineeringU- nits	Double	Used only if you are using ArchiveDead- bandPercent.
LoEngineeringU- nits	Double	Used only if you are using ArchiveDead- bandPercent.
ArchiveCompres- sion	ih- Boolean	TRUE if you are using percent or absolute archive.
ArchiveDeadband- PercentRange	Float	It is one way to configure the deadband instead of absolute archive.
InterfaceGeneral1	ihString	Spare string field for application use.
InterfaceGeneral2	ihString	Spare string field for application use.
InterfaceGeneral3	ihString	Spare string field for application use.
InterfaceGeneral4	ihString	Spare string field for application use.
InterfaceGeneral5	ihString	Spare string field for application use.
ReadSecurity- Group	ihString	Only needed if you are using tag level security.
WriteSecurity- Group	ihString	Only needed if you are using tag level security.
AdministratorSe- curityGroup	ihString	Only needed if you are using tag level security.
UTCBias	Long	You can store an offset from GMT+0 here, such as -300. But it is up to the client programs to use it.

Property	Type	Description
ArchiveCompressionTimeout	ihUnsigned-Long	--
ArchiveAbsoluteDeadbanding	ih-Boolean	--
ArchiveAbsoluteDeadband	Double	--
TimeResolution	ihTime-Resolution	If the tag is using seconds, milliseconds or microseconds.
TagId	ihTagId	You can refer to tags by their tagname or their TagId
EnumeratedSetName	ihString	If you want to retrieve using an Enumerated Set. This is optional.
DataStoreName	ihString	Defines what data store the tag belongs to or should be added to during an write function. Blank means default data store.
DefaultQueryModifiers	ihQuery-Modifiers	Query modifier string. This is optional.
UserDefinedTypeName	ihString	If you are using custom data types.
NumberOfElements	ihUnsigned-long	If you are using an array data type.
DataDensity	ihTag-DataDensity	--

Tag Functions

ihTagAdd

Use this function to add a tag to Historian.

Prototype

```
ihTagAdd {
    ihServerHandle hServer, // handle from previous call to ihServerConnect
    ihTagFields *hFields, // the tag fields you are providing in the ihTagProperties
    ihTagProperties *hTag // tag property values such as tagname and data type
};
```

Remarks

There are many tag properties but the minimum set is that you need tagname and data type. Since you do not need to provide all properties, use the ihTagFields to indicate which properties you are providing in the ihTagProperties

Adding a tag that already exists will update that tag to the properties that you provide.

For examples, refer to the Sample Programs included with the SDK.

Returns

Returns	Description
ihSTATUS_OK	On success
ihSTATUS_API_TIMEOUT	If the server name or IP address provided cannot be located.
ihSTATUS_NOT_CONNECTED	If you are not currently connected.
ihSTATUS_ACCESS_DENIED	If you are not allowed to add or modify tags. Possibly you are not a member of the "ih Tag Admins" group.
ihSTATUS_LIC_TOO_MANY_TAGS	If adding this tag would exceed your licensed tag count ihSTATUS_FAILED - for any other type of error.
ihSTATUS_FAILED	For any other type of error.

ihTagMultiAdd

Use this function to add more than one tag in a single call to Proficy Historian.

Prototype

```
ihTagMultiAdd {
    ihServerHandle hServer,
    ihTagFields *hFields,
```

```
ihTagProperties *hTag,
int NumTags
};
```

This function takes an array of tag structures and a count. Typically, you call `ihTagAdd` function to add or modify your tags. For more information on adding a single tag, refer to `ihTagAdd()` function. If you have thousands of tags to add use `ihTagMultiAdd()` function.

Returns

Returns	Description
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the server name or IP address provided cannot be located.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to add or modify tags. Possibly you are not a member of the "ih Tag Admins" group.
<code>ihSTATUS_LIC_TOO_MANY_TAGS</code>	If adding this tag would exceed your licensed tag count.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihTagDelete

Use this function to delete a tag from Historian.

Prototype

```
ihTagDelete {
ihServerHandle hServer, // a server handle returned from ihServerConnect
ihString Tagname, // the tag to delete
ihBoolean DeletePermanent // FALSE if you only want to make the tag not appear in tag browse.
TRUE if you want to delete the tag and its data entirely.
};
```

Remarks

You can delete a tag if it was created by mistake or if you no longer need the data. In most cases, passing DeletePermanent=FALSE is sufficient and hides the tag from future tag lists. Only if you need to re-use the tagname should you pass DeletePermanent=TRUE.

Returns

Returns	Description
ihSTATUS_OK	On success.
ihSTATUS_API_TIMEOUT	If the server name or IP address provided cannot be located.
ihSTATUS_NOT_CONNECTED	If you are not currently connected.
ihSTATUS_ACCESS_DENIED	If you are not allowed to add or modify tags. Possibly you are not a member of the "ih Tag Admins" group.
ihSTATUS_FAILED	For any other type of error.

ihTagRename

Use this function to rename a tag in Historian.

Prototype

```
ihTagRename {
    ihServerHandle hServer, // a server handle returned from ihServerConnect
    ihString Tagname, // the current tagname
    ihString NewTagname, // the new tagname
    ihBoolean TrueRename // TRUE if you want to reject reads to the old tagname and want to make the
    old tagname available for reuse.
};
```

Remarks

You can rename tags to a single, new name or keep the old name available to legacy clients. Only the current name appears in a tag browse. Pass TRUE to permanently rename a tag.

Returns

Returns	Description
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the server name or IP address provided cannot be located.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to add or modify tags. Possibly you are not a member of the "ih Tag Admins" group.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihTagFreeproperties (Tag Properties)

Use this function to correctly free one tag properties structure that was returned from an `ihTagGetProperties()` call.

Prototype

```
void ihTagFreeProperties {
    ihTagFields *hFields, // indicates which fields in the tag properties are valid
    ihTagProperties *hTagProps // structure containing tag properties to be freed.
};
```

Use this function to correctly free one tag properties structure. You do not need to call this to free the tag recordset returned from a browse. Use `ihTagCloseRecordset()` ([on page 1443](#)) instead.

Returns

Returns	Description
Void	Void

ihTagOpenRecordset

This function is used to browse tags that exist in the Data Archiver.

```
ihTagOpenRecordset {
    ihServerHandle hServer, // a server handle returned from ihServerConnect
    ihTagFields *RequestedFields, // indicates which tag properties you want included with the returned tags
    ihTagCriteria *Criteria, // used to determine which tags to return
```

```
ihTagFields *CriteriaFields, // used to indicate which criteria fields should be used
ihTagRecordset *TagRecordset // output parameter that contains the returned tag recordset

};
```

Remarks

This is the function used to browse tags that exist in the Data Archiver. You specify a criteria and which fields of each matching tag you want returned and a recordset of matching tags is returned. Since a tag has many properties it is a waste of resources to return all the tag properties if for example you only want the tagnames.

Using filtering criteria you can perform a simple wildcard search on tagname or description, or you can get all tags of integer data type, or otherwise use any condition on any tag property. The CriteriaFields is where you indicate which tag properties to use in the filter.

The tag recordset will contain a number of tags returned. It is possible that no tags match your criteria. After you are finished using the tag recordset you should free it using `ihTagCloseRecordset()`. Do not free any individual tag string fields.

An example of tag filtering and browsing is provided in SDK sample program.

Returns

Returns	Description
<code>ihSTATUS_OK</code>	On success and the tags are returned in the Tag-Recordset.
<code>ihSTATUS_API_TIMEOUT</code>	The client program did not receive a portion of the tag list before the timeout expired. Large browses are sent back in multiple responses and the SystemAPI must receive at least a partial response before the timeout expires. For example if there is 90 second timeout configured, a browse can take several minutes or as long as at least a part of the response is received every 90 seconds.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.

Returns	Description
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to add or modify tags. Possibly you are not a member of the “ih Tag Admins” group.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihTagCloseRecordset

Use this function to return the recordset returned from an `ihTagOpenRecordset()` call.

Prototype

```
ihTagCloseRecordset {
    ihTagRecordset *TagRecordset
};
```

Remarks

Use this function to return the recordset returned from an `ihTagOpenRecordset()` call.

Returns

Returns	Description
<code>ihSTATUS_OK</code>	Always

ihTagExists

This function checks if a given tag exists in Historian.

```
ihTagExists {
    ihServerHandle hServer, // a server handle returned from ihServerConnect

    ihString Tagname
};
```

Remarks

Use this function to check if a tag exists as it is easier than using `ihTagOpenRecordset()`. Tags that have been deleted are usually hidden and they still exist. `ihTagOpenRecordset()` only returns non-deleted tags.

Returns

Returns	Description
ihSTATUS_OK	If the tag exists.
ihSTATUS_INVALID_PARAMETER	On invalid input parameters.

This function is more convenient than using the `ihTagOpenRecordset()` function when you know the tag-name and want to check for tag existence or get more information about a tag.

If the call succeeds and properties are returned you should call `ihTagFreeProperties()` to free any string properties.

ihTagGetProperties

This function returns the properties of the tags.

```
ihTagGetProperties {
    ihServerHandle hServer, // a server handle returned from ihServerConnect
    ihString Tagname, // the tagname to locate. Wildcards are not allowed.
    ihTagFields *hFields, // the fields you want returned
    ihTagProperties *hTag // an output parameter containing the returned tag properties
};
```

Remarks

This function is more convenient than using the `ihTagOpenRecordset()` function when you know the tag-name and want to check for tag existence or get more information about a tag.

If the call succeeds and properties are returned you should call `ihTagFreeProperties()` to free any string properties.

Returns

Returns	Description
ihSTATUS_OK	If the tag exists.
ihSTATUS_INVALID_PARAMETER	On invalid input parameters.

ihTagFreeProperties

This function used to free the information returned by an `ihTagGetProperties()` call.

Prototype

```
void ihTagFreeProperties {
    ihTagFields *hFields, // the fields you want freed
    ihTagProperties *hTag // contains the tag properties
};
```

Remarks

Use this function to free the information returned by an `ihTagGetProperties()` call.

Returns

Returns	Description
Void	Void

ihTagSetProperties

This function is used to set the tag properties.

Prototype

```
ihTagSetProperties {
    ihServerHandle hServer, // a server handle returned from ihServerConnect
    ihTagFields *hFields,
    ihTagProperties *hTag
};
```

ihTagSubscribe

This function is used to setup a subscription to tag changes.

Prototype

```
ihTagSubscribe {
    ihServerHandle hServer, // a server handle returned from ihServerConnect
    ihString Tagname, // the tagname to monitor for changes. Wildcards are allowed
    ihBoolean Subscribe // TRUE if you want to subscribe or FALSE to unsubscribe
};
```

Remarks

Use this function to setup a subscription to tag changes. A tag change would be a change to a tag property. Data being written to a tag is not a tag change but can be monitored using ihDataSubscribe.

You must register a callback function using ihTagRegisterCallback() and that function will be called on change.

To detect tag additions pass the wildcard * and you will be notified of all changes to all tags. Discard any incoming subscriptions you are not interested in.

An example of tag subscriptions is provided in the SDK sample program.

ihTagRegisterCallback

This function returns which tag properties have changed

```
ihTagRegisterCallback {
    ihServerHandle hServer, // a server handle returned from ihServerConnect
    ihTagCallbackFunction CallbackFunction, // the function to be called
    void *UserParameter
};
```

When your callback function is called there will be an indication of what tag property changed.

ihTagClearAllFields

This function clears the tag properties.

Prototype

```
void ihTagClearAllFields {
    ihTagFields *Fields
};
```

Returns

Returns	Description
Void	Void

Read and Write Functions

Data reading and writing is a key part of Historian functionality. There are many rules and best practices and many use cases that are not all documented here. With the following documentation you will see how to write raw values and read them back as raw values and then how to instruct the Data Archiver to perform calculations on the raw samples and return the result.

The method to pass filter parameters and query modifiers is shown but not the meaning of those parameters. Store and forward buffering is available for data writes but is an advanced topic not demonstrated here.

The Read and Write functions are:

ihDataAdd

Use this function to add data to the Data Archiver:

Prototype

```
ihDataAdd {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect
    ihUNSIGNED long NumberOfTags, // the number of data samples being written
    ihString *TagNames, // the tagname of each sample
    ihDataProperties *DataValues, // the timestamp, value, and quality of each sample
    ihAPIStatus *ErrorStatuses, // output parameter for per data sample errors
    ihBoolean WaitForReply, // TRUE if the call should wait for success or failure from Data Archiver.
    FALSE means that you do not want to do any error checking
    ihBoolean ErrorOnReplace // TRUE if you want an error returned instead of overwriting data
};
```

Remarks

Although the parameter is called NumberOfTags it is really NumberOfSamples. Even if you are writing multiple samples to the same tagname you need to pass the tagname with each data sample. Every data sample you pass needs a tagname in the TagNames parameter and a timestamp, value, and quality in the DataValues parameter.

The application would write data timestamps that are in GMT+0 timezone. The Data Archiver does not do any conversion. If your timestamps are in local time and the data is retrieved in other clients, the timestamps will not be adjusted to your time zone. The System API uses the ihTimeLCLPartsToUTCStructEx () function to help you convert timestamps.

Part of your application design is to bundle multiple data samples into one write. You can send one sample per call to `ihDataAdd` or send 100,000 samples or more. In most cases you can write data periodically to make it available to clients in bundles of 1,000 to 10,000 samples per call to `ihDataAdd`

Part of your application design is to determine what to consider bad or uncertain quality and what sub-quality to use. Your tags may be in a Data Archiver with many other tags from many other sources, these include tags written by collectors or Excel Import. You must be consistent with those tags so that clients need not have special logic for specific tags. For example, collectors use a quality of bad and a subquality of `ihOffline` to indicate that collection has stopped at this time in the real world. Consider including such a data sample and using the same quality and subquality in your program. In this way reports and trends need not know where the data came from.

The data type you write in the `ihDataProperties` does not need to match the data type of the tag in the Data Archiver. The Data Archiver will do the conversion prior to storing the data.

You should typically write with `WaitForReply=TRUE` so that you can check for errors and implement error handling such as retries. If you have no error handling strategy or if you are relying on the store and forward functionality to deliver data you can write with `wait = FALSE`. This is a rare use case. Understand that store and forward functionality only make sure that the data reaches the Data Archiver, not that the data is stored in the Historian archive. There could be security errors or the Archiver may be out of disk space. The most reliable way to write data is to check for errors and even possibly to read back the data that was written.

If you do get a per data sample error that does not mean the whole write failed. Samples that return `ihSTATUS_OK` were written successfully.

If your program only writes data going forward in time, there is no risk of replacing data and you can pass either `TRUE` or `FALSE` for the `ErrorOnReplace` parameter. Otherwise, pass `TRUE` if you do not want accidental data overwrite or `FALSE` to intentionally overwrite existing data.

There are rules about writes having timestamps that are too old or too new and those are not all given here. But, you will receive an error if your write is rejected.

Returns

If you write with `WaitForReply=FALSE` then the return code will be `ihSTATUS_OK`. When using `WaitForReply=FALSE` the return value of the overall function will be `ihSTATUS_OK` on success and non `ihSTATUS_OK` on error which means you should investigate the per data sample error returned in the `ErrorStatuses` output parameter. Those errors include these values:

If you write with WaitForReply=FALSE then the return code will be ihSTATUS_OK. When using WaitForReply=FALSE the return value of the overall function will be ihSTATUS_OK on success and non ihSTATUS_OK on error which means you should investigate the per data sample error returned in the ErrorStatuses output parameter. Those errors include these values:

Returns Status	Message
ihSTATUS_OK	The data sample was successfully written.
ihSTATUS_API_TIMEOUT	If the client program did not receive a return code before the timeout expired. This does not necessarily mean the write was not performed at the archiver, only that the client did not receive a response.
ihSTATUS_NOT_CONNECTED	If you are not currently connected to the Data Archiver.
ihSTATUS_WRITE_IN_FUTURE	If you specified a timestamp that was more than 15 minutes ahead of the Data Archiver PC clock. The Data Archiver will not accept writes that are too far into the future because it has no data file to hold them.
ihSTATUS_DUPLICATE_DATA	If you set ErrorOnReplace to TRUE and you would have overwritten data.
ihSTATUS_WRITE_ARCH_OFFLINE	If you wrote to a time period that has no archive.
ihSTATUS_ARCH_READONLY	If the archive covering the timestamp written is set to read only in Historian Administrator
ihSTATUS_ACCESS_DENIED	<p>If you are not allowed to write data to this tag and timestamp. Under most conditions, writes from user programs are allowed. But if you receive this error consider the following scenarios:</p> <ul style="list-style-type: none"> • Your account is not a member of ihAudited-Writers or ihUnaudited Writers group. • The tag you are writing has tag level security enabled. • The entire archive is set to read only in Historian Administrator.

Returns Status	Message
	The tag you are writing has tag level security enabled. The entire archive is set to read only in Historian Administrator.
<code>ihSTATUS_WRITE_OUTSIDE_ACTIVE</code>	The timestamp on the data sample is older than the "data is read only"
<code>ihSTATUS_INVALID_TAGNAME</code>	The tagname you wrote to does not exist in the Data Archiver configuration.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihDataDelete

This function is used to delete data. By using this function you are not actually deleting the data from the Data Archiver but instead hiding it and marking it as deleted.

Prototype

```
ihDataDelete {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect
    ihUNSIGNED long NumberOfTags, // the number of data samples included in the Tagnames and DataValues parameters
    ihString *Tagnames, // the tagname of the data sample to be deleted
    ihDataProperties *DataValues, // the list of data samples to be deleted
    ihAPIStatus *ErrorStatuses // output parameter containing error codes for individual data samples
};
```

Remarks

Deleting data is not actually done and this function does not clear or reset an entire tag. The reason is that the data is only hidden and not truly deleted. If you write and delete the same time range repeatedly the Historian storage becomes very inefficient.

Use the delete function to delete individual data samples so they are not returned in raw data queries or considered in calculation modes. Delete a small range of data if you have recalculated values and want to discard the previous calculations. You do not need to delete data prior to data overwrite.

The return codes for a delete are much like the ones returned from a write. `ihSTATUS_OK` - the data sample was successfully deleted.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	The data sample was successfully deleted.
<code>ihSTATUS_API_TIMEOUT</code>	If the client program did not receive a return code before the timeout expired. This does not necessarily mean the write was not performed at the archiver, only that the client did not receive a response.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver
<code>ihSTATUS_WRITE_ARCH_OFFLINE</code>	If you wrote to a time period that has no archive.
<code>ihSTATUS_ACCESS_DENIED</code>	<p>If you are not allowed to write data to this tag and timestamp. Under most conditions, writes from user programs are allowed. But if you receive this error consider the following scenarios:</p> <ul style="list-style-type: none"> • The tag you are writing has tag level security enabled. • The entire archive is set to read only in Historian Administrator. <p>The tag you are writing has tag level security enabled. The entire archive is set to read only in Historian Administrator.</p>
<code>ihSTATUS_WRITE_OUTSIDE_ACTIVE</code>	The timestamp on the data sample is older than the "data is read only"
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihDataOpenRecordset

This function is used to read values for one or more tags for a single start and end time, and sampling mode.

Prototype

```

ihDataOpenRecordset {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect
    ihDataFields *Fields, // which fields such as value and quality and comments you want returned
    ihDataCriteria *Criteria, // all of the parameters for the read including the tagname and time range and
    sampling mode
    ihDataRecordset *DataRecordset // output parameter containing the returned data samples or any per tag errors
};
    
```

Remarks

This function is used to read values for a single start and end time and sampling mode. This function is typically used to read a single tagname. However, a wildcard can be passed or multiple individual tagnames can be passed.

The list of sampling and calculation modes, filtering parameters and query modifiers are passed to this function to indicate if you want raw samples returned or you want the Data Archiver to perform some calculation or summarization of the data and return the results. For example you can instruct the Data Archiver to perform hourly averages and return the results instead of returning the samples themselves.

All calculated values are returned as Double Float, regardless of the data type of the tag. Sampling modes such as lab or interpolated will return data in the tag's current data type, even if the data type was changed over a period of time.

The start and end time that you enter are assumed to be in the GMT+0 time zone. If you need to convert local time zone timestamps to UTC use the ihTimeLCLPartsToUTCStructEx() utility function. The returned data will also be in GMT+0 timezone and you can use the ihTimeUTCStructToLCLPartsEx() function to convert to local time in preparation for trending or reporting.

The memory holding the returned data must be freed but do not free each field directly. Simply call the ihDataCloseRecordset() function.

For examples, refer to SDK Sample Programs.

Returns

Returns Status	Message
ihSTATUS_OK	The data sample was successfully read.
ihSTATUS_API_TIMEOUT	The client program did not receive a portion of the returned values before the timeout expired. Large reads are sent back in multiple responses and the

Returns Status	Message
	SystemAPI must receive at least a partial response before the timeout expires. For example if there is 90 second timeout configured, a read can take several minutes or more, as long as at least a part of the response is received every 90 seconds.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver
<code>ihSTATUS_ACCESS_DENIED</code>	<p>If you are not allowed to read data:</p> <ul style="list-style-type: none"> • The tag you are reading has tag level security enabled. • You are not a member of the <code>ihReaders</code> security group. . <p>The tag you are writing has tag level security enabled. The entire archive is set to read only in Historian Administrator.</p>
<code>ihSTATUS_WRITE_OUTSIDE_ACTIVE</code>	The timestamp on the data sample is older than the "data is read only"
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihDataCloseRecordset

This function used to free the data recordset that was allocated inside the System API in a previous read call.

Prototype

```
void ihDataCloseRecordset {
    ihDataRecordset *DataRecordset // the recordset to be freed. This comes from a previous call to
    ihDataOpenRecordset
};
```

Remarks

Use this function to free the data recordset that was allocated inside the System API in a previous read calls.

Returns

Returns Status	Message
VOID	Void

ihDataClearAllFields

This function is used to clear the set of requested data fields.

```
void ihDataClearAllFields {
    ihDataFields *Fields // structure to be cleared
};
```

Remarks

Use this function to clear the set of requested data fields (timestamp,value,quality and so on) in preparation for doing a read. After

clearing, you should set the fields that you want returned.

Returns

Returns Status	Message
VOID	Void

ihDataSubscribe

This function is used to subscribe or unsubscribe the data changes for a tag or tags in the Data Archiver.

Prototype

```
ihDataSubscribe {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect
    ihChar *Tagname, // the tagname or wildcard of tagnames to subscribe
    ihUNSIGNED long MinimumElapsedTime, // the fastest rate in milliseconds that you want data returned or 0 to return
    every data change
    ihBoolean Subscribe // TRUE to setup a subscription or FALSE to stop receiving changes from an existing subscription
};
```

Remarks

Use this function to subscribe or unsubscribe to data changes for a tag or tags in the Data Archiver.

Subscriptions will be delivered within a few seconds of data change and are delivered to you as `DataRecordset` structures through the callback you previously registered with `ihDataRegisterCallback()` callback function. You must register a callback first if you want to receive changes. This `ihDataSubscribe()` function indicates the tags you want to monitor.

You can subscribe to one tag by passing a specific tagname or pass a * or other wildcard to get changes for multiple tags. If you need to monitor multiple individual tag names, then call `ihDataSubscribe()` function once for each tag.

Most applications will pass a 0 for minimum elapsed time indicating they want all data changes. But you can specify a minimum rate. However, you may not be notified of every change. As you are notified, you should receive the data, possibly queuing the data change, and return from the callback.

Subscriptions stay in place even after the connection lost to archiver. However, once you call `ihServerDisconnect()` all subscriptions are cleared. It is not necessary to unsubscribe before calling disconnect but it is suggested.

For Examples, refer Sample Programs section.

Returns Status	Message
<code>ihSTATUS_OK</code>	if the data was successfully read.
<code>ihSTATUS_API_TIMEOUT</code>	if the client program did not receive a portion of the returned values before the timeout expired. Large reads are sent back in multiple responses and the SystemAPI must receive at least a partial response before the timeout expires. For example, if there is 90 second timeout configured, a read can take several minutes or more, as long as at least a part of the response is received every 90 seconds.
<code>ihSTATUS_NOT_CONNECTED</code>	if you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihDataGetCurrentValue

Use this function to get the current values of the one or more tags.

Prototype

```
ihDataGetCurrentValue {
    ihServerHandle hServer,
    ihDataFields *Fields,
    unsigned long NumberOfTags,
    ihChar **Tagnames,
    ihDataProperties *DataValues,
    ihAPIStatus *ErrorStatuses
};
```

Remarks

The ihDataGetCurrentValue function returns timestamp, value, quality, and comments. You can choose to return any of these values using the ihDataFields.

Values are returned based on the tag data type. You should free the returned values using ihDataFreeCurrentValue() function. Do not free the memory in your program.

You can have per tag errors. For example, if the tag does not exist or you are not allowed to read it.

Returns

Returns Status	Message
ihSTATUS_OK	The data sample was successfully read.
ihSTATUS_ACCESS_DENIED	If you are not allowed to add or modify tags, or you are not a member of the ihReaders security group.
ihSTATUS_FAILED	If the tag does not exist.

ihDataFreeCurrentValue

Use this function to free the memory in your program for the current value of the selected tags.

Prototype

```
ihDataFreeCurrentValue {
    ihUNSIGNED long NumberOfRecords,
    ihDataProperties *DataValues
};
```

Remarks

Use this function to free what is returned from `ihDataGetCurrentValue()` function. Do not free the memory any other way.

Returns

Returns Status	Message
<code>VOID</code>	Void

ihDataSubscribe

Use this function to subscribe or unsubscribe to data changes for a tag or tags in the Data Archiver. Subscriptions will be delivered within a few seconds of data change and are delivered to you as `DataRecordset` structures through the callback you previously registered with `ihDataRegisterCallback()` callback function. You must register a callback first if you want to receive changes. This `ihDataSubscribe()` function indicates the tags you want to monitor.

You can subscribe to one tag by passing a specific tagname or pass a * or other wildcard to get changes for multiple tags. If you need to monitor multiple individual tag names, then call `ihDataSubscribe()` function once for each tag.

Most applications will pass a 0 for minimum elapsed time indicating they want all data changes. But you can specify a minimum rate. However, you may not be notified of every change. As you are notified, you should receive the data, possibly queuing the data change, and return from the callback.

Subscriptions stay in place even after the connection lost to archiver. However, once you call `ihServerDisconnect()` all subscriptions are cleared. It is not necessary to unsubscribe before calling disconnect but it is suggested.

For Examples, refer to the Sample Programs section.

Returns Status	Message
<code>ihSTATUS_OK</code>	The data sample was successfully read.
<code>ihSTATUS_API_TIMEOUT</code>	The client program did not receive a portion of the returned values before the timeout expired. Large reads are sent back in multiple responses and the SystemAPI must receive at least a partial response before the timeout expires. For example if there is 90 second timeout configured, a read can take sev-

Returns Status	Message
	eral minutes or more, as long as at least a part of the response is received every 90 seconds.
ihSTATUS_NOT_CONNECTED	If you are not currently connected to the Data Archiver
ihSTATUS_FAILED	For any other type of error.

ihDataOpenMultiRecordset

This function is used if you need to do a single read but use different sampling or calculation modes or different start and end times.

```
ihDataOpenMultiRecordset {
    ihServerHandle hServer,
    ihUNSIGNED long NumberOfRequests,
    ihDataFields *Fields,
    ihDataCriteria *Criteria,
    ihDataRecordset *DataRecordset
};
```

Remarks

This function can be used if you need to do a single read but use different sampling or calculation modes or different start and end times. You do not need to use this function simply to read multiple tags.

After checking the return value of the API call you can check the return value of each included query.

Returns

Returns Status	Message
ihSTATUS_OK	The data sample was successfully read.
ihSTATUS_API_TIMEOUT	The client program did not receive a portion of the returned values before the timeout expired. Large reads are sent back in multiple responses and the SystemAPI must receive at least a partial response before the timeout expires. For example if there is 90 second timeout configured, a read can take sev-

Returns Status	Message
	eral minutes or more, as long as at least a part of the response is received every 90 seconds.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to read data. <ul style="list-style-type: none"> • The tag you are reading has tag level security enabled. • You are not a member of the ihReaders security group
<code>ihSTATUS_DATA_RETRIEVAL_COUNT_EXCEEDED</code>	If the read exceeded the Max Query Time or Max Query Intervals configured in Historian Administrator.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihDataCloseMultiRecordset

This function is used to free the multiple recordsets returned from a `ihDataOpenMultipleRecordset()` call.

Prototype

```
void ihDataCloseMultiRecordset {
    ihUNSIGNED long NumberOfRequests,
    ihDataRecordset *DataRecordsetd
};
```

Remarks

Use this function to properly free the multiple recordsets that were allocated inside the System API in a previous read call.

Returns

Returns Status	Message
VOID	Void

ihArchiver options

ihArchiverFreeOption Function

Prototype

```
ihArchiveFreeOption{
    ihChar *OptionValue // the string returned from ihArchiveGetOption()
};
```

Remarks

Use this function to free the memory inside the structure. Do not free the fields in your code.

Returns

Returns Status	Message
VOID	Void

ihArchiverGetOption

This function retrieves an Archiver option from the data store.

```
ihArchiverGetOption {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect
    ihOptionEx *Option, // the option and data store name
    ihChar **OptionValue // output parameter containing the option value
};
```

This function retrieves an Archiver option from a data store. You can indicate the data store in the ihOptionEx structure. You can pass NULL as the data store name to use the default data store.

You can get an option value to confirm it is set as requested by your application, or you can use this call to verify that a set option call was successful.

ihArchiverSetOption

This function sets an Archiver option from a data store.

ihArchiverGetStatistics

This function is used to get performance statistics from the Data Archiver.

```

ihArchiverGetStatistics(
ihServerHandle hServer,
ihArchiveStatistics *Statistics
);

```

This returns the performance statistics about data writes, failed writes, and disk space usage.

Returns Status	Message
<code>ihSTATUS_OK</code>	If the option was successfully read
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read and you can try again later
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver
<code>ihSTATUS_FAILED</code>	For any other type of error.

Archiver Configuration Functions

You can add and configure tags as part of Data Archiver configuration but there are other options that can be configured.

A subset of all the options and their meanings is given in this section, and the rest are listed in the `ihapi.h` file.

Most options are set as per data store and some are applicable for the overall Data Archiver.

Menu `ihOptions`

Option	Description
<code>ihArchiveDefaultPath</code>	The default path for new archive creations.
<code>ihArchiveActiveHours</code>	Set to a larger number if you need to write data with timestamps in the past older than the "data is read only after" setting in Historian Administrator.
<code>ihArchiveDefaultSize</code>	The default size for new archives, when you are not using <code>ihArchiveDuration</code> for time based archives.
<code>ihArchiveAutomatic-Create,</code>	TRUE if new archives should be created or FALSE if old archives should be reused instead.

Option	Description
<code>ihArchiveAutomaticFreeSpace</code>	The amount of disk space to be left free.
<code>ihArchiveOverwriteOld</code>	TRUE if you should overwrite old archives instead of refusing incoming data.
<code>ihArchiveDefaultBaseFileName</code>	The default base file name which typically matches the computer name but you can update this if you move the Data Archiver to a new computer.
<code>ihArchiveDefaultBaseArchiveName</code>	The default base file name which typically matches the computer name but you can update this if you move the Data Archiver to a new computer.
<code>ihArchiveDefaultBackupPath</code>	The default location for archive backups; typically this location is the same location as the online archives.
<code>ihArchiveCreateOfflineArchive</code>	Set to TRUE if you need to write data with a timestamp before the first archive so that an archive gets created.
<code>ihMessageOnDataUpdate</code>	Set to TRUE if you want an audit trail message for every data sample that is overwritten.
<code>ihArchiverNumReadThreads</code>	Increase from default if you need more read threads so that you can perform parallel reads.
<code>ihSecurityUseLocalGroups</code>	Set to FALSE if you want to use domain security groups.
<code>ihArchiverMaxIntervalRetrievalCount</code>	Increase this number if you typically do large queries that return error <code>ihSTATUS_DATA_RETRIEVAL_COUNT_EXCEEDED</code> .
<code>ihArchiverMaxQueryTime</code>	Increase this number if you typically do large queries that return error <code>ihSTATUS_DATA_RETRIEVAL_COUNT_EXCEEDED</code> .
<code>ihArchiverMaintainAutoRecoveryFiles</code>	Set to FALSE if you do not want to use this feature.
<code>ihArchiverAllowDataOverwrites</code>	Set to FALSE if you don't want to allow accidental or intentional data overwrites.
<code>ihArchiverTargetPrivateBytes</code>	Leave as 0 for system managed unless you have a specific target.
<code>ihArchiverNumWriteThreads</code>	Leave as default value.

Option	Description
<code>ihSecurityStrictClientAuthentication</code>	True to only permit SSPI-based authentication.
<code>ihSecurityStrictCollectorAuthentication</code>	True to only permit collector connections from 5.0 and above.
<code>ihArchiveTotalDuration</code>	Number of Hours that the archives for a DataStore can span (only used for trending DataStores).
<code>ihArchiveDurationType</code>	The type of archive duration. It is the integer value of <code>ihArchiveDurationType</code> .
<code>ihArchiveDuration</code>	Number of Units of time an archive can hold. Defined by <code>ihArchiveDurationType</code> .
<code>StructFieldsInBrowsesByDefault</code>	TRUE if you want each field of a structure to appear as its own tag during tag browse. Useful for legacy clients that are not aware of structures.
<code>ihOptionMax</code>	The highest option number for this version of historian. Use this to check for invalid option values.

Archiver Configuration Functions

ihArchiveOpenRecordset

This function is used to get the list of archives listed in the server.

Prototype

```
ihArchiveOpenRecordset
(
    ihServerHandle hServer,
    ihArchiveCriteria *Criteria,
    ihArchiveRecordset *ArchiveRecordset
);
```

Remarks

Use the criteria if you only want a specific archive or archives from a specific data store. Otherwise you can get all archives and loop through them to see their start and end times and sizes for example.

Call `ihArchiveCloseRecordset()` to free the memory when you are done. Do not free memory in your program.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveCloseRecordset

This function is used to free up the memory associated with the `ArchiveRecordset`.

Prototype

```
ihArchiveCloseRecordset (
    ihArchiveRecordset *ArchiveRecordset
);
```

Remarks

Use this function to free the memory associated with the `ArchiveRecordset` that was returned from `ihArchiveOpenRecordset()`. Do not free the fields in your code.

Returns

Returns Status	Message
<code>Void</code>	<code>Void</code>

ihArchiveGetOption

This function retrieves an Archiver option from the data store. This option controls the behavior of the Data Archiver for writes, security and timeouts.

Prototype

```
ihArchiveGetOption {

ihServerHandle hServer, ihOptionEx *Option, ihChar **OptionValue

};
```

Remarks

This function retrieves an Archiver option from a data store. You can indicate the data store in the `ihOptionEx` structure. You can pass NULL as the data store name to use the default data store. You can get an option value to confirm it is set as requested by your application, or you can use this call to verify that a set option call was successful.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveSetOption

This function sets an Archiver option from a data store

Prototype

```
ihArchiveSetOption {

ihServerHandle hServer, ihOptionEx *Option, ihChar *OptionValue

};
```

Remarks

This function sets an Archiver option from a data store. You can indicate the data store in the `ihOptionEx` structure. You can pass NULL as the data store name to use the default data store.

The list of possible options in *ihapi.h* is listed in the Archiver Configuration Functions. Set an option value when the default does not meet the needs of your application or to confirm that no other application has changed it. Archive option changes are audited in the Historian messages and you can see them using `ihMessageOpenRecordset` call.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiverFreeOption

This function is used to free the memory inside the structure returned from an `ihArchiveGetOption()`.

Prototype

```
ihArchiveFreeOption{
    ihChar *OptionValue // the string returned from ihArchiveGetOption()
};
```

Remarks

Use this function to free the memory inside the structure. Do not free the fields in your code.

Returns

Returns Status	Message
<code>Void</code>	<code>Void</code> .

ihArchiveGetProperties

This function retrieves the properties for an archive in a data store identified by the ArchiveDescriptor.

Prototype

```

ihArchiveGetProperties (
    ihServerHandle hServer,

    ihArchiveDescriptor *ArchiveDescriptor,

    ihArchiveProperties *Archive
);

```

Remarks

You can pass NULL as the data store name to use the default data store.

The `ihArchiveProperties` contains information such as the `StartTime` and `EndTime` and size of the archive.

Make sure to free the archive properties using `ihArchiveFreeProperties()` function.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveSetProperties

This function sets the properties for an archive.

Prototype

```

ihArchiveSetProperties {
    ihServerHandle hServer,

    ihArchiveProperties *Archive
};

```

Remarks

This is the only archive property set by a user program to make the archive read only.

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveFreeProperties

This function is used to free up the memory associated with the ArchiveProperties returned from an `ihArchiveGetProperties` call.

Prototype

```
ihArchiveFreeProperties {
    ihArchiveProperties *ArchiveProperties
};
```

Remarks

Use this function to free the memory. Do not free the memory by calling operating system functions.

Returns

Returns Status	Message
<code>Void</code>	Void.

ihArchiveGetStatistics

This function is used to get performance statistics from the Data Archiver of a particular data store.

Prototype

```
ihArchiveGetStatistics {
    ihServerHandle hServer, ihString DataStoreName, ihArchiveStatistics *Statistics
```

```
);
```

Remarks

This returns the performance statistics about data writes, failed writes, and disk space usage. To get the performance of a particular data store you need pass the data store name.

Returns

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_API_TIMEOUT	If the option could not be read. You can try again later.
ihSTATUS_NOT_CONNECTED	If you are not currently connected to the Data Archiver.
ihSTATUS_FAILED	For any other type of error.

ihArchiveBackupResponse

This function is used by the Alarm Archiver only.

Prototype

```
ihArchiveBackupResponse
(
    ihServerHandle hServer, ihCallbackId CallbackId, ihAPIStatus Status, ihBoolean FinalMessage
);
```

Remarks

None

Returns

None

ihArchiveRemoveResponse

This function is used by the Alarm Archiver only.

Prototype

```
ihArchiveRemoveResponse {
    ihServerHandle hServer, ihCallbackId CallbackId, ihAPIStatus Status, ihBoolean FinalMessage
};
```

Remarks

None

Returns

None

ihConfigurationGetProperties

This function returns the configuration properties such as the Data Archiver version.

Prototype

```
ihConfigurationGetProperties {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

    ihConfigurationProperties *Properties // output parameter to contain the properties
};
```

ihConfigurationFreeProperties

This function is used to free the memory inside the structure.

Prototype

```
void ihConfigurationFreeProperties {
    ihConfigurationProperties *Properties // pointer to the structure filled in by
    ihConfigurationGetProperties
};
```

Remarks

Use this function to free the memory inside the structure. Do not free the fields within your code.

Returns

Returns Status	Message
Void	Void.

Archiver Backup/Restore Functions

You can use Archive Backup/Restore functions to backup archive data.

There are synchronous and asynchronous calls for loading archives, making a backup and removing an archive. The synchronous functions are typically used for smaller archives because the operation completes in a few seconds. The asynchronous functions are typically used for larger archives because the operation can take longer, one minute or more, to complete.

Archive Backup/Restore functions are as follows:

ihArchiveBackup

This function is used to back up archive (.iha) files. If you are storing alarms and events data in Historian, an IHA backup also backs up any alarms.

Prototype

```
ihArchiveBackup {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

    ihArchiveDescriptor *ArchiveDescriptor,

    ihString BackupFileName

};
```

Remarks

This function is used to back up the archive (.iha) files residing on the server specified. The ArchiveDescriptor specifies the archive name that you want to add and the DataStore name to which it should be added. The BackupFileName has the backup of the IHA file with the name and the file location that you specified. For example: `C:\Program Files\Historian Data\Archives\myarchive.iha.`

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	If the option was successfully read.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to perform the operations. For most options you need to be a member of the <code>ihArchiveAdmins</code> group

Returns Status	Message
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveBackupEx

This function is used to back up the archive (.iha) files and process Windows messages at the same time.

Prototype

```
ihArchiveBackupEx {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

    ihArchiveDescriptor *ArchiveDescriptor,

    ihString BackupFileName, long hWnd);
```

Remarks

This function is used to back up the archive (.iha) files residing on the server specified. The ArchiveDescriptor specifies the archive name that you want to add and the DataStore name to which it should be added. The BackupFileName has the backup of the IHA file with the name and the file location that you specified. For example: `C:\Program Files\Historian Data\Archives\myarchive.iha`.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	If the option was successfully read.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to perform the operations. For most options you need to be a member of the <code>ihArchiveAdmins</code> group
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.

Returns Status	Message
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveRegisterBackupCallBack

This function is used to register a callback which should be called after the `ihArchiveBackup()` function completes. Archive backup can take several minutes. By using this callback, your System API program can know that the backup is complete.

Prototype

```
ihArchiveRegisterBackupCallBack {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

    ihArchiveBackupCallbackFunction CallbackFunction,

    void *UserParameter

};
```

Remarks

The register callback will be performed when the Archive backup is completed on Historian.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	If the option was successfully read.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to perform the operations. For most options you need to be a member of the <code>ihArchiveAdmins</code> group
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveRemove

This function is used to delete or unload an archive file. You can unload a file if you no longer need it at the current time but may need it later or in another archive. You can delete a file if you do not expect to need it again or if you have made a backup.

Prototype

```
ihArchiveRemove {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

    ihArchiveDescriptor *ArchiveDescriptor,

    ihBoolean ShouldDeleteFile

}
```

Remarks

This function is used to delete or unload the archive file residing on the server specified. The ArchiveDescriptor specifies the archive name that you want to add and the DataStore name to which it should be added. ShouldDeleteFile determines whether the file should be deleted or not.

The following are the scenarios which you can use with `ihArchiveRemove()` function:

If Should-DeleteFile is:	ZipRegistry enabled	Zip successful	Then...
TRUE	YES	YES	Archive file is deleted.
TRUE	YES	NO	The archive file is not deleted but unloaded.
FALSE	YES	YES	The archive file is not deleted.
FALSE	YES	NO	The archive file is not deleted.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	If the option was successfully read.

Returns Status	Message
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to perform the operations. For most options you need to be a member of the <code>ihArchiveAdmins</code> group
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveRemoveEx

This function is used to delete or unload the archive files and process Windows messages at the same time.

Prototype

```
ihArchiveRemoveEx {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

    ihArchiveDescriptor *ArchiveDescriptor,

    ihBoolean ShouldDeleteFile,

    long hWnd
};
```

Remarks

This function is used to delete or unload the archive file residing on the server specified. The `ArchiveDescriptor` specifies the archive name that you want to add and the DataStore name to which it should be added. `ShouldDeleteFile` determines whether the file should be deleted or not.

The following are the scenarios which you can use with `ihArchiveRemoveEX()` function:

If Should-DeleteFile is:	ZipRegistry enabled	Zip successful	Then...
TRUE	YES	YES	Archive file is deleted.

If Should-DeleteFile is:	ZipRegistry enabled	Zip successful	Then...
TRUE	YES	NO	The archive file is not deleted but unloaded.
FALSE	YES	YES	The archive file is not deleted.
FALSE	YES	NO	The archive file is not deleted.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	If the option was successfully read.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to perform the operations. For most options you need to be a member of the <code>ihArchiveAdmins</code> group
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveRegisterRemoveCallback

This function allows you to register a callback for removing an archive. This callback function is called when you remove the archive from Proficy Historian.

Prototype

```
ihArchiveRegisterRemoveCallback {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

    ihArchiveRemoveCallbackFunction CallbackFunction,

    void *UserParamter
};
```

Remarks

To register a function as a callback, you must have a callback or a function with the same signature as `ihArchiveRemoveCallback` function, and then pass it to `ihArchiveRegisterRemoveCallback`.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	If the option was successfully read.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to perform the operations. For most options you need to be a member of the <code>ihArchiveAdmins</code> group
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihArchiveAdd

This function is used to create a new archive or load an existing one.

Prototype

```
ihArchiveAdd {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

    ihArchiveDescriptor *ArchiveDescriptor,

    ihString FileLocation, ihBoolean ShouldCreateFile,

    ihUNSIGNED long FileSize
};
```

Remarks

This function is used to create or load the archive file residing on the server specified. The `ArchiveDescriptor` specifies the archive name that you want to add and the `DataStore` name to which it should be added. Then, specify the `FileLocation`. To determine whether the file should be created or not with the specified `FileSize`, use `ShouldCreateFile`.

Returns

Returns Status	Message
ihSTATUS_OK	If the option was successfully read.
ihSTATUS_ACCESS_DENIED	If you are not allowed to perform the operations. For most options you need to be a member of the ihArchiveAdmins group
ihSTATUS_API_TIMEOUT	If the option could not be read. You can try again later.
ihSTATUS_NOT_CONNECTED	If you are not currently connected to the Data Archiver.
ihSTATUS_FAILED	For any other type of error.

ihArchiveAddEx

This function is used to create a new archive or load an existing one.

Prototype

```

ihArchiveAddEx {
    ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

    ihArchiveDescriptor *ArchiveDescriptor,

    ihString FileLocation,

    ihBoolean ShouldCreateFile,

    ihUNSIGNED long FileSize,

    long hWnd

};

```

Remarks

This function is used to create or load the archive file residing on the server specified. The ArchiveDescriptor specifies the archive name that you want to add and the DataStore name to which it

should be added. Then, specify the FileLocation. To determine whether the file should be created or not with the specified FileSize, use ShouldCreateFile.

Returns

Returns Status	Message
ihSTATUS_OK	If the option was successfully read.
ihSTATUS_ACCESS_DENIED	If you are not allowed to perform the operations. For most options you need to be a member of the ihArchiveAdmins group
ihSTATUS_API_TIMEOUT	If the option could not be read. You can try again later.
ihSTATUS_NOT_CONNECTED	If you are not currently connected to the Data Archiver.
ihSTATUS_FAILED	For any other type of error.

ihArchiveRegisterLoadCallback

This function allows you to register a callback for adding an archive file. That registered callback is called when you add the archive file in Historian. It can take several minutes to load large archive files, so by using callbacks your System API program can be notified when the archives finish loading.

Prototype

```
ihArchiveRegisterLoadCallback {

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

ihArchiveLoadCallbackFunction CallbackFunction,

void *UserParameter

};
```

Remarks

You need to have a callback or a function with the same signature as ihArchiveLoadCallback function, and then pass it to ihArchiveRegisterLoadCallback to register that function as a callback.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	If the option was successfully read.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to perform the operations. For most options you need to be a member of the <code>ihArchiveAdmins</code> group
<code>ihSTATUS_API_TIMEOUT</code>	If the option could not be read. You can try again later.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected to the Data Archiver.
<code>ihSTATUS_FAILED</code>	For any other type of error.

User Defined Type Functions

User defined data types should be added to the Data Archiver before they can be used in tags. The User defined type functions are as follows:

`ihUserDefinedTypeAdd`

This function is used to add a user defined type.

Prototype

```
ihUserDefinedTypeAdd(

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

ihUserDefinedTypeProperties *UserDefinedType, // structure containing the user defined type

ihString *ErrorMsg // output parameter to contain any error string if there is error. The memory, if there is an error,
will be allocated in the System API and should be freed using ihUserDefinedTypeFreeError

);
```

Remarks

If the set already exists, it is overwritten by this new set. You need to be an *ihTagAdmin* to add or modify a set. The memory, if there is an error, will be allocated in the System API and should be freed using `ihUserDefinedTypeFreeErrorMessage`.

Returns

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_API_TIMEOUT	If the server name or IP address provided cannot be located.
ihSTATUS_NOT_CONNECTED	If you are not currently connected.
ihSTATUS_ACCESS_DENIED	If you are not allowed to add or modify the user defined types, perhaps you are not a member of the <code>ihTagAdmins</code> group.
ihSTATUS_FAILED	For any other type of error.

ihUserDefineTypeDelete

This function is used to delete a user defined type.

Prototype

```

ihUserDefinedTypeDelete(

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

ihString UserDefinedTypeName, // the name of the user defined type. Any characters can be used other than * or ?

ihString *ErrorMsg // output parameter to contain any error string if there is error. The memory, if there is an error,
will be allocated in the System API and should be freed using ihUserDefinedTypeFreeError

);

```

Remarks

You need to be an `ihTagAdmin` to be able to delete a User Defined type. The memory, if there is an error, will be allocated in the System API and should be freed using `ihUserDefinedTypeFreeErrorMessage`.

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_API_TIMEOUT	If the server name or IP address provided cannot be located.
ihSTATUS_NOT_CONNECTED	If you are not currently connected.

Returns Status	Message
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to add or modify the user defined types, perhaps you are not a member of the <code>ihTagAdmins</code> group.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihUserDefinedTypeRename

This function is used to rename the existing user defined type name.

Prototype

```
ihUserDefinedTypeRename(

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

ihString UserDefinedTypeName, // the current name of the user defined type

ihString NewUserDefinedTypeName // the new name

);
```

Remarks

After you rename, the old name is available for reuse.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the server name or IP address provided cannot be located.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to add or modify the user defined types, perhaps you are not a member of the <code>ihTagAdmins</code> group.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihUserDefinedTypeExists

Use this function to check whether the user defined type exists or not.

Prototype

```
ihUserDefinedTypeExists(

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

ihString UserDefinedTypeName // the name to check

);
```

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_API_TIMEOUT	If the server name or IP address provided cannot be located.
ihSTATUS_NOT_CONNECTED	If you are not currently connected.
ihSTATUS_ACCESS_DENIED	If you are not allowed to add or modify the user defined types, perhaps you are not a member of the ihTagAdmins group.
ihSTATUS_FAILED	For any other type of error.

ihUserDefinedTypeSetProperties

This function is used to set the user defined type properties.

Prototype

```
ihUserDefinedTypeSetProperties(

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

ihUserDefinedTypeProperties *UserDefinedType, // the name and properties to set

ihString *ErrorMsg // output parameter to contain any error string if there is error. The memory, if there is a
an error, will be allocated in the System API and should be freed using ihUserDefinedTypeFreeError

);
```

Remarks

You need to be an `ihTagAdmin` to set the properties. The memory, if there is an error, will be allocated in the System API and should be freed using `ihUserDefinedTypeFreeErrorMessage`.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the server name or IP address provided cannot be located.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to add or modify the user defined types, perhaps you are not a member of the <code>ihTagAdmins</code> group.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihUserDefinedTypeGetProperties

This function returns the user defined type properties.

Prototype

```
ihUserDefinedTypeGetProperties(

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

ihString UserDefinedTypeName , // the name of the custom data type

ihUserDefinedTypeProperties *UserDefinedType // output parameter containing the returned properties. The return
);
```

Remarks

You need to be an `ihTagAdmin` to get the properties.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the server name or IP address provided cannot be located.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to add or modify the user defined types, perhaps you are not a member of the <code>ihTagAdmins</code> group.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihUserDefinedTypeFreeProperties

This function is used to free the memory allocated by the `ihUserDefinedTypeGetProperties()` call.

Prototype

```
void ihUserDefinedTypeFreeProperties(

ihUserDefinedTypeProperties *UserDefinedTypeProps // properties as returned from an
ihUserDefinedTypeGetProperties call

);
```

Remarks

You need to call this once to free all memory in the recordset. Do not free the memory in your program.

Returns

Returns Status	Message
Void	Void.

ihUserDefinedTypeOpenRecordset

This function is used to return the list of user defined types.

Prototype

```
ihUserDefinedTypeOpenRecordset (
```

```

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect

ihString Mask, // * or specific set name or some other mask to specify the list

ihUserDefinedTypeRecordset *RecordSet // output parameter to contain the returned list. The list should be
freed with ihUserDefinedTypeFreed when done using the ihUserDefinedTypeCloseRecordset()

);

```

Remarks

You need to specify the user defined type set name to open the recordset. This function call should be freed after the retrieval using `ihUserDefinedTypeCloseRecordset`.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the server name or IP address provided cannot be located.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to add or modify the user defined types, perhaps you are not a member of the <code>ihTagAdmins</code> group.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihUserDefinedTypeCloseRecordset

This function used to free the user defined type recordset that was allocated inside the System API in a previous read call.

Prototype

```

void ihUserDefinedTypeCloseRecordset(

ihUserDefinedTypeRecordset *Recordset // recordset to be freed

);

```

Returns

Returns Status	Message
Void	Void.

ihUserDefinedTypeFreeErrorMessage

This function is used to free the memory from the previous error message call.

Prototype

```
ihUserDefinedTypeFreeErrorMessage(

ihString ErrorMsg // string to be freed as returned from a previous call

);
```

Returns

Returns Status	Message
Void	Void.

Utility Functions

Utility functions help you to make use of the other System API calls such as data read and write and connect. Utility Functions are as follows:

ihTimeLCLPartsToUTCStructEx

This function returns timestamps that can be used in read and write functions.

```
ihTimeLCLPartsToUTCStructEx {

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect or just pass
ihINVALID_HANDLE if not using server time zone

int Year, // the 4 digit year such as 1998 or 2004 in the local time zone

int Month, // the month 1 (January) to 12 (December) in the local time zone

int Day, // the day 1 to 31 in the local time zone

int Hour, // the hour 0 to 23 in the local time zone

int Minute, // the minute 1 to 59 in the local time zone

int Second, // the second 1 to 59 in the local time zone

int MilliSecond, // the millisecond 0 to 999 in the local time zone

ihTimeZones TimeZoneFlag, // client or server or explicit timezone
```

```

int TimeZoneBiasExplicit, // only used if TimeZoneFlag is explicit

int DaylightSavingsTime, // TRUE if you want to use the Daylight Saving Time setting in Control Panel,
FALSE if you want to never use Daylight Saving Time.

ihTimeStruct *Time // the output parameter containing the converted timestamp

);

```

Remarks

Use this function to return timestamps to be used in data read and write functions for start and end time of queries. The function takes a server handle however, you need not be connected to the server unless you specify the TimeZoneFlag as server time zone. If you are just using timestamps in local time zone you can use `ihTimeLCLPartsToUTCStruct()`.

Returns

Returns Status	Message
ihuSTATUS_OK	On success.

ihTimeUTCStructToLCLPartsEx

This function is used to convert the timestamps returned by System API into your local time zone.

```

void ihTimeUTCStructToLCLPartsEx {

ihServerHandle hServer, // server handle returned from previous call to ihServerConnect or just pass
ihINVALID_HANDLE if not using server time zone

int *Year, // output parameter to contain the 4 digit year

int *Month, // output parameter to contain the month 1 to 12

int *Day, // output parameter to contain the day 1 to 31

int *Hour, // output parameter to contain the hour 0 to 23

int *Minute, // output parameter to contain the minute 0 to 59

int *Second, // output parameter to contain the second 0 to 59

int *MilliSecond, // output parameter to contain the milliseconds 0 to 999

ihTimeZones TimeZoneFlag, // client or server or explicit timezone

int TimeZoneBiasExplicit, // only used if TimeZoneFlag is explicit

int DaylightSavingsTime, // TRUE if you want to use the Daylight Saving Time setting in Control Panel,
FALSE if you want to never use Daylight Saving Time.

ihTimeStruct *UTCTime // the timestamp to be converted

);

```

Remarks

Use this function to convert timestamps returned by the System API into your local time zone for display. The function takes a server handle however, you need not be connected to the server unless you specify the TimeZoneFlag as server time zone. If you are just using client time zone you can use

```
ihTimeUTCStructToLCLParts().
```

Returns

Returns Status	Message
Void	Void.

ihTimeCurrentUTCStruct

This function returns the current time stamp as UTC. You can add and subtract seconds from this time to read and write data with timestamps relative to now.

Prototype

```
void ihTimeCurrentUTCStruct {
    ihTimeStruct *UTCTime // output parameter containing the current time
};
```

Remarks

Use this function to get the current time so that you can use it in other System API functions such as the end time of a query or the timestamp of a data write.

Returns

Returns Status	Message
Void	Void.

ihUtilAnsiToUnicode

This function is used to convert Unicode string to ANSI format which can be used by API applications and other programs.

Prototype

```
ihUtilAnsiToUnicode {
    char *MBStr, // the non Unicode string
```

```
ihChar *WCStr // the output buffer to contain the converted Unicode string
);
```

Remarks

Use this function if you want to convert any Unicode string returned by the System API to ANSI format that can be used by other API application and programs.

You must allocate the buffer for the Unicode string. Allocate a large enough buffer as System API does not validate the length.

Returns

Returns Status	Message
Void	Void.

ihUtilUnicodeToAnsi

This function is used to convert ANSI strings to Unicode in order to pass them into System API functions.

Prototype

```
ihUtilUnicodeToAnsi {
char *MBStr,ihChar *WCStr
);
```

Remarks

Use this function to convert ANSI strings to Unicode for passing them into the System API connect or read or write functions and so on.

You must allocate the buffer for the ANSI string. Allocate a large enough buffer as System API does not validate the length.

Returns

Returns Status	Message
Void	Void.

ihUtilErrorDesc

This function returns a string for a numeric error code. The string is not translated into other languages.

```

ihUtilErrorDesc {
    ihStatus ErrorNum, // the error number
    ihString ErrorDesc, // the output parameter to contain the string
    int Len // the length of the output buffer
};

```

Remarks

This utility function returns an English language string for a numeric error code if you don't want to provide your own.

Returns

Returns Status	Message
Void	Void.

Time Functions

ihTimeLCLPartsToUTCStruct

Use this function to convert Local Date/Time Parts to Universal Time Coordinated Structure.

Prototype

```

ihTimeLCLPartsToUTCStruct {
    int Year,
    int Month,
    int Day,
    int Hour,
    int Minute,
    int Second,
    int MilliSecond,
    ihTimeStruct *UTCTime};

```

Remarks

The System API functions that read and write data require timestamps to be in GMT+0 timezone. This function can be used to convert your local timestamps into a format that can be passed into other System API functions such as `ihDataAdd`.

Enter your timestamp in the first 6 parameters and the converted timestamp gets returned in the UTC Time parameter. The time that you enter should be in the timezone of the system that is running your program. If you need additional control of the time zone and Daylight Saving Time parameters then use the `ihTimeLCLPartsToUTCStructEx` function.

Returns

Returns Status	Message
Void	Void.

ihTimeUTCStructToLCLParts

Use this function to convert Universal Time Coordinated (UTC) time zone structure to Local Date/Time parts.

```
ihTimeUTCStructToLCLParts {
    int *Year,
    int *Month,
    int *Day,
    int *Hour,
    int *Minute,
    int *Second,
    int *MilliSecond,
    ihTimeStruct *UTCTime
};
```

Remarks

Enter your timestamp in as the UTCTime parameter and the converted timestamp is returned in the first 6 parameters. For example the samples returned from an `ihDataOpenRecordset` have timestamps that can be converted with this function.

The hours and minutes and seconds will be returned in the timezone of the system running your program. If you need additional control over the time zone or Daylight Saving Time parameters then use the `ihTimeUTCStructToLCLPartsEx` function.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On Success.

Returns Status	Message
ihSTATUS_FAILED	

ihTimeUTCStructToFileTime

Use this function to convert UTC structure to FILETIME.

Prototype

```
ihTimeUTCStructToFileTime {
    ihTimeStruct *UTCTime,
    void *FileTime
};
```

Remarks

Use this function to convert Historian UTC timestamps into a FILETIME that could be passed into other Microsoft Windows functions.

Returns

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_FAILED	For any other type of error.

ihTimeLCLFileTimeToUTCStruct

Use this function to convert FILETIME (LOCAL) to UTC structure.

Prototype

```
ihTimeLCLFileTimeToUTCStruct {
    void *FileTime, ihTimeStruct *UTCTime
};
```

Remarks

If you got a FILETIME from some Microsoft Windows call, use this function to convert it to a format that can be used by other System API functions. The FILETIME is assumed to be in UTC timezone. If the FILETIME is in local time then use the ihTimeLCLFileTimeToUTCStruct function.

Returns

Returns Status	Message
1	On success.
0	Any type of error.

Query Modifiers Functions

ihQueryModifiersAssign

Use this function to clear the previously assigned modifiers and then set new modifiers.

Prototype

```
ihQueryModifiersAssign {
    ihQueryModifiers *Modifiers, int NumModifiers, ...
};
```

Returns

This function would not be called by a user program.

Returns Status	Message
Void	Void.

ihQueryModifiersClear

Use this function to clear the modifiers.

Prototype

```
ihQueryModifiersClear {
    ihQueryModifiers *Modifiers
};
```

Remarks

This function would not be called by a user program.

Returns

Returns Status	Message
Void	Void.

ihQueryModifiersSet

Use this function to add a modifier to a mask of modifiers.

Prototype

```
ihQueryModifiersSet {
    ihQueryModifiers *Modifiers, ihQueryModifier Modifier
};
```

Remarks

Use this function to add a querymodifier to a mask of modifiers that would then be passed into a data read call. The set of available modifiers is available in the `ihQueryModifier` enumeration.

Returns

Returns Status	Message
Void	Void.

ihQueryModifiersIsSet

Use this function to check whether the specified modifier is already present in the modifier mask.

Prototype

```
ihQueryModifiersIsSet {
    ihQueryModifiers *Modifiers, ihQueryModifier Modifier
};
```

Remarks

You can use this function to prepare a query modifier mask which can then be passed to a data read call.

Returns

Returns Status	Message
True	The modifier has already been added to the task.
False	Otherwise.

ihQueryModifierOpenRecordset

Use this function to get a list of possible query modifiers from the destination archiver. Older versions of Historian might support fewer modifiers than the version your program is running on.

Prototype

```
ihQueryModifierOpenRecordset {
    ihServerHandle hServer, ihQueryModifierRecordset *QueryModifierRecordset
};
```

Remarks

You should use this function if your program can be communicating with older Data Archivers to ensure your query modifier is available.

Free the returned recordset using the `ihQueryModifierCloseRecordset` function.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_FAILED</code>	For any other type of error.

ihQueryModifierCloseRecordset

Use this function to free memory returned from `ihQueryModifierOpenRecordset`.

Prototype

```
ihQueryModifierCloseRecordset { ihQueryModifierRecordset *RecSet };
```

Remarks

Use this function and do not call any Microsoft Windows functions to free the memory.

Returns

Returns Status	Message
Void	Void

ihDataCriteriaFromString

Use this function to build a data criteria from the criteria string.

Prototype

```
ihDataCriteriaFromString {
    ihServerHandle hServer, ihDataCriteria *Criteria, ihString CriteriaString
};
```

Remarks

This function would not be called by a user program.

Returns

Returns Status	Message
None	None

DataStore Functions

ihDataStoreAdd

Use this function to create additional data stores if your license allows it.

Prototype

```
ihDataStoreAdd { ihServerHandle hServer,
    ihString DataStoreName,
    ihBoolean IsDefault,
    ihString Description,
    ihDataStorageType StorageType
};
```

Remarks

Some data stores are created automatically when the Data Archiver is started. Use this function if you need to create additional ones. The number of data stores is licensed on your key.

Returns

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_NOT_PERMITTED	If adding the data store would exceed your licensed count.
ihSTATUS_FAILED	For any other type of error.

ihDataStoreDelete

Use this function to delete a data store on the specified Data Archiver.

Prototype

```
ihDataStoreDelete {
    ihServerHandle hServer, ihString DataStoreName
};
```

Remarks

You can only delete a data store if all tags have been removed from it. You cannot delete the System data store.

Returns

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_FAILED	For any other type of error.

ihDataStoreRename

Use this function to rename an existing data store.

Prototype

```
ihDataStoreRename {
    ihServerHandle hServer, ihString DataStoreName, ihString NewDataStoreName
};
```

Remarks

Once the data store is renamed it can only be referred to by its new name.

You must be a member of the ihArchive Admin security group to perform renames.

Returns

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_FAILED	For any other type of error.

ihDataStoreOpenRecordset

Use this function to get the details of the configured data stores on the specified Data Archiver.

Prototype

```
ihDataStoreOpenRecordset {
    ihServerHandle hServer, ihString DataStoreMask, ihDataStoreRecordset *Recordset
};
```

Remarks

You can specify a name mask or just pass NULL or "r;*" to get all data stores.

Free the returned list using the `ihDataStoreCloseRecordset` function.

Returns

Returns Status	Message
ihSTATUS_OK	On success.
ihSTATUS_FAILED	For any other type of error.

ihDataStoreCloseRecordset

Use this function to free the memory in the list returned from `ihDataStoreOpenRecordset`.

Prototype

```
ihDataStoreCloseRecordset {
    ihDataStoreRecordset *Recordset
};
```

Remarks

Use this function to free the memory, do not use Microsoft Windows calls to free the memory.

Returns

Returns Status	Message
Void	Void

ihDataStoreSetProperties

Use this function to set or change properties of an existing data store. You use `ihArchiverSetOption` to set options and use this function to indicate a data store is the default or to set the description.

Prototype

```
ihDataStoreSetProperties {
    ihServerHandle hServer,
    ihString DataStoreName,
    ihBoolean IsDefault,
    ihString Description,
    ihDataStorageType StorageType
};
```

Remarks

Most data store configuration will be done by setting options but this function is available if you need to change the default data store.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_API_TIMEOUT</code>	If the servername or IP address provided cannot be located.
<code>ihSTATUS_NOT_CONNECTED</code>	If you are not currently connected.
<code>ihSTATUS_ACCESS_DENIED</code>	If you are not allowed to add or modify tags. Possibly you are not a member of the "r" ih Tag Admins" group.

Returns Status	Message
<code>ihSTATUS_LIC_TOO_MANY_TAGS</code>	If adding this tag would exceed your licensed tag count.
<code>ihSTATUS_FAILED</code>	For any other type of error.

Security Functions

ihSecurityGroupOpenRecordset

Use this function to get the list of security groups that exist in the operating system where the Data Archiver is running. This can be a different list than where your client program is running.

All security groups would be returned, not just the specific ihSecurity Admins, ihTag Admins, and so on. You must free the returned recordset using the `ihSecurityGroupCloseRecordset` call.

Prototype

```
ihSecurityGroupOpenRecordset {
    ihServerHandle hServer, ihSecurityGroups *Grps
};
```

Remarks

To know the list of security groups while setting up a tag to use tag level security, use this function call to give you the name of any groups that exist at the archiver. And when you assign that name to a tag read security group, then the Data Archiver will check that group when the tag is read. This is why you need the list of groups at the Data Archiver and not at the client PC, because the Data Archiver should be able to access the group and its members.

All security groups would be returned, not just the specific ih Security Admins, ih Tag Admins, and so on.

You must free the returned recordset using the `ihSecurityGroupCloseRecordset` call.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_FAILED</code>	For any other type of error. Other errors on their respective Network or Security failures.

ihSecurityGroupCloseRecordset

Use this function to free the list returned from a `ihSecurityGroupOpenRecordset` call.

Prototype

```
ihSecurityGroupCloseRecordset {
    ihSecurityGroups *Grps
};
```

Remarks

Use this function instead of freeing the memory via operating system calls.

Returns

Returns Status	Message
Void	Void

ihSecurityGetOption

Use this function to get the value of security options from the specified Data Archiver.

Prototype

```
ihSecurityGetOption {
    ihServerHandle hServer, ihOption Option, ihChar **OptionValue
};
```

Remarks

You could get the value of security related options such as `ihSecurityStrictClientAuthentication` or `ihSecurityStrictCollectorAuthentication`.

You need to be a member of ih Readers security group to be able to get options.

Returns

Returns Status	Message
ihSTATUS_OK	On success.

Returns Status	Message
<code>ihSTATUS_FAILED</code>	For any other type of error. Other errors on their respective Network or Security failures.

ihSecurityFreeOption

Use this function to free the memory returned by a previous `ihSecurityGetOption` call.

Prototype

```
ihSecurityFreeOption{
    ihChar *OptionValue
};
```

Remarks

Use this function to free the option value. Do not free the memory using operating system calls.

Returns

Returns Status	Message
Void	Void

ihSecurityGetmemberships

Use this function on an established connection to determine what Proficy Historian security groups that the Data Archiver considers you a member of. This will determine what permissions you have within Historian.

Prototype

```
ihSecurityGetmemberships {
    ihServerHandle hServer, ihSecurityGrpMembership *Memberships
};
```

Remarks

Group memberships are established at connect time. If groups are created or your account is added to groups then you need to disconnect and connect again to get the correct level of permissions.

Returns

Returns Status	Message
<code>ihSTATUS_OK</code>	On success.
<code>ihSTATUS_FAILED</code>	For any other type of error. Other errors on their respective Network or Security failures.

Sample Programs

Sample Programs

Sample programs are provided with the API, demonstrating how to perform common tasks. The following sample programs are supplied with the System API:

- `ihCopyData.cpp` – demonstrates copying all the tags and data from Server1 to Server2 including UserDefinedType tags then subscribes to tag and data changes.
- `ihPlotLike.cpp` - shows how to determine the default server and reading multiple tags in one call.

**Note:**

No guidance is given regarding application conversion from other products or APIs. It is assumed that the reader is familiar with the Historian features and functionality.

Chapter 10. Historian User API

Historian User API Overview

About the Historian User API

The Historian User API provides high-speed read/write access to Historian data and read access to Historian tags. There is no access to archives, alarms, events, or messages.

Use this API to develop applications that read and write data to the Historian server when the Historian SDK and Historian OLE DB do not meet your project requirements for performance or programming language.

You can connect the Historian API to a local Historian server in the same manner as to a remote Historian server by simply providing the name of the server. This name must be the computer name or the IP address of the target Historian server, and the server must have a TCP/IP connectivity. If you use the computer name of the server rather than the IP address, the IP address must be available to the client through DNS, a WINS server, or through the local host table.



Note:

At this time, the Historian User API supports single-byte strings only.

The Historian Client Access API is a .NET Core assembly that interacts with Historian from any .NET Core applications. Since the API uses .NET Core, you can use it on any operating system. The required DLLs are available in the `DotNetCoreCAAPI` folder in the ISO. This folder also contains a sample program, which you can use as a starting point to build an application.



Note:

You can still use the old Client Access API, which is a .NET assembly. You can use this API only on Windows. It is installed when you install Historian Client Tools. By default, the Install Wizard places both the API and Client Access `.dlls` in GAC (Global Assembly Cache). It is recommended that you add Historian Client Access API references from the `INSTALLPATH` directory since global assembly cache is part of the run-time environment.

The applications that call into the User API are limited by the security access granted at the server level.

Prerequisites

You must run the programs you create with the Historian User API on a machine with the following software installed and configured:

- Historian 5.5 or greater
- Historian 5.5 or greater Client Tools

The Historian User API has been tested with Visual Studio .NET 2003, 2005, and 2008.

The Historian User API has no additional hardware requirements.

Historian allows you to develop both 32-bit and 64-bit User API programs.



Note:

To build a 32-bit User API program on a 64-bit operating system, you must rename `ihuapi32.lib` to `ihuapi.lib` and include it in your program.

Connect Functions

Connect Functions Overview

This group of functions provides a means to connect to and disconnect from an Historian server. A minimal number of properties are exposed.

Connect Functions

- [ihuConnect \(on page 1514\)](#)
- [ihuConnectEx \(on page 1516\)](#)
- [ihuDisconnect \(on page 1517\)](#)
- [ihuSetConnectionParameters \(on page 1517\)](#)
- [ihuRestoreDefaultConnectionParameters \(on page 1519\)](#)
- [ihuServerRegisterCallbacks \(on page 1519\)](#)
- [ihuBrowseCollectors \(on page 1520\)](#)

ihuConnect

Use the `ihuConnect` function to connect to a Historian server. The function provides a server handle to be used in subsequent calls.

Prototype

```
ihuConnect {
    in MSO MSO Char * server,
    in MSO MSO Char * username, in MSO MSO Char * password, out long * serverhandle
};
```

Remarks

The inputs to the function are `server`, `username`, and `password`. Each has a default value if `NULL` is passed.

- `server`: If `NULL` is passed, then the connection attempt is to the local machine.
- `username` and `password`: If `NULL` is passed, then the username that owns the process is used. Most of the time this is the same as the user logged into the operating system. However, in the case of a program running as a service, you can specify a username and password that the process should use.

The output of this function is a server handle.

Server handles are valid only during the lifetime of the process. They should not be saved to a file and reused.

You do not need to call `ihuConnectEx` more than one time for a username and password. If the connection to the server was lost and restored, the handle can be used after reconnection. If the server was not available at connect time, a handle is still returned, which you can use as soon as the connection becomes available. Reconnects are performed inside the API. The application should wait and retry reads and writes with the returned server handle. Reads and writes succeed after the underlying connection is re-established.

You should still call `ihuDisconnect` with the returned server handle, even if an error is returned.

A connection to the server consumes a Client Access License (CAL) only if you have not already accessed the server from your current IP address. There is no way to connect without consuming a CAL.

Returns

The `ihuConnect` function returns the following values:

- `ihuSTATUS_OK`
- `ihuSTATUS_FAILED`
- `ihuSTATUS_API_TIMEOUT`

- `ihuSTATUS_NOT_VALID_USER`
- `ihuSTATUS_LIC_TOO_MANY_USERS`

ihuConnectEx

Use the `ihuConnectEx` function to connect to a server with store and forward support.

Prototype

```
ihuErrorCode IHUAPI ihuConnectEx (  
MSO Char * server,  
MSO Char * username,  
MSO Char * password,  
MSO Char * buffername,  
unsigned long MaxMegMemory,  
unsigned long MinMegDiskFree,  
long * serverhandle  
);
```

Remarks

The inputs to this function are:

- `server`: If `NULL` is passed, then the connection attempt is to the local machine.
- `username` and `password`: If `NULL` is passed, then the username that owns the process is used. Most of the time this is the same as the user logged into the operating system. However, in the case of a program running as a service, you can specify a username and password that the process should use.
- `buffername`: The target filename and location to store buffered data. The buffer file name must be unique.
- `MaxMegMemory`: Maximum memory in MB. Buffered data is stored in this memory until it is full and is later stored to disk.
- `MinMegDiskFree`: Minimum free disk space in MB.

The output of this function is a server handle.

Server handles are valid only during the lifetime of the process. They should not be saved to a file and reused.

There is no need to call `ihuConnectEx` more than one time for a username and password. If the connection to the server was lost and restored, the handle can be used after reconnection. If the server was not

available at connect time, a handle is still returned, which you can use as soon as the connection becomes available. Reconnects are performed inside the API. The application should wait and retry reads and writes with the returned server handle. Reads and writes succeed after the underlying connection is re-established.

You should still call `ihuDisconnect` with the returned server handle, even if an error is returned.

A connection to the server consumes a Client Access License (CAL) only if you have not already accessed the server from your current IP address. There is no way to connect without consuming a CAL.

Returns

The `ihuConnectEx` function returns the following values:

- `ihuSTATUS_OK`
- `ihuSTATUS_FAILED`
- `ihuSTATUS_API_TIMEOUT`
- `ihuSTATUS_NOT_VALID_USER`
- `ihuSTATUS_LIC_TOO_MANY_USERS`

ihuDisconnect

Use the `ihuDisconnect` function to release connection resources.

Prototype

```
ihuDisconnect {  
    in long serverhandle  
};
```

Returns

The `ihuDisconnect` function returns the following values:

- `ihuSTATUS_OK`

ihuSetConnectionParameters

Use the `ihuSetConnectionParameters` function to set the socket connection timeout.

Prototype

```
ihuSetConnectionParameters {  
  
in IHU_CONNECTION_PARAMETERS*Params  
  
};
```

Remarks

The input to the function is `IHU_CONNECTION_PARAMETERS` structure to pass in a connection timeout:

```
/* Client-side, global connection parameters */  
  
typedef struct {  
  
int Size; // Structure size in bytes  
  
int TCPConnectionWindow; // Max time to establish a TCP connection with server in seconds (default 5s)  
  
} IHU_CONNECTION_PARAMETERS;
```

The default connection timeout is 5 seconds. There is no maximum value, but it is not recommended to set the value to longer than 60 seconds. If you increase the timeout, server connection attempts take more time to return if the server is unavailable.

Sample Code

If an archiver is too busy to process connections, you can set a longer timeout by using the following code:

```
IHU_CONNECTION_PARAMETERS params;  
  
params.Size = sizeof(IHU_CONNECTION_PARAMETERS);  
  
params.TCPConnectionWindow = 30; // extend window to 30s  
  
ihuSetConnectionParameters(&params);
```



Note:

This code applies only to the connections made from your program. You must make this call each time you run your program.

Returns

The `ihuSetConnectionParameters` function returns the following values:

- `ihuSTATUS_OK`
- `ihuSTATUS_FAILED`

ihuRestoreDefaultConnectionParameters

Use the `ihuRestoreDefaultConnectionParameters` function to reset all connection parameters (for example, the socket connection timeout) to default values.

Prototype

```
ihuRestoreDefaultConnectionParameters {
    void,
};
```

Remarks

The example code resets the connection timeout to 5 seconds.

Returns

`IhuSTATUS_OK`

ihuServerRegisterCallbacks

Use the `ihuServerRegisterCallbacks` function if you want your program to be notified of changes in buffering or connection state. For example, your program can be notified of connection loss or that buffering is full.

Prototype

```
ihuErrorCode IHUAPI ihuServerRegisterCallbacks (
    long hServer,
    void *UserParameter,
    long *RegisterCallbacksStatus,
    void *BufferCallbackFunction,
    void *ConnectionCallbackFunction
);
```

Remarks

The inputs to this function are:

- `hServer`: Server handle from the connection. Callbacks are as per server handle, so you can have callbacks for some connections and not for others, or specific callbacks for different handles.
- `UserParameter`: `NULL` or an integer value that you want passed to you in the callback.
- `RegisterCallbacksStatus`: Callback setup success or failure.

- `BufferCallbackFunction`: Callback function for buffer state changes.
- `ConnectionCallbackFunction`: Callback function for connection state changes.

Returns

`ihuServerRegisterCallbacks` returns the following values:

- `ihuSTATUS_OK`
- `ihuSTATUS_FAILED`

ihuBrowseCollectors

Use the `ihuBrowseCollectors` function to browse collectors that are connected to the archiver.

Prototype

```
ihuErrorCode IHUAPI ihuBrowseCollectors (  
    long hServer,  
    MSO Char *InterfaceNameMask  
    IHU_COLLECTOR **Collectors,  
    int *NumOfCollectors  
);
```

Remarks

The inputs to the function are:

- `hServer`: Server handle for the server to be browsed.
- `*InterfaceNameMask`: Pass * for all interfaces, or the interface name or detailed mask for efficiency.

The outputs of the function are:

- `**Collectors`: Returns a list of interfaces/collectors.
- `*NumOfCollectors`: Returns the number of interfaces found.

Returns

The `ihuBrowseCollectors` function returns the following values:

- `ihuSTATUS_OK`
- `ihuSTATUS_FAILED`

Archiver Functions

Archiver Functions Overview

This group of functions provides a means to read and write a set of archiver properties. A minimum of properties (only those related to reads, writes, and tag browses) are available. See the code comments in the Historian User API header (`ihuapi.h`) for more details.

Archiver Functions

- [ihuGetArchiverProperty \(on page 1523\)](#)
- [ihuSetArchiverProperty \(on page 1521\)](#)

ihuSetArchiverProperty

Use the `ihuSetArchiveProperty` function to change the value of specific Historian server options.

Prototype

```
ihuSetArchiverProperty
(long serverhandle,
MSO Char *ArchiveProperty,
MSO Char *PropertyValue)
```

The following properties are supported:

Table 265. Archiver Properties

Property	Read/Write Access	Values	Description
ARCHIVER_PROP_CREATE_OFFLIN-EARCHIVES	Read/Write	1, 0	When set to 0. (false) writes before the start time of the earliest archive are not enabled. Set to 1 only when you are migrating legacy data, and set the value back to 0 after migration is complete. Leaving this value set to 1 can cause excessive archive creation, especially when data is sent to the archiver out of order.
ARCHIVER_PROP_CON-	Read-Only		A large value that changes when the tag configuration changes. Typically used to cache configuration properties such as a set of tags. You can

Table 265. Archiver Properties (continued)

Property	Read/Write Access	Values	Description
FIGSERIALNUMBER			determine when your cache is out of date by comparing your saved serial number with the current serial number.
ARCHIVER_PROP_ACTIVEHOURS	Read/Write	1-232800 hours (30 years)	The number of hours before the present time that the archive data became read-only. When migrating legacy data, you might need to set a large value.
SECURITY_PROP_STRICT_CLIENTAUTHENTICATION	Read/Write	1, 0	Enables or disables strict client authentication. Set to 1 (true) by default for new Historian installations. When set to 1, only version 4.7 or later clients can access the Historian server.
SECURITY_PROP_STRICT_COLLECTORAUTHENTICATION	Read/Write	1, 0	Enables or disables strict collector authentication. Set to 1 (true) by default for new Historian installations. When set to 1, only version 4.7 or later collectors can access the Historian server.

Returns

The `ihuSetArchiverProperty` returns the following values:

- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_OK`
- `ihuSTATUS_ACCESS_DENIED`

To change this property...	You must be a member of this group...
ARCHIVER_PROP_CREATEOFFLINEARCHIVES	ihArchive Admins or ihSecurity Admins
ARCHIVER_PROP_ACTIVEHOURS	ihArchive Admins

To change this property...	You must be a member of this group...
SECURITY_PROP_STRICTCLIENTAUTHENTICATION	ihArchive Admins
SECURITY_PROP_STRICTCOLLECTORAUTHENTICATION	ihArchive Admins

ihuGetArchiverProperty

Use the `ihuGetArchiverProperty` function to read the value of certain archiver properties.

Prototype

```
ihuGetArchiverProperty {
    in long serverhandle,
    in MSO Char *ArchiveProperty,
    out MSO Char *PropertyValue
};
```

Remarks

To read properties, you must be a member of the ih Readers security group. There is no need for you to be a member of the ih Security Admins or ih Archive Admins groups, unless you want to change property values.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_ACCESS_DENIED`

Tag Functions

Tag Functions Overview

Tag functions provide browse, add, modify, and delete access to the configured tags on a server. You can retrieve the properties for each tag with User API calls. For example, you can retrieve user-defined collection parameters for a tag before collection, or retrieve user-configured display parameters to prepare for plotting.

You can retrieve string and numeric tag properties. Every tag property is classified as string or numeric (double float). For example, Boolean properties are converted to double float and time data type properties are converted to string.

You can add, delete, or modify tags using the User API.

You can browse tags in three different ways. The simplest mode uses `ihuFetchTagCache` to filter by tagname. To filter by additional properties, such as data type or collector name, use `ihuFetchTagCacheEx`. Finally, to browse in multiple browser windows at the same time, for example, to compare the tags on one server with those on another server, use `ihuFetchTagCacheEx2` or `ihuFetchTagCacheEx3`.

Tag Functions

- [ihuCreateTagCacheContext \(on page 1527\)](#)
- [ihuFetchTagCache \(on page 1527\)](#)
- [ihuFetchTagCacheEx \(on page 1528\)](#)
- [ihuFetchTagCacheEx2 \(on page 1528\)](#)
- [ihuFetchTagCacheEx3 \(on page 1529\)](#)
- [ihuGetTagNameCacheIndex \(on page 1530\)](#)
- [ihuGetTagNameCacheIndexEx2 \(on page 1530\)](#)
- [ihuGetNumericTagPropertyByTagname \(on page 1531\)](#)
- [ihuGetNumericTagPropertyByIndex \(on page 1531\)](#)
- [ihuGetNumericTagPropertyByIndexEx2 \(on page 1532\)](#)
- [ihuGetStringTagPropertyByTagname \(on page 1533\)](#)
- [ihuGetStringTagPropertyByTagnameEx2 \(on page 1533\)](#)
- [ihuGetStringTagPropertyByIndex \(on page 1534\)](#)
- [ihuGetStringTagPropertyByIndexEx2 \(on page 1535\)](#)
- [ihuTagAdd \(on page 1535\)](#)
- [ihuTagDelete \(on page 1536\)](#)
- [ihuTagRename \(on page 1537\)](#)
- [ihuTagCacheCriteriaClear \(on page 1539\)](#)
- [ihuTagCacheCriteriaClearEx2 \(on page 1539\)](#)
- [ihuTagCacheCriteriaSetStringProperty \(on page 1540\)](#)
- [ihuTagCacheCriteriaSetStringPropertyEx2 \(on page 1540\)](#)
- [ihuTagCacheCriteriaSetNumericProperty \(on page 1541\)](#)
- [ihuTagCacheCriteriaSetNumericPropertyEx2 \(on page 1541\)](#)
- [ihuTagClearProperties \(on page 1542\)](#)
- [ihuTagSetStringProperty \(on page 1542\)](#)
- [ihuTagSetNumericProperty \(on page 1542\)](#)
- [ihuCloseTagCache \(on page 1542\)](#)
- [ihuCloseTagCacheEx2 \(on page 1543\)](#)

Tag Property Value Types

The following table lists the current set of tag properties that are exposed, and indicates whether they are numeric or string. Use [ihuGetNumericTagPropertyByIndex \(on page 1531\)](#) and [ihuGetNumericTagPropertyByTagname \(on page 1531\)](#) to retrieve numeric properties, and [ihuGetStringTagPropertyByIndex \(on page 1534\)](#) and [ihuGetStringTagPropertyByTagname \(on page 1533\)](#) to retrieve string properties.

Table 266. Tag Property Value Types

Property	Value Type
ihuTagPropTagname	String
ihuTagPropDescription	String
ihuTagPropEngineeringUnits	String
ihuTagPropComment	String
ihuTagPropDataType	Numeric
ihuTagPropFixedStringLength	Numeric
ihuTagPropInterfaceName	String
ihuTagPropSourceAddress	String
ihuTagPropCollectionType	Numeric
ihuTagPropCollectionInterval	Numeric
ihuTagPropCollectionOffset	Numeric
ihuTagPropLoadBalancing	Numeric
ihuTagPropTime stampType	Numeric
ihuTagPropHighEngineeringUnits	Numeric
ihuTagPropLowEngineeringUnits	Numeric
ihuTagPropInputScaling	Numeric
ihuTagPropHighScale	Numeric
ihuTagPropLowScale	Numeric
ihuTagPropCollectorCompression	Numeric
ihuTagPropCollectorDeadbandPercentRange	Numeric

Table 266. Tag Property Value Types (continued)

Property	Value Type
ihuTagPropArchiveCompression	Numeric
ihuTagPropArchiveDeadbandPercentRange	Numeric
ihuTagPropSpare1	String
ihuTagPropSpare2	String
ihuTagPropSpare3	String
ihuTagPropSpare4	String
ihuTagPropSpare5	String
ihuTagPropReadSecurityGroup	String
ihuTagPropWriteSecurityGroup	String
ihuTagPropAdministratorSecurityGroup	String
ihuTagPropLastModified (not currently implemented)	String
ihuTagPropLastModifiedUser	String
ihuTagPropInterfaceType	Numeric
ihuTagPropStoreMilliseconds	Numeric
ihuTagPropUTCBias	Numeric
ihuTagPropNumberOfCalculationDependencies	Numeric
ihuTagPropCalculationDependencies (only the first dependency is returned)	String
ihuTagPropAverageCollectionTime	Numeric
ihuTagPropCollectionDisabled	Numeric
ihuTagPropArchiveCompressionTimeout	Numeric
ihuTagPropCollectorCompressionTimeout	Numeric
ihuTagPropDataDensity	Numeric

Table 266. Tag Property Value Types (continued)

Property	Value Type
 Note: Tag data density categories are minimum (1), medium (4), and maximum (7).	
<code>ihuTagPropNumberOfElements</code>  Note: If the <code>NumberOfElements</code> value is -1, the tag is an array tag.	Numeric

ihuCreateTagCacheContext

Use the `ihuCreateTagCacheContext` function to create tag cache context to use in the `ihuFetchTagCacheEx2` or `ihuFetchTagCacheEx3` functions.

Prototype

```
void * IHUAPI ihuCreateTagCacheContext {
};
```

ihuFetchTagCache

Use this function to fetch a current set of tags and properties from the Historian server and place them into an API cache for subsequent queries, such as [ihuGetNumericTagPropertyByTagname \(on page 1531\)](#).

Prototype

```
ihuFetchTagCache {
    in long serverhandle,
    in MSO Char * tagmask,
    out int * NumTagsFound
};
```

Remarks

The function retrieves properties for each tag received.

There is a single API tag cache. You must free the previous tag cache before you do another fetch from the same or a different server. Keep this in mind when you access the tag cache from multiple threads in the same application. Alternatively, use the `ihuCreateTagCacheContext` and `ihuFetchTagCacheEx2` or `ihuFetchTagCacheEx3` functions.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`

ihuFetchTagCacheEx

Use the `ihuFetchTagCacheEx` function to fetch a current set of tags and properties from the Historian server and place them into an API cache for subsequent queries, such as `ihuGetNumericTagPropertyByTagname`.

Prototype

```
ihuFetchTagCacheEx {  
    in long serverhandle,  
    out int * NumTagsFound,  
};
```

Remarks

This function uses the criteria set up by `ihuTagCacheCriteriaSetStringProperty` and `ihuTagCacheCriteriaSetNumericProperty` for tag browsing.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`

ihuFetchTagCacheEx2

Use the `ihuFetchTagCacheEx2` function to fetch a current set of tags and properties from the Historian server and place them into an API cache for subsequent queries.

Prototype

```
ihuFetchTagCacheEx2 {
    void * tagCacheContext,
    long serverhandle,
    MSO Char * tagmask,
    int * NumTagsFound
};
```

Remarks

This function uses the criteria specified in `ihuTagCacheCriteriaSetStringProperty` and `ihuTagCacheCriteriaSetNumericProperty` for tag browsing.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`

ihuFetchTagCacheEx3

Use the `ihuFetchTagCacheEx3` function to fetch a current set of tags and properties from the Historian server and place them into an API cache for subsequent queries.

Prototype

```
ihuFetchTagCacheEx3 {
    void * tagCacheContext,
    long serverhandle,
    int * NumTagsFound
};
```

Remarks

This function uses the criteria specified in `ihuTagCacheCriteriaSetStringProperty` and `ihuTagCacheCriteriaSetNumericProperty` for tag browsing.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`

ihuGetTagNameCacheIndex

Use the `ihuGetTagNameCacheIndex` function to find the index of the specified tagname in the cache. You can use the index for fast access in subsequent get property by index calls. This call only queries the API tag cache. It does not access the archiver.

Prototype

```
ihuGetTagNameCacheIndex {  
    in MSO Char *Tagname  
    out unsigned int *CacheIndex  
};
```

Remarks

The value returned in `CacheIndex` is a zero-based index suitable to be passed into the get property by index functions. The index is valid only if the function returns a success error code.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_TAGNAME`

ihuGetTagNameCacheIndexEx2

Use the `ihuGetTagNameCacheIndexEx2` function to find the index of the specified tagname in the cache. You can use the index for fast access in subsequent get property by index calls. This call only queries the API tag cache. It does not access the archiver.

Prototype

```
ihuGetTagNameCacheIndexEx2 {  
    Void *TagCacheContext,  
    MSO Char *Tagname  
    unsigned int *CacheIndex  
};
```

Remarks

The value returned in `CacheIndex` is a zero-based index suitable to be passed into the get property by index functions. The index is valid only if the function returns a success error code.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_TAGNAME`

ihuGetNumericTagPropertyByTagname

Use the `ihuGetNumericTagPropertyByTagname` function to retrieve the value of a specified numeric tag property from the API tag cache for a specified tag. This call queries the cache, but not the archiver. The tag property may have changed since the cache was fetched.

Prototype

```
ihuGetNumericTagPropertyByTagname {
    in MSO Char *Tagname,
    in ihuTagProperties TagProperty,
    out double *Value
};
```

Remarks

The get by tagname function is slower than the get by index function because it loops through all tags in the cache to find the requested tag. To retrieve multiple properties for a tag, consider calling `ihuGetTagnameCacheIndex` to get the cache index of a tag so that you can use the get by index functions.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuGetNumericTagPropertyByIndex

Use the `ihuGetNumericTagPropertyByIndex` function to retrieve the value of a specified numeric tag property from the API tag cache at a specified cache index. This call queries the cache, but not the archiver. The tag property may have changed since the cache was fetched.

Prototype

```
ihuGetNumericTagPropertyByIndex {
    in int Index,
    in ihuTagProperties TagProperty,
```

```
    out double *Value
};
```

Remarks

Use the get property by index functions after you locate tags with `ihuGetTagnameCacheIndex`, or when you want to iterate through all tags in the cache.

The index is zero-based.

Tags are returned from the cache in no particular order.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuGetNumericTagPropertyByIndexEx2

Use the `ihuGetNumericTagPropertyByIndexEx2` function to retrieve the value of a specified numeric tag property from the API tag cache at a specified cache index. This call queries the cache, but not the archiver. The tag property may have changed since the cache was fetched.

Prototype

```
ihuGetNumericTagPropertyByIndexEx2 {
    void * TagCacheContext,
    int Index,
    ihuTagProperties TagProperty,
    double *Value
};
```

Remarks

Use the get property by index functions when you do not know the tagname.

The index is zero-based.

Tags are returned from the cache in no particular order.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuGetStringTagPropertyByTagName

Use the `ihuGetStringTagPropertyByTagName` function to retrieve the value of a specified string tag property from the API tag cache for a specified tag. This call queries the cache, but not the archiver. The tag property may have changed since the cache was fetched.

Prototype

```
ihuGetStringTagPropertyByTagName {
    in MSO Char *TagName,
    in ihuTagProperties TagProperty,
    in int valuelength,
    out MSO Char *Value
};
```

Remarks

The get by tagname function is slower than the get by index function because it loops through all tags in the cache to find the requested tag. To retrieve multiple properties for a tag, consider calling `ihuGetTagNameCacheIndex` to get the cache index of a tag so that you can use the get by index functions.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuGetStringTagPropertyByTagNameEx2

Use the `ihuGetStringTagPropertyByTagNameEx2` function to retrieve the value of a specified string tag property from the API tag cache for a specified tag. This call queries the cache, but not the archiver. The tag property may have changed since the cache was fetched.

Prototype

```
ihuGetStringTagPropertyByTagnameEx2 {
    void * TagCacheContext, MSO
    Char * Tagname,
    ihuTagProperties TagProperty,
    MSO Char * Value,
    int valuelength,
};
```

Remarks

The get by tagname function is slower than the get by index function because it loops through all tags in the cache to find the requested tag. To retrieve multiple properties for a tag, consider calling `ihuGetTagnameCacheIndex` to get the cache index of a tag so that you can use the get by index functions.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuGetStringTagPropertyByIndex

Use the `ihuGetStringTagPropertyByIndex` function to retrieve the value of a specified string tag property from the API tag cache at a specified cache index. This call queries the cache, but not the archiver. The tag property may have changed since the cache was fetched.

Prototype

```
ihuGetStringTagPropertyByIndex {
    in int Index,
    in ihuTagProperties TagProperty,
    out MSO Char *Value,
    in int valuelength,
};
```

Remarks

Use the get property by index functions after you locate tags with `ihuGetTagnameCacheIndex`, or when you want to iterate through all tags in the cache.

The index is zero-based.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuGetStringTagPropertyByIndexEx2

Use the `ihuGetStringTagPropertyByIndexEx2` function to retrieve the value of a specified string tag property from the API tag cache at a specified cache index. This call queries the cache, but not the archiver. The tag property may have changed since the cache was fetched.

Prototype

```
ihuGetStringTagPropertyByIndexEx2 {
void * TagCacheContext,
int Index,
ihuTagProperties TagProperty,
MSO Char * Value,
int valueLength,
};
```

Remarks

Use the get property by index functions when you do not know the tag name, or when you want to iterate through all tags in the cache.

The index is zero-based.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuTagAdd

Use the `ihuTagAdd` function to add or modify tags.

Prototype

```
ihuTagAdd {  
    in long serverhandle,  
};
```

Remarks

This function uses `serverhandle` as a parameter.

Tag names that contain question marks (?) or asterisks (*) are not added to the server.

To modify a tag, you must add it again with new properties. Whenever you change or copy a tag name, the old and new tag names and time stamps are recorded in the audit trail.

Returns

- `ihuSTATUS_OK`: Success
- `ihuSTATUS_INVALID_PARAMETER`: Invalid input parameters
- `ihuSTATUS_LIC_TOO_MANY_TAGS`: Added tags exceed the licensed tag count
- `ihuSTATUS_ACCESS_DENIED`: You do not have rights to add tags

ihuTagDelete

Use the `ihuTagDelete` function to delete tags from the server.

Prototype

```
ihuTagDelete {  
    in long serverhandle,  
    in MSO Char * tagname,  
};
```

Remarks

This function uses `serverhandle` and `tagname` as parameters.

Returns

- `ihuSTATUS_OK`: Success
- `ihuSTATUS_INVALID_PARAMETER`: Invalid input parameters
- `ihuSTATUS_ACCESS_DENIED`: You do not have rights to delete tags

ihuTagDeleteEx

You can use the `ihuTagDeleteEx` function to permanently delete a tag by passing `TRUE` as a parameter.

Prototype

```
ihuTagDeleteEx {  
    in long serverhandle,  
    in MSO Char * tagname,  
    BOOL DeletePermanent  
};
```

Remarks

Use `DeletePermanent` to create a new tag with a previously used name. The `ihuTagDeleteEx` function uses the following parameters:

- `serverhandle`: The Historian server from which to fetch tags
- `tagname`: Name of the tag to be deleted, which must be returned in a tag browse
- `DeletePermanent`: Permanently deletes a tag when set to `TRUE`



Note:

After you permanently delete a tag, you can no longer query its data, and the tag name is available for reuse.

Returns

- `ihuSTATUS_OK`: Success
- `ihuSTATUS_INVALID_PARAMETER`: Invalid input parameters
- `ihuSTATUS_ACCESS_DENIED`: You do not have rights to delete tags



Note:

You must be a member of the ihTag Admin security group to delete tags.

ihuTagRename

Use the `ihuTagRename` function to rename tags.

Prototype

```
ihuTagRename {  
    in long serverhandle,  
    in MSO Char * OldTagName,  
    in MSO Char * NewTagName,  
};
```

Remarks

This function uses the following parameters:

- `serverhandle`: The Historian 4.0 server from which to fetch tags
- `OldTagname`: Name of the tag to be renamed
- `NewTagname`: New tag name



Note:

When you use this function to update or modify tag names, the tag properties are not modified. If you modify a renamed tag property, be aware that all the tag properties for the alias are also updated.

Returns

- `ihuSTATUS_OK`: Success
- `ihuSTATUS_INVALID_PARAMETER`: Invalid input parameters
- `ihuSTATUS_ACCESS_DENIED`: You do not have rights to rename tags

ihuTagRenameEx

You can use the `ihuTagRenameEx` function to permanently rename a tag by passing `TRUE` as a parameter.

Prototype

```
ihuTagRenameEx {  
    in long serverhandle,  
    in MSO Char * OldTagName,  
    in MSO Char * NewTagName,  
    BOOL TrueRename,  
};
```

Remarks

You can permanently rename tags that you do not want to read and write with their previous names. This function uses the following parameters:

- `serverhandle`: The Historian 4.0 server from which to fetch tags
- `OldTagname`: Name of the tag to be renamed
- `NewTagname`: New tag name
- `TrueRename`: Permanently renames a tag when set to `TRUE`.

Returns

- `ihuSTATUS_OK`: Success
- `ihuSTATUS_INVALID_PARAMETER`: Invalid input parameters
- `ihuSTATUS_ACCESS_DENIED`: You do not have rights to rename tags



Note:

You must be a member of the ihTag Admin security group to rename tags.

ihuTagCacheCriteriaClear

Use the `ihuTagCacheCriteriaClear` function to clear any cached criteria before you set up tag browse criteria.

Prototype

```
void IHUAPI ihuTagCacheCriteriaClear();
};
```

ihuTagCacheCriteriaClearEx2

Use the `ihuTagCacheCriteriaClear` function to clear any cached criteria before you set up tag browse criteria.

Prototype

```
void IHUAPI ihuTagCacheCriteriaClearEx2
(
void * TagCacheContext,
};
```

ihuTagCacheCriteriaSetStringProperty

Use the `ihuTagCacheCriteriaSetStringProperty` function to set up tag browse criteria before you call `ihuFetchTagCacheEx`.

Prototype

```
ihuTagCacheCriteriaSetStringProperty {  
    in ihuTagProperties TagProperty,  
    in MSO Char *Value,  
};
```

Remarks

This function fetches a current set of tags and properties from the Historian server and places them into an API cache for subsequent queries, such as `ihuGetNumericTagPropertyByTagName`.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuTagCacheCriteriaSetStringPropertyEx2

Use the `ihuTagCacheCriteriaSetStringPropertyEx2` function to set up tag browse criteria before you call `ihuFetchTagCacheEx`.

Prototype

```
ihuTagCacheCriteriaSetStringPropertyEx2 {  
    void * TagCacheContext,  
    ihuTagProperties TagProperty,  
    MSO Char *Value,  
};
```

Remarks

This function fetches a current set of tags and properties from the Historian server and places them into an API cache for subsequent queries, such as `ihuGetNumericTagPropertyByTagName`.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuTagCacheCriteriaSetNumericProperty

Use the `ihuTagCacheCriteriaSetNumericProperty` function to set up tag browse criteria.

Prototype

```
ihuTagCacheCriteriaSetNumericProperty {
    in ihuTagProperties TagProperty,
    in double Value,
};
```

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuTagCacheCriteriaSetNumericPropertyEx2

Use the `ihuTagCacheCriteriaSetNumericPropertyEx2` function to set up tag browse criteria.

Prototype

```
ihuTagCacheCriteriaSetNumericPropertyEx2 {
    void * TagCacheContext,
    ihuTagProperties TagProperty,
    double Value,
};
```

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_INVALID_TAGNAME`

ihuTagClearProperties

Use the `ihuTagClearProperties` function to clear tag properties before you add tags to a server.

Prototype

```
void IHUAPI ihuTagClearProperties()  
};
```

ihuTagSetStringProperty

Use the `ihuTagSetStringProperty` function to set string tag properties before you call `ihuTagAdd`.

Prototype

```
ihuTagSetStringProperty {  
    in ihuTagProperties TagProperty,  
    in MSO Char *Value,  
};
```

Returns

- `ihuSTATUS_OK`

ihuTagSetNumericProperty

Use the `ihuTagSetNumericProperty` function to set numeric tag properties before you call `ihuTagAdd`.

Prototype

```
ihuTagSetNumericProperty {  
    in ihuTagProperties TagProperty,  
    in double.Value,  
};
```

Returns

- `ihuSTATUS_OK`

ihuCloseTagCache

Use the `ihuCloseTagCache` function to free the API cache from memory. Be sure to close the tag cache when not in use to free memory and prevent accidental usage.

Prototype

```
ihuCloseTagCache {
};
```

Returns

- `ihuSTATUS_OK` in all cases

ihuCloseTagCacheEx2

Use the `ihuCloseTagCacheEx2` function to free the API cache from memory. Be sure to close the tag cache when not in use to free memory and prevent accidental usage.

Prototype

```
ihuCloseTagCache {
void * TagCacheContext
};
```

Returns

- `ihuSTATUS_OK` in all cases

Write Functions

Write Functions Overview

The write functions are designed for high-performance data write access to the archiver. Groups of data samples are built up in the application and then sent as a whole into the API for transmission to the server. Write errors can be returned to the application, which can then implement its own error handling. Or, the program can write without a wait if there is no error handling.

The application is responsible for all error handling, including retrying failed writes.

Write Functions

- [ihuWriteData \(on page 1543\)](#)
- [ihuWriteComment \(on page 1546\)](#)

ihuWriteData

Use the high-performance `ihuWriteData` function to write multiple samples for multiple tags.

Prototype

```
ihuWriteData {
    in long serverhandle,
    in int number_of_samples,
    in IHU_DATA_SAMPLE *data_values,
    in ihuErrorCode *error_returns ,
    in bool wait_for_reply,
    in bool error_on_replace
};
```



Important:

You cannot write more than 100,000 samples in each call to this function. It is recommended that you write 1,000 to 10,000 samples per call.

Remarks

The Historian archiver has the following strict data-write rules that apply to all applications and collectors:

1. No application is allowed to write data with a time stamp older than now minus the "Data is read only after" active hours setting. Such writes fail.
2. No application is allowed to write data with a time stamp before the start time of the first archive, even if the write satisfies the previous rule.
3. No application can write data to a read-only archive.
4. No application can write data with a time stamp more than 15 minutes in the future.

The write function has two Boolean parameters to control optional behavior:

- `wait_for_reply`: When set to `TRUE`, write operations are blocked until the values are acknowledged by the archiver. This allows you to check the error returns to reach a degree of confidence that the data was written successfully. You cannot check error codes unless you wait for the reply.

If it is important to return control to your program so that collection can be performed, consider setting `wait_for_reply=FALSE`. You might also want to set `wait_for_reply=FALSE` if you have no specific error-handling strategy, or if you are using data readbacks to verify write success.

If you are using store and forward in the User API, set `wait_for_reply=FALSE`.

**Note:**

If you set `wait_for_reply=FALSE`, you must pass a `NULL` error array for the `ihuErrorCode` *error_returns value.

- `error_on_replace`: This parameter has no effect on performance. Use it to specify how the archiver behaves when an existing archived sample has the same time stamp as a new sample being written. Set `error_on_replace=TRUE` to discard the new sample and return an error that you can see when `wait_for_reply=TRUE`. Set `error_on_replace=FALSE` to overwrite the existing sample with the new sample.

Time Stamps

You can use this function to specify a time stamp or pass a time stamp of 0 seconds to use the current system time on the written sample. Pass a time stamp structure where `seconds=0`, and do not pass `NULL`. All samples in the group with a 0 time stamp specified use the system time at the time of the write as a time stamp. Values are in microseconds.

Values

Values to be written are not required to have matching data types as the Historian tags. The archiver converts written data types to tag data types if needed.

Qualities

You are required to specify the data quality and subquality for the sample when you use this function. There are no default values.

**Note:**

Although the `IHU_DATA_SAMPLE` function has a field for comments, you cannot call it to write a comment. Use the [ihuWriteComment \(on page 1546\)](#) function instead.

Error Handling

The User API does not provide store and forward or retry functionality for failed writes. That is the responsibility of the application. You can write User API programs that perform retries or use store and forward.

If you get a timeout back from a write, the write may be waiting in a write queue on the data archiver.

Security

Historian has audited and unaudited write security groups and a security administration group.

To perform writes, you must be a member of one of these groups. Otherwise, you get an

`ihuSTATUS_ACCESS_DENIED` error.

Returns

This function returns `ihuSTATUS_OK` when values are successfully written.

Errors are returned on timeouts, when you are not a member of the necessary security group, or when tags are not found.



Important:

The User API passes through any timestamps it is given without adjusting for time offsets. The application is responsible to account for time differences between clients and archivers running on different machines.

ihuWriteComment

Use the `ihuWriteComment` function to write a single comment to a single data sample.

Prototype

```
ihuWriteComment {  
  
    in long serverhandle,  
  
    in MSO Char *Tagname,  
  
    in IHU_timestamp *time stamp,  
  
    in MSO Char *Comment,  
  
    in MSO Char *SuppliedUser,  
  
    in MSO Char *SuppliedPassword  
  
};
```

Remarks

Comments can be written with any time stamp that is valid for a data write. See [ihuWriteDatafunction \(on page 1543\)](#) for details on valid time stamps. If there is an existing raw sample for the specified tag and time stamp, the comment is attached with no loss of data values stored with that sample. Otherwise, a new raw sample with no value is created to hold the comment.

If a time stamp with 0 seconds is passed in, the current time is used.

Currently, comments written with the User API must be string text.

The `SuppliedUser` and `SuppliedPassword` parameters are optional and can be `NULL`. If set, values must be a valid username and password with write permissions, or the comment write fails.

Returns

- `ihuSTATUS_OK` on success, error otherwise.

Query Modifiers Functions

Query Modifiers Functions Overview

You can use query modifier functions to specify various ways to retrieve data from Historian. For example, you can use `ONLYGOOD` to request only good-quality data, or `INCLUDEREPLACED` to retrieve replaced values.

Query Modifier Functions

- [ihuBrowseQueryModifiers \(on page 1547\)](#)
- [ihuClearQueryModifiers \(on page 1548\)](#)
- [ihuRetrieveCalculatedDataEx2 \(on page 1548\)](#)
- [ihuSetQueryModifiers \(on page 1549\)](#)

ihuBrowseQueryModifiers

Use the `ihuBrowseQueryModifiers` function to return a list of all supported query modifiers from the Historian Server. Various versions of the Historian Data Archiver may support different sets of modifiers.

Prototype

```
ihuBrowseQueryModifiers (
    long serverhandle,
    IHU_QUERY_MODIFIER **QueryModifiers,
    int *NumberOfModifiers
);
```

Remarks

The `NumberOfModifiers` parameter returns a total count of modifiers. The `QueryModifiers` parameter returns a list of supported query modifiers.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`

ihuClearQueryModifiers

Use the `ihuClearQueryModifiers` function to clear any previously set query modifiers so that they are not used in subsequent reads.

Prototype

```
ihuErrorCode ihuClearQueryModifiers(void)
```

Remarks

Use `ihuSetQueryModifiers()` to set a modifier string to be used in all reads. Call `ihuClearQueryModifiers()` to stop using that modifier.

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_OUT_OF_MEMORY`

ihuRetrieveCalculatedDataEx2

Use the `ihuRetrieveCalculatedDataEx2` function with the `ihuStateCount` and `ihuStateTime` calculation modes to return calculated data based on the raw samples stored in the archive.

You can request data by specifying a number of samples or an interval. Set one to a nonzero value and the other to 0. To split the duration, divide the time from start to finish into evenly spaced time intervals.

Prototype

```
ihuRetrieveCalculatedDataEx2
(long serverhandle,
IHU_TIMESTAMP StartTime,
IHU_TIMESTAMP EndTime,
ihuCalculationMode CalculationMode,
ihuDataType StateDataType,
ihuValue StateValue,
unsigned long NumberOfSamples,
```

```
IHU_DATA_INTERVAL Interval,
IHU_RETRIEVED_DATA_RECORDS_EX *DataRecords)
```

Returns

This function returns `ihuSTATUS_OK` when values are retrieved successfully, and returns the following errors:

- Read timeouts
- User is not a member of the iH Readers security group
- Tag not found

ihuSetQueryModifiers

Use the `ihuSetQueryModifiers` function to define query modifier criteria for all subsequent data reads.

Prototype

```
ihuSetQueryModifiers (
long serverhandle,
MSO Char *CriteriaString
)
```

Returns

- `ihuSTATUS_OK`
- `ihuSTATUS_INVALID_PARAMETER`
- `ihuSTATUS_OUT_OF_MEMORY`

Read Functions

Read Functions Overview

You can use read functions to retrieve raw, sampled, and calculated values stored in the Historian server for usage in reporting, plotting, or data analysis applications.

In most cases, multiple tags can be read in a single function call.

Most of the read functions serve the general purpose of retrieving raw, sampled or calculated data. Additionally, targeted functions are exposed to provide easy access to current tag values or values interpolated to a specific date and time stamp.

Comments, if they exist, are returned with retrieved data. See the sample programs for more information.

You can combine read functions with write functions to read back newly written data, which is the most secure way to verify successful data writes.

Read Functions

- [ihuReadCurrentValue](#) (on page 1550)
- [ihuReadInterpolatedValue](#) (on page 1551)
- [ihuReadInterpolatedValueEx](#) (on page 1552)
- [ihuReadRawDataByTime](#) (on page 1553)
- [ihuReadRawDataByTimeEx](#) (on page 1554)
- [ihuReadMultiTagRawDataByCountEx](#) (on page 1557)
- [ihuReadRawDataByCount](#) (on page 1555)
- [ihuReadRawDataByCountEx](#) (on page 1556)
- [ihuReadMultiTagRawDataByCount](#) (on page 1557)
- [ihuReadMultiTagRawDataByCountEx](#) (on page 1557)
- [ihuRetrieveSampledData](#) (on page 1558)
- [ihuRetrieveSampledDataEx](#) (on page 1559)
- [ihuRetrieveSampledDataEx2](#) (on page 1560)
- [ihuRetrieveCalculatedData](#) (on page 1561)
- [ihuRetrieveCalculatedDataEx](#) (on page 1562)
- [ihuRetrieveCalculatedDataEx3](#) (on page 1563)

ihuReadCurrentValue

Use the `ihuReadCurrentValue` function to return the current tag value. The current tag value has a specific definition in Historian, but is generally the last raw sample sent to the archiver for that tag.

Prototype

```
ihuReadCurrentValue {  
    in long serverhandle,  
  
    in int number_of_tags,  
  
    in/out IHU_DATA_SAMPLE *pSamples,  
  
    out ihuErrorCode *error_returns  
};
```

Remarks

You can retrieve current values for multiple tags with one call. A single sample for each requested tag is returned.

For each tag, set only the tagname field in `IHU_DATA_SAMPLE`. All other fields are set by the function.

Data is returned based on the data type of the tag.

Returns

The `ihuReadCurrentValue` function returns errors in two ways. The function has a return code, and each tag name has an error code. Check function-level errors before you examine tag-level errors.

Both are `ihuSTATUS_OK` when the current value is successfully retrieved.

The `ihuReadCurrentValue` function can return errors on read timeouts or when the user is not a member of the `ih Readers` security group.

For example, each tag can return an error in cases where tags are not found or have no raw samples.

ihuReadInterpolatedValue

Use the `ihuReadInterpolatedValue` function to return the value of a tag interpolated to a specified date and time.

Prototype

```
ihuReadInterpolatedValue {
    in long serverhandle,
    in int number_of_tags,
    in/out IHU_DATA_SAMPLE * pSamples,
    out ihuErrorCode * error_returns
};
```

Remarks

You can retrieve values for multiple tags with one call. A single sample for each requested tag is returned.

For each tag, set only the tagname and time stamp fields in `IHU_DATA_SAMPLE`. All other fields are set by the function. The time stamp in the first requested tag is used for all tags.

Data is returned based on the data type of the tag.

The data quality returned is either `ihuOPCGood` or `ihuOPCBad`, and the substatus is always `ihuOPCNonspecific`.

You must specify a time stamp in `IHU_DATA_SAMPLE` for the first requested tag, for example:

```
//you only need to populate the time stamp in the first sample
lRet = IHU_timestamp_FromParts(2003,
7,
22,
11,
0,
0,
0,
&pSamples[0].timestamp);
lRet= ihuReadInterpolatedValue (serverhandle, // handle from connect
number_of_tags, // number of tags, one sample per tag
pSamples, // allocated by caller, value set by API
error_returns); // error code per tag
```

For an example, refer to the ReportLike sample program.

Returns

The `ihuReadInterpolatedValue` function returns errors in two ways. The function has a return code, and each tag name has an error code. Check function-level errors before you examine tag-level errors.

Both are `ihuSTATUS_OK` when the current value is successfully retrieved.

The `ihuReadInterpolatedValue` function returns errors on read timeouts or when the user is not a member of the ih Readers security group.

For example, each tag can return an error in cases where tags are not found or have no raw samples.

ihuReadInterpolatedValueEx

Use the `ihuReadInterpolatedValueEx` function to return the number of samples of a tag interpolated to a given date and time with filters and query modifiers by using `pszFilterExpression` and `CriteriaString`.

Prototype

```
ihuErrorCode IHUAPI ihuReadInterpolatedValueEx
(
```

```

long serverhandle, // [in] used for communication with server

int number_of_tags, // [in] the number of tags to retrieve

IHU_DATA_SAMPLE *pSamples, // [in/out] user fills tagname and timestamp and the API fills other fields

MSO_Char *pszFilterExpression, // [in] Filter Expression e.g. Tag > 20

IHU_FILTER_MODE FilterMode, // [in] Filter Modes

MSO_Char *CriteriaString, // [in] QueryModifiers to use with data reads

ihuErrorCode *error_returns // [out] populated with per tag error

);

```

Remarks

To skip filtering, you can pass `NULL` to `pszFilterExpression` and `ihuExactTime` to `FilterMode`, or you can use [ihuReadInterpolatedValue\(\)](#) (on page 1551).

Pass `NULL` to `CriteriaString` if you do not use a `QueryModifier`.

You can retrieve values for multiple tags with one call. A single sample for each requested tag is returned.

For each tag, set only the tagname and time stamp fields in `IHU_DATA_SAMPLE`. All other fields are set by the function. The time stamp in the first requested tag is used for all tags.

Data is returned based on the data type of the tag.

The data quality returned is either `ihuOPCGood` or `ihuOPCBad`, and the substatus is always `ihuOPCNonspecific`.

If you want to specify a time stamp, you must do so in `IHU_DATA_SAMPLE` for the first requested tag.

Returns

The `ihuReadInterpolatedValueEx` function returns errors on:

- Read timeouts
- User is not a member of the ih Readers security group
- Tag not found
- Filter criteria or query modifiers cannot be set

ihuReadRawDataByTime

Use the `ihuReadRawDataByTime` function to return multiple raw samples for a single tag in a specified time range.

Prototype

```
ihuReadRawDataByTime {
    in long serverhandle,
    in MSO Char * tagname,
    in IHU_timestamp * StartTime,
    in IHU_timestamp * EndTime,
    out int * number_of_samples,
    out IHU_DATA_SAMPLE **data_values
};
```

Remarks

The time stamp, value, and quality of each raw sample are returned.

Returns

The `ihuReadRawDataByTime` function returns `ihuSTATUS_OK` when values are successfully retrieved.

Errors are returned on read timeouts, when the user is not a member of the ih Readers security group, or if the tag is not found.

ihuReadRawDataByTimeEx

Use the `ihuReadRawDataByTimeEx` function to return multiple raw samples for a single tag in a specified time range with filters and query modifiers by using `pszFilterExpression` and `CriteriaString`.

Prototype

```
ihuReadRawDataByTimeEx {
    long serverhandle, // [in] the serverhandle
    MSO_Char *tagname, // [in] the single tagname to fetch data for
    MSO_Char *pszFilterExpression, // [in] Filter Expression e.g. Tag > 20
    IHU_FILTER_MODE FilterMode, // [in] Filter Modes
    MSO_Char *CriteriaString, // [in] QueryModifiers to use with data reads
    IHU_TIMESTAMP * StartTime, // [in] Start time of query
    IHU_TIMESTAMP * EndTime, // [in] End Time of query
    int * number_of_samples, //[out] the number of samples returned
    IHU_DATA_SAMPLE **data_values // [out] the returned data samples, unlimited number
};
```

Remarks

To skip filtering, you can pass `NULL` to `pszFilterExpression` and `ihuExactTime` to `FilterMode`, or you can use `ihuReadRawDataByTime()`.

Pass `NULL` to `CriteriaString` if you do not use a `QueryModifier`.

The time stamp, value, and quality of each raw sample are returned.

Returns

The `ihuReadRawDataByTimeEx` function returns `ihuSTATUS_OK` on success, or returns errors on:

- Read timeouts
- User is not a member of the ih Readers security group
- Tag not found
- Filter criteria or query modifiers cannot be set

ihuReadRawDataByCount

Use the `ihuReadRawDataByCount` function to return the requested number of raw samples for a single tag going forward or backward in time from a specified time stamp. In cases where the number of samples available is less than the value specified in the `number_of_samples` parameter, the function stops returning data.

Prototype

```
ihuReadRawDataByCount {
    in long serverhandle,
    in MSO Char *tagname,
    in IHU_timestamp * StartTime,
    in/out int * number_of_samples,
    in int TimeForward,
    out IHU_DATA_SAMPLE **data_values
};
```

Remarks

The time stamp, value, and quality of each raw sample are returned.

Returns

The `ihuReadRawDataByCount` function returns `ihuSTATUS_OK` when values are successfully retrieved.

Errors are returned on read timeouts, when the user is not a member of the ih Readers security group, or if the tag is not found.

ihuReadRawDataByCountEx

Use the `ihuReadRawDataByCountEx` function to return the requested number of raw samples for a single tag going forward or backward in time from a specified time stamp by using `pszFilterExpression` and `CriteriaString`. In cases where the number of samples available is less than the value specified in the `number_of_samples` parameter, the function stops returning data.

Prototype

```
ihuReadRawDataByCountEx {
    long serverhandle, // [in] the serverhandle

    MSO_Char *tagname, // [in] the single tagname to fetch data for

    MSO_Char *pszFilterExpression, // [in] Filter Expression e.g. Tag > 20

    IHU_FILTER_MODE FilterMode, // [in] Filter Modes

    MSO_Char *CriteriaString, // [in] QueryModifiers to use with data reads

    IHU_TIMESTAMP * StartTime, // [in] Start time of query

    IHU_TIMESTAMP * EndTime, // [in] End time of query

    int * number_of_samples, // [in/out] the number of samples to return and actually returned

    int TimeForward, // [in] TRUE if search should be in forward time order

    IHU_DATA_SAMPLE **data_values // [out] the returned data samples, unlimited number
};
```

Remarks

To skip filtering, you can pass `NULL` to `pszFilterExpression` and `ihuExactTime` to `FilterMode`, or you can use [ihuReadRawDataByCount\(\)](#) (on page 1555).

Pass `NULL` to `CriteriaString` if you do not use a `QueryModifier`.

The time stamp, value, and quality of each raw sample are returned.

Returns

The `ihuReadRawDataByCountEx` function returns `ihuSTATUS_OK` when values are successfully retrieved, and returns errors on:

- Read timeouts
- User is not a member of the ih Readers security group
- Tag not found
- Filter criteria or query modifiers cannot be set

ihuReadMultiTagRawDataByCount

Use the `ihuReadMultiTagRawDataByCount` function to return up to the requested number of raw samples for multiple tags.

Prototype

```
ihuErrorCode IHUAPI ihuReadMultiTagRawDataByCount (
    long serverhandle,
    int number_of_tags,
    IHU_TIMESTAMP *StartTime,
    int *number_of_samples, BOOL TimeForward,
    ihuErrorCode **error_returns, IHU_RETRIEVED_RAW_VALUES *pSamples
);
```

Remarks

The `ihuReadMultiTagRawDataByCount` function returns per-tag and overall errors.

Returns

The `ihuReadMultiTagRawDataByCount` function returns `ihuSTATUS_OK` when values are successfully retrieved.

Errors are returned on read timeouts, when the user is not a member of the ih Readers security group, or if the tag is not found.

ihuReadMultiTagRawDataByCountEx

Use the `ihuReadMultiTagRawDataByCountEx` function to return up to a requested number of multiple raw samples for multiple tags with filters and query modifiers by using `pszFilterExpression` and `CriteriaString`.

Prototype

```
ihuErrorCode IHUAPI ihuReadMultiTagRawDataByCountEx (
    long serverhandle, // [in] the serverhandle
    int number_of_tags, // [in] the number of tags to retrieve
```

```

IHU_TIMESTAMP * StartTime, // [in] Start time of query

IHU_TIMESTAMP * EndTime, // [in] End time of query

MSO_Char *pszFilterExpression, // [in] Filter Expression e.g. Tag > 20

MSO_Char *CriteriaString, // [in] QueryModifiers to use with data reads

IHU_FILTER_MODE FilterMode, // [in] Filter Modes

int * number_of_samples, // [in/out] the number of samples to return and actually returned

BOOL TimeForward, // [in] TRUE if search should be in forward time order ihuErrorCode ** error_returns, // [out]
    populated with per tag error

IHU_RETRIEVED_RAW_VALUES *pSamples // [in/out] the returned data samples, unlimited number memory is allocated

);

```

Remarks

To skip filtering, you can pass `NULL` to `pszFilterExpression` and `ihuExactTime` to `FilterMode`, or you can use [ihuReadMultiTagRawDataByCount\(\)](#) (on page 1557).

Pass `NULL` to `CriteriaString` if you do not use a `QueryModifier`.

The `ihuReadMultiTagRawDataByCount` function returns per-tag and overall errors.

Returns

The `ihuReadRawDataByCountEx` function returns `ihuSTATUS_OK` when values are successfully retrieved, and returns errors on:

- Read timeouts
- User is not a member of the ih Readers security group
- Tag not found
- Filter criteria or query modifiers cannot be set

ihuRetrieveSampledData

Use the `ihuRetrieveSampledData` function to return sampled data based on the raw samples stored in the archive. `Interpolated`, `Trend`, and `Lab` are example `SamplingMode` values.

Prototype

```

ihuRetrieveSampledData {
    in long serverhandle,
    in IHU_timestamp StartTime,
    in IHU_timestamp EndTime,

```

```

in ihuSamplingMode SamplingMode,

in unsigned long NumberOfSamples,

in unsigned long IntervalMilliseconds,

in/out IHU_RETRIEVED_DATA_RECORDS *DataRecords

};

```

Remarks

To request data, you can specify a number of samples or a time interval. Set one parameter to a non-zero value and the other to 0. To split the duration, divide the time from start to finish into evenly spaced time intervals.

Returns

The `ihuRetrieveSampledData` function returns `ihuSTATUS_OK` when values are successfully retrieved.

Errors are returned on read timeouts, when the user is not a member of the ih Readers security group, or if the tag is not found.

ihuRetrieveSampledDataEx

Use the `ihuRetrieveSampledDataEx` function to return sampled data based on the raw samples stored in the archive. `Interpolated`, `Trend`, and `Lab` are example `SamplingMode` values. Use this function with hybrid sampling modes such as `TrendToRaw` or `InterpolatedToRaw` to return the sampling mode that was actually used.

Prototype

```

ihuRetrieveSampledDataEx {

long serverhandle, // [in] which server to fetch from

IHU_TIMESTAMP StartTime, // [in] Start time for the query

IHU_TIMESTAMP EndTime, // [in] End time for the query

ihuSamplingMode SamplingMode, // [in] The requested sampling mode

unsigned long NumberOfSamples, // [in] 0 or num samples to return

IHU_DATA_INTERVAL Interval, // [in] 0 or sampling interval in units provided by IntervalType

IHU_RETRIEVED_DATA_RECORDS_EX *DataRecords // [in/out] - caller fills in tagnames of the structures and API will

};

```

Remarks

To request data, you can specify a number of samples or a time interval. Set one parameter to a non-zero value and the other to 0. To split the duration, divide the time from start to finish into evenly spaced time intervals.

If you are not using hybrid sampling modes, use [ihuRetrieveSampledData\(\)](#) (on page 1558).

Returns

The `ihuReadRawDataByTimeEx` function returns `ihuSTATUS_OK` when values are successfully retrieved, and returns errors on:

- Read timeouts
- User is not a member of the ih Readers security group
- Tag not found

ihuRetrieveSampledDataEx2

Use the `ihuRetrieveSampledDataEx2` function to return sampled data based on the raw samples stored in the archive with filters and query modifiers by using `pszFilterExpression` and `CriteriaString`.

`Interpolated`, `Trend`, and `Lab` are example `SamplingMode` values. Use this function with hybrid sampling modes such as `TrendToRaw` or `InterpolatedToRaw` to return the sampling mode that was actually used.

Prototype

```
ihuRetrieveSampledDataEx2 {
    long serverhandle, // [in] which server to fetch from
    IHU_TIMESTAMP StartTime, //[in] Start time for the query
    IHU_TIMESTAMP EndTime, //[in] End time for the query
    ihuSamplingMode SamplingMode, //Sampling Modes
    MSO_Char *pszFilterExpression, // [in] Filter Expression e.g. Tag > 20
    IHU_FILTER_MODE FilterMode, // [in] Filter Modes
    MSO_Char *CriteriaString, // [in] QueryModifiers to use with data reads
    unsigned long NumberOfSamples, //[in] 0 or number of samples to return
    IHU_DATA_INTERVAL Interval, // [in] 0 or sampling interval in units provided by IntervalType
    IHU_RETRIEVED_DATA_RECORDS_EX *DataRecords //[in/out] - you fill in tagnames of the structures and API will fill
};
```

Remarks

To request data, you can specify a number of samples or a time interval. Set one parameter to a non-zero value and the other to 0. To split the duration, divide the time from start to finish into evenly spaced time intervals.

To skip filtering, you can pass `NULL` to `pszFilterExpression` and `ihuExactTime` to `FilterMode`, or you can use `ihuRetrieveSampledData()` (on page 1558).

Pass `NULL` to `CriteriaString` if you do not use a `QueryModifier`.

Returns

The `ihuRetrieveSampledDataEx2` function returns `ihuSTATUS_OK` when values are successfully retrieved, and returns errors on:

- Read timeouts
- User is not a member of the ih Readers security group
- Tag not found
- Filter criteria or query modifiers cannot be set

ihuRetrieveCalculatedData

Use the `ihuRetrieveCalculatedData` function to return calculated data based on the raw samples stored in the archive. `Average`, `Minimum`, and `Count` are example `CalculationMode` values.

Prototype

```
ihuRetrieveCalculatedData {
    in long serverhandle,
    in IHU_timestamp StartTime,
    in IHU_timestamp EndTime,
    in ihuCalculationMode CalculationMode,
    in unsigned long NumberOfSamples,
    in unsigned long IntervalMilliseconds,
    in/out IHU_RETRIEVED_DATA_RECORDS *DataRecords
};
```

Remarks

To request data, you can specify a number of samples or a time interval. Set one parameter to a non-zero value and the other to 0. To split the duration, divide the time from start to finish into evenly spaced time intervals.

Returns

The `ihuRetrieveCalculatedData` function returns `ihuSTATUS_OK` when values are successfully retrieved.

Errors are returned on read timeouts, when the user is not a member of the ih Readers security group, or if the tag is not found.

ihuRetrieveCalculatedDataEx

Use the `ihuRetrieveCalculatedDataEx` function to return calculated data based on the raw samples stored in the archive. `Average`, `Minimum`, and `Count` are example `CalculationMode` values.

Prototype

```
ihuRetrieveCalculatedDataEx {
    long serverhandle, // [in] which server to fetch from
    IHU_TIMESTAMP StartTime, //[in] Start time of query
    IHU_TIMESTAMP EndTime, //[in] End time of query
    ihuCalculationMode CalculationMode, //[in] Calculation Mode
    unsigned long NumberOfSamples, //[in] Number of samples to be returned
    IHU_DATA_INTERVAL Interval, // [in] Interval in Milliseconds
    IHU_RETRIEVED_DATA_RECORDS_EX *DataRecords //[in/out] - you fill in tagnames of the structures and API will fill
};
```

Remarks

To request data, you can specify a number of samples or a time interval. Set one parameter to a non-zero value and the other to 0. To split the duration, divide the time from start to finish into evenly spaced time intervals.

Returns

The `ihuReadRawDataByTimeEx2` function returns `ihuSTATUS_OK` when values are successfully retrieved, and returns errors on:

- Read timeouts
- User is not a member of the ih Readers security group
- Tag not found

ihuRetrieveCalculatedDataEx3

Use the `ihuRetrieveCalculatedDataEx3` function to return sampled data based on the raw samples stored in the archive with filters and query modifiers by using `pszFilterExpression` and `CriteriaString`. `Average`, `Minimum`, and `Count` are example `CalculationMode` values.

Prototype

```
ihuRetrieveCalculatedDataEx3 {
    long serverhandle, // [in] which server to fetch from
    IHU_TIMESTAMP StartTime, // [in] Start time of query
    IHU_TIMESTAMP EndTime, // [in] End time of query
    ihuCalculationMode CalculationMode, //[in] Calculation Mode
    MSO_Char *pszFilterExpression, // [in] Filter Expression e.g. Tag > 20
    IHU_FILTER_MODE FilterMode, // [in] Filter Modes
    MSO_Char *CriteriaString, // [in] QueryModifiers to use with data reads
    ihuDataType StateDataType, // DataType of the StateValue to compare for ihuStateCount calculation mode
    ihuValue StateValue, // Value to compare for ihuStateCount calculation mode unsigned long NumberOfSamples,
    IHU_DATA_INTERVAL Interval, // [in] Interval in Milliseconds
    IHU_RETRIEVED_DATA_RECORDS_EX *DataRecords // [in/out] - you fill in tagnames of the structures and API will fill
};
```

Remarks

To request data, you can specify a number of samples or a time interval. Set one parameter to a non-zero value and the other to 0. To split the duration, divide the time from start to finish into evenly spaced time intervals.

To skip filtering, you can pass `NULL` to `pszFilterExpression` and `ihuExactTime` to `FilterMode`, or you can use [ihuRetrieveCalculatedData\(\)](#) (on page 1561).

Pass `NULL` to `CriteriaString` if you do not use a `QueryModifier`.

Returns

The `ihuRetrieveCalculatedDataEx3` function returns `ihuSTATUS_OK` when values are successfully retrieved, and returns errors on:

- Read timeouts
- User is not a member of the ih Readers security group
- Tag not found
- Filter criteria or query modifiers cannot be set

Utility Functions

Utility Functions Overview

Utility functions ease programming. Time stamp conversion functions are necessary to produce the time stamps needed in most API functions.

Utility Functions

- [IHU_timestamp_FromParts](#) (on page 1564)
- [IHU_timestamp_ToParts](#) (on page 1565)
- [ihuServerGetTime](#) (on page 1566)

IHU_timestamp_FromParts

Use the `IHU_timestamp_FromParts` function to use supplied time parts (date, hour, minutes, seconds, and so on) to produce a UTC time stamp in the format needed by the Historian User API read and write calls.

Prototype

```
IHU_timestamp_FromParts {  
  
    in int Year,  
  
    in int Month,  
  
    in int Day,  
  
    in int Hour,  
  
    in int Minute,  
  
    in int Second,  
  
    in long Subsecond,  
  
    out IHU_timestamp *time stamp  
  
};
```

Remarks

The time parts passed in are assumed to be in the local time zone of the machine where you make the call.

During UTC conversion, the **Use Daylight Saving Time** setting of your local machine is used.

Returns

The `IHU_timestamp_FromParts` function returns `ihuSTATUS_OK` on success, or an error code on failure.

IHU_timestamp_ToParts

Use the `IHU_timestamp_ToParts` function to convert UTC time stamps to the following human-readable parts:

- `Year`
- `Month`
- `Date`
- `Hour`
- `Minute`
- `Second`
- `Subsecond`

You can use this function to convert the time stamps of retrieved data samples.

Prototype

```
IHU_timestamp_ToParts {  
    in IHU_timestamp time stamp  
  
    out int *Year,  
    out int *Month,  
    out int *Day,  
    out int *Hour,  
    out int *Minute,  
    out int *Second,  
    out long *Subsecond,  
};
```

Remarks

The time parts produced are in the local time zone of the machine where you make the call.

During conversion from UTC, the **Use Daylight Saving Time** setting of your local machine is used.

Returns

The `IHU_timestamp_ToParts` function returns `ihuSTATUS_OK` on success, or an error code on failure.

ihuServerGetTime

Use the `ihuServerGetTime` function to return the current time on the Historian server.

Prototype

```
ihuErrorCode IHUAPI ihuServerGetTime  
  
(  
    long serverhandle,  
    IHU_TIMESTAMP *CurrentTime  
)
```

Remarks

The `ihuServerGetTime` function has the following inputs and outputs:

- `hServer`: Server handle from the connection
- `CurrentTime`: Current time on the server in the local time zone

Returns

The `ihuServerGetTime` function returns `ihuSTATUS_OK` on success, or an error code on failure.

Enumerated Sets Functions

Enumerated Sets Functions Overview

You can use the enumerated sets functions to create, modify, delete, and browse enumerated sets, and assign tags to those sets.

When you query tag data by using these functions, the string state name value is returned by default. To retrieve the numeric value, use `ihuEnumeratedSetRawValue`.

When you write to a tag by using these functions, write the numeric value.

Use these functions to retrieve all the enumerated sets that match the `setname` mask criteria. If you want to retrieve all sets, pass `*` as the mask.

Enumerated Sets Functions

- [ihuGetEnumeratedSets](#) (on page 1567)
- [ihuEnumeratedSetAdd](#) (on page 1567)
- [ihuEnumeratedSetRawValue](#) (on page 1568)
- [ihuEnumeratedSetsFree](#) (on page 1569)
- [ihuEnumeratedSetRename](#) (on page 1570)
- [ihuEnumeratedSetDelete](#) (on page 1570)
- [ihuEnumeratedStateAdd](#) (on page 1571)
- [ihuEnumeratedStateModify](#) (on page 1572)
- [ihuEnumeratedStateDelete](#) (on page 1572)

ihuGetEnumeratedSets

Use the `ihuGetEnumeratedSets` function to retrieve all the enumerated sets that match the `setname` mask criteria. To retrieve all sets, pass `*` as the mask.

Prototype

```
ihuErrorCode IHUAPI ihuGetEnumeratedSets (
    in long serverhandle,
    in MSO Char *EnumeratedSetMask,
    out long *numberofrecords,
    out ihuEnumeratedSetRecordSet
    *EnumeratedSetRecordSet )
```

Remarks

The `ihuGetEnumeratedSets` function returns the number of enumerated set records, plus the enumerated sets.

Returns

The `ihuGetEnumeratedSets` function returns `ihuSTATUS_OK` on success, or errors if invalid input parameters are found or if out-of-memory issues occur during dynamic memory allocation.

ihuEnumeratedSetAdd

Use the `ihuEnumeratedSetAdd` function to add enumerated sets. You can specify sets that have states, or add states later on.

Prototype

```
ihuEnumeratedSetAdd
( in long serverhandle,
  in ihuEnumeratedSetProperties
  *EnumeratedSet )
```

Remarks

Any existing set with a name that matches the specified set name is overwritten by the new set.

Returns

The `ihuEnumeratedSetAdd` function returns `ihuSTATUS_OK` on success, or returns errors on:

- Invalid input parameters
- Out-of-memory issues during dynamic memory allocation
- User not a member of ihTag Admin group



Note:

Set the `Administrator` parameter to the ihTag Admin security group to assign the highest precedence to this parameter.

ihuEnumeratedSetRawValue

Use the `ihuEnumeratedSetRawValue` function to specify whether to return string or numeric values returned when reading tags by using enumerated sets. By default, string values are retrieved for tags associated with enumerated sets. To retrieve numeric values, set `SetRawValue` to `TRUE`. If string values are unavailable, raw values are retrieved.

Prototype

```
ihuEnumeratedSetRawValue (
  in long serverhandle,
  in BOOL SetRawValue
)
```

Remarks

Override the default value of `FALSE` only to return numeric values. The value persists until the function is called again or your program exits.

Returns

The `ihuEnumeratedSetRawValue` function returns `ihuSTATUS_OK` on success, or returns errors on:

- Invalid input parameters
- User not a member of ihTag Admin group



Note:

Set the `Administrator` parameter to the ihTag Admin security group to assign the highest precedence to this parameter.

ihuEnumeratedSetsFree

Use the `ihuEnumeratedSetsFree` function to clear the enumerated set buffers after you call

`ihuGetEnumeratedSets()`.

Prototype

```
ihuEnumeratedSetsFree (  
in long serverhandle,  
ihuEnumeratedSetRecordSet  
in *EnumeratedSetRecordSet )
```

Remarks

When you use the `ihuEnumeratedSetsFree` function, memory is cleared from the enumerated set buffers.

Returns

The `ihuEnumeratedSetsFree` function returns `ihuSTATUS_OK` on success, or returns errors on:

- Invalid input parameters
- User not a member of ihTag Admin group



Note:

Set the `Administrator` parameter to the ihTag Admin security group to assign the highest precedence to this parameter.

ihuEnumeratedSetRename

Use the `ihuEnumeratedSetRename` function to rename an enumerated set.

Prototype

```
ihuEnumeratedSetRename (  
in long serverhandle,  
in MSO Char *oldEnumeratedSetName,  
in MSO Char *newEnumeratedSetName )
```

Remarks

You must be an administrator of a set to rename it.

Returns

The `ihuEnumeratedSetRename` function returns `ihuSTATUS_OK` on success, or returns errors on:

- Invalid input parameters
- Out-of-memory issues during dynamic memory allocation
- No set name that matches `OldEnumeratedSetName` value
- User not a member of ihTag Admin group



Note:

Set the `Administrator` parameter to the ihTag Admin security group to assign the highest precedence to this parameter.

ihuEnumeratedSetDelete

Use the `ihuEnumeratedSetDelete` function to delete an enumerated set.

Prototype

```
ihuEnumeratedSetDelete (  
in long serverhandle,  
in MSO Char *EnumeratedSetName )
```

Remarks

You must be an administrator of a set to delete it.

Returns

The `ihuEnumeratedSetDelete` function returns `ihuSTATUS_OK` on success, or returns errors on:

- Invalid input parameters
- Out-of-memory issues during dynamic memory allocation
- No set name that matches `EnumeratedSetName` value
- User not a member of ihTag Admin group



Note:

Set the `Administrator` parameter to the ihTag Admin security group to assign the highest precedence to this parameter.

ihuEnumeratedStateAdd

Use the `ihuEnumeratedStateAdd` function to add a state to an existing enumerated set.

Prototype

```
ihuEnumeratedStateAdd (
    in long serverhandle,
    in MSO Char *EnumSetName,
    in ihuEnumeratedSetState *EnumState )
```

Remarks

When you add a state to an existing enumerated set, the data type of the new state matches the data type of other states in the set.

Any existing state with a name that matches the specified state name is overwritten by the new state.

Returns

The `ihuEnumeratedStateAdd` function returns `ihuSTATUS_OK` on success, or returns errors on:

- Invalid input parameters
- Out-of-memory issues during dynamic memory allocation
- No set name that matches `EnumSetName` value
- User not a member of ihTag Admin group

**Note:**

Set the `Administrator` parameter to the ihTag Admin security group to assign the highest precedence to this parameter.

ihuEnumeratedStateModify

Use the `ihuEnumeratedStateModify` function to modify a state in an enumerated set.

Prototype

```
ihuEnumeratedStateModify (  
    in long serverhandle,  
    in MSO Char *EnumeratedSetName,  
    in MSO Char *EnumeratedStateName,  
    ihuEnumeratedSetState  
    in *EnumStateToModify )
```

Remarks

You can modify state values and names, but not data types. To change a state name, pass the old and new names as string values inside the `EnumStateToModify` parameter.

Returns

The `ihuEnumeratedStateModify` function returns `ihuSTATUS_OK` on success, or returns errors on:

- Invalid input parameters
- No set name that matches `EnumeratedSetName` value
- No state name that matches `EnumeratedStateName` value
- User not a member of ihTag Admin group

**Note:**

Set the `Administrator` parameter to the ihTag Admin security group to assign the highest precedence to this parameter.

ihuEnumeratedStateDelete

Use the `ihuEnumeratedStateDelete` function to delete a state from an enumerated set.

Prototype

```
ihuEnumeratedStateDelete
( in long serverhandle,
  in MSO Char *EnumeratedSetName,
  in MSO Char *EnumeratedStateName
)
```

Remarks

When only one state is available in a set, you cannot delete the state. The only way to delete the state is to delete the set. There is no need to delete each state before you delete a set.

You must be an administrator of a set to delete its associated states.

Returns

The `ihuEnumeratedStateDelete` function returns `ihuSTATUS_OK` on success, or returns errors on:

- Invalid input parameters
- No set name that matches `EnumeratedSetName` value
- No state name that matches `EnumeratedStateName` value
- Out-of-memory issues during dynamic memory allocation
- User not a member of ihTag Admin group



Note:

Set the `Administrator` parameter to the ihTag Admin security group to assign the highest precedence to this parameter.

User-Defined Type Functions

User-Defined Type Functions Overview

You can use the user-defined type functions to create, modify, delete, and browse user-defined data types that contain multiple fields. You must add user-defined data types to the Data Archiver before you can use them in tags.

User-Defined Type Functions

- [ihuUserDefinedTypeAdd](#) (on page 1574)
- [ihuUserDefinedTypeDelete](#) (on page 1574)
- [ihuUserDefinedTypeRename](#) (on page 1575)
- [ihuUserDefinedTypeExists](#) (on page 1576)
- [ihuGetUserDefinedTypes](#) (on page 1576)
- [ihuUserDefinedTypeSetProperties](#) (on page 1577)
- [ihuUserDefinedTypeFreeProperties](#) (on page 1577)

ihuUserDefinedTypeAdd

Use the `ihuUserDefineTypeAdd` function to create or add `MultiField` type tags. The user-defined type you pass to this function can have multiple fields defined, or you can add fields later by using [ihuUserDefinedTypeSetProperties\(\)](#) (on page 1577).

You can also use this function to modify user-defined data types. To modify an existing type, add a user-defined data type with the same name.

Prototype

```
ihuUserDefinedTypeAdd
(
    long serverhandle, // [in] connected server handle
    ihuUserDefinedTypeProperties *InUserDefinedType // [in] UserDefined type that needs to be added / modified
)
```

Remarks

Existing types are overwritten by new types with the same names. You must be a member of the ihTag Admin group to add or modify a type.

Returns

- `ihuSTATUS_OK`: on success
- `ihuSTATUS_INVALID_PARAMETER`: `NULL` value or invalid server handle
- `ihuSTATUS_FAILED`: on any error

ihuUserDefinedTypeDelete

Use the `ihuUserDefinedTypeDelete` function to delete a user-defined type that you no longer use.

Prototype

```
ihuUserDefinedTypeDelete
(
long serverhandle, // [in] connected server handle
MSO_Char * UserDefinedTypeName //[in] UserDefined type name to be deleted
)
```

Remarks

You must be a member of the ihTag Admin group to delete a type.

Returns

- `ihuSTATUS_OK`: on success
- `ihuSTATUS_INVALID_PARAMETER`: `NULL` value or invalid server handle
- `ihuSTATUS_FAILED`: on any error

ihuUserDefinedTypeRename

Use the `ihuUserDefinedTypeRename` function to rename a user-defined type.

Prototype

```
ihuUserDefinedTypeRename
(
long serverhandle, // [in] connected server handle
MSO_Char * UserDefinedTypeName, //[in] UserDefined type name which needs to be renamed
MSO_Char *NewUserDefinedTypeName //[in] new UserDefined type name
)
```

Remarks

You must be a member of the ihTag Admin group to rename a type.

Returns

- `ihuSTATUS_OK`: on success
- `ihuSTATUS_INVALID_PARAMETER`: `NULL` value or invalid server handle
- `ihuSTATUS_FAILED`: on any error

ihuUserDefinedTypeExists

Use the `ihuUserDefinedTypeExists` function to check whether a specific user-defined type exists.

Prototype

```
ihuUserDefinedTypeExists  
  
(  
  
long serverhandle, // [in] connected server handle  
  
MSO_Char * UserDefinedTypeName // [in] UserDefined type name  
  
)
```

Returns

- `ihuSTATUS_OK`: if the type exists
- `ihuSTATUS_INVALID_PARAMETER`: `NULL` value or invalid server handle
- `ihuSTATUS_FAILED`: if the type does not exist or the server cannot be reached

ihuGetUserDefinedTypes

Use the `ihuGetUserDefinedTypes` function to return a list of user-defined types and their values. After you call this function, you must call `ihuUserDefinedTypeFreeProperties()` to release memory allocations.

Prototype

```
ihuGetUserDefinedTypes  
  
(  
  
long serverhandle, // [in] connected server handle  
  
MSO_Char *StructSetMask, //[in] Pass * to get the all the Structure or pass the name of the structure you want  
  
long *numberofrecords, //[out] Number of records  
  
ihuUserDefinedTypeRecordSet *RecordSet //[out] returns the records for the UserDefined defined types  
  
)
```

Remarks

You must be a member of the `ihReader` group to get a list of user-defined types. The list is returned in the `RecordSet` parameter.

Returns

- `ihuSTATUS_OK`: on success
- `ihuSTATUS_INVALID_PARAMETER`: NULL value passed for `StructSetMask` Or `RecordSet` Or `numberofrecords`
- `ihuSTATUS_FAILED`: on any error

ihuUserDefinedTypeSetProperties

Use the `ihuUserDefinedTypeSetProperties` function to set user-defined type properties after you add types by using `ihuUserDefinedTypeAdd()` ([on page 1574](#)).

Prototype

```
ihuUserDefinedTypeSetProperties
(
    long serverhandle, // [in] connected server handle

    ihuUserDefinedTypeProperties *UserDefinedType //[in] UserDefined type that needs to be added / created
)

```

Remarks

You must be a member of the ihTag Admin group to set type properties.

Returns

- `ihuSTATUS_OK`: on success
- `ihuSTATUS_INVALID_PARAMETER`: invalid server handle or `NULL` property pointer value passed
- `ihuSTATUS_FAILED`: on any error

ihuUserDefinedTypeFreeProperties

Use the `ihuUserDefinedTypeFreeProperties` function to free the memory allocated by the `ihuGetUserDefinedTypes()` ([on page 1576](#)) function.

Prototype

```
ihuUserDefinedTypeFreeProperties
(
    ihuUserDefinedTypeRecordSet *UserDefinedTypeRecordSet //[in] UserDefinedTypeRecordSet that needs to be fr
)

```

Remarks

Call the `ihuUserDefinedTypeFreeProperties` function once to release all memory in the recordset returned by `ihuGetUserDefinedTypes()`. Do not free the memory in your program.

Returns

Void

Publish Functions

Publish Functions Overview

You can use the publish functions to manage the data forwarding of local Historian server tags to one or more remote destination servers by using the Server-to-Server Distributors. When you publish a tag, you initiate continuous transmission of its historical data values to a destination server.

Publish Functions

- `ihuPublishAddTag` (on page 1578)
- `ihuPublishRemoveTag` (on page 1579)
- `ihuPublishTagCloseCache` (on page 1579)
- `ihuPublishGetTagPropertiesToCache` (on page 1580)
- `ihuPublishTagGetNumericPropertyByTagname` (on page 1581)
- `ihuPublishTagGetNumericPropertyByIndex` (on page 1581)
- `ihuPublishTagGetStringPropertyByTagname` (on page 1582)
- `ihuPublishTagGetStringPropertyByIndex` (on page 1582)
- `ihuPublishSetTagProperties` (on page 1583)
- `ihuPublishTagSetNumericProperty` (on page 1584)
- `ihuPublishTagSetStringProperty` (on page 1584)
- `ihuPublishTagClearProperties` (on page 1585)
- `ihuPublishGetDestinationServer` (on page 1585)
- `ihuPublishSetDestinationServer` (on page 1586)

ihuPublishAddTag

Use the `ihuPublishAddTag` function to publish a tag to a destination server. When you publish, a tag is created in the destination server.

Prototype

```
ihuPublishAddTag (
    long hSourceServer,
    MSO Char *InterfaceName,
    MSO Char *SourceTagname,);
```

Remarks

After you publish a tag, any new data for the `SourceTagname` is written to the `DestinationTagname`.

The tag is added to the destination server with default parameters that you can modify by using [ihuPublishGetTagPropertiesToCache \(on page 1580\)](#) and [ihuPublishSetTagProperties \(on page 1583\)](#).

Returns

The `ihuPublishAddTag` function returns `ihuSTATUS_OK` on success, or an error if the tag was not added to the destination server.

ihuPublishRemoveTag

Use the `ihuPublishRemoveTag` function to prevent tag publishing by a specified collector.

Prototype

```
ihuPublishRemoveTag
( long hServer,
  MSO Char *DestinationTagname,
  MSO Char *SourceTagname );
```

Remarks

The `ihuPublishRemoveTag` function does not remove the tag from the source server but marks it as deleted in the destination server. To completely stop data collection, you must disable collection.

Returns

The `ihuPublishRemoveTag` function returns `ihuSTATUS_OK` on success.

ihuPublishTagCloseCache

Use the `ihuPublishTagCloseCache` function to close a cache returned by the `ihuPublishGetTagPropertiesToCache` function.

Prototype

```
ihuPublishTagCloseCache
(
    void
);
```

Remarks

To avoid memory leaks, close the cache.

Returns

The `ihuPublishTagCloseCache` function returns `ihuSTATUS_OK` on success.

ihuPublishGetTagPropertiesToCache

Use the `ihuPublishGetTagPropertiesToCache` function to retrieve a list of tags published by the specified Server-to-Server Distributor. Be sure to match tags with the exact tag name or a name with a specified wildcard mask.



Note:

A separate published tag properties cache exists for each process thread. To avoid confusion and unexpected results, ensure that all cache-related function calls are invoked on the same thread. When threads are mixed, two or more distinct caches are referenced, which enables concurrent access to multiple different cached results at the cost of additional memory.

Prototype

```
ihuPublishGetTagPropertiesToCache
(
    long hServer,
    MSO Char *DistributorName,
    MSO Char *DestinationTagnameOrMask,
    out int *NumTagsFound
);
```

Remarks

The `ihuPublishGetTagPropertiesToCache` function returns the number of tags found in the `NumTagsFound` parameter.

Use this function to retrieve tags before you get and set string or numeric tag properties by using the `ihuPublishTagGetNumericPropertyByTagname` OR `ihuPublishTagSetStringProperty` and similar functions.

Returns

The `ihuPublishGetTagPropertiesToCache` function returns `ihuSTATUS_OK` on success, even if no tags are found. The function returns errors if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishTagGetNumericPropertyByTagname

Use the `ihuPublishTagGetNumericPropertyByTagname` function to retrieve a numeric tag property, such as the deadband for a tag. The tag is identified by name within the cache previously populated by [ihuPublishGetTagPropertiesToCache \(on page 1580\)](#).

Prototype

```
ihuPublishTagGetNumericPropertyByTagname
( MSO Char *Tagname,
  ihuTagProperties TagProperty,
  *Value );
```

Remarks

The `ihuPublishTagGetNumericPropertyByTagname` function returns the numeric tag property value.

Returns

The `ihuPublishTagGetNumericPropertyByTagname` function returns `ihuSTATUS_OK` on success, or returns an error if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishTagGetNumericPropertyByIndex

Use the `ihuPublishTagGetNumericPropertyByIndex` function to retrieve a single numeric tag property from the cache.

Prototype

```
ihuPublishTagGetNumericPropertyByIndex
(
  int Index,
  ihuTagProperties TagProperty,
  double *Value );
```

Remarks

The `ihuPublishTagGetNumericPropertyByIndex` function returns the numeric tag property retrieved. The index is zero-based.

Returns

The `ihuPublishTagGetNumericPropertyByIndex` function returns `ihuSTATUS_OK` on success, or returns an error if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishTagGetStringPropertyByTagname

Use the `ihuPublishTagGetStringPropertyByTagname` function to retrieve a single string tag property by tagname from the cache.

Prototype

```
ihuPublishTagGetStringPropertyByTagname  
  
(  
  
    MSO Char *Tagname,  
  
    ihuTagProperties TagProperty,  
  
    MSO Char *Value,  
  
    int ValueLength );
```

Remarks

The `ihuPublishTagGetStringPropertyByTagname` function returns a single string tag property by tagname from the cache.

Returns

The `ihuPublishTagGetStringPropertyByTagname` function returns `ihuSTATUS_OK` on success, or returns an error if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishTagGetStringPropertyByIndex

Use the `ihuPublishTagGetStringPropertyByIndex` function to retrieve a single string tag property from the cache. The index is zero-based.

Prototype

```
ihuPublishTagGetStringPropertyByIndex (  
  
    int Index,
```

```
ihuTagProperties TagProperty, MSO Char *Value,
int ValueLength );
```

Remarks

The `ihuPublishTagGetStringPropertyByIndex` function returns the string tag property from the cache. The index is zero-based.

Returns

The `ihuPublishTagGetStringPropertyByIndex` function returns `ihuSTATUS_OK` on success, or returns an error if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishSetTagProperties

Use the `ihuPublishSetTagProperties` function to define properties such as the deadband for a published tag. Before you call this function, set properties by using `ihuPublishTagSetStringProperty` or `ihuPublishTagSetNumericProperty`.

A separate collection of tag properties is available for each process thread, similar to the published tag properties cache. To avoid confusion, be sure to invoke this function on the same thread as `ihuPublishTagSetNumericProperty`, `ihuPublishTagSetStringProperty`, and `ihuPublishTagClearProperties`.

Prototype

```
ihuPublishSetTagProperties (
    long hServer,
    MSO Char *InterfaceName,
    MSO Char *DestinationTagname,
);
```

Remarks

After you add a tag by using the `ihuPublishAddTag` function, use the `ihuPublishSetTagProperties` function to set tag properties.

Returns

The `ihuPublishSetTagProperties` function returns `ihuSTATUS_OK` on success, or returns an error if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishTagSetNumericProperty

Use the `ihuPublishTagSetNumericProperty` function to define a numeric tag property before you invoke [ihuPublishSetTagProperties](#) (on page 1583).

Prototype

```
ihuPublishTagSetNumericProperty  
(  
    ihuTagProperties TagProperty,  
    double Value  
);
```

Remarks

The `ihuPublishTagSetNumericProperty` function returns the numeric tag property.

Returns

The `ihuPublishTagSetNumericProperty` function returns `ihuSTATUS_OK` on success, or errors on invalid input parameters or if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishTagSetStringProperty

Use the `ihuPublishTagSetStringProperty` function to define a string tag property before you invoke [ihuPublishSetTagProperties](#) (on page 1583).

Prototype

```
ihuPublishTagSetStringProperty (  
    ihuTagProperties TagProperty,  
    MSO Char *Value  
);
```

Remarks

The `ihuPublishTagSetStringProperty` function returns the string tag property.

Returns

The `ihuPublishTagSetStringProperty` function returns `ihuSTATUS_OK` on success, or errors on invalid input parameters or if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishTagClearProperties

Use the `ihuPublishTagClearProperties` function to clear any previously defined tag properties.

Prototype

```
ihuPublishTagClearProperties
(
    void
);
```

Remarks

The `ihuPublishTagClearProperties` function clears previously defined tag properties.

Returns

The `ihuPublishTagClearProperties` function returns `ihuSTATUS_OK` on success, or returns an error if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishGetDestinationServer

Use the `ihuPublishGetDestinationServer` function to retrieve the name of the destination Historian server configured for a specific distributor.

Prototype

```
ihuPublishGetDestinationServer (
    long hServer,
    MSO Char *InterfaceName,
    MSO Char **DestinationServer );
```

Remarks

The `ihuPublishGetDestinationServer` function returns the destination Historian server name.

Returns

The `ihuPublishGetDestinationServer` function returns `ihuSTATUS_OK` on success, or returns an error if any out-of-memory issues occur during dynamic memory allocation.

ihuPublishSetDestinationServer

Use the `ihuPublishSetDestinationServer` function to define the destination Historian server for a specific collector.

Prototype

```
ihuPublishSetDestinationServer (
    long hServer,
    MSO Char *InterfaceName,
    MSO Char *DestinationServer
);
```

Remarks

The `ihuPublishSetDestinationServer` function returns the Historian server name that is defined for the specified collector. The new name is assigned without a collector restart, and can be used at any time the distributor is restarted.

Returns

The `ihuPublishSetDestinationServer` function returns `ihuSTATUS_OK` on success, or returns an error if any out-of-memory issues occur during dynamic memory allocation.

Historian User API Error Codes

Error Codes

You might encounter the following error codes while you use the Historian User API:

Table 267. Historian API Error Codes

Code	Message	Description
100	<code>ihuSTATUS_FAILED</code>	Generic failure.
101	<code>ihuSTATUS_API_TIMEOUT</code>	Server machine name not found, or server found but archiver service not running.
102	<code>ihuSTATUS_NOT_CONNECTED</code>	Not currently connected to a Historian server.
103	<code>ihuSTATUS_INTERFACE_-NOT_FOUND</code>	Interface not found.

Table 267. Historian API Error Codes (continued)

Code	Message	Description
104	<code>ihuSTATUS_NOT_SUPPORTED</code>	Reserved.
105	<code>ihuSTATUS_DUPLICATE_DATA</code>	<code>ihuWriteData</code> was called with <code>error_on_replace = TRUE</code> and the supplied data would have overwritten existing data.
106	<code>ihuSTATUS_DUPLICATE_DATA</code>	Server found, but invalid username or password.
107	<code>ihuSTATUS_ACCESS_DENIED</code>	Access denied by the Historian server. Check username and password or security group membership.
108	<code>ihuSTATUS_WRITE_IN_FUTURE</code>	Write time stamp is too far in the future.
109	<code>ihuSTATUS_WRITE_ARCH_OFFLINE</code>	There is no archiver to hold the write time stamp.
110	<code>ihuSTATUS_ARCH_READONLY</code>	The destination archive to hold the write time stamp is marked as read-only.
111	<code>ihuSTATUS_WRITE_OUTSIDE_ACTIVE</code>	The write time stamp is before the active hours (now - "data is read only after") setting.
112	<code>ihuSTATUS_WRITE_NO_ARCH_AVAILABLE</code>	No archive is available to hold the write time stamp.
113	<code>ihuSTATUS_INVALID_TAGNAME</code>	Tagname used is not valid. Tagname does not exist in the Historian server.
114	<code>ihuSTATUS_LIC_TOO_MANY_TAGS</code>	Exceeded tag license count on the server.
115	<code>ihuSTATUS_LIC_TOO_MANY_USERS</code>	Exceeded user license count on the server.
116	<code>ihuSTATUS_LIC_INVALID_LIC_DLL</code>	An invalid license DLL is installed.
117	<code>ihuSTATUS_NO_VALUE</code>	No value has been passed to the function.
118	<code>ihuSTATUS_NOT_LICENSED</code>	Your Historian installation is not licensed.

Table 267. Historian API Error Codes (continued)

Code	Message	Description
119	ihuSTATUS_CALC_CIRC_REFERENCE	Reserved.
120	ihuSTATUS_DUPLICATE_INTERFACE	Reserved.
121	ihuSTATUS_BACKUP_EXCEEDED_SPACE	Reserved.
122	ihuSTATUS_INVALID_SERVER_VERSION	You are attempting to use this API on an invalid version of Historian.
123	ihuSTATUS_DATA_RETRIEVAL_COUNT_EXCEEDED	You requested too many samples in one read request.
124	ihuSTATUS_INVALID_PARAMETER	Generic failure when an invalid value is passed into the User API.

Historian User API Sample Programs

Sample Programs Overview

Sample programs are provided with the Historian User API to demonstrate how to perform common tasks. The following sample programs are supplied with the User API:

- `CollectorLike.c`: Shows an example of a program that writes thousands of samples per second to Historian tags.
- `CollectorLikeSAF.c`: Shows an example of callbacks and store and forward in the User API.
- `PlotLike.cpp`: Shows an example of a program that retrieves calculated and interpolated data suitable for plotting.
- `ReportLike.cpp`: Shows how to retrieve raw data samples from Historian.
- `MigrationLike.c`: Shows how to transfer legacy historical data into Historian.
- `QueryModifiers.c`: Shows how to retrieve data using query modifiers.
- `Blobdatatype.c`: Shows how to create tags of blob (binary object) data type and read and write data.
- `ByTag`: Shows how to read and write data for a tag by using its tag ID instead of its tag name.

No guidance is provided on how to convert applications from other products or APIs, including the Historian SDK.

To work with these samples, you must be familiar with Historian features and functionality. Refer to the Historian product documentation. This is especially important if you are using security groups with Historian, since the applications that call into the User API are limited by the security access granted at the server level.

Compiling the Samples

Only a release build configuration is provided. A debug configuration is not provided because the release mode configuration produces a program database and has compiler optimizations turned off, so that you can easily step through the sample code in the debugger.

Review the sample program source code for additional details.



Note:

The sample programs provided in this help document are for review only. Compilable source code is included in the Historian User API installation directory.

CollectorLike

This sample demonstrates how to read string and numeric tag properties and write groups of data samples to multiple tags. Data is sent to the archiver until a key is pressed. Sample code is provided for writing data of various data types and data qualities. Tips are included for achieving optimal performance. This sample program also demonstrates how to iterate through all archiver tags to find tags that belong to the collector.

PlotLike

This sample program demonstrates how to read numeric tag properties and read evenly spaced sampled or calculated data suitable for plotting. Percent good data quality indicators are described. Any comments retrieved are printed to the program window. Finally, an example is provided for how to write a comment in cases where your trending application allows users to enter comments.

ReportLike

This sample program demonstrates how raw samples are retrieved, one tag per call, by timespan and by number of samples. Comments are retrieved if they exist. The retrieved samples can be used in custom quality calculations or to implement calculation modes not available in Historian. An example of how to

calculate a raw maximum is provided. The program has a loop that fetches the current value of a tag until a key is pressed.

MigrationLike

This sample program demonstrates how to migrate data from a legacy system into Historian. Tips are provided for the most efficient sequence to use to send data to minimize archive disk space and migration time. This sample program also demonstrates how to add tags to the Historian server.

Chapter 11. Historian SDK

Object Model Overview

Historian SDK Overview

The Historian Software Development Kit (SDK) is a COM object designed to simplify access to Historian services and data for the purposes of application development.

This object provides the following functionality to developers:

- Browsing Available Historian Servers
- Browsing and Configuring Tags
- Browsing, Adding, and Modifying Data
- Browsing, Adding, and Modifying Alarms and Events
- Browsing and Adding Messages and Alerts
- Controlling the Archiving Functions of the System
- Controlling the Collection and Interface Functions of the System
- Adherence to Historian Security Constraints

If you need to create customized programming for the Historian server, use the Historian Software Development Kit (SDK) with Visual Basic or any application that provides a VBA programming interface, such as iFIX, Microsoft Excel or Microsoft Word. After you install Client Tools, the Historian SDK is available in the `System32` folder is automatically registered. To use the SDK, set up a project reference with the Historian SDK.


You can use the Historian SDK under any Win32 platform using a development language that supports Microsoft COM/DCOM. The SDK relies on the run-time version of the Historian API. You must install the Historian API prior to the installation of the SDK on any client that accesses the Historian system through the SDK. For instructions, refer to [installing Client Tools \(on page 150\)](#).

The Historian SDK is a COM DL(`ihSDK.dll`) that must be instantiated prior to use. A single instance of the SDK may connect and converse with many Historian servers simultaneously. You can create multiple instances of the SDK, however, the developer must maintain this collection and respond to events from the appropriate instance.

The following table lists general information regarding SDK naming and dependencies.

SDK DLL	ihSDK.dll
Class Name	iHistorian_SDK
Version	5.0.0.x
Dependencies	ihAPI50.dll

The following diagram describes the object model employed by the Historian SDK. For more information on the individual objects, refer to the SDK Object Reference.



Working with Comments

Comments are retrieved with a data query. To retrieve comments, request all fields from the `DataValue` object and then perform a `DataRecordset.QueryRecordset`. The comments will be contained in the `DataValue.Comments` collection. Comments are stored to the archive using the `DataRecordset.WriteRecordset` method. Store comments to the `DataValue` object first by calling the `DataValue.AddComment` method.

Adding Data

Use the `DataValue` object to insert data by setting the value, quality, and timestamp before calling the `WriteRecordset` method.

Sample SDK Program

A sample program for the SDK is included in the `Samples\SDK` folder when you install Historian. Refer to this sample for more detailed examples than the ones that appear in this Help system.



Note:

The SDK sample is designed to work on Visual Basic 6 (VB6).

Connect the SDK to the Server

After instantiation of the SDK, connect to one or more servers by providing a valid user name and password for the target Historian server domain. The SDK does not support any other functions until you make a successful connection and authentication. The authenticated user also controls which functions may be performed through the SDK and potentially what data may be accessed.

The following example displays the Visual Basic code for instantiation of the SDK and connection to the target server.

```
Dim MyServer as Object

'Instantiate The SDK

Set MyServer = CreateObject("iHistorian_SDK.Server")

'Attempt Connection

If Not MyServer.Connect("USGB014", "Fred", "000") Then
Err.Raise 1, "Failed To Connect To USGB014" End If

In the example above, "MyServer" does not receive events from the Historian server.

In order to receive events, Dim WithEvents MyServer As iHistorian_SDK.Server

'Instantiate The SDK

Set MyServer = New iHistorian_SDK.Server

'Attempt Connection

If Not MyServer.Connect("USGB014", "Fred", "000") Then
Err.Raise 1, "Failed To Connect To USGB014" End If
```

**Note:**

After each session, disconnect each Server connection prior to exiting the application.

Working with Blob Data

Historian is capable of storing many different data types, such as Floating Point, Integer, String, Binary, and BLOB (undetermined binary data type, such as an Excel spreadsheet, a PDF file, or a Word file). The source of the data defines the ability of Historian to collect specific data types.

The following example demonstrates how to read and write a file into Historian. It contains a sample script for adding, writing, and reading a tag of BLOB data type. You will need to change the server name, folder, and file names as appropriate.

```
Dim MyServer As Server

Private Function Connect1() As Boolean
    If Not MyServer Is Nothing Then
        MyServer.Disconnect
    End If
    Set MyServer = Nothing

    Set MyServer = New Server

    Connect1 = MyServer.Connect("FRIEDENTHAL")
End Function

Private Function AddTag(Tagname As String) As Boolean
    Dim Tags As TagRecordset
    Dim NewTag As Tag

    Set Tags = MyServer.Tags.NewRecordset
    Set NewTag = Tags.Add(Tagname)
    NewTag.DataType = Blob
    AddTag = Tags.WriteRecordset

End Function

Private Function WriteBlob(Tagname As String, TimeStamp As Date, ByteArray() As Byte, FileName As String) As Boolean
```

```

Dim Data As DataRecordset

Dim NewValue As DataValue

Set Data = MyServer.Data.NewRecordset

Set NewValue = Data.Add(Tagname, TimeStamp)

NewValue.Value = ByteArray

NewValue.DataQuality = Good

'Store the file name as a comment
NewValue.AddComment FileName

WriteBlob = Data.WriteRecordset

End Function

Private Function ReadBlob(Tagname As String, TimeStamp As Date, ByteArray() As Byte, FileName As String) As Boolean

Dim Data As DataRecordset

Dim NewValue As DataValue

Set Data = MyServer.Data.NewRecordset

With Data.Criteria

.Tagmask = Tagname

.StartTime = DateAdd("s", -1, TimeStamp)

.EndTime = DateAdd("s", 1, TimeStamp)

.SamplingMode = RawByTime

End With

With Data.Fields

.AllFields

End With

ReadBlob = Data.QueryRecordset

ByteArray = Data.Item(1).Item(1).Value

FileName = Data.Item(1).Item(1).Comments.Item(1).Comment

End Function

Function ReadFile(FileName$, fileDirectory$) As Variant

Dim ByteArray() As Byte

Dim FileLen As Long

```

```
Dim MyByte As Byte

Dim i As Long

Dim fName As String

fName = fileDirectory + FileName

Open fName For Binary Access Read As #1 ' Open file for reading.

FileLen = LOF(1) - 1

ReDim ByteArray(FileLen)

For i = 0 To FileLen

Get #1, , MyByte

ByteArray(i) = MyByte

Next

Close #1

ReadFile = ByteArray

End Function

Function WriteFile(fName, ByteArray() As Byte)

Dim FileLen As Long

Dim i As Long

FileLen = UBound(ByteArray)

Open fName For Binary Access Write As #1

For i = 0 To FileLen - 1

Put #1, , ByteArray(i)

Next

Close #1

End Function

Private Sub RunTest()

Dim ByteArray() As Byte

Dim i As Integer

Dim TheTime As Date

Dim FileName As String

FileName = "iHvbs.log"

Const ReadFileDirectory = "C:\\"

Const WriteFileDirectory = "C:\Temp\"

ReDim ByteArray(0 To 9)
```

```
If Not Connect1() Then

MsgBox "Did Not Connect"

Exit Sub

End If

If Not AddTag("TestBlob2") Then

MsgBox "Did Not Add Tag"

Exit Sub

End If

'Read the input file

ByteArray = ReadFile(FileName, ReadFileDirectory)

TheTime = Now

'Write the file to Historian

If Not WriteBlob("TestBlob2", TheTime, ByteArray, FileName) Then

MsgBox "Did Not Write Blob"

Exit Sub

End If

Erase ByteArray

FileName = ""

'Read back the file from Historian

If Not ReadBlob("TestBlob2", TheTime, ByteArray, FileName) Then

MsgBox "Did Not Read Blob"

Exit Sub

End If

FileName = WriteFileDirectory + FileName 'copy file to the write directory

WriteFile FileName, ByteArray

End Sub

Private Sub CommandButton1_Click()

End Sub
```

Working with Archives

You can backup, restore, and create archives using the SDK. To restore an archive, you add an existing archive file to the archives collection using the Add method.

Example

The following code shows an example of how to restore an archive.

```
Dim myarchives As iHistorian_SDK.Archives
Dim myarchive As iHistorian_SDK.Archive
Dim i As Long
Set myarchives = DefaultServer.Archives
Set myarchive = myarchives.Add("MY_SERVER_archive001", "d:\program
files\Historian\Archives\MY_SERVER_archive001_Backup.IHA", 100)
If myarchive Is Nothing Then
MsgBox "An Error Occured Trying To Restore The Archive." + Chr(10) + Chr(10) + _
"The Details Of The Error Follow:" + Chr(10) + DefaultServer.Archives.LastError, vbCritical, "Historian"
Err.Raise 1,, "Error Restoring Archive: " + DefaultServer.Archives.LastError
Else
MsgBox "success"
End If
```

SDK Reference

Object Summary

This section contains the Historian objects that are available in the Historian Software Development Kit.

Alarms Object

You can use Historian to store data for alarms and events. From the SDK, you can add and query these alarms and events. This class is slightly different from other SDK classes in that you will mostly be accessing lower level functionality to add and query alarms and events. By following the directions below, you should be able to perform these tasks fairly easily.

Add Historian Type Library to the Project

As previously mentioned, access to methods for alarms and events is lower level. You must add the Historian COM 1.1 Type library to your project. In Visual Basic, in the Project menu, select References, and then add the library. You can now access the lower level alarms and events methods.

Query by Alarms and Events

For instructions on querying alarms and events, see the documentation for the AlarmRecordSet function.

Add Alarms and Events

You can add alarms and events to Historian by using the AlarmInfo object. In general, adding alarms or events is easy; declare a new AlarmInfo object, fill it up with the required details, and then run the Add function on the AlarmInfo object. In practice, you must be aware of the lifecycle of your alarm.

Create a new AlarmInfo Object

To create a new AlarmInfo object, use the CreateObject method as follows:

```
Dim myAlarmInfo As AlarmInfo

Set myAlarmInfo = CreateObject("Historian_API.AlarmInfo")
```

Alarm or Event?

Historian distinguishes between alarms and events. Alarms follow a lifecycle as described below, while events are generally one-shot deals. Example events include Set Point Events, Login Events, or other audit trail events. Alarms are generally characterized by a tag going into and out of an abnormal condition. You must identify your AlarmInfo object as an alarm or event by setting the AlarmType field.

```
Alarm:myAlarmInfo.AlarmType = ihALARM_CONDITION

Event: myAlarmInfo.AlarmType = ihALARM_TRACKING
```

Alarm Life Cycle

As previously mentioned, Alarms generally follow a lifecycle. To avoid bad quality alarms in the archive, when adding alarms, ensure that you follow the lifecycle rules below.



Note:

For each lifecycle phase, you must create and add a new AlarmInfo object. Or, if you prefer to use the same AlarmInfo object for each lifecycle phase, you can use the CleartheAlarmInfo object after you have added it.

```
myAlarmInfo.AddMyServer myAlarmInfo.Clear
```

New Alarm

To instantiate a new alarm, specify the start time in the AlarmInfo object.

```
myAlarmInfo.StartTime= Now
```

State Change

If the alarm changes states (from HI to HIHI for example), you must specify only the new subcondition (along with the other required fields mentioned below). You can optionally specify the starttime field as the original start time (when the alarm first went to HI), but it is not mandatory.



Important:

Do not specify a new start time. If you do so, a new alarm will be created instead.

```
myAlarmInfo.SubConditionName= "HIHI"
```

Wrong: `myAlarmInfo.StartTime= Now`

OK: `myAlarmInfo.StartTime=AlarmStartTime`

Acknowledge an Alarm

To acknowledge an alarm, set the Acked field in the AlarmInfo to True, and also specify the time of the acknowledgement by populating the AckTime alarm field. In addition, you must populate the starttime field with the start time of the alarm (when it first went into an alarm condition, not the last state change).

```
myAlarmInfo.Acked= TRUE

myAlarmInfo.AckTime = Now

myAlarmInfo.StartTime = AlarmStartTime
```

Return to Normal

When your alarm condition has ended, specify the endtime in the AlarmInfo Object. Similar to the state change and acknowledgements, you can optionally specify the start time of the alarm in the starttime alarm field.

```
myAlarmInfo.EndTime= Now myAlarmInfo.StartTime = AlarmStartTime
```

Associating Alarms and Events with Tag Data

The easiest way to associate alarms and events with tag data is to specify the TagName in the AlarmInfo. Historian will sort out everything behind the scenes. However, if you are adding alarms before the associated tag actually exist in Historian, this avenue will not work. You must populate the ItemId field with the source address of the future tag, and populate the DataSourceName field with the collector name of the tag. When the tag is added to the system, the alarms will be correctly linked.

```
myAlarmInfo.Tagname = TheTagName
```

Or

```
myAlarmInfo.DataSourceName = MyCollector.Name myAlarmInfo.ItemId = TheSourceAddress
```

AlarmInfoFields

The following table lists the AlarmInfo fields. The fields that are marked as required must be filled in for every call to add. In addition, populate the correct fields based on the current state in the lifecycle of your alarm (see above).

FieldName	Data Type	Required for Alarms or Events?	Description
AlarmType	Long	Both	Classifies this AlarmInfo as an alarm or an event. Enter 1 for an event and 4 for an alarm.
ItemID	String	None	The ItemID of the alarm or event. This contains the source address of the data access tag that the alarm is associated with. This can be NULL if the alarm is not associated with a tag.
Source	String	Both	This is the unique identifier used for the alarm or event.
DataSourceName	String	Both	The collector interface name associated with the alarm or event.
Tagname	String	None	The Historian Tag Name associated with the alarm.
EventCategory	String	None	The event category of the alarm or event.
ConditionName	String	Alarms	The condition of the alarm. This does not apply to event data. This, combined with the source, comprises an alarm.

FieldName	Data Type	Required for Alarms or Events?	Description
SubConditionName	String	Alarms	The sub-condition of the alarm. This does not apply to event data. This is the state of the alarm.
StartTime	Date	None	The start time or time stamp of the alarm or event.
EndTime	Date	None	The end time of the alarm. This does not apply to event data.
AckTime	Date	None	The time the alarm was acknowledged. This does not apply to event data.
Timestamp	Date	Both	The time stamp of the alarm or event.
Message	String	None	The message attached to the alarm or event.
Acked	Boolean	None	Stores the acknowledgement status of the alarm. If the alarm is acknowledged, this will be set to TRUE.
Severity	Long	None	The severity of the alarm or event. This is stored as an integer value with a range of 1-1000.
Actor	String		The operator who acknowledged the alarm, or caused the tracking event.
Quality	Long	Alarms	The quality of the alarm or event. 0 for bad, 3 for good.

Example

```
Dim MyServer As iHistorian_SDK.Server
Set MyServer = GetServer

Dim myAlarmInfo As AlarmInfo
Set myAlarmInfo = CreateObject("iHistorian_API.AlarmInfo")

Dim AlarmStartTime As Date
AlarmStartTime = Now
```

```
' New Alarm myAlarmInfo.AlarmType = ihALARM_CONDITION
myAlarmInfo.ConditionName = "SampleCondition"
myAlarmInfo.DataSourceName = "SampleDataSource"
myAlarmInfo.Message = "Sample Alarm"
myAlarmInfo.Source = "SampleSource"
myAlarmInfo.StartTime = AlarmStartTime
myAlarmInfo.SubConditionName = "HI"
myAlarmInfo.Timestamp = Now
myAlarmInfo.Quality = 3
myAlarmInfo.Add MyServer
myAlarmInfo.Clear

' State Change myAlarmInfo.AlarmType = ihALARM_CONDITION
myAlarmInfo.ConditionName = "SampleCondition"
myAlarmInfo.DataSourceName = "SampleDataSource"
myAlarmInfo.Message = "Sample Alarm State II"
myAlarmInfo.Source = "SampleSource"

' Not required, but pointing out the start time of the alarm doesn't hurt
myAlarmInfo.StartTime = AlarmStartTime
myAlarmInfo.SubConditionName = "HIHI"
myAlarmInfo.Timestamp = Now
myAlarmInfo.Quality = 3
myAlarmInfo.Add MyServer
myAlarmInfo.Clear

' Ack the HIHI state
myAlarmInfo.Acked = True
myAlarmInfo.AckTime = Now
myAlarmInfo.AlarmType = ihALARM_CONDITION
myAlarmInfo.ConditionName = "SampleCondition"
myAlarmInfo.DataSourceName = "SampleDataSource"
myAlarmInfo.Source = "SampleSource"
myAlarmInfo.StartTime = AlarmStartTime
myAlarmInfo.SubConditionName = "HIHI"
myAlarmInfo.Timestamp = Now
myAlarmInfo.Quality = 3
myAlarmInfo.Add MyServer myAlarmInfo.Clear

' Return to Normal
myAlarmInfo.AlarmType = ihALARM_CONDITION
```

```
myAlarmInfo.ConditionName = "SampleCondition"  
myAlarmInfo.DataSourceName = "SampleDataSource"  
myAlarmInfo.EndTime = Now  
myAlarmInfo.Source = "SampleSource"  
  
' Not required, but pointing out the start time of the alarm doesn't hurt  
myAlarmInfo.StartTime = AlarmStartTime  
myAlarmInfo.Timestamp = Now  
myAlarmInfo.Quality = 3  
myAlarmInfo.Add MyServer  
myAlarmInfo.Clear
```

Archive Object

The Archive object contains the configuration and status information for a single archive file on the Historian server.

Archives Object

The Archives object provides access to Historian archive configuration information and performance statistics. It also provides functionality to add, delete, and modify Historian archives.

Alarms.PurgeAlarmsById

The following sample is used to develop an SDK sample for purging alarms by their alarm IDs.

```
Dim Alarms() As String  
Dim AlarmIds() As Long  
Dim i As Long  
Dim numberOfAlarms As Long  
Dim AlarmsObj As iHistorian_SDK.Alarms  
Dim Status As Boolean  
i = 0  
numberOfAlarms = 0  
Status = False  
If CheckConnection = True Then  
    Set AlarmsObj = ConnectedServer.Alarms  
    If TextAlarmIds.Text = "" Then  
        MsgBox "Alarms cannot be empty", vbCritical, "Historian"  
    Exit Sub  
End If
```

```

Trim (TextAlarmIds.Text)

'Multiple alarms are separated by semicolon
Alarms() = Split(TextAlarmIds.Text, ";")
numberOfAlarms = UBound(Alarms)

If numberOfAlarms <> 0 Then
ReDim AlarmIds(0 To numberOfAlarms) As Long

  For i = 0 To numberOfAlarms
    If Alarms(i) <> "" Then
      AlarmIds(i) = CLng(Alarms(i))
    End If
  Next

  Status = AlarmsObj.PurgeAlarmsById(AlarmIds())

  If Status <> True Then
    MsgBox "An error occurred while deleting the alarms. See the Historian Alerts for more details.", vbCritical,
    "Historian"
  Else
    MsgBox "Successfully deleted the alarms.", vbInformation, "Historian"
  End If

  TextAlarmIds.Text = ""
Else
  MsgBox "Please enter Alarm Ids followed by ';'", vbCritical, "Historian"
End If

Else
  MsgBox "Not connected", vbCritical, "Historian"
End If

```

Collector Object

The Collector object contains the configuration and status information for a single collector connected to the Historian Server.

Collectors Object

The Collectors Object provides access to the Historian Collector configuration information and performance statistics. It also provides functionality to add, delete, and modify Historian Collectors.

Data Objects

Data Object

The **Data** object provides access to Historian data and provides functionality to add, delete, and modify data samples in the Historian archives.

DataComments Object

The **DataComments** object contains a collection of comments attached to a specific DataValue record.

DataCriteria Object

The **DataCriteria** object sets the criteria for the retrieval of DataValue records into a DataRecordset Object. For example, you may want values between a certain start and end time.

DataFields Object

The **DataFields** object identifies which DataValue fields a DataRecordset query retrieves. For example, you may not want to retrieve comments with your data.

DataRecordset Object

The **RecordSet** contains a collection of DataValue records. Use the DataRecordset object to add, delete, or modify data samples.

To add, modify, or delete a DataValue record:

1. Create a DataRecordset Object.
2. Add, delete, or modify the DataValue Records.
3. Perform a WriteRecordset operation to save the changes to the Historian archives.

DataValue Object

The **DataValue** object contains data for a single tag and timestamp. It also contains a data quality and one or more comments attached to the specific data value. You can modify the Value, DataQuality, and Comments properties and commit them to the Historian server by using the WriteRecordset Method of the DataRecordsetObject. You cannot modify the timestamp.

Message Objects

Message Object

The **Message** object provides access to a single message retrieved from the Historian server.

MessageCriteria Object

The **MessageCriteria** object sets the criteria for retrieval of message records into a MessageRecordset object.

MessageFields Object

The **MessageFields** object identifies which message fields the MessageRecordset query retrieves.

MessageRecordset Object

The **MessageRecordset** contains a collection of messages from the Historian Server. Use the MessageRecordset Object to add and retrieve messages. To add new messages, create a MessageRecordset, add the appropriate messages, and then perform the WriteRecordset operation to store the changes in the Historian archives.

Messages Object

The **Messages** object contains Historian messages and provides functionality for adding new messages to the Historian Server. For example, you may want only alerts or you may want messages associated with a certain user.

OPC Objects

OPCBrowse Object

The OPCBrowse object allows you to retrieve hierarchical areas from OPC AE servers.

OPCFilters Object

Returns whether Auto-Reconnect logic is Enabled/Disabled.

Option Object

This object acts a simple container for providing a name and values for a named parameter. The possible option values are found in *Options.bas*.

Server Objects

Server Object

Use the **Server** object to establish and maintain a connection to a specific Historian server. All other configuration and data access objects are subordinate to the Server object.

ServerManager Object

The **ServerManager** object permits you to browse the available servers registered on the client. The ServerManager object also provides functionality for adding new server connections and for setting the default login information.

Tag Objects

Tag Object

The **Tag** object contains configuration information for a single tag. You can modify properties of the Tag object and save them to the Historian server by using the WriteRecordset method of the TagRecordset object.

TagCriteria Object

The TagCriteria object sets the criteria for retrieval of Tag records into a TagRecordset object.

TagDependencies Object

The **TagDependencies** object represents a list of Historian Tags which trigger a given calculation when their values change.

TagFields Object

The **TagFields** object identifies which tag fields are retrieved in a TagRecordset query.

TagRecordset Object

The **TagRecordset** object is a collection of tag records that contain tag configuration information.


To add, modify, or delete tags:

1. Create a TagRecordset object.
2. Add, delete, and modify tag records.
3. Perform a WriteRecordset operation to save the changes to the Historian tag database.

Tags Object

The **Tags** object contains Historian tag configuration information and provides functionality for adding, deleting, and modifying this configuration.

The following figure describes the Tags object.



UserCalcFunction Object

The UserCalcFunction object contains the definition of a user function that can be stored in the Calculation library.

Property Reference A-B

The following list contains the Historian properties that are available in the Historian Software Development Kit in the alphabetical order.

A

ActualDataStores Property (Server Object)

Returns the actual data stores currently configured on the Historian Server.

Syntax

object.**ActualDataStores**

Parameters

None

Remarks

ActualDataStores is a read-only property of type Long.

ActualTags Property (Server Object)

Returns the number of tags currently configured on the Server. This number is less than or equal to the number of licensed tags.

Syntax

object.**ActualTags**

Parameters

None

Remarks

ActualTags is a read-only property of type Long.

ActualUsers Property (Server Object)

Returns the number of users currently connected to the Server. This number is less than or equal to the number of licensed users.

Syntax

object.**ActualUsers**

Parameters

None

Remarks

ActualUsers is a read-only property of type Long.

AdministratorSecurityGroup Property (Tag Object)

Returns or sets the name of the security group controlling configuration changes for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**AdministratorSecurityGroup**[= *String*]

Parameters

None

AdministratorSecurityGroup Property (TagCriteria Object)

Sets the administrator security group for which the TagRecordset query searches.

Syntax

object.**AdministratorSecurityGroup**[= *String*]

Parameters

None

AdministratorSecurityGroup Property (TagFields Object)

Determines whether the TagRecordset query returns the AdministratorSecurityGroup field.

Parameters

object.**AdministratorSecurityGroup**[= *Boolean*]

Parameters

None

AdministratorSecurityGroup Property (UserDefinedType Object)

Returns or sets the name of the Administrator Security Group that controls the definition of a User Defined Type. You can create, modify or delete types if you have Administration Security Group permission to do so. If there is no assigned group then the name will be empty.

Syntax

object.**MyAdministratorSecurityGroup**

Parameters

None

Returns

String

AdministratorSecurityGroupSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**AdministratorSecurityGroupSet**[= *Boolean*]

Parameters

None

AdministratorSecurityGroupUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**AdministratorSecurityGroupUpdated**[= *Boolean*]

Parameters

None

Alarms Property (Server Object)

Returns the Alarms object for the current server. Use the Alarms object to query Alarms and Events data of the server.

Syntax

object.**Alarms**

Parameters

None

Remarks

Alarms is a read-only property of type Alarms.

AllAlerts Property (MessageCriteria Object)

Causes the MessageRecordset query to include all alert topic messages.

Syntax

object.**AllAlerts**[= *Boolean*]

Parameters

None.

Example

```
MyMessages.Criteria.AllAlerts = True
```

AllMessages Property (MessageCriteria Object)

Specifies that all message topic messages (non-alerts) should be returned by the MessageRecordset query.

Syntax

```
object.AllMessages[ = Boolean]
```

Parameters

None

Example

```
MyMessages.Criteria.AllMessages = True
```

ArchiveAbsoluteDeadband Property (Tag Object)

Returns or sets the Absolute Deadband value for this tag to be used in the Archiver.

Syntax

```
object.ArchiveAbsoluteDeadband[ = Double]
```

Parameters

None

ArchiveAbsoluteDeadband Property (TagCriteria Object)

Sets the ArchiveAbsoluteDeadband to search for in the TagRecordset query.

Syntax

```
object.ArchiveAbsoluteDeadband[ = Double]
```

Parameters

None

ArchiveAbsoluteDeadband Property (TagFields Object)

Determines whether the ArchiveAbsoluteDeadband field should be returned in the TagRecordset query.

Syntax

object.**ArchiveAbsoluteDeadband**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbandSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveAbsoluteDeadbandSet**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbandUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveAbsoluteDeadbandUpdatedSet**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbanding Property (Tag Object)

Returns or sets whether this tag is using Absolute Deadbanding in the Archiver or not.

Syntax

object.**ArchiveAbsoluteDeadbandingSet**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbanding Property (TagCriteria Object)

Sets the ArchiveAbsoluteDeadbanding to search for in the TagRecordset query.

Syntax

object.**ArchiveAbsoluteDeadbandingSet**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbandSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveAbsoluteDeadbandsetSet**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbandUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveAbsoluteDeadbandupdated**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbanding Property (Tag Object)

Returns or sets whether this tag is using Absolute Deadbanding in the Archiver or not.

Syntax

object.**ArchiveAbsoluteDeadbanding**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbanding Property (TagCriteria Object)

Sets the ArchiveAbsoluteDeadbanding to search for in the TagRecordset query.

Syntax

object.**ArchiveAbsoluteDeadbanding**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbanding Property (TagFields Object)

Determines whether the ArchiveAbsoluteDeadbanding field should be returned in the TagRecordset query.

Syntax

object.**ArchiveAbsoluteDeadbanding**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbandingSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveAbsoluteDeadbandingSet**[= *Boolean*]

Parameters

None

ArchiveAbsoluteDeadbandingUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveAbsoluteDeadbandingUpdated**[= *Boolean*]

Parameters

None

ArchiveAllowDataOverwrites Property (Archives Object)

Returns whether or not a Data Archiver should allow overwriting of an existing data.

ArchiveBaseFileName Property (Archives Object)

Returns a default string that an archive file names must be based on.

ArchiveCompression Property (Tag Object)

Returns or sets the archive compression for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.ArchiveCompression[= *Boolean*]

Parameters

None

ArchiveCompression Property (TagCriteria Object)

Sets the archive compression value for which the TagRecordset query searches.

Syntax

object.ArchiveCompression[= *Byte*]

Parameters

None

ArchiveCompression Property (TagFields Object)

Determines whether the TagRecordset query returns the ArchiveCompression field.

Syntax

object.ArchiveCompression[= *Boolean*]

Parameters

None

ArchiveCompressionSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.ArchiveCompressionSet[= *Boolean*]

Parameters

None

ArchiveCompressionTimeout Property (Tag Object)

Gets or sets the value of the Archive Compression Timeout. This is the amount of time after which a value will be written to the archive regardless of compression.

Syntax

object.**ArchiveCompressionTimeout**[= *Long*]

Parameters

None

ArchiveCompressionTimeout Property (TagCriteria Object)

Sets the Archive Compression Timeout value to search for in the TagRecordset query.

Syntax

object.**ArchiveCompressionTimeout**[= *Long*]

Parameters

None

ArchiveCompressionTimeout Property (TagFields Object)

Determines whether the TagRecordset query returns the *ArchiveCompressionTimeout* field.

Syntax

object.**ArchiveCompressionTimeout**[= *Boolean*]

Parameters

None

ArchiveCompressionTimeoutSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveCompressionTimeoutSet**[= *Boolean*]

Parameters

None

ArchiveCompressionTimeoutUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveCompressionTimeoutUpdated**[= *Boolean*]

Parameters

None

ArchiveCompressionUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveCompressionUpdated**[= *Boolean*]

Parameters

None

ArchiveCreateOfflineArchives Property (Archives Object)

Returns whether a Data Archiver should accept data before starting an old archive.

ArchiveDeadbandPercentRange Property (Tag Object)

Returns or sets the deadband in percent of engineering unit range for archive compression for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**ArchiveDeadbandPercentRange**[= *Single*]

Parameters

None

ArchiveDeadbandPercentRange Property (TagCriteria Object)

Sets the archive compression deadband for which the TagRecordset query searches.

Syntax

object.**ArchiveDeadbandPercentRange**[= *Single*]

Parameters

None

ArchiveDeadbandPercentRange Property (TagFields Object)

Determines whether the TagRecordset query returns the ArchiveDeadbandPercentRange field.

Syntax

object.**ArchiveDeadbandPercentRange**[= *Boolean*]

Parameters

None

ArchiveDeadbandPercentRangeSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveDeadbandPercentRangeSet**[= *Boolean*]

Parameters

None

ArchiveDeadbandPercentRangeUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiveDeadbandPercentRangeUpdated**[= *Boolean*]

Parameters

None

ArchiveMaxMemoryBufferSize Property (Archives Object)

Returns memory size of Data Archiver queues.

ArchiveUseClientLoginUser Property (Archives Object)

Returns whether a Data Archiver requires users to enter a user name and password details in the client application.

Remarks

Set to FALSE to require a username and password.

ArchiverClustered Property (Server Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ArchiverClustered**

Parameters

None

Remarks

ArchiverClustered is a read-only property of type Boolean.

ArchiverDemoMode Property (Server Object)

Returns whether the server is currently running in demo-license mode. Demo mode is restricted to 100 tags and a single user connection.

Syntax

object.**ArchiverDemoMode**

Parameters

None

Remarks

ArchiverDemoMode is a read-only property of type Boolean.

Archives Property (Server Object)

Returns the Archives Object for the current server. The Archives Property does not return the Archives Object unless the authenticated user is a member of the Historian archive Administrators group.

Syntax

object.**Archives**

Parameters

None

Remarks

Archives is a read-only property of type Archives.

Example

```
Dim MyServer As New iHistorian_SDK.Server

    Dim MyArchives As iHistorian_SDK.Archives ' Connect to the local server

    If Not MyServer.Connect("", "", "")

    Then    err.Raise 1, , "Failed to connect to the local server" End If

    ' We are connected, try to instantiate the Archives object Set MyArchives =

    MyServer.Archives

    If MyArchives Is Nothing Then    err.Raise 1, , "User is not able to manage archives" End If
```

Archiving Property (Archives Object)

Returns the Archiving status of the current archive.

Syntax

object.**Archiving**[= *Boolean*]

Parameters

None

ArchivingOptions Property (Archives Object)

Exposes the ArchivingOptions collection to control the behavior of the Historian Archiver.

Table 268. Archiving Options

Option	Description
ArchiveSizeIncrement	Sets the size increments of the archive file (Default=100MB). This option is specific to a data store.
ArchiveDefaultPath	Specifies the default path that the archives are created in. This option is specific to a data store.
ArchiveActiveHours	Specifies the hours before now that the data becomes Read-Only. This option is specific to data store.
ArchiveDefaultSize	Specifies the create archive default size in MB. This option is specific to a data store.
ArchiveAutomaticCreate	Specifies whether the system automatically creates archives when all empty archives are filled. This option is specific to a data store.
ArchiveAutomaticFreeSpace	The amount of free space required on the drive of the default path after creating an archive of default size. This option is specific to a data store.
ArchiveOverwriteOld	Determines whether or not old archives are cleared and re-used when no other empty space is available. This option is specific to a data store.
ArchiveBackupPath	Specifies the default path for backup archives. This option is specific to a data store.
ArchiveBaseName	Specifies the default string archive names should be based on. This option is specific only to a data store.
ArchiveBaseFileName	Returns a default string that an archive file names must be based on. This option is specific to a data store.
ArchiveCreateOfflineArchives	Returns whether a Data Archiver should accept data before starting an old archive. This option is specific to a data store.

Table 268. Archiving Options (continued)

Option	Description
ArchiveUseClientLoginUser	Returns whether a Data Archiver requires users to enter a user name and password details in the client application. This option is specific to a data store.
ArchiveAllowDataOverwrites	Returns whether or not a Data Archiver should allow overwriting of an existing data. This option is specific to a data store.
ArchiveDuration	Number of Units of time an archive can hold. Defined by ArchiveDurationType. This option is specific to a data store.
ArchiveTotalDuration	Number of Hours that the archives for a DataStore can span. (This is only meaningful for Scada-Buffer DataStores) This option is specific to a data store.
ArchiveDurationType	<p>The type of archive duration.</p> <ul style="list-style-type: none"> • ArchiveDurationBySize • ArchiveDurationDaily • ArchiveDurationHourly <p>This option is specific to a data store.</p>
ArchiveUseCaching	Indicates whether the archive should use caching or not. Set it to 1 to use caching and to 0 if you do not want to use caching. This option is specific to a data store.
ArchiveCacheSize	This is for internal use.
ArchiverServerMemoryLoad	How much server memory the Historian Data Archive is consuming. This option is specific to the data archiver.
ArchiverEquipmentDelimiter	This is for internal use.

Table 268. Archiving Options (continued)

Option	Description
ArchiverServerMemoryLoad	How much server memory the Historian Data Archive is consuming. This option is specific to the data archiver.
ArchiverEquipmentDelimiter	This is for internal use.
MessageOnDataUpdate	How much server memory the Historian Data Archive is consuming. This option is specific to the data archiver.
ArchiveMaxMemoryBufferSize	The maximum buffer memory (MB). This option is specific to the data archiver.
ArchiverTargetPrivateBytes	The memory size of the archiver. If it is 0, it means that it is managed by server. Otherwise, enter a number in megabytes of memory. This option is specific to the data archiver.
CollectorIdleTime	The number of seconds before a collector is considered idle. If this number is set to 270 seconds and no data for any tags is received for 270 seconds then the collector is considered idle. This option is specific to the data archiver.
MaximumQueryIntervals	Specifies the maximum number of samples per tag that Historian can return from a non-raw data query. Use this setting to throttle query results for non-raw data queries. This setting does not apply to filtered data queries or raw data queries. This option is specific to the data archiver.
MaximumQueryTime	Specifies the maximum time that a data or message query can take before it is terminated. Use this setting to limit query time and provide balanced read access to the archiver. This applies to all query types. This option is specific to the data archiver.

Syntax

object.**ArchivingOptions**(OptionName) [*= Variant*]

Parameters

Name **OptionName** Data type **String** Description **The name of an archiving option.**

Example

```
MyServer.DataStores.DataStoreUpdate("MYDATASTORE", True, "", "") Then

maintain auto recovery files

MyServer.MaintainAutoRecoveryFiles =TRUE
```

AreaCount Property (OPCBrowse Object)

Returns the number of Areas under a browse position. When a browse operation occurs, the server returns all areas and sources under the BrowsePosition. AreaCount gives you the number of Areas, which you can use to iterate the AreaNames and FullAreaNames arrays.

Syntax

object.**AreaCount**

Parameters

None

Remarks

AreaCount is a read-only property returned as type Long.

AreaNames Property (OPCBrowse Object)

Returns an area name for an AE server. See FullAreamames property for details.

Syntax

object.**AreaNames**(Index)

Parameters

Index. Integer. The index into the area nae array

Remarks

AreaNames is a read-only String property returned as a variant for script compatibility.

Areas Property (OPCFilters Object)

Returns a list of the Areas selected for collection. This list is only applied when isAreaFiltering (true) has been called.

Syntax

object.**Areas**

Parameters

None

AuditMessage Property (Server Object)

Returns or sets the E-signature audit message. Setting the audit message to an empty string will use the system default message.

Syntax

object.**AuditMessage**[= *String*]

Parameters

None

AutoReconnectRateSeconds Property (OPCFilters Object)

If AutoReconnect logic is enabled (isAutoReconnectOn(true)) this property represents the rate in seconds that the Alarm Collector will attempt to determine if the server is still alive.

Syntax

object.**AutoReconnectRateSeconds**[= *Long*]

Parameters

None

B

BrowsePosition Property (OPCBrowse Object)

Returns the current value of the browse position in the hierarchy.

Syntax

object.**BrowsePosition**[= *Variant*]

Parameters

None

Remarks

This is used for subsequent browse calls to get the leaf under the current position.

BrowseRoot Property (OPCBrowse Object)

Returns the root name of the OPC area hierarchy.

Syntax

object.**BrowseRoot**

Parameters

None

Remarks

BrowseRoot is a read-only property of type String.

Property Reference C-D

CalcType Property (Tag Object)

Returns or sets the CalcType for the tag. The CalcType is used to determine whether the tag is a Python Expression tag or a Raw tag.

Name	Description	Value
RawTag	A tag is not a Python Expression Tag	0
PythonExprTag	A tag that uses a Python Expression to transform raw data into derived values.	2

Syntax

object.CalcType [=ihTagCalcType]

Parameters

None

CalcType Property (TagCriteria Object)

Returns or sets the CalcType for the tag. The CalcType is used to determine whether the tag is a Python Expression tag or a Raw tag.

Name	Description	Value
RawTag	A tag is not a Python Expression Tag	0
PythonExprTag	A tag that uses a Python Expression to transform raw data into derived values.	2

Syntax

```
object.CalcType [=ihTagCalcType]
```

Parameters

None

CalcType Property (TagFields Object)

Determines whether the CalcType field should be returned in the TagRecordset query.

Syntax

```
object.CalcType [ = Boolean]
```

Parameters

None

CalcTypeList Property (Tags Object)

Returns a list of valid calculation types available on a tag in Historian.

Syntax

```
object.CalcType
```

Parameters

None

CalcTypeSet Property (TagCriteria Object)

A flag to indicate whether or not the CalcType property has been set or not.

Syntax

```
object.CalcTypeSet [ = Boolean]
```

Parameters

None

CalcTypeUpdated Property (Tag Object)

A flag to indicate whether or not the CalcType property has been set.

Syntax

```
object.CalcTypeUpdated [ = Boolean]
```

Parameters

None

Calculation Property (Tag Object)

Returns or sets the calculation for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.Calculation[ = String]
```

Parameters

None

Calculation Property (TagCriteria Object)

Sets the calculation to search for in the TagRecordset query.

Syntax

```
object.Calculation[ = String]
```

Parameters

None

Calculation Property (TagFields Object)

Determines whether the TagRecordset query returns the Calculation field.

Syntax

```
object.Calculation[ = Boolean]
```

Parameters

None

CalculationDependencies Property (Tag Object)

Returns a collection of tagnames that the calculation is dependent upon. Use the CalculationDependencies property with unsolicited tags only.

Syntax

```
object.CalculationDependencies
```

Parameters

None

Remarks

CalculationDependencies is a read-only property of type TagDependencies.

CalculationDependencies Property (TagFields Object)

Determines whether the CalculationDependencies field should be returned in the TagRecordset query.

Syntax

```
object.CalculationDependencies[ = Boolean]
```

Parameters

None

CalculationDependenciesUpdated Property (Tag Object)

Returns whether or not the Calculation Dependencies have been updated. & Boolean true if the dependencies have been updated, false otherwise.

Syntax

```
object.CalculationDependenciesUpdated
```

Parameters

None

CalculationExecutionTime Property (Tag Object)

Returns the average time, in milliseconds, it takes to execute a calculation formula for the tag.

Syntax

```
object.CalculationExecutionTime
```

Parameters

None

Remarks

CalculationExecutionTime is a read-only property of type Long.

CalculationExecutionTime Property (TagFields Object)

Determines whether the CalculationExecutionTime field should be returned in the TagRecordset query.

Syntax

```
object.CalculationExecutionTime[ = Boolean]
```

Parameters

None

CalculationMode Property (DataCriteria Object)

Returns or sets the type of calculation to perform on archive data retrieved in the DataRecordset query. CalculationMode only applies to a Calculated SamplingMode.

The table below defines the available Calculation Modes:

Name	Description	Value
Average	Retrieves the time-weighted average for each calculation interval.	1

Name	Description	Value
StandardDeviation	Retrieves the time-weighted standard deviation for each calculation interval.	2
Total	<p>Retrieves the time-weighted rate total for each calculation interval. A rate total would be appropriate for totalizing a continuous measurement.</p> <p>Time weighting is necessary due to the fact that compressed data is not evenly spaced in time. A factor must be applied to the totalized value to convert into the appropriate engineering units. Given the fact that this is a rate total, a base rate of Units/Day is assumed. If the actual units of the continuous measurement were Units/Minute, it would be necessary to multiply the results by 1440 Minutes / Day to convert the totalized number into the appropriate engineering units.</p>	3
Minimum	Retrieves the minimum value for each calculation interval.	4
Maximum	Retrieves the maximum value for each calculation interval.	5
Count	Retrieves the count of archive values found within each calculation interval.	6
RawAverage	Retrieves the arithmetic average of archive values for each calculation interval.	7
RawStandardDeviation	Retrieves the arithmetic standard deviation of archive values for each calculation interval.	8
RawTotal	Retrieves the arithmetic total of archive values for each calculation interval.	9
MinimumTime	Retrieves the timestamp of the minimum value found within each calculation interval. It may be a raw or an interpolated value. The minimum must be a good data quality sample.	10

Name	Description	Value
MaximumTime	Retrieves the timestamp of the maximum value found within each calculation interval. It may be a raw or an interpolated value. The maximum must be a good data quality sample.	11
TimeGood	Retrieves the amount of time (in milliseconds) during the interval when the data is of good quality and the filter condition is met.	12
StateCount	Retrieves the amount of time a tag has transitioned to another state from a previous state during a time interval.	13
OPCAnd	Retrieves the OROPCQAND, bit-wise AND operation of all the 16-bit OPC qualities of the raw samples stored in the specified interval.	16
OPCOr	Retrieves the OPCQOR, bit-wise OR operation of all the 16-bit OPC qualities of the raw samples stored in the specified interval.	16

Syntax

```
object.CalculationMode[ = iHistorian_SDK.ihCalculationMode]
```

Parameters

None

CalculationModeList Property (Data Object)

This function returns a list of the available Calculation modes for a data request.

Syntax

```
object.CalculationModeList
```

Parameters

None

CalculationModeSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CalculationModeSet[ = Boolean]
```

Parameters

None

CalculationSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CalculationSet[ = Boolean]
```

Parameters

None

CalculationUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CalculationUpdated[ = Boolean]
```

Parameters

None

CanAdministerConfiguration Property (Archives Object)

Returns whether the current user is authorized to perform configuration changes to Archives or Archiving options.

Syntax

```
object.CanAdministerConfiguration
```

Parameters

None

Remarks

CanAdministerConfiguration is a read-only property of type Boolean.

Example

```
' Check Security If Not MyServer.Archives.CanAdministerConfiguration Then  err.Raise 1, "Security",  
"You Are Not Authorized To Make Configuration Changes" End If
```

CanAdministerConfiguration Property (Collectors Object)

Returns whether the current user is authorized to perform configuration changes to Collectors.

Syntax

```
object.CanAdministerConfiguration
```

Parameters

None

Remarks

CanAdministerConfiguration is a read-only property of type Boolean.

Example

```
' Check Security If Not MyServer.Archives.CanAdministerConfiguration Then  err.Raise 1, "Security",  
"You Are Not Authorized To Make Configuration Changes" End If
```

CanAdministerSecurity Property (Server Object)

Returns whether the current user is authorized to perform tag security changes.

Syntax

```
object.CanAdministerSecurity
```

Parameters

None

Remarks

CanAdministerSecurity is a read-only property of type Boolean.

Example

```
Dim MyServer As New iHistorian_SDK.Server ' Connect to the local server If Not MyServer.Connect("", "",
    "") Then
    err.Raise 1, , "Failed to connect to local server" End If If Not
    MyServer.Tags.CanAdministerConfiguration Then
    err.Raise 1, , "Cannot administer security" End If
```

CanAdministerSecurity Property (Tags Object)

Returns whether the current user is authorized to security configuration changes.

Syntax

```
object.CanAdministerSecurity
```

Parameters

None

Remarks

CanAdministerSecurity is a read-only property of type Boolean.

CanAudit Property (Server Object)

Returns whether E-signatures are enabled on the hardware key.

Syntax

```
object.CanAudit
```

Parameters

None

Remarks

CanAudit is a read-only property of type Boolean.

CanCalculate Property (Server Object)

Returns whether the Calculation collector is enabled on the hardware key.

Syntax

```
object.CanCalculate
```

Parameters

None

Remarks

CanCalute is a read-only property of type Boolean.

CanRead Property (Data Object)

Returns whether the current user is authorized to read data from the server.

Syntax

```
object.CanRead
```

Parameters

None

Remarks

CanRead is a read-only property of type Boolean.

Example

```
' Check Security If Not MyData.CanRead Then err.Raise 1, , "You are not authorized to read data from  
this server" End If
```

CanRead Property (Messages Object)

Returns whether the current user is authorized to read messages from the server.

Syntax

```
object.CanRead
```

Parameters

None

Remarks

CanRead is a read-only property of type Boolean.

Example

```
' Check Security If Not MyData.CanRead Then err.Raise 1, , "You are not authorized to read messages  
from this server" End If
```

CanReplicate Property (Server Object)

Returns whether ServerToServer collector is enabled on the hardware key.

Syntax

```
object.CanRelpicate
```

Parameters

None

Remarks

CanReplicate is a read-only property of type Boolean.

CanSupportRedundantCollectors Property (Server Object)

Returns whether Collector Redundancy is enabled on the hardware key.

Syntax

```
object.CanSupportRedundantCollectors
```

Parameters

None

Remarks

CanSupportRedundantCollectors is a read-only property of type Boolean.

CanWrite Property (Data Object)

Returns whether the current user is authorized to write data to the server.

Syntax

```
object.CanWrite
```

Parameters

None

Remarks

CanWrite is a read-only property of type Boolean.

Example

```
' Check Security If Not MyData.CanWrite Then err.Raise 1, , "You are not authorized  
to write data to this server" End If
```

CanWrite Property (Messages Object)

Returns whether the current user is authorized to write messages to the Server.

Syntax

```
object.CanWrite
```

Parameters

None

Remarks

CanWrite is a read-only property of type Boolean.

Example

```
' Check Security If Not MyMessages.CanWrite Then err.Raise 1, , "You are not  
authorized to write data to this server" End If
```

CollectionDisabled Property (Tag Object)

Gets or sets whether the collection status of this tag.

Syntax

```
object.CollectionDisabled[ = Boolean]
```

Parameters

None

CollectionDisabled Property (TagFields Object)

Determines whether the CollectionDisabled field should be returned in the TagRecordset query.

Syntax

```
object.CollectionDisabled[ = Boolean]
```

Parameters

None

CollectionDisabledUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectionDisabledUpdated[ = Boolean]
```

Parameters

None

CollectionInterval Property (Tag Object)

Returns or sets the collection interval (in milliseconds) for a Tag. For polled collection, the interval schedules evenly spaced samples of the data from the data source. For unsolicited collection, the collection interval establishes the MINIMUM time allowed in between reports of unsolicited values from the data source. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectionInterval[ = Long]
```

Parameters

None

CollectionInterval Property (TagCriteria Object)

Sets the collection interval to search for in the TagRecordset Query.

Syntax

```
object.CollectionInterval[ = Long]
```

Parameters

None

CollectionInterval Property (TagFields Object)

Determines whether the TagRecordset query returns the CollectionInterval field.

Syntax

```
object.CollectionInterval[ = Boolean]
```

Parameters

None

CollectionIntervalSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectionIntervalSet[ = Boolean]
```

Parameters

None

CollectionIntervalUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectionIntervalUpdated[ = Boolean]
```

Parameters

None

CollectionOffset Property (Tag Object)

Returns or sets the collection offset (in milliseconds) for a tag. The collection offset only applies to polled type collection as used to schedule sampling of data at a specific time of day. The collection offset is applied from midnight to determine the time of the first sample. The collection interval is then used to schedule subsequent samples.

For example, with a collection interval of 60,000ms and a collection offset of 30,000ms, data would be collected one per minute on the half minute. To collect data once per day at a specific time, the collection interval should be set to one day, $1440 * 60 * 1000 = 86,400,000\text{ms}$, and the collection offset should be set to the time in milliseconds from midnight (for example, 6am = $6 * 3600 * 1000 = 21,600,000\text{ ms}$).

Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectionOffset[ = Long]
```

Parameters

None

CollectionOffset Property (TagCriteria Object)

Sets the collection offset to search for in the TagRecordset query.

Syntax

```
object.CollectionOffset[ = Long]
```

Parameters

None

CollectionOffset Property (TagFields Object)

Sets Determines whether the TagRecordset query returns the CollectionOffset field.

Syntax

```
object.CollectionOffset[ = Boolean]
```

Parameters

None

CollectionOffsetSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectionOffset[ = Boolean]
```

Parameters

None

CollectionOffsetUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectionOffsetupdated[ = Boolean]
```

Parameters

None

CollectionType Property (Tag Object)

Returns or sets the type of collection used to acquire data for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

The following table lists the available types of collection:

Name	Description	Value
Unsolicited	New values are reported by the source.	1
Polled	New values are polled from the source.	2

Syntax

```
object.CollectionType[ = ihCollectionType]
```

Parameters

None

CollectionType Property (TagCriteria Object)

Sets the collection type to search for in the TagRecordset query.

Syntax

```
object.CollectionType[ = ihCollectionType]
```

Parameters

None

CollectionType Property (TagFields Object)

Determines whether the TagRecordset query returns the CollectionType field.

Syntax

```
object.CollectionType[ = Boolean]
```

Parameters

None

CollectionTypeList Property (Tags Object)

Returns a list of the valid Collection types available in Historian.

Syntax

```
object.CollectionTypeList
```

Parameters

None

CollectionTypeSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectionTypeSet[ = Boolean]
```

Parameters

None

CollectionTypeUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectionTypeUpdated[ = Boolean]
```

Parameters

None

CollectorCompression Property (Tag Object)

Returns or sets whether collector compression is enabled for the Tag. Specify the deadband in the CollectorDeadbandPercentRange property.

Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectorCompression[ = Boolean]
```

Parameters

None

CollectorCompression Property (TagCriteria Object)

Sets the collector compression status to search for in the TagRecordset query.

Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectorCompression[ = Boolean]
```

Parameters

None

CollectorCompression Property (TagFields Object)

Determines whether the TagRecordset query returns the CollectorCompression field.

Syntax

```
object.CollectorCompression[ = Boolean]
```

Parameters

None

CollectorCompressionSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorCompressionSet[ = Boolean]
```

Parameters

None

CollectorCompressionTimeout Property (Tag Object)

Gets or sets the value of the Collector Compression Timeout. This is the amount of time after which a value will be sent to the Archiver regardless of compression.

Syntax

```
object.CollectorCompressionTimeout[ = Long]
```

Parameters

None

CollectorCompressionTimeout Property (TagCriteria Object)

Sets the Collector Compression Timeout value to search for in the TagRecordset query.

Syntax

```
object.CollectorCompressionTimeout[ = Long]
```

Parameters

None

CollectorCompressionTimeout Property (TagFields Object)

Determines whether the TagRecordset query returns the CollectorCompressionTimeout field.

Syntax

```
object.CollectorCompressionTimeout[ = Boolean]
```

Parameters

None

CollectorCompressionTimeoutSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorCompressionTimeoutSet[ = Boolean]
```

Parameters

None

CollectorCompressionTimeoutUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorCompressionTimeoutUpdated[ = Boolean]
```

Parameters

None

CollectorCompressionUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorCompressionTimeoutUpdated[ = Boolean]
```

Parameters

None

CollectorCompressionUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorCompressionTimeoutUpdated[ = Boolean]
```

Parameters

None

CollectorConditionEventList Property (OPCFilters Object)

Returns a list of the Condition Event Categories available for filtering on the Alarm Collector.

Syntax

```
object.CollectorConditionEventList
```

Parameters

None

CollectorDeadbandPercentRange Property (Tag Object)

Returns or sets the deadband in percent of engineering unit range for collector compression for the Tag. You must enable CollectorCompression before setting the CollectorDeadbandPercentRange.

Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectorDeadbandPercentRange[ = Single]
```

Parameters

None

CollectorDeadbandPercentRange Property (TagCriteria Object)

Sets the collector compression deadband to search for in the TagRecordset query.

Syntax

```
object.CollectorDeadbandPercentRange[ = Single]
```

Parameters

None

CollectorDeadbandPercentRange Property (TagFields Object)

Determines whether the TagRecordset query returns the CollectorDeadbandPercentRange field.

Syntax

```
object.CollectorDeadbandPercentRange[ = Boolean]
```

Parameters

None

CollectorDeadbandPercentRangeSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorDeadbandPercentRangeSet[ = Boolean]
```

Parameters

None

CollectorDeadbandPercentRangeUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorDeadbandPercentRangeUpdated[ = Boolean]
```

Parameters

None

CollectorGeneral1 Property (Tag Object)

Returns or sets the general1 (or spare) configuration field for the tag. Changes to tag properties are not committed until the WriteRecordset method of the TagRecordset object is called.

Syntax

```
object.CollectorGeneral1[ = String]
```

Parameters

None

Example

```
MyTag.CollectorGeneral1 = "Model2:123"
```

CollectorGeneral1 Property (TagCriteria Object)

Sets the general1 (spare) field value to search for in the TagRecordset query.

Syntax

```
object.CollectorGeneral1[ = String]
```

Parameters

None

Example

```
With MyRecordset.Criteria .TagName = "*.F_CV" .CollectorGeneral1 = "Model" End With
```

CollectorGeneral1 Property (TagFields Object)

Determines whether the CollectorGeneral1 field should be returned in the TagRecordset query.

Syntax

```
object.CollectorGeneral1[ = Boolean]
```

Parameters

None

Example

```
With MyRecordset.Fields .Clear .TagName = True .Description = True .CollectorGeneral1  
= True .CollectorGeneral2 = True .CollectorGeneral3 = True .CollectorGeneral4 =  
True .CollectorGeneral5 = True End With
```

CollectorGeneral1Set Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorGeneral1Set[ = Boolean]
```

Parameters

None

CollectorGeneral1Updated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorGeneral1Updated[ = Boolean]
```

Parameters

None

CollectorGeneral2 Property (Tag Object)

Returns or sets the general2 (or spare) configuration field for the tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectorGeneral2[ = String]
```

Parameters

None

CollectorGeneral2 Property (Tagcriteria Object)

Sets the general2 (spare) field value to search for in the TagRecordset query.

Syntax

```
object.CollectorGeneral2[ = String]
```

Parameters

None

CollectorGeneral2 Property (TagFields Object)

Determines whether the CollectorGeneral2 field should be returned in the TagRecordset query.

Syntax

```
object.CollectorGeneral2[ = Boolean]
```

Parameters

None

Example

```
With MyRecordset.Fields .Clear .TagName = True .Description = True .CollectorGeneral1 =
True .CollectorGeneral2 = True
.CollectorGeneral3 = True .CollectorGeneral4 = True .CollectorGeneral5 = True End With
```

CollectorGeneral2Set Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorGeneral2[ = Boolean]
```

Parameters

None

CollectorGeneral2Updated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorGeneral2Updated[ = Boolean]
```

Parameters

None

CollectorGeneral3Updated Property (Tag Object)

Returns or sets the general3 (or spare) configuration field for the tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectorGeneral3[ = String]
```

Parameters

None

CollectorGeneral3 Property (TagCriteria Object)

Sets the general3 (spare) field value to search for in the TagRecordset query.

Syntax

```
object.CollectorGeneral3[ = String]
```

Parameters

None

CollectorGeneral3 Property (TagFields Object)

Determines whether the CollectorGeneral3 field should be returned in the TagRecordset query.

Syntax

```
object.CollectorGeneral3[ = Boolean]
```

Parameters

None

Example

```
With MyRecordset.Fields .Clear .TagName = True .Description = True .CollectorGeneral1 = True  
.CollectorGeneral2 = True .CollectorGeneral3 = True .CollectorGeneral4 = True .CollectorGeneral5 = True  
End With
```

CollectorGeneral3Set Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorGeneral3Set[ = Boolean]
```

Parameters

None

CollectorGeneral3Updated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorGeneral3Updated[ = Boolean]
```

Parameters

None

CollectorGeneral4 Property (Tag Object)

Returns or sets the general4 (or spare) configuration field for the tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectorGeneral4[ = String]
```

Parameters

None

CollectorGeneral4 Property (TagCriteria Object)

Sets the general4 (spare) field value to search for in the TagRecordset query.

Syntax

```
object.CollectorGeneral4[ = String]
```

Parameters

None

CollectorGeneral4 Property (TagFields Object)

Determines whether the CollectorGeneral4 field should be returned in the TagRecordset query.

Syntax

```
object.CollectorGeneral4[ = Boolean]
```

Parameters

None

Example

```
With MyRecordset.Fields .Clear .TagName = True .Description = True .CollectorGeneral1 = True  
.CollectorGeneral2 = True .CollectorGeneral3 = True .CollectorGeneral4 = True .CollectorGeneral5 = True  
End With
```

CollectorGeneral4Set Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorGeneral4Set[ = Boolean]
```

Parameters

None

CollectorGeneral4Updated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorGeneral4Updated[ = Boolean]
```

Parameters

None

CollectorGeneral5 Property (Tag Object)

Returns or sets the general5 (or spare) configuration field for the tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectorGeneral5[ = String]
```

Parameters

None

CollectorGeneral5 Property (TagCriteria Object)

Sets the general5 (spare) field value to search for in the TagRecordset query.

Syntax

```
object.CollectorGeneral5[ = String]
```

Parameters

None

CollectorGeneral5 Property (TagFields Object)

Determines whether the CollectorGeneral5 field should be returned in the TagRecordset query.

Syntax

```
object.CollectorGeneral5[ = Boolean]
```

Parameters

None

CollectorGeneral5Set Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorGeneral5Set[ = Boolean]
```

Parameters

None

CollectorName Property (Tag Object)

Returns or sets the name of the Collector responsible for collecting data for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectorName[ = String]
```

Parameters

None

CollectorName Property (TagFields Object)

Determines whether the CollectorName field should be returned in the TagRecordset query.

Syntax

```
object.CollectorName[ = Boolean]
```

Parameters

None

CollectorNameSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorNameSet[ = Boolean]
```

Parameters

None

CollectorNameUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.CollectorNameUpdated[ = Boolean]
```

Parameters

None

CollectorOptions Property (Collector Object)

Exposes the CollectorOptions collection to control the behavior of a specific collector.

The following table describes each of the options:

Table 269. Options

Option	Capability
CollectorCanBrowseSource	TRUE if the collector supports browse.
CollectorMaxMemoryBufferSize	Specifies the size in megabytes of the memory buffer assigned to the store and forward function.
Source Address	Yes
CollectorMaxDiskBufferSize	Specifies the minimum free disk space that must be available on the computer and cannot be used for store and forward function.

Table 269. Options (continued)

Option	Capability
CollectorRateOutputAddress	Specifies the address in the source database into which the collector will write the current value of the events per minute output.
CollectorStatusOutputAddress	Specifies the address in the source database into which the collector will write the current value of the collector status (running, stopped, unknown, etc.).
CollectorAdjustForTimeDifference	TRUE if you want to adjust collector timestamps to match the server clock.
CollectorStartDelay	A delay, in seconds, after collector startup before collection starts.
CollectorSourceTimesLocal	If you are using source timestamps, set this to TRUE if the source timestamps are in local time.
CollectorMakeTagChangesOnline	Set to TRUE if you want tag changes to take effect without restarting collector.

Syntax

object.**CollectorOptions**(OptionName) [= Variant]

Parameters

OptionName - Variant - The name of a collection

CollectorSimpleEventList Property (OPCFilters Object)

Returns a list of the Simple Event Categories available for filtering on the Alarm Collector.

Syntax

`object.CollectorSimpleEventList`

Parameters

None

CollectorSupportsAreaFiltering Property (OPCFilters Object)

Returns whether or not Area Filtering is supported by the Alarm Collector. This can only be determined if the collector is connected to the Alarm Server.

Syntax

```
object.CollectorSupportsAreaFiltering
```

Parameters

None

CollectorSupportsCategoryFiltering Property (OPCFilters Object)

Returns whether or not Category Filtering is supported by the Alarm Collector. This can only be determined if the collector is connected to the Alarm Server.

Syntax

```
object.CollectorSupportsCategoryFiltering
```

Parameters

None

CollectorSupportsCategoryFiltering Property (OPCFilters Object)

Returns whether or not Category Filtering is supported by the Alarm Collector. This can only be determined if the collector is connected to the Alarm Server.

Syntax

```
object.CollectorSupportsCategoryFiltering
```

Parameters

None

CollectorSupportsEventFiltering Property (OPCFilters Object)

Returns whether or not Event Filtering is supported by the Alarm Collector. This can only be determined if the collector is connected to the Alarm Server.

Syntax

```
object.CollectorSupportsEventFiltering
```

Parameters

None

CollectorSupportsSeverityFiltering Property (OPCFilters Object)

Returns whether or not Severity Filtering is supported by the Alarm Collector. This can only be determined if the collector is connected to the Alarm Server.

Syntax

```
object.CollectorSupportsSeverityFiltering
```

Parameters

None

CollectorSupportsSourceFiltering Property (OPCFilters Object)

Returns whether or not Source Filtering is supported by the Alarm Collector. This can only be determined if the collector is connected to the Alarm Server.

Syntax

```
object.CollectorSupportsSourceFiltering
```

Parameters

None

CollectorTrackingEventList Property (OPCFilters Object)

Returns a list of the Tracking Event Categories available for filtering on the Alarm Collector.

Syntax

```
object.CollectorTrackingEventList
```

Parameters

None

CollectorType Property (Collector Object)

Returns or sets Collector Type property for the Collector.

Syntax

```
object.CollectorType[ = String]
```

Parameters

None

Example

```
' Print Out The CollectorType configured for the collector  
Debug.Print MyCollector.CollectorType
```

CollectorType Property (Tag Object)

Returns or sets the type of Collector responsible for collecting data for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.CollectorType[ = String]
```

Parameters

None

CollectorType Property (TagCriteria Object)

Sets the collector type to search for in the TagRecordset query.

Syntax

```
object.CollectorType[ = String]
```

Parameters

None

CollectorType Property (TagFields Object)

Determines whether the CollectorType field should be returned in the TagRecordset query.

Syntax

```
object.CollectorType[ = Boolean]
```

Parameters

None

CollectorTypeList Property (Collectors Object)

Returns a list of Collector Types available. These types may be used in other SDK functions.

Syntax

object.**CollectorTypeList**

Parameters

None

Example

```
'Get a List of the Available Collector Types Dim ListArray As Variant Dim I As Integer
ListArray = MyCollectors.CollectorTypeList For I = LBound(ListArray) To UBound(ListArray)
Debug.Print "Historian has a " + ListArray(I, 2) + " collector" Next I
```

CollectorTypeSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object..**CollectorTypeSet**[= *Boolean*]

Parameters

None

CollectorTypeUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**CollectorTypeUpdated**[= *Boolean*]

Parameters

None

Examples

Body text goes here.

Column Header	Column Header
Table text	Table text

Column Header	Column Header
Table text	Press Tab to add rows.

CollectorVersion Property (Collector Object)

Returns the collector version. This version information is available for collectors of version 5.0 and later

Syntax

```
Object.CollectorVersion
```

Parameters

None

Sample Code

```
Public ConnectedServer As iHistorian_SDK.Server

Dim MyCollector As iHistorian_SDK.Collector

Dim CollectorName As String

Dim ServerName As String

Private Sub BTNGetVersion_Click()

On Error GoTo errc

    If Not ConnectedServer Is Nothing Then

        ConnectedServer.Disconnect

        Set ConnectedServer = Nothing

        Set ConnectedServer = CreateObject("iHistorian_SDK.Server")

    Else

        Set ConnectedServer = CreateObject("iHistorian_SDK.Server")

    End If

    If Not ConnectedServer.Connect(ServerName, "", "") Then

        MsgBox "Connect To Server: " + ServerName + " Failed."

    Else

        Set MyCollector = ConnectedServer.Collectors.Item(CollectorName)

        If MyCollector.Running = True Then

            MsgBox "Collector version: " + MyCollector.CollectorVersion

        Else

            MsgBox "Collector version: Unknown"

        End If

    End If

End Sub
```

```
End If  
Exit Sub  
errc:  
    MsgBox Err.Number  
End Sub
```

Comment Property (Collector Object)

Returns or sets the Comment property for this collector.

Syntax

object.**Comment**[= *String*]

Parameters

None

Comment Property (DataComments Object)

Returns the comment associated with the DataValue.

Syntax

object.**Comment**

Parameters

None

Remarks

Comment is a read-only property of type Variant.

Comment Property (Tag Object)

Returns or sets the comment associated with the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**Comment**[= *String*]

Parameters

None

Comment Property (TagCriteria Object)

Sets the comment to search for in the TagRecordset query.

Syntax

object.**Comment**[= *String*]

Parameters

None

Comment Property (TagFields Object)

Determines whether the Comment field should be returned in the TagRecordset query.

Syntax

object.**Comment**[= *Boolean*]

Parameters

None

CommentSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**CommentSet**[= *Boolean*]

Parameters

None

CommentTimestamp Property (DataComments Object)

Returns the time that the comment was added to the archive.

Syntax

object.**CommentTimestamp**

Parameters

None

Remarks

CommentTimestamp is a read-only property of type Date.

Example

```
Debug.Print "Comment added at: " + _ Format$(MyValue.Comme
```

CommentSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**CommentSet**[= *Boolean*]

Parameters

None

CommentUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**CommentUpdated**[= *Boolean*]

Parameters

None

Comments Property (DataFields Object)

Determines whether the Comments field should be returned in the DataRecordset query.

Syntax

object.**Comments**[= *Boolean*]

Parameters

None

Comments Property (DataValue Object)

Returns the collection of comments that applies to the DataValue.

Syntax

object.**Comments**

Parameters

None

Remarks

Comments is a read-only property of type Collection.

CommentsUpdated Property (DataValue Object)

This property is for internal use only.

Syntax

object.**CommentsUpdated**

Parameters

None

ComputerName Property (Collector Object)

Returns or sets the name of the computer that the collector executes on.

Syntax

object.**ComputerName**[= *String*]

Parameters

None

Remarks

ComputerName is a read-only property of type String.

ConditionCollectionCompareValue Property

Returns or Contains compare value against the value of the triggertag.

Syntax

object.**ConditionCollectionCompareValue** [= *String*]

Parameters

None

ConditionCollectionCompareValue Property

Returns or Contains compare value against the value of the trigger tag.

Syntax

object.**ConditionCollectionCompareValue** [= String]

Parameters

None

ConditionCollectionComparison Property

Contains the condition collection for a tag.

Syntax

object.**ConditionCollectionComparison** [= Enum]

Parameters

None

ConditionCollectionEnabled Property

Sets the condition collection for a tag.

Syntax

object.**ConditionCollectionEnabled** [= Boolean]

Parameters

None

ConditionCollectionMarkers Property

Returns or Sets if the end of the markers to be stored when the condition becomes FALSE. If FALSE, a bad data marker is not inserted when the condition becomes false.

Syntax

object.**ConditionCollectionMarkers** [= Boolean]

Parameters

None

ConditionCollectionTriggertag Property

Contains a trigger tag from the list of tags associated with the collector.

Syntax

object.**ConditionCollectionTriggertag** [= String]

Parameters

None

Connected Property (Server Object)

Returns the authentication status of the current server connection. True means you are connected to the server.

Syntax

object.**Connected**

Parameters

None

Remarks

Connected is a read-only property of type Boolean.

ConnectionOptions Property (Server Object)

Returns the collection of options for the current connection. To set individual options refer to the following table.

TimeOption	Converts timestamps to and from the local time zone	String = Local
	Converts timestamps to and from the server time zone.	String = Server
	Converts Timestamps To/From Explicit. The time-zone is specified in the TimeZoneBias option.	String = Explicit

TimeOption	Converts timestamps to and from the local time zone	String = Local
TimeZoneBias	Converts timestamps to and from a specific offset from GMT (minutes)	Long
AdjustDayLightSavings	Converts timestamps by adjusting for daylight savings	Boolean

Syntax

object.**ConnectionOptions**(OptionName) [*= Variant*]

Parameters

Name	Data Type	Description
OptionName	Variant	The name of a connection option

None

Remarks

ConnectionOptions is a read-only property of type Collection of Options.

Count Property (TagDependencies Object)

This function returns the current number of Dependent Tags configured.

Syntax

object.**Count**

Parameters

None

Count Property (DataStores Object)

Gets the number of items in the collection.

Syntax

object.**Count**

Parameters

None

Remarks

Count is a read-only property of type Collection.

Count Property (EnumeratedStates Object)

Returns the number of items in the EnumeratedStates collection.

Syntax

object.**Count**

Parameters

None

Remarks

Long

Criteria Property (DataRecordset Object)

Returns the Criteria object used to identify which DataValues the Historian server returns when a DataRecordset query is executed.

The following procedure describes the steps involved in specifying criteria of a DataRecordset Query.

1. Specify the sampling mode.

A sampling mode must be set to determine how values are retrieved from the Historian archive. Depending on the sampling mode, you may also need to modify the Direction and NumberOfSamples. The following table lists the available Sampling Modes and their explanations.

Name	Description	Value
CurrentValue	Retrieves the current value. The time frame criteria are ignored.	1
Interpolated	Retrieves evenly spaced interpolated values based on NumberOfSamples and the time frame criteria.	2

Name	Description	Value
Trend	Retrieves the raw minimum and raw maximum value for each specified interval. Use the Trend sampling mode to maximize performance when retrieving data points for plotting. A start time, end time, and an interval or number of samples must be specified.	3
RawByTime	Retrieves raw archive values (compressed) based on time frame criteria.	4
RawByNumber	Retrieves raw archive values (compressed) based on the StartTime criteria, the NumberOfSamples, and Direction criteria. NOTE: The EndTime criteria is ignored for this Sampling mode.	5
Calculated	Retrieves evenly spaced calculated values based on NumberOfSamples, the time frame criteria, and the CalculationMode criteria.	6

2. Supply tags for query. You can specify tags in one of two ways:
 - a. Supply a Tagmask that searches for all tags that match the mask and apply the remaining criteria to retrieve data. The mask can include wildcards.
 - b. Supply an array of strings representing the list of tags to retrieve data for by using the Tags() property of the DataCriteria object.

- a. Supply time frame for query.

To supply a time frame for the query, set the StartTime and EndTime properties or set the StartTimeShortcut and EndTimeShortcut properties.

3. Specify the Calculation Mode.

For the calculated SamplingMode, you must also specify the Calculation Mode.

The following table describes the available calculation modes.

Table 270. Enumeration: ihCalculationMode

Name	Description	Value
Equal	Filter condition is True, when the FilterTag is equal to the comparison value.	1
NotEqual	Filter condition is True, when the FilterTag is NOT equal to the comparison value.	2
LessThan	Filter condition is True, when the FilterTag is less than the comparison value.	3
GreaterThan	Filter condition is True, when the FilterTag is greater than the comparison value.	4
LessThanEqual	Filter condition is True, when the FilterTag is less than or equal to the comparison value.	5
GreaterThanEqual	Filter condition is True, when the FilterTag is greater than or equal to the comparison value.	6

The filter eliminates archive data from retrieval or calculations that occur within the time period that the specified filter criterion is True. FilterMode determines exactly how changes in state of the FilterTag are interpreted for retrieval of data.

Name	Description	Value
ExactTime	Retrieves data for the exact times that the filter condition is True.	1
BeforeTime	Retrieves data from the time of the last False filter condition up to the time of the True condition.	2

Name	Description	Value
AfterTime	Retrieves data from the time of the True filter condition up to the time of next False condition.	3
BeforeAndAfterTime	Retrieves data from the time of the last False filter condition up to the time of next False condition.	4

Syntax

object.**Count**

Parameters

None

Remarks

Criteria is a read-only property of type DataCriteria.

Criteria Property (MessageRecordset Object)

Use this property to specify which Messages to return from the Historian server when a MessageRecordset query executes.

A Topic may be optionally supplied to limit the Message queries to specific message topics. The following table provides a list of message topics.

Name	Description	Value
Connections	Provides messages about client connections.	1
Security	Provides messages and alerts about login attempts and attempts to access restricted resources.	2
ConfigurationAudit	Provides messages about configuration changes and audit trail.	3
ServiceControl	Provides messages and alerts regarding startup and shutdown of the system and specific services.	4

Name	Description	Value
Performance	Provides messages and alerts regarding system and archive performance.	5

You can also optionally supply a time frame for the query. To do this, either set the StartTime and EndTime properties or set the StartTimeShortcut and EndTimeShortcut properties, or a combination of both.

All other fields of the MessageCriteria are evaluated by exact match if set.

Syntax

object.**Criteria**

Parameters

None

Remarks

Criteria is a read-only property of type MessageCriteria.

Criteria Property (TagRecordset Object)

Use this property to specify which Tags to return from the Historian server when a TagRecordset query is executed.

You can supply the Tagname and Description as a mask including wildcards to return all matching tags. All other fields of the TagCriteria object are tested for exact match if they are supplied or set.

Syntax

object.**Criteria**

Parameters

None

Remarks

Criteria is a read-only property of type TagCriteria.

CurrentValue Property (Tag Object)

Returns the current value of the Tag as a DataValue object. The DataValue object contains properties for the Value, TimeStamp, and DataQuality of the current value.

Syntax

object.**CurrentValue**

Parameters

None

Remarks

CurrentValue is a read-only property of type DataValue.

D**Data Property (Server Object)**

Returns the Data object for the current server. Use the Data object to build queries for collected data.

Syntax

object.**Data**

Parameters

None

DataStores Property (Server Object)

Returns the collection of the available data stores.

Syntax

object.**DataStores**

Parameters

None

Remarks

DataStores

DataQuality Property (DataFields Object)

Determines whether the DataQuality field should be returned in the DataRecordset query.

Syntax

object.**DataQuality**[= *Boolean*]

Parameters

None

DataQuality Property (DataValue Object)

Returns or sets the quality of the DataValue.

The table below defines the possible values for DataQuality:

Name	Data Type	Description
Good	The quality of the value is GOOD.	1
Bad	The quality of the value is BAD.	2
Unknown	The quality of the value is UNKNOWN.	3

Syntax

object.**DataQuality**[= *ihDataQuality*]

Parameters

None

DataQualityUpdated Property (DataValue Object)

This property is for internal use only.

Syntax

object.**DataQualityUpdated**[= *Boolean*]

Parameters

None

DataStore Property (Archive Object)

Returns the data store name of the specified Archive.

Syntax

object.DataStore

Parameters

None

Remarks

String

DataQualityUpdated Property (DataValue Object)

This property is for internal use only.

Syntax

object.DataQualityUpdated[= *Boolean*]

Parameters

None

DataTimestamp Property (DataComments Object)

Returns the timestamp of the DataValue the comment is associated with.

Syntax

object.DataTimestamp

Parameters

None

Remarks

DataTimeStamp is a read-only property of type Date.

Example

```
Debug.Print "Commented point at: " + _ Format$(MyValue.Com
```

DataType Property (DataComments Object)

Returns the data type of the associated data.

Syntax

object.**DataType**

Parameters

None

DataType Property (Tag Object)

Returns or sets the data type of the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

The table below lists the available data types.

Name	Description	Value
Scaled	Tag scaled between high engineering units and low engineering units.	1
Float	Tag stored as single precision floating point.	2
DoubleFloat	Tag stored as double precision floating point.	3
Integer	Tag stored as 2-byte integer.	4
DoubleInteger	Tag stored as 4-byte integer.	5
FixedString	Tag stored as fixed length UNICODE string.	6
VariableString	Tag stored as variable length UNICODE string.	7
Blob	Tag stored as binary large object.	8

Syntax

object.**DataType**[= *ihDataType*]

Parameters

None

DataType Property (DataComments Object)

Sets the data type to search for in the TagRecordset query.

Syntax

object.**DataType**[= *ihDataType*]

Parameters

None

DataType Property (TagFields Object)

Determines whether the DataType field should be returned in the TagRecordset query.

Syntax

object.**DataType** = *Boolean*

Parameters

None

DataTypeList Property (Tags Object)

Returns the list of Historian data types.

Syntax

object.**DataTypeList**

Parameters

None

Remarks

DataTypeList is a read-only property of type Variant.

DataTypeSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**DataTypeSet**[= *Boolean*]

Parameters

None

DataTypeUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**DataTypeUpdated**[= *Boolean*]

Parameters

None

DefaultCollectionInterval Property (Collector Object)

Returns or sets the Default Collection Interval property for the Collector.

Syntax

object.**DefaultCollectionInterval**[= *Long*]

Parameters

None

Example ' Print Out The DefaultCollectionInterval configured for the collector Debug.Print

DefaultCollectionInterval Property (Collector Object)

Returns or sets the Default Collection Interval property for the Collector.

Syntax

object.**DefaultCollectionInterval**[= *Long*]

Parameters

None

Example

```
' Print Out The DefaultCollectionInterval configured for the collector Debug.Print
```

DefaultCollectionType Property (Collector Object)

Returns or sets the Default Collection Type for the given collector. This can be either Polled or Solicited.

Syntax

```
object.DefaultCollectionType[ = iHistorian_SDK.ihCollectionType]
```

Parameters

None

Example

```
' Print Out The DefaultCollectionType configured for the collectorDebug.Print
MyCollector.DefaultCollectorAbsoluteDeadband
```

DefaultCollectorAbsoluteDeadbanding Property (Collector Object)

Returns or sets the Default Collector Absolute Deadbanding for the Collector. This specifies if the compression applied to newly added tags from the collector use absolute or relative compression.

Syntax

```
object.DefaultCollectorAbsoluteDeadbanding[ = Boolean]
```

Parameters

None

Example

```
' Print Out The DefaultCollectorAbsoluteDeadbanding configured for the collector DebugPr
```

DefaultCollectorCompression Property (Collector Object)

Returns or sets whether the collector uses Compression by default.

Syntax

```
object.DefaultCollectorCompression[ = Boolean]
```

Parameters

None

Example

```
' Print Out The DefaultCollectorCompression configured for the collector Debug.Print MyColl
```

DefaultCollectorCompressionDeadband Property (Collector Object)

Returns or sets the Default Collector Compression Deadband for the given collector. This is default compression value to be applied to newly added tags from the collector.

Syntax

object.**DefaultCollectorCompressionDeadband**[= *Single*]

Parameters

None

Example

```
' Print Out The DefaultCollectorCompressionDeadband configured for the collector Debug.Print MyC
```

DefaultCollectorCompressionTimeout Property (Collector Object)

Returns or sets the Default Collector Compression Timeout for the Collector. This specifies the amount of time after which a value will be sent to the archiver by the collector even if it would have been compressed.

Syntax

object.**DefaultCollectorCompressionTimeout**[= *Long*]

Parameters

None

Example

```
' Print Out The DefaultCollectorCompressionTimeout configured for the collector Debug
```

DefaultLoadBalancing Property (Collector Object)

Returns or sets whether the collector uses Load Balancing by default.

Syntax

object.**DefaultLoadBalancing**[= *Boolean*]

Parameters

None

Example

```
' Print Out The DefaultLoadBalancing configured for the collector Debug.Print MyCo
```

DefaultServer Property (ServerManager Object)

Returns or sets a reference to the default Server Object.

Syntax

object.**DefaultServer**

Parameters

None

DefaultSpikeInterval Property (Collector Object)

Returns or sets the Default Spike Interval property for the Collector.

Syntax

object.**DefaultSpikeInterval**[= *Long*]

Parameters

None

Example

```
' Print Out The DefaultSpikeInterval configured for the collector Debug.Print  
MyCollector.DefaultSpikeInter
```

DefaultSpikeLogic Property (Collector Object)

Returns or sets the Default Collector Spike Logic property for the Collector.

Syntax

object.**DefaultSpikeLogic**[= *Boolean*]

Parameters

None

Example

```
' Print Out The DefaultSpikeLogic configured for the collector Debug.Print  
MyCollector.DefaultSpikeLogic
```

DefaultSpikeMultiplier Property (Collector Object)

Returns or sets the Default Spike Multiplier property for the Collector.

Syntax

object.**DefaultSpikeMultiplier**[= *Double*]

Parameters

None

Example

```
' Print Out The DefaultSpikeMultiplier configured for the collector Debug.Pri
```

DefaultTagPrefix Property (Collector Object)

Returns or sets the Default Tag Prefix property for the Collector.

Syntax

object.**DefaultTagPrefix**[= *String*]

Parameters

None

Example

```
' Print Out The DefaultTagPrefix configured for the collector Debug
```

DefaultTimestampType Property (Collector Object)

Returns or sets the Default Timestamp Type for the given collector. The Timestamps may be assigned by either the Data Source or the Collector itself.

Syntax

object.**DefaultTimestampType**[= *iHistorian_SDK.ihTimeStampType*]

Parameters

None

Example

```
' Print Out The DefaultTimestampType configured for the collector Debug.Print  
  
MyCollector.DefaultTimestampType
```

Definition Property (UserCalcFunction Object)

Returns the definition of the specified UserCalcFunction.

Syntax

object.**Definition**[= *String*]

Parameters

None

Description Property (Collector Object)

Returns or sets the description for the given collector.

Syntax

```
object.Description[ = String]
```

Parameters

None

Example

```
' Print Out The Description configured for the collector Debug.P
```

Description Property (EnumeratedSets Object)

Returns or sets the description or comments for an enumerated set.

Syntax

```
object.Description
```

Parameters

None

Returns

String

Description Property (EnumeratedState Object)

Returns or defines the description or comments for a state.

Syntax

```
object.Description
```

Parameters

None

Remarks

String. Returns the description or comments for each state.

Description Property (Tag Object)

Returns or sets the description of the Tag. Changes to tag Properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**Description**[= *String*]

Parameters

None

Description Property (TagCriteria Object)

Sets the description or description mask to search for in the TagRecordset query. The description may include wildcard characters.

Syntax

object.**Description**[= *String*]

Parameters

None

Description Property (TagFields Object)

Determines whether the Description field should be returned in the TagRecordset query.

Syntax

object.**Description**[= *Boolean*]

Parameters

None

Description Property (UserDefinedTypeFields Object)

Returns or sets the description or comments for a field in a User Defined Type.

Syntax

object.**Description**

Parameters

None

Returns

String

DescriptionSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.DescriptionSet[ = Boolean]
```

Parameters

None

DescriptionUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.DescriptionUpdated[ = Boolean]
```

Parameters

None

Direction Property (DataCriteria Object)

Sets the direction (forward or backward) of sampling data from the archive by the DataRecordset query. This parameter is only used for "RawByNumber" Sampling Mode.

The following table details the available sampling directions.

Name	Description	Value
Forward	Data sampled from the start time forward in time.	1
Backward	Data sampled from the start time backwards in time.	2

Syntax

```
object.Direction[ = iHistorian_SDK.ihSamplingDirection]
```

Parameters

None

DirectionSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**DescriptionSet**[= *Boolean*]

Parameters

None

Property Reference E-F

EndTime Property (Archive Object)

Returns the end time of the specified archive. This represents the latest timestamp for any tag contained in the archive.

Syntax

object.**EndTime**

Parameters

None

Remarks

EndTime is a read-only property of type Date.

EndTime Property (DataCriteria Object)

Returns or sets the end of the time range to retrieve data for in the DataRecordset query.

Syntax

object.**EndTime**[= *Date*]

Parameters

None

EndTime Property (MessageCriteria Object)

Establishes the end time of the MessageRecordset query.

Syntax

object.**EndTime**[= *Date*]

Parameters

None

EndTimeSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**EndTimeSet**[= *Boolean*]

Parameters

None

EndTimeSet Property (MessageCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**EndTimeSet**[= *Boolean*]

Parameters

None

EndTimeShortcut Property (DataCriteria Object)

Returns or sets the end of the time range to retrieve data for in the DataRecordset query. Shortcuts are strings that define absolute or relative times. The time shortcuts are the following:

Value	Description
(N)ow	The current time (absolute).
(T)oday	Today at midnight (absolute).
(Y)esterday	Yesterday at midnight (absolute).
(D)ays	Number of Days (relative).

Value	Description
(M)in	Number of Minutes (relative).
(H)our	Number of Hours (relative).
(W)EEK	Number of Weeks (relative).
(BOM)	Beginning of this month at Midnight (absolute).
(EOM)	Last Day of this month at Midnight (absolute).
(BOY)	First Day of this year at Midnight (absolute).
(EOY)	Last Day of this year at Midnight (absolute).

Syntax

object.**EndTimeShortcut**[= String]

Parameters

None

Example

```
With MyRecordset.Criteria .Tagmask = "*.F_CV" ' Start two days Ago at 8am in the morning
.StartTimeShortcut = "Today-2d+8h" ' End this morning at 8am .EndTimeShortcut = "Today+8h" End With
```

EndTimeShortcut Property (MessageCriteria Object)

Establishes the end time of the MessageRecordset query by specifying a time shortcut string versus a date. The time shortcuts are the following:

Value	Description
(N)ow	The current time (absolute).
(T)oday	Today at midnight (absolute).
(Y)esterday	Yesterday at midnight (absolute).
(D)ays	Number of Days (relative).
(M)in	Number of Minutes (relative).
(H)our	Number of Hours (relative).
(W)EEK	Number of Weeks (relative).

Value	Description
(BOM)	Beginning of this month at Midnight (absolute).
(EOM)	Last Day of this month at Midnight (absolute).
(BOY)	First Day of this year at Midnight (absolute).
(EOY)	Last Day of this year at Midnight (absolute).

Syntax

object.**EndTimeShortcut**[= *String*]

Parameters

None

Example

```
' Set A End Time For Now MyMessages.Criteria.EndTimeShortcut = "Now"
```

EndTimeShortcutSet Property (MessageCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**EndTimeShortcutSet**[= *Boolean*]

Parameters

None

EngineeringUnits Property (Tag Object)>

Returns or sets the engineering unit description of the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**EngineeringUnits**[= *String*]

Parameters

None

EngineeringUnits Property (TagCriteria Object)

Sets the engineering unit description to search for in the TagRecordset query.

Syntax

object.**EngineeringUnits**[= *String*]

Parameters

None

EngineeringUnits Property (TagFields Object)

Determines whether the EngineeringUnits field should be returned in the TagRecordset query.

Syntax

object.**EngineeringUnits**[= *Boolean*]

Parameters

None

EngineeringUnitsSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**EngineeringUnits**[= *Boolean*]

Parameters

None

EngineeringUnitsUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**EngineeringUnitsUpdated**[= *Boolean*]

Parameters

None

ErrorList Property (Server Object)

Returns a collection of error messages accumulated during the current session of the Server object. Each message includes a timestamp indicating the time the error was generated and each includes an error message translated into the locale of the client, when possible.

Syntax

object.**ErrorList**

Parameters

None

Remarks

ErrorList is a read-only property of type Collection of String.

Example

```
ErrorTrap: Dim I As Long ' Loop through the ErrorList and print to the debug window
For I = 1 To MyServer.ErrorList.count Debug.Print MyServer.ErrorList(I) Next I
```

F**FailoverOnBadQuality Property (Collector Object)**

Returns or sets whether the collector should automatically failover when the watchdog tag quality goes to BAD.

Syntax

object.**FailoverOnBadQuality**[= *Boolean*]

Parameters

None

FailoverOnCollectorStatus Property (Collector Object)

Returns or sets whether the collector should automatically failover when the currently active collector status goes to UNKNOWN.

Syntax

object.**FailoverOnCollectorStatus**[= *Boolean*]

Parameters

None

FailoverOnNonZeroValue Property (Collector Object)

Returns or sets whether the collector should automatically failover when the watchdog tag value goes to non-zero.

Syntax

```
object.FailoverOnNonZeroValue[ = Boolean]
```

Parameters

None

FailoverOnValue Property (Collector Object)

Returns or sets whether the collector should automatically failover based on the value of the watchdog tag. Set the FailoverOnNonZeroValue property or FailoverOnValueUnchanged property to indicate the exact criteria.

Syntax

```
object.FailoverOnValue[ = Boolean]
```

Parameters

None

FailoverOnValueUnchanged Property (Collector Object)

Returns or sets whether the collector should automatically failover when the watchdog tag value remains unchanged. Use the WatchdogValueMaxUnchangedPeriod property to specify the time period.

Syntax

```
object.FailoverOnValueUnchanged[ = Boolean]
```

Parameters

None

Fields Property (DataRecordset Object)

Returns the DataFields object which contains the information on which fields are returned in the DataRecordSet

Syntax

object.**Fields**

Parameters

None

Fields Property (MessageRecordset Object)

Returns the Fields object that is used to identify which Message fields to return from the Historian server when a MessageRecordset query executes.

Syntax

object.**Fields**

Parameters

None

Remarks

Fields is a read-only property of type MessageFields.

Fields Property (TagRecordset Object)

Returns the Fields object that is used to identify which Tag fields to return from the Historian server when a TagRecordset query executes.

Syntax

object.**Fields**

Parameters

None

Remarks

Fields is a read-only property of type TagFields.

FileName Property (Archive Object)

Returns or sets the file name of the specified archive. The filename must be specified in the context of the Historian server drives and directories.

Changing the file name of an archive moves the archive from one file location to another.

Syntax

```
object.FileName[ = String]
```

Parameters

None

Example

```
Dim I As Long ' List The FileName and FileSize Of Each Archive With MyArchives
For I = 1 To .Item.count      Debug.Print .Item(I).Name, .Item(I).FileName, .Item(I).FileSizeCurrent
Next I End With ' Move The Archive To A New Directory,
Path Context Of Server On Error GoTo ErrorTrap MyArchive.FileName = NewArchiveFilename ErrorTrap:
Debug.Print "
```

FileSizeCurrent Property (Archive Object)

Returns the number of MB used in the specified archive file. This number is less than or equal to the file size on disk.

Changing the file name of an archive moves the archive from one file location to another.

Syntax

```
object.FileSizeCurrent
```

Parameters

None

Remarks

FileSizeCurrent is a read-only property of type Long.

Example

```
Dim I As Long ' List The FileName and FileSizeCurrent Of Each Archive With MyArchives
For I = 1 To .Item.count      Debug.Print .Item(I).Name, .Item(I).FileName, .Item(I).FileSizeCurrent
Next I End With
```

FileSizeTarget Property (Archive Object)

Returns or sets the target file size for the specified archive file in MB.

Syntax

```
object.FileSizeTarget[ = Long]
```

Parameters

None

Remarks

FileSizeCurrent is a read-only property of type Long.

Example

```
Debug.Print "Target File Size for archive " & MyArchive.FileSizeTarget
```

FilterComparisonMode Property (DataCriteria Object)

Returns or sets the type of comparison to be made on the FilterComparisonValue to apply appropriate filter to the DataRecordset query. If a FilterTag and FilterComparisonValue are supplied the query attempts to filter out time periods from the results where the filter condition is False. The FilterComparisonMode defines how archive values for the FilterTag should be compared to the FilterComparisonValue to establish the state of the filter condition.

The table below defines the available Filter Comparison Modes:

Value	Description	Value
Equal	Filter condition is True when the FilterTag is equal to the comparison value.	1
NotEqual	Filter condition is True when the FilterTag is NOT equal to the comparison value.	2
LessThan	Filter condition is True when the FilterTag is less than the comparison value.	3
GreaterThan	Filter condition is True when the FilterTag is greater than the comparison value.	4

Value	Description	Value
LessThanEqual	Filter condition is True when the FilterTag is less than or equal to the comparison value.	5
GreaterThanOrEqual	Filter condition is True when the FilterTag is greater than or equal to the comparison value.	6

Syntax

object.**FilterComparisonMode**[= *iHistorian_SDK.ihFilterComparisonMode*]

Parameters

None

FilterComparisonModeList Property (Data Object)

This function returns a list of the available Filter Comparison modes for a data request.

Syntax

object.**FilterComparisonModeList**

Parameters

None

FilterComparisonModeSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**FilterComparisonModeSet**[= *Boolean*]

Parameters

None

FilterComparisonValue Property (DataCriteria Object)

Sets the value to compare the filter tag with when applying the appropriate filter to the DataRecordset query.

Syntax

object.**FilterComparisonValue**[= *Variant*]

Parameters

None

FilterComparisonValue Property (DataCriteria Object)

Sets the value to compare the filter tag with when applying the appropriate filter to the DataRecordset query.

Syntax

object.**FilterComparisonValue**[= *Variant*]

Parameters

None

FilterComparisonValueSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**FilterComparisonValueSet**[= *Boolean*]

Parameters

None

FilterMode Property (DataCriteria Object)

Returns or sets the type of time filter applied to the DataRecordset query. If a FilterTag and FilterComparisonValue are supplied the query attempts to filter time periods from the results where the filter condition equals False. The FilterMode defines how time periods before and after transitions in the filter condition should be handled. For example, "AfterTime" indicates that the filter condition should be True starting at the timestamp of the archive value that triggered the True condition and leading up to the timestamp of the archive value that triggered the False condition.

Use the filter query to directly retrieve data for a particular lot number or batch of material. In this scenario, you must know whether the batch number was written into the archive at the beginning of the batch or at the end of the batch. If the batch number is written at the

beginning of the batch, use the "AfterTime" filter mode. If the batch number is written at the end of the batch, use the "BeforeTime" filter mode.

The table below defines the available Filter Modes:

Name	Description	Value
ExactTime	Retrieves data for the exact times that the filter condition is True.	1
BeforeTime	Retrieves data from the time of the last False filter condition up until the time of the True condition.	2
AfterTime	Retrieves data from the time of the True filter condition up until the time of next False condition	3
BeforeAndAfterTime	Retrieves data from the time of the last False filter condition up until the time of next False condition.	4

Syntax

object.**FilterMode**[= *iHistorian_SDK.ihFilterMode*]

Parameters

None

FilterModeList Property (Data Object)

This function returns a list of the available Filtering modes for a data request.

Syntax

object.**FilterModeList**

Parameters

None

FilterModeSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**FilterModeSet**[= *Boolean*]

Parameters

None

FilterTag Property (DataCriteria Object)

Returns or sets the tagname used to define the filter applied to the DataRecordset query. You can only specify a single tag (no wildcards).

Syntax

object.**FilterTag**[= *String*]

Parameters

None

FilterTagSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**FilterTagSet**[= *Boolean*]

Parameters

None

FullAreaNames Property (OPCBrowse Object)

Returns the fully-qualified area name for an AE server. When a browse operation occurs, the server returns all areas and sources under the BrowsePosition. The areas are akin to nodes (they can be set to the next browse position to traverse the tree). Sources are like leaves, and do not have children.

After a browse, the areas and leaves are populated in arrays, and the LeafName and AreaName properties allow you to access those arrays by index. The fully-qualified area name should be used to set the Browse Position. The Areanames property is used to display the individual areas.

Syntax

object.**FullAreaNames**(Index)

Parameters

Index - Integer - The index into the full area name array.

Remarks

FullAreaNames is a read-only String property returned as a variant for script compatibility.

FullLeafNames Property (OPCBrowse Object)

Returns the fully-qualified leaf name (source) for an AE server. When a browse operation occurs, the server returns all areas and sources under the BrowsePosition. The areas are akin to nodes (they can be set to the next browse position to traverse the tree). Sources are like leaves, and do not have children.

After a browse, the areas and leaves are populated in arrays, and the LeafName and AreaName properties allow you to access those arrays by index.

Syntax

object.**FullLeafNames**(Index)

Parameters

Index - Integer - The index into the full leaf name array.

Remarks

FullLeafNames is a read-only String property returned as a variant for script compatibility.

Property Reference G-H

G

General1 Property (Collector Object)

Returns or sets the general fields of the specified collector. The general fields control the behavior of specific collector types. Refer to the documentation of a specific collector type to interpret the meaning of the general collector fields for that collector type.

Syntax

object.**General1**[= *String*]

Parameters

None

Example

```
MyCollector.General1 = "CanUseOPTime=True"
```

General2 Property (Collector Object)

Returns or sets the general fields of the specified collector. The general fields control the behavior of specific collector types. Refer to the documentation of a specific collector type to interpret the meaning of the general collector fields for that collector type.

Syntax

```
object.General2[ = String]
```

Parameters

None

General3 Property (Collector Object)

Returns or sets the general fields of the specified collector. The general fields control the behavior of specific collector types. Refer to the documentation of a specific collector type to interpret the meaning of the general collector fields for that collector type.

Syntax

```
object.General3[ = String]
```

Parameters

None

General4 Property (Collector Object)

Returns or sets the general fields of the specified collector. The general fields control the behavior of specific collector types. Refer to the documentation of a specific collector type to interpret the meaning of the general collector fields for that collector type.

Syntax

```
object.General4[ = String]
```

Parameters

None

General5 Property (Collector Object)

Returns or sets the general fields of the specified collector. The general fields control the behavior of specific collector types. Refer to the documentation of a specific collector type to interpret the meaning of the general collector fields for that collector type.

Syntax

object.**General4**[= *String*]

Parameters

None

H

Handle Property (Server Object)

Returns the internal identifier for the current server.

Syntax

object.**Handle**

Parameters

None

Remarks

Handle is a read-only property of type Long.

HeartbeatOutputAddress Property (Collector Object)

Returns or sets the address in the data source that the collector sends heartbeat information to. The collector will write a 1 to this address once per minute.

Syntax

object.**HeartbeatOutputAddress**[= *String*]

Parameters

None

Example

```
'Print Out The Heartbeat Output Address configured for the collector DebugPrint  
MyCollector.HeartbeatOutputAddress
```

HiEngineeringUnits Property (Tag Object)

Returns or sets the high engineering unit range of the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

```
object.HiEngineeringUnits[ = Double]
```

Parameters

None

HiEngineeringUnits Property (TagCriteria Object)

Sets the high engineering unit range to search for in the TagRecordset query.

Syntax

```
object.HiEngineeringUnits[ = Double]
```

Parameters

None

HiEngineeringUnits Property (TagFields Object)

Determines whether the HiEngineeringUnits field should be returned in the TagRecordset query.

Syntax

```
object.HiEngineeringUnits[ = Boolean]
```

Parameters

None

HiEngineeringUnitsSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.HiEngineeringUnitsSet[ = Boolean]
```

Parameters

None

HiEngineeringUnitsUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**HiEngineeringUnitsUpdated**[= *Boolean*]

Parameters

None

HiScale Property (Tag Object)

Sets the high scale value used for input scaling on the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**HiScale**[= *String*]

Parameters

None

HiScale Property (TagCriteria Object)

Sets the high input scale range value to search for in the TagRecordset query.

Syntax

object.**HiScale**[= *String*]

Parameters

None

HiScale Property (TagFields Object)

Determines whether the HiScale field should be returned in the TagRecordset query.

Syntax

object.**HiScale**[= *Boolean*]

Parameters

None

HiScaleSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**HiScaleSet**[= *Boolean*]

Parameters

None

HiScaleUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**HiScaleUpdated**[= *Boolean*]

Parameters

None

HighPart Property (QueryModifiers Object)

Returns or sets the HighPart of the query modifier. Use the Server.CriteriaFromStrings method to determine the HighPart and LowPart of a query modifier.

Syntax

object.**HighPart**

Parameters

None

Remarks

Long

HighSeverity Property (OPCFilters Object)

Gets/Sets the High Severity filter in the Alarm Collector. Only events with a severity less than or equal to HighSeverity will be collected.

Syntax

object.**HighSeverity**[= *Long*]

Parameters

None

Property Reference I-J

I

Id Property (DataStore Object)

Returns or sets the ID (GUID) of a data store. This is a read-only property.

Syntax

object.**Id**

Parameters

None

Remarks

String. This is a read-only property.

ImportErrors Property (Alarms Object)

Returns a list of Import Error messages.

Syntax

object.**ImportErrors**

Parameters

None

ImportErrors Property (DataRecordset Object)

Returns a list of Import Error messages.

Syntax

object.**ImportErrors**

Parameters

None

ImportErrors Property (MessageRecordset Object)

Returns a list of Import Errors.

Syntax

object.**ImportErrors**

Parameters

None

ImportErrors Property (TagRecordset Object)

Returns a list of tag import errors.

Syntax

object.**ImportErrors**

Parameters

None

InputScaling Property (Tag Object)

Returns or sets whether input scaling is enabled for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**InputScaling**[= *Boolean*]

Parameters

None

InputScaling Property (TagCriteria Object)

Sets the input scaling to search for in the TagRecordset query.

Syntax

object.**InputScaling**[= *Boolean*]

Parameters

None

InputScaling Property (TagFields Object)

Determines whether the InputScaling field should be returned in the TagRecordset query.

Syntax

`object.InputScaling[= Boolean]`

Parameters

None

InputScalingSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

`object.InputScalingSet[= Boolean]`

Parameters

None

InputScalingUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

`object.InputScalingUpdated[= Boolean]`

Parameters

None

IsSystem Property (DataStore Object)

Indicates or sets that data store is the single-system data store and therefore, cannot be modified.

Syntax

`object.IsSystem`

Parameters

None

InterfaceAbsoluteDeadband Property (Tag Object)

Returns or sets the Absolute Deadband value for this tag to be used in the Collector.

Syntax

object.**InterfaceAbsoluteDeadband**[= *Double*]

Parameters

None

InterfaceAbsoluteDeadband Property (TagCriteria Object)

Sets the InterfaceAbsoluteDeadband to search for in the TagRecordset query.

Syntax

object.**InterfaceAbsoluteDeadband**[= *Double*]

Parameters

None

InterfaceAbsoluteDeadband Property (TagFields Object)

Determines whether the InterfaceAbsoluteDeadband field should be returned in the TagRecordset query.

Syntax

object.**InterfaceAbsoluteDeadband**[= *Double*]

Parameters

None

InterfaceAbsoluteDeadbandSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**InterfaceAbsoluteDeadbandSet**[= *Boolean*]

Parameters

None

InterfaceAbsoluteDeadbandUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**InterfaceAbsoluteDeadbandUpdated**[= *Boolean*]

Parameters

None

InterfaceAbsoluteDeadbanding Property (Tag Object)

Returns or sets whether this tag is using Absolute Deadbanding in the Collector or not.

Syntax

object.**InterfaceAbsoluteDeadbanding**[= *Boolean*]

Parameters

None

InterfaceAbsoluteDeadbanding Property (TagCriteria Object)

Sets the InterfaceAbsoluteDeadbanding to search for in the TagRecordset query.

Syntax

object.**InterfaceAbsoluteDeadbanding**[= *Boolean*]

Parameters

None

InterfaceAbsoluteDeadbanding Property (TagFields Object)

Determines whether the InterfaceAbsoluteDeadbanding field should be returned in the TagRecordset query.

Syntax

object.**InterfaceAbsoluteDeadbanding**[= *Boolean*]

Parameters

None

InterfaceAbsoluteDeadbandingSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.InterfaceAbsoluteDeadbandingSet[ = Boolean]
```

Parameters

None

InterfaceAbsoluteDeadbandingUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.InterfaceAbsoluteDeadbandingUpdated[ = Boolean]
```

Parameters

None

IsActiveRedundantCollector Property (Collector Object)

Returns whether this collector is currently the active collector in a redundant set of collectors.

Syntax

```
object.IsActiveRedundantCollector
```

Parameters

None

Remarks

IsActiveRedundantCollector is a read-only property of type Boolean.

IsAudited Property (Data Object)

Returns whether or not this data has an Audit Trail associated with it.

Syntax

object.**IsAudited**

Parameters

None

IsAudited Property (Server Object)

Returns or sets whether the point verification feature is enabled. With point verification enabled, the system will prompt for a username and password upon any request to change data or configuration.

Syntax

object.**IsAudited**[= *Boolean*]

Parameters

None

IsCurrent Property (Archive Object)

Returns whether or not the specified archive is the newest archive where new data currently flows into.

Syntax

object.**IsCurrent**

Parameters

None

Remarks

IsCurrent is a read-only property of type Boolean.

Example

```
'Find The Current Archive, Then Initiate A Backup With MyArchives
For I = 1 To .Item.count If .Item(I).IsCurrent Then
If Not .Item(I).Backup(BackupFilename) Then err.Raise 1, "Backup", "Backup Failed" End If
End If Next I End With
```

IsDefaultServer Property (Server Object)

Returns and/or determines if the current server is the default server. You can create an instance of the Server object and connect it without supplying a server name, username, or password. In this case, the default server and associated user information establishes the default connection.

Syntax

object.**IsDefaultServer**

Parameters

None

IsDeleted Property (DataValue Object)

This function returns a Boolean which indicates whether or not this DataValue has been deleted or not.

Syntax

object.**IsDeleted**

Parameters

None

IsDeleted Property (Tag Object)

Returns whether or not this tag has been deleted.

Syntax

object.**IsDeleted**

Parameters

None

Modified Property (DataValue Object)

This function returns Boolean which indicates whether or not any of this DataValue's fields have been modified.

Syntax

object.**IsModified**

Parameters

None

IsModified Property (Tag Object)

Returns whether or not this tag has been modified.

Syntax

object.**IsModified**

Parameters

None

IsNew Property (DataComments Object)

Returns whether or not this Comment is new or not.

Syntax

object.**IsNew**

Parameters

None

IsNew Property (DataValue Object)

This function returns a Boolean which indicates whether or not this DataValue is new.

Syntax

object.**IsNew**

Parameters

None

IsNew Property (Message Object)

Returns whether this is a new message or not.

Syntax

object.**IsNew**

Parameters

None

IsNew Property (Tag Object)

Tag.IsNew indicates whether this is a newly created tag. Returns true if the tag's name does not exist in the server.

Syntax

object.**IsNew**

Parameters

None

Item Property (Archives Object)

Returns a specific Archive object contained in the Archives object. The Item collection can loop through all Archives, or reference a specific Archive object directly by archive name.

The Archive Item collection automatically populates when the Archives object is instantiated.

Syntax

object.**Item**

Parameters

None

Remarks

Item is a read-only property of type Collection of Archives.

Item Property (Collectors Object)

Returns a specific Collector object contained in the Collectors Object collection. The Item collection can loop through all Collectors, or reference a specific Collector object directly by Collector name.

The Collector Item collection automatically populates when the Collectors object is instantiated.

Syntax

object.**Item**

Parameters

None

Remarks

Item is a read-only property of type Collection.

Item Property (DataRecordset Object)

Returns a specific DataValue object contained in the DataRecordset object. The Item collection can loop through all DataValues, or reference a specific DataValue object directly by Tagname and Timestamp.

The DataRecordset (and thus the Item collection) is populated with DataValues in three ways. The first is to set up query criteria and call the QueryRecordset method. The second is to import a list of DataValues using the Import method. The last way is to use the Add method to add new DataValues.

Syntax

object.**Item**(Tagname)

Parameters

Tagname - Variant - The name of the tag whose values to retrieve.

Remarks

Item is a read-only property of type Collection of DataValue.

Item Property (DataStores Object)

Returns a specific data store object contained in the DataStores Object collection. The Item collection can loop through all DataStores, or reference a specific DataStore object directly by DataStore name.

Syntax

object.Item() As Collection

Parameters

None

Remarks

Item is a read-only property of type Collection.

Item Property (EnumeratedStates Object)

Returns an individual item from the EnumeratedStates collection.

Parameters

None

Remarks

Enumerated State.

Item Property (MessageRecordset Object)

Returns a specific Message object contained in the MessageRecordset object. The Item collection can loop through all Messages or reference a specific Message object directly by the timestamp.

The MessageRecordset (and thus the Item collection) populates with the Message in two ways: set up query criteria and call the QueryRecordset method, or use the Add method to add new Messages. Item is a read-only property of type Collection of Message.

Syntax

object.**Item**

Parameters

None

Item Property (TagDependencies Object)

This function attempts to find the given Tagname within the collection of currently configured tags.

Syntax

```
object.Item(Tagname)
```

Parameters

Tagname - Variant - Name of the tag to locate.

Item Property (TagRecordset Object)

Returns a specific Tag object contained in the TagRecordset object. The Item collection can loop through all Tags, or reference a specific Tag object directly by the tag name.

The TagRecordset (and thus the Item collection) populates with Tags in three ways:

The first is to set up query criteria and call the QueryRecordset method. The second is to import a list of Tags using the Import method. The last way is to use the Add method to add new Tags.

Syntax

```
object.Item
```

Parameters

None

Remarks

Item is a read-only property of type Collection of Tag.

Item Property (UserDefinedTypeFields Object)

Returns an individual item from the multiple fields of the User Defined Type.

Syntax

```
object.item(Index)
```

Parameters

Index - Variant - The index has to be returned.

Remarks

UserDefinedTypeField.

Property Reference K-L

L

LastBackup Property (Archive Object)

Returns the date and time of the last archive backup.

Syntax

object.**LastBackup**

Parameters

None

Remarks

`LastBackup` is a read-only property of the type Date.

Example

```
Dim I As Long ' List The Start and End Time Of Each Archive With MyArchives For I = 1 To .Item.count
Debug.Print .Item(I).Name, .Item(I).StartTime, .Item(I).LastBackup Next I End With
```

LastBackupUser Property (Archive Object)

Returns username of the person who performed the last backup of the archive.

Syntax

object.**LastBackupUser**

Parameters

None

Remarks

`LastBackupUser` is a read-only property of type String.

Example

```
Debug.Print "Modified By: " + MyArchive.LastBackupUser
```

LastError Property (Archive Object)

Returns the last error message encountered by the Archive object. To see a complete list of messages, refer to the ErrorList property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError**

Parameters

None

Remarks

LastError is a read-only property of type String.

LastError Property (Archives Object)

Returns the last error message encountered by the Archives object. To see a complete list of messages, refer to the ErrorList property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError**

Parameters

None

Remarks

LastError is a read-only property of type String.

LastError Property (Collector Object)

Returns the last error message encountered by the Collector object. To see a complete list of messages, refer to the ErrorList property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError**

Parameters

None

Remarks

LastError is a read-only property of type String.

LastError Property (Collectors Object)

Returns the last error message encountered by the Collectors Object. To see a complete list of messages, refer to the ErrorList property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError**

Parameters

None

Remarks

LastError is a read-only property of type String.

LastError Property (DataRecordset Object)

Returns the last error message encountered by the DataRecordset object. To see a complete list of messages, refer to the ErrorList property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError**

Parameters

None

Remarks

LastError is a read-only property of type String.

LastError Property (DataStores Object)

Returns the last error message encountered by the Collectors Object.

Syntax

object.**LastError**

Parameters

None

Remarks

LastError is a read-only property of type String.

LastError Property (EnumeratedSets Object)

Returns the last error message encountered by the EnumeratedSets object. To see a complete list of messages, refer to the ErrorList Property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError()**

Parameters

None

Remarks

String. Indicates whether the string contains an error or not. This is a read-only property.

LastError Property (EnumeratedSets Object)

Returns the last error message encountered by the EnumeratedSets object. To see a complete list of messages, refer to the ErrorList Property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError()**

Parameters

None

Remarks

String. Indicates whether the string contains an error or not. This is a read-only property.

LastError Property (Messages Object)

Returns the last error message encountered by the EnumeratedSets object. To see a complete list of messages, refer to the ErrorList Property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError()**

Parameters

None

Remarks

`LastError` is a read-only property of type String.

LastError Property (Messages Object)

Returns the last error message encountered by the EnumeratedSets object. To see a complete list of messages, refer to the ErrorList Property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError**

Parameters

None

Remarks

`LastError` is a read-only property of type String.

LastError Property (Server Object)

Returns the last error message encountered by the Server object. To see a complete list of messages, refer to the ErrorList property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError**[= *String*]

Parameters

None

LastError Property (ServerManager Object)

Returns a text description of the last error encountered by the ServerManager object.

Syntax

object.**LastError**

Parameters

None

Remarks

`LastError` is a read-only property of type String.

LastError Property (Tag Object)

Contains the last error string generated.

Syntax

object.**LastError**[= *String*]

Parameters

None

LastError Property (TagRecordset Object)

Returns the last error message encountered by the TagRecordset object. To see a complete list of messages, refer to the ErrorList property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError**

Parameters

None

Remarks

`LastError` is a read-only property of type String.

LastError Property (Tags Object)

Returns the last error message encountered by the Tags Object. To see a complete list of messages, refer to the ErrorList property. When possible, the system translates messages into the locale of the client.

Syntax

object.**LastError**

Parameters

None

Remarks

`LastError` is a read-only property of type String.

LastModified Property (Tag Object)

Returns the time the tag configuration of this Tag was last modified.

Syntax

object.**LastModified**

Parameters

None

Remarks

`LastModified` is a read-only property of type Date.

LastModified Property (TagCriteria Object)

Sets the last modified time to search for in the TagRecordset query.

Syntax

object.**LastModified**[= Date]

Parameters

None

LastModified Property (TagFields Object)

Determines whether the LastModified field should be returned in the TagRecordset query.

Syntax

object.**LastModified**[= *Boolean*]

Parameters

None

LastModified Property (UserDefinedTypes Object)

Returns the time when the User Defined Type was last modified.

Syntax

object.**LastModified**

Parameters

None

Returns

`LastModified` is a read-only property of type Date.

LastModifiedSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**LastModified**[= *Boolean*]

Parameters

None

LastModifiedUser Property (Tag Object)

Returns the user who last modified this Tag configuration.

Syntax

object.**LastModifiedUser**

Parameters

None

Remarks

`LastModifiedUser` is a read-only property of type Date.

LastModifiedUser Property (TagCriteria Object)

Sets the last modified user to search for in the TagRecordset query.

Syntax

```
object.LastModifiedUser[=string]
```

Parameters

None

LastModifiedUser Property (TagFields Object)

Determines whether the LastModifiedUser field should be returned in the TagRecordset query.

Syntax

```
object.LastModifiedUser[=Boolean]
```

Parameters

None

LastModifiedUser Property (UserDefinedType Object)

Returns the last user that modified the User Defined Type.

Syntax

```
object.LastModifiedUser
```

Parameters

None

Returns

`LastModifiedUser` is a read-only property of type String.

LastModifiedUserSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**LastModifiedUser**[*=Boolean*]

Parameters

None

LeafCount Property (OPCBrowse Object)

Returns the number of leaves under a browse position. When a browse operation occurs, the server returns all areas and sources under the BrowsePosition. LeafCount gives you the number of leaves, which you can use to iterate the LeafNames and FullLeafNames arrays.

Syntax

object.**LeafCount**

Parameters

None

Returns

`LeafCount` is a read-only property of type String.

LeafNames Property (OPCBrowse Object)

Returns the display leaf name (source) for an AE server. See "FullLeafnames" property for more information.

Syntax

object.**LeafNames**(Index)

Parameters

Index - Integer - The index into the leaf name array.

Returns

`LeafNames` is a read-only String property returned as a variant for script compatibility.

LicensedTags Property (Server Object)

Returns the maximum number of tags that you can configure on the Server.

Syntax

object.**LicensedTags**(Index)

Parameters

None

Remarks

`LicensedTags` is a read-only property of type Long.

LicensedUsers Property (Server Object)

Returns the maximum number of users that may be connected to the Server at one time.

Syntax

object.**LicensedUsers**

Parameters

None

Remarks

`LicensedUser` is a read-only property of type Long.

LoEngineeringUnits Property (Tag Object)

Returns or sets the low engineering unit range of the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**LoEngineeringUnits**[= *Double*]

Parameters

None

LoEngineeringUnits Property (TagCriteria Object)

Sets the low engineering unit range to search for in the TagRecordset query.

Syntax

object.**LoEngineeringUnits**[= *Double*]

Parameters

None

LoEngineeringUnits Property (TagFields Object)

Determines whether the LoEngineeringUnits field should be returned in the TagRecordset query.

Syntax

object.**LoEngineeringUnits**[= *Boolean*]

Parameters

None

LoEngineeringUnitsSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**LoEngineeringUnitsSet**[= *Boolean*]

Parameters

None

LoEngineeringUnitsUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**LoEngineeringUnitsUpdated**[= *Boolean*]

Parameters

None

LoScale Property (Tag Object)

Returns or sets the low scale value used for input scaling on the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**LoScale**[= *String*]

Parameters

None

LoScale Property (TagCriteria Object)

Sets the low input scale range value to search for in the TagRecordset query.

Syntax

object.**LoScale**[= *String*]

Parameters

None

LoScale Property (TagFields Object)

Determines whether the LoScale field should be returned in the TagRecordset query.

Syntax

object.**LoScale**[= *Boolean*]

Parameters

None

LoScale Property (TagCriteria Object)

Determines whether the LoScale field should be returned in the TagRecordset query.

Syntax

object.**LoScaleSet**[= *Boolean*]

Parameters

None

LoScaleUpdated (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**LoScaleUpdated**[= *Boolean*]

Parameters

None

LoadBalancing Property (Tag Object)

Returns or sets the status of data collection load balancing for the Tag. Load balancing is used for polled type collection to evenly distribute data collection load over available sampling times. This is sometimes called "Phase Shifting". Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**LoadBalancing**[= *Boolean*]

Parameters

None

LoadBalancing Property (TagCriteria Object)

Sets the load balancing to search for in the TagRecordset query.

Syntax

object.**LoadBalancing**[= *Boolean*]

Parameters

None

LoadBalancing Property (TagFields Object)

Determines whether the LoadBalancing field should be returned in the TagRecordset query.

Syntax

object.**LoadBalancing**[= *Boolean*]

Parameters

None

LoadBalancingSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**LoadBalancingSet**[= *Boolean*]

Parameters

None

LoadBalancingUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**LoadBalancingUpdated**[= *Boolean*]

Parameters

None

LowPart Property (QueryModifiers Object)

Returns or sets the LowPart of query modifier. Use the Server.CriteriaFromStrings method to determine the HighPart and LowPart of a query modifier.

Syntax

object.**LowPart**

Parameters

None

Remarks

Long

LowSeverity Property (OPCFilters Object)

Gets/Sets the Low Severity filter in the Alarm Collector. Only events with a severity higher than or equal to LowSeverity will be collected.

Syntax

object.**LowSeverity**[= *Long*]

Parameters

None

Property Reference M-N

M

MaintainAutoRecoveryFiles Property (Server Object)

Returns or sets whether auto recovery files are maintained by the server. Auto recovery files are periodic backups of the current .IHA and .IHC and protect against data loss due to ungraceful server shutdown.

Syntax

object.**MaintainAutoRecoveryFiles**[= *Boolean*]

Parameters

None

MajorVersion Property (Server Object)

Returns the server or client major version number (1, 2, 3, and so on).

Syntax

object.**MajorVersion**(*[API]*)

Parameters

Name	Data Type	Description
API	Boolean	When True, the server version is returned. When False, the client version is returned. The default is False.

Remarks

`MajorVersion` is a read-only property of type Long.

Master Property (TagRecordset Object)

Returns the Master tag upon which bulk changes to tag configuration may be performed. When calling the WriteRecordset method, and supplying the "UserMasterTag" parameter, all

changes made to the Master tag will be replicated to each tag in the TagRecordset whose Selected property is set to True.

Syntax

object.**Master**(*[ClearUpdates]*)

Parameters

Name	Data Type	Description
ClearUpdates	Boolean	Whether to clear all pending updates in the master tag (optional, default = False).

Remarks

`Master` is a read-only property of type Tag.

Example

```
Dim Recordset As TagRecordset Dim Master As Tag ' Get a new TagRecordset Set Recordset =
MyServer.Tags.NewRecordset '
Fill in criteria, get all tags with collector compression on With Recordset.Criteria
.Tagname = "*" .CollectorCompression = True End With Recordset.QueryRecordset
Set Master = Recordset.Master ' Set Compression Percent to 0.5% Master.CollectorDeadbandPercentRange =
0.5 '
Select all tags in the recordset Recordset.SelectAll ' Commit Changes If Not
Recordset.WriteRecordset(True)
Then MsgBox "Failed To Commit Tag Changes" End If
```

MaxReturnCells Property (DataRecordset Object)

Sets the Maximum number of cells to return in the DataRecordSet.

Syntax

object.**MaxReturnCells**(*[size]*)

Parameters

Name	Data Type	Description
Size	Long	Number of cells to return.

MaximumQueryIntervals Property (Server Object)

Returns or sets the maximum query intervals enforced by the server. This property restricts the maximum number of samples per tag that the server can return for non-raw data queries. Filtered and raw data queries are not throttled.

Syntax

object.**MaximumQueryIntervals**(*[Long]*)

Parameters

None

MaximumQueryTime Property (Server Object)

Returns or sets the maximum query time enforced by the server. The property restrict query times and provides balanced access to the server.

Syntax

object.**MaximumQueryTime**(*[Long]*)

Parameters

None

MessageNumber Property (Message Object)

Returns the message number of the Message. A message number is a unique identifier for each Message required for national language support.

Syntax

object.**MessageNumber***[Long]*

Parameters

None

Remarks

MessageNumber is a read-only property of type Long.

MessageNumber Property (MessageCriteria Object)

Establishes which message number the MessageRecordset query will filter by. A message number is a unique identifier for each Message required for national language support.

Syntax

object.**MessageNumber**[*Long*]

Parameters

None

MessageNumber Property (MessageFields Object)

Determines whether the MessageNumber field should be returned in the MessageRecordset query.

Syntax

object.**MessageNumber**[=*Boolean*]

Parameters

None

MessageNumberSet Property (MessageCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**MessageNumberSet**[=*Boolean*]

Parameters

Option	Description
MessageOnDataUpdate	Determines whether data updates generate a message.

MessageOptions Property (Messages Object)

Exposes the MessageOptions collection to control the behavior of the Historian message generation and archiving.

If the property is set to True, all applications connected to the archiver will cause the archiver to generate a message on a data update, not just the application that set the

property. For instance, if you set the property with the SDK and the File collector updates data (a single value) a message will be generated by the archiver.

An example of a message that appears in Historian Administrator after you change a specified tag property through the SDK would be:

```
bsmith(MY_DOMAIN\bsmith) wrote 96 to tag aa at 01/10/2003 04:13:49.861 PM, Replaced 94.000
```

The message topic type would be Security.

The following table describes each of the messaging options:

Syntax

object.**MessageOptions**(OptionName)[=*Variant*]

Parameters

Name	Data Type	Description
OptionName	String	The name of the message option.

Remarks

MessageOptions is a read-only property of type Collection of options.

Example

```
ConnectedServer.Messages.MessageOptions("MessageOnDataUpdate") = True
```

MessageString Property (Message Object)

Returns the translated text of the message, including any substitutions. Messages generally include translated fixed text and variable substitutions such as timestamps, usernames, and tagnames.

Syntax

object.**MessageString**[*String*]

Parameters

None

MessageString Property (MessageCriteria Object)

Establishes text search criteria the MessageRecordset query filters by. The MessageString may be any sub-string of the message. You should not include wildcard characters.

Syntax

object.**MessageString**[*=String*]

Parameters

None

MessageString Property (MessageFields Object)

Determines whether the MessageString field should be returned in the MessageRecordset query.

Syntax

object.**MessageString**[*=Boolean*]

Parameters

None

MessageStringSet Property (MessageCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**MessageStringSet**[*=Boolean*]

Parameters

None

Messages Property (Server Object)

Returns the Messages Object for the current Server. Use the Messages Object to build queries for message data.

Syntax

object.**Messages**

Parameters

None

MessageOptions Property (Server Object)

Returns the server or client minor version number (0, 1, 2, and so on).

Syntax

object.**MessageVersion**([API])

Parameters

Name	Data Type	Description
API	Boolean	When True, the server version is returned. When False, the client version is returned. The default is False.

Remarks

MinorVersion is a read-only property of type Long.

N

Name Property (Archive Object)

Returns the name of the specified Archive.

Syntax

object.**Name**

Parameters

None

Name Property (Collector Object)

Returns the name of the specified Collector.

Syntax

object.**Name**

Parameters

None

Remarks

Name is a read-only property of type String.

Name Property (DataStore Object)

Returns the name of data store.

Syntax

object.**Name**

Parameters

None

Remarks

String.

Name Property (Option Object)

The name parameter of this option.

Syntax

object.**Name***[= String]*

Parameters

None

Name Property (UserCalcFunction Object)

Returns the name of the specified UserCalcFunction.

Syntax

object.**Name***[= String]*

Parameters

None

NodeFilter Property (OPCBrowse Object)

Some OPCA servers allow you to set a filter for the browse. The areas returned by the browse operation will be only those that match the filter criterion. If this property is not set, no filtering takes place.

Syntax

object.**NodeFilter**[= *Variant*]

Parameters

None

Remarks

Nodefilter is a read/write property of type Variant for script compatibility.

NumberOfElements Property (Tag Object)

Returns or sets the number of elements of a tag to specify if it is an array. If the value of the NumberOfElements is -1 then it is an array tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**NumberOfElements**[= *Long*]

Parameters

None

NumberOfElements Property (TagCriteria Object)

Sets the NumberOfElements property to search for in the TagRecordset query. For example you can set to -1 if you want only array tags to be returned or set to 0 if you want non-array tags.

Syntax

object.**NumberOfElements**[= *Long*]

Parameters

None

NumberOfElements Property (TagFields Object)

Determines whether the NumberOfElements field should be returned in the TagRecordset query.

Syntax

object.**NumberOfElements**[= *Boolean*]

Parameters

None

NumberOfFields Property (UserDefinedType Object)

Returns the number of fields in the User Defined Type.

Syntax

object.**NumberOfFields**

Parameters

Integer

NumberOfSamples Property (DataCriteria Object)

Returns or sets the number of samples to retrieve from the archive in the DataRecordset query. Samples will be evenly spaced within the time range defined by start time and end time for most sampling modes. For the "RawByNumber" sampling mode the NumberOfSamples determines the maximum number of values to retrieve. For the "RawByTime" sampling mode, the NumberOfSamples is ignored.

Syntax

object.**NumberOfFields**[= *Long*]

Parameters

None

NumberOfSamplesSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**NumberOfSamplesSet**[= *Long*]

Parameters

None

NumStateNames Property (EnumeratedState Object)

Returns the number of states in the set.

Syntax

object.**NumStateNames**

Parameters

None

Remarks

Long

Property Reference O-P

P

PercentGood Property (DataValue Object)

Returns the percentage of time the value was of good quality during the interval the DataValue applies to. Does not apply to **RawByNumber** and **RawByTime** sampling modes.

Syntax

object.**PercentGood**

Parameters

None

Remarks

PercentGood is a read-only property of type Single.

Example

```
If MyValue.PercentGood < 50 Then    err.Raise 1,, "We do not have enough good data" End If
```

PerformanceDSStatistics (Archives Object)

Exposes performance statistics for the data store. These statistics are updated periodically.

The Product server and new current values are automatically reported to the client and updated in the PerformanceDSStatistics collection.

Syntax

object.**PerformanceDSStatistics**

Parameters

None

Remarks

PerformanceDSStatistics is a read-only property of type Collection of Variant.

PerformanceDSStatistics (Archives Object)

Exposes performance statistics for the data stores. These statistics are updated periodically.

The server and new current values are automatically reported to the client and updated in the PerformanceDSStatistics collection.

The following table describes each of the performance statistics and their purpose.

DataStores Performance Statistics

Statistic	Description
ArchiveTotalEvents	Total number of data points received by the data store. This option is specific only to data stores.
ArchiveTotalOutOfOrder	Total number of data points received by the server out of time order with the current value. This option is specific only to data stores.
ArchiveAverageEventRate	Average events processed per minute. This option is specific only to data stores.
ArchiveMinimumEventRate	Minimum events processed per minute. This option is specific only to data stores.

Statistic	Description
ArchiveMaximum-EventRate	Maximum events processed per minute. This option is specific only to data stores.
ArchiveWriteCache-HitRatio	Hit Ratio To Write Cache. This option is specific only to data stores.
ArchiveAverageCompressionRatio	Average compression ratio for all tags. This option is specific only to data stores.
ArchiveMinimum-CompressionRatio	Minimum compression ratio for any tag. This option is specific only to data stores.
ArchiveTotalFailed-Writes	Total number of refused write attempts by any connection. This option is specific only to data stores.
ArchiveTotalMessages	Total number of non-alert messages generated. This option is specific only to data stores.
ArchiveTotalAlerts	Total number of alert messages generated. This option is specific only to data stores.
ArchiveFreeSpace	Amount of free space (MB) in the current archive. This option is specific only to data stores.
ArchiveSpaceConsumptionRate	Current free space consumption rate (MB/Day). This option is specific only to data stores.
ArchivePredicted-DaysToFull	Predicted days to archive full. This option is specific only to data stores.
ArchiveSpaceEfficiency	Efficiency of archive space utilization. This option is specific only to data stores.
ArchiveAverageEventRateArray	An array of archiver received rates used to make the trend. This option is specific only to data stores.

Statistic	Description
ArchiveAverage-AlarmRate	<p>Displays the rate at which Historian is receiving alarms and events data.</p> <p>This option is specific only to data stores.</p>
ArchiveTotalAlarm	<p>The rate at which Historian is receiving data.</p> <p>This option is specific only to data stores.</p>

Syntax

object.**PerformanceDSStatistics**

Parameters

None

Remarks

PerformanceDSStatistics is a read-only property of type Collection of Variant.

PerformanceStatistics (Archives Object)

Exposes performance statistics for the Product Archiver. These statistics are updated periodically.

The Product server and new current values are automatically reported to the client and updated in the PerformanceStatistics collection.

Syntax

object.**PerformanceStatistics**

Parameters

None

Remarks

PerformanceStatistics is a read-only property of type Collection of Variant.

PerformanceStatistics Property (Archives Object)

Exposes performance statistics for the Historian Archiver. These statistics are updated periodically. The Historian server and new current values are automatically reported to the client and updated in the PerformanceStatistics collection.

The following table describes each of the performance statistics and their purpose.

Archives Performance Statistics

Statistic	Description
ArchiveTotalOutOfOrder	Total number of data points received by the server out of time order with the current value. This option is specific only to data stores.
ArchiveAverageEventRate	Average events processed per minute. This option is specific only to data stores.
ArchiveMinimumEventRate	Minimum events processed per minute. This option is specific only to data stores.
ArchiveMaximumEventRate	Maximum events processed per minute. This option is specific only to data stores.
ArchiveWriteCacheHitRatio	Hit Ratio To Write Cache. This option is specific only to data stores.
ArchiveAverageCompressionRatio	Average compression ratio for all tags. This option is specific only to data stores.
ArchiveMinimumCompressionRatio	Minimum compression ratio for any tag. This option is specific only to data stores.
ArchiveTotalFailedWrites	Total number of refused write attempts by any connection. This option is specific only to data stores.
ArchiveTotalMessages	Total number of non-alert messages generated. This option is specific only to data stores.
ArchiveTotalAlerts	Total number of alert messages generated.

Statistic	Description
	This option is specific only to data stores.
ArchiveFreeSpace	Amount of free space (MB) in the current archive. This option is specific only to data stores.
ArchiveSpaceConsumptionRate	Current free space consumption rate (MB/Day). This option is specific only to data stores.
ArchivePredicted-DaysToFull	Predicted days to archive full. This option is specific only to data stores.
ArchiveSpaceEfficiency	Efficiency of archive space utilization. This option is specific only to data stores.
ArchiveAverageEventRateArray	An array of archiver received rates used to make the trend. This option is specific only to data stores.
ArchiveAverageAlarmRate	Displays the rate at which Historian is receiving alarms and events data. This option is specific only to data stores.
ArchiveTotalAlarm	The rate at which Historian is receiving data. This option is specific only to data stores.

Syntax

object.**PerformanceStatistics**[AsLocalizedString])

Parameters

Name	Data Type	Description
StatisticName	String	Name of the statistic to retrieve (read-only).
AsLocalizedString	Boolean	Whether to return the statistic value(s) as a localized string (optional, default = True, read-only).

Remarks

PerformanceStatistics is a read-only property of type Collection of Variant.

Example

```
Dim TheStatistic As Variant
' Get The Overall Compression Performance Statistic
TheStatistic = MyArchives.PerformanceStatistics("ArchiveAverageCompressionRatio")
```

PerformanceStatistics Property (Collector Object)

Exposes performance statistics for the selected collector.

The following table describes each of the performance statistics and their purpose.

Collector Performance Statistics

Statistic Description

CollectorTotal-EventsCollected	Total Values Collected
CollectorTotal-EventsReported	Total Values Reported To Server.
CollectorOutOfOrder-Events	Total Events Out Of Timestamp Order.
CollectorAverage-EventRate	Average Events Reported / Minute.
CollectorMinimum-EventRate	Minimum Events Reported / Minute.
CollectorMaximum-EventRate	Maximum Events Reported / Minute.
CollectorReportRatio	Ratio Of Events Collected To Events Reported.
CollectorCompressionPercent	The percent of data compressed by the collector.
CollectorMisses	The data that are missed by the collector due to missing scheduled collection times. Also called Overruns.

Syntax

object.**PerformanceStatistics**(StatisticName,[AsLocalizedString])

Parameters

Name	Data Type	Description
StatisticName	Variant	Name of the statistic to retrieve (read-only).
AsLocalizedString	Boolean	Whether to return the statistic value(s) as a localized string (optional, default = True, read-only).

Example

```
Dim TheStatistic As Variant
' Get The Overall Compression Performance Statistic
TheStatistic = MyCollector.PerformanceStatistics("CollectorEventRate")
```

PrimaryUsername Property (DataComments Object)

Returns the user who added the comment to the archive.

Syntax

object.**PrimaryUsername**

Parameters

None

Remarks

PrimaryUsername is a read-only property of type String.

Example

```
Debug.Print "Comment added by: " + MyValue.Comments(1).PrimaryUsername
```

PrincipalCollector Property (Collector Object)

The name of the collector this collector is backing up. If the principal collector is not responding this collector is next in line to become active.

Syntax

object.**PrincipalCollector**[= String]

Parameters

None

PropertyList Property (Archives Object)

This function returns a list of the supported Archive properties.

Syntax

object.**PropertyList**

Parameters

None

PropertyList Property (Collectors Object)

Returns a list of the available collector properties. This is a complete list across all collector types. A given collector may ignore certain properties if they do not apply.

Syntax

object.**PropertyList**

Parameters

None

PropertyList Property (Data Object)

This function returns a list of the available Properties of a Data value.

Syntax

object.**PropertyList**([ExcludeRaw], [ExcludeAlarms])

Parameters

Name	Data Type	Description
ExcludeRaw	Boolean	Whether to exclude the PercentGood property (optional, default = False).
ExcludeAlarms	Boolean	Whether to exclude the Alarm Message and Alarm ID properties (optional, default = False).

PropertyList Property (Messages Object)

Returns a list of available Properties for a message.

Syntax

object.**PropertyList**

Parameters

None

PropertyList Property (Tags Object)

Returns a list of valid Properties for a Tag.

Syntax

object.**PropertyList**

Parameters

None

QueryModifiers Property (QueryModifiers Object)

Returns or sets the QueryModifiers to be used during the DataRecordset query.

Syntax

object.**QueryModifiers**

```
Set resQueryModifiers ConnectedServer.CriteriaFromStrings(txtQueryModifier.Text)
.Criteria.QueryModifiers = resQueryModifiers.QueryModifiers
```

Property Reference Q-R

R

RawValue Property (Option Object)

The raw numeric value of this option.

Syntax

object.**RawValue**[= *Double*]

Parameters

None

ReadOnly Property (Archive Object)

Returns or sets the ReadOnly status of the specified archive. If you attempt to set the current archive to ReadOnly (the archive receiving newest data), an error is generated.

Syntax

`object.ReadOnly` [= *Boolean*]

Parameters

None

Example `' Set Archive To ReadOnly MyArchive.ReadOnly = True ' Reset Archive
ReadOnly Status MyArchive.ReadOnly = False`

ReadSecurityGroup Property (Tag Object)

RReturns or sets the name of the security group controlling the reading of data for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

`object.ReadSecurityGroup` [= *String*]

Parameters

None

ReadSecurityGroup Property (TagCriteria Object)

Returns or sets the ReadOnly status of the specified archive. If you attempt to set the current archive to ReadOnly (the archive receiving newest data), an error is generated.

Syntax

`object.ReadSecurityGroup` [= *String*]

Parameters

None

Example `With MyRecordset.Criteria .TagName = "*.F_CV" .ReadSecurityGroup = "Power
Users" End With`

ReadSecurityGroup Property (TagFields Object)

Determines whether the ReadSecurityGroup field should be returned in the TagRecordset query.

Syntax

object.**ReadSecurityGroup**[= *Boolean*]

Parameters

None

Example With MyRecordset.Fields .Clear .TagName = True .Description = True .ReadSecurityGroup = True .WriteSecurityGroup = True .AdministratorSecurityGroup = True End With

ReadSecurityGroupSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ReadSecurityGroup**[= *Boolean*]

Parameters

None

ReadSecurityGroupUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**ReadSecurityGroupUpdated**[= *Boolean*]

Parameters

None

RedundancyEnabled Property (Collector Object)

Returns or sets whether the collector is part of a redundant configuration.

Syntax

object.**RedundancyEnabled**[= *Boolean*]

Parameters

None

Running Property (Collector Object)

Returns or sets the running state of the specified Collector. Use this property to pause and resume collection without restarting and stopping the collector.

Syntax

```
object.Running[ = Boolean]
```

Parameters

None

Example

```
' Resume the collector MyCollector.Running = True  
  
' Pause the collector MyCollector.Running = False
```

Property Reference S-T

S

SamplingDirectionList Property (Data Object)

This function returns a list of the available Sampling directions for a data request.

Syntax

```
object.SamplingDirectionList
```

Parameters

None

SamplingInterval Property (DataCriteria Object)

Returns or sets the interval (in milliseconds) between samples from the archive in the DataRecordset query. For the "RawByNumber" and "RawByTime" sampling modes, the SamplingInterval is ignored. This property can be used in place of the NumberOfSamples property.

Syntax

```
object.SamplingInterval[=Long]
```

Parameters

None

SamplingIntervalSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**SamplingIntervalSet**[*=Boolean*]

Parameters

None

SamplingMode Property (DataCriteria Object)

Returns or sets the mode of sampling data from the archive by the DataRecordset query.

The following table details the available sampling modes:

Name	Description	Value
CurrentValue	Retrieves the current value, the time frame criteria are ignored.	1
Interpolated	Retrieves evenly spaced interpolated values based on NumberOfSamples and the time frame criteria.	2
Trend	Retrieves the raw minimum and raw maximum value for each specified interval. Use the Trend sampling mode to maximize performance when retrieving data points for plotting. A start time, end time, and an interval or number of samples must be specified.	3
RawByTime	Retrieves raw archive values (compressed) based on time frame criteria.	4
RawByNumber	Retrieves raw archive values (compressed) based on the StartTime criteria, the NumberOfSamples, and Direction criteria. Note the EndTime criteria is ignored for this Sampling mode.	5

Name	Description	Value
Calculated	Retrieves evenly spaced calculated values based on NumberOfSamples, the time frame criteria, and the Calculation-Mode criteria.	6
Lab	<p>The Lab sampling mode only returns the collected values, without any interpolation of the value. The collected value is repeated for each interval until there is a change in the raw data sample's value.</p> <p>Lab sampling is most often used to create a step chart rather than a smooth curve.</p> <p>Use Lab sampling instead of interpolated if you only want true collected values returned. The Lab sampling mode is generally not useful on highly compressed data. Use interpolated sampling instead.</p>	7
InterpolatedtoRaw	<p>When you request interpolated data, you specify an interval or number of samples. If the actual stored number of raw samples is greater than required, you will get interpolated data as described above. If the actual number of stored samples are less than the required, then you will get the raw samples. In this way, the needs of trending detail and application load are balanced.</p> <p>This mode is best used when querying compressed data because the Data Archiver can switch to the more efficient raw data query.</p>	8
TrendtoRaw	TrendtoRaw retrieves raw data between a given intervals when the actual data	9

Name	Description	Value
	samples are fewer than the requested number of samples.	
LabtoRaw	LabtoRaw is an extension to Lab mode of sampling and similar to Interpolated-toRaw mode where you will be switched to raw data or lab when the actual data samples are fewer than the requested samples.	10
RawByFilterToggle	RawByFilterToggle returns filtered time ranges. The values returned are 0 and 1. If the value is 1, then the condition is true and 0 means false. This sampling mode is used with the time range and filter tag condition. The result starts with a starting time stamp and ends with an ending timestamp.	11

Syntax

object.**SamplingMode**[=*iHistorian_SDK.ihSamplingMode*]

Parameters

None

SamplingModeList Property (Data Object)

This function returns a list of the available Sampling Modes for Data.

Syntax

object.**SamplingModeList**([*ExcludeRaw*])

Parameters

Name	Data Type	Description
ExcludeRaw	Boolean	Whether to exclude raw sampling modes (optional, default = False).

SamplingModeSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**SamplingModeSet**[= *Boolean*]

Parameters

None

SecondaryUsername Property (DataComments Object)

Returns the user who signed the comment when it was added to the archive.

Syntax

object.**SecondaryUsername**

Parameters

None

Remarks

SecondaryUserName is a read-only property of type String.

Example

```
Debug.Print "Comment signed by:"+MyValue.Comments(1).SecondaryUsername
```

SecurityGroupList Property (Server Object)

Returns the list of security groups from the current server. Security groups determine the system functions permitted by users within the group.

Syntax

object.**SecurityGroupList**

Parameters

None

Remarks

SecurityGroupList is a read-only property of type Variant.

SecurityGroupLocation Property (Server Object)

Returns or sets the location of the security groups used by the server. The Historian server can either use security groups assigned to the local server computer ("Local" location) or groups configured for the domain ("Domain" location). Note, changing the SecurityGroupLocation requires a server restart to take effect.

Syntax

```
object.SecurityGroupLocation[ = String]
```

Parameters

None

Selected Property (Tag Object)

Returns whether or not this tag is selected.

Syntax

```
object.Selected[ = Boolean]
```

Parameters

None

Server Property (Archive Object)

Returns the server associated with the Archive object.

Syntax

```
object.Server
```

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String ' Get The Name Of The Server ServerName = MyArchive.Server.ServerName
```

Server Property (Archives Object)

Returns the Server associated with the Archives object.

Syntax

object.**Server**

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String ' Get The Name Of The Server ServerName = MyArchives.Server.ServerName
```

Server Property (Collector Object)

Returns the Server associated with the Collector Object.

Syntax

object.**Server**

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String ' Get The Name Of The Server ServerName = MyCollector.Server.ServerName
```

Server Property (Collectors Object)

Returns the Server associated with the Collectors object.

Syntax

object.**Server**

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String ' Get The Name Of The Server ServerName = MyCollectors.Server.ServerName
```

Server Property (Data Object)

Returns the server associated with the Data object.

Syntax

object.**Server**

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String ' Get The Name Of The Server ServerName = MyDataServer.Server.ServerName
```

Server Property (DataRecordset Object)

Returns the Server associated with the DataRecordset object.

Syntax

object.**Server**

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String ' Get The Name Of The Server ServerName = MyRecordset.Server.ServerName
```

Server Property (DataStores Object)

Returns the Server associated with the DataRecordset object.

Syntax

object.**Server()** As Server

Parameters

None

Remarks

Server is a read-only property of type Server.

Server Property (MessageRecordset Object)

Returns the Server associated with the DataRecordset object.

Syntax

object.**Server**

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String  
  
    ' Get the name of the server  
  
    ServerName = MyRecordset.Server.ServerName
```

Server Property (Messages Object)

Returns the Server associated with the Messages object.

Syntax

object.**Server**

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String
    ' Get The Name Of The Server
    ServerName = MyMessages.Server.ServerName
```

Server Property (TagRecordset Object)

Returns the Server associated with the TagRecordset object.

Syntax

object.**Server**

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String
    ' Get the name of the server
    ServerName = MyRecordset.Server.ServerName
```

Server Property (Tags Object)

Returns the Server associated with the Tags Object.

Syntax

object.**Server**

Parameters

None

Remarks

Server is a read-only property of type Server.

Example

```
Dim ServerName As String

    ' Get the name of the server

    ServerName = MyTags.Server.ServerName
```

ServerName Property (Server Object)

Returns the name of the computer that the server is running on.

Syntax

object.**ServerName**[= *String*]

Parameters

None

Remarks

Server is a read-only property of type String.

ServerName Property (Server Object)

Returns the name of the computer that the server is running on.

Syntax

object.**ServerName**[= *String*]

Parameters

None

Remarks

Server is a read-only property of type String.

ServerTime Property (Server Object)

Returns the current time on the connected server. The system then converts the time from UTC into formatted time based on the ConnectionOptions (TimeOption) setting.

Syntax

object.**ServerTime**

Parameters

None

Servers Property (ServerManager Object)

Maintains a list of registered servers on the client. To connect a listed server, use the Connect Method of a selected Server Object.

Syntax

object.**Servers**

Parameters

None

SetName Property (EnumeratedSets Object)

Returns or defines the name of an Enumerated Set.

Syntax

object.**SetName**

Parameters

None

Returns

String

SimpleEvents Property (OPCFilters Object)

Returns the list of Simple Event Categories being filtered on the Alarm Collector. This list is only applied if isSimpleEventsOn(true) has been called.

Syntax

object.**SimpleEvents**

Parameters

None

SourceAddress Property (Tag Object)

Returns or sets the address used to identify the Tag in the data source. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**SourceAddress**[= *String*]

Parameters

None

SourceAddress Property (TagCriteria Object)

Sets the tag source address to search for in the TagRecordset query.

Syntax

object.**SourceAddress**[= *String*]

Parameters

None

SourceAddress Property (TagFields Object)

Determines whether the SourceAddress field should be returned in the TagRecordset query.

Syntax

object.**SourceAddress**[= *Boolean*]

Parameters

None

SourceAddressSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**SourceAddressSet**[= *Boolean*]

Parameters

None

SourceAddressUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**SourceAddressUpdated**[= *Boolean*]

Parameters

None

Sources Property (OPCFilters Object)

Returns a list of the Sources selected for collection. This list is only applied when isSourceFiltering (true) has been called.

Syntax

object.**Sources**[= *Boolean*]

Parameters

None

SpikeLogic Property (Tag Object)

Returns or sets whether this tag uses the spike logic compression algorithm.

Syntax

object.**SpikeLogic**[= *Boolean*]

Parameters

None

SpikeLogic Property (TagCriteria Object)

Sets the spike logic to search for in the TagRecordset query.

Syntax

object.**SpikeLogic**[= *Boolean*]

Parameters

None

SpikeLogic Property (TagFields Object)

Determines whether the SpikeLogic field should be returned in the TagRecordset query.

Syntax

object.**SpikeLogic**[= *Boolean*]

Parameters

None

SpikeLogicOverride Property (Tag Object)

Returns or sets whether this tag should use the its own Spike Logic setting or the default Collectors setting.

Syntax

object.**SpikeLogicOverride**[= *Boolean*]

Parameters

None

SpikeLogicOverride Property (TagCriteria Object)

Sets the spike logic override to search for in the TagRecordset query.

Syntax

object.**SpikeLogicOverride**[= *Boolean*]

Parameters

None

SpikeLogicOverride Property (TagFields Object)

Determines whether the SpikeLogicOverride field should be returned in the TagRecordset query.

Syntax

object.**SpikeLogicOverride**[= *Boolean*]

Parameters

None

SpikeLogicOverrideSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**SpikeLogicOverrideSet**[= *Boolean*]

Parameters

None

SpikeLogicOverrideUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**SpikeLogicOverrideUpdated**[= *Boolean*]

Parameters

None

SpikeLogicSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**SpikeLogicSet**[= *Boolean*]

Parameters

None

SpikeLogicUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**SpikeLogicUpdated**[= *Boolean*]

Parameters

None

StartTime Property (Archive Object)

Returns the start time of the specified archive. This represents the earliest timestamp for any sample contained in the archive.

Syntax

object.**StartTime**

Parameters

None

StartTime Property (DataCriteria Object)

Returns or sets the start of the time range to retrieve data for in the DataRecordset query.

Syntax

object.**StartTime**[= *Date*]

Parameters

None

StartTime Property (MessageCriteria Object)

Establishes the start time of the MessageRecordset query.

Syntax

object.**StartTime**[= *Date*]

Parameters

None

StartTimeSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.StartTimeSet[ = Boolean]
```

Parameters

None

StartTimeSet Property (MessageCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.StartTimeSet[ = Boolean]
```

Parameters

None

StartTimeShortcut Property (DataCriteria Object)

Returns or sets the start of the time range to retrieve data for in the DataRecordset query. Shortcuts are strings that define absolute or relative times.

The time shortcuts are the following:

Value	Description
(N)ow	The current time (absolute).
(T)oday	Today at midnight (absolute).
(Y)esterday	Yesterday at midnight (absolute).
(D)ays	Number of Days (relative).
(M)in	Number of Minutes (relative).

Value	Description
(H)our	Number of Hours (relative).
(W)EEK	Number of Weeks (relative).
(BOM)	Beginning of this month at Midnight (absolute).
(EOM)	Last Day of this month at Midnight (absolute).
(BOY)	First Day of this year at Midnight (absolute).
(EOY)	Last Day of this year at Midnight (absolute).

Syntax

object.**StartTimeShortcut**[= *String*]

Parameters

None

Example

```
With MyRecordset.Criteria .Tagmask = "*.F_CV" ' Start two days Ago at 8am in the morning
.StartTimeShortcut = "Today-2d+8h" ' End this morning at 8am
.EndTimeShortcut = "Today+8h" End With
```

StartTimeShortcut Property (MessageCriteria Object)

Establishes the start time of the MessageRecordset Query by specifying a time shortcut string versus a date.

The time shortcuts are the following:

Value	Description
(N)ow	The current time (absolute).
(T)oday	Today at midnight (absolute).
(Y)esterday	Yesterday at midnight (absolute).
(D)ays	Number of Days (relative).
(M)in	Number of Minutes (relative).

Value	Description
(H)our	Number of Hours (relative).
(W)EEK	Number of Weeks (relative).
(BOM)	Beginning of this month at Midnight (absolute).
(EOM)	Last Day of this month at Midnight (absolute).
(BOY)	First Day of this year at Midnight (absolute).
(EOY)	Last Day of this year at Midnight (absolute).

Syntax

object.**StartTimeShortcut**[= *String*]

Parameters

None

Example

```
'Set A Start Time For Two Days Ago
MyMessages.Criteria.StartTimeShortcut = "-2d"
```

StartTimeShortcutSet Property (MessageCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**StartTimeShortcutSet**[= *Boolean*]

Parameters

None

State Property (DataStore Object)

Returns or sets the state of data store. For example, Running.

Syntax

object.**State**

Parameters

None

Remarks

`ihDataStoreState`

State Property (DataStore Object)

Returns or sets the state of data store. For example, Running.

Syntax

object.**State**

Parameters

None

Remarks

`ihDataStoreState`

State Property (DataStore Object)

Returns or sets the state of data store. For example, Running.

Syntax

object.**State**

Parameters

None

Remarks

`ihDataStoreState`

StateLowRawValue Property (EnumeratedState Object)

Returns or defines the minimum value of a state when you are using a range of values for a state. For example, if your state value is from 0 to 5 and it is defined as ON, then this would be 0.

Syntax

object.**StateLowRawValue**

Parameters

None

Remarks

```
Variant. Returns the low raw value of the state.
```

StateValue Property (QueryModifiers Object)

Returns or sets the state value to be used when querying data with the StateCount and StateTime calculation modes.

Syntax

object.**StateValue = value**

Status Property (Archive Object)

Returns the status of the specified Archive. This status is typically Current or Active.

Syntax

object.**Status**

Parameters

None

Remarks

Status is a read-only property of type String.

Example

```
' Print Out The Archive Status Debug.Print MyArchive.Status
```

Status Property (Collector Object)

Returns the status of the specified Collector. This status is typically Running or Stopped.

Syntax

object.**Status**

Parameters

None

Remarks

Status is a read-only property of type String.

Example

```
' Print Out The Collector Status Debug.Print MyCollector.Status
```

StepValue Property (Tag Object)

Returns or sets whether this tag is using Step Value or not.

Syntax

object.**StepValue**[= *Boolean*]

Parameters

None

StepValue Property (TagCriteria Object)

Sets the Step Value value to search for in the TagRecordset query.

Syntax

object.**StepValue**[= *Boolean*]

Parameters

None

StepValue Property (TagFields Object)

Determines whether the StepValue field should be returned in the TagRecordset query.

Syntax

object.**StepValue**[= *Boolean*]

Parameters

None

StepValueSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**StepValueSet**[= *Boolean*]

Parameters

None

StepValueUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**StepValueUpdated**[= *Boolean*]

Parameters

None

StorageType Property (DataStore Object)

Returns the type of data store. For example, ScadaBufferStore or Historical data store.

Syntax

object.**StorageType**

Parameters

None

Remarks

ihDataStorageType

StoreMilliseconds Property (Tag Object)

Returns or sets the time resolution of the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**StoreMilliseconds**[= *Boolean*]

Parameters

None

StoreMilliseconds Property (TagCriteria Object)

Sets the time resolution to search for in the TagRecordset query.

Syntax

object.**StoreMilliseconds**[= *Boolean*]

Parameters

None

StoreMilliseconds Property (TagFields Object)

Determines whether the StoreMilliseconds field should be returned in the TagRecordset query.

Syntax

object.**StoreMilliseconds**[= *Boolean*]

Parameters

None

StoreMillisecondsSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**StoreMilliseconds**[= *Boolean*]

Parameters

None

StoreMillisecondsUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**StoreMillisecondsUpdated**[= *Boolean*]

Parameters

None

StoreOPCQuality Property (Server Object)

Returns or sets whether the server stores the raw (16-bit) OPC quality flags.

Syntax

object.**StoreOPCQuality**[= *Boolean*]

Parameters

None

Strict Client Authentication Property

Returns or sets whether to enforce strict client authentication. Setting this value to TRUE will disallow connections from clients older than version 4.7.

Syntax

object.**StrictClientAuthentication**

Parameters

None

Strict Collector Authentication (Archives Object)

Returns or sets whether to enforce strict client authentication. Setting this value to TRUE will disallow connections from clients older than version 4.7.

Syntax

object.**StrictCollectorAuthentication**

Parameters

None

StringLength Property (Tag Object)

Returns or sets the fixed string length associated with a fixed string type Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**StringLength**[= *Byte*]

Parameters

None

StringLength Property (TagFields Object)

Determines whether the StringLength field should be returned in the TagRecordset query.

Syntax

object.**StringLength**[= *Boolean*]

Parameters

None

StringLengthSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**StringLengthSet**[= *Boolean*]

Parameters

None

StringLengthUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**StringLengthUpdated**[= *Boolean*]

Parameters

None

SubscribeStatus Property (Archives Object)

Subscribes to changes in Archive status and configuration. The Historian server publishes messages to any client signed up for Archive status changes as modifications are committed to the Archive Database. Setting the SubscribeStatus to True signs up for status and configuration changes on all archives.

Status and configuration changes are reported asynchronously to the client through the `Status_Received` event of the Archives object.

Syntax

```
object.SubscribeStatus[ = Boolean]
```

Parameters

None

Example

```
' Subscribe To Archive Status Updates

    MyArchives.SubscribeStatus = True

' Unsubscribe To Archive Status Updates

    MyArchives.SubscribeStatus = False
```

SubscribeStatus Property (Collectors Object)

Subscribes to changes in Collector status and configuration. The Historian server publishes messages to any client signed up for Collector status changes as modifications are committed to the Collector database. Setting the `SubscribeStatus` to `True` will sign up for status and configuration changes on all Collectors.

Status and configuration changes are reported asynchronously to the client through the `Status_Received` event of the Collectors object.

Syntax

```
object.SubscribeStatus[ = Boolean]
```

Parameters

None

Example

```
' Subscribe To Collector Status Updates

    MyCollectors.SubscribeStatus = True

' Unsubscribe To Collector Status Updates

    MyCollectors.SubscribeStatus = False
```

Substitutions Property (Message Object)

Returns the variable text of a message such as timestamps, usernames, and tagnames.

Syntax

object.**Substitutions**

Parameters

None

Remarks

Substitutions is a read-only property of type String.

Example

```
Dim MySubstitutions As Collection Dim I As Integer Set MySubstitutions = MyMessage.Substitutions
For I = 1 To MySubstitutions.count Debug.Print MySubstitutions(I) Next I
```

Substitutions Property (MessageFields Object)

Determines whether the Substitutions should be returned in the MessageRecordset query.

Syntax

object.**Substitutions**[= *Boolean*]

Parameters

None

Example

```
Dim MyMessages As iHistorian_SDK.MessageRecordset Set MyMessages = GetServer.Messages.NewRecordset
With
MyMessages.Fields .Topic = True .TimeStamp = True .MessageString = True .Substitutions = True
End With
```

T

Tagmask Property (DataCriteria Object)

Returns or sets a mask of tags to retrieve data for in the DataRecordset query. The tag mask may include wildcard characters including the "*" and "?".

Syntax

object.**Tagmask**[= *String*]

Parameters

None

T

TagmaskSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**TagmaskSet**[= *Boolean*]

Parameters

None

Tagname Property (Tag Object)

Returns the Tagname property of the Tag. Tagname is a read-only property.

Syntax

object.**Tagname**[= *String*]

Parameters

None

Remarks

Tagname is a read-only property of type String.

Tagname Property (Tag Object)

Returns the Tagname property of the Tag. Tagname is a read-only property.

Syntax

object.**Tagname**[= *String*]

Parameters

None

Remarks

Tagname is a read-only property of type String.

Tagname Property (TagCriteria Object)

Sets the Tagname or tag mask to search for in the TagRecordset query. The Tagname may include wildcard characters.

Syntax

```
object.Tagname[ = String]
```

Parameters

None

Tagname Property (TagFields Object)

Determines whether the Tagname field should be returned in the TagRecordset query.

Syntax

```
object.Tagname[ = Boolean]
```

Parameters

None

TagnameSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.TagnameSet[ = Boolean]
```

Parameters

None

TagnameUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

```
object.TagnameUpdated[ = Boolean]
```

Parameters

None

Tags Property (DataCriteria Object)

Returns or sets an array of Tagnames to retrieve data for in the DataRecordset query.

Syntax

object.**Tags**[= *Variant*]

Parameters

None

Tags Property (DataRecordset Object)

Exposes the list of Tagnames associated with the collection of DataValue results maintained in the DataRecordset object. The Item property takes a tagname or tag index as a parameter to expose the collection of DataValues for that tag. The first collection of DataValues in the Item property.

Syntax

object.**Tags**

Parameters

None

Remarks

Tags is a read-only property of type Collection of String.

Tags Property (Server Object)

Returns the Tags object for the current server, but only if the authenticated user is a member of the Historian tag administrators group.

Syntax

object.**Tags**

Parameters

None

TagsSet Property (DataCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**TagsSet**[= *Boolean*]

Parameters

None

TimeStamp Property (DataFields Object)

Determines whether the Timestamp field should be returned in the DataRecordset query.

Syntax

object.**TimeStamp**[= *Boolean*]

Parameters

None

TimeStamp Property (DataValue Object)

Returns the timestamp of the DataValue in a localized time.

Syntax

object.**TimeStamp**

Parameters

None

Remarks

TimeStamp is a read-only property of type Date.

TimeStamp Property (Message Object)

Returns the time the Message was created.

Syntax

object.**TimeStamp**[= *Date*]

Parameters

None

Remarks

TimeStamp is a writeable property of type Date.

TimeStamp Property (MessageFields Object)

Determines whether the TimeStamp field should be returned in the MessageRecordset query.

Syntax

object.**TimeStamp**[= *Boolean*]

Parameters

None

TimeStampType Property (Tag Object)

Returns or sets the type of time stamping applied to data at collection time.

Name	Description	Value
Source	New values take timestamp from data source.	1
Collector	New values are timestamped by Collector.	2

Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**TimeStampType**[= *ihTimeStampType*]

Parameters

None

TimeStampType Property (TagCriteria Object)

Sets the timestamp type to search for in the TagRecordset query.

Syntax

object.**TimeStampType**[= *Boolean*]

Parameters

None

TimeStampType Property (TagFields Object)

Determines whether the TimeStampType field should be returned in the TagRecordset query.

Syntax

object.**TimeStampType**[= *Boolean*]

Parameters

None

TimeStampTypeSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**TimeStampTypeSet**[= *Boolean*]

Parameters

None

TimeStampTypeUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**TimeStampTypeUpdated**[= *Boolean*]

Parameters

None

TimeZoneBias Property (Tag Object)

Returns or sets the time zone bias for the tag. Time zone bias is used to indicate the natural time zone of the tag expressed as an offset from GMT in minutes. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**TimeZoneBias**[= *Long*]

Parameters

None

TimeZoneBias Property (TagCriteria Object)

Sets the time zone bias to search for in the TagRecordset query.

Syntax

object.**TimeZoneBias**[= *Long*]

Parameters

None

TimeZoneBias Property (TagFields Object)

Determines whether the TimeZoneBias field should be returned in the TagRecordset query.

Syntax

object.**TimeZoneBias**[= *Boolean*]

Parameters

None

TimeZoneBiasUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**TimeZoneBiasUpdated**[= *Boolean*]

Parameters

None

TimeZoneBiasSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**TimeZoneBiasSet**[= *Boolean*]

Parameters

None

TimestampTypeList Property (Tags Object)

Returns a list of the valid Timestamp types available in Historian.

Syntax

object.**TimestampTypeList**

Parameters

None

Topic Property (Message Object)

Returns the Topic Number of the Message.

Syntax

object.**Topic**[= *ihMessageTopic*]

Parameters

None

Remarks

Topic is a writeable property of type *ihMessageTopic*.

Example

```
If MyMessage.Topic = ihMessageTopic.General Then Debug.Print "This is a General Message" End If
```

Topic Property (MessageCriteria Object)

Establishes which Topic the MessageRecordset query will filter by.

Syntax

object.**Topic**[= *ihMessageTopic*]

Parameters

None

Remarks

Topic is a writeable property of type ihMessageTopic.

Example

```
MyMessages.Criteria.Topic = ihMessageTopic.General
```

Topic Property (MessageFields Object)

Determines whether the Topic field should be returned in the MessageRecordset query.

Syntax

object.**Topic** [= *Boolean*]

Parameters

None

Remarks

Topic is a writeable property of type ihMessageTopic.

Example

```
Dim MyMessages As iHistorian_SDK.MessageRecordset Set MyMessages = GetServer.Messages.NewRecordset With
MyMessages.Fields .Topic = True End With
```

TopicList Property (Messages Object)

Returns a list of available Topics.

Syntax

object.**TopicList**(*[IncludeMessages]*, *[IncludeAlerts]*)

Parameters

Name	Data Type	Description
IncludeMessages	Boolean	Indicates whether Message topics should be included in the returned list

Name	Data Type	Description
IncludeAlerts	Boolean	Indicates whether Alert topics should be included in the returned list

TopicName Property (Message Object)

Returns the Topic Name of the Message.

Syntax

object.**TopicName**

Parameters

None

Remarks

Topic is a writeable property of type String.

Example

```
Debug.Print "This is a " + MyMessage.TopicName + " message."
```

TopicSet Property (MessageCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**TopicSet**[= *Boolean*]

Parameters

None

TrackingEvents Property (OPCFilters Object)

Returns the list of Tracking Event Categories being filtered on the Alarm Collector. This list is only applied if `isTrackingEventsOn(true)` has been called.

Syntax

object.**TrackingEvents**

Parameters

None

Property Reference U-V

U

UserName Property (Message Object)

Returns the username who generated the message, or who the message is associated with.

Syntax

`object.UserName[= String]`

Parameters

None

Remarks

UserName is a writeable property of type String.

UserName Property (MessageFields Object)

Determines whether the UserName field should be returned in the MessageRecordset query.

Syntax

`object.UserName[= Boolean]`

Parameters

None

UserName Property (Server Object)

Returns the name of the currently authenticated user for the server.

Syntax

`object.UserName`

Parameters

None

UsernameSet Property (MessageCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**UserNameSet**[= *Boolean*]

Parameters

None

V

Value Property (DataFields Object)

Determines whether the Value field should be returned in the DataRecordset query.

Syntax

object.**Value**[= *Boolean*]

Parameters

None

Value Property (DataValue Object)

Returns or sets the value of the DataValue.

Syntax

object.**Value**[= *Variant*]

Parameters

None

Value Property (Option Object)

The value parameter of this option expressed as a localized string.

Syntax

object.**Value**[= *Variant*]

Parameters

None

Version Property (Server Object)

Returns the server or client version number.

Syntax

object.**Version**(*[API]*)

Parameters

Name	Data Type	Description
API	Boolean	<p>When True, the server version is returned. When False, the client version is returned. The default is False. '</p> <p>When connecting to an Historian v1.0 server and passing True, Historian returns "Unknown" for the version number.</p>

Remarks

Version is a read-only property of type String.

Property Reference W-Z**W****WatchdogTag Property (Collector Object)**

Returns or sets the collector redundancy watchdog tag name.

Syntax

object.**WatchdogTag**[= *String*]

Parameters

None

WatchdogValueMaxUnchangedPeriod Property (Collector Object)

Returns or sets the time in seconds when the collector should automatically failover if a raw sample is not received for the watchdog tag from the primary collector. Use with FailoverOnValueUnchanged property.

Syntax

object.**WatchdogValueMaxUnchangedPeriod**[= *Long*]

Parameters

None

WriteSecurityGroup Property (Tag Object)

Sets the name of the security group controlling the writing of data for the Tag. Changes to tag properties are not committed until you call the WriteRecordset method of the TagRecordset object.

Syntax

object.**WriteSecurityGroup**[= *String*]

Parameters

None

WriteSecurityGroup Property (TagCriteria Object)

Sets the write security group to search for in the TagRecordset query.

Syntax

object.**WriteSecurityGroup**[= *String*]

Parameters

None

WriteSecurityGroup Property (TagFields Object)

Determines whether the WriteSecurityGroup field should be returned in the TagRecordset query.

Syntax

object.**WriteSecurityGroup**[= *Boolean*]

Parameters

None

WriteSecurityGroupSet Property (TagCriteria Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**WriteSecurityGroupSet**[= *Boolean*]

Parameters

None

WriteSecurityGroupUpdated Property (Tag Object)

A flag to indicate whether this property has been set or not.

Syntax

object.**WriteSecurityGroupUpdated**[= *Boolean*]

Parameters

None

Method Reference A-B

APIStatusToString Method (Server Object)

Converts a status ID into a string.

Syntax

object.**APIStatusToString**(nStatus, bHRESULT)

Table 271. Parameters

Name	Data Type	Description
nStatus	Long	The status ID to be converted.
bHRESULT	Boolean	If true, then the status ID is an HRESULT; otherwise, it is an APIStatus.

Returns

String. The translation of the status code.

Add Method (Archives Object)

Adds a new archive with the specified characteristics to the Historian server. You can also use this method to add an existing archive file to the archives collection to restore an archive.

Specify the FileLocation in the context of the Historian server machine drive and directory structure. If the specified FileLocation points to an existing valid Historian archive, the method effectively re-registers this archive and automatically loads it. Use this method when you return a previously unloaded archive to the system.

Since the Add request is synchronous, it immediately creates a new Archive object on the Historian server and another one in the Archives collection on the client.

Syntax

```
object.Add(ArchiveName As String, FileLocation As String, FileSize As Long,
ArchiveDataStoreName As String)
```

Table 272. Parameters

Name	Data Type	Description
ArchiveName	String	Name of the archive to add (Read-Only).
FileLocation	String	Fully qualified name of the archive file (Read-Only).
FileSize	Long	Size of archive in MB (Read-Only).
ArchiveDataStore-Name	String	Name of the archive data store the archive belongs to. This is an optional parameter.

Returns

Archive. The newly added Archive object or Nothing.

Add Method (Collectors Object)

Adds a new collector with the specified name to the Historian server. The collector name must be unique in a given Historian server.

Since the Add request is synchronous, it immediately creates a new Collector Object on the Historian server and another one in the Collectors collection on the client.

Syntax

object.**Add**(CollectorName)

Table 273. Parameters

Name	Data Type	
CollectorName	String	Name of the new collector to add. (Read-only)

Returns

Collector. Returns a reference to the newly created Collector object.

Add Method (DataRecordset Object)

Adds a new blank DataValue record to the current DataRecordset for the specified tag. The DataValue is written to the server when the WriteRecordset method of the DataRecordset object is called. You can optionally specify the value of the record or specify it after creation by operating on the DataValue object.

Syntax

object.**Add**(Tagname, TimeStamp, [InValue])

Table 274. Parameters

Name	Data Type	Definition
Tagname	String	Tag to which you are adding a new data value (read-only).
TimeStamp	Date	Timestamp to add value at (read-only).
InValue	DataValue	New value (optional).

Returns

DataValue. Returns a reference to the newly created data value.

Add Method (DataStores Object)

Adds a data store.

Syntax

object.**Add**(MyDataStoreName,MyDefaultDS, MyDataStoreType, MyDataStoreDescription)

Table 275. Parameters

Name	Data Type	
DataStoreName	String	Indicates the name of the data store.
IsDefault	Boolean	Indicates whether the data store is the default data store.
DataStoreType	String	Indicates the type of the data store: Historical, User, or SCADA buffer.
Description	String	The description provided for the data store.

Returns

DataStore.

Add Method (EnumeratedSets Object)

Adds an enumerated set to the Enumerated Sets collection. The enumerated set is not added to the Historian Server until the SaveSet Method is called.

Syntax

object.**Add**(MySet)

Table 276. Parameters

Name	Data Type	Description
MySet	EnumeratedSet	The set that has to be added.

Returns

None.

Add Method (EnumeratedStates Object)

Adds an enumerated state to the enumerated set collection. The enumerated state is not added to the Historian Server until the SaveSet Method is called.

Syntax

Object.**Add**(MyState)

Table 277. Parameters

Name	Data Type	Description
MyState	EnumeratedState	The state that has to be added.

Returns

None.

Add Method (MessageRecordset Object)

Adds a new blank message record to the current MessageRecordset. The message is written to the server when the WriteRecordset method of the MessageRecordset object is called.

Syntax

object.Add

Parameters

None

Returns

The empty message that was added.

Add Method (TagDependencies Object)

Adds a dependent Tag to the current calculation. The calculation will be triggered when the value of this tag changes.

Syntax

object.Add(Tagname)

Table 278. Parameters

Name	Data Type	Description
Tagname	String	Name of the tag to add

Returns

Boolean. Whether the Add operation succeeded.

Add Method (TagRecordset Object)

Adds a new blank tag record to the current TagRecordset. The tag is written to the server when the WriteRecordset method of the TagRecordset object is called.

Syntax

object.**Add**(Tagname)

Table 279. Parameters

Name	Data Type	Description
Tagname	String	Name of the tag to add

Returns

Returns a reference to the newly created tag.

Add Method (UserDefinedtypeFields Object)

Adds multiple fields to the User Defined Type. The User Defined Type is not added to the Historian Server until the SaveSet Method is called.

Syntax

object.**Add**(MyField)

Table 280. Parameters

Name	Data Type	Description
MyField	UserDefinedType-Field	The field to be added.

Returns

None.

AddComment Method (DataValue Object)

Adds a comment to the current DataValue. If you supply a secondary username and password, the SDK authenticates the username and password before the committing the comment.

Syntax

object.**AddComment**(Comment, [DataTypeHint], [SecondaryUser], [SecondaryPassword])

Table 281. Parameters

Name	Data Type	Description
Comment	Variant	The comment to add.
DataTypeHint	String	The name of the data type for the comment (optional, read-only).
SecondaryUser	String	Supervisor's username to sign comment (optional, read-only).
SecondaryPassword	String	Supervisor's password to sign comment (optional, read-only).

Returns

Boolean. Returns True if the AddComment Method operation succeeded.

AddEx Method (Archives Object)

Adds a new archive with the specified characteristics to the Historian server. You can also use this method to add an existing archive file to the archives collection to restore an archive.

Specify the FileLocation in the context of the Historian server machine drive and directory structure. If the specified FileLocation points to an existing valid Historian archive, the method effectively re-registers this archive and automatically loads it. Use this method when you return a previously unloaded archive to the system.

Since the Add request is synchronous, it immediately creates a new Archive object on the Historian server and another one in the Archives collection on the client.

The window pointed to by hWnd is kept alive (messages processed) while the archive is being added.

Syntax

object.**AddEx**(ArchiveName As String, FileLocation As String, FileSize As Long, hWnd As Long, ArchiveDataStoreName As String)

Table 282. Parameters

Name	Data Type	Description
ArchiveName	String	Name of the archive to add (Read-Only).
FileLocation	String	Fully qualified name of the archive file (Read-Only).
FileSize	Long	Size of archive in MB (Read-Only).
hWnd	Long	The window handle to keep alive.
ArchiveDataStore-Name	String	Name of the archive data store the archive belongs to. This is an optional parameter.

Returns

Archive. The newly added Archive object or Nothing.

AddServer Method (ServerManager Object)

Registers a new server to the list of registered servers on the client. It makes an attempt to authenticate the connection based on the username and password supplied. If a username and password are not supplied, it assumes the user to be the currently authenticated domain user.

If it cannot authenticate the connection, because of incorrect user information or an invalid ServerName, the AddServer method returns False and does not register the supplied ServerName on the client.

Syntax

object.**AddServer**(ServerName, [UserName], [Password], [ConnectionTimeout])

Table 283. Parameters

Name	Data Type	Description
ServerName	String	Computer name of the Historian server (read-only).
UserName	String	Username to authenticate (optional, read-only).
Password	String	Password to authenticate (optional, read-only).
Connection-Timeout	Long	The maximum length of time clients should wait for messages from the server before concluding the server is unavailable (optional, read-only).

Returns

Boolean. Returns True if the AddServer operation succeeded.

Example

```
Dim MyManager As New iHistorian_SDK.ServerManager
Dim MyServer As iHistorian_SDK.Server
' Try to add the new server
If MyManager.AddServer("USGB014") Then
Set MyServer = MyManager.Servers("USGB014") Else
err.Raise 1, , "Failed to authenticate new server" End If
```

AlarmAttributesRecordSet Method (Alarms Object)

This function returns a list of all the Vendor Attributes in the Alarm Archiver.

Syntax

object.**AlarmAttributesRecordSet**

Parameters

None.

Returns

AlarmAttributes. The AlarmAttributes object contains the list of vendor attributes.

AlarmRecordSet Method (Alarms Object)

This function is used to query alarms or events from the archiver. This function takes one parameter, an AlarmOpenRecordSetInfo object, which specifies the query. The following sections describe how to populate this object to perform an Alarm or Event query.

AlarmOpenRecordSetInfo Parameter

This object contains details on what to select, and any filters for the query. After creating the object, you first specify which fields to select, and which fields to sort (SelectFields), and then specify any criteria/filter to apply (AlarmCriteria).

Create the object: `Dim myAlarmOpenRecordSetInfo As New AlarmOpenRecordSetInfo`

Alarm Fields

The following is a list of the alarm fields that can be returned in the recordset, or used to sort or filter the recordset. These are used in the SelectFields and AlarmCriteria object (see below for more details).

Table 284.

Option	Data Type	Description
AlarmID	Long	The unique ID of the alarm or event in the Historian alarm database.
ItemID	String	The OPC ItemID of the alarm. This contains the source address of the data access tag the alarm is associated with. This could contain a NULL value if the alarm is not associated with a tag.
Source	String	This is the unique identifier used by the OPC AE Collector for the alarm or event.
DataSource	String	The collector interface name associated with the alarm or event.
TagName	String	The Historian Tag Name associated with the alarm. The tag name will be NULL unless the tag is also collected by Historian.
EventCategory	String	The OPC event category of the alarm or event.
ConditionName	String	The OPC condition of the alarm. This does not apply to event data. This, combined with the Source, comprises an alarm.
SubCondition-Name	String	The OPC sub-condition of the alarm. This does not apply to event data. This is the state of the alarm.
StartTime	Date	The start time or time stamp of the alarm or event.
EndTime	Date	The end time of the alarm. This does not apply to event data.
AckTime	Date	The time the alarm was acknowledged. This does not apply to event data.

Table 284. (continued)

Option	Data Type	Description
Timestamp	Date	The time stamp of the alarm or event.
Message	String	The message attached to the alarm or event.
Acked	Boolean	Stores the acknowledgement status of the alarm. If the alarm is acknowledged, this will be set to TRUE.
Severity	Long	The severity of the alarm or event. This is stored as an integer value with a range of 1-1000.
Actor	String	The operator who acknowledged the alarm, or caused the tracking event.
Quality	String	The quality of the alarm or event.

AlarmOpenRecordSetInfo.SelectFields

Each of the fields above can be selected, or used to sort the alarm recordset. Fill in the AlarmOpenRecordSetInfo.SelectFields for each field, according to the following table.

Option	Data Type	Description
Select	Boolean	True to select the field.
OrderBy	Boolean	True to order by the field.
OrderPriority	Integer	Relative priority compared to other field order priorities. Highest first. Ties are random.
Descending	Boolean	True to sort descending. OrderBy must also be True.

Example

Set up SelectFields to select the AlarmId and ItemId. Order by the AlarmId, then the ItemId.

```
myAlarmOpenRecordSetInfo.SelectFields.AlarmId.Select = TRUE
myAlarmOpenRecordSetInfo.SelectFields.AlarmId.OrderBy = TRUE
myAlarmOpenRecordSetInfo.SelectFields.AlarmId.OrderPriority = 10
myAlarmOpenRecordSetInfo.SelectFields.ItemId.Select = TRUE
```

```
myAlarmOpenRecordSetInfo.SelectFields.ItemId.OrderBy = TRUE
myAlarmOpenRecordSetInfo.SelectFields.ItemId.OrderPriority = 20
```

The SelectFields object has one other field, AllFields, which can be used to select all fields.

```
SelectFields.AllFields = TRUE
```

Choose Query Type

For all queries, the type of query should be specified. If it is not specified, the default is to return a record set containing the events. The query type is specified by setting the AlarmOpenRecordSetInfo.AlarmCriteria.AlarmType object.

```
Query Alarms: myAlarmOpenRecordSetInfo.AlarmType = ihALARM_CONDITION
Query Events: myAlarmOpenRecordSetInfo.AlarmType = ihALARM_TRACKING
Query Historical Alarm Transitions: myAlarmOpenRecordSetInfo.AlarmType = ihALARM_CONDITION_HIST
```

Add filters

Similar to the SelectFields object, each field listed above (Alarm Fields) can have criteria associated with it. This criteria is used to filter the record set, so for example, you can ask for all alarms with severity greater than 500. The type of Criteria that can be applied is dependant on the Data Type of the field. The following table lists the available criteria:

Field Data Type	Criteria Types
Integer/Long	Min, Max, Equal, NotEqual
Float	Min, Max, Equal, NotEqual
String	StringMask
Quality	Min, Max, Equal, NotEqual

For example, the Severity field is of type Long. Therefore, Min, Max, Equal, or NotEqual criteria can be specified for the severity. To query where severity is greater than 500:

```
myAlarmOpenRecordSetInfo.AlarmCriteria.SeverityCriteria.Min = 500
```

Specify Max Records

An optional criteria, MaxRecords, can be set to set the upper limit size of the recordset.

Example: Return the first 10 records:

```
myAlarmOpenRecordSetInfo.AlarmCriteria.MaxRecords = 10
```



Note:

To avoid having random rows returned, if you specify a MaxRecords criteria, you should generally also specify an Order By (see SelectFields above).

Syntax

object.**AlarmRecordSet**(theAlarmOpenRecordSetInfo)

Table 285. Parameters

Name	Data Type	Description
theAlarmOpenRecordSetInfo	Variant	See above for details.

Returns

AlarmRecordset. An AlarmRecordset object, populated according the details specified in the AlarmOpenRecordSetInfo parameter.

Example

```
Dim MyServer As iHistorian_SDK.Server
Set MyServer = GetServer

Dim myAlarmOpenRecordSetInfo As AlarmOpenRecordSetInfo
' Select the last 100 alarms in the alarm history table
myAlarmOpenRecordSetInfo.SelectFields.AllFields = True
myAlarmOpenRecordSetInfo.SelectFields.Timestamp.OrderBy = True
myAlarmOpenRecordSetInfo.SelectFields.Timestamp.Descending = True
myAlarmOpenRecordSetInfo.AlarmCriteria.AlarmType = ihALARM_CONDITION_HIST
myAlarmOpenRecordSetInfo.AlarmCriteria.MaxRecords = 100

Dim myAlarmRecordSet As AlarmRecordSet
Set myAlarmRecordSet = MyServer.Alarms.AlarmRecordSet(myAlarmOpenRecordSetInfo)
```

AllFields Method (DataFields Object)

Specifies that all DataFields should be returned in the DataRecordset query.

Syntax

Syntax object.**AllFields**

Parameters

None.

Returns

None.

AllFields Method (MessageFields Object)

Specifies that all MessageFields should be returned in the MessageRecordset query.

Syntax

object.**AllFields**

Parameters

None.

Returns

None.

AllFields Method (TagFields Object)

Sets all fields for retrieval in the TagRecordset query.

Syntax

object.**AllFields**

Parameters

None.

Returns

None.

Backup Alarms Method

Backs up or saves a copy of the alarms to an offline file.

Syntax

object.**BackupAlarms****Table 286. Parameters**

Name	Data Type	Description
BackupFile	String	The file that stores the backup alarm data.
StartTime	Date	Start time of the alarm data.
EndTime	Date	End time of the alarm data.

Returns

Boolean. Returns TRUE if the alarms are backed up.

Example

```

Dim Status As ihStatus

Dim ReturnStatus As Boolean

Dim AlarmsStartTime As ihTimeStruct

Dim AlarmsEndTime As ihTimeStruct Status = ihSTATUS_FAILED ReturnStatus = False

AlarmsStartTime = Date_To_UTC(StartTime) AlarmsEndTime = Date_To_UTC(EndTime)

On Error GoTo errc

Status = ihBackupAlarms(MyServer.Handle, BackupFile, AlarmsStartTime, AlarmsEndTime, 0)

If Status <> ihSTATUS_OK Then err.Raise 1, , "Error while performing Backup alarms [" +
    ErrorDescription(Status) ReturnStatus = True

BackupAlarms = ReturnStatus errc:

zLastError = "Backup Alarms >> " + err.Description

BackupAlarms = ReturnStatusEnd Function

```

Backup Method (Archive Object)

Performs an online backup of the specified archive by stopping inbound data flow and copying an image of the specified archive into the file identified by the BackupFileName parameter.

When the online backup operation completes, the archive returns to normal operation and accepts inbound data flow.

Syntax

object.**Backup**(BackupFileName As String, Optional DataStoreName As String)

Table 287. Parameters

Name	Data Type	Description
BackupFileName	String	Fully qualified name of the backup file (read-only).
DataStoreName	String	Name of the data store to which the backup file belongs. This is an optional parameter.

Returns

Boolean. Returns whether or not the BackupFile operation succeeded.

Example

```

Dim BackupFilename As String

BackupFilename = ArchiverLauncher.Archives & "\TheCurrentArchive.ZIP"

Set MyArchives = GetServer.Archives

' Find The Current Archive, Then Initiate A Backup

With MyArchives

  For I = 1 To .Item.count

    If .Item(I).IsCurrent Then

      If Not .Item(I).Backup(BackupFilename) Then

        err.Raise 1, "Backup", "Backup Failed"

      End If

    End If

  Next I

End With

```

BackupEx Method (Archive Object)

Performs an online backup of the specified archive by stopping inbound data flow and copying an image of the specified archive into the file identified by the BackupFileName parameter.

When the online backup operation completes, the archive returns to normal operation and accepts inbound data flow.

The Ex method will process messages for a client window while waiting for the backup to complete (so clients do not appear to be frozen).

Syntax

object.**BackupEx**(BackupFileName As String, hWnd As Long, DataStoreName As String)

Table 288. Parameters

Name	Data Type	Description
BackupFileName	String	Fully qualified name of the backup file (read-only)
hWnd	Long	The handle of the window to keep alive.
DataStoreName	String	Name of the data store. This is an optional parameter.

Returns

Boolean. Returns whether or not the BackupFile operation succeeded.

Example

```
Dim BackupFilename As String

BackupFilename = ArchiverLauncher.Archives & "\TheCurrentArchive.ZIP" Set MyArchives =
GetServer.Archives

' Find The Current Archive, Then Initiate A Backup

With MyArchives

  For I = 1 To .Item.count

    If .Item(I).IsCurrent Then

      If Not .Item(I).Backup(BackupFilename)

        Then err.Raise 1, "Backup", "Backup Failed"

      End If

    End If

  Next I

End With
```

Browse Method (OPCBrowse Object)

Populates the Browse Object with sources and areas for the current browse position.

Syntax

object.**Browse**(theServer, theCollector)

Table 289. Parameters

Name	Data Type	Description
theServer	Variant	The Server Object for the Historian Server.
theCollector	Variant	The Collector Object for the Collector to Browse.

Returns

Boolean. Returns whether or not the Browse operation succeeded.

BrowseCollector Method (TagRecordset Object)

Browses a collector for its available tags.

Syntax

object.**BrowseCollector**(CollectorName, AdditionsOnly, SourceFilter, DescriptionFilter, [BrowsePosition], [Recursive])

Table 290. Parameters

Name	Data Type	Description
CollectorName	String	The name of the collector to browse.
AdditionsOnly	Boolean	Browse only tags that are additions to the Historian server.
SourceFilter	String	The tag source address filter.
DescriptionFilter	String	The tag description filter.
BrowsePosition	String	The browse position when performing an OPC hierarchical browse (optional, default = "").
Recursive	Boolean	Whether to perform an OPC hierarchical browse (optional, default = False).

Returns

Boolean. Success/Failure.

BrowseTags Method (Collector Object)

BrowseTags is available for collection in the data source. The tags can then be added to the archiver using the WriteRecordSet Method.

Syntax

object.**BrowseTags**([AdditionsOnly], [SourceFilter], [DescriptionFilter], [BrowsePosition], [Recursive])

Table 291. Parameters

Name	Data Type	Description
AdditionsOnly	Boolean	Browse only tags that are additions to the Historian server (optional, default = True).
SourceFilter	String	The tag source address filter (optional, default = "").
DescriptionFilter	String	The tag description filter (optional, default = "").
BrowsePosition	String	The browse position when performing an OPC hierarchical browse (optional, default = "").
Recursive	Boolean	Whether to perform an OPC hierarchical browse (optional, default = False).

Returns

TagRecordset. Returns a reference to the tag record that resulted from browsing the selected collector.

Example

```
Dim MyNewTags As iHistorian_SDK.TagRecordset

' Request The Collector To Browse Its Tag Source

Set MyNewTags = MyCollectors.Item("USIM031_OPC1").BrowseTags

' Modify Tag Records In Recordset To Add Additional Configuration Information

' Go Ahead And Add New Tags To System

If Not MyNewTags.WriteRecordset Then

    err.Raise 1, , "TagRecordset.WriteRecord failed: " + MyNewTags.LastError

End If
```

Method Reference C-D

C

Clear Method (DataCriteria Object)

Clears any previously supplied criteria for the DataRecordset query. Use this method to initialize the DataRecordset query.

Syntax

object.**Clear**

Parameters

None.

Returns

None.

Clear Method (DataFields Object)

Clears all DataFields from being returned in the DataRecordset query. Use this method to initialize the DataRecordset query.

Syntax

object.**Clear**

Parameters

None.

Returns

None.

Clear Method (Enumerated Sets Object)

Applies to:

Clears all the elements from the EnumeratedSets collection object and create a new instance of the EnumeratedSets collection.

Syntax

object.**Clear**

Parameters

None.

Returns

None.

Clear Method (EnumeratedStates Object)

Applies to:

Clears all the states from the enumerated set collection.

Syntax

object.**Clear**

Parameters

None.

Returns

None.

Clear Method (MessageCriteria Object)

Clears all previously supplied criteria for the MessageRecordset query. Use this method to initialize the MessageRecordset query.

Syntax

object.**Clear**

Parameters

None.

Returns

None.

Clear Method (MessageFields Object)

Clears all previously supplied criteria for the MessageRecordset query. Use this method to initialize the MessageRecordset query.

Syntax

object.**Clear**

Parameters

None.

Returns

None.

Clear Method (TagCriteria Object)

Clears previously entered criteria for the TagRecordset query. Use this method to initialize the TagRecordset query.

Syntax

object.**Clear**

Parameters

None.

Returns

None.

Clear Method (TagFields Object)

Clears all fields for retrieval in the TagRecordset query.

Syntax

object.**Clear**

Parameters

None.

Returns

None.

Returns**Clear Method (UserDefinedTypeFields Object)**

Applies to:

Clears all the fields from the User Defined Type.

Syntax

object.**Clear**

Parameters

None.

Returns

None.

Returns**ClearRecordset Method (DataRecordset Object)**

Clears specific records from the DataRecordset without deleting them from the Historian server.

You can specify a tagname to remove all DataValues for a specific tag, or supply a specific timestamp to remove a single DataValue.

**CAUTION:**

You can clear the entire DataRecordset by omitting both the tagname and timestamp.

Syntax

object.**ClearRecordset**([Tagname], [TimeStamp])

Table 292. Parameters

Name	Data Type	Description
Tagname	String	Tag to clear records for (optional, read-only).

Table 292. Parameters (continued)

Name	Data Type	Description
TimeStamp	Date	Timestamp to clear records for (optional, read-only).

Returns

Boolean. Returns True if the ClearRecordset operation succeeded.

ClearRecordset Method (TagRecordset Object)

Clears specific records from the TagRecordset without deleting them from the Historian server. You can specify a tagname to delete a specific record.

**CAUTION:**

You can clear the entire TagRecordset by omitting the tag name.

Syntax

object.**ClearRecordset**([Tagname])

Table 293. Parameters

Name	Data Type	Description
Tagname	String	Name of tag to remove from record set (read-only, optional).

Returns

Boolean. Success/Failure.

CloseAlarms Method (Alarms Object)

This function sends a special alarm request to close alarms on a specific collector before a specific date. This is useful to close out any alarms that are stuck mid-lifecycle.

Syntax

object.**CloseAlarms**(endDate, theCollector)

Table 294. Parameters

Name	Data Type	Description
endDate	Date	The date from which to close alarms. Alarms before this date are closed.
theCollector	String	Close alarms associated with this collector/datasource. <div data-bbox="820 556 1339 777" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: If your alarm collector is linked to a data collector, pass in the data collector name. </div>

Returns

None.

CloseArchive Method (Archive Object)

Closes the specified archive for new data flow. You can perform this operation on the current archive only (the one accepting the newest data). Once an archive is closed, the Historian server looks to the next available empty archive to re-commence data storage.

If no empty archive is found, the method creates one or overwrites the oldest loaded archive. The archiving options, `ArchiveAutomaticCreate`, `ArchiveAutomaticFreeSpace`, `ArchiveDefaultSize`, and `ArchiveOverWriteOld`, control this behavior.

If `ArchiveAutomaticCreate` is running and enough free space exists on the drive of the `ArchiveDefaultPath`, the method creates a new archive of default size after it creates an archive of default size.

If the method cannot create a new archive, it overwrites the oldest archive based on `ArchiveOverWriteOld` being on. If `ArchiveOverWriteOld` is not on, the Historian archiver shuts down and the collectors start buffering data.

Syntax

```
object.CloseArchive(DataStoreName As String)
```

Table 295. Parameters

Name	Data Type	Description
DataStoreName	String	The name of the data store the archive belongs to. This is an optional parameter.

Returns

Boolean. Returns whether or not the CloseArchive operation succeeded.

CollectorHasBackup Method (Collectors Object)

Returns whether a collector has a backup collector.

Syntax

object.**CollectorHasBackup**(CollectorName)

Table 296. Parameters

Name	Data Type	Description
CollectorName	String	Name of the collector to determine if a backup exists.

Returns

Boolean. True if the Collector has a backup, False otherwise.

Example

```
Dim MyCollectors As iHistorian_SDK.Collectors
Set MyCollectors = MyServer.Collectors
Dim HasBackup As Boolean
HasBackup = MyCollectors.CollectorHasBackup("SimulationCollector")
```

CommitImport Method (Alarms Object)

Writes the alarms/events acquired via the Import method to the Historian Archiver.

Syntax

object.**CommitImport**

Parameters

None

Returns

Boolean. Returns whether or not the Import operation succeeded.

Connect Method (Server Object)

Initiates a connection to the current server. Calling the Connect method on a currently connected session re-authenticates the user.

If a ServerName has been set, the method authenticates the user by the username and password supplied, if any. If they are not supplied, it authenticates the user by the currently authenticated domain user. If a ServerName has not been set, it uses the ServerName registered as the Default Server. If a username and password are not supplied, it uses the username and password registered with the default server. If neither establishes a username, it authenticates the user by the currently authenticated domain user.

Syntax

object.**Connect**([ServerName], [UserName], [Password])

Table 297. Parameters

Name	Data Type	Description
ServerName	String	Table text
UserName	String	Username to authenticate (optional).
Password	String	Password to authenticate (optional).

Returns

Boolean. Returns whether or not the Connect operation succeeded.

Example

```
Dim MyServer As New iHistorian_SDK.Server

' Connect to the default server using default user
If Not MyServer.Connect Then
err.Raise 1, , "Failed to authenticate on server " + MyServer.ServerName
End If

' Connect to the default server using specific user
If Not MyServer.Connect("Fred", "000") Then
```

```
err.Raise 1, , "Failed to authenticate on server " + MyServer.ServerName
End If

' Connect to specific server using specific user
If Not MyServer.Connect("USGB014", "Fred", "000") Then
err.Raise 1, , "Failed to authenticate on server " + MyServer.ServerName
End If
```

ConvertShortcutToTime Method (Server Object)

Converts a time shortcut to a date. It converts the time from UTC into formatted time based on the ConnectionOptions (TimeOption) settings listed below.

Value	Description
(N)ow	The current time (absolute).
(T)oday	Today at midnight (absolute).
(Y)esterday	Yesterday at midnight (absolute).
(D)ays	Number of Days (relative).
(M)in	Number of Minutes (relative).
(H)our	Number of Hours (relative).
(W)EEK	Number of Weeks (relative).
(BOM)	Beginning of this month at Midnight (absolute).
(EOM)	Last Day of this month at Midnight (absolute).
(BOY)	First Day of this year at Midnight (absolute).
(EOY)	Last Day of this year at Midnight (absolute).

Syntax

object.**ConvertShortcutToTime**(Shortcut)

Table 298. Parameters

Name	Data Type	Description
Shortcut	String	Date of shortcut to convert (read-only).

Returns

Date. Returns date converted from string shortcut.

CopyTo Method (Tag Object)

Copies the properties of the given tag to the specified destination tag.

Syntax

object.**CopyTo**(TargetTag)

Table 299. Parameters

Name	Data Type	Description
TargetTag	Variant	The destination tag.

Returns

None.

CriteriaFromStrings Method (QueryModifiers Object)

Applies to:

Returns the sampling mode, calculation mode and query modifiers associated with the input CriteriaString.

Syntax

object.**CriteriaFromStrings**(CriteriaString As String)

Table 300. Parameters

Name	Data Type	Description
CriteriaString	String	Indicates the criteria string. For example, #ONLYGOOD.

Returns

DataCriteria

D

DataStoreUpdate Method (DataStores Object)

Updates the changes made to the data store settings.

Syntax

`object.MyDataStores.Item(DataStoreName)`

Table 301. Parameters

Name	Data Type	Description
DataStoreName	String	Name of the data store that should be updated.
IsDefault	Boolean	Indicates whether the data store is the default data store.
Description	String	Description of the data store. This is an optional parameter.
StorageType	String	Indicates whether the storage type is historical or SCADA buffer. This is an optional parameter.

Returns

Boolean. Returns TRUE if the data store has been updated and FALSE if there is an error in updating the data store.

Delete Method (Archive Object)

Deletes the specified archive on the Historian server. This is a synchronous operation that executes immediately when you call the Delete Method.

Syntax

`object.Delete(DataStoreName As String)`

Table 302. Parameters

Name	Data Type	Description
DataStoreName	String	Name of the data store that contains the archive. This is an optional parameter.

Returns

Boolean. Returns whether or not the Delete operation succeeded.

Delete Method (Archives Object)

Attempts to delete an Archive from the Historian server.

Syntax

object.**Delete**(ArchiveName As String, ArchiveDataStoreName As String)

Table 303. Parameters

Name	Data Type	Description
ArchiveName	String	Name of the archive to delete.
ArchiveDataStore-Name	String	Name of the archive data store the archive belongs to. This is an optional parameter.

Returns

Boolean. Returns whether or not the Delete operation succeeded.

Delete Method (Collector Object)

Deletes the specified collector on the Historian Server.

**CAUTION:**

The default option also deletes all tags marked with this collector as their source (CollectorName Property) at the same time it deletes the collector.

Syntax

object.**Delete**([DeleteTags])

Table 304. Parameters

Name	Data Type	Description
DeleteTags	Boolean	Deletes collector tags when deleting the collector. (optional, default = True)

Returns

Boolean. Whether the Delete was successful.

Delete Method (Collectors Object)

Removes an existing collector with the specified name from the Historian server.

Syntax

object.**Delete**(CollectorName, [DeleteTags])

Table 305. Parameters

Name	Data Type	Description
CollectorName	String	Name of the collector to Delete.
DeleteTags	Boolean	Should the tags from this collector be deleted as well?

Returns

Boolean. Success/Failure.

Example

```
Dim MyCollectors As iHistorian_SDK.Collectors
Set MyCollectors = MyServer.Collectors
MyCollectors.Delete "OPC Collector"
```

Delete Method (DataRecordset Object)

Marks the specified tag in the current TagRecordset for deletion. If the specified tag does not exist in the current TagRecordset, the method adds it. If the tag is not found, the Delete method fails.

In either case, the method does not delete this tag on the Historian server until the WriteRecordset Method of the TagRecordset object is called.

Syntax

object.**Delete**(Tagname, TimeStamp)

Table 306. Parameters

Name	Data Type	Description
Tagname	String	Name of the tag to delete (read-only).
TimeStamp	Date	Tag timestamp (optional).

Returns

Boolean. Returns True if successful.

Delete Method (DataStores Object)

Deletes the data store.

Syntax

object.**Delete**(DataStoreName As String)

Table 307. Parameters

Name	Data Type	Description
DataStoreName	String	Indicates the name of the data store that has to be deleted.

Returns

Boolean. Returns TRUE if the data store has been deleted and FALSE if there is an error in deleting the data store.

Delete Method (DataValue Object)

Deletes the DataValue from the archive. Commit the Delete operation by calling the WriteRecordset method of the DataRecordset object.

Syntax

object.**Delete**

Parameters

None

Returns

Boolean. Returns whether or not the Delete operation succeeded.

Delete Method (EnumeratedSets Object)

Deletes the specified set from the Historian Server. This is a synchronous operation that is executed immediately when you call the Delete method.

Syntax

object.**Delete**(setName)

Table 308. Parameters

Name	Data Type	Description
SetName	Variant	The name of the set that has to be deleted.

Returns

Boolean. Returns True if the method has been deleted

Delete Method (EnumeratedStates Object)

Deletes the specified state from the enumerated set. This is a synchronous operation that is executed immediately when you call the Delete method.

Syntax

object.**Delete**(StateName)

Table 309. Parameters

Name	Data Type	Description
StateName	Variant	The name of the state that has to be deleted.

Returns

Boolean. Returns True if the state has been deleted or False if not.

Delete Method (Tag Object)

Deletes the specified tag on the Historian Server. This is a synchronous operation that executes immediately when you call the Delete method. You can choose to delete a tag permanently from the Historian Server by passing an additional parameter as True or False.

**Note:**

This method is called within the WriteRecordset method. For more information, refer to the Sample Code section.

Syntax

object.**Delete**((Optional) DeletePermanent)

Table 310. Parameters

Name	Data Type	Description
DeletePermanent	Boolean	(Optional) Pass TRUE to permanently delete a tag.

Returns

Boolean. Returns whether or not the Delete operation succeeded.

Delete Method (TagRecordset Object)

Marks the specified tag in the current TagRecordset for deletion. If the specified tag does not exist in the current TagRecordset, the method adds it. If the tag is not found, the Delete method fails. In either case, the method does not delete this tag on the Historian server until the WriteRecordset method of the TagRecordset object is called.

Syntax

object.**Delete**(Tagname)

Table 311. Parameters

Name	Data Type	Description
Tagname	String	Name of the tag to delete (read-only).

Returns

Boolean. Returns whether or not the Delete operation succeeded.

Delete Method (UserDefinedTypeFields Object)

Deletes a field from the User Defined Type. This is a synchronous operation that is executed immediately when you call the Delete method.

Syntax

object.**Delete**(FieldName)

Table 312. Parameters

Name	Data Type	Description
FieldName	Variant	The name of the state that has to be deleted.

Returns

Boolean. Returns TRUE if the state has been deleted.

DeleteEx Method (Archive Object)

Deletes the specified archive on the Historian server. This is a synchronous operation that executes immediately when you call the Delete Method. The window associated with the handle passed in is kept alive (messages processed) while the operation takes place.

Syntax

object.**DeleteEx**(hWnd As Long, DataStoreName As String)

Table 313. Parameters

Name	Data Type	Description
hWnd	Long	The handle of the window to keep alive.
DataStoreName	String	Name of the data store that contains the archive. This is an optional parameter.

Returns

Boolean. Returns whether or not the Delete operation succeeded.

DeleteEx Method (Archives Object)

Attempts to delete an Archive from the Historian server. Keeps the window with handle hWnd alive by processing its messages while waiting for the deletion to occur.

Syntax

object.**DeleteEx**(ArchiveName As String, hWnd As Long, ArchiveDataStoreName As String)

Table 314. Parameters

Name	Data Type	Description
ArchiveName	String	Name of the archive to delete
hWnd	Long	The window handle to keep alive.
ArchiveDataStore-Name	String	Name of the archive data store the archive belongs to. This is an optional parameter.

Returns

Boolean. Success/Failure.

Disconnect Method (Server Object)

Disconnects the currently authenticated connection to the Server.

Syntax

object.**Disconnect**

Parameters

None

Returns

None.

Method Reference E-H

E

Export Method (Alarms Object)

Exports the contents of the AlarmRecordSet into the specified file.

Syntax

object.**Export**(AlmRS, RSInfo, FileName, FileFormat)

Table 315. Parameters

Name	Data Type	Description
AlmRS	AlarmRecordSet	Returns the requested records (writeable).
RSInfo	AlarmOpenRecord-SetInfo	Contains descriptions of the desired records (read-only).
FileName	String	Fully qualified export filename (read-only).
FileFormat	ihFileFormat	File format of the export file (read-only).

Returns

Boolean. Returns whether or not the Export operation succeeded.

Export Method (DataRecordset Object)

Exports the contents of the current DataRecordset into the specified file.

Syntax

object.**Export**(FileName, FileFormat)

Table 316. Parameters

Name	Data Type	Description
FileName	String	Fully qualified export filename (read-only).
FileFormat	ihFileFormat	File format of the export file (read-only).

Returns

Boolean. Returns whether or not the Export operation succeeded.

Example

```
' Export File From Existing Query Results
If Not MyRecordset.Export("C:\Temp\DataReport.RPT", ihFileFormat.Report) Then
Err.Raise 1, , "Error Exporting File: " + MyRecordset.LastError
End If
```

Export Method (EnumeratedSets Object)

Applies to:

Exports the contents of the EnumeratedSets collection into the specified file.

The following file formats are supported:

Name	Description	Value
CSV	File is imported/exported as comma separated values.	1
XML	File is imported/exported as XML.	2

Imported files follow a specific format that contains specific keywords. With CSV, the first row of the file establishes the fields in the file and their positions. With XML reports, the files describe the format of the data.

Syntax

object. **Export**(FileName, FileFormat)

Table 317. Parameters

Name	Data Type	Description
FileName	String	Fully qualified export file name (read-only).
FileFormat	ihFileFormat	File format of the export file (read-only).

Returns

Boolean. Returns True if the sets have been exported successfully.

Export Method (MessageRecordset Object)

Exports the contents of the current MessageRecordset into the specified file.

The following file formats are supported. Exported files follow a specific format containing specific keywords. With CSV and tabular reports, the first row of the file establishes the fields in the file and their positions. With XML, the file itself describes the format of the data.

Name	Description	Value
CSV	File is imported/exported as comma separated values.	1
XML	File is imported/exported as XML.	2
Report	File is exported as a columnar report	3

Syntax

object.**Export**(FileName, FileFormat)

Table 318. Parameters

Name	Data Type	Description
FileName	String	Fully qualified export file name (read-only).
FileFormat	ihFileFormat	File format of the export file (read-only).

Returns

Boolean. Success/Failure.

Export Method (TagRecordset Object)

Exports the contents of the current TagRecordset into the specified file.

The following file formats are supported:

Name	Description	Value
CSV	File is imported/exported as comma separated values.	1
XML	File is imported/exported as XML.	2
Report	File is exported as a columnar report	3

Imported files follow a specific format that contains specific keywords. With CSV and tabular reports, the first row of the file establishes the fields in the file and their positions. With XML reports, the files describe the format of the data. Prepare a file for import by exporting it with the desired fields for import.

Syntax

object.**Export**(FileName, FileFormat)

Table 319. Parameters

Name	Data Type	Description
FileName	String	Fully qualified export file name (read-only).
FileFormat	ihFileFormat	File format of the export file (read-only).

Returns

Returns whether or not the Export operation succeeded.

Example

```
' Export file from existing query results
Set MyRecordset = MyServer.Tags.NewRecordset
MyRecordset.Criteria.Tagname = ""
MyRecordset.Fields.AllFields
MyRecordset.QueryRecordset
If Not MyRecordset.Export(Path & "TagReport.RPT", ihFileFormat.Report) Then
err.Raise 1, , "Error exporting file: " & MyRecordset.LastError
End If
```

Export Method (UserDefinedType Object)

Applies to:

Exports the contents of the User Defined Type into the specified file.

The following file formats are supported:

Name	Description	Value
CSV	File is imported/exported as comma separated values.	1
XML	File is imported/exported as XML.	2

Imported files follow a specific format that contains specific keywords. With CSV, the first row of the file establishes the fields in the file and their positions. With XML reports, the files describe the format of the data.

Syntax

object. **Export**(FileName, FileFormat)

Table 320. Parameters

Name	Data Type	Description
FileName	String	Fully qualified export file name (read-only).
FileFormat	ihFileFormat	File format of the export file (read-only).

Returns

Boolean. Returns TRUE if the User Defined Type is exported successfully.

G**GetCurrentValue Method (Collector Object)**

Returns the current value for a given tag.

Syntax

object.**GetCurrentValue**(SourceAddress, ErrorMessage, CurrentValue)

Table 321. Parameters

Name	Data Type	Description
SourceAddress	String	The tag source address.
ErrorMessage	String	The error message string encountered, if any.
CurrentValue	String	A DataValue object representing the current tag value.

Returns

Boolean. Succeeded/Failed. **Example**

```
Dim OPC1 As iHistorian_SDK.Collector

Dim MyTagValue As Variant

Dim MyErrorMessage As String

' Request The Collector To Get the Current Value for a Tag

Set OPC1 = MyCollectors.Item("USIM031_OPC1")

OPC1.GetCurrentValue "OPCTag1", MyErrorMessage, MyTagValue
```

GetFilters Method (OPCFilters Object)

Returns the current set of Filters configured for MyCollector.

Syntax

object.GetFilters(MyServer, MyCollector)

Table 322. Parameters

Name	Data Type	Description
MyServer	Variant	The Historian server connection.
MyCollector	MyCollector	The Collector object to acquire the Filter information for.

Returns

Boolean true on success, false otherwise

GetLastError Method (Server Object)

Returns the last error message encountered by the Server object. To see a complete list of messages, refer to the ErrorList property. When possible, the system translates messages into the locale of the client.

Syntax

object.**GetLastError**

Parameters

None

Returns

String. The last error message encountered.

GetPrimaryCollectorName Method (Collectors Object)

Returns the name of the Primary Collector for a set of redundantly configured Collectors.

Syntax

object.**GetPrimaryCollectorName**(CollectorName)

Table 323. Parameters

Name	Data Type	Description
CollectorName	String	The name of the Collector.

Returns

String. The primary collector name.

Method Reference I-L

I

Import Method (Alarms Object)

This function imports the alarms/events in the specified file into this Alarms object.



CAUTION:

Any previously imported alarms will be discarded.

Syntax

```
object.Import(FileName, FileFormat)
```

Table 324. Parameters

Name	Data Type	Description
FileName	String	Fully qualified import filename (read-only).
FileFormat	Long	File format of the import file (read-only).

Returns

Boolean. Returns whether or not the Import operation succeeded.

Import Method (DataRecordset Object)

Imports the specified file into the current DataRecordset. If the DataRecordset contains items when the Import Method is invoked, the method first clears current DataRecordset before it imports the specified file.

Syntax

```
object.Import(FileName, FileFormat)
```

Table 325. Parameters

Name	Data Type	Description
FileName	String	Fully qualified import filename (read-only).
FileFormat	Long	File format of the import file (read-only).

Returns

Boolean. Returns whether or not the Import operation succeeded.

Example

```
' Get A New Recordset
Set MyRecordset = MyData.NewRecordset

' Import The File
If Not MyRecordset.Import("C:\Temp\ImportData.CSV", ihFileFormat.CSV) Then
Err.Raise 1, , "Error Importing File:" + MyRecordset.LastError
End If
```

```

' Commit Data

If Not MyRecordset.WriteRecordset Then

Err.Raise 1, , "Error Committing File: " + MyRecordset.LastError

End If

```

ImportMethod (EnumeratedSets Object)

Imports the specified file into the EnumeratedSets collection. The following file formats are supported:

Name	Description	Value
CSV	File is imported/exported as comma separated values.	1
XML	File is imported/exported as XML.	2

Imported files follow a specific format that contains specific keywords. With CSV files, the first row of the file establishes the fields in the file and their positions. With XML reports, the files describe the format of the data.

Syntax

object.**Import**(FileName, FileFormat, Server)

Table 326. Parameters

Name	Data Type	Description
FileName	String	Fully qualified export file name (read-only).
FileFormat	ihFileFormat	File format of the export file (read-only).
Server	Server	Server from which the sets are imported.

Returns

Boolean. Returns True if the sets have been imported successfully.

Import Method (MessageRecordset Object)

Attempts to import a list of Messages from a file.

Syntax

object.**Import**(FileName, FileFormat)

Table 327. Parameters

Name	Data Type	Description
FileFormat	ihFileFormat	The format of the file specified in FileName
FileName	String	The name of the file to import.

Returns

Boolean true if the Import succeeded, false otherwise.

Import Method (TagRecordset Object)

Imports the specified file into the current TagRecordset. If the TagRecordset contains items when the Import method is invoked, the method first clears the current TagRecordset before importing the specified file. After you have imported a file, call the WriteRecordset method of the TagRecordset object to save the data to the Historian server. The following file formats are supported:

Name	Description	Value
CSV	File is imported/exported as comma separated values.	1
XML	File is imported/exported as XML.	2
Report	File is exported as a columnar report.	3

Imported files follow a specific format that contains specific keywords. With CSV and tabular reports, the first row of the file establishes the fields in the file and their positions. With XML reports, the files describe the format of the data.

**Note:**

Prepare a file for import by exporting it with the desired fields for import.

Syntax

```
object.Import(FileName, FileFormat)
```

Table 328. Parameters

Name	Data Type	Description
FileName	String	Fully qualified import file name (read-only).

Table 328. Parameters (continued)

Name	Data Type	Description
FileFormat	Long	File format of the import file (read-only).

Returns

Returns whether or not the Import operation succeeded.

Example

```
' Get a new recordset
Set MyRecordset = MyTags.NewRecordset

' Import the file
If Not MyRecordset.Import(Path & "ImportTags.csv", ihFileFormat.CSV) Then err.Raise 1, , "Error
importing file: " & MyRecordset.LastError

End If

' Commit Data
If Not MyRecordset.WriteRecordset Then
err.Raise 1, , "Error committing file: " & MyRecordset.LastError

End If
```

Import Method (UserDefinedType Object)

Applies to:

Imports the specified file into the User Defined Type collection. The following file formats are supported:

Name	Description	Value
CSV	File is imported/exported as comma separated values.	1
XML	File is imported/exported as XML.	2

Imported files follow a specific format that contains specific keywords. With CSV files, the first row of the file establishes the fields in the file and their positions. With XML reports, the files describe the format of the data.

Syntax

object. **Import**(FileName, FileFormat, Server)

Table 329. Parameters

Name	Data Type	Description
FileFormat	ihFileFormat	File format of the import file (read-only).
FileName	String	Fully qualified export file name (read-only).
Server	Server	Server from which the sets are imported.

Returns

Boolean. Returns TRUE if the type imports successfully.

InitiateFailover Method (Collectors Object)

Manually tries to initiate a Failover to a redundantly configured collector.

Syntax

object.**InitiateFailover**(CollectorName)

Table 330. Parameters

Name	Data Type	Description
CollectorName	String	Name of the collector to fail-over.

Returns

Collector. Returns Success/Failure.

Example

```
Dim MyCollectors As iHistorian_SDK.Collectors
Set MyCollectors = MyServer.Collectors
MyCollectors.InitiateFailover "SimulationCollector"
```

L**LastError Method (Alarms Object)**

This function returns the last error message generated by this object.

Syntax

object.**LastError**

Parameters

None

Returns

String. The last error message encountered.

LoadUserCalcLibrary Method (Server Object)

Retrieves the user calculation library from the Server object. This library contains all of the user-created functions and subroutines available for calculations on this Server. The calculation library will be returned as an array of UserCalcFunction objects. If no functions exist in the library, UserCalcFunctions should be set to Empty

Syntax

object.**LoadUserCalcLibrary**(UserCalcFunctions)

Table 331. Parameters

Name	Data Type	Description
UserCalcFunctions	VARIANT	Resulting array of UserCalcFunction objects.

Returns

Boolean. Returns whether or not the calculation library was loaded successfully.

Example

```
Dim MyServer As New iHistorian_SDK.Server
Dim MyUserCalcFunctions() As iHistorian_SDK.UserCalcFunction
Dim MyNewFunction As New iHistorian_SDK.UserCalcFunction

' Connect to the local server
If Not MyServer.Connect("", "", "") Then
err.Raise 1, , "Failed to connect to the local server" End If

' Load the calculation library
MyServer.LoadUserCalcLibrary MyUserCalcFunctions

' Create a new function
MyNewFunction.Name = "Sum"
MyNewFunction.Definition = "Function Sum(a, b)" & vbCrLf & "Sum = a + b" & vbCrLf & "End Function"

' Add it to the loaded library
If IsArray(MyUserCalcFunctions) Then
```

```

ReDim Preserve MyUserCalcFunctions(UBound(MyUserCalcFunctions) + 1) Else
ReDim MyUserCalcFunctions(0) End If

Set MyUserCalcFunctions(UBound(MyUserCalcFunctions)) = MyNewFunction

' Save the changes to the calculation library

If Not MyServer.SaveUserCalcLibrary(MyUserCalcFunctions) Then err.Raise 1, , "Failed to save the
    calculation library"

End If
    
```

Method Reference M-P

M

ManageServerDialog Method (ServerManager Object)

Displays a window to manage server connection information on the client. This window allows you to add and remove new connections, and to modify the default username and password. This method optionally returns the name of the server last selected in the window.

Syntax

object.**ManageServerDialog**([SelectedServer])

Table 332. Parameters

Name	Data Type	Description
SelectedServer	String	Name of the selected Historian Server (optional, read/write).

Returns

None.

Example

```

Dim MyManager As New iHistorian_SDK.ServerManager

Dim MyServer As iHistorian_SDK.Server

Dim SelectedServer As String

' Show the manage server window

MyManager.ManageServerDialog SelectedServer

' If a server was selected, get the server
    
```

```
If Trim(SelectedServer) <> "" Then  
Set MyServer = MyManager.Servers(SelectedServer) End If
```

N

NewRecordset Method (Data Object)

Returns a new DataRecordset object to subsequently build a query for tag data from the Historian server. It is the responsibility of the developer to release the DataRecordset object when processing has been completed. DataRecordset objects may be re-used by re-executing a query with new criteria set through the DataCriteria of the DataRecordset object.

You must also use a new DataRecordset object to add new data points to the system and delete existing data points from the system. Changes are not committed until calling the WriteRecordset method of the DataRecordset object.

Syntax

object.**NewRecordset**

Parameters

None

Returns

DataRecordset. A new, empty, DataRecordset object.

NewRecordset Method (Messages Object)

Returns a new MessageRecordset object to build a query for messages and alerts from the Historian server message archive. You must release the MessageRecordset object when processing completes. You can re-use a MessageRecordset object by re-executing a query with new criteria set through the MessageCriteria of the MessageRecordset object.

To add new messages, you must use a new MessageRecordset object. Call the WriteRecordset method of the MessageRecordset object to commit changes to the archiver.

Syntax

object.**NewRecordset**

Parameters

None

Returns

MessageRecordset. Returns the newly created MessageRecordset object.

NewRecordset Method (Tags Object)

Returns a new TagRecordset object to build a query for tag information. You must terminate the TagRecordset object when processing completes. You can re-use the TagRecordset objects by re-executing a query with new criteria set through the TagCriteria of the TagRecordset object.

You must also use a new TagRecordset object to add new tags to the system and to delete tags from the system. Call the WriteRecordset Method of the TagRecordset object to commit changes to the archiver.

Syntax

object.**NewRecordset**

Parameters

None.

Returns

TagRecordset. Returns a reference to the newly created Recordset Object.

Purge Alarms By Id Method

Purges a single alarm as identified by its alarm ID.

Syntax

object.**AlarmIds**

Table 333. Parameters

Name	Data Type	Description
AlarmIds	Long	Alarm ID of the alarm.

Returns

Boolean. Returns TRUE if the alarm is purged.

Example

```

Dim Status As ihStatus

    Dim ReturnStatus As Boolean

    Dim Alarms() As Long

    Dim NumberOfAlarms As Long

    Dim i As Long

    Status = ihSTATUS_FAILED ReturnStatus = False

    NumberOfAlarms = (UBound(AlarmIds) + 1)

    ReDim Alarms(0 To NumberOfAlarms - 1) As Long

    On Error GoTo errc

    For i = 0 To NumberOfAlarms - 1

        Alarms(i) = AlarmIds(i)

    Next i

    Status = ihPurgeAlarmsById(MyServer.Handle, Alarms(0), NumberOfAlarms, 0)

    If Status <> ihSTATUS_OK Then err.Raise 1, , "Error Purging alarms by Id[" +
ErrorDescription(Status) + "," + CS ReturnStatus = True

    PurgeAlarmsById = ReturnStatus errc:

    zLastError = "Purge Alarms By Id>> " + err.Description

    PurgeAlarmsById = ReturnStatus

End Function

```

Purge Alarms Method

Purges or deletes the alarms from the Archiver.

Syntax

object.**PurgeAlarms**

Table 334. Parameters

Name	Data Type	Description
BackupFile	String	The file that stores the purged alarm data.
ShouldZipAlarms	Boolean	Indicates whether the alarms should be zipped into file or not.
StartTime	Date	Start time of the alarms.
EndTime	Date	End time of the alarms.

Returns

Boolean. Returns TRUE if the alarms are purged.

Example

```

Dim Status As ihStatus

        Dim AlarmsStartTime As ihTimeStruct Dim AlarmsEndTime As ihTimeStruct Dim

ShouldZip As ihBoolean

        Dim ReturnStatus As Boolean

        Status = ihSTATUS_FAILED ReturnStatus = False

        AlarmsStartTime = Date_To_UTC(StartTime) AlarmsEndTime = Date_To_UTC(EndTime)

        If ShouldZipAlarms = True Then

        ShouldZip = ihTRUE Else

        ShouldZip = ihFALSE End If

        On Error GoTo errc

        Status = ihPurgeAlarms(MyServer.Handle, BackupFile, ShouldZip, AlarmsStartTime,

AlarmsEndTime, 0)

        If Status <> ihSTATUS_OK Then err.Raise 1, , "Error Purging alarms [" +

ErrorDescription(Status) + ", " + CStr(St

        ReturnStatus = True PurgeAlarms = ReturnStatus errc:

zLastError = "Purge Alarms>> " + err.Description

PurgeAlarms = ReturnStatus

End Function

```

Method Reference Q-T

Q

QueryArray Method (Archives Object)

This function returns a list of properties of an Archive found on the Historian server.

Syntax

object.**QueryArray**(ArchiveName, Params, SortAscending, ArrayOrientation, ArraySize, ReturnCount, ReturnArray)

Table 335. Parameters

Name	Data Type	Description
ArchiveName	String	Name of the Archive to return information on.
Params	Variant	A list of the parameters to retrieve on the specified Archive.
SortAscending	Boolean	Sorting preference for the returned list of properties.
ArrayOrientation	Integer	The desired orientation of the returned array.
ArraySize	Long	The desired size of the returned array.
ReturnCount	Long	The number of rows returned in ReturnArray
ReturnArray	Variant	A returned array which contains the requested properties.

Returns

Boolean. Success/Failure.

QueryArray Method (Collectors Object)

This function returns a list of properties for a set of Collectors.

Syntax

object.**QueryArray**(CollectorName, Params, SortAscending, ArrayOrientation, ArraySize, ReturnCount, ReturnArray)

Table 336. Parameters

Name	Data Type	Description
CollectorName	String	Name of the Collector to return information on.
Params	Variant	A list of the parameters to retrieve from the Collectors.

Table 336. Parameters (continued)

Name	Data Type	Description
SortAscending	Boolean	Sorting preference for the returned list of properties.
ArrayOrientation	Integer	The desired orientation of the returned array.
ArraySize	Long	The desired size of the returned array.
ReturnCount	Long	The number of rows returned in ReturnArray
ReturnArray	Variant	A returned array which contains the requested properties.

Returns

Boolean. Success/Failure.

QueryArray Method (DataRecordset Object)

This function returns an array of data records from the Historian server.

Syntax

object.**QueryArray**(Params, SortAscending, ArrayOrientation, ArraySize, ReturnCount, ReturnArray)

Table 337. Parameters

Name	Data Type	Description
Params	Variant	A list of the parameters to retrieve.
SortAscending	Boolean	Sorting preference for the returned list of properties.
ArrayOrientation	Integer	The desired orientation of the returned array.
ArraySize	Long	The desired size of the returned array.
ReturnCount	Long	The number of rows returned in ReturnArray
ReturnArray	Variant	A returned array which contains the requested properties.

Returns

Boolean. Success/Failure.

QueryArray Method (MessageRecordset Object)

This function returns an array of Messages from the Historian server.

Syntax

object.**QueryArray**(Params, SortAscending, ArrayOrientation, ArraySize, ReturnCount, ReturnArray)

Table 338. Parameters

Name	Data Type	Description
Params	Variant	A list of the parameters to retrieve.
SortAscending	Boolean	Sorting preference for the returned list of properties.
ArrayOrientation	Integer	The desired orientation of the returned array.
ArraySize	Long	The desired size of the returned array.
ReturnCount	Long	The number of rows returned in ReturnArray
ReturnArray	Variant	A returned array which contains the requested properties.

Returns

Boolean. Success/Failure.

QueryArray Method (TagRecordset Object)

This function returns an array of Tags from the Historian server.

Syntax

object.**QueryArray**(Params, SortAscending, ArrayOrientation, ArraySize, ReturnCount, ReturnArray)

Table 339. Parameters

Name	Data Type	Description
Params	Variant	A list of the parameters to retrieve.
SortAscending	Boolean	Sorting preference for the returned list of properties.
ArrayOrientation	Integer	The desired orientation of the returned array.
ArraySize	Long	The desired size of the returned array.
ReturnCount	Long	The number of rows returned in ReturnArray.
ReturnArray	Variant	A returned array which contains the requested properties.

Returns

Boolean. Success/Failure

QueryRecordset Method (DataRecordset Object)

Executes the DataValue query based on the fields and criteria specified.

Syntax

object.**QueryRecordset**

Parameters

None

Returns

Boolean. Returns whether or not the QueryRecordset operation succeeded.

Example

```
Dim I As Integer
Dim J As Integer
Dim K As Integer
Dim strComment$
Dim lngInterval As Long
```

```
Dim TagCount As Integer

Dim strDataQuality As String

Dim iDataRecordset As iHistorian_SDK.DataRecordset

Dim iDataValue As iHistorian_SDK.DataValue

Dim lEndTime&, lStartTime&, lNumSamples&

Dim lNumSeconds, lNumSamplesPerSecond

On Error GoTo Error_Handle

If CheckConnection = True Then

If lbTags.Text = "" Then

MsgBox "No Tag Selected", vbOKOnly, "SDK Sample" Exit Sub

End If

Set iDataRecordset = ConnectedServer.Data.NewRecordset

'reset lstValues.Clear

'build query

With iDataRecordset

'filter code

If txtFilterTag.Text <> "" Then

.Criteria.FilterTagSet = True

.Criteria.FilterTag = txtFilterTag.Text

.Criteria.FilterComparisonModeSet = True

'comparison mode

Select Case cboComparisonMode.Text

Case Is = "Equal"

.Criteria.FilterComparisonMode = 1

Case Is = "NotEqual "

.Criteria.FilterComparisonMode = 2

Case Is = "LessThan"

.Criteria.FilterComparisonMode = 3

Case Is = "GreaterThan"

.Criteria.FilterComparisonMode = 4

Case Is = "LessThanEqual"

.Criteria.FilterComparisonMode = 5

Case Is = "GreaterThanEqual"

.Criteria.FilterComparisonMode = 6

End Select

.Criteria.FilterModeSet = True

'filter mode
```

```
Select Case cboFilterMode.Text

Case Is = "ExactTime"

.Criteria.FilterMode = 1

Case Is = "BeforeTime"

.Criteria.FilterMode = 2

Case Is = "AfterTime"

.Criteria.FilterMode = 3

Case Is = "BeforeAndAfterTime"

.Criteria.FilterMode = 4

End Select

.Criteria.FilterComparisonValue = txtFilterValue.Text

End If

.Criteria.Tagmask = lbTags.Text

.Criteria.StartTime = dtStartTime.Value

.Criteria.EndTime = dtEndTime.Value

'get sample mode

Select Case cboSampleMode.Text

Case Is = "Interpolated"

.Criteria.SamplingMode = 2 'interpolated

Case Is = "Raw By Number"

.Criteria.SamplingMode = 5 'raw by number

Case Is = "Raw By Time"

.Criteria.SamplingMode = 4 'raw by time

Case Is = "Current Value"

.Criteria.SamplingMode = 1 'current value

Case Is = "Calculated"

.Criteria.SamplingMode = 6 'calculation

Case Is = "Trend"

.Criteria.SamplingMode = 3 'trend

End Select

If .Criteria.SamplingMode = 5 Then

'if raw by number get direction

If optDirectionForward.Value = True Then

.Criteria.Direction = 1 'forward

Else

.Criteria.Direction = 2 'backward

End If
```

```
End If

'if calculation get calc mode
If .Criteria.SamplingMode = 6 Then
Select Case cboCalculationMode.Text
Case Is = "Average"
.Criteria.CalculationMode = 1 'average
Case Is = "Standard Deviation"
.Criteria.CalculationMode = 2 'standard deviation
Case Is = "Total"
.Criteria.CalculationMode = 3 'total
Case Is = "Minimum"
.Criteria.CalculationMode = 4 'minimum
Case Is = "Maximum"
.Criteria.CalculationMode = 5 'maximum
Case Is = "Count"
.Criteria.CalculationMode = 6 'count
Case Is = "Raw Average"
.Criteria.CalculationMode = 7 'raw average
Case Is = "Raw Standard Deviation"
.Criteria.CalculationMode = 8 'raw standard deviation
Case Is = "Raw Total"
.Criteria.CalculationMode = 9 'raw total
Case Is = "Minimum Time"
.Criteria.CalculationMode = 10 'minimum time
Case Is = "Maximum Time"
.Criteria.CalculationMode = 11 'maximum time
Case Is = "Time Good"
.Criteria.CalculationMode = 12 'time good
End Select
End If

If optSamplingByNumber.Value = True Then
.Criteria.NumberOfSamples = Int(txtNumSamples.Text) Else
Select Case cboTimeUnits.Text
Case Is = "Milliseconds"
.Criteria.SamplingInterval = Int(txtInterval.Text) Case Is = "Seconds"
.Criteria.SamplingInterval = Int(txtInterval.Text) * 1000
Case Is = "Minutes"
```

```

.Criteria.SamplingInterval = Int(txtInterval.Text) * 60000

Case Is = "Hours"

.Criteria.SamplingInterval = Int(txtInterval.Text) * 3600000

Case Is = "Days"

.Criteria.SamplingInterval = Int(txtInterval.Text) * 86400000

End Select

End If

.Fields.AllFields

VB.Screen.MousePointer = vbHourglass 'wait wait wait lStartTime = Timer

'do query

If Not .QueryRecordset Then lEndTime = Timer

MsgBox "Query Failed..." & Chr(13) & iDataRecordset.LastError

VB.Screen.MousePointer = vbDefault

Exit Sub

End If

lEndTime = Timer VB.Screen.MousePointer = vbDefault lNumSamples = 0

TagCount = iDataRecordset.Item(1).Count

For I = 1 To iDataRecordset.Tags.Count

For J = 1 To iDataRecordset.Item(I).Count

Set iDataValue = iDataRecordset.Item(I).Item(J) Select Case iDataValue.DataQuality

Case Is = 1

strDataQuality = "Good" Case Is = 2

strDataQuality = "Bad" Case Is = 3

strDataQuality = "Unknown"

Case Else

strDataQuality = "ERROR" End Select

strComment = ""

For K = 1 To iDataValue.Comments.Count

strComment = strComment & " " & iDataValue.Comments(K).Comment

Next K

lstValues.AddItem Format(iDataValue.TimeStamp, "MM/dd/yyyy hh:mm:ss") & _

Space(10) & CStr(iDataValue.Value) & vbTab & strDataQuality & vbTab & strComment lNumSamples =

lNumSamples + 1

Next J

Next I

End With

lNumSeconds = lEndTime - lStartTime lNumSamplesPerSecond = lNumSamples If lNumSeconds > 0 Then

```

```

lNumSamplesPerSecond = lNumSamples / lNumSeconds

End If

txtReadTime.Caption = lNumSamples & " returned in " & lEndTime - lStartTime & " seconds (" &
lNumSamplesPerSec

Caption = "Output values for " & lbTags.Text & " (" & TagCount & ")" VB.Screen.MousePointer = vbDefault

'done

Else

MsgBox "Not Connected"

End If

Exit Sub

Error_Handle:

VB.Screen.MousePointer = vbDefault

Select Case Err.Number

Case Is = 6 'overflow

MsgBox "Error Number: " & Err.Number & Chr(13) & "Description: " & Err.Description & Chr(13) & "Check
numb

Case Is = 13 'type mismatch

MsgBox "Error Number: " & Err.Number & Chr(13) & "Description: " & Err.Description & Chr(13) & "Check
numb

Case Is = 91

MsgBox "Error Number: " & Err.Number & Chr(13) & "Check connection to server"

Case Else

MsgBox "Error Number: " & Err.Number & Chr(13) & Err.Description, vbOKOnly, "Error"

End Select

```

QueryRecordset Method (MessageRecordset Object)

Executes the message query based on the fields and criteria specified.

Syntax

object.**QueryRecordset**

Parameters

None

Returns

Boolean. Success/Failure.

Example

```

Dim MyRecordset As iHistorian_SDK.MessageRecordset

Dim I As Integer

Dim J As Integer

Dim lEndTime&, lStartTime&, lNumMessages& Dim lNumSeconds&, lNumMessagesPerSecond&

If CheckConnection = True Then

' Get A New Recordset

Set MyRecordset = ConnectedServer.Messages.NewRecordset

' Return Timestamp, Message Number, and Message String Fields In Query

With MyRecordset.Fields

.Timestamp = True

.MessageNumber = True

.MessageString = True

End With

' Query messages for given start and end time

With MyRecordset.Criteria

.Clear

.StartTime = dtMessageStart.Value

.EndTime = dtMessageEnd.Value

If txtMessageContains.Text <> "" Then

.MessageString = txtMessageContains.Text

End If

End With

VB.Screen.MousePointer = vbHourglass ' wait wait wait

' Run Query lStartTime = Timer

If Not MyRecordset.QueryRecordset Then lEndTime = Timer

MsgBox "Query Failed..." & Chr(13) & MyRecordset.LastError

VB.Screen.MousePointer = vbDefault

Exit Sub

End If

lEndTime = Timer

' reset output list lstRetrievedMessages.Clear

' display all messages lNumMessages = 0

For J = 1 To MyRecordset.Item.Count

lstRetrievedMessages.AddItem Format(MyRecordset.Item(J).TimeStamp, "MM/dd/yyyy hh:mm:ss") & _

vbTab & MyRecordset.Item(J).MessageString lNumMessages = lNumMessages + 1

Next J

```

```

' calculate performance statistics lNumSeconds = lEndTime - lStartTime lNumMessagesPerSecond =
lNumMessages If lNumSeconds > 0 Then
lNumMessagesPerSecond = lNumMessages / lNumSeconds
End If
VB.Screen.MousePointer = vbDefault
txtReadTime.Caption = lNumMessages & " returned in " & lEndTime - lStartTime & " seconds (" &
lNumMessagesP
End If

```

QueryRecordset Method (TagRecordset Object)

Executes the tag query based on the fields and criteria specified.

Syntax

object.**QueryRecordset**

Parameters

None.

Returns

Boolean. Returns whether the QueryRecordset operation succeeded.

Example

```

Dim MyTags As iHistorian_SDK.Tags
Dim MyRecordset As iHistorian_SDK.TagRecordset
Dim lStartTime&, lEndTime&, lNumSeconds&, lNumTagsPerSecond& Dim I As Integer
On Error GoTo errc lbTags.Clear
' If we are connected to server
If CheckConnection = True Then
' Query all the tagnames
Set MyTags = ConnectedServer.Tags
Set MyRecordset = MyTags.NewRecordset
MyRecordset.Criteria.Tagname = txtTagMask.Text
If txtDescriptionMask.Text <> "" Then
MyRecordset.Criteria.Description = txtDescriptionMask.Text
End If MyRecordset.Fields.Clear
MyRecordset.Fields.Tagname = True
VB.Screen.MousePointer = vbHourglass
lStartTime = Timer

```

```

If Not MyRecordset.QueryRecordset Then Err.Raise 1, , "Tag Query Failed: " + MyRecordset.LastError

lEndTime = Timer

For I = 1 To MyRecordset.Item.Count

lbTags.AddItem MyRecordset.Item(I).Tagname

Next I

VB.Screen.MousePointer = vbDefault

' Calculate performance statistics

lNumSeconds = lEndTime - lStartTime

lNumTagsPerSecond = MyRecordset.Item.Count

If lNumSeconds > 0 Then

lNumTagsPerSecond = MyRecordset.Item.Count / lNumSeconds

End If

lblAddTime.Caption = MyRecordset.Item.Count & " tags returned in " & lEndTime - lStartTime & " seconds

( " & lN MyRecordset.ClearRecordset

Set MyRecordset = Nothing

Else

MsgBox "Not connected"

End If

Exit Sub errc:

MsgBox "TestBrowseTags >> " + Err.Description
    
```

QueryTagAlias Method (TagRecordset Object)

This function returns a list of tag aliases for the tag name passed in. Pass in the current name of the tag and this function will return if there are any previous names for the tag due to tag rename.

Syntax object.**QueryTagAlias**(TagNames(), NumberofTags, TagAlias(), NoOfAliases)

Table 340. Parameters

Name	Data Type	Description
TagNames()	String	Name of the tags to return information on.
NumberofTags	Long	Total count of tag names passed in. This must be equal to 1.
TagAlias()	String	List of 0 or more tag aliases.
NoOfAliases	Integer	The number of tag aliases returned.

Returns

Boolean. TRUE if successful. FALSE otherwise.

QueryUserDefinedType Method (UserDefinedType Object)

Queries the Historian Server and loads all the User Defined Types that match the query mask.

Syntax

object.**QueryUserDefinedType**(Server, QueryMask)

Table 341. Parameters

Name	Data Type	Description
Server	Server	The reference to the Historian Server object.
QueryMask	String	A mask string that can be used to search for UserDefinedType on the Historian Server. The string can include wild-card characters like "*" and "?".

Returns

Boolean. Indicates whether the query was successful.

R**Reload Method (Collector Object)**

Causes a re-calculation of tags to occur for a specified tag period. You can reload all tags for the time period or specify specific tags that you want to reload.

**Note:**

This method is only supported by ServerToServer and Calculation collectors.

Syntax

object.**Reload**(StartTime, EndTime, [Tags])

Table 342. Parameters

Name	Data Type	Description
StartTime	Date	The time that you want the reload to begin at (read-only).
EndTime	Date	The time that you want the reload to end at (read-only).
Tags	Variant	The specified tag names either in an array of tag names, or in a tagRecordset object for tags that you want to reload (optional).

Returns

Boolean. Returns whether or not the Reload operation succeeded.

Remove Method (TagDependencies Object)

Removes a Tag dependency from the current calculation.

**CAUTION:**

If no Tagname is specified, **all** the Tag dependencies will be removed.

Syntax

object.**Remove**([Tagname])

Table 343. Parameters

Name	Data Type	Description
Tagname	Variant	Name of the tag to remove (optional), default = "").

Returns

Boolean. Whether the Remove operation succeeded.

RemoveServer Method (ServerManager Object)

Removes the specified server from the list of registered servers on the client.

Syntax

object.**RemoveServer**(ServerName)

Table 344. Parameters

Name	Data Type	Description
ServerName	String	Computer name of the Historian server (read/write).

Returns

Boolean. Whether the server was successfully removed from the list.

Rename Method (Tags Object)

Use this method to rename tag names. You can rename a tag permanently by passing an additional parameter as TRUE or FALSE.



Note:

This method is called within the WriteRecordset method. For more information, refer to the Sample Code section.

Syntax

object.**Rename**(newTagName, (Optional) RenamePermanent)

Table 345. Parameters

Name	Data Type	Description
newTagName	String	Name of the new tag to rename.
RenamePermanent (Optional)	Boolean	Pass TRUE to permanently rename a tag.

Returns

Boolean. Returns whether or not the Rename operation succeeded.

Restore Alarms Method

Restores the alarms.

Syntax

object.**RestoreAlarms**

Table 346. Parameters

Name	Data Type	Description
RestoreFileName	String	The name of the file to be restored to the absolute path.

Returns

Boolean. Returns TRUE if the alarms have been restored.

Example

```

Dim Status As ihStatus

Dim ReturnStatus As Boolean Status = ihSTATUS_FAILED ReturnStatus = False

On Error GoTo errc

Status = ihRestoreAlarms(MyServer.Handle, RestoreFileName, 0)

If Status <> ihSTATUS_OK Then err.Raise 1, , "Error in restoring the alarms [" +
    ErrorDescription(Status) + "," ReturnStatus = True

RestoreAlarms = ReturnStatus errc:

zLastError = "Purge Alarms>> " + err.Description

RestoreAlarms = ReturnStatus

End Function
    
```

S

SaveSet Method (EnumeratedSets Object)

Saves the Enumerated Set that has been passed into the Historian Server.

Syntax

object.**SaveSet**(SetTosave)

Table 347. Parameters

Name	Data Type	Description
SetToSave	EnumeratedSet	The set that is passed in to be saved.

Returns

None.

SaveSet Method (UserDefinedType Object)

Saves the UserDefinedType that has been passed into the Historian Server.

Syntax

object.**SaveSet**(Handle, MySet, Datatype)

Table 348. Parameters

Name	Data Type	Description
Handle	Long	Server handle.
MySet	UserDefinedType	The UserDefinedType to be saved.
Data Type	ihDatatype	The data type of the UserDefinedType

Returns

Boolean. Returns TRUE if the UserDefinedType is saved.

SaveToCollectorProperty Method (OPCFilters Object)

Saves the current filter configuration in the Collector object.

Syntax

object.**SaveToCollectorProperty**(Collector)

Table 349. Parameters

Name	Data Type	Description
Collector	VARIANT	The Collector object in which to save the filtering information.

Returns

Boolean true on success, false otherwise.

SaveUserCalcLibrary Method (Server Object)

Saves the given user calculation library to the Server object. This will update the set of user-created functions and subroutines available for calculations on this Server. The new calculation library must be passed in as an array of UserCalcFunctions.

This list of functions will replace any existing user calculation library on the Server. To save an empty calculation library, pass a non-array value such as Empty.

Syntax

object.**SaveUserCalcLibrary**(UserCalcFunctions)

Table 350. Parameters

Name	Data Type	Description
UserCalcFunctions	VARIANT	Array of UserCalcFunction objects.

Returns

Boolean. Returns whether or not the calculation library was saved successfully.

Example

```

Dim MyServer As New iHistorian_SDK.Server

Dim MyUserCalcFunctions() As iHistorian_SDK.UserCalcFunction

Dim MyNewFunction As New iHistorian_SDK.UserCalcFunction

' Connect to the local server

If Not MyServer.Connect("", "", "") Then

err.Raise 1, , "Failed to connect to the local server" End If

' Load the calculation library

MyServer.LoadUserCalcLibrary MyUserCalcFunctions

' Create a new function

MyNewFunction.Name = "Sum"

MyNewFunction.Definition = "Function Sum(a, b)" & vbCrLf & "Sum = a + b" & vbCrLf & "End Function"

' Add it to the loaded library

If IsArray(MyUserCalcFunctions) Then

ReDim Preserve MyUserCalcFunctions(UBound(MyUserCalcFunctions) + 1) Else

ReDim MyUserCalcFunctions(0) End If

Set MyUserCalcFunctions(UBound(MyUserCalcFunctions)) = MyNewFunction

' Save the changes to the calculation library

If Not MyServer.SaveUserCalcLibrary(MyUserCalcFunctions) Then err.Raise 1, , "Failed to save the

calculation library"

End If

```

SelectAll Method (TagRecordset Object)

Selects each tag in the current TagRecordset. Use in conjunction with the Master tag to perform bulk update operations on the selected tags of the TagRecordset.

Syntax

object.**SelectAll**

Parameters

None.

Returns

None.

Example

```

' Query for tags
Set MyRecordset = MyServer.Tags.NewRecordset
MyRecordset.QueryRecordset
' Select all tags
MyRecordset.SelectAll
' Update the HiEngineeringUnits for all tags
MyRecordset.Master.HiEngineeringUnits = 300
' Commit changes
MyRecordset.WriteRecordset
    
```

SetFields Method (DataRecordset Object)

Sets the DataValue fields to return from the Historian server when a DataRecordset query is executed.

Syntax

object.**SetFields**(Params)

Table 351. Parameters

Name	Data Type	Description
Params	Variant	Array of DataValue fields to set.

Returns

Boolean. Success / Failure

SetFields Method (MessageRecordset Object)

Set a list of desired Fields to be returned for the messages.

Syntax

object.**SetFields**(Params)

Table 352. Parameters

Name	Data Type	Description
Params	Variant	Array of Message fields

Returns

Boolean. Success / Failure

SetFields Method (TagRecordset Object)

Sets the Fields to retrieve in the TagRecordSet.

Syntax

object.**SetFields**(Params)

Table 353. Parameters

Name	Data Type	Description
Params	Variant	The array of field values to set.

Returns

Boolean. Success / failure.

SetNames Method (EnumeratedSets Object)

This function returns an array of names of all the loaded Enumerated Sets within the Historian server object.

Syntax

object.**SetNames**()

Parameters

None.

Returns

String Array.

ShowErrorListDialog Method (Server Object)

Displays a window that details errors messages accumulated during the current session of the Server object. Each message is timestamped at the time the error generated and includes an error message translated into the locale of the client when possible.

Syntax

object.**ShowErrorListDialog**

Parameters

None.

Returns

None

Example

```
ErrorTrap:  
  
' On error display the error list window  
  
If MyServer.ErrorList.count > 0 Then  
  
MyServer.ShowErrorListDialog  
  
End If
```

SubscribeAlerts Method (Messages Object)

Subscribes to alert messages reported by the Historian Server. As the server receives alerts, the Historian server publishes messages to any client signed up for alerts.

- To subscribe to messages of specific types, supply a topic.
- To subscribe to all topics, do not supply a topic. Subscribe all is the default.
- Subscribe to individual topics by making multiple calls to the SubscribeAlerts with different topics.
- To subscribe to all topics, call SubscribeAlerts and pass 0.
- To **unsubscribe** to a specific topic or all topics, call SubscribeAlerts and supply the Subscribe parameter set to False.

The Alert_Received event of the Messages object reports alert messages to the client asynchronously.

Syntax

object.**SubscribeAlerts**(Topic, Subscribe)

Table 354. Parameters

Name	Data Type	Description
Topic	ihMessageTopic	Topics of Alerts to subscribe to (optional, default = All).
Subscribe	Boolean	Flag to subscribe / unsubscribe to alerts (optional, default = True). Set to False to unsubscribe.

Returns

Boolean. Returns whether or not the SubscribeAlerts operation succeeded.

SubscribeChanges Method (Tags Object)

Subscribes to changes in tag configuration. The Historian server publishes messages to any client signed up for tag configuration changes as modifications are saved to the tag database.

The system reports tag configuration messages asynchronously to the client through the ChangeReceived event of the Tags Object.

To **unsubscribe** to a specific tag, or all tags, call SubscribeChanges and supply the Subscribe parameter set to False.

Syntax

object.**SubscribeChanges**(Tagname, Subscribe)

Table 355. Parameters

Name	Data Type	Description
Tagname	String	Name of tag to Subscribe for configuration changes (read-only).
Subscribe	Boolean	Flag to Subscribe/Unsubscribe to tag changes (default = True).

Returns

Boolean. Returns whether or not the SubscribeChanges operation succeeded.

SubscribeData Method (Data Object)

Subscribes to changes in the current value of a specific tag. The Historian server publishes messages as new values are received to any client signed up for current value changes. To qualify as a new current value, any new data point must have a newer timestamp than the previously established current value. Values received by the Historian server have passed a deadband check by the collector reporting the data. Since new current values have not been compressed, however, values reported as current may not exactly match those that reach the archive.

You can use the `MinimumElapsedTime`, in milliseconds, to throttle the rate at which current values are reported to a specific server connection. If the same tag is subscribed twice, the last supplied `MinimumElapsedTime` is used. If `MinimumElapsedTime` is not supplied, or is zero, the system reports all current values.

The system reports current values asynchronously to the client through the `DataReceived` event of the `Data` object.

To unsubscribe to a specific tag, or all tags, call `SubscribeData` and set the `Subscribe` parameter to `False`.

Syntax

object.**SubscribeData**(Tagname, MinimumElapsedTime, Subscribe)

Table 356. Parameters

Name	Data Type	Description
Tagname	String	Name of the tag to Subscribe for current values (read-only).
MinimumElapsed-Time	MinimumElapsed-Time	Minimum elapsed time (ms) between values (read-only).
Subscribe	Boolean	Flag to subscribe/unsubscribe to current values (read-only).

Returns

Boolean. Operation success / fail

SubscribeMessages Method (Messages Object)

Subscribes to messages reported by the Historian Server. The Historian Server publishes messages as messages are received to any client signed up for messages. As an option, you may supply a topic to subscribe only to messages of specific types. If you do not supply a topic, all topics are subscribed. You can subscribe to individual topics by making multiple calls to the `SubscribeMessages` method with different topics, or pass 0 to subscribe to all topics.

The system reports alert messages asynchronously to the client through the `Message_Received` event of the `Messages` object.

To unsubscribe to a specific topic, or all topics, call `SubscribeMessages` and set the `Subscribe` parameter to `False`.

Syntax

object.**SubscribeMessages**(Topic, Subscribe)

Table 357. Parameters

Name	Data Type	Description
Topic	ihMessageTopic	Topics of messages to Subscribe to (optional, default = True).
Subscribe	Boolean	Flag to unsubscribe to a specific topic (optional, default = True).

Returns

Boolean. Operation success / fail

Substitutions Method (MessageFields Object)

Determines whether the Substitutions should be returned in the `MessageRecordset` query.

Syntax

object.**Substitutions**

Parameters

None

Returns

None

Example

```
Dim maMyMessages As iHistorian_SDK.MessageRecordset
Set MyMessages = GetServer.Messages.NewRecordset With MyMessages.Fields

.Topic = True

.TimeStamp = True

.MessageString = True

.Substitutions = True

End With
```

T

TestCalculation Method (Tag Object)

Runs the calculation currently stored in the Calculation property. This calculation will be run with a current time of "Now". The results of the calculation will be stored in the Value and DataQuality parameters.

If an error occurs during the test, a description of the error will be stored in the ErrorMessage parameter.

Syntax

object.**TestCalculation**(Value, DataQuality, ErrorMessage)

Table 358. Parameters

Name	Data Type	Description
Value	Variant	Value of the calculation result.
DataQuality	String	Quality of the calculation result.
ErrorMessage	String	Description of any error that occurred during the test.

Returns

Boolean. Operation success / fail

TranslateMessage Method (Server Object)

Returns a translated message or prompt based on the current locale and the MessageNumber specified. If no translation is available for the current locale, the method uses the default message.

To insert context specific information into the generic message string, use substitutions. For example, the generic message string:

```
Connection To Server:[1]
Failed With Error Number: [2]
```

requires two substitutions, the first being the server, and the second being the error number.

The substituted message then reads:

```
Connection To Server: USGB014
Failed With Error Number: 65535.
```

Syntax

object.**TranslateMessage**(MessageNumber, DefaultMessage, Substitutions)

Table 359. Parameters

Name	Data Type	Description
MessageNumber	Long	Message or prompt number to translate (read-only).
DefaultMessage	String	Default message to translate (optional, read-only).
Substitutions	ParamArray	Ordered substitutions into message (optional, read-only).

Returns

String. The translated message text.

Example

```
Dim MyServer As New iHistorian_SDK.Server
Dim MyPrompt As String
' Connect to the default server
If Not MyServer.Connect Then
err.Raise 1, , "Failed to authenticate on server " + MyServer.ServerName
End If
```

```
' Translate the prompt from the connected server  
MyPrompt = MyServer.TranslateMessage(549, "User: [1]", MyServer.Username)  
' Prompt is translated to "User: Fred"
```

Method Reference U-Z

U

UnselectAll Method (TagRecordset Object)

Applies to:

Clears all selections in the current TagRecordset. See the SelectAll method and the Master Tag Property.

Syntax

object.**UnselectAll**

Parameters

None

Returns

None

Example

```
' Clear any current selection MyRecordset.UnselectAll
```

UserCalcFunctionsFromString Method (Server Object)

Applies to:

Converts the given string to an array of user calculation functions. The string is assumed to have been generated from a call to UserCalcFunctionsToString.

If no functions exist in the string, UserCalcFunctions will be set to Empty.

Syntax

object.**UserCalcFunctionsFromString**(FuncStr, UserCalcFunctions)

Table 360. Parameters

Name	Data Type	Description
FuncStr	String	String to convert.
UserCalcFunctions	Variant	Resulting array of UserCalcFunction objects.

Returns

Boolean. Conversion successful / failed.

UserCalcFunctionsToString Method

Applies to:

Converts the given array of user calculation functions to a string.

To convert an empty set of functions, pass a non-array value such as Empty.

Syntax

object.**UserCalcFunctionsToString**(UserCalcFunctions, FuncStr)

Table 361. Parameters

Name	Data Type	Description
UserCalcFunctions	Variant	Array of UserCalcFunction objects.
FuncStr	String	String resulting from conversion

Returns

Boolean. Conversion successful / failed.

W

WriteArray Method (DataRecordset Object)

Applies to:

Attempt to write a set of Data to the Historian archiver.

**Note:**

This function is not fully implemented yet and will always return `false` `current` `DataRecordset` before it imports the specified file.

Syntax

object.**WriteArray**(DataArray)

Table 362. Parameters

Name	Data Type	Description
DataArray	Variant	Data Array to be written to the Historian archiver.

Returns

Boolean. Write succeeded / failed.

WriteRecordset Method (DataRecordset Object)

Applies to:

Saves changes made to the DataRecordset object to the Historian server. If DataValues have not changed, the method does not write DataValues to the server.

Syntax

object.**WriteRecordset**

Parameters

None

Returns

Boolean. Write succeeded / failed.

WriteRecordset Method (MessageRecordset Object)

Applies to:

Saves changes made to the MessageRecordset object to the Historian server. Only new messages are written to the server.

Syntax

object.**WriteRecordset**

Parameters

None

Returns

Boolean. Write succeeded / failed.

WriteRecordset Method (TagRecordset Object)

Applies to:

Saves changes made to the TagRecordset Object to the Historian server. If tags have not changed, they are not re-written to the server.

Syntax

object.**WriteRecordset**([UseMasterTag])

Table 363. Parameters

Name	Data Type	Description
UseMasterTag	Boolean	Whether to apply Master tag changes to all tags (read-only optional).

Returns

Boolean. Write succeeded / failed.

X

XML Method (DataRecordset Object)

Applies to:

Returns an XML document fragment representing the DataValues and DataFields contained in the current DataRecordset.

Syntax

object.**XML**([XMLHeader], [StartIndex], [EndIndex])

Table 364. Parameters

Name	Data Type	Description
XMLHeader	String	XML to include before the DataRecordset XML (optional).
StartIndex	Long	Index of first tag to include in XML (optional).
EndIndex	Long	Index of last tag to include in XML (optional).

Returns

String. An XML document fragment string.

Example

```
Dim Recordset As DataRecordset

' Get A New Data Recordset

Set Recordset = MyServer.Data.NewRecordset

' Fill In Criteria, Get One Tag For Yesterday

With Recordset.Criteria

    .Tagmask = "MyNode.OneTag.F_CV"

    .StartTime = DateAdd("d", -1, Now)

    .EndTime = Now

End With

' Fill In Fields, Timestamp and Value

With Recordset.Fields

    .TimeStamp = True

    .Value = True End With

Recordset.QueryRecordset

' Print XML to Debug Window

Debug.Print Recordset.XML
```

XML Method (MessageRecordset Object)

Applies to:

Returns an XML document fragment representing the Messages and MessageFields contained in the current MessageRecordset.

Syntax

object.**XML**([XMLHeader], [StartIndex], [EndIndex])

Table 365. Parameters

Name	Data Type	Description
XMLHeader	String	XML to include before message XML (read-only, optional).
StartIndex	Long	Index of first message to Include in XML (read-only, optional).
EndIndex	Long	Index of last message to include in XML (read-only, optional).

Returns

String. An XML document fragment string.

XML Method (TagRecordset Object)

Applies to:

Returns an XML document fragment representing the Tags and TagFields contained in the current TagRecordset.

Syntax

object.**XML**([XMLHeader], [StartIndex], [EndIndex])

Table 366. Parameters

Name	Data Type	Description
XMLHeader	String	XML to include before the TagRecordset XML (read-only, optional).
StartIndex	Long	Index of first tag to Include in XML (read-only, optional).
EndIndex	Long	Index of last tag to include in XML (read-only, optional).

Example

```

Dim Recordset As TagRecordset

' Get a new tag recordset

Set Recordset = MyServer.Tags.NewRecordset

' Fill in criteria, aet all tags

With Recordset.Criteria

.Tagname = "*"

End With

' Fill in fields, get tagname and description

With Recordset.Fields

.Tagname = True

.Description = True

End With

Recordset.QueryRecordset

' Print XML to debug window

Debug.Print Recordset.XML

```

Event Reference A-Z

A

AlertReceived Event (Messages Object)

The AlertReceived event fires each time an alert is reported to a client. This event fires only for those alert topics that you subscribed to by using the SubscribeAlerts method of the Messages object.

Syntax

AlertReceived(NewAlert)

Table 367. Parameters

Name	Data Type	Description
NewAlert	Message	The Alert reported by the Historian server (read-only).

Example

```

' It is necessary to declare Messages "WithEvents" Dim WithEvents MyMessages As iHistorian_SDK.Messages

Attribute MyMessages.VB_VarHelpID = -1

```

```

Private Sub Form_Load()

' Subscribe To All Alert Topics

If Not MyMessages.SubscribeAlerts(ihMessageTopic.Security, True) Then

Err.Raise 1, , "Failed To Subscribe" End If

End Sub

' Event Procedure

Private Sub MyMessages_Alert_Received(NewMessage As Message)

' We Just Received A New Alert

With NewMessage

Debug.Print "Received Alert " + CStr(.MessageNumber) + _ " " + .MessageString

End With

End Sub
    
```

C

ChangeReceived Event (Tags Object)

Fires each time a tag configuration change is reported to a client. Subscribe to data changes using the current data received event. This event fires only for tags that you subscribed to by using the SubscribeChanges method of the Tags object. You can subscribe to tag changes on a per tag basis or you can pass "" to subscribe to changes on any tag.

Syntax

ChangeReceived(ChangedTag)

Table 368. Parameters

Name	Data Type	Description
ChangedTag	Tag	Tag configuration change reported by the server (read-only).

D

DataReceived Event (Data Object)

Fires each time a changed value is reported to a client. This event fires only for tags that you subscribed to by using the SubscribeData method of the Data object.

Syntax

DataReceived(Tagname, Value)

Table 369. Parameters

Name	Data Type	Column Header
Tagname	String	Tag with the current value change reported by the server (read-only).
Value	DataValue	Value reported by the server (read-only).

Example

```

' It is necessary to declare Data "WithEvents" Dim WithEvents MyData As iHistorian_SDK.Data Attribute
MyData.VB_VarHelpID = -1

Private Sub Form_Load()

' Subscribe To Changes

If Not MyData.SubscribeData("USGB014.FIC101.F_CV", 5000, True) Then

Err.Raise 1, , "Failed To Subscribe" End If

End Sub

' Event Procedure

Private Sub MyData_DataReceived(Tagname As String, DataValue As DataValue)

' We Just Received a Current Value Update

With DataValue

Debug.Print "Received Current Value For " + Tagname + " " + _

" At " + Format$ (.TimeStamp) + " With Value of " + _ CStr (.Value)

End With

End Sub

```

M**MessageReceived Event (Messages Object)**

) Fires each time a message is reported to a client. This event fires only for message topics that you subscribed to by using the SubscribeMessages method of the Messages object.

Syntax

MessageReceived(NewMessage)

Table 370. Parameters

Name	Data Type	Description
NewMessage	Message	Message reported by the Historian Server (read-only).

S**StatusReceived Event (Archives Object)**

Fires each time a tag configuration change is reported to a client. This event fires only if the SubscribeStatus property of the Archives object is set to true.

Syntax

StatusReceived(ChangedArchive)

Table 371. Parameters

Name	Data Type	Description
ChangedArchive	Archive	Reported change for Historian server archive (read-only).

Example

```
' It is necessary to declare Archives "WithEvents" Dim WithEvents MyArchives As iHistorian_SDK.Archives
Attribute MyArchives.VB_VarHelpID = -1

Private Sub Form_Load()

' Subscribe To Changes

MyArchives.SubscribeStatus = True

End Sub

' Event Procedure

Private Sub MyArchives_StatusReceived(ChangedArchive As Archive)

' We Just Received An Archive Status Update

With ChangedArchive

Debug.Print "Received Update For " + .Name + " (" + .FileName + ")" End With

End Sub
```

StatusReceived Event (Collectors Object)

Fires each time a Collectors' status or configuration change is reported to a client. This event fires only if the SubscribeStatus property of the Collectors object is set to True.

Syntax

StatusReceived(ChangedCollector)

Table 372. Parameters

Name	Data Type	Description
ChangedCollector	Collector	Reported change for collector (read-only).

Example

```
' It is necessary to declare Collectors "WithEvents"
Dim WithEvents MyCollectors As iHistorian_SDK.Collectors
Attribute MyCollectors.VB_VarHelpID = -1
Private Sub Form_Load()
' Subscribe To Changes
MyCollectors.SubscribeStatus = True
End Sub
```

T**TagNameChangeReceived Event (Tags Object)**

Occurs each time a tag is renamed. This event occurs only for tags that you subscribed to by using the SubscribeChanges method of the Tags object. You can subscribe to tag changes on a per tag basis or you can pass "" to subscribe to changes on any tag.

Syntax

TagNameChangeReceived(ChangedTag, oldTag)

Table 373. Parameters

Name	Data Type	Description
ChangedTag	Tag	Tag rename change reported by the server (read-only).
oldTag	String	Old tag name reported by the server (read-only).

Chapter 12. Historian Utility Suite

Alerting System

The Alerting System is a reliable and efficient solution designed to promptly notify users via email when a particular service becomes unavailable or experiences an unexpected interruption. This system aims to minimize downtime and ensure timely response to service disruptions, enabling users to take appropriate actions to mitigate the impact on their operations. By providing real-time alerts, it empowers users to stay informed about service interruptions and promptly address any issues.

Key features of this utility include:

- **Service Monitoring:** The alerting system continuously monitors the availability and status of the targeted service, whether it's a custom service or an application service like Historian Data Archiver(x64), or any other critical service.
- **Customizable Alert Conditions:** Alerting system is driven by a config file, which give the flexibility to use by any product. Users can define for alerts for specific services under which they want to receive alert emails. This system accommodates two categories of the services, in case of Historian, user can specify IH and Collectors, since the system do a search a 'contains' condition of the given string. It will monitor all the
- **Real-Time Email Notifications:** When the system detects a service stop or meets the predefined alert conditions, it immediately triggers an email notification to the designated user. The email includes relevant service name in the subject and the body.
- **User Management:** The alerting system allows users to manage their notification preferences and frequency settings in milli seconds to monitor services. They can change recipients to receive alerts, add or remove email addresses.
- **Dump Creation & Uploading to FTP:** A configurable attribute will allow the alerting system to create a dump when a service stops. uploads the mini dumps to preconfigured ftp sites, which reduces the manual errors during the setting to create dumps and ftp upload. Let's assume a user starts the alerting system, and after a few hours, a service get down, then the system automatically creates mini dumps and automatically uploads to the ftp mentioned for analysis.



Note:

The ServiceRunCheck.exe utility should be run with Administrator privileges. The ServiceRunCheck.exe.config, also provided with this utility, can be edited in any text editor (such as Notepad). In this file you can update details like user names, passwords, smtp clients, and so on.

For more information, see article ID 000068757 on the GE Vernova Support center: https://digitalsupport.ge.com/s/article/Historian-Alerting-System-Utility?language=en_US

Version Validator


The Version Validator utility reports if all the .exes and .dlls from a given folder are of correct version with the correct last modified date. This Utility aids the user to identify any mismatches of binaries.



Note:

The HistorianPayloadCheck.exe utility should be run with Administrator privileges, in order to generate master files.

This utility has two tabs: **PayloadCheck** and **Generate Masterfile** as shown in the following figure:



For more information on how to use, see article ID 000068787 on the GE Vernova Support center: https://digitalsupport.ge.com/s/article/Historian-Version-Validator-Utility?language=en_US

DiagnostiX Tool

The DiagnostiX is a powerful software solution designed to streamline the support and development process by providing a comprehensive understanding of the customer environment. This tool helps Support teams and Developers tackle customer issues, enabling them to self-solve obvious problems and significantly reducing the time and effort spent on resolution.

Key features and benefits include:

- **Environment Snapshot:** This tool offers a holistic view of the customer environment, capturing essential details such as operating system, hardware specifications, software versions, network configuration, and other relevant parameters. This comprehensive snapshot eliminates the need for back-and-forth communication to gather information, saving valuable time for both support teams and developers.
- **Self-Solve Capabilities:** This tool goes beyond just identifying issues; it also provides built-in solutions for common problems. Through a knowledge base of known issues and their resolutions, the tool offers step-by-step guidance to support teams and developers, enabling them to self-solve straightforward issues efficiently. This not only saves time but also empowers the teams to handle a broader range of customer concerns independently.
- **Enhanced Collaboration:** This tool acts as a collaborative platform, facilitating seamless communication between support teams and developers. It provides a centralized repository for sharing diagnostic reports, annotated screenshots, log files, and other relevant artifacts. This ensures that all stakeholders have access to the same information, fostering better collaboration and reducing the back-and-forth communication that often delays issue resolution.
- **Early Resolution and Customer Satisfaction:** With its comprehensive insights and self-solve capabilities, This tool empowers support teams to resolve customer issues at an earlier stage. By addressing problems swiftly, customer satisfaction levels soar, as frustrations are minimized, and the time taken for issue resolution is significantly reduced. Ultimately, this tool helps support teams deliver exceptional customer service and enhance overall customer experience.



Note:

The DiagnostiX.exe utility should be run with Administrator privileges. The DiagnostiX.exe.config, also provided with this utility, can be edited in any text editor (such as Notepad). In this file you can update details like user names, passwords, smtp clients, and so on.

For more information, see article ID 000068924 on the GE Vernova Support center: <https://digitalsupport.ge.com/s/article/DiagnostiX-Historian-Diagnostic-Report-Tool>

Chapter 13. Collector Tool Kit

Collector Toolkit Overview

Overview

The Collector Toolkit lets you write programs that integrate tightly with Proficy Historian and let you leverage the same configuration tools, redundancy schemes, and health monitoring as collectors that ship with Proficy Historian. A custom collector is a collector developed using the Collector Toolkit. It collects data and messages from a data source and writes them to a Data Archiver. Using the Collector Toolkit, you can create custom collectors that:

- Collect data and messages from any data source
- Perform collector compression and buffer collected data
- Report data and messages to a local or remote Data Archiver

Custom collectors can be developed to function much like the standard OPC and iFIX collectors that come with the Proficy Historian product. The collected data can be used in any application that connects to Proficy Historian.

The toolkit enables development of programs that collect data at the current time. It is not suitable for developing migration programs, file import programs, SQL import programs or other programs that produce data which has timestamps in the past. Use other Proficy Historian toolkits to accomplish these task.

The toolkit supports pre-processing raw data with Python Expression Tags during collection, provided that you enable this. For details on how to use these tags, refer to the Python Expression Tags in *Data Collectors General* .

Prerequisites

Prerequisites

This topic covers prerequisites for using the Collector Toolkit in Windows. To use the Collector Toolkit in Linux, consult [Installing and Configuring the Collector Toolkit for Linux \(on page 1900\)](#).

To create custom collectors using the Collector Toolkit:

- You must have Visual Studio 2010 and Historian 6.0 SP1 or higher installed and configured on your machine.
- You must ensure that you have administrative rights and open Visual Studio in Administrative mode.
- The collectors developed based on the Collector Toolkit must be written in C++.



Note:

- Both the computer the collector is running on and the Data Archiver it connects to must be Historian 6.0SP1 or higher. Also, Historian Administrator should be 6.0 SP1 or newer.
- You can create custom collectors using Collector Toolkit on both 32-bit and 64-bit collectors.

Enabling Python Expression Tags with the Collector Toolkit

To enable Python Expression Tags with the Collector Toolkit:

1. Open the registry in regedit.
2. Navigate to the key created for the specific collector type for which you want expression use enabled. The collector type is the value of `ServiceName` that is specified in the method call to `CCollectorDelegator::InitializeCollector`.
 - If you are creating a 64 bit collector, this is under `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services`.
 - If you are creating a 32 bit collector, this is under `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\Services`.
 - For example, if you are creating a 32 bit collector with a `ServiceName` of `RabbitMQCollector` with the toolkit, go to `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\Services\RabbitMQCo`.
3. Under that key, add a string variable with the following values:
 - Name: `ServiceExtensions`
 - Type: `REG_SZ`
 - Data: `PythonExpressions`
4. Ensure that the Python Expression Extension binary dependencies (`casablanca100.dll`, `python34.dll`, `PythonExpressionExtension.dll`) are in the same location as the collector executable.

Refer to the *Python Expression Tags* for details on how to use these tags.

Installing the Collector Toolkit with Historian

About Installation

This topic covers installing the Collector Toolkit with Historian in Windows. To use the Collector Toolkit in Linux, see [Installing and Configuring the Collector Toolkit for Linux \(on page 1900\)](#).

Before you install the Collector Toolkit, verify that Microsoft Visual Studio 2010 is already installed on your computer. The Collector Toolkit is one of the standard options available during the installation of Proficy Historian. User developed Collectors built with the Collector Toolkit will require a client license in the same manner as other API programs. Run the install on the computer on which you want to develop your collector and select the Collector Toolkit option at the prompt. Refer to the Getting Started with Historian guide for the complete installation procedure

Creating the Custom Collector Using the Wizard

You can create a custom collector using the Visual Studio wizard or the sample application available as part of the installation. If you want to create a collector using the wizard, follow the below procedure.

The toolkit, by default, gets saved in the same installation folder as Historian in the Program files folder of your computer. For example, `C:\Program Files\Proficy\Proficy Historian\CollectorToolkit\CollectorToolkit`. The example here indicates that Historian is installed in C drive. If Historian is installed in D drive, the location changes accordingly.

1. Navigate to the folder where the toolkit utility is saved. For example, `C:\Program Files\Proficy\Proficy Historian\CollectorToolkit\CollectorToolkit` in the case of a 32-bit collector and `C:\Program Files\Proficy\Historian\x86\CollectorToolkit` in case of a 64-bit collector.
2. Double-click the `CollectorToolkit.sln` file. A Microsoft Visual Studio window appears in Administrator mode.
3. Right-select the project in the Solution Explorer pane and select one of the following: **Build Solution** or **Rebuild Solution**.

An output window appears indicating whether the Build or Rebuild has been successful. If you see the message, `Build succeeded` or `Rebuild All succeeded`, it indicates that the wizard has been activated. If the wizard is successful, the `CollectorToolkit.ico` and `CollectorToolkit.vsz` files appear in the wizards' folder in Visual Studio.

4. Proceed to create a custom collector.

Installing and Configuring the Collector Toolkit for Linux

Installing and Configuring the Collector Toolkit for Linux

The toolkit is compiled and tested on CentOS 7 and Ubuntu 14. The minimum system requirements are:

- g++(GCC) 4.8.x
- glibc2.17+

Installing the Collector Tool kit for Linux

The Collector Toolkit is delivered as a *tar* file. There are four different artifacts to choose from: static and shared library versions of debug and non-debug (release) versions. Choose whichever of the artifacts best fits your needs.

Unzip the tar file at a location where you want to install it. There are 4 folders at the top level.

- **shared:** The **shared** folder contains an example collector using the Collector Toolkit. A sample **Make** file is also provided. This example works as is. You can use this as a template to create your own custom collector.
- **lib:** The **lib** folder contains two libraries: `libihAPI` and `libihCollectorDelegator`.
- **include:** The **include** folder contains include files that you would need to include in your custom collector. `ihAPI.h` is optional. It needs to be included only if you are making use of any System APIs directly in your custom collector.
- **bin:** The **bin** folder contains some pre-compiled binaries. `Random` is the binary for the Simulation Collector. `RandomValueSimulator` is the sample collector built using the example code in the **shared** folder.

Configuring the Collector Tool Kit

1. Update the following key in the `HistorianServers.reg` file: `[HKEY_LOCAL_MACHINE\Software\Intellution, Inc.\iHistorian\Services\<ServiceName>`.
`<ServiceName>` must match the service name passed to the `InitializeCollector()` function in `main()` in your custom collector.
2. Update the following two properties in the `HistorianServers.reg` file.
 - `HistorianNodeName`: Update this to your Historian Server's name or IP Address. The custom collector tries to connect to the Historian Server specified by this property.
 - `InterfaceName`: Change this to the interface name of your choice. The custom collector uses this to identify itself in Historian Admin Console.

Configuring Custom Collector Wizard

Configuring a Custom Collector using the Wizard

You can create a custom collector using the Visual Studio wizard or the sample application available as part of the installation.

To create a collector using the wizard, follow the below procedure.

1. Navigate to the folder where the toolkit utility is saved. For example, `C:\Program Files\Proficy\ProficyHistorian\CollectorToolkit\CollectorToolkit`. The toolkit, by default, gets saved in the same installation folder as Historian in the Program files folder of your computer. The example here indicates that Proficy Historian is installed on the C drive. If Proficy Historian is installed in D drive, the location changes accordingly.
2. Double-click the `CollectorToolkit.sln` file. A Microsoft Visual Studio window appears in Administrator mode.
3. Right-select the project in the Solution Explorer pane and select one of the following: **Build Solution** or **Rebuild Solution**.

An output window appears indicating whether the Build or Rebuild has been successful.

- If you see the message, `Build succeeded` or `Rebuild All succeeded`, it indicates that the wizard has been activated. If the wizard is successful, the `CollectorToolkit.ico` and `CollectorToolkit.vsz` files appear in the wizards' folder in Visual Studio.
 - Ensure that the `CollectorToolkit.vsz` and `CollectorToolkit.ico` files exist in the above corresponding Operating system locations.
 - If you are working in 64 bit operating system, open `CollectorToolkit.vsz` in Notepad and replace the following line: `Param="ABSOLUTE_PATH = C:\Program Files\Proficy\ProficyHistorian\CollectorToolkit\CollectorToolkit"` with `Param="ABSOLUTE_PATH = C:\Program Files\Proficy\ProficyHistorian\x86\CollectorToolkit\CollectorToolkit"`. This enables you to open the wizard correctly.
4. Proceed to Creating a custom collector as described below.

Creating a Custom Collector



Note:

The Collector Toolkit runtime for 32-bit collectors uses `ihCollector-DelegatorN.dll` and `ihCollector-DelegatorN.lib`, where *N* is a version number, which changes from version to version.



The Collector Toolkit runtime for 64-bit collectors uses `ihCollector-DelegatorN_x64.dll` and `ihCollector-DelegatorN_x64.lib`, where *N* is a version number, which changes from version to version.

1. Open Microsoft Visual Studio 2010 in Administrator Mode.
2. Open a new project by navigating to **File > New > Project**.
The New Project page appears.
3. In the Installed Templates section, select **Wizards**.
The Collector Toolkit Wizard window appears.
4. Enter the following information in the New Project page.
 - Provide the name of the collector in the Name field.
 - Provide the location where you want to save the Collector in the Location field. Select **Browse...** to navigate to the desired location.
 - Provide the solution name in the Solution name field. A solution name is the name of the Collector solution.
 - Select the Create directory for solution check box to create a directory for the collector.

5. Select **OK** to proceed.

The Welcome to the Historian Collector Toolkit Wizard page appears.

6. Select **Next** to proceed.

The Application Settings page appears. The options that you see on the Application Setting page are set by default. These are the recommended settings and should not be changed.

7. Select **Finish**

The Microsoft Visual Studio appears in Administrator mode with the source code framework for the custom collector. Write the custom logic in the Skeletal Methods generated through the Wizard for the respective functionality. Refer to [About Interfaces \(on page 1903\)](#) for a description of the methods.

Changing Historian Server Name

Changing the Historian Server Name Using Registry

By default, custom collector tries to connect to the local Historian server. If you want the collector to connect to a remote Historian server, you must change the `HistorianNodeName` registry key located at:

- On a 64 bit machine, this is under `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\Services\<CollectorName>\`
- On a 32 bit collector, this is under `\HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\<CollectorName>\`

Working with collector Interfaces

About Interfaces

A collector is an interface through which data can be sent to the Data Archiver.

The custom collector is a 32 bit windows executable, where you need to implement only the collector specific functionality. The toolkit provides the code that schedules collection, performs compression and buffering, and writes data to the Data Archiver.

The following is a list to provide better understanding.

Interfaces Enabling Basic Functionality

- `ihCollectorToolkitPreInitialize`
- `ihCollectorToolkitInitialize`
- `ihCollectorToolkitInitializeCompleted`
- `ihCollectorToolkitDefinitionInitialize`
- `ihCollectorToolkitReset`
- `ihCollectorToolkitPropertyUpdate`
- `ihCollectorGetTags`
- `ihCollectorToolkitShutdown`

Interfaces Enabling Advanced Functionality

These interfaces are further categorized as follows.

The following methods are used to perform operations on Polled tags:

- `ihCollectorToolkitPolledInit`
- `ihCollectorToolkitPolledInitCompleted`
- `ihCollectorToolkitASyncStartReading`
- `ihCollectorToolkitASyncAddTag`
- `ihCollectorToolkitASyncDeleteTag`
- `ihCollectorToolkitASyncReload`
- `ihCollectorToolkitDataCallback`

The following methods are used to perform operations on Hierarchical and Miscellaneous functions:

- `ihCollectorToolkitGetTagsHierarchical`
- `ihCollectorToolkitDestroyGroupData`
- `ihCollectorToolkitWriteValue`
- `ihCollectorToolkitDebugModeChange`
- `ihCollectorToolkitMiscReload`
- `ihCollectorToolkitGetData`

Collector Development

You can develop a collector that uses polled reads or unsolicited reads or both. Polled reads are grouped within the shell are present to collector specific code a list of tags to be polled. The collector specific code can do whatever grouping is necessary or efficient for that data source. Unsolicited tags are simply passed on by one to the collector specific code at collector start up and on configuration change. It is up to the collector specific code to group tags and report data changes into the collector shell.

You can support tag browse or you can hard code responses to browse requests and require the tags to be created in some other way such as the Microsoft Excel tag import.

Throughout development, consider what information would be useful to see in the collector logs to troubleshoot issues and use the debug mode functionality to control what messages should appear. Your collector specific code will be notified of changes to debug mode in the `ihCollectorToolkitDebugModeChange` function.

Collection can be paused and resumed without the collector `exe` being restarted. Pause and resume are relayed to the collector specific code in the `ihCollectorToolkitReset` function.

Your collector can choose to support a heartbeat, status, and rate functionality via the `ihCollectorToolkitWriteValue` function. In this case the collector would write into the data source in addition to the reading done during collection. The toolkit will call the write function once per minute and you will need to write to the data source.

Your collector can react to configuration changes sent to collector specific code in the `ihCollectorToolkitPropertyUpdate` function. These are changes to the collector itself in the General1-5 fields not changes to the tag list

Possibly the most complex design decision is if you should support on-the-fly configuration changes or require collector restart. Adding or removing tags to collection or changing collection intervals for active tags is not always possible for all data sources. Consider this as an advanced feature.

Custom Collector Design

Design topics for Creating Custom Collectors

Among the first design decisions to be made with a collector is to map the data source's timestamps, values, and qualities to the Proficy Historian types.

Timestamps

You can let the toolkit assign timestamps to polled or unsolicited data or you can provide the timestamps with unsolicited data. If you choose to provide timestamps, you must provide them in the GMT+0 time zone. Proficy Historian offers microsecond resolution on timestamps, which should be sufficient for most applications.

Values

The Proficy Historian has a finite set of data types. If your data source has other types that cannot be converted then do not collect those tags. If there is any scaling or adjustments to the data, consider if those should be done in your collector specific code or via input scaling in the toolkit or calculation tags in the Data Archiver. Also, consider what the value means if the data quality is not good. In most parts of Proficy Historian, if you set the data quality to bad then the value will be ignored.

Quality

This can be the most important design decision of your collector. Your design needs to indicate what data is meaningful and should be used in trends and reports and what data is not meaningful. If the Historian contains tags from other data sources, you should be consistent with other collectors so that the retrieval program need to be aware of where the data came from.

Once you have a design for timestamp, value, and quality, you should think about how best to group your tags for the most efficient collection. The toolkit will pass a list of polled and unsolicited tags to your code at startup and their intervals. For polled tags, you can mostly ignore the tags because you will be sent a list later when it is time to poll the data. For unsolicited tags, you need to build your own groups and notify the toolkit when data changes.

Adding Browsing functionality is optional but is recommended to have. Think about how your code will respond to browse requests and how you will filter the tagnames and descriptions.

Your code does not need to do anything for collector compression or for store and forward of data.

You collector can utilize the same log file mechanism as other collectors but you should decide what you should write to help troubleshoot the collector.

Finally, you should consider how your collector should react to tag changes made while the collector is running. Tags can be added or deleted or properties like Collection interval or Deadband can be modified.

Backward Compatibility of the Collector Toolkit

Backward Compatibility of the Collector Toolkit

From time to time, the runtime library files of the Collector Toolkit (namely `ihCollectorDelegator.dll` and its variants) undergo changes to introduce new features or fix defects.

In some cases, changes are introduced that break backward compatibility. This means that the new runtime library does not work with custom collectors developed with past versions of the Toolkit. In such cases, a new version number appears in the names of the DLL files to indicate that they should not replace previous releases of the runtime library.

In other cases, a new runtime library, with changes, still works with custom collectors developed with past versions of the Toolkit. If the replacement library has the same name as the replaced library, you can safely replace earlier versions of the runtime library with the new library.

The Collector Toolkit includes the latest version of header files and import libraries (`.h` and `.lib` files), but no previous versions of these files. However, the Toolkit ships all previously released runtime DLLs that are necessary for custom collectors developed in the past to run. When there have been successive releases of a DLL that are backward compatible (indicated by their shared name), only the latest release is shipped.

If you want to develop new custom collectors, you should acquire and use the latest version of the Collector Toolkit. If you want to maintain or fix defects in an existing custom collector, you can use the version of the Toolkit with which the collector was developed. Alternately, you may want to try a more recent version. However, in such a case, some changes to the source code may be necessary if the Toolkit contains changes that break backward compatibility.

Custom Collector Toolkit Interface Technical Reference

Custom Collector Toolkit Interface Technical Reference

The Collector Toolkit interfaces help in writing collectors with basic functionality such as initializing collectors, adding data and tags, the others help in writing advanced features such as store and forward functions, heartbeat, buffering, queuing. The following are the various interfaces in detail:

ihCollectorToolkitASyncAddTag

The shell will call this function at start up and on change to indicate a tag that should be collected. The collector specific code should keep all information about the tags and use it later to deliver the collected data.

Prototype

```
int ihInterfaceTKASyncAddTag(ihInterfaceTKASyncTagInfo *ASyncTag,
int IsCollectorStarting)
```

Returns

TRUE on success. FALSE if the tag could not be added. For example, if the tag has an invalid address you can return an error here or report bad data later after

`ihCollectorToolkitAsyncStartReading` is called.

Parameters

Name	Data Type	Description
ASyncTag	ihInterfaceTKASyncTagInfo	Refer to the structure description.
IsCollectorStarting	int	TRUE if this function is being called as part of collector start-up. FALSE if this is being called because a tag was added or modified while the collector was running.

ihCollectorToolkitAsyncDeleteTag

Use this tag to update information to the Collector when a tag is deleted so that it will stop collecting data from the source. For example, if you delete a tag or stop collection in the administrator then the shell will call this function.

Prototype

```
int ihCollectorToolkitAsyncDeleteTag(int tagId)
```

Returns

TRUE on success; your collector specific code should always return TRUE.

Parameters

Name	Data Type	Description
tagId	Int	Tag identifier; the tag name is not passed into this function. You would have to match the tag identifier with a magnate passed in <code>ihCollectorToolkitASyncAddTag</code> .

ihCollectorToolkitASyncInit

The collector shell will call this to indicate the start of a list of tags to be collected asynchronously. The tags will be delivered via the `ihCollectorToolkitASyncAddTag` function and the collector specific code should keep track of all tag information.

Prototype

```
int ihInterfaceTKASyncInit(void);
```

Returns

TRUE on success; your collector specific code should always return TRUE.

ihCollectorToolkitASyncInitCompleted

The collector shell will call this method to indicate the end of a list of tags to be collected asynchronously.

Prototype

```
int ihInterfaceTKASyncInitCompleted(void)
```

Returns

TRUE on success; your collector specific code should always return TRUE.

ihCollectorToolkitASyncReload

This function is used to perform a recalculation on all unsolicited tags in the custom collector. Custom collector must implement the necessary changes to read data from the source and send values via the `ihCollectorToolkitDataCallback`. The time frame for recalculation is given in the input parameters `StartTime` and `EndTime`.

For more information on the methods of unsolicited tags, refer the methods listed for unsolicited tags in [About Interfaces \(on page 1903\)](#).

Prototype

```
int ihCollectorToolkitASyncReload(ihTKTimeStruct TimeStruct *StartTime, ihTKTimeStruct TimeStruct
*EndTime)
```

Returns

Always, TRUE.

Parameters

Name	Data Type	Description
StartTime	ihTKTimeStruct	Reserved
EndTime	ihTKTimeStruct	Reserved

ihCollectorToolkitASyncStartReading

The collector shell will call this method to indicate that the collector should start reading data for asynchronous tags from the source and report any data changes to the shell.

Prototype

```
int CustomCollector:: ihCollectorToolkitASyncStartReading(void)
```

Returns

TRUE on success; your collector specific code should return TRUE.

ihCollectorToolkitDataCallback

This callback is used when unsolicited tags get the data and asynchronously writes them into the Historian. Custom collector receives the data from unsolicited tags and sends it to the `ihCollectorToolkitDataCallback`. This call back function internally writes the data into the Historian.

Prototype

```
void ihCollectorToolkitDataCallback(void *Param)
```

Returns

Void.

Parameters

Name	Data Type	Description
ASyncTag	ihInterfaceTKASyncData	Refer to the structure description.

Example

You can use this function as shown in the following example to create a thread using which the unsolicited tags

data is written into the Historian.

```

/// Summary;

/// Unsolicited dedicated thread corresponding method.
Here all unsolicited tags get data from source(usually, way should be source
notification to historian) and sends to historian

/// </summary>
/// <param name="param">;Collector instance</param>
UINT RandomValueSimulator::TKAsyncReadFunc(void* param)
{
    POSITION pos = NULL;

    RandomValueSimulator* pColl = (RandomValueSimulator*) param;

    while (TRUE)
    {
        if (g_DoAsyncRead)
        {
            CSingleLock lock(&g_Sync, TRUE);

            if (!g_AsyncTags.IsEmpty())
            {
                // gets each unsolicited tag into ihInterfaceTKAsyncTagInfo object

                if (!pos)

                    pos = g_AsyncTags.GetHeadPosition();

                ihInterfaceTKAsyncTagInfo* tag = g_AsyncTags.GetNext(pos);

                int numTags = 1;

                ihInterfaceTKDataInfo data;

                memset(&data, 0, sizeof(ihInterfaceTKDataInfo));

                data.Tag = pColl->TKStrdup(tag->Tag);

                data.DataProp.ValueDataType = tag->DataType;

                data.DataProp.TimeStamp = pColl->TKGetSystemTime();

                // gets data for selected tag

                pColl->ihCollectorToolkitGetData(0, 0, 0, numTags, NULL, &data);

                unsigned long collectionTime = (unsigned long)time(0);

                int tagId = tag->TagId;

                ihInterfaceTKAsyncData asyncData;

                memset(&asyncData, 0, sizeof(ihInterfaceTKAsyncData));
            }
        }
    }
}

```

```

    asyncData.NumValues = numTags;

    asyncData.TagIds = &tagId;

    asyncData.Values = &data.DataProp;

    asyncData.CollectionTimes = &collectionTime;

    // sends to historian
    pColl->ihCollectorToolkitDataCallback(&asyncData);
}

else
{
    pos = NULL;
}

}

else
{
    pos = NULL;
}

long sleepTimeInMs = 500 + (rand() % 46) * 100;

// sleep from 0.5 to 5 seconds
Sleep(sleepTimeInMs);

}

return 0;

}

```

ihCollectorToolkitDefinitionInitialize

Use this interface to specify what labels you want to appear on the collector configuration page of the administrator. The administrator will show 5 edit boxes for General 1 to General 5 but with this function you can control what text is show next to each edit box.

All custom collectors share the same set of labels.

Prototype

```
void ihCollectorToolkitDefinitionInitialize(ihCollectorToolkitDefProperties* CustomPropertyDesc)
```

Returns

Void.

Parameters

Name	Data Type	Description
CustomPropertyDesc	ihCollectorToolkitDefProp- erties	Pointer to a Custom Collec- tor's specific properties Gen- eral 1-5 definitions.

ihCollectorToolkitDestroyGroupData

Reserved for future use. Your collector specific code should call the `CCollectorDelegator` function.

Prototype

```
void ihCollectorToolkitDestroyGroupData(int NumTags, void *Data, void *Misc)
```

Returns

Void.

Parameters

Name	Data Type	Description
NumTags	int	Reserved
Data	void	Reserved
Misc	void	Reserved

ihCollectorToolkitDebugModeChange

The collector calls this method when a change is detected. 0 indicates only errors and important information should be written to log. 255 is the highest setting for all debug information to display.

Prototype

```
void ihCollectorToolkitDebugModeChange(int DoDebug)
```

Returns

Void.

Parameters

Name	Data Type	Description
DoDebug	int	Zero or non zero debug level.

ihCollectorToolkitGetData

This is the function called by the collector shell each time the collector should poll data from the data source. The shell will pass a list of tags by tag id to be read. The tagids were provided to the collector specific code in the `PolledAddTag` call. The string tagnames, if needed, are available in the `ihInterfaceTKDataInfo` structure. The collector should gather the data and fill in the remaining fields of the `ihInterfaceTKDataInfo`.

Prototype

```
void ihCollectorToolkitGetData(int MinInterval, int AnySourceTimes, int CreatePermGroup, int NumTags,
int *TagIds, ihInterfaceTKDataInfo *Data)
```

Returns

Void.

Parameters

Name	Data Type	Description
<code>MinInterval</code>	<code>int</code>	The minimum configured collection interval of the tags being passed in for polling.
<code>AnySourceTimes</code>	<code>Int</code>	TRUE if any of the tags to be collected are configured for Time assigned by source. This would mean the collector specific code has to do additional work to provide a timestamp with the data. If this is FALSE, then the collector shell will provide the timestamp.
<code>CreatePermGroup</code>	<code>Int</code>	FALSE if this is a one time read such at start up or collector redundancy fail over. In this case, you can choose to not make a permanent collection group inside your code. If this is TRUE, then this is a normal scheduled polled read and you should

Name	Data Type	Description
		consider making a permanent group in your code for greater efficiency.
NumTags	Int	Number of tags to be read.
TagIds	Int	List of tags to be read, identified by tag ID. The tag names are in the data parameter, if required.
Data	ihInterfaceTKDataInfo	Pointer to the Proficy Historian Collector Data Properties. This contains some information from the shell and then the collector specific code needs to fill in the collected values.

Example

Populating data for a single tag.

```
ihInterfaceTKDataInfodata;
memset(&data,0, sizeof(ihInterfaceTKDataInfo));
data.Tag= L"computername.OperatorName"
data.DataProp.ValueDataType= ihTKFloat; // correct data type- same as tag type
data.DataProp.TimeStamp= pColl->TKGetSystemTime(); //10/01/2014 07:05:00
data.DataProp.Value = 10; // value that matches the data type.
data.DataProp.Quality = ihTKOPCGood;
```

ihCollectorToolkitGetTagsHierarchical

Use this interface to retrieve and represent the data in a hierarchical manner.

Prototype

```
void ihCollectorToolkitGetTagsHierarchical(wchar_t* BrowsePosition, wchar_t* NodeFilter,
ihInterfaceTKHierarchicalBrowseResponse* Response)
```

Returns

Void.

Parameters

Name	Data Type	Description
BrowsePosition	wchar_t*	Position of browsing for specific Tag.
NodeFilter	wchar_t*	Node filtering required for tag to get hierarchical information.
Response	ihTKHierarchicalBrowseResponse	Hierarchical Groups of tags browse response.

ihCollectorGetTags

Use this interface to browse tags from source. The shell will give some criteria and the collector specific code should fill in the result.

Tags can be skipped when they exist in the data source but should not be collected into Proficy Historian. For example, if a tag has a data type that is not compatible with Proficy Historian, you would not return it and you can increment the number skipped.

Prototype

```
void ihCollectorToolkitGetTags(ihInterfaceTKTagRecordset *Tags, ihInterfaceTKCfgInfo *Cfg, wchar_t
    *BrowsePosition,
    ihTKBoolean Recursive, wchar_t *DescriptionMask, wchar_t *SourceAddressMask, int CanReadASync,
    int DoMsgPump, int *NumSkipped
```

Returns

Void.

Parameters

Name	Data Type	Description
Tags	ihInterfaceTKRecordset	Pointer to a Proficy Historian Tags Record set containing browse criteria and where you can return the tags.

Name	Data Type	Description
Cfg	ihInterfaceTKCfgInfo	Pointer to Proficiency Historian Collector Configuration Information. Use this if necessary to help determine the browse results.
BrowsePosition	wchar_t	Pointer to a position of browsing for specific Tag.
Recursive	ihTKBoolean	TRUE if the browse should be recursive in collector specific code. Applies only if your data source has a tree of available tags.
DescriptionMask	wchar_t	* or a description mask that you should use when determining tags to return.
SourceAddressMask	wchar_t	* or a source address mask that you should use when determining tags to return.
CanReadASync	int	Non-zero if your collector is capable of asynchronous reads. Typically, this parameter does not affect browse results.
DoMsgPump	int	0 should be ignored.
NumSkipped	int	Use this to return any tags that were skipped because they did not match the description or source address mask or had an invalid data type.

ihCollectorToolkitInitializeCompleted

When this method is called by the collector shell, it indicates that the initialization is complete.

Prototype

```
ihCollectorToolkitInitializeCompleted(void)
```

Returns

FALSE on success; collector should return FALSE.

ihCollectorToolkitInitialize

Use this interface to initialize the collector by using information in the `ihInterfaceTKCfgInfo` and `ihInterfaceTKPreCfgInfo` structures. Your code also needs to save away the callback pointers passed into this function for use later with unsolicited reads and browses.

Prototype

```
int ihCollectorToolkitInitialize(ihInterfaceTKCfgInfo *Cfg, ihInterfaceTKPreCfgInfo *PreCfg, wchar_t
*ErrorMsg,
int ErrorMsgSize, wchar_t *RegKeyName, ihCollectorToolkitCollectorCallbacks *Callbacks, int DoDebug)
```

Returns

TRUE if initialization was successful. Otherwise, FALSE. If initialization failed, you can return a text string error message in the `ErrorMsg` parameter and that message will be entered into the collector log.

Parameters

Name	Data Type	Description
<code>Cfg</code>	<code>ihInterfaceTKCfgInfo</code>	Pointer to the Proficy Historian Collector Configuration Information.
<code>PreCfg</code>	<code>ihInterfaceTKPreCfgInfo</code>	Pointer to the Collector pre-Configuration Information.
<code>ErrorMsg</code>	<code>wchar_t</code>	Pointer to an Initialization Error Message, if any. Any error would be reported to collector log.
<code>ErrorMsgSize</code>	<code>int</code>	Error Message Size. This is the maximum length that your error message size can be.

Name	Data Type	Description
RegKeyName	wchar_t	Pointer to a Registry Key Name. Will be filled in with the location of your collector's registry information.
Callbacks	ihTKCollectorCallbacks	Pointer to callbacks to functions inside the collector shell. Save these function pointers and call them at the appropriate time, such as to deliver unsolicited data into the shell.
DoDebug	int	This value will be zero if the collector is not in debug mode and non-zero if debug mode is enabled. Save this value and use it to log more or less information to your collector log.

ihCollectorToolkitMiscReload

Reserved for future use. Your collector specific code should simply call the function in the `CCollectorDelegator`.

Prototype

```
int ihCollectorToolkitMiscReload(ihTKTimeStruct *StartTime, ihTKTimeStruct *EndTime)
```

Returns

TRUE; your collector specific code should return TRUE.

Parameters

Name	Data Type	Description
*StartTime	ihInterfaceTKTimeStruct	Reserved
*EndTime	ihTKTimeStruct	Reserved

ihCollectorToolkitPolledAddTag

The collector shell calls this to indicate the tag will be used later in polled collection. The collector specific code should keep all information given as it will be used in the `ihInterfaceGetData` call.

The polled tag add notification is done via `ihCollectorToolkitPolledAddTag` and data is sent to Historian via `ihCollectorToolkitGetData`. The frequency of asking for data for polled tag is based on the tag collection interval.

Prototype

```
int ihCollectorToolkitPolledAddTag(ihInterfaceTKPolledTagInfo *PolledTag, int IsCollectorStarting)
```

Returns

TRUE on success; your collector specific code should return TRUE.

Parameters

Name	Data Type	Description
PolledTag	ihInterfaceTKPolledTagInfo	Pointer to a Historian Collector Polled Tag Information.
IsCollectorStarting	int	Parameter to provide information about collector state.

ihCollectorToolkitPreInitialize

Use this interface to provide the toolkit with some of the capabilities of the collector. Here, you can specify if you support multiple instances, if you support unsolicited reads, and if your collector supports browsing.

Information filled into the `ihInterfaceTKCfgInfo` structure will later be passed into the `ihCollectorToolkitInitialize` function.

Prototype

```
void ihCollectorToolkitPreInitialize(ihInterfaceTKPreCfgInfo *PreCfg, ihInterfaceTKCfgInfo *Cfg)
```

Returns

Void.

Parameters

Name	Data Type	Description
PreCfg	ihInterfaceTKPreCfgInfo	Pointer to Collector Configuration Information.
Cfg	ihInterfaceTKCfgInfo	Pointer to additional Collector Configuration Information.

ihCollectorToolkitPropertyUpdate

This function is called when the user changes any collector property in Historian Administrator such as the General1 -5 properties. Your collector specific code can decide what changes are meaningful.

Prototype

```
void ihCollectorToolkitPropertyUpdate(ihInterfaceTKCfgInfo *Cfg)
```

Returns

Void.

Parameters

Name	Data Type	Description
Cfg	ihInterfaceTKCfgInfo	Current values of Collector configuration information.

ihCollectorToolkitPolledInit

The collector shell calls this method at start up and on change to indicate the start of a list of tags to be polled, as the collector runs. The actual polling takes place in the `ihInterfaceGetData` call.

Prototype

```
int ihCollectorToolkitPolledInit(void);
```

Returns

FALSE on success; your collector specific code should return FALSE.

ihCollectorToolkitPolledInitCompleted

The collector shell will call this to indicate the end of the polled tag list. This informs the source to begin its initialization.

Prototype

```
int ihCollectorToolkitPolledInitCompleted(void);
```

Returns

FALSE on success; your collector specific code should return FALSE.

ihCollectorToolkitPropertyUpdate

This function is called when the user changes any collector property in Historian Administrator such as the General1 -5 properties. Your collector specific code can decide what changes are meaningful.

Prototype

```
void ihCollectorToolkitPropertyUpdate(ihInterfaceTKCfgInfo *Cfg)
```

Returns

Void.

Parameters

Name	Data Type	Description
Cfg	ihInterfaceTKCfgInfo	Current values of Collector configuration information.

ihCollectorToolkitPolledDeleteTag

The shell calls this function to notify the collector specific code that a tag will no longer be polled.

Prototype

```
int ihCollectorToolkitPolledDeleteTag(int tagId);
```

Returns

TRUE on success; your collector specific code should return TRUE.

Parameters

Name	Data Type	Description
TagId	int	TagId that is being deleted. The tag name is not passed into this function. Match the TagId with the information passed in the ihCollectorToolkitPolledAddTag.

ihCollectorToolkitPolledInitCompleted

The collector shell will call this to indicate the end of the polled tag list. This informs the source to begin its initialization.

Prototype

```
int ihCollectorToolkitPolledInitCompleted(void);
```

Returns

FALSE on success; your collector specific code should return FALSE.

ihCollectorToolkitReset

The toolkit will call this function when the collector is being paused or shutdown. Proficy Historian stores collector information before the Collector is shut down.

Prototype

```
void ihCollectorToolkitReset(int Shutdown)
```

Returns

Void.

Parameters

Name	Data Type	Description
Shutdown	int	0 if the collector pauses and non-zero if the collector is shutting down.

ihCollectorToolkitStartReading

When the shell calls this method, it indicates the collector specific code to start polled and unsolicited reading from the source.

Prototype

```
int ihCollectorToolkitStartReading(void)
```

Returns

TRUE on success; your collector specific code should return TRUE.

ihCollectorToolkitShutdown

The collector shell will call this function when the collector executable (.exe) is shutting down.

Prototype

```
void ihInterfaceTKShutdown(void);
```

Returns

Void.

ihCollectorToolkitTagChange

The toolkit will call this function when the properties of a tag are changed in Client Tools, Historian Administrator, or other external tools. The tag and what properties have changed are indicated in the tag props and changed fields.

This function is called on tag property change and is not involved with data changes.

Your collector should decide how to react to tag property changes or should ignore the changes.

Prototype

```
int ihCollectorToolkitTagChange(int TagId, iHTKTagProperties *TagProps, iHTKTagFields *ChangedFields
```

Returns

int (TRUE/FALSE).

Parameters

Name	Data Type	Description
TagId	int	TagID that has changed.
TagProps	iHTKTagProperties	Pointer to a Proficy Historian Tag Property structure that indicates the new tag property values.
ChangedFields	iHTKTagFields	Pointer to information about which tag properties have changed.

ihCollectorToolkitGetEnumeratedSets

The toolkit calls this function based on the value configured under the `SynchInterval` registry key value.

This function is called every x minutes, where x is the value configured for the registry key.

Collectors implemented using the Collector Toolkit have to implement this method to fetch the `EnumeratedSet` from their source.

Prototype

```
int ihCollectorToolkitGetEnumeratedSets(ihTKEnumeratedSetRecordSet *EnumeratedSetRecordSet)
```

Returns

int (TRUE/FALSE).

Parameters

Name	Data Type	Description
<code>EnumeratedSetRecordSet</code>	<code>ihTKEnumeratedSetRecordSet</code>	Pointer to an <code>EnumeratedSetRecordSet</code> structure which should be added to Historian Server.

ihCollectorToolkitWriteValue

The toolkit will call this function once per minute if the user has configured heartbeat/status/rate tags. If your collector does not support this feature you can hard code a return value and not do the write.

Prototype

```
void ihCollectorToolkitWriteValue(wchar_t *Tag, wchar_t *SValue, double DValue)
```

Returns

Void.

Parameters

Name	Data Type	Description
<code>Tag</code>	<code>wchar_t</code>	Pointer to a source address in the data source to write to.
<code>doubled Value</code>	<code>DValue</code>	Numeric value to be written, if the Tag is a numeric tag. For example, a report rate would be written to a rate tag or a 1 would be written to a heartbeat tag.

Name	Data Type	Description
SValue	SValue	The string value to be written if tag source address is a string tag. For example, the string Running would be written to a status tag.

What is a Helper Method?

Helper Methods are used to allocate memory for variables while developing Collectors. Using these helper methods will prevent cross boundary issues. The following are the Helper Methods:

Name	Description
<code>wchar_t*TKStrdup(const wchar_t* string)</code>	Use this method to allocate memory on the heap, assign values and returns.
<code>voidTKFree(void* pointer)</code>	Use this method to free up pointer memory.
<code>void*TKMalloc(_In_ size_t _Size)</code>	Use this method to allocate memory.

Custom Structure Technical Reference

What is a Structure?

A Structure is a user defined data type. Structures are used in Interface Methods to represent data types that are compatible with Historian and allow the custom collectors to interact with Historian.



Note:

The abbreviation, TK stands for Toolkit.

For developing basic Custom Collectors, you should have knowledge about the following structures:

- `ihInterfaceTKPreCfgInfo`, `ihInterfaceTKCfgInfo` - Maintains collector configuration information.
- `ihCollectorToolKitDefProperties` - Maintains collectors specific properties.
- `ihInterfaceTKDataInfo` - Maintains data information.
- `ihInterfaceTKRecordset` - Maintains tag recordset.
- `ihTKTagProperties` - Maintains tag properties.
- `ihTKTagFields` - Maintains tag fields details
- `ihTKTagCriteria` - Maintains tag criteria details.

- `ihTKDataType` - Maintains tag data type
- `ihInterfaceTKHierarchicalBrowseResponse` - Maintains hierarchical browse response information.
- `ihInterfaceTKASyncTagInfo` - Maintains Unsolicited tag information.
- `ihInterfaceTKPolledTagInfo` - Maintains Polled tag information.

The following are few more structures that are used for developing Custom Collectors:

- `ihTKTagRecordset`
- `ihTKBlobData`
- `ihTKHiddenValue`
- `ihTKRawQuality`
- `ihTKQuality`
- `ihTKCommentData`
- `ihTKComments`
- `ihTKDataProperties`
- `ihInterfaceTKASyncData`
- `ihTKGetDataType`
- `ihTKStatus`
- `ihTKMessageTopic`
- `ihTKCollectorCallbacks`
- `ihTKTimeStruct`
- `ihTKQualityStatus`
- `ihTKQualitySubStatus`
- `ihTKDataType`
- `ihTKInterfaceType`
- `ihTKCollectionType`
- `ihTKTimeStampType`
- `ihTKTimeResolution`
- `ihTKTagId`
- `ihTKConditionCollectionComparison`
- `ihTKAlarmInterfaceProperties`
- `ihTKHierarchicalBrowseResponse`

Custom Collector Toolkit Structure Reference

Following are the custom Collector Toolkit structure references:

ihInterfaceTKPreCfgInfo

The `ihInterfaceTKPreCfgInfo` structure maintains the pre-configuration information of a collector.

Definition

```
typedef struct ihInterfaceTKPreCfgInfo {
    ihTKInterfaceType InterfaceType;

    int MultipleInstancesAllowed;

    int MinimumInterval;

    int MaxTagsPerRead;

    int CanReadASync;

    int CanBrowseSource;

    int CanSourceTimestamp;

    int ForceInputScaling;

    int NeedMsgPump;

    float ForcedScaleHI;

    float ForcedScaleLO;

    int ForceASyncSource;

    int ForcePolledSource;

    int AsyncAllowAdjustWhenSource;

    int PolledAllowAdjustWhenSource;

    int DontWriteASyncOfflineValue;

    int DontWritePolledOfflineValue;

    int DoesReloadMode;

    int DoesLagTimes;

    ihTKTagFields ReloadTagFields;

    ihTKTagFields NotifyTagFields;

    int IsHistoricalCollector;

    int CanBrowseHierarchical;

    wchar_t ReloadModeName[100];

    TKCallBackFunctionCalcLibraryTag * CalcLibraryTagCallback;

    void * CalcLibraryTagCallbackParam;

    int CanSendOPCQuality;
} ihInterfaceTKPreCfgInfo;
```

Parameters

Name	Description
InterfaceType	Indicates the collector responsible for collecting data for the tag.

Name	Description
MultipleInstancesAllowed	Indicates whether multiple instances are allowed.
MinimumInterval	Indicates the minimum interval the collector uses.
MaxTagsPerRead	Indicates the maximum tags per read.
CanReadASync	Indicates whether Async tags can be read.
CanBrowseSource	If True, this column indicates that the collector is capable of browsing its source for tags.
CanSourceTimestamp	Indicates whether the data source is capable of providing timestamps along with the data.
ForceInputScaling	Forces input scaling to be used.
NeedMsgPump	Indicates whether a message pump is required.
ForcedScaleHI	Forces to use Hi Scaling.
ForcedScaleLO	Forces to use Low scaling.
ForceAsyncSource	Forces to use Async source.
ForcePolledSource	Forces to use polled source.
AsyncAllowAdjustWhenSource	Forces Async to allow adjust when source.
PolledAllowAdjustWhenSource	Forces to polled to allow adjust when source.
DontWriteASyncOfflineValue	Forces not to write Async offline value.
DontWritePolledOfflineValue	Forces not to write polled offline values.
DoesReloadMode	Uses the reload mode.
DoesLagTimes	Defines the lag times.
IsHistoricalCollector	Indicates whether it is a historical collector.
CanBrowseHierarchical	Indicates whether a hierarchical browse can be done.
ReloadModeName	Reload mode name.
CalcLibraryTagCallback	Call back function for calculation tag.
CalcLibraryTagCallbackParam	Calculation tag call back parameters
CanSendOPCQuality	Indicates whether OPC Quality can be sent.

ihInterfaceTKCfgInfo

The `ihInterfaceTKCfgInfo` structure maintains the configuration information of the collectors.

Definition

```
typedef struct ihInterfaceTKCfgInfo {
    int CanBrowseSource;
    int CanSourceTimestamp;
    int ForcePolled;
    int DoOnFly;
    wchar_t* CustomProp1;
    wchar_t* CustomProp2;
    wchar_t* CustomProp3;
    wchar_t* CustomProp4;
    wchar_t* CustomProp5;
    wchar_t StatusOutputAddress[500];
    wchar_t RateOutputAddress[500];
    wchar_t HeartbeatOutputAddress[500];
    wchar_t InterfaceName[500];
    wchar_t HistorianNodeName[1024];
    wchar_t LogFilePath[500];
    wchar_t BufferFilePath[500];
    uint32 MinimumDiskFreeBufferSize;
    uint32 MaximumMemoryBufferSize;
    int ShouldAdjustTime;
    int ShouldQueueWrites;
    int SourceTimeInLocalTime;
    volatile int32_t CollectionDelay;
    wchar_t DefaultTagPrefix[200];
    uint32_t DefaultCollectionInterval;
    ihTKCollectionType DefaultCollectionType;
    ihTKTimeStampType DefaultTimeStampType;
    int DefaultLoadBalancing;
    int DefaultCollectorCompression;
    float DefaultCollectorCompressionDeadband;
    uint32_t DefaultCollectorCompressionTimeout;
    int ReloadMode;
    volatile int32_t DisableOnTheFlyTagChanges;
}
```

```

uint32_t ReadLagTime;

int32_t MaxHistoricalRecoverySeconds;

int32_t HistoricalOverrunThresholdSecs;

int DontStartupPolling;

int DefaultSpikeLogic;

float DefaultSpikeMultiplier;

uint32_t DefaultSpikeInterval;

volatile int32_t DataRecoveryQueueEnabled;

int DefaultAbsoluteDeadbanding;

double DefaultAbsoluteDeadband;

int RedundancyEnabled;

wchar_t RedundancyPrincipalCollector[500];

volatile int32_t RedundancyIsActiveCollector;

wchar_t RedundancyPrimaryCollector[500];

uint32_t SyncThreadInterval;

} ihInterfaceTKCfgInfo;
    
```

Parameters

Name	Description
CanBrowseSource	If True, this column indicates that the collector is capable of browsing its source for tags.
CanSourceTimestamp	Indicates whether the data source is capable of providing timestamps along with the data.
ForcePolled	If you set as true then collection type will be forced to be <code>ihPolled</code> .
DoOnFly	Indicates whether to enable or disable on the fly changes.
CustomProp1	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral1</code> column is not user defined; it is different for each collector.
CustomProp2	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral2</code> column is not user defined; it is different for each collector.

Name	Description
CustomProp3	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral3</code> column is not user defined; it is different for each collector.
CustomProp4	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral4</code> column is not user defined; it is different for each collector.
CustomProp5	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral5</code> column is not user defined; it is different for each collector.
StatusOutputAddress[500]	The address in the source database into which the collector writes the status signal output.
RateOutputAddress[500]	An address or tag name in the data source into which the collector writes the current value of the events per minute output.
HeartbeatOutputAddress[500]	The address in the source database into which the collector writes the heartbeat signal output.
InterfaceName[500]	The name of the collector. The collector name is unique in a given Historian Server.
HistorianNodeName[1024]	The name of the <code>DataArchiver</code> server where we need to store our data.
LogFilePath[500]	Path name to specify the location of the log files.
BufferFilePath[500]	Path name to specify the location of the buffer files.
MinimumDiskFreeBufferSize	The minimum size (in MB) of disk buffer for buffering outgoing data.
MaximumMemoryBufferSize	The maximum size of memory buffer (in MB) for buffering outgoing data.
ShouldAdjustTime	If the data source supplies the timestamps, the <code>ShouldAdjustTime</code> value is False. If the collector supplies the timestamps, the <code>ShouldAdjustTime</code> value is True.
ShouldQueueWrites	Indicates whether queue writes are allowed or not.

Name	Description
SourceTimeInLocalTime	Applicable only for data source timestamps. Indicates whether the timestamps use local time. If SourceTimeInLocalTime is False, then UTC time is used.
CollectionDelay	The length of time, in seconds, that the collector should delay collection at start-up (to allow data source time to initialize).
DefaultTagPrefix[200]	The prefix that is automatically added to all tag names added by the specified collector.
DefaultCollectionInterval	The collection interval, in milliseconds, for tags added by the collector.
ihTKCollectionType DefaultCollectionType	<p>Type of collection used to acquire data for tags added by the collector:</p> <ul style="list-style-type: none"> • Unsolicited - The collector accepts data from the source whenever the source presents the data. • Polled - The collector acquires data from a source on a periodic schedule determined by the collector.
ihTKTimeStampType DefaultTimeStampType	<p>The type of time stamping applied to data samples at collection time for tags added by the collector:</p> <ul style="list-style-type: none"> • Source - The source delivers the timestamp along with the data sample. • Collector - The collector delivers the timestamp along with the collected data.
DefaultCollectorCompression	Indicates whether the default collector compression is enabled for tags added by the collector.
DefaultCollectorCompression-Deadband	The default collector compression deadband for tags added by the collector.
DefaultCollectorCompression-Timeout	Indicates the default collector compression time out value.
DisableOnTheFlyTagChanges	Indicates whether a user can perform on the fly changes to this tag. When enabled (True), you can

Name	Description
	<p>make changes to this tag without having to restart the collector.</p> <p>If this option is disabled (False), any changes you make to this tag does not affect collection until you restart the collector.</p>
DefaultSpikeLogic	Indicates whether the Spike Logic is enabled.
DefaultSpikeMultiplier	Indicates the default Spike Logic multiplier.
DefaultSpikeInterval	Indicates the default Spike Logic interval.
DataRecoveryQueueEnabled	Indicates whether the Recovery queue is enabled.
DefaultAbsoluteDeadbanding	Indicates if the absolute deadband is enabled.
RedundancyEnabled	Indicates that the collector redundancy is enabled.
RedundancyPrincipalCollector[500]	Indicates the principal collector.
RedundancyIsActiveCollector	Indicates that the current collector is active.
RedundancyPrimaryCollector[500]	Indicates the principal collector.
SyncThreadInterval	<p>If greater than 0, indicates that the collector is capable of synchronizing <code>EnumeratedSets</code> populated by <code>ihCollectorToolkitGetEnumeratedSets</code> implementation.</p> <p><code>ihCollectorToolkitGetEnumeratedSets</code> is fired every x minutes, where x is the value of <code>SyncThreadInterval</code>.</p>

ihCollectorToolkitDefProperties

The `ihCollectorToolkitDefProperties` structure maintains the Custom Collectors specific properties General1-5 definitions.

Definition

```
typedef struct {
    wchar_t* InterfaceDefName;
    int32_t InterfaceType;
    unsigned char IsSystemInterface;
```

```
wchar_t* General1Description;

wchar_t* General2Description;

wchar_t* General3Description;

wchar_t* General4Description;

wchar_t* General5Description;

} ihCollectorToolkitDefProperties;
```

Parameters

Name	Description
InterfaceDefName	The name of the Custom Collector.
InterfaceType	ihTKCustom- specifies the custom collector type.
IsSystemInterface	Boolean. If true, specifies whether it is a System collector or a custom collector. Default - false.
General1Description	Collector general-1 property description.
General2Description	Collector general-2 property description.
General3Description	Collector general-3 property description.
General4Description	Collector general-4 property description.
General5Description	Collector general-5 property description.

The parameters `General1Description`, `General2Description` to `General5Description`, specifies the collector specific properties descriptions which are not listed among the general collector properties. Using Collector Toolkit we can add up to 5 collector specific properties descriptions.

ihInterfaceTKDataInfo

The `ihInterfaceTKDataInfo` structure maintains data properties of a collector.

Definition

```
typedef struct ihInterfaceTKDataInfo {

wchar_t

*ArchiveTagName;

wchar_t *Tag;
```

```

ihTKDataProperties DataProp;

ihTKAPIStatus ErrorStatus;

ihTKGetDataTypes GetDataTypes;

wchar_t *ErrorMessage;

uint32_t CollectionTime;

wchar_t *CustomProp1;

wchar_t *CustomProp2;

wchar_t *CustomProp3;

wchar_t *CustomProp4;

wchar_t *CustomProp5;

} ihInterfaceTKDataInfo;
    
```

Parameters

Name	Description
*ArchiveTagName	Tag name of the archive.
*Tag	Name of the tag.
DataProp	Properties of the data.
ErrorStatus	Status of the error.
GetDataTypes	Data type.
*ErrorMessage	Error message.
CollectionTime	Collection time.
*CustomProp1	CustomProp1 property description.
*CustomProp2	CustomProp2 property description.
*CustomProp3	CustomProp3 property description.
*CustomProp4	CustomProp4 property description.
*CustomProp5	CustomProp5 property description.

Example

Populating data for a single tag.

```

ihInterfaceTKDataInfo data;

memset(&data, 0, sizeof(ihInterfaceTKDataInfo));

data.Tag= L"computername.OperatorName"
    
```

```

data.DataProp.ValueDataType= ihTKFloat;// correct data type- same as tag type

data.DataProp.TimeStamp = pColl->TKGetSystemTime(); //10/01/2014 07:05:00

data.DataProp.Value = 10; // value that matches the data type.

data.DataProp.Quality = ihTKOPCGood;

```

ihTKTagProperties

The `ihTKTagProperties` structure maintains the properties of a Historian tag.

Definition

```

typedef struct ihTKTagProperties {wchar_t* Tagname; wchar_t*
Description; wchar_t*
EngineeringUnits; wchar_t*
Comment; ihTKDataType
DataType;
unsigned char FixedStringLength;
wchar_t* InterfaceName; wchar_t*
SourceAddress; ihTKCollectionType
CollectionType; uint32_t
CollectionInterval; uint32_t
CollectionOffset; ihTKBoolean
LoadBalancing; ihTKTimeStampType
TimeStampType; double
HiEngineeringUnits;
double LoEngineeringUnits;
ihTKBoolean InputScaling;
double HiScale;
double LoScale;
ihTKBoolean InterfaceCompression;
float InterfaceDeadbandPercentRange;
ihTKBoolean ArchiveCompression;
float ArchiveDeadbandPercentRange;
wchar_t* CustomProp1;
wchar_t* CustomProp2;
wchar_t* CustomProp3;
wchar_t* CustomProp4;
wchar_t* CustomProp5;
wchar_t* ReadSecurityGroup;

```

```

wchar_t* WriteSecurityGroup;

wchar_t* AdministratorSecurityGroup;

ihTKTimeStruct LastModified;

wchar_t* LastModifiedUser;

ihTKInterfaceType InterfaceType;

ihTKBoolean ObsoleteField;

int32_t UTCBias;

uint32_t NumberOfCalculationDependencies;

wchar_t** CalculationDependencies;

uint32_t AverageCollectionTime;

ihTKBoolean CollectionDisabled;

uint32_t ArchiveCompressionTimeout;

uint32_t InterfaceCompressionTimeout;

ihTKBoolean SpikeLogic;

ihTKBoolean SpikeLogicOverride;

ihTKBoolean InterfaceAbsoluteDeadbanding;

double InterfaceAbsoluteDeadband;

ihTKBoolean ArchiveAbsoluteDeadbanding;

double ArchiveAbsoluteDeadband;

ihTKBoolean StepValue;

ihTKTimeResolution TimeResolution;

ihTKBoolean ConditionCollectionEnabled;

wchar_t* ConditionCollectionTriggerTag;

ihTKConditionCollectionComparison ConditionCollectionComparison;

wchar_t* ConditionCollectionCompareValue;

ihTKBoolean ConditionCollectionMarkers;

ihTKTagId TagId;

} ihTKTagProperties;

```

Parameters

Name	Description
Tagname	Tagname property of the tag.
Description	User description of the tag.
EngineeringUnits	Engineering units description of the tag.

Name	Description
Comment	User comment associated with the selected tag.
DataType	The data type returned in this column is the data type that is defined in Historian Administrator application.
FixedStringLength	Zero unless the data type is <code>FixedString</code> . If the data type is <code>FixedString</code> , this number represents the maximum length of the string value.
InterfaceName	Name of the collector responsible for collecting data for the specified tag.
SourceAddress	Address used to identify the tag at the data source. For <code>iFIXsystems</code> , this is <code>NTF(Node.Tag.Field)</code> .
CollectionType	Types of collection used to acquire data for the tag.
CollectionInterval	The time interval, in milliseconds, between readings of data from this tag.
CollectionOffset	The time shift from midnight, in milliseconds, for collection of data from this tag.
LoadBalancing	Indicates whether the data collector should automatically shift the phase of sampling to distribute the activity of the processor evenly over the polling cycle. This is sometimes called Phase Shifting.
TimeStampType	The type of time stamping applied to data samples at collection time:

Name	Description
	<ul style="list-style-type: none"> • Source: The source delivers the timestamp along with the data sample. • Collector: The collector delivers the timestamp along with the collected data.
HiEngineeringUnits	The high end of the engineering units range. Used only for scaled data types and input scaled tags.
LoEngineeringUnits	The low end of the engineering units range. Used only for scaled data types and input scaled tags.
InputScaling	<p>Indicates whether the measurement should be converted to an engineering unit's value. When set to False, the measurement is interpreted as a raw measurement.</p> <p>With input scaling set to True, the system converts the value to engineering units by scaling the value between the Hi and Lo Scale. If <code>InputScaling</code> is not enabled, the system assumes that the measurement is already converted into engineering units.</p>
HiScale	The high end value of the input scaling range used for the tag.
LoScale	The low end value of the input scaling range used for the tag.
InterfaceCompression	<p>Indicates whether collector compression is enabled for the tag.</p> <p>Collector compression applies a smoothing filter to incoming data by ignoring incremental changes in values that fall within a dead-band centered around the last collected value. The collector passes (to the archiver)</p>

Name	Description
	any new value that falls outside the deadband and then centers the deadband around the new value.
InterfaceDeadbandPercentRange	The current value of the compression deadband.
ArchiveCompression	Indicates whether the archive collector compression is enabled for the tag.
ArchiveDeadbandPercentRange	The current value of the archive compression deadband.
CustomProp1	The general (or spare) configuration fields for the collector. The CustomProp1 column is not user-defined; it is different for each collector.
CustomProp2	The general (or spare) configuration fields for the collector. The CustomProp2 column is not user-defined; it is different for each collector.
CustomProp3	The general (or spare) configuration fields for the collector. The CustomProp3 column is not user-defined; it is different for each collector.
CustomProp4	The general (or spare) configuration fields for the collector. The CustomProp4 column is not user-defined; it is different for each collector.
CustomProp5	The general (or spare) configuration fields for the collector. The CustomProp5 column is not user-defined; it is different for each collector.
ReadSecurityGroup	The name of the Windows security group controlling the reading of data for the tag.

Name	Description
WriteSecurityGroup	The name of the Windows security group controlling the writing of data for the tag.
AdministratorSecurityGroup	The name of the Windows security group responsible for controlling configuration changes for the tag.
LastModified	The date and time that the tag configuration for this tag was last modified. The time structure includes milliseconds.
LastModifiedUser	The user name of the Windows user who last modified this tag's configuration.
InterfaceType	The collector responsible for collecting data for the tag.
ObsoleteField	
UTCBias	<p>The time zone bias for the tag. Time zone bias is used to indicate the natural time zone of the tag expressed as an offset from UTC (Universal Time Coordinated) in minutes.</p> <p>UTC is the international time standard, the current term for what was commonly referred to as Greenwich Mean Time (GMT).</p>
ArchiveCompressionTimeout	<p>Indicates the maximum amount of time from the last stored point before another point is stored, if the value does not exceed the archive compression deadband.</p> <p>The data archiver treats the incoming sample after the timeout occurs as if it exceeded compression. It then stores the pending sample.</p>

Name	Description
InterfaceCompressionTimeout	Indicates the maximum amount of time the collector will wait between sending samples to the archiver.
SpikeLogic	Indicates whether the Spike Logic is enabled for the tag.
SpikeLogicOverride	Indicates whether the Spike Logic setting for this tag overrides the collector.
InterfaceAbsoluteDeadbanding	Indicates if absolute collector deadband is enabled for this tag.
InterfaceAbsoluteDeadband	Indicates the value for absolute collector deadband.
ArchiveAbsoluteDeadbanding	Indicates if absolute archive deadband is enabled for this tag.
ArchiveAbsoluteDeadband	Indicates the value for absolute archive deadband.
StepValue	Indicates if the <code>StepValue</code> property is enabled for the tag.
TimeResolution	Indicates the timestamp resolution in seconds, milliseconds, or microseconds.
ConditionCollectionEnabled	Indicates whether condition-based collection is enabled.
ConditionCollectionTriggerTag	Tag condition-based collection trigger tag.
ConditionCollectionComparison	Tag condition-based collection comparison operator.
ConditionCollectionCompareValue	Tag condition-based collection compare value.
ConditionCollectionMarkers	Indicates whether to employ condition-based collection markers.
TagId	TagID associated with this tag.

ihTKTagFields

The `ihTKTagFields` structure maintains the information that should be provided to Historian while creating tags.

Definition

```
typedef struct ihTKTagFields {  
  
    ihTKBoolean    AllFields;  
  
    ihTKBoolean    Tagname;  
  
    ihTKBoolean    Description;  
  
    ihTKBoolean    EngineeringUnits;  
  
    ihTKBoolean    Comment;  
  
    ihTKBoolean    DataType;  
  
    ihTKBoolean    FixedStringLength;  
  
    ihTKBoolean    InterfaceName;  
  
    ihTKBoolean    SourceAddress;  
  
    ihTKBoolean    CollectionType;  
  
    ihTKBoolean    CollectionInterval;  
  
    ihTKBoolean    CollectionOffset;  
  
    ihTKBoolean    LoadBalancing;  
  
    ihTKBoolean    TimeStampType;  
  
    ihTKBoolean    HiEngineeringUnits;  
  
    ihTKBoolean    LoEngineeringUnits;  
  
    ihTKBoolean    InputScaling;  
  
    ihTKBoolean    HiScale;  
  
    ihTKBoolean    LoScale;  
  
    ihTKBoolean    InterfaceCompression;  
  
    ihTKBoolean    InterfaceDeadbandPercentRange;  
  
    ihTKBoolean    ArchiveCompression;  
  
    ihTKBoolean    ArchiveDeadbandPercentRange;  
  
    ihTKBoolean    CustomProp1;  
  
    ihTKBoolean    CustomProp2;  
  
    ihTKBoolean    CustomProp3;  
  
    ihTKBoolean    CustomProp4;  
  
    ihTKBoolean    CustomProp5;  
  
    ihTKBoolean    ReadSecurityGroup;  
  
    ihTKBoolean    WriteSecurityGroup;  
  
    ihTKBoolean    AdministratorSecurityGroup;
```

```

ihTKBoolean    ObsoleteField;
ihTKBoolean    LastModified;
ihTKBoolean    LastModifiedUser;
ihTKBoolean    InterfaceType;
ihTKBoolean    TimeResolution;
ihTKBoolean    UTCBias;
ihTKBoolean    AverageCollectionTime;
ihTKBoolean    CalculationDependencies;
ihTKBoolean    CollectionDisabled;
ihTKBoolean    ArchiveCompressionTimeout;
ihTKBoolean    InterfaceCompressionTimeout;
ihTKBoolean    SpikeLogic;
ihTKBoolean    SpikeLogicOverride;
ihTKBoolean    InterfaceAbsoluteDeadbanding;
ihTKBoolean    InterfaceAbsoluteDeadband;
ihTKBoolean    ArchiveAbsoluteDeadbanding;
ihTKBoolean    ArchiveAbsoluteDeadband;
ihTKBoolean    StepValue;
ihTKBoolean    MaxTagsToRetrieve;
ihTKBoolean    ConditionCollectionEnabled;
ihTKBoolean    ConditionCollectionTriggerTag;
ihTKBoolean    ConditionCollectionComparison;
ihTKBoolean    ConditionCollectionCompareValue;
ihTKBoolean    ConditionCollectionMarkers;
ihTKBoolean    TagId;
} ihTKTagFields;

```

Parameters

Name	Description
AllFields	Tag request contains all fields.
Tagname	Tag request contains Tagname.
Description	Tag request contains Description.
EngineeringUnits	Tag request contains EngineeringUnits.
Comment	Tag request contains Comment.
DataType	Tag request contains DataType.

Name	Description
FixedStringLength	Tag request contains FixedStringLength.
InterfaceName	Tag request contains InterfaceName.
SourceAddress	Tag request contains SourceAddress.
CollectionType	Tag request contains CollectionType.
CollectionInterval	Tag request contains CollectionInterval.
CollectionOffset	Tag request contains CollectionOffset.
LoadBalancing	Tag request contains LoadBalancing.
TimeStampType	Tag request contains TimeStampType.
HiEngineeringUnits	Tag request contains HiEngineeringUnits.
LoEngineeringUnits	Tag request contains LoEngineeringUnits.
InputScaling	Tag request contains InputScaling.
HiScale	Tag request contains HiScale.
LoScale	Tag request contains LoScale.
InterfaceCompression	Tag request contains InterfaceCompression.
InterfaceDeadbandPercentRange	Tag request contains InterfaceDeadbandPercentRange.
ArchiveCompression	Tag request contains ArchiveCompression.
ArchiveDeadbandPercentRange	Tag request contains ArchiveDeadbandPercentRange.
CustomProp1	Tag request contains CustomProp1.
CustomProp2	Tag request contains CustomProp2.
CustomProp3	Tag request contains CustomProp3.
CustomProp4	Tag request contains CustomProp4.
CustomProp5	Tag request contains CustomProp5.
ReadSecurityGroup	Tag request contains ReadSecurityGroup.
WriteSecurityGroup	Tag request contains WriteSecurityGroup.

Name	Description
AdministratorSecurityGroup	Tag request contains AdministratorSecurityGroup.
ObsoleteField	Tag request contains ObsoleteField.
LastModified	Tag request contains LastModified.
LastModifiedUser	Tag request contains LastModifiedUser.
InterfaceType	Tag request contains InterfaceType.
TimeResolution	Tag request contains TimeResolution.
UTCBias	Tag request contains UTCBias.
AverageCollectionTime	Tag request contains AverageCollectionTime.
CalculationDependencies	Tag request contains CalculationDependencies.
CollectionDisabled	Tag request contains CollectionDisabled.
ArchiveCompressionTimeout	Tag request contains ArchiveCompressionTimeout.
SpikeLogic	Tag request contains SpikeLogic.
SpikeLogicOverride	Tag request contains SpikeLogicOverride.
InterfaceAbsoluteDeadbanding	Tag request contains InterfaceAbsoluteDeadbanding.
InterfaceAbsoluteDeadband	Tag request contains InterfaceAbsoluteDeadband.
ArchiveAbsoluteDeadbanding	Tag request contains ArchiveAbsoluteDeadbanding.
ArchiveAbsoluteDeadband	Tag request contains ArchiveAbsoluteDeadband.
StepValue	Tag request contains StepValue.
MaxTagsToRetrieve	Tag request contains MaxTagsToRetrieve.

Name	Description
ConditionCollectionEnabled	Tag request contains ConditionCollection-Enabled.
ConditionCollectionTriggerTag	Tag request contains ConditionCollection-TriggerTag.
ConditionCollectionComparison	Tag request contains ConditionCollection-Comparison.
ConditionCollectionCompareValue	Tag request contains ConditionCollection-CompareValue.
ConditionCollectionMarkers	Tag request contains ConditionCollection-Markers.
TagId	Tag request contains TagId

ihTKTagCriteria

The `ihTKTagCriteria` structure maintains the information required while retrieving data from Historian.

Definition

```
typedef struct ihTKTagCriteria {
    wchar_t* TagnameMask;
    uint32_t NumberOfTags;
    wchar_t** TagnameArray;
    wchar_t* DescriptionMask;
    wchar_t* EngineeringUnits;
    wchar_t* Comment;
    ihTKDataType DataType;
    unsigned char FixedStringLength;
    wchar_t* InterfaceName;
    wchar_t* SourceAddress;
    ihTKCollectionType CollectionType;
    uint32_t CollectionInterval;
    uint32_t CollectionOffset;
    ihTKBoolean LoadBalancing;
    ihTKTimeStampType TimeStampType;
    double HiEngineeringUnits;
    double LoEngineeringUnits;
}
```

```
ihTKBoolean InputScaling;

double HiScale;

double LoScale;

ihTKBoolean InterfaceCompression;

float InterfaceDeadbandPercentRange;

ihTKBoolean ArchiveCompression;

float ArchiveDeadbandPercentRange;

wchar_t* CustomProp1;

wchar_t* CustomProp2;

wchar_t* CustomProp3;

wchar_t* CustomProp4;

wchar_t* CustomProp5;

wchar_t* ReadSecurityGroup;

wchar_t* WriteSecurityGroup;

wchar_t* AdministratorSecurityGroup;

ihTKTimeStruct LastModified;

wchar_t* LastModifiedUser;

ihTKInterfaceType InterfaceType;

ihTKBoolean ObsoleteField;

int32_t UTCBias;

uint32_t AverageCollectionTime;

ihTKBoolean CollectionDisabled;

uint32_t ArchiveCompressionTimeout;

uint32_t InterfaceCompressionTimeout;

ihTKBoolean SpikeLogic;

ihTKBoolean SpikeLogicOverride;

ihTKBoolean InterfaceAbsoluteDeadbanding;

double InterfaceAbsoluteDeadband;

ihTKBoolean ArchiveAbsoluteDeadbanding;

double ArchiveAbsoluteDeadband;

ihTKBoolean SourceAddressIsMask;

ihTKBoolean StepValue;

int32_t MaxTagsToRetrieve;

ihTKTimeResolution TimeResolution;

ihTKBoolean ConditionCollectionEnabled;

wchar_t* ConditionCollectionTriggerTag;

ihTKConditionCollectionComparison ConditionCollectionComparison;
```

```

wchar_t* ConditionCollectionCompareValue;

ihTKBoolean ConditionCollectionMarkers;

ihTKTagId TagId;

} ihTKTagCriteria;

```

Parameters

Name	Description
TagnameMask	Tag name mask criteria.
NumberOfTags	Number of tags for a tag.
TagnameArray	Tag name array of a tag.
DescriptionMask	Tag description mask criteria.
EngineeringUnits	Tag engineering units criteria.
Comment	Tag comment criteria.
DataType	Tag data type criteria.
FixedStringLength	Tag fixed string length criteria.
InterfaceName	Tag interface name.
SourceAddress	Tag source address criteria.
CollectionType	Tag collection type criteria.
CollectionInterval	Tag collection interval criteria.
CollectionOffset	Tag collection offset criteria.
LoadBalancing	Tag load balancing enabled criteria.
TimeStampType	Tag timestamp type criteria.
HiEngineeringUnits	Tag high engineering unit criteria.
LoEngineeringUnits	Tag low engineering unit criteria.
InputScaling	Tag input scaling enabled criteria.
HiScale	Tag high scale value criteria.
LoScale	Tag low scale value criteria.
InterfaceCompression	Tag interface compression.

Name	Description
InterfaceDeadbandPercentRange	Tag interface deadband percentage range.
ArchiveCompression	Tag archive compression enabled criteria.
CustomProp1	Tag custom property 1.
CustomProp2	Tag custom property 2.
CustomProp3	Tag custom property 3.
CustomProp4	Tag custom property 4.
CustomProp5	Tag custom property 5.
ReadSecurityGroup	Tag read security group name criteria.
WriteSecurityGroup	Tag write security group name criteria.
AdministratorSecurityGroup	Tag administrator security group name criteria.
LastModified	Tag last modified time criteria.
LastModifiedUser	Tag last modified user name criteria.
InterfaceType	Tag interface type.
ObsoleteField	Tag obsolete field.
UTCBias	Tag UTC bias criteria.
AverageCollectionTime	Tag average collection time.
CollectionDisabled	Tag collection disabled criteria.
ArchiveCompressionTimeout	Tag archive-compression time out criteria.
InterfaceCompressionTimeout	Tag interface compression time out.
SpikeLogic	Tag spike logic enabled criteria.
SpikeLogicOverride	Tag spike logic override enabled criteria.
InterfaceAbsoluteDeadbanding	Tag interface absolute deadband.
ArchiveAbsoluteDeadbanding	Tag archive compression absolute deadband criteria.

Name	Description
SourceAddressIsMask	Whether to interpret source address criteria as a wildcard expression.
StepValue	Tag step value enabled criteria.
MaxTagsToRetrieve	Maximum number of tags to retrieve per query.
TimeResolution	Tag time resolution criteria.
ConditionCollectionEnabled	Tag condition-based collection enabled criteria.
ConditionCollectionTriggerTag	Tag condition-based collection trigger tag criteria.
ConditionCollectionComparison	Tag condition-based collection comparison operator criteria.
ConditionCollectionCompareValue	Tag condition-based collection compare value criteria.
ConditionCollectionMarkers	Tag condition-based collection markers enabled criteria.
TagId	TagId criteria.

ihTKDataType

The `ihTKDataType` structure contains the data types supported by Historian.

Definition

```
typedef enum ihTKDataType {
    ihTKDataTypeUndefined = 0,
    ihTKScaled,
    ihTKFloat,
    ihTKDoubleFloat,
    ihTKInteger,
    ihTKDoubleInteger,
    ihTKFixedString,
    ihTKVariableString,
    ihTKBlob, ihTKTime,
```

```
ihTKInt64,
ihTKUInt64,
ihTKUInt32,
ihTKUInt16,
ihTKMaxDataType} ihTKDataType;
```

Parameters

Name	Description
ihTKDataTypeUndefined	An Undefined data type.
ihTKScaled	A single precision (32-bit) floating-point type.
ihTKFloat	A single precision (32-bit) floating-point type.
ihTKDoubleFloat	A double precision (64-bit) floating-point type.
ihTKInteger	A short, signed integral type (16-bit).
ihTKDoubleInteger	A long, signed integral type (32-bit).
ihTKFixedString	A fixed-length UNICODE string The length is determined by <code>Tag.FixedStringLengthtag</code> property.
ihTKVariableString	A variable-length UNICODE string.
ihTKBlob	An unstructured, binary data type.
ihTKTime	A date-time type (64-bit), capable of storing one DateTime instance value.
ihTKInt64	A __int64-bit quad integer.
ihTKUInt64	A __int64-bit unsigned quad integer.
ihTKUInt32	A long, unsigned integral type (32-bit).
ihTKUInt16	A short, unsigned integral type (16-bit).
ihTKMaxDataType	A max data type.

ihInterfaceTKASyncTagInfo

The `ihInterfaceTKASyncTagInfo` structure contains unsolicited tag information.

Definition

```
typedef struct ihInterfaceTKASyncTagInfo {
    int TagId;
    wchar_t *ArchiveTagName;
    wchar_t *Tag;
    int Interval;
    double DeadbandPct;
    ihTKDataType DataType;
    int UseSourceTimeStamp;
    wchar_t *CustomProp1;
    wchar_t *CustomProp2;
    wchar_t *CustomProp3;
    wchar_t *CustomProp4;
    wchar_t *CustomProp5;
} ihInterfaceTKASyncTagInfo;
```

Parameters

Name	Description
TagId	TagId of the tag to be stored.
*ArchiveTagName	Tag name of the corresponding TagId stored in the archiver.
*Tag	Tag name used as primary key.
Interval	Collection interval of the tag.
DeadbandPct	Deadband percentage used for compression.
DataType	Datatype of the tag.
UseSourceTimeStamp	Enables you to specify to use source time stamp or collector timestamp.
*CustomProp1	The general (or spare) configuration fields for the collector. The CustomProp1 column is not user-defined; it is different for each collector.

Name	Description
*CustomProp2	The general (or spare) configuration fields for the collector. The CustomProp2 column is not user-defined; it is different for each collector.
*CustomProp3	The general (or spare) configuration fields for the collector. The CustomProp3 column is not user-defined; it is different for each collector.
*CustomProp4	The general (or spare) configuration fields for the collector. The CustomProp4 column is not user-defined; it is different for each collector.
*CustomProp5	The general (or spare) configuration fields for the collector. The CustomProp5 column is not user-defined; it is different for each collector.

ihInterfaceTKPolledTagInfo

The `ihInterfaceTKPolledTagInfo` structure maintains the polled tag information of the collectors.

Definition

```
typedef struct ihInterfaceTKPolledTagInfo {
    int TagId;
    wchar_t *ArchiveTagName;
    wchar_t *Tag;
    int Interval;
    int Offset;
    double DeadbandPct;
    ihTKDataType DataType;
    int UseSourceTimeStamp;
    wchar_t *CustomProp1;
    wchar_t *CustomProp2;
    wchar_t *CustomProp3;
    wchar_t *CustomProp4;
```

```
wchar_t *CustomProp5;
} ihInterfaceTKPolledTagInfo;
```

Parameters

Name	Description
TagId	TagId of the tag to be stored.
*ArchiveTagName	Tag name of the corresponding tag ID stored in the archiver.
*Tag	Tag name used as primary key.
Interval	Collection interval of the tag.
Offset	Offset from midnight (in seconds) to force sampling at a specific time of day.
DeadbandPercentage	Deadband percentage used for compression.
ihTKDataType DataType	Datatype of the tag.
UseSourceTimeStamp	Enables you to specify to use source time stamp or collector timestamp.
*CustomProp1	The general (or spare) configuration fields for the collector. The CollectorGeneral1 column is not user-defined; it is different for each collector.
*CustomProp2	The general (or spare) configuration fields for the collector. The CollectorGeneral2 column is not user-defined; it is different for each collector.
*CustomProp3	The general (or spare) configuration fields for the collector. The CollectorGeneral3 column is not user-defined; it is different for each collector.
*CustomProp4	The general (or spare) configuration fields for the collector. The CollectorGeneral4 col-

Name	Description
	umn is not user-defined; it is different for each collector.
*CustomProp5	The general (or spare) configuration fields for the collector. The CollectorGeneral5 column is not user-defined; it is different for each collector.

ihTKTagRecordset

The `ihTKTagRecordset` structure maintains Historian tags' record set.

Definition

```
typedef struct ihTKTagRecordset {
    ihTKTagFields RequestedFields;
    ihTKTagCriteria Criteria;
    ihTKTagFields CriteriaFields;
    uint32_t NumberOfRecords;
    ihTKTagPropertiesPtr TagRecords;
} ihTKTagRecordset;
```

Parameters

Name	Description
RequestedFields	Tag fields structure, which can be used to retrieve the specific fields of tags.
Criteria	Criteria structure, which can be used to query the tags based on the fields that are set.
CriteriaFields	Tag fields structure that need to be populated based on query criteria. For example, if user wants to query the tags based on Tag names then <code>CriteriaFields.Tagname</code> must set to true.
NumberOfRecords	Number of <code>TagRecords</code> .

Name	Description
TagRecords	Array of TagRecords. Each TagRecord is a tag property of each tag.

ihTKBlobData

The `ihTKBlobData` structure contains some memory that can support data in any format such as XML or CSV.

Definition

```
typedef struct ihTKBlobData {
    void*Blob;
    uint32_tBlobSize;
}ihTKBlobData;
```

Parameters

Name	Description
Blob	Blob data.
BlobSize	Blob size.

ihTKHiddenValue

The `ihTKHiddenValue` structure represents the mapping of supported data types Historian and Microsoft, the operating system.

Definition

```
typedef union ihTKHiddenValue {
    short Integer;
    int32_t DoubleInteger;
    float Float;
    double DoubleFloat;
    ihTKBlobData Blob;
    wchar_t* String;
    ihTKTimeStruct Time;
    int64_t Int64;
    uint64_t UInt64;
    uint32_t UInt32;
    uint16_t UInt16;
```

```
} ihTKHiddenValue;
```

Parameters

Name	Description
Integer	Single integer.
DoubleInteger	Double integer.
Float	Float.
DoubleFloat	Double float.
Blob	Blob.
String	String.
Time	Timestamp structure with seconds and nanoseconds.
Int64	Quad integer.
UInt64	Unsigned quad integer.
UInt32	Unsigned double integer.
UInt16	Unsigned short.

ihTKRawQuality

The `ihTKRawQuality` structure maintains the raw quality types of the tag data.

Definition

```
typedef struct ihTKRawQuality {
    ihTKBoolean Deleted;
    ihTKBoolean Replaced;
    unsigned char QualityStatus;
    unsigned char QualitySubStatus;
    ihTKBoolean OPCQualityValid;
    unsigned short OPCQuality;
} ihTKRawQuality;
```

Parameters

Name	Description
Deleted	Deleted tag data.
Replaced	Replaced tag data.
QualityStatus	QualityStatus of the tag data.
QualitySubStatus	QualitySubStatus of the tag data.
OPCQualityValid	OPCQualityValid.
OPCQuality	OPCQuality.

ihTKQuality

The `ihTKQuality` structure determines the percentage of good data in the raw quality.

Definition

```
typedef union ihTKQuality {
    ihTKRawQuality RawQuality;
    float PercentGood;
}ihTKQuality;
```

Parameters

Name	Description
<code>ihTKRawQuality</code>	RawQuality.
<code>ihTKQuality</code>	PercentGood.

ihTKCommentData

The `ihTKCommentData` structure maintains the comment about Comment Data in the tag, if any.

Definition

```
typedef struct ihTKCommentData {
    wchar_t*DataTypeHint;
    ihTKBlobDataCommentData;
}ihTKCommentData;
```

Parameters

Name	Description
<code>DataTypeHint</code>	Data type.
<code>CommentData</code>	Comment data.

ihTKComments

The `ihTKComments` structure maintains the information about comment data.

Definition

```
typedef struct ihTKComments {
    ihTKTimeStruct StoredOnTimeStamp;
    ihTKTimeStruct CommentTimeStamp;
    wchar_t* SuppliedUsername;
    wchar_t* Username;
    ihTKCommentData CommentData;
} ihTKComments;
```

Parameters

Name	Description
<code>StoredOnTimeStamp</code>	Stored time (Set by Archiver).
<code>CommentTimeStamp</code>	Timestamp.
<code>SuppliedUsername</code>	Supplied username (optionally given in <code>ih-CommentAdd</code>).
<code>Username</code>	NT user name of writer. (Set by Archiver).
<code>CommentData</code>	Comment Data.

ihTKDataProperties

The `ihTKDataProperties` structure represents the properties of the data.

Definition

```
typedef struct ihTKDataProperties {
    ihTKTimeStruct TimeStamp;
    ihTKDataType ValueDataType;
    ihTKValue Value;
    ihTKQuality Quality;
```

```

unsigned char NumberOfComments;

ihTKCommentsPtr Comments;

} ihTKDataProperties;

```

Parameters

Name	Description
TimeStamp	Time stamp of the data.
ValueDataType	Data type.
Value	Data value.
Quality	Quality.
NumberOfComments	Number of comments, if any.
Comments	Array of comments.

ihInterfaceTKASyncData

The `ihInterfaceTKASyncData` structure represents the unsolicited tags' data. `ihInterfaceTKASyncData` can be defined as an array of pointers if user want to send multiple data for multiple tags in one callback. This callback doesn't return errors, but will log any errors in writing to either the DA log or the collector specific log.

Definition

```

typedef struct ihInterfaceTKASyncData {

int NumValues; int *TagIds;

ihTKDataProperties *Values;

uint32_t *CollectionTimes;

} ihInterfaceTKASyncData;

```

Parameters

Name	Description
NumValues	Number of data properties.
*TagIds	Tag ids.
*Values	Array of data properties.
*CollectionTimes	Collected Times.

Example

Adding data to `ihInterfaceTKASyncData` structure.

```
uint32_t collectionTime = (uint32_t)time(0);

int tagId = tag->TagId;

ihInterfaceTKASyncData asyncData;

memset(&asyncData, 0, sizeof(ihInterfaceTKASyncData));

asyncData.NumValues = 1; asyncData.TagIds = &tagId;

asyncData.Values = &data.DataProp;

asyncData.CollectionTimes = &collectionTime;

pColl->ihCollectorToolkitDataCallback(&asyncData);
```

ihTKGetType

The `ihTKGetType` structure indicates the different ways data is collected from source.

Definition

```
typedef enum ihTKGetType {
    ihTKGetTypeTimed = 0,
    ihTKGetTypeAsync,
    ihTKGetTypeDemand
} ihTKGetType;
```

Parameters

Name	Description
<code>ihTKGetTypeTimed</code>	Polled data. The collector acquires data from a source on a periodic schedule determined by the collector.
<code>ihTKGetTypeAsync</code>	Asynchronous data, the collector accepts data from the source whenever the source presents the data.
<code>ihTKGetTypeDemand</code>	Data on demand, the collector accepts data from source whenever there is a demand for data.

ihTKStatus

The `ihTKStatus` structure contains the error statuses of Historian.

Definition

```
typedef enum ihTKStatus {  
  
    ihTKSTATUS_OK = 0,  
  
    ihTKSTATUS_FAILED = -1,  
  
    ihTKSTATUS_API_TIMEOUT = -2,  
  
    ihTKSTATUS_NOT_CONNECTED = -3,  
  
    ihTKSTATUS_INTERFACE_NOT_FOUND = -4,  
  
    ihTKSTATUS_NOT_SUPPORTED = -5,  
  
    ihTKSTATUS_DUPLICATE_DATA = -6,  
  
    ihTKSTATUS_NOT_VALID_USER = -7,  
  
    ihTKSTATUS_ACCESS_DENIED = -8,  
  
    ihTKSTATUS_WRITE_IN_FUTURE = -9,  
  
    ihTKSTATUS_WRITE_ARCH_OFFLINE = -10,  
  
    ihTKSTATUS_ARCH_READONLY = -11,  
  
    ihTKSTATUS_WRITE_OUTSIDE_ACTIVE = -12,  
  
    ihTKSTATUS_WRITE_NO_ARCH_AVAIL = -13,  
  
    ihTKSTATUS_INVALID_TAGNAME = -14,  
  
    ihTKSTATUS_LIC_TOO_MANY_TAGS = -15,  
  
    ihTKSTATUS_LIC_TOO_MANY_USERS = -16,  
  
    ihTKSTATUS_LIC_INVALID_LIC_DLL = -17,  
  
    ihTKSTATUS_NO_VALUE = -18,  
  
    ihTKSTATUS_DUPLICATE_INTERFACE = -19,  
  
    ihTKSTATUS_NOT_LICENSED = -20,  
  
    ihTKSTATUS_CALC_CIRC_REFERENCE = -21,  
  
    ihTKSTATUS_BACKUP_EXCEEDED_SPACE = -22,  
  
    ihTKSTATUS_INVALID_SERVER_VERSION = -23,  
  
    ihTKSTATUS_DATA_RETRIEVAL_COUNT_EXCEEDED= -24,  
  
    ihTKSTATUS_DELETEDATA_OUTSIDE_ACTIVE = -25,  
  
    ihTKSTATUS_ALARM_ARCHIVER_UNAVAILABLE = -26,  
  
    ihTKSTATUS_ARGUMENT_INVALID = -27,  
  
    ihTKSTATUS_ARGUMENT_NULL = -28,  
  
    ihTKSTATUS_ARGUMENT_OUT_OF_RANGE = -29,  
  
    ihTKSTATUS_MAX_ERROR_NUM = -30,  
  
} ihTKStatus;
```

Parameters

Name	Description
ihTKSTATUS_FAILED	Generic failure.
ihTKSTATUS_API_TIMEOUT	Server machine name not found, or server found but Archiver service is not running.
ihTKSTATUS_NOT_CONNECTED	Not currently connected to a Historian server.
ihTKSTATUS_INTERFACE_NOT_FOUND	Interface not found.
ihTKSTATUS_NOT_SUPPORTED	Reserved.
ihTKSTATUS_DUPLICATE_DATA	WriteData was called with <code>error_on_replace = TRUE</code> and the supplied data would have overwritten the existing data.
ihTKSTATUS_NOT_VALID_USER	Server found, but invalid username or password.
ihTKSTATUS_ACCESS_DENIED	Access is denied by the Historian server. Check user name/password or security group membership.
ihTKSTATUS_WRITE_IN_FUTURE	Write time stamp is too far in the future.
ihTKSTATUS_WRITE_ARCH_OFFLINE	There is no Archiver to hold the write time stamp.
ihTKSTATUS_ARCH_READONLY	The archive to hold the write time stamp is marked as read-only.
ihTKSTATUS_WRITE_OUTSIDE_ACTIVE	The write time stamp is before the active hours (now - "data is read only after") setting.
ihTKSTATUS_WRITE_NO_ARCH_AVAILABLE	No archive is available to hold the write time stamp.
ihTKSTATUS_INVALID_TAGNAME	Tagname used is not valid. Tagname does not exist in the Historian server.
ihTKSTATUS_LIC_TOO_MANY_TAGS	Exceeded tag license count on the server.
ihTKSTATUS_LIC_TOO_MANY_USERS	Exceeded user license count on the server.
ihTKSTATUS_LIC_INVALID_LIC_DLL	An invalid license DLL is installed.
ihTKSTATUS_NO_VALUE	No value has been passed to the function.
ihTKSTATUS_NOT_LICENSED	Your installation of Historian is not licensed.

Name	Description
ihTKSTATUS_CALC_CIRC_REFERENCE	Reserved.
ihTKSTATUS_DUPLICATE_INTERFACE	Reserved.
ihTKSTATUS_BACKUP_EXCEEDED_SPACE	Reserved.
ihTKSTATUS_INVALID_SERVER_VERSION	You are attempting to use this API on an invalid version of Historian.
ihTKSTATUS_DATA_RETRIEVAL_COUNT_EXCEEDED	You tried to request too many samples in one read request.
ihTKSTATUS_INVALID_PARAMETER	Generic failure when an invalid value is passed into the user API.

ihTKMessageTopic

The `ihTKMessageTopic` structure posts the status messages of Historian.

Definition

```
typedef enum ihTKMessageTopic {
    ihTKMessageTopicUndefined=0,
    ihTKConnections,
    ihTKConfigurationAudit,
    ihTKGeneral,
    ihTKServiceControl,
    ihTKPerformance,
    ihTKSecurity,
    ihTKMessageTopicMax,
    ihTKAllTopics=10000,
    ihTKAlertTopics, ihTKMessageTopics,
} ihTKMessageTopic;
```

Parameters

Name	Description
ihTKConnections	Connection related messages.
ihTKConfigurationAudit	Audit messages.
ihTKGeneral	General messages.

Name	Description
ihTKServiceControl	Service control messages.
ihTKPerformance	Performance related messages.
ihTKSecurity	Security related messages.
ihTKMessageTopicMax	Must be the last one after the basic topics and before the combinations.
ihTKAlertTopics	Any alerts.

ihTKCollectorCallbacks

The ihTKCollectorCallbacks structure controls the way the Async tag's functions are performed.

Definition

```
typedef struct ihTKCollectorCallbacks {
    TKCallBackFunctionNoParams *ShutdownFunc;
    TKCallBackFunctionOneParam *LogMsgFunc;
    TKCallBackFunctionOneParam *DataFunc;
    TKCallBackFunctionOneLongParam *AsyncOverrunFunc;
    TKCallBackFunctionOneLongParam *ChangeInterfaceControlFunc;
    TKCallBackFunctionTwoLongParams *ReconnectFunc;
    TKCallBackFunctionMessageAdd *AddMessageCallback;
    //CallbackFunctionAlarmNotification *AlarmNotificationFunc;
    TKCallBackFunctionGetTimeOffset *GetTimeOffsetFunc;
} ihTKCollectorCallbacks;
```

Parameters

Name	Description
*ShutdownFunc	When the Collector shuts down, this callback will be called from the toolkit.
*LogMsgFunc	When user wants to log any information, this call back is used.
*DataFunc	When data needs to be added, this call back is used.
*AsyncOverrunFunc	This callback is called for data overruns.

Name	Description
*ReconnectFunc	When user needs to reconnect to Historian, this callback is used.
*AddMessageCallback	When user wants to add a message to Historian, this callback is used.
*GetTimeOffsetFunc	When time offsets need to be adjusted, this callback is used.

ihTKTimeStruct

The `ihTKTimeStruct` structure contains the time value in seconds and Nanoseconds.

Definition

```
typedef struct ihTKTimeStruct {
    uint32_t Seconds;
    uint32_t Nanoseconds;
} ihTKTimeStruct
```

Parameters

Name	Description
Seconds	The time value in seconds.
Nanoseconds	The time value in nanoseconds.

ihTKQualityStatus

The `ihTKQualityStatus` structure defines the quality of the incoming data value that Historian stores.

Definition

```
typedef enum ihTKQualityStatus {
    ihTKOPCBad = 0,
    ihTKOPCUncertain,
    ihTKOPCNA, ihTKOPCGood,
} ihTKQualityStatus;
```

Parameters

Name	Description
Bad	The quality of the associated data value is bad. There is low or no confidence in the associated data value.
Uncertain	There is uncertainty about the associated data value.
NA	The associated data value is unused.
Good	The quality of the associated data value is good.

ihTKQualitySubStatus

The `ihTKQualitySubStatus` structure indicates the reasons for the quality of associated data value.

Definition

```
typedef enum ihTKQualitySubStatus {
    ihTKOPCNonspecific = 0,
    ihTKOPCConfigurationError,
    ihTKOPCNotConnected,
    ihTKOPCDeviceFailure,
    ihTKOPCSensorFailure,
    ihTKOPCLastKnownValue,
    ihTKOPCCommFailure,
    ihTKOPCOutOfService,
    ihTKScaledOutOfRange,
    ihTKOffline, ihTKNoValue,
    ihTKCalculationError,
    ihTKConditionCollectionHalted,
    ihTKCalculationTimeout
} ihTKQualitySubStatus;
```

Parameters

Name	Description
Nonspecific	The quality of the data value due to a non-specific status.
ConfigurationError	The quality of the data value due to a configuration error.

Name	Description
NotConnected	The quality of the data value due to a non-connectivity.
DeviceFailure	The quality of the data value due to device failure.
SensorFailure	The quality of the data value due to sensor failure.
LastKnownValue	The quality of the data value from the last known value.
CommFailure	The quality of the data value due to sensor failure.
OutOfService	The quality of the data value due to an out of service status.
ScaledOutOfRange	The quality of the data value due to the value being out of range.
OffLine	The quality of the data value due to the source being offline.
NoValue	The quality of the data value if the source does not provide a value.
CalculationError	The quality of the data value due to a calculation error.
ConditionCollectionHalted	The quality of the data due to halting the collection.
CalculationTimeout	The quality of the data value due to calculation time-out

ihTKDataType

The `ihTKDataType` structure contains the data types supported by Historian.

Definition

```
typedef enum ihTKDataType {
    ihTKDataTypeUndefined = 0,
```

```

ihTKScaled,
ihTKFloat,
ihTKDoubleFloat,
ihTKInteger,
ihTKDoubleInteger,
ihTKFixedString,
ihTKVariableString,
ihTKBlob,
ihTKTime,
ihTKInt64,
ihTKUInt64,
ihTKUInt32,
ihTKUInt16,
ihTKMaxDataType
} ihTKDataType;

```

Parameters

Name	Description
ihTKDataTypeUndefined	An Undefined data type.
ihTKScaled	A single precision (32-bit) floating-point type.
ihTKFloat	A single precision (32-bit) floating-point type.
ihTKDoubleFloat	A double precision (64-bit) floating-point type.
ihTKInteger	A short, signed integral type (16-bit).
ihTKDoubleInteger	A long, signed integral type (32-bit).
ihTKFixedString	A fixed-length UNICODE string The length is determined by <code>Tag.FixedStringLengthtag</code> property.
ihTKVariableString	A variable-length UNICODE string.
ihTKBlob	An unstructured, binary data type.
ihTKTime	A date-time type (64-bit), capable of storing one <code>Date-Time</code> instance value.
ihTKInt64	A <code>__int64</code> -bit quad integer.
ihTKUInt64	A <code>__int64</code> -bit unsigned quad integer.

Name	Description
ihTKUInt32	A long, unsigned integral type (32-bit).
ihTKUInt16	A short, unsigned integral type (16-bit).
ihTKMaxDataType	A max data type.

ihTKInterfaceType

The `ihTKInterface` structure contains the different interfaces that can interact with Historian. For example, `ihTKCustom` is a custom collector type generated by Toolkit.

Definition

```
typedef enum ihTKInterfaceType {
    ihTKInterfaceUndefined=0,
    ihTKIFix,
    ihTKRandom,
    ihTKOPC,
    ihTKFile,
    ihTKIFixLabData,
    ihTKManualEntry,
    ihTKOther,
    ihTKCalcEngine,
    ihTKServerToServer,
    ihTKPI,
    ihTKOPCAE,
    ihTKCIMPE,
    ihTKPIDistributor,
    ihTKCIMME,
    ihTKPerfTag,
    ihTKCustom
} ihTKInterfaceType;
```

Parameters

Name	Description
ihTKIFix	Interface for iFix_collector.
ihTKRandom	Interface for Simulation collector.

Name	Description
ihTKOPC	Interface for OPC DA collector.
ihTKFile	Interface for File collector.
ihTKIFixLabData	Interface for Deprecated.
ihTKManualEntry	Interface for Deprecated.
ihTKOther	Interface for Deprecated.
ihTKCalcEngine	Interface for Calculation collector.
ihTKServerToServer	Interface for ServerToServer collector.
ihTKPI	Interface for OSI PI collector.
ihTKOPCAE	Interface for OPC A&E collector.
ihTKCIMPE	Interface for Native CIMPLICITY collector.
ihTKPIDistributor	Interface for OSI PI distributor.
ihTKCIMME	Interface for Proficy Machine Edition collector.
ihTKCustom	Interface for Custom collector.

ihTKCollectionType

The `ihTKCollectionType` structure indicates the types of data collection methods Historian supports.

Definition

```
typedef enum ihTKCollectionType {
    ihTKUnsolicited=1, ihTKPolled
} ihTKCollectionType;
```

Parameters

Name	Description
ihTKUnsolicited	Asynchronous data collection based on incoming data value changes.
ihTKPolled	Periodic data collection based on a configured interval.

ihTKTimeStampType

The `ihTKTimeStampType` structure stores timestamp for data according to source time or the collector time.

Definition

```
typedef enum ihTKTimeStampType {
    ihTKSource = 1, ihTKInterface,
} ihTKTimeStampType;
```

Parameters

Name	Description
<code>ihTKSource</code>	Stores the timestamp from data source.
<code>ihTKInterface</code>	Stores the timestamp from the collector based on the host computer clock.

ihTKTimeResolution

The `ihTKTimeResolution` structure contains the time resolution that Historian supports.

Definition

```
typedef enum ihTKTimeResolution {
    ihTKSeconds = 0,
    ihTKMilliseconds,
    ihTKMicroseconds,
    ihTKNanoseconds
} ihTKTimeResolution;
```

Parameters

Name	Description
<code>ihTKSeconds</code>	Time up to a resolution of 1 second.
<code>ihTKMilliseconds</code>	Time up to a resolution of 1 millisecond (1-thousandth of a second).
<code>ihTKMicroseconds</code>	Time up to a resolution of 1 microsecond (1-millionth of a second).
<code>ihTKNanoseconds</code>	Time up to a resolution of 1 nanosecond (1-billionth of a second).

ihTKTagId

The `ihTKTagId` structure indicates the GUID of a tag.

Definition

```
typedef struct { uint32_t
Data1; unsigned short
Data2; unsigned short
Data3;
unsigned char Data4[ 8 ];
} ihTKTagId;
```

ihTKConditionCollectionComparison

The `ihTKConditionCollectionComparison` structure eliminates storing the values that are not within the defined range.

Definition

```
typedef enum ihTKConditionCollectionComparison
{
ihTKConditionComparisonUndefined = 0,
ihTKConditionComparisonEqual,
ihTKConditionComparisonLessThan,
ihTKConditionComparisonLessThanEqual,
ihTKConditionComparisonGreaterThan,
ihTKConditionComparisonGreaterThanEqual,
ihTKConditionComparisonNotEqual
}ihTKConditionCollectionComparison;
```

Parameters

Name	Description
<code>ihTKConditionComparisonEqual</code>	Equality comparison operator.
<code>ihTKConditionComparisonLessThan</code>	Value less than the comparison operator.
<code>ihTKConditionComparisonLessThanEqual</code>	Value less than or equal comparison operator.
<code>ihTKConditionComparisonGreaterThan</code>	Value greater than comparison operator.
<code>ihTKConditionComparisonGreaterThanEqual</code>	Value greater than or equal comparison operator.

Name	Description
ihTKConditionComparisonNotEqual	Inequality comparison operator.

ihTKAlarmInterfaceProperties

Definition

```
typedef struct ihTKAlarmInterfaceProperties {
    ihTKBoolean SupportsEventFiltering;
    ihTKBoolean SupportsCategoryFiltering;
    ihTKBoolean SupportsSourceFiltering;
    ihTKBoolean SupportsAreaFiltering;
    ihTKBoolean SupportsSeverityFiltering;
    int NumSimpleEvents;
    wchar_t** SimpleEventList;
    int NumTrackingEvents;
    wchar_t** TrackingEventList;
    int NumConditionEvents;
    wchar_t** ConditionEventList;
} ihTKAlarmInterfaceProperties;
```

Parameters

Name	Description
SupportsEventFiltering	Indicates if it supports event filtering.
SupportsCategoryFiltering	Indicates if it supports category filtering.
SupportsSourceFiltering	Indicates if it supports source filtering.
SupportsAreaFiltering	Indicates if it supports area filtering.
SupportsSeverityFiltering	Indicates if it supports severity filtering.
NumSimpleEvents	Number of simple events.
SimpleEventList	Simple events.
NumTrackingEvents	Number of tracking events.
TrackingEventList	Tracking events.
NumConditionEvents	Number of condition events.
ConditionEventList	Condition events.

ihTKHierarchicalBrowseResponse

The `ihTKHierarchicalBrowseResponse` structure represents the tags in a hierarchical way.

Definition

```
typedef struct ihTKHierarchicalBrowseResponse {
    int NodeCount;
    wchar_t** NodeNames;
    wchar_t** FullNodeNames;
    int LeafCount;
    wchar_t** LeafNames;
    wchar_t** FullLeafNames;
} ihTKHierarchicalBrowseResponse;
```

Parameters


Name	Description
NodeCount	Number of elements in the node.
NodeNames	Names of all the node names.
FullNodeNames	Complete node name.
LeafCount	Number of leaf elements.
LeafNames	Names of all the leaf elements.
FullLeafNames	Complete leaf names.

Hierarchical Custom Controller Browsing

Browsing Custom Controller in a Hierarchy

Hierarchical browsing can be developed using the Collector Toolkit. Hierarchical browsing enables you to browse custom collectors in a hierarchical manner if your server supports hierarchical organization of tags in a tree structure.

To browse for Custom Collector tags in a hierarchy:



1. Browse your data source for new tags.
2. From the Collector list, select the custom collector you wish to browse. A hierarchical tree appears in the Browse Results window.
3. To limit the displayed tags to only those that are not collected, from the Show Only list select **Source Tags Not Collected**.
4. To limit the displayed tags to match a tag name or tag description, enter the value to match in the **Source Tag Name** or **Description** text boxes.
5. Navigate to the node in the tree you want to browse, and then select Browse. The tags within the selected portion of the Custom Collector tag hierarchy will be displayed.
 - a. To browse automatically, select the **AutoBrowse** check box. The available tags will be displayed in the Browse Results window whenever a node is selected in the tree.
 - b. To show all child elements within a hierarchy, enable the **Show All Children** check box. All tags at, or below the hierarchical level of the selected node in the tree will be displayed in the Browse Results window.
6. Select the tag or tags you want to add to Historian, and select **Add Selected Tags**. Collected tags will appear in black in the tag list.

**Note:**

- The Browse option for the Custom Collector will not return all items that reside in the Server configuration. Items that may not get returned include, but are not limited to, unsupported data types and user-defined items in some Simulation Servers. Occasionally, items that do not appear in the browse can still be added manually using the Add Tag Manually option.
- If you are browsing and adding tags with the Custom Collector, note that some Custom Collectors do not support data blocks with a length greater than 1. These Servers can choose to show the first item in an array in the browse rather than show them all. For example, an OPC Server may contain 3000 analog values datablock:1 to datablock:3000, but would only show datablock:1.
- If you want to archive data from poll records of a length greater than 1, it is recommended that you use the Excel Add-In to configure a large block of tags - including the missing items - and add the tags.
- If you are unable to browse items on your server containing forward slashes (/), you may have to change the default separator in your Custom Collector configuration. To do so, you will need to open the Windows Registry Editor and edit the `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc\iHistorian\Services\[Collector Name]\OPCBrowseTreeSep` key (where [Collector Name] is the name of your Custom collector) and change the string value to a character not present among your Server item IDs. Typical values include |, !, or &. Create this key, if it does not already exist.
- If you are unable to browse readable items in your server with the Custom collector, you may need to change the browse access mask used by the collector. To do so, you will need to open the Windows Registry Editor and edit the `[HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\[Collector Name]` (where [Collector Name] is the name of your Custom collector) and add DWORD key "OPCBrowseAccessRightsMask"=dword:00000003. Valid values are 0, 1, 2, 3 with 1 being the default. Use 0 or 3 if you are unable to browse readable items. Creating or changing the value takes effect on the next browse attempt and does not require a collector restart.

Developing Hierarchical Browsing using Collector Toolkit

The following callback is used to develop hierarchical browsing using the Collector Toolkit:

```
ihCollectorToolkitGetTagsHierarchical(wchar_t* BrowsePosition, wchar_t* NodeFilter,
ihTKHierarchicalBrowseResponse* Response);
```

The following are the parameters in this callback:

Name	Description
BrowsePosition	The place where the current node is selected.
NodeFilter	The delimiter using which hierarchical node differentiation is made
Response structure	Contains the number of nodes/leaves for a particular node.

To define the hierarchical tree format as illustrated in the Add Multiple Tags from Collector figure above, Historian provides the following information in three responses, provided as a sample here. Use the information in the following three responses to browse the tags and add the required tags.

As a first response Historian returns:

```
ihInterfaceGetTagsHierarchical()
```

The following are the parameter values:

```
BrowsePosition "ihHierarchicalBrOwSeRoOt"
NodeFilter: "" (By default, this uses a "/")
Response = NULL
NodeCount 1 int
NodeNames "_Status" wchar_t *
FullNodeNames "/_Status" wchar_t *
ihInterfaceGetTags()
BrowsePosition "ihHierarchicalBrOwSeRoOt" wchar_t*
```

Second response:

```
ihInterfaceGetTagsHierarchical()
BrowsePosition "/_Status"
NodeNames "DA_Server"
FullNodeNames "/_Status/DA_Server"
ihInterfaceGetTags()
BrowsePosition "/_Status"
```

Third response:

```
ihInterfaceGetTagsHierarchical()
BrowsePosition "/_Status/DA_Server"
BrowsePosition "/_Status/DA_Server"
```

Collector Initialization Callbacks

The following are the callbacks used for a collector when it is initialized:

- `ihCollectorToolkitPreInitialize`
- `ihCollectorToolkitInitialize`
- `ihCollectorToolkitInitializeCompleted`

When a collector is shutting down, `ihCollectorToolkitShutdown` method is called and the collector performs all the necessary steps before it is completely shut down.

Example

The following sample program helps you understand the `ihCollectorToolkitPreInitialize` function.

Historian expects Custom Collector Pre-Initialization information from the user. For example, custom collector can browse tags, collector type and so on.

```
/// </summary>
/// <param name="PreCfg">Collector Pre - Configuration information structure</param>
/// <param name="Cfg">Collector Configuration information structure</param>
void RandomValueSimulator::ihCollectorToolkitPreInitialize(ihInterfaceTKPreCfgInfo *PreCfg, ihInterfaceTKCfgInfo *Cfg)
{
    // Initializes General1-5 values, here General1,2 were initialized with 1000, 60.
    Cfg->CustomProp1 = TKStrdup(_T("1000"));
    Cfg->CustomProp2 = TKStrdup(_T("60"));
    // Historian follows representation of the collectors in the form of ComputerName_CollectorName, Tags in the form of
    ComputerName.TagName.
    // In the following section custom collector is trying to get the computer name.
    CString ComputerName, IP;
    TKGetHostNameAndIP(ComputerName, IP);
    if (ComputerName.GetLength() > 0)
    {
        ComputerName.Append(_T("."));
        wcsncpy_s(Cfg->DefaultTagPrefix, ComputerName.GetBuffer());
    }
}
```

```

}

RandPreCfg = *PreCfg;

RandPreCfg.CanSendOPCQuality = TRUE; // to send OPC Quality

RandPreCfg.InterfaceType = ihTKCustom; // interface type

RandPreCfg.MultipleInstancesAllowed = FALSE;

RandPreCfg.MinimumInterval = RandMinimumInterval;

RandPreCfg.MaxTagsPerRead = MaxTagsPerGroup;

RandPreCfg.CanReadASync = TRUE;// to read tags Asynchronously

RandPreCfg.CanBrowseSource = TRUE;// you can browse the collector

RandPreCfg.CanSourceTimestamp = TRUE;// collector sends data containing source time stamp or server time stamp

RandPreCfg.ForceInputScaling = FALSE;

RandPreCfg.NeedMsgPump = FALSE;

RandPreCfg.ForcedScaleLO = 0.0; // Low engineering unit

RandPreCfg.ForcedScaleHI = (float) RAND_MAX;// High engineering unit

RandPreCfg.DoesReloadMode = FALSE;

RandPreCfg.DoesLagTimes = FALSE;

RandPreCfg.CanBrowseHierarchical = TRUE;

*PreCfg = RandPreCfg;
}

```

For the `ihCollectorToolkitInitialize` function:

```

Collector Initialization

/// </summary>

/// <param name="Cfg">Collector Configuration information</param>

/// <param name="PreCfg">Collector Pre-Configuration Information</param>

/// <param name="ErrorMsg">Error Message while initializing</param>

/// <param name="ErrorMsgSize">Size of Error Message</param>

/// <param name="RegKeyName">modification required registry keys, if any </param>

/// <param name="Callbacks">Callbacks of all the asynchronous methods</param>

/// <param name="DoDebug">debug param</param>

/// <returns>status of the method call</returns>

int RandomValueSimulator::ihCollectorToolkitInitialize(ihInterfaceTKCfgInfo *Cfg,
ihInterfaceTKPreCfgInfo *PreCfg, wchar_t *ErrorMsg, int ErrorMsgSize, wchar_t *RegKeyName, ihCollectorToolkitCallback
*Callbacks, int DoDebug)
{
// updates configuration information to collector
ihCollectorToolkitPropertyUpdate(Cfg);

```

```

TKFree(TagPrefix);

// Historian follows representation of Tags in the form of ComputerName.TagName.
TagPrefix = TKStrdup(Cfg->DefaultTagPrefix);

Cfg->DoOnFly = 1;

// Initializes error msg to ""(NULL)
ErrorMsg = TKStrdup(_T(""));

srand((unsigned) time(NULL));

RandCfg = *Cfg;

g_Callbacks = Callbacks;

return(TRUE);

}

```

Polled Tag Callbacks

For polled tags we use different callback functions at various stages.

Step 1

At collector start up, `ihCollectorToolkitPolledInit` and `ihCollectorToolkitPolledInitCompleted` callbacks are triggered and the details of all the Polled tags for the given collector is returned.

Step 2

If a polled tag is added, `ihCollectorToolkitPolledAddTag` method is called and the details of the tag is entered in the collector tag list.

Step 3

If a polled tag is deleted, `ihCollectorToolkitPolledDeleteTag` method is called and the tag details are removed from the collector tag list.

Example

The following sample helps you understand the given callback functions.

The collectors maintains the polled tag details in the local Cache as:

```
map<int, ihInterfaceTKPolledTagInfo> TagIdToTagInfoMap;
```

This map is filled using this sample example:

```

/// Polled tags initialization started
/// </summary>
/// <returns>TRUE/FALSE</returns>

```

```

int RandomValueSimulator::ihCollectorToolkitPolledInit(void)
{
    TagIdToTagInfoMap.clear();

    return CCollectorDelegator::ihCollectorToolkitPolledInit();
}

-----

/// <summary>
/// Historian updating the source saying that, polled tags initialization successful.
/// Are there any initialization from source for polled tags?
/// <summary>
/// <returns>TRUE/FALSE</returns>
int RandomValueSimulator::ihCollectorToolkitPolledInitCompleted(void)
{
    return CCollectorDelegator::ihCollectorToolkitPolledInitCompleted();
}

-----

/// <summary>
/// Adds polled tag to the historian from source
/// </summary>
/// <param name="PolledTag">ihInterfaceTKPolledTagInfo instance</param>
/// <param name="IsCollectorStarting">collector status</param>
/// <returns>TRUE/FALSE</returns>
int RandomValueSimulator::ihCollectorToolkitPolledAddTag(ihInterfaceTKPolledTagInfo
*PolledTag, int IsCollectorStarting)
{
    TagIdToTagInfoMap.insert(std::pair<int, ihInterfaceTKPolledTagInfo>
(PolledTag->TagId, *PolledTag));

    return CCollectorDelegator::ihCollectorToolkitPolledAddTag(PolledTag,
IsCollectorStarting);
}

-----

```

```

/// <summary>
/// Deleted polled tag from Historian from Client Tools/non web admin/external tools
/// <summary>
/// <param name="tagId">Tag Identification</param>
/// <returns>TRUE/FALSE</returns>
int RandomValueSimulator::ihCollectorToolkitPolledDeleteTag(int tagId)
{
    TagIdToTagInfoMap.erase(TagIdToTagInfoMap.find(tagId));
    return CCollectorDelegator::ihCollectorToolkitPolledDeleteTag(tagId);
}

```

Unsolicited Tags Callbacks

For unsolicited tags we use different callback functions at various stages.

Step 1

At collector start up, `ihCollectorToolkitASyncInit` and `ihCollectorToolkitASyncInitCompleted` callbacks are triggered and the details of all the unsolicited tags for the given collector is returned.

Step 2

If an unsolicited tag is added, `ihCollectorToolkitASyncAddTag` method is called and the details of the tag is entered in the collector tag list.

Step 3

If an unsolicited tag is deleted, `ihCollectorToolkitASyncDeleteTag` method is called and the tag details are removed from the collector tag list.

Example

The following sample helps you understand the given callback functions. The below sample code creates a thread for simulating the Unsolicited tag's collector behavior.

```

//This structure is the list of Unsolicited Tags.
struct AsyncTagList : public CList<ihInterfaceTKASyncTagInfo*, ihInterfaceTKASyncTagInfo*>
{
    virtual ~AsyncTagList()
    {
        FreeAll();
    }
}

```

```

void AddTag(ihInterfaceTKASyncTagInfo* tag)
{
    ihInterfaceTKASyncTagInfo* info = new ihInterfaceTKASyncTagInfo;//need to allocate in delegator
    memcpy(info, tag, sizeof(ihInterfaceTKASyncTagInfo));
    AddTail(info);
}

void FreeAll()
{
    while (!IsEmpty())
        delete RemoveHead();
}

};

AsyncTagList g_AsyncTags;

-----

/// <summary>
/// Initializes unsolicited tags, by creating dedicated thread
/// <summary>
/// <returns></returns>
int RandomValueSimulator::ihCollectorToolkitASyncInit(void)
{
    CSingleLock lock(&g_Sync, TRUE);
    g_AsyncTags.FreeAll();
    if (!g_AsyncThread)
        g_AsyncThread = AfxBeginThread(TKASyncReadFunc, this);
    return TRUE;
}

-----

/// <summary>
/// unsolicited tags initialization completed
/// <summary>
/// <returns>TRUE/FALSE</returns>
int RandomValueSimulator::ihCollectorToolkitASyncInitCompleted(void)
{

```

```

    return TRUE;
}

-----

/// <summary>
/// Custom Collector Initialization completed and is ready to read data from Source for unsolicited tag
/// <summary>
/// <returns>TRUE/FALSE</returns>
int    RandomValueSimulator::ihCollectorToolkitASyncStartReading(void)
{
    InterlockedExchange(&g_DoAsyncRead, TRUE);

    return TRUE;
}

-----

/// <summary>
/// Adds unsolicited tag to the historian
/// <summary>
/// <param name="ASyncTag">ihInterfaceTKASyncTagInfo pointer</param>
/// <param name="IsCollectorStarting">Current Status of the Collector</param>
/// <returns>TRUE/FALSE</returns>
int    RandomValueSimulator::ihCollectorToolkitASyncAddTag(ihInterfaceTKASyncTagInfo *ASyncTag, int
    IsCollectorStarting)
{
    CSingleLock lock(&g_Sync, TRUE);

    g_AsyncTags.AddTag(ASyncTag);

    return TRUE;
}

-----

/// <summary>
/// From Clients tools/non-web admin/custom tools, if user deletes a tag, historian updates custom collector saying
    that tag got deleted.
/// So that, custom collector stops collecting data from source for that tag

```

```

/// <summary>
/// <param name="tagId">Tag Identifier</param>
/// <returns>TRUE/FALSE</returns>
int RandomValueSimulator::ihCollectorToolkitASyncDeleteTag(int tagId)
{
    CSingleLock lock(&g_Sync, TRUE);

    POSITION pos = g_AsyncTags.GetHeadPosition();

    while (pos)
    {
        ihInterfaceTKASyncTagInfo * tagInfo = g_AsyncTags.GetAt(pos);

        if (tagInfo->TagId == tagId)
        {
            g_AsyncTags.RemoveAt(pos);

            return TRUE;
        }

        g_AsyncTags.GetNext(pos);
    }

    return TRUE;
}

-----

/// <summary>
/// This method called by historian, if it needs to perform any calculations on source data. This method is only
usefull in "Calculation collector" way of collection for unsolicited tags
/// <summary>
/// <param name="StartTime"> start time for reload</param>
/// <param name="EndTime"> end time for reload</param>
/// <returns>TRUE/FALSE</returns>
int RandomValueSimulator::ihCollectorToolkitASyncReload(ihTKTimeStruct *StartTime, ihTKTimeStruct *EndTime)
{
    return CCollectorDelegator::ihCollectorToolkitASyncReload(StartTime, EndTime);
}

-----

/// <summary>

```

```

/// Unsolicited dedicated thread corresponding method. Here all unsolicited tags get data from source(usually, way
should be source notification to historian) and sends to historian

/// <summary>

/// <param name="param"> Collector instance </param>

UINT RandomValueSimulator::TKAsyncReadFunc(void* param)
{
    POSITION pos = NULL;

    RandomValueSimulator* pColl = (RandomValueSimulator*) param;

    while (TRUE)
    {
        if (g_DoAsyncRead)
        {
            CSingleLock lock(&g_Sync, TRUE);

            if (!g_AsyncTags.IsEmpty())
            {
                // gets each unsolicited tag into ihInterfaceTKAsyncTagInfo object

                if (!pos)
                    pos = g_AsyncTags.GetHeadPosition();

                ihInterfaceTKAsyncTagInfo* tag = g_AsyncTags.GetNext(pos);

                int numTags = 1;

                ihInterfaceTKDataInfo data;

                memset(&data, 0, sizeof(ihInterfaceTKDataInfo));

                data.Tag = pColl->TKStrdup(tag->Tag);

                data.DataProp.ValueDataType = tag->DataType;

                data.DataProp.TimeStamp = pColl->TKGetSystemTime();

                // gets data for selected tag

                pColl->ihCollectorToolkitGetData(0, 0, 0, numTags, NULL, &data);

                unsigned long collectionTime = (unsigned long)time(0);

                int tagId = tag->TagId;

                ihInterfaceTKASyncData asyncData;

                memset(&asyncData, 0, sizeof(ihInterfaceTKASyncData));

                asyncData.NumValues = numTags;

                asyncData.TagIds = &tagId;

                asyncData.Values = &data.DataProp;

                asyncData.CollectionTimes = &collectionTime;

                // sends to historian

                pColl->ihCollectorToolkitDataCallback(&asyncData);
            }
        }
    }
}

```


```
    }  
    else  
    {  
        pos = NULL;  
    }  
}  
else  
{  
    pos = NULL;  
}  
long sleepTimeInMs = 500 + (rand() % 46) * 100; // sleep from 0.5 to 5 seconds  
Sleep(sleepTimeInMs);  
}  
return 0;  
}
```

Chapter 14. Data Collectors - General

Data Collectors Overview

About Historian Data Collectors

A data collector gathers data from a data source on a schedule or event basis, processes it, and forwards it to the Historian server or a cloud destination for archiving. The following image shows the data flow in a typical Historian system from a data source to the archive.



The following table provides a list of collectors, their usage, and whether each of them is toolkit-based and consumes a client access license (CAL).

Collector Name	Description	Is Toolkit-Based?	Consumes a CAL?
The Calculation collector <i>(on page 2098)</i>	Performs data calculations on values stored in the archiver.	No	Yes
The CygNet collector <i>(on page 2167)</i>	Collects data from a CygNet server.	Yes	Yes
The File collector <i>(on page 2181)</i>	Imports CSV and XML files into Historian.	No	No
The HAB collector <i>(on page 2208)</i>	Collects data from Habitat.	Yes	
The iFIX Alarms and Events collector <i>(on page 2251)</i>	Collects alarms and events data from iFIX.	No	No
The iFIX collector <i>(on page 2251)</i>	Collects tag data from iFIX.	No	No
The MQTT collector <i>(on page 2298)</i>	Collects data published to a topic using an MQTT broker.	Yes	Yes
The MQTT Sparkplug B collector <i>(on page 2312)</i>	Enables you to connect as a Primary Host application and collect data based on the MQTT Sparkplug B specification (Sparkplug 3.0.0). Specifically, you can subscribe to a topic that was published using the Sparkplug B payload and collect time-series data in a structured and understandable format.	Yes	Yes

Collector Name	Description	Is Toolkit-Based?	Consumes a CAL?
The ODBC collector (on page 2341)	Collects data from an application based on an ODBC driver.	Yes	Yes
The OPC Classic Alarms and Events collector (on page 2390)	Collects data from an OPC Classic Alarms and Events server (such as CIMPLICITY).	No	No
The OPC Classic DA collector (on page 2356)	Collects data from an OPC Classic Data Access (DA) server (such as CIMPLICITY).		
The OPC Classic HDA collector (on page 2374)	Collects data from an OPC Classic Historical Data Access (HDA) server (such as CIMPLICITY).	Yes	Yes
The OPC UA Data Access (DA) collector (on page 2426)	Collects data from an OPC UA DA server (such as CIMPLICITY).	Yes	Yes
The OSI PI collector (on page 2443)	Collects data from an OSI PI server.	No	No
The Python collector (on page 2463)	Run Python scripts on tag values and stores them in Historian	No	No
The Server-to-Server collector (on page 2499)	Collects data from a Historian server and sends it to another Historian server.	No	Yes
The Server-to-Server distributor (on page 2554)	Collects data from a smaller Historian server and sends it to a larger, centralized Historian	No	Yes

Collector Name	Description	Is Toolkit-Based?	Consumes a CAL?
	server or a cloud destination.		
The Simulation collector (on page 2558)	Generates random numbers and string patterns for testing/demonstration purposes.	No	No
The Windows Performance collector (on page 2562)	Collects Windows performance counter data.	Yes	Yes
The Wonderware collector (on page 2566)	Collects data from a Wonderware Historian 2014 R2 server.	Yes	Yes

Data collectors use a specific data acquisition interface that match the data source type, such as iFIX Easy Data Access (EDA) or OPC 1.0 or 2.0 (Object Linking and Embedding for Process Control). For more information, see [Supported Acquisition Interfaces \(on page 1998\)](#). The Simulation collector generates random numeric and string data. The File collector reads data from text files.

Limitations: When failover occurs from a primary collector to a secondary collector (or vice versa), there will be some data loss as the collector tries to connect to the source to fetch the data.

Bi-Modal Cloud Data Collectors

Collectors can send data to an on-premises Historian server as well as cloud destinations such as Google Cloud, Azure IoT Hub, AWS Cloud, and Predix Cloud. Therefore, these collectors are called bi-modal collectors. The following collectors, however, are not bi-modal collectors; they can send data only to an on-premises Historian server:

- The File collector
- The HAB collector
- The iFIX Alarms and Events collector
- The Calculation collector
- The Server-to-Server distributor
- The OSI PI Distributor
- The OPC Classic Alarms and Events collector
- The Python collector

When you create a collector instance, you can choose whether you want the collector to send data to an on-premises Historian server or a cloud destination. You can create multiple instances of the same collector, and configure each of them to send data to a different destination.



Note:

Bi-modal Collectors support up to Transport Layer Security (TLS) 1.2.

The Predix cloud destination (via a secure web socket) supports APM, Automation, or Brilliant Manufacturing Cloud subscription. The Collector Toolkit is updated as well. Hence, a custom collector created using the toolkit has the same capabilities.

There are a few differences in the working of a bi-modal collector based on whether the destination is Historian or cloud. Following table explains the key differences.

Functionality	Destination - Historian	Destination - Cloud
HISTORIANN-ODENAME registry key	Contains the destination Historian Server's name/ IP Address.	Contains the cloud destination settings as well as proxy historian server name or IP if applicable (configServer). Cloud destination format: <code>CloudDestinationAddress configServer IdentityIssuer ClientID ClientSecret ZoneID Proxy proxyUser proxyPassword</code>
Mapping Source Tags with Destination Tags (Add Tags)	You must map tags in Historian Server to Data Source tags using one of the Admin tools (VB Admin/Web Admin). The data gets stored in IHA files and the Tag configurations are stored in IHC files.	As it is not possible to map tags in the Cloud with tags in the Data Source, user must select if mapping should be done through Historian (works as a proxy) or through Offline Configuration File at the time of installation. If the user selects Historian, then tags will be created in the Cloud which in turn may have been mapped through one of the Admin tools (VB Admin/Web Admin). If Offline Configuration File is selected, the user must provide an XML configuration file containing tag configurations that need to be cre-

Functionality	Destination - Historian	Destination - Cloud
		ated in the Cloud for mapping them with the Source tags.
Other Tag Management Operations such as Delete, Rename, Data cleaning	It is possible to do all tag management operations.	No tag management operations are allowed. After you update the offline tag configuration file, or after you specify the tags using Historian Administrator, the changes are reflected automatically (without the need to restart the collector).
Data Type support	All standard data types are supported.	All other data types, excepting arrays, enums and User defined types (UDT), BLOB, are supported.

Data Collector Software Components

Data Collector software consists of four main components:

- Data Collector Program

Executable data collection program for the type of collector. For example, `ihFileCollector.exe`.

- Local Tag Cache

Cache of configuration information that permits the collector to perform collection even when the archiver is not present at start-up (`*.cfg`).

- Local Outgoing Data Buffer

Buffer of the data sent to the server that the server has not yet confirmed receiving.

- Historian API

Interface that connects the collector to the Historian Server for configuration, data flow, and control functions.

Supported Windows versions for Data Collectors

The following table displays the supported Windows processor versions (32-bit or 64-bit) for the Historian data collectors.

Collector Name	32-bit	64-bit
The Calculation collector	Yes	Yes
The CygNet collector	No	Yes
The File collector	Yes	Yes
The HAB collector	No	Yes
The iFIX Alarms and Events collector collector	Yes	Yes
The iFIX collector	Yes	Yes
The OPC Classic Alarms and Events collector	Yes	Yes
The OPC DA collector	Yes	Yes
The OPC Classic HDA collector	No	Yes
The OPC UA Data Access (DA) collector	No	Yes
The OSI PI collector (API / SDK)	Yes	Yes
The OSI PI distributor	Yes	Yes
The Python collector	Yes	Yes
The Server-to-Server collector	Yes	Yes
The Server-to-Server distributor	Yes	Yes
The Simulation collector	Yes	Yes
The Windows Performance collector	Yes	Yes
The Wonderware Collector	No	Yes
The ODBC collector	No	Yes
The MQTT collector	No	Yes

Data Collector Functions

A Historian Data Collector performs the following functions:

- Connects to the data source using a specific data acquisition interface, such as EDA, OPC 1.0, or OPC2.0.
- Groups tags by collection interval for efficient polling.

- Reads data as frequently as 10 times/sec, depending on the configuration parameters of individual tags. An OPC Collector configured for unsolicited collection can read data as frequently as 1 millisecond (or 1000 times/second).
- Scales the collected value to the EGU Range.
- Compresses collected data based on a deadband specified on a tag by tag basis, and forwards only values that exceed the deadband to the Historian Server for final compression and archiving.
- Automatically stores data during a loss of connection to the server and forwards that data to the server after the connection is restored.

Common Collector Functions

Each collector performs some functions common to all types of collectors (except the File collector).

These functions are:

- Maintains a local cache of tag information to sustain collection while the server connection is down.
- Automatically discovers available tags from a data source and presents them to Historian Administrator.
- Buffers data during loss of connection to the server and forwards it to the server when the connection is restored.
- Automatically adjusts timestamps, if enabled, for synchronizing collector and archiver timestamps.
- Supports both collector and device timestamp, where applicable.
- Schedules data polling for polled collection.
- Performs first level of data compression (collector compression).
- Responds to control requests, such as pause/resume collection.

After collecting and processing information, a collector forwards the data to the Historian Server, which optionally performs final compression and stores the information in the Archive Database. The Archive Database consists of one or more files, each of which contains a specific time period of historical data. For more information on Historian Server architecture, refer to [System Architecture \(on page 69\)](#).

File collector Functions

The File collector imports files in either CSV (Comma Separated Variables) or XML (Extensible Markup Language) format. Since this is basically a file transfer operation, a File collector does not perform the typical collector functions of data polling, browsing for tags, pause/resume collection, data compression, or storing/forwarding of data on loss of server connection. A File collector, however, is an extremely useful tool for importing and configuring tags, for bulk updating of tag parameters and messages, and for importing data from all types of systems.

Supported Acquisition Interfaces

This section provides a list of specific Data Collectors and the associated Data Acquisition Interfaces (protocols or ways in which data is input).

Data Collector	Data Acquisition Interface
iFIX Data Collector	EDA data acquisition interface
Machine Edition View Data Collector	Point Management API Interface
OPC Data Collector	OPC data acquisition interface
OPC Classic Alarms and Events collector	The OPC Alarms and Events server
CygNet collector	SQL Server ODBC Driver Interface
File Data Collector	CSV or XML file import
Simulation Data Collector	Random pattern of data
Calculation collector	Calculations performed on data already in the server
Server-to-Server Collector	Data and messages collected from one Historian Server (source) to another Historian Server (destination)
OPC UA Data Access (DA) collector	OPC Data Acquisition interface for Microsoft Windows
Wonderware Data Collector	SQL Server ODBC Driver Interface
ODBC collector	SQL Server ODBC Driver Interface

Best Practices for Working with Data Collectors

Here are some best practices that enable the collectors collect and store the most accurate data:

- Synchronize the Windows clock for the following computers:
 - Source Data Archiver of a Server-to-Server Collector
 - Computer on which the Data Collector is running
 - Destination Data Archiver
- Turn on the Data Recovery Mode option for Historical Collectors such as Server-to-Server and Calculation collectors. This ensures that most gaps in data collection due to the unavailability of

source Archiver or in the case of collector not running are automatically filled in the next time the collector runs.

- If you are using polled collection with Calculation or Server-to-Server Collector, ensure that you have at least one uncompressed polled tag so that the polled data is frequently sent to the destination Archiver. This ensures that the bad data marker sent when a collector shuts down has an accurate time stamp that reflects the time of shutdown of the collector.

About Installing Historian Data Collectors

When you install collectors, the required binaries are downloaded. In addition, if iFIX/CIMPLICITY are installed on the same machine as the collectors, instances of the following collectors are created:

- The iFIX collector
- The iFIX Alarms & Events collector
- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

If an iFIX collector instance created in version 9.0 exists, after you upgrade collectors, another instance of the iFIX collector is created. Because of this, the Remote Collector Manager (RCM) will not work correctly. Therefore, if you want to use RCM, you must delete one of the instances. If needed, you can manually create another instance of the iFIX collector using Configuration Hub or the RemoteCollectorConfigurator utility. This is applicable to the iFIX Alarms and Events collector as well.



Note:

If you want to upgrade collectors earlier than version 7.1, additional registries that you create manually are deleted. Therefore, we recommend that you back them up, uninstall the collectors, and then install the latest version.

Install Collectors Using the Installer

After you install collectors, the following artefacts will be available:

- **Executable files:** These files are required to add a collector instance.
- **Instances of the following collectors:**
 - The iFIX collector
 - The iFIX Alarms & Events collector
 - The OPC Classic Data Access collector for CIMPLICITY
 - The OPC Classic Alarms and Events collector for CIMPLICITY

These instances will be created only if iFIX and/or CIMPLICITY are installed on the same machine as the collectors.

- **The Remote Collector Management agent:** Provides the ability to manage collectors remotely.

1. Run the `InstallLauncher.exe` file.

2. Select **Install Collectors**.


The welcome page appears.

3. Select **Next**.

The license agreement appears.


4. Select the **Accept** check box, and then select **Next**.

The default installation drive appears.




5. If needed, modify the installation drive, and then select **Next**.

The data directory page appears.



6. If needed, change the folder for storing the collector log files, and then select **Next**.
The destination Historian server page appears.



The image shows a dialog box titled "Historian Server Details" with a dark background and a grid pattern. The title is in white. Below the title is a white instruction: "Provide a valid windows user of the default Historian server to which the Remote Collector Manager will connect." There are four input fields, each with a label to its left: "Historian Server:", "User Name:", "Password:", and "Confirm Password:". The "Confirm Password:" field has a blue border. Below the fields is a yellow note: "Note: If you have created security groups or enabled strict client/collector authentication, provide the destination Historian credentials. If the password changes, you must reinstall Remote Management Agents to reset the password." At the bottom are three buttons: "Cancel" (grey), "Previous" (blue), and "Next" (blue).

7. Provide the credentials of the Windows user account of the destination Historian server to which you want Remote Management Agent to connect.

These details are required for Remote Collector Manager to connect to Historian to manage the collectors remotely. If you are installing collectors on same machine as the Historian server, and if strict collector authentication is disabled, you need not provide these details; by default, the machine name of the local Historian server is considered. If, however, they are installed on different machines, or if strict collector authentication is enabled, you must provide the credentials of the Historian server user.

8. Select **Next**.

The **You are ready to install** page appears.

9. Select **Install**.

The installation begins.

10. When you are prompted to reboot your system, select **Yes**.

The collector executable files are installed in the following folder: `<installation drive>:\Program Files (x86)\GE Digital\<collector name>`. The iFIX collectors are installed in the following folder: `C:\Program Files\GE\iFIX`. The following registry paths are created:

- `HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\ GE Digital\iHistorian\Services\<collector type>`
- `HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\iHistorian\Services\<collector type>`

In addition, if iFIX and/or CIMPLICITY are installed on the same machine as the collectors, instances of the following collectors are created:

- The iFIX collector
- The iFIX Alarms & Events collector
- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

Installing a Collector at a Command Prompt

After you install collectors and Remote Management Agent, the following artefacts will be available:

- **Executable files:** These files are required to add a collector instance.
- **Instances of the following collectors:**
 - The iFIX collector
 - The iFIX Alarms & Events collector
 - The OPC Classic Data Access collector for CIMPLICITY
 - The OPC Classic Alarms and Events collector for CIMPLICITY

These instances will be created only if iFIX and/or CIMPLICITY are installed on the same machine as the collectors.

- **The Remote Collector Management agent:** Provides the ability to manage collectors remotely.

Using Configuration Hub, you will then add a collector instance and begin using the collector.

This topic describes how to install collectors at a command prompt. You can also [install them using the installer \(on page 143\)](#).

1. Navigate to the `Collectors` folder in the installation folder.
2. At a command prompt, enter:

```
Collectors_Install.exe -s RootDrive=<value> DestinationServerName=<value>
DataPath="<value>" UserName1=<value> Password=<value>
```

Parameter	Description	Default Value
RootDrive	The installation drive for the collectors.	C:\
DataPath	The folder for storing the collector log files.	C:\Proficiency Historian Data
DestinationServerName	<p>The host name of the destination Historian server to which you want collectors to send data.</p> <p>This is required for Remote Collector Manager to connect to Historian to manage the collectors remotely. If you are installing collectors on the same machine as the Historian server, and if strict collector authentication is disabled, you need not provide the server name; by default, the machine name of the local Historian server is considered. If, however, they are installed on different machines, or if strict collector authentication is enabled, you must provide the credentials of the Historian server user.</p>	local host name
UserName1	The username of the Windows user of the destination Historian server. A value is required only if the destination Historian server and collectors are on different machines.	

Parameter	Description	Default Value
Password	The password of the Windows user of the destination Historian server. A value is required only if the destination Historian server and collectors are on different machines.	

For example: `Collectors_Install.exe -s RootDrive=C:\ DestinationServerName=myservername DataPath="C:\Proficy Historian Data" UserName=user123 Password=xyz123`

- Restart the machine. If you uninstall a collector or install another one before restarting the machine, an error may occur.

The collector executable files are installed. In addition, if iFIX and/or CIMPLICITY are installed on the same machine as the collectors, instances of the following collectors are created:

- The iFIX collector
- The iFIX Alarms & Events collector
- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

1. Ensure that the Windows user that you have specified while installing collectors is added to the iH Security Admins and iH Collector Admins groups.
2. [Enable trust for a client certificate for Configuration Hub.](#)
3. [Enable trust for a self-signed certificate on Chrome \(on page 97\).](#)
4. [Import an issuer certificate.](#)

You are now ready to use Configuration Hub. To add and manage collector instances, you can use Configuration Hub or Remote Collector Management. For instructions specific to setting up the iFIX collector and the iFIX Alarms and Events collector, refer to [Working with iFIX Collectors](#).

Upgrade Collectors

- Ensure that you are attempting to upgrade the collectors that were installed using the Historian Installation Package. If you previously installed the collectors using the Proficy Installer, such as the iFIX Proficy Installer, you must upgrade the collectors using the Proficy Installer only.
- If an iFIX collector instance created in version 9.0 exists, after you upgrade collectors, another instance of the iFIX collector is created. Because of this, the Remote Collector Manager (RCM)

will not work correctly. Therefore, if you want to use RCM, you must delete one of the instances. If needed, you can manually create another instance of the iFIX collector using Configuration Hub or the RemoteCollectorConfigurator utility. This is applicable to the iFIX Alarms and Events collector as well.

- For collectors earlier than version 7.1, additional registries that you create manually are deleted. Therefore, we recommend that you back up them, uninstall the collectors, and then install the latest version.

[Install the collectors \(on page 142\)](#).

The collectors are upgraded to the latest version.

Sending Data to Cloud

Send Data to Alibaba Cloud

Generate a password using [the utility](#). While generating the password, use the same algorithm that you will use to connect to Alibaba Cloud.

To send data to Alibaba Cloud, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector
- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

1. Access Alibaba IoT Platform console.
2. [Create a product](#). When you do so:
 - In the **Node Type** field, select **Directly Connected Device**.
 - In the **Network Connection Method** field, select **Wi-Fi**.
 - In the **Data Type** field, select **ICA Standard Data Format**.

* Product Name

* Node Type



Directly Connected Device



Gateway sub-device



Gateway device

Networking and Data Format

* Network Connection Method

* Data Type ?

[✓ Checksum Type](#)
[✓ Authentication Mode](#)

More

[✓ Product Description](#)

3. Note down the region ID for the region you have selected. For a list of region IDs, refer to <https://www.alibabacloud.com/help/doc-detail/40654.htm>.
4. Access the product certificate, and note down the product secret and product key values.
5. [Create a device](#).
6. [Access Configuration Hub \(on page 336\)](#).
7. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the system appears.
8. If needed, select the system in which you want to add a collector instance.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE
Filter	Filter	Filter	Filter
.Distributor	Unknown	Historian	
.Simulation	Running	Historian	
.To_WIN10TECH	Unknown	Historian	

9. In the upper-right corner of the main section, select **+**.

COLLECTOR NAME	STATUS
Filter	Filter
Calculation	Running
Simulation	Running

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

10. In the **COLLECTOR TYPE** field, select a collector type, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

11. Select **Next**.

The **Source Configuration** section appears, populating the hostname of the collector machine.

12. As needed, enter values in the available fields, and then select **Next**.

The **Destination Configuration** section appears.

Add Collector Instance:

- Collector Selection: Simulation Collector
- Source Configuration: WIN10TECH
- Destination Configuration: MQTT**
- Collector Initiation

CHOOSE DESTINATION*

Historian Server
 Predix Timeseries
 Azure IoT Hub
 MQTT

HOST ADDRESS* **PORT***
 Enter Address Enter Port

CLIENT ID* **TOPIC***
 Enter Client ID Enter Topic

AUTHENTICATION

AUTO REFRESH ⓘ

USER CREDENTIAL

USERNAME* **PASSWORD**
 Enter Username Enter Password

SSL/TLS

13. In the **CHOOSE DESTINATION** field, select **MQTT**, and then provide values as described in the following table.

Field	Description
HOST ADDRESS	Enter a value in the following format: <code><product name>.iot-as-mqtt.<region ID>.aliyuncs.com</code> . A value is required. For example: <code>a23dr53dwr.t-iot-as-mqtt.cn-shanghai.aliyuncs.com</code>
PORT	Enter 1883. A value is required.
CLIENT ID	Enter a value in the following format: <code><device name> securemode=<value>,signmethod=<algorithm name></code> . A value is required. <ul style="list-style-type: none"> ◦ For securemode, enter 2 for direct TLS connection, or enter 3 for direct TCP connection. ◦ For signmethod, specify the signature algorithm that you want to use. Valid values are hmacmd5, hmacsha1, hmacsha256, and sha256. You must use the same algorithm to generate the password. For example: <code>MyDevice securemode=3,signmethod=hmacsha1</code>

Field	Description
TOPIC	<p>Enter a value in the following format: <code>/sys/<product name>/<device name>/thing/event/property/post</code>. A value is required.</p> <p>For example: <code>/sys/a23dr53dwrt/MyDevice/thing/event/property/post</code></p>
USERNAME	<p>Enter a value in the following format: <code><device name><product name></code>. A value is required.</p> <p>For example: <code>MyDevicea23dr53dwrt</code></p>
PASSWORD	<p>Enter the password that you have generated. A value is required.</p>
CHOOSE CONFIGURATION	<p>Select the type of the configuration to specify the tags whose data you want to collect. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Historian Configuration: Select this option if you want to add the tags manually using Historian Administrator (on page 659). If you select this option, the CONFIGURATION HISTORIAN SERVER field appears. ◦ Offline Configuration: Select this option if you want to provide the tag names using the offline configuration (on page 2039) file instead of adding tags manually. By default, this file is located in the following location: <code><installation folder of Historian>\GE Digital\<collector name></code>

14. Select **Next**.

The **Collector Initiation** section appears.

15. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

16. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

17. Select **Add**.

The collector instance is created.

18. Specify the tags for which you want to collect data.

- If you have selected **Historian Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags manually \(on page 357\)](#).
- If you have selected **Offline Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags using the offline configuration file \(on page 2039\)](#).

The collector begins sending Historian data to the device that you have created.

Send Data to AWS IoT Core

To send data to an AWS IoT Code, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector
- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

1. Access the **AWS Management Console** page.


2. Search and select **IoT Core**.

The **AWS IoT** page appears.

3. [Create a policy](#) allowing the permissions that you want to grant on your device (for example, iot:Connect, iot:Publish, iot:Subscribe, iot:Receive). For the resource, provide the topic name. If, however, you want to use all topics, enter *****.

4. [Create a thing](#), linking it with the policy that you have created.


5. Download the certificates and key files for the device to communicate. In addition, download the root CA certificate.



Important:

This is mandatory, and it is the only time you can download the certificates.

6. In the left navigation pane, select **Settings**.
7. Make a note of the endpoint that appears.




8. [Access Configuration Hub \(on page 336\)](#).
9. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the system appears.

10. If needed, select the system in which you want to add a collector instance.



11. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

12. In the **COLLECTOR TYPE** field, select a collector type (except the File collector and the Server-to-Server collector), and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

13. Select **Next**.

The **Source Configuration** section appears, populating the hostname of the collector machine.

14. As needed, enter values in the available fields, and then select **Next**.

The **Destination Configuration** section appears.

15. In the **CHOOSE DESTINATION** field, select **MQTT**, and then provide values as described in the following table.

Field	Description
HOST ADDRESS	Enter the endpoint that you have noted down. A value is required.
PORT	Enter 8883. A value is required.
CLIENT ID	Enter the thing name. A value is required.
TOPIC	Enter the MQTT topic to which you want the collector to publish data. A value is required. For information on topic names, refer to https://docs.aws.amazon.com/iot/latest/developer-guide/topics.html .
USERNAME	Enter any value. Since we will use a certificate-based authentication, username and password will not be used; however, you must still enter a value.

Field	Description
PASSWORD	Enter any value. Since we will use a certificate-based authentication, username and password will not be used; however, you must still enter a value.
CA SERVER ROOT FILE	Enter the path of the root CA certificate file that you have downloaded.
CLIENT CERTIFICATE	Enter the path of the device certificate that you have downloaded.
PRIVATE KEY FILE	Enter the path of the private key file that you have downloaded.
PUBLIC KEY FILE	Enter the path of the public key file that you have downloaded.
CHOOSE CONFIGURATION	<p>Select the type of the configuration to specify the tags whose data you want to collect. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Historian Configuration: Select this option if you want to add the tags manually using Historian Administrator (on page 659). If you select this option, the CONFIGURATION HISTORIAN SERVER field appears. ◦ Offline Configuration: Select this option if you want to provide the tag names using the offline configuration (on page 2039) file instead of adding tags manually. By default, this file is located in the following location: <code><installation folder of Historian>\GE Digital\<collector name></code>

16. Select **Next**.

The **Collector Initiation** section appears.

17. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

18. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

19. Select **Add**.

The collector instance is created.


20. Specify the tags for which you want to collect data.

- If you have selected **Historian Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags manually \(on page 357\)](#).
- If you have selected **Offline Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags using the offline configuration file \(on page 2039\)](#).

The collector begins sending Historian data to the thing that you have created.

21. Access AWS IoT Core, and in the left pane, select **Test**.

The **MQTT test client** page appears.



22. Subscribe to the topic to which the collector is publishing data, and then select **Subscribe**.

The messages received from the topic appear, indicating that the collector is sending data to the AWS IoT device.

AWS supports a payload of maximum 128 KB. Therefore, if the message size is greater than 128 KB, create a registry key named CloudMaxSamplesPerMsg for the collector instance, and decrease the value to 700 or less. If, however, you want to send more data in a message, we recommend that you create another collector instance and send data to another thing resource in AWS.

**Tip:**

To find out the message size, [modify the collector instance \(on page 634\)](#) and set the log level to 3 or more.

23. Create a [VPC destination](#) or an [HTTP destination](#) for the messages.
24. [Monitor the data that you have collected.](#)

Send Data to Azure Cloud in the Key-Value Format

To send data to an Azure IoT Hub device, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector
- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

This topic describes how to send data in the key-value format. In this format, the message size is bigger because names of the tag properties are repeated. However, it provides clarity to novice users. For example: `{"body":`

```
[{"tagname": "Azure_Iot_simulation_tag_1", "epochtime": 1629730936000, "tagvalue": 7129.124023438, "quality": 3}, {"tagname": "Azure_Iot_simulation_tag_2", "epochtime": 1629730936000, "tagvalue": 123.3738924567, "quality": 3}] , "message"
```

You can also [send data in the KairosDB format \(on page 608\)](#).

**Note:**

Data in Azure IoT Hub is stored for maximum seven days, after which it is deleted from the hub. Therefore, you must consume the data within seven days. Based on your requirement, you can store it in a relevant Azure storage. You can then use Azure functions or streaming analytics to analyse the data.


1. Create Azure IoT Hub.



Tip:

To choose the correct Azure IoT Hub tier based on your data throughput, refer to <https://docs.microsoft.com/en-us/azure/iot-hub/iot-hub-devguide-quotas-throttling>. For guidance on choosing the appropriate subscription, refer to <https://azure.microsoft.com/en-us/pricing/details/iot-hub/>

2. After you create Azure IoT Hub, select **Go to resource**, and then note down the hostname:




3. Create devices in Azure IoT Hub to group related tag information; thus mapping a collector instance to a device. We recommend that you create one device per collector instance. Ensure that the device is running.

When you create a device, use the following guidelines to choose the authentication type:

- **Symmetric Key:** Select this option if you want to use a Shared Access Signature (SAS) authentication.
- **X.509 Self-Signed:** Select this option if you want to create self-signed certificates using OpenSSL. We recommend that you use these certificates only for testing purposes. For instructions, refer to <https://docs.microsoft.com/en-us/azure/iot-hub/tutorial-x509-self-sign>.
- **X.509 CA Signed:** Select this option if you want to use CA-signed certificates


4. If you have selected **Symmetric Key** in the previous step, select the link in the **Device ID** column, and note down the shared access key value.



5. [Access Configuration Hub \(on page 336\)](#).
6. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
7. If needed, select the system in which you want to add a collector instance.
8. If needed, select the system in which you want to add a collector instance.



9. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

10. In the **COLLECTOR TYPE** field, select a collector type, and then select **Get Details**.
The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.
11. Select **Next**.
The **Source Configuration** section appears.
12. As needed, enter values in the available fields.
13. Select **Next**.

The **Destination Configuration** section appears.

The screenshot shows a configuration window titled "Add Collector Instance:". On the left, a vertical navigation pane lists four steps: "Collector Selection Simulation Collector" (checked), "Source Configuration WIN10TECH" (checked), "Destination Configuration MQTT" (selected), and "Collector Initiation". The main area is titled "CHOOSE DESTINATION*" and contains four radio buttons: "Historian Server", "Predix Timeseries", "Azure IoT Hub", and "MQTT" (which is selected). Below this are input fields for "HOST ADDRESS*" (with placeholder "Enter Address"), "PORT*" (with placeholder "Enter Port"), "CLIENT ID*" (with placeholder "Enter Client ID"), and "TOPIC*" (with placeholder "Enter Topic"). A section titled "AUTHENTICATION" contains a toggle switch for "AUTO REFRESH" (which is turned on) and a help icon. Below that are fields for "USER CREDENTIAL" with "USERNAME*" (placeholder "Enter Username") and "PASSWORD" (placeholder "Enter Password"). At the bottom, there is an "SSL/TLS" section. At the very bottom of the window are three buttons: "Previous", "Cancel", and "Next".

14. Select **MQTT**, and provide values as described in the following table.

Field	Description
HOST ADDRESS	Enter the host name of the resource that you have noted down in step 2. A value is required and must be in the following format: <code><Azure IoT Hub name>.azure-devices.net</code>
PORT	Enter 8883.
CLIENT ID	Enter the ID of the device that you created in step 3. A value is required and must be unique for an MQTT broker.
TOPIC	Enter <code>devices/<device ID>/messages/events</code> .
AUTO REFRESH	Indicates whether you want to automatically create/refresh the SAS authentication token when it expires.

Field	Description
	<ul style="list-style-type: none"> ◦ If you switch the toggle off, you must manually provide the token as soon as it expires. ◦ If you switch the toggle on, you must provide the shared access key that you have noted down in step 4. And, you can leave the PASSWORD field blank. <p>This is applicable only if you have selected Symmetric Key in step 3.</p>
USERNAME	<p>Enter a value in the following format: <code><host name or IP address>/<device ID>/?api-version=2018-06-30</code></p>
PASSWORD	<p>Enter the SAS token. This is applicable only if you have selected Symmetric Key in step 3 and if you have switched off the AUTO REFRESH toggle.</p> <p>For instructions on generating a SAS token, refer to https://docs.microsoft.com/en-us/azure/cognitive-services/translator/document-translation/create-sas-tokens?tabs=Containers.</p>
DEVICE SHARED KEY	<p>Enter the shared access key value that you noted down in step 4. A value is required. This is applicable only if you have selected Symmetric Key in step 3 and if you have switched the AUTO REFRESH toggle on.</p>
CA SERVER ROOT FILE	<p>Enter the path of the CA server root file that you want to use. You can find the file here: https://github.com/Azure-Samples/loTMQTTSample/blob/master/loTHubRootCA_Baltimore.pem.</p>
CLIENT CERTIFICATE	<p>Enter the path to the client certificate. A value is required. This is applicable only if you have selected one of these options in step 3:</p>

Field	Description
	<ul style="list-style-type: none"> ◦ X.509 Self-Signed: If you have selected this option, you can generate the certificate using OpenSSL. ◦ X.509 CA Signed: If you have selected this option, you would receive the certificate from CA.
PRIVATE KEY FILE	<p>Enter the complete path to the private key file. A value is required. This is applicable only if you have selected one of these options in step 3:</p> <ul style="list-style-type: none"> ◦ X.509 Self-Signed: If you have selected this option, you can generate the key file using OpenSSL. ◦ X.509 CA Signed: If you have selected this option, you would receive the key file from CA.
PUBLIC KEY FILE	<p>Enter the path to the public key file. This is applicable only if you have selected one of these options in step 3:</p> <ul style="list-style-type: none"> ◦ X.509 Self-Signed: If you have selected this option, you can generate the key file using OpenSSL. ◦ X.509 CA Signed: If you have selected this option, you would receive the key file from CA.
CHOOSE CONFIGURATION	<p>The type of the configuration to specify the tags whose data you want to collect. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Historian Configuration: Select this option if you want to add the tags manually (on page 357). If you select this option, the CONFIGURATION HISTORIAN SERVER field appears. ◦ Offline Configuration: Select this option if you want to provide the tag names using the offline configuration (on page

Field	Description
	2039) file instead of adding tags manually. By default, this file is located in the following location: <i><installation folder of Historian>\GE Digital\<collector name></i>
CONFIGURATION HISTORIAN SERVER	The host name of the machine from which you want to access Historian Administrator to add the tags manually for the collector. This field appears only if you have selected Historian Configuration in the CHOOSE CONFIGURATION field.

15. Select **Next**.

The **Collector Initiation** section appears.

The screenshot shows the 'Add Collector Instance' wizard. On the left, a vertical list of steps is shown: 'Collector Selection' (Simulation Collector), 'Source Configuration', 'Destination Configuration' (Historian Server), and 'Collector Initiation' (Simulation). The 'Collector Initiation' step is highlighted with a blue circle. The main area contains the following fields and options:

- COLLECTOR NAME:** A text box containing 'Simulation'.
- RUNNING MODE*:** Two radio button options: 'Service - Local System Account' (selected) and 'Service Under Specific User Account'.
- Note:** 'Once an instance of the collector is created, you can run the collector either in Windows service mode or in Command line mode.'
- USERNAME:** A text box with the placeholder 'Enter Username'.
- PASSWORD:** A text box with the placeholder 'Enter Password'.

At the bottom of the wizard, there are three buttons: 'Previous' (disabled), 'Cancel' (disabled), and 'Add' (active).

16. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.

- Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
17. In the **RUNNING MODE** field, select one of the following options.
- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
 - **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

18. Select **Add**.

The collector instance is created.

19. Specify the tags for which you want to collect data.

- If you have selected **Historian Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags manually \(on page 357\)](#).
- If you have selected **Offline Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags using the offline configuration file \(on page 2039\)](#).

The collector begins sending Historian data to the Azure IoT Hub device that you have created.

Send Data to Google Cloud

1. Download the Google root CA certificate from <https://pki.google.com/roots.pem>.
2. [Create public/private key pairs](#). Use OpenSSL only for testing purposes.

To send data to a Google Cloud device, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector

- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

1. Access Google Cloud Platform.
2. [Create a project](#). Note down the project ID.
3. [Create a registry](#).

When you create the registry:

- Use the MQTT protocol.
- You can choose to provide a CA certificate.

Note down the registry ID and the region values.

4. [Add a device to the registry](#).

When you add the device:


- Allow device communication.
- Upload the public key or enter the details manually.

Note down the device ID.

5. [Access Configuration Hub \(on page 336\)](#).
6. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
7. If needed, select the system in which you want to add a collector instance.
8. If needed, select the system in which you want to add a collector instance.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE
<i>Filter</i>	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>
.Distributor	Unknown	Historian	
.Simulation	Running	Historian	
.To_WIN10TECH	Unknown	Historian	

9. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

10. In the **COLLECTOR TYPE** field, select a collector type, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

11. Select **Next**.

The **Source Configuration** section appears.

12. As needed, enter values in the available fields.

13. Select **Next**.

The **Destination Configuration** section appears.

The screenshot shows the 'Add Collector Instance' configuration interface. On the left, a vertical navigation pane shows four steps: 'Collector Selection' (checked), 'Source Configuration' (checked), 'Destination Configuration' (active), and 'Collector Initiation'. The main area is titled 'CHOOSE DESTINATION*' and contains four radio buttons: 'Historian Server', 'Predix Timeseries', 'Azure IoT Hub', and 'MQTT' (selected). Below this are input fields for 'HOST ADDRESS*' (with placeholder 'Enter Address'), 'PORT*' (with placeholder 'Enter Port'), 'CLIENT ID*' (with placeholder 'Enter Client ID'), and 'TOPIC*' (with placeholder 'Enter Topic'). An 'AUTHENTICATION' section contains an 'AUTO REFRESH' toggle switch (currently off) and an information icon. Below that are 'USER CREDENTIAL' fields for 'USERNAME*' (with placeholder 'Enter Username') and 'PASSWORD' (with placeholder 'Enter Password'). At the bottom, there is an 'SSL/TLS' section. Navigation buttons 'Previous', 'Cancel', and 'Next' are located at the bottom of the window.

14. Select **MQTT**, and provide values as described in the following table.

Field	Description
HOST ADDRESS	Enter <code>mqtt.googleapis.com</code> . A value is required.
PORT	Enter 8883 or 443.
CLIENT ID	Enter the ID of the device that you created in the following format: <code>projects/<project ID>/locations/<cloud region>/registries/<registry ID>/devices/<device ID></code> . For example: <code>projects/mygcpproject/locations/asia-east1/registries/testmqttgcpiot/devices/gcptesting</code> A value is required and must be unique for an MQTT broker.
TOPIC	Enter <code>devices/<device ID>/events</code> .
AUTO REFRESH	Indicates whether you want to automatically refresh the authentication token when it expires. If you switch the toggle off, you must manually

Field	Description
	provide the token as soon as it expires. Google Cloud accepts only those tokens that expire in 24 hours or less; therefore, we recommend that you switch the toggle on.
USERNAME	Enter any value. This value is not used, but only if you enter a value, you can proceed.
PASSWORD	If you have switched the AUTO REFRESH toggle on, leave this field blank. Historian generates a JSON Web Token (JWT) and uses it automatically.
CA SERVER ROOT FILE	Enter the path of the Google root CA certificate that you have downloaded.
CLIENT CERTIFICATE	Enter the path to the client certificate.
PRIVATE KEY FILE	Enter the complete path to the private key file. A value is required.
PUBLIC KEY FILE	Enter the path to the public key file. A value is required.
CHOOSE CONFIGURATION	<p>The type of the configuration to specify the tags whose data you want to collect. Select one of the following options:</p> <ul style="list-style-type: none"> ◦ Historian Configuration: Select this option if you want to add the tags manually (on page 357). If you select this option, the CONFIGURATION HISTORIAN SERVER field appears. ◦ Offline Configuration: Select this option if you want to provide the tag names using the offline configuration (on page 2039) file instead of adding tags manually. By default, this file is located in the following location: <i><installation folder of Historian>\GE Digital\<collector name></i>

Field	Description
CONFIGURATION HISTORIAN SERVER	The host name of the machine from which you want to access Historian Administrator to add the tags manually for the collector. This field appears only if you have selected Historian Configuration in the CHOOSE CONFIGURATION field.

15. Select **Next**.

The **Collector Initiation** section appears.

16. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

17. In the **RUNNING MODE** field, select one of the following options.


- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

18. Select **Add**.

The collector instance is created.

19. Access Google Cloud Platform, and select **Pub/Sub > Topics**.



20. Select **Messages > PULL**.

Messages published to the topic that you have created appear. These messages contain the data sent by the collector instance. You can verify that the message content is correct by selecting **Message body**.

Send Data to Predix Cloud

To send data to Predix Cloud, you can choose any of the following collectors:

- The iFIX collector
- The MQTT collector
- The ODBC collector
- The OPC Classic DA collector
- The OPC Classic HDA collector

- The OPC UA DA collector
- The OSI PI collector
- The Python Collector
- The Server-to-Server collector
- The Simulation collector
- The Windows Performance collector
- The Wonderware collector

1. [Register with the Timeseries service or any UAA service that you want to use](#). Note down the destination address, URI, client ID, client secret, and the zone ID that you have provided.
2. [Access Configuration Hub \(on page 336\)](#).
3. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the system appears.
4. If needed, select the system in which you want to add a collector instance.

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE
.Distributor	Unknown	Historian	
.Simulation	Running	Historian	
.To_WIN10TECH	Unknown	Historian	

5. In the upper-right corner of the main section, select .

COLLECTOR NAME	STATUS
Calculation	Running
Simulation	Running

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

- In the **COLLECTOR TYPE** field, select a collector type (except the File collector and the Server-to-Server collector), and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

- Select **Next**.

The **Source Configuration** section appears, populating the hostname of the collector machine.

- As needed, enter values in the available fields, and then select **Next**.

The **Destination Configuration** section appears.

The screenshot shows the 'Add Collector Instance' window with the following configuration options:

- CHOOSE DESTINATION*:** Radio buttons for Historian Server, Predix Timeseries, Azure IoT Hub, and MQTT (selected).
- HOST ADDRESS*:** Text input field with placeholder 'Enter Address'.
- PORT*:** Text input field with placeholder 'Enter Port'.
- CLIENT ID*:** Text input field with placeholder 'Enter Client ID'.
- TOPIC*:** Text input field with placeholder 'Enter Topic'.
- AUTHENTICATION:** Section header.
- AUTO REFRESH:** Toggle switch (disabled) with an information icon.
- USER CREDENTIAL:** Section header.
- USERNAME*:** Text input field with placeholder 'Enter Username'.
- PASSWORD:** Text input field with placeholder 'Enter Password'.
- SSL/TLS:** Section header.

Navigation buttons at the bottom: Previous, Cancel, Next.

- In the **CHOOSE DESTINATION** field, select **Predix Timeseries**, and then provide values as described in the following table.

Field	Description
CLOUD DESTINATION ADDRESS	The URL of a data streaming endpoint exposed by the Predix Time Series instance to which you want to send data. Typically, it starts with "wss://". This value is used as part of the interface name and default tag prefix of the collector. Your Predix Time Series administrator can provide this URL.

Field	Description
IDENTITY ISSUER	The URL of an authentication endpoint for the collector to authenticate itself and acquire necessary credentials to stream to the Predix Time Series. In other words, this is the issuer ID of the Proficy Authentication instance that you want to use to connect to Predix Time Series. Typically, it starts with https:// and ends with "/oauth/token".
CLIENT ID	Identifies the collector when interacting with Predix Time Series. This is equivalent to the username in many authentication schemes. The client must exist in the Proficy Authentication instance identified by the identity issuer, and the system requires that the <code>timeseries.zones. {ZoneId}. ingest</code> and <code>timeseries.zones. {ZoneId}. query</code> authorities are granted access to the client for the Predix Zone ID specified. Your Predix Time Series administrator can provide this information.
CLIENT SECRET	The secret to authenticate the collector. This is equivalent to the password in many authentication schemes.
ZONE ID	Unique identifier of the instance to which the collector will send data.
PROXY	Identifies the URL of the proxy server to be used for both the authentication process and for sending data. If the collector is running on a network where proxy servers are used to access web resources outside of the network, then you must provide the proxy server settings. However, it does not affect the proxy server used by Windows when establishing secure connections. As a result, you must still configure the proxy settings for the Windows user account under which the collector service runs.
PROXY USERNAME	The username to connect to the proxy server.
PROXY PASSWORD	The password to connect to the proxy server.
DATAPPOINT ATTRIBUTES	The attributes or parameters related to a datapoint that you want the collector to collect. Select Add Attributes to specify the attributes. You can add maximum five attributes for each collector instance.

11. Enter a collector name.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

If you choose the first option, you can also configure the collector to start automatically when you start the computer, or, in the case of iFIX collectors, whenever you start iFIX.

13. Select **Add**.

The collector instance is created.

14. Specify the tags for which you want to collect data.

- If you have selected **Historian Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags manually \(on page 357\)](#).
- If you have selected **Offline Configuration** in the **CHOOSE CONFIGURATION** field, [specify the tags using the offline configuration file \(on page 2039\)](#).

The collector begins sending Historian data to Predix Timeseries.

Protocols and Port Numbers

The following table provides a list of protocols that are available to send data to Azure IoT Hub, guidelines on which protocol to choose, and the port number that each protocol uses.

Protocol	When to Use	Port Number
HTTP	Use this protocol if the data that you want to send is not large and/or the default ports for the other protocols are not available.	80
MQTT	MQTT is lightweight compared to AMQP, and is widely used. Use this protocol if you want to send data using low bandwidth and/or you do not want to connect to multiple devices using the same connection.	8883
AMQP	AMQP is more reliable compared to other protocols. It sends data in batches, and hence, the network traffic is less compared to that of MQTT. Use this protocol if you want to send a large amount of data from multiple collectors frequently.	5671
MQTT over web sockets	MQTT is lightweight compared to AMQP, and is widely used. In addition, communication using web sockets is more reliable and secure. Use this protocol if you want to send data using low bandwidth and securely.	443
AMQP over web sockets	AMQP is more reliable compared to other protocols. It sends data in batches, and hence, the network traffic is less compared to that of MQTT. In addition, communication using web sockets is more reliable and secure. Use this protocol if you want to send a large amount of data from multiple collectors frequently and securely.	443

Offline Collector Configuration

Offline Configuration for Collectors

Offline Configuration helps you to define the configuration properties of a collector (Taglist, Tag properties, and collector interface properties) in XML format. This feature is particularly useful when collectors connect to a cloud destination.

When collectors connect to both Historian server and cloud, you can add tags, set tag configuration properties, and collector interface properties.

The path to the Offline Tag Configuration file is provided in the collector registry as:

OfflineTagConfigurationFile (Data Type: String). This key contains the path to offline configuration file. For Server to Server Collector the default value is: C:\Program Files (x86)\GE Digital\Historian Server to Server Collector\Config\S2S_Offline_Config.xml.

The following tag properties are required for Cloud collector tags:

Mandatory properties for non-historical collector (PI to Cloud, OPCUA to Cloud etc)

Tagname, Data Type and Source Address

Mandatory properties for historical collector (Server to Cloud)

Tagname, Data Type, Source Address and CalculationDependency

All other properties are not mandatory.

Creating Offline Configuration XML file

It is recommended that you add the Collector property section above the Tag property section in your offline configuration XML file.

1. Add the following collector interface properties to the top of your configuration XML file.

The following is an example for the Server to Server Collector interface properties:

```
<Import>

<Collectors>

<Collector Name="<Collector Name>">

<InterfaceType>ServerToServer</InterfaceType>

<InterfaceGeneral1>10</InterfaceGeneral1>

.....

</Collector>

</Collectors>
```

2. Add your TagList and Tag properties to your XML file.

```
<Collectors>

...

</Collectors>
```

```

<TagList Version="1.0.71">

<Tag>

<Tagname>simCollector1</Tagname>

<SourceAddress>Result = CurrentValue("SJC1GEIP05.Simulation00002")</SourceAddress>

...

</Tag>

<Tag>

<Tagname>simCollector2</Tagname>

<SourceAddress>Result = CurrentValue("SJC1GEIP05.Simulation00002")</SourceAddress>

...

</Tag>

...

</TagList>

</Import>

```

3. Add the closing `</Import>` tag to the end of your XML file.

Collector Interface Properties

The collector interface properties are written in the following format in the XML file.

```

<Import>

<Collectors>

<Collector Name="<Collector Name>">

<InterfaceType>ServerToServer</InterfaceType>

<InterfaceGeneral1>10</InterfaceGeneral1>

.....

</Collector>

</Collectors>

</Import>

```

where `<Collector Name>` is the collector name found in the `ServerToServerCollector.shw` file.

You can configure the following properties:

Property Name	Possible Values	Example
InterfaceType	ServerToServer, PI, Custom	<InterfaceType>ServerToServer</InterfaceType>
DefaultTagPrefix	Any tag prefix name	<DefaultTagPrefix>OfflineCloud</DefaultTagPrefix>
CanBrowseSource	Yes, No	<CanBrowseSource>Yes</CanBrowseSource>
CanSourceTimestamp	Yes, No	<CanSourceTimestamp>Yes</CanSourceTimestamp>
MinimumDiskFreeBufferSize	Size in MB	<MinimumDiskFreeBufferSize>150</MinimumDiskFreeBufferSize>
MaximumMemoryBufferSize	Size in MB	<MaximumMemoryBufferSize>200</MaximumMemoryBufferSize>
ShouldAdjustTime	Yes, No	<ShouldAdjustTime>Yes</ShouldAdjustTime>
ShouldQueueWrites	Yes, No	<ShouldQueueWrites>No</ShouldQueueWrites>
SourceTimeInLocalTime	Yes, No	<SourceTimeInLocalTime>No</SourceTimeInLocalTime>
CollectionDelay	Time in seconds	<CollectionDelay>2</CollectionDelay>
DefaultCollectionInterval	Time in milliseconds	<DefaultCollectionInterval>1000</DefaultCollectionInterval>
DefaultCollectionType	Polled, Unsolicited	<DefaultCollectionType>Unsolicited</DefaultCollectionType>
DefaultTimeStampType	Source, Collector	<DefaultTimeStampType>Source</DefaultTimeStampType>
DefaultLoadBalancing	Yes, No	<DefaultLoadBalancing>No</DefaultLoadBalancing>
DefaultCollectorCompression	Yes, No	<DefaultCollectorCompression>No</DefaultCollectorCompression>
DefaultCollectorCompressionDeadband	Double type value	<DefaultCollectorCompressionDeadband>0.00000</DefaultCollectorCompressionDeadband>
DisableOnTheFlyTagChange	Yes, No	<DisableOnTheFlyTagChange>No</DisableOnTheFlyTagChange>
DefaultCollectorCompressionTimeout	Time in milliseconds	<DefaultCollectorCompressionTimeout>0</DefaultCollectorCompressionTimeout>

Property Name	Possible Values	Example
DefaultSpikeLogic	Yes, No	<DefaultSpikeLogic>Yes</DefaultSpikeLogic>
DefaultSpikeMultiplier	Any numeric value	<DefaultSpikeMultiplier>4</DefaultSpikeMultiplier>
DefaultSpikeInterval	Any numeric value	<DefaultSpikeInterval>5</DefaultSpikeInterval>
DataRecoveryQueueEnabled	Yes, No	<DataRecoveryQueueEnabled>No</DataRecoveryQueueEnabled>
DefaultAbsoluteDeadbanding	Yes, No	<DefaultAbsoluteDeadbanding></DefaultAbsoluteDeadbanding>
DefaultAbsoluteDeadband	Double type value	<DefaultAbsoluteDeadband>0.00000</DefaultAbsoluteDeadband>
RedundancyEnabled	Yes, No	<RedundancyEnabled>No</RedundancyEnabled>
RedundancyPrincipalCollector		<RedundancyPrincipalCollector></RedundancyPrincipalCollector>
RedundancyIsActiveCollector	Yes, No	<RedundancyIsActiveCollector>No</RedundancyIsActiveCollector>
InterfaceGeneral1	Customized for each collector	<InterfaceGeneral1>10</InterfaceGeneral1>
InterfaceGeneral2	Customized for each collector	<InterfaceGeneral2>4</InterfaceGeneral2>
InterfaceGeneral3	Customized for each collector	<InterfaceGeneral3>3.188.87.41</InterfaceGeneral3>
InterfaceGeneral4	Customized for each collector	<InterfaceGeneral4></InterfaceGeneral4>
InterfaceGeneral5	Customized for each collector	<InterfaceGeneral5></InterfaceGeneral5>

Tag List and Tag Properties

The format of Source Address for the Server to Cloud Collector is typically of format: Result = CurrentValue("SJC1GEIP05.Simulation00002"). For other collectors the format of the source address should be the value expected by the source server, for example, OPC and PI Collector tags typically use the Tag source item id for the SourceAddress.

Server to Cloud Tag Example:

```
<Tag>
  <Tagname>simCollector2</Tagname>
  <SourceAddress>Result = CurrentValue("SJC1GEIP05.Simulation00002")</SourceAddress>
  ...
</Tag>
```

OPC Collector Tag Example:

```
<Tag>
  <Tagname>simCollector2</Tagname>
  <SourceAddress>Channel1.Device1.Tag1</SourceAddress>
  ...
</Tag>
```

You can configure the following properties:

Property Name	Possible Values	Example
Tagname	Any name	<Tagname>sim-Tag1</Tagname>
Description	Description of tag	<Description>sim-Tag1</Description>
EngineeringUnits	Unit of value	<EngineeringUnits>Centigrade</EngineeringUnits>
Comment	Comment of tag	<Comment>sim-Tag1</Comment>
DataType	SingleFloat, SingleInteger, DoubleFloat, FixedString, VariableString, Scaled, Byte, Boolean, DoubleInteger, UnsignedSingleInteger, UnsignedDoubleInteger, QuadInteger, UnsignedQuadInteger, Blob, Time, Array, MultiField	<DataType>SingleFloat</DataType>
FixedStringLength		<FixedStringLength></FixedStringLength>
InterfaceName		<InterfaceName></InterfaceName>

Property Name	Possible Values	Example
SourceAddress	Tag source address	<code><SourceAddress>Result = CurrentValue("SJC1GEIP05.Simulation00002")</SourceAddress></code>
CollectionType	Polled, Unsolicited	<code><CollectionType>Unsolicited</CollectionType></code>
CollectionInterval	Interval of collection. Unit depends on TimeResolution.	<code><CollectionInterval>2</CollectionInterval></code>
CollectionOffset	Time in seconds	<code><CollectionOffset>0</CollectionOffset></code>
LoadBalancing	Yes, No	<code><LoadBalancing>No</LoadBalancing></code>
TimeStampType	Source, Collector	<code><TimeStampType>Source</TimeStampType></code>
HiEngineeringUnits	Any numeric value	<code><HiEngineeringUnits>200000.00</HiEngineeringUnits></code>
LoEngineeringUnits	Any numeric value	<code><LoEngineeringUnits>0</LoEngineeringUnits></code>
InputScaling	Yes, No	<code><InputScaling>Yes</InputScaling></code>

Property Name	Possible Values	Example
HiScale	Any numeric value	<HiScale>32767.00</HiScale>
LoScale	Any numeric value	<LoScale>0</LoScale>
SpikeLogic	Yes, No	<SpikeLogic>Yes</SpikeLogic>
SpikeLogicOverride	Yes, No	<SpikeLogicOverride>Yes</SpikeLogicOverride>
InterfaceCompression	Yes, No	<InterfaceCompression>Yes</InterfaceCompression>
InterfaceDeadbandPercentRange	Any double type value	<InterfaceDeadbandPercentRange>0</InterfaceDeadbandPercentRange>
InterfaceCompressionTimeout	Time in milliseconds	<InterfaceCompressionTimeout>0</InterfaceCompressionTimeout>
InterfaceAbsoluteDeadband	Any double type value	<InterfaceAbsoluteDeadband>0</InterfaceAbsoluteDeadband>
InterfaceAbsoluteDeadbanding	Yes, No	<InterfaceAbsoluteDeadbanding>No</InterfaceAbsoluteDeadbanding>
ConditionCollectionEnabled	Yes, No	<ConditionCollectionEnabled>No</ConditionCollectionEnabled>

Property Name	Possible Values	Example
ConditionCollectionTriggerTag	Name of tag	<code><ConditionCollectionTriggerTag>simTag1</ConditionCollectionTriggerTag></code>
ConditionCollectionComparison	= , EQ , < , LT , <= , LE , > , GT , >= , GE , != , NE	<code><ConditionCollectionComparison>EQ</ConditionCollectionComparison></code>
ConditionCollectionCompareValue	Any numeric value	<code><ConditionCollectionCompareValue>0</ConditionCollectionCompareValue></code>
ConditionCollectionMarkers	Yes, No	<code><ConditionCollectionMarkers>No</ConditionCollectionMarkers></code>
NumberOfElements		<code><NumberOfElements></NumberOfElements></code>
UserDefinedTypeName		<code><UserDefinedTypeName></UserDefinedTypeName></code>
CalcType	Raw, Analytic, PythonExpr	<code><CalcType>Raw</CalcType></code>
TimeResolution	Seconds, Milliseconds, Microseconds	<code><TimeResolution>Seconds</TimeResolution></code>
InterfaceGeneral1	Customized for each collector	<code><InterfaceGeneral1>10</InterfaceGeneral1></code>

Property Name	Possible Values	Example
InterfaceGeneral2	Customized for each collector	<code><InterfaceGeneral2>4</InterfaceGeneral2></code>
InterfaceGeneral3	Customized for each collector	<code><InterfaceGeneral3>3.188.87.41</InterfaceGeneral3></code>
InterfaceGeneral4	Customized for each collector	<code><InterfaceGeneral4></InterfaceGeneral4></code>
InterfaceGeneral5	Customized for each collector	<code><InterfaceGeneral5></InterfaceGeneral5></code>

About Updating Tag Properties Dynamically

When you add or delete tags for a collector, or when you modify the properties of the tags or the collector using the offline configuration file, the changes are reflected without the need to restart the collector.

The following conditions apply for the changes to reflect automatically:

- This is applicable only to bi-modal collectors.
- The changes are reflected in 90 seconds.



Note:

If you do not want tag properties to be updated dynamically for a collector, perform the following steps:

1. Access the offline configuration file for the collector. By default, this file is available in the following location: `<installation folder of Historian>\GE Digital \<collector name>`. For example, for the simulation collector, the path to the file is `C:\Program Files (x86)\GE Digital\Historian Simulation Collector \Config\Sim_Offline_Config.xml`.



2. Inside the `<collector>` element, for the `<DisableOnTheFlyTagChanges>` parameter, enter Yes, and save the file. By default, the value is No.

**Tip:**

To verify that the changes are saved, verify the .shw file for the collector.

Troubleshooting

By default, the offline configuration file is continuously monitored for any changes in the tag names and/or properties, and the changes are reflected dynamically. If, however, the changes are not reflected, you can create the following registry key to fix the issue: `OfflineTagForceCheckDuration`

Cloud Collector Specific Registry Configuration

Various registry keys are available for modifying the default behavior of cloud collector. These keys can be added to the specific cloud collectors for altering the default behavior.

For a Server-to-Server collector, the keys will be added to: `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\GE Digital\iHistorian\Services\ServerToServerCollector`

ZIP compression: Zip compression is available for Cloud collectors so that the JSON Payload can be compressed with a reduced network bandwidth.

Following registry key is available for compression:

`JsonPayloadGzipCompression:` Use this registry key to reduce the network usage while the data is transferred from collector to cloud.

Default value: 0, means no compression (if registry key does not exist)

Valid values: 1 to 9. 1 is minimal compression and 9 is maximum compression.

Data Type: DWORD

Registry key for Controlling Max send queue size

`CloudMaxOutstandingMsgs:` Use this registry key to configure the maximum send queue size.

Default value: 512

Valid values: 24 to 512

Data Type: DWORD

Registry key to save messages in failed queues

`FailedMsgQueueEnabled`: Use this registry key to save messages in failed queues as backup. This is done when any message fails for any unexpected reason.

Default: 0 (Disabled). (if no registry key)

Valid Values: 0 (Disabled) or 1(Enabled)

Data Type: Binary

Working with Tags

Understanding Tag names

Historian tag names vary according to the type of collector. By default, the tag name is the source address prepended with a string.

It is recommended that tag names use only characters available for folders and file names to avoid the problems (limitations) with some clients and filtering. You can use tag names that contain the characters & and + in the Non-Web Historian Administrator.

iFIXCollector Tagnames

The format of Historian tag names for an iFIX collector generally is

```
Node.Tag.Field
```

where

- `Node`, by default, is the name of the SCADA node, the data source. This field is configurable, however.
- `Tag` is the database tag.
- `Field` is the database field.

Examples of typical tag names:

```
NODE8.WATER-_SWITCH.F_CV  
NODE2.MASH_LEVEL.B_CUALM  
USGBS1.FIC101.F_CV  
USGBS1.FT102.A_LAALM
```

where

- `NODE8`, `NODE2`, and `USGBS1` are the names of the iFIX SCADA nodes.
- `WATER_SWITCH`, `MASH_LEVEL`, `FIC101`, and `FT102` are the names of the database tags.
- `4F_CV` means single floating point, current value.
- `B_CUALM` means current alarm status.
- `A_LAALM` means analog input, latched alarm.

OPC or Simulation Collector Tagnames

The format of Historian tags for an OPC or Simulation collector is:

```
ComputerName.ItemID
```

where

- `ComputerName`, by default, is the name of the machine on which the collector is installed. This field is configurable, however.
- `ItemID` is the data point being polled.

Calculation collector Tagnames

There is no specified format for Historian tags for a Calculation collector. We recommend that you select a consistent naming convention so the tags are easily and clearly identifiable. You should avoid using spaces and other special characters or reserved words used in SQL or VBScript. This applies to any tag being used as a source tag in the formula.

Server-to-Server Collector Tagnames

There is no specified format for Historian tags for a Server-to-Server Collector. We recommend that you select a consistent naming convention so the tags are easily and clearly identifiable. Server-to-Server Collectors allow you to specify a prefix to add to the Server-to-Server Collector tags.



Note:

In cases where you want the destination tag's data to be a duplicate of the source tag, then the tag name would be identical. This is especially important so that all messages and alerts are included.

Adding Tags from a Collector

Add Multiple Tags from a Collector Using Historian Administrator

This topic describes how to add multiple tags from a collector using Historian Administrator. You can also [add tags using the Web Admin console \(on page 2055\)](#).



Note:

When you add a tag, do not enter a leading space or a trailing space in the tag name.

1. Select the **Add Tags From Collector** link in the **Tag Maintenance** page.
The **Add Multiple Tags from Collector** window appears.

Add Multiple Tags From Collector

Browse Criteria

Collector: [Select A Collector] Show Only: All Source Tags

Source Tag Name: * Description: *

Select one or more tags to add to Historian.

Reset Browse

Browse Results (0)

Tagname	Description
---------	-------------

Select All Unselect All

Tag Property - Data Store

User

Add Selected Tags Help Cancel

2. Select a collector from the **Collector** drop-down list.

**Note:**

If you add tags from a File collector, the file you import specifies the collector to which the tags are assigned. Those tags are then returned by a browse of the specified collector. It is also possible to leave the assignment blank. If the file does not specify a Collector Name for a tag, the tag is added with no collector name.

You cannot browse a Calculation collector through the **Add Tags From Collector** window in Historian Administrator.


3. In the **Show Only** field, select either **All Source Tags** or **Source Tags Not Collected**.

If you select the second option, the browse returns only the tags that are not currently included for collection.

If a Historian tag name is different from its source address tag name, the source tag is displayed in the returned list even if you browse the collector using the **Show Source Tags Not Collected** criterion. Collection on the same source address using a unique tag name is allowed.

4. In the **Source Tag name** and **Description** fields, you can optionally enter masks for the browse, using standard Windows wildcard characters.
5. Select **Browse** to initiate the search or **Reset** to start over.

The browse returns a list of tags, as shown in the following figure. In the Historian Non-Web Administrator, a tag that is currently collected appears in black type. A tag that is not currently collected appears in blue type.




Adding Uncollected Tags from a Collector

1. Select the required tags. Selecting a tag selects its tag name and description.

you can select:

- a single tag by selecting on the name of the tag.
- multiple tags by pressing the **Ctrl** key and selecting the tags.
- a contiguous group by selecting the first tag, pressing the **Shift** key, and selecting the last tag of the group.
- all tags by selecting **Select All** at the bottom of the page.

To clear all tags, select **Unselect All**.



2. Select **Add Selected Tags**. The selected tags are added to the Historian Tag Database. The **Tag Maintenance** page appears. The lower left portion of the page displays a list of all tag names added to the Historian Tag Database.

Add Tags from a Collector Using the Web Admin Console

This topic describes how to add tags from a collector using the Web Admin console. You can also [add tags using Historian Administrator \(on page 2052\)](#).



Note:

When you add a tag, do not enter a leading space or a trailing space in the tag name.

1. Select the  plus sign in the **Tag** page.
2. Select **Add Tags from Collector**.
The **Add Tags from Collector** window appears.
3. Select the collector from the **Collector name** list.
For collectors with hierarchical browsing, expand the folder to select the desired tags. The > symbol indicates that you need to navigate further within the folder.

4. Enter the **Source Tag Name** or select **Browse**.
The list of available tags is displayed.
5. Select tags.
You can select a single tag and or select multiple tags. To select a series of tags, press and hold the **Shift** key and select the series.
6. Select **Add** to add the tags. To add all the tags, select **Add All**.
7. Select **Preview** to preview the selected tag details.
8. Select **Add Selected Tags** to add the selected tags from the collectors.

Adding Tags for Collectors with Hierarchical Browsing

1. Select the  plus sign in the **Tag** page.
2. Select **Add Tags from Collector**.
The **Add Tags from Collector** window appears.
3. Select the collector from the **Collector name** list.
4. Enter the **Source Tag Name** or select **Browse**.
The list of available tags is displayed.
5. Select tags.
You can select a single tag and or select multiple tags. To select a series of tags, press and hold the **Shift** key and select the series.
6. Select **Add** to add the tags. To add all the tags, select **Add All**.
7. Select **Preview** to preview the selected tag details.
8. Select **Add Selected Tags** to add the selected tags from the collectors.

Manually Adding Tags

Typically, you add new tags to the Historian by browsing the data source or by bulk importing a group of tags with the Excel Add-In tool. Occasionally, you may need to add a single tag manually. You can add tags manually:

- for creating a calculation tag.
- for holding values that are added using the Excel Add-In or custom SDK application.
- for testing purposes.

For example, if you are currently not connected to a collector, the browse is slow, or is not supported, and if you want to configure tags associated with that collector, you can add them manually.

When adding a tag manually, you must manually configure the fields for the tag that the **Add Tag Manually** window does not include. For instance, when you add a tag manually, the **Data Type** field does not automatically populate after you select a **Source Address**. You must manually set the data type from the **Collection** section after you add the tag. Use caution when selecting the data type. If you select the wrong data type, you most likely will get incorrect data or you could even lose data. It does not use the collector default settings, such as those for archive and collector compression, as it would with the browse and pick.

Add a Tag Using Historian Administrator

1. [Add an instance of the collector \(on page 357\)](#) that you want to use to collect the tag data.
2. [Create a data store \(on page 852\)](#) in which you want to store the tag data.

1. Access Historian Administrator.
2. Select **Tags > Add Tag Manually**.

The **Add Tag Manually** window appears.

The screenshot shows the "Add Tag Manually" dialog box. The fields are as follows:

- Collector Name: [Dropdown menu]
- Source Address: [Text box with browse button]
- Tag Name: [Text box]
- Data Store: [Dropdown menu showing "User"]
- Data Type: [Dropdown menu showing "Single Float" and an adjacent empty text box]
- User Def Type Name: [Text box with browse button]
- Is Array Tag
- Time Resolution: [Dropdown menu showing "Seconds"]

Buttons at the bottom: OK, Help, Cancel.

3. Enter values in the available fields as described in the following table.

Field	Description
Collector Name	Select the collector that you want to use to collect data of the tag.
Source Address	Enter the
Tag Name	Enter a name for the tag.
Data Store	Select the type of the data store in which you want to store the tag data.
Data Type	Select the data type of the tag. If you select MultiField , the User Def Type Name field is enabled.
User Def Type Name	For a tag of the multi-field data type, select the data type of the tag that you have defined.
Is Array Tag	Select this check box if the tag stores an array of data.
Time Resolution	
Time Adjustment	<div style="border: 1px solid #ccc; border-radius: 10px; background-color: #fff9c4; padding: 10px;"> <p>! Important:</p> <p>If you manually add a Server-to-Server tag, ensure that you set the Time Adjustment field for the tag to the Adjust for Source Time Difference option, after you add the tag. The Time Adjustment field is located in the Advanced section in the Tag Maintenance page. This field only applies to Server-to-Server tags that use a polled collection type.</p> </div>

4. Select **OK**.

The tag is added.

Add a Tag Using the Web Admin Console

The dynamic collector update feature ensures that any modifications done to the tag configuration do not affect all the tags in a collector. Only the tags that stop data collection will record zero data and bad quality without restarting the collector. In other words, the tags that do not stop data collection do not record bad data samples to the collection.

Whenever you add tags, delete tags, or modify certain tag properties, the following collectors reload only the modified tag(s) without restarting the collectors:

- OPC Collector
- iFIX collector
- Calculation collector
- Simulation Collector
- Server to Server Collector
- PI Collector
- PI Distributor

For a tag to stop and restart the collection without restarting the collector, you must enable the **On-line Tag Configuration Changes** option in the **Advanced** section of the **Collector Maintenance** page. By default, the **On-line Tag Configuration Changes** option is enabled.

If you disable the **On-line Tag Configuration Changes** option, any changes you make to the tags do not affect collection until after you restart the collector. To restart the collector, you must stop and start the collector service or executable. Restarting the collector stops and restarts the tag(s) collection and records bad data samples to the collection.

All the collector configuration changes done within a 30 second time frame are batched up to let you update/modify a small set of tags at a time to collect the modified data faster.

**Note:**

It is recommended that you disable the **On-line Tag Configuration Changes** option while updating large sets of tags at the same time, and restart the collector after modification.

Follow these steps to add a new tag manually from the Web Administrator:

1. Select the  link in the Tag Details page and select **Add Tags Manually**.
The **Add Tag** window appears.
2. Select a collector from the drop-down list in the **Collector Name** field.

This associates the new tag with a specific collector.

3. Enter the **Source Address** and **Tag Name** in the appropriate fields.
4. Select the data store in the **Data Store** field.
5. Select a **Data Type** from the drop-down list.
6. For fixed string data types only, enter a value in the field adjacent to the **Data Type** field.
7. Select Seconds, Milliseconds, or Microseconds in the **Time Resolution** field.
8. Select the **Is Array Tag** option, if the tag is an Array Tag.
9. Select **Add** to add the tag.



Important:

If you manually add a Server-to-Server tag, ensure that on the **Tag Maintenance** page **Advanced** tab, you set the **Time Adjustment** field to **Adjust for Source Time Difference** , after you add the tag. Note that, this field only applies to Server-to-Server tags that use a polled collection type.

Add a Source Address Using the Web Admin Console

1. Select a collector from the drop-down list in the **Collector Name** field.
This associates the new tag with a specific collector.
2. Enter the **Source Address** or select the **Browse** button.
The **Add Tags from Collectors** window appears.
3. Select the tag you want to associate to source address. You can select only one tag.
4. Select **OK**.
The source address of the tag will be added.

Copy a Tag

If you want to create a copy of an existing tag with all the same properties, use the **Copy Tag** function.

Copy Tag works only for individual tags. You cannot copy multiple tags at once.

1. To copy a tag using Historian Administrator:
 - a. Select a tag to copy from the tag list.
 - b. Select the **Copy Tag** link in the **Tag Maintenance** page.
The **Copy Tag** window appears.
 - c. Type a new tag name.
 - d. Select **OK** to copy the tag and all the associated tag properties.

2. To copy a tag using the Web Admin console:
 - a. Select the **Copy Tag** icon in the **Tag** page.
The **Copy Tag** window appears.
 - b. Type a new tag name.
 - c. Select **OK** to copy the tag and all the associated tag properties.

Search for Tags

1. To search for tags using Historian Administrator:
 - a. In the **Tag Maintenance** page, select the **Search Historian Tag Database** link.
The Search **Historian Tag Database** window appears.



The screenshot shows a dialog box titled "Search Historian Tag Database". It contains the following fields and controls:

- Tag Mask**: A text input field.
- Description**: A text input field.
- Data Store**: A dropdown menu.
- Collector**: A dropdown menu.
- Max. Tag Count**: A text input field containing the value "5000".
- Buttons: **OK**, **Help**, and **Cancel**.

- b. Enter a tag search mask in the **Tag Mask** field, using * and ? wildcard characters.
You can search for a description instead of a tag by entering a mask in the **Description** field.

If you leave both fields blank, the search returns all tags.
 - c. Select the name of the collector in the **Collector** field.
 - d. Enter the maximum number of tags the search should return.
If you leave this field blank, your search will return all the tags available in the Historian Tag Database.
 - e. Select **OK**.
The **Tag Maintenance** page appears.



Note:

Prior to performing any maintenance, it is recommended to adhere to the accepted practice of performing a backup of your Historian archive. It is also recommended that you use the Excel Add-In to export your tag configuration for all tags. It is recommended that you export tags associated with each collector on a separate worksheet.

- f. If you want to change the default tag properties, select the name of the tag.
- g. Enter the properties of the tag in the appropriate fields.
- h. Select **Update** to save your entries.



CAUTION:

Multi-select and property change will affect all selected tags. Changing the collector type for the Calculation and Server-to-Server tags will result in a loss of the calculation formula.

2. To search for tags using the Web Admin console:

- a. Select **Advanced Search** in the **Tags** page.
The **Advanced Search** window appears.
- b. In the **Step 1** section, select the tag criteria from the list.
- c. Enter or select the **Tag Criteria Value**.
If you leave the fields blank, the search returns all the available tags.
- d. Select **Add Criteria** and choose **Collector Name** as criteria.
- e. Select the collector from the list.
- f. Select **Find Tags**.
All the tags that satisfy the query criteria are displayed in the **Step 2** section.
- g. Select the tags and select **Apply** to return the list of tags to the parent **Tags** page.
- h. If you want to change the default tag properties, select the name of the tag from the list and edit the properties in the **Tag Editor** section.

- i. Select **Update** to save your entries.

**CAUTION:**

Multi-select and property change will affect all selected tags. Changing the collector type for the Calculation and Server-to-Server tags will result in a loss of the calculation formula.

Remove Tags

Deleting a tag only removes it from the browse list; the data remains intact in the Archive and can be queried by tag name. It is recommended that you export your tag configuration before and after tag modifications.

1. To remove a tag using Historian Administrator:

- a. On Historian Administrator **Main** page, select the **Tags** link on the toolbar.

The **Tag Maintenance** page appears.

- b. Select the name of the tag you want to remove.

To remove multiple tags:

- Select a tag to highlight it.
- Select multiple tags by pressing the **Control** key and selecting the individual tags.
- Select contiguous tags by pressing the **Shift** key and selecting the first and last tags of the sequence.

- c. Select the **Delete** button.

The **Delete Tag** window appears.

- d. Select either **Remove Tag from System** or **Stop Data Collection** and select **OK**.

If you want to stop collection temporarily and resume collection later for a specified time, you can disable collection for that tag instead. To do this, select the tag on the **Tag Maintenance** page, select **Collection**, and then select the **Disable** option for the **Collection** field.

2. To remove a tag using the Web Admin console:

- a. On Historian Administrator **Main** page, select the **Tags** link on the toolbar.

The **Tag Maintenance** page appears.

- b. Select the name of the tag you want to remove.

To remove multiple tags:

- Select a tag to highlight it.
- Select multiple tags by pressing the **Control** key and selecting the individual tags.
- Select contiguous tags by pressing the **Shift** key and selecting the first and last tags of the sequence.

c. Select the **Delete** button.

The **Delete Tag** window appears.

d. Select either **Remove Tag from System** or **Stop Data Collection** and select **OK**.

Browse a Data Source for New Tags

To browse for new tags, your collector must be running. If it is not running, start the collector.

The most common way to add tags to an Historian Database is to browse the data source for new tags.



Note:

Performing large tag browses in Historian Administrator may cause your session to time out. Use the browse filter criteria to return a smaller list. In the Non-Web Administrator, if your OPC server supports hierarchical organization of your tags, see [Adding Tags for Collectors with Hierarchical Browsing \(on page 2056\)](#) to speed browse sessions.

1. To browse for new tags using Historian Administrator:

a. Open the Historian Non-Web Administrator.

b. Select the **Collectors** link from the toolbar.

The **Collector Maintenance** page appears.

c. If you have multiple collectors listed, select a collector from the **Collectors** list.

d. To browse for new tags from your data source, select **Add Tags** at the bottom of the page.

The **Add Multiple Tags From Collector** window appears.

Add Multiple Tags From Collector

Browse Criteria

Collector: [Select A Collector] Show Only: All Source Tags

Source Tag Name: "*" Description: "*"

Select one or more tags to add to Historian.

Reset Browse

Browse Results (0)

Tagname	Description

Select All Unselect All

Tag Property - Data Store

User

Add Selected Tags Help Cancel

- e. In the **Show Only** field, select either **All Source Tags** or **Source Tags Not Collected**. If you select the second option, the browse returns only the tags that are not currently included for collection.


If a Historian tagname is different from its source address tagname, the source tag is displayed in the returned list even if you browse the collector using the **Show Source Tags Not Collected** criterion. Collection on the same source address using a unique tagname is allowed.

A check mark beside a tag indicates that the tag is currently being collected. Absence of a mark indicates that the tag is not currently being collected.

- f. In the **Source Tagname** and **Description** fields, you can optionally enter masks for the browse, using standard Windows wildcard characters.

- g. Select **Browse** to initiate the search or **Reset** to start over.

The browse returns a list of tags, as shown in the following figure. In the Historian Non-Web Administrator, a tag that is currently collected appears in black type. A tag that is not currently collected appears in blue type.



See also [Add Multiple Tags from a Collector Using Historian Administrator \(on page 2052\)](#).

2. To browse for new tags using the Web Admin console:

- a. Open the Historian Web Administrator.
- b. Select the **Collectors** link from the toolbar.
The **Collector** page appears.
- c. If you have multiple collectors listed, select a collector from the **Collectors** list.
- d. To browse for new tags from your data source, go to the **Tags** page from the **Configuration** page.
- e. Select **Add Tags** at the bottom of the page and select **Add Tag from Collector**.
The **Add Tags from Collector** window appears.
- f. Select single or multiple tags, select on **Add Selected Tags** button.
See also [Add Tags from a Collector Using the Web Admin Console \(on page 2055\)](#).

About Configuring Collector Options

If you are using Historian Administrator, configure collector options as follows:

- Start at the **Collector Maintenance** page in Historian Administrator. You can access the Collector Maintenance page in several ways:
 - Select the Collectors link in any of the major pages in Historian Administrator.
 - Select the collector name in the Collectors section of Historian Administrator Main page. This displays the page with the specific collector already selected.

The Collector Maintenance page lists all connected collectors at the left of the page. The right-side displays parameter values, in several tabs, for the collector you select by selecting on a name in the list.

- To make a change in a configurable parameter, enter the value in the appropriate field and select **Update**. For more information, refer to *Historian Administrator*.

If you are using the Web Admin console,

- Go to the **Collectors** page. This displays the list of available collectors and their status. You can edit the collector configurable parameters.
- From the **Collector Maintenance page** or the **Collector page**, select the various tabs to display parameters of various types for the specific collector you have selected.

For more information, refer to *Historian Web Administrator Help*.

About Collector Redundancy

Historian includes support for collector redundancy, which decreases the likelihood of lost data due to software or hardware failures. Implementing collector redundancy ensures that collection of your data remains uninterrupted. Collector redundancy makes use of two or more collectors, gathering data from a single source. For more information, refer to the [About Collector Redundancy \(on page 975\)](#).



Note:

Use Polled tags only as watchdog tags.

Collect Vendor Attributes

Data sources are often customized to include information specific to a site's installation in the form of vendor attributes. This customization adds data not covered by the OPC or OPCAE specifications and may or may not require storage in the Historian Archive. As a result, Historian Administrator provides a means to specify which vendor attributes will be collected from any given data source. A maximum of 10 vendor attributes can be collected.

1. To collect vendor attributes using Historian Administrator:

a. In the Historian Administrator **Main** page, select the **Collectors** link in the toolbar.
The **Collector Maintenance** page appears.

b. Select **Configuration**.

c. To collect all vendor attributes from the data source, select **All**.

d. To collect up to 10 selected vendor attributes from the data source:

i. Select the **Selected** option.

ii. Select **Add** to add a vendor attribute to collect from the data source.

The **Vendor Attributes** window appears.

e. In the **Vendor Attribute** field, enter the vendor attribute you wish to collect from the data source and select **OK**.

The vendor attribute appears in the list box on the **Collector Configuration** page.

f. To remove a vendor attribute, select it in the list box and select **Remove**.

g. Select **Update** to apply your changes.

2. To collect vendor attributes using the Web Admin console:

a. In the Historian Dashboard, select the **Details** button in the Collectors section.
The **Collect Statistics** window appears.

b. Select the **Configure** button.

The **Collector Configuration** page appears.

c. To collect all vendor attributes from the data source, select **All**.

d. To collect up to 10 selected vendor attributes from the data source:

i. Select the **Selected** option.

ii. Select **Add** to add a vendor attribute to collect from the data source.

The **Vendor Attributes** window appears.

e. In the **Vendor Attribute** field, enter the vendor attribute you wish to collect from the data source and select **OK**.

The vendor attribute appears in the list box on the **Collector Configuration** page.

- f. To remove a vendor attribute, select it in the list box and select **Remove**.
- g. Select **Update** to apply your changes.

Collector Spare Configuration

Spare configuration enables you to add additional configuration to the tag using the **Spare 1** to **Spare 5** fields in all the collectors except in a Server-to-Server collector, Server-to-Server distributor, and an OSI PI distributor.

- In case of an OSI PI distributor, data is read from the Historian tag displayed in the **Source Address** field and sent to the OSI PI tag name displayed in the **Spare 1** field. To control the source and destination tags, change the **Source Address** and **Spare 1** values. You can add or update values in the remaining spare fields.
- In case of Server-to-Server collector and Server-to-Server distributor, you can update the **Spare 1** to **Spare 4** values, but the **Spare 5** field is used only for internal purposes. Therefore, do not update the **Spare 5** field.

Data Collector Operation and Troubleshooting

Data Collector File Locations

Historian data collector files are installed in the following default directories:

- **Executables**

- OPC, Simulator, File, Calculation, and Server-to-Collectors

```
c:\Program Files\Proficy\Historian\Server
```

- iFIXCollector

```
C:\Program Files (x86)\GE\iFIX
```

- **LOG files and SHOW files**

```
C:\Historian Data\LogFiles (*.log, *.shw)
```

- **Buffer files and local tag cache**

```
C:\Historian Data\BufferFiles (*.msq, *.cfg)
```

Pause or Resume Data Collection for All Tags

1. To pause or resume data collection using Historian Administrator:
 - a. Open Historian Administrator.
 - b. Select the **Collectors** link.
The **Collector Maintenance** page appears.
 - c. From the list of collectors at the left of the page, select the collector you want to pause or resume.
 - d. Select the appropriate running status from the **Collection Status** section in the **General** section.
No data buffering occurs while collection is paused.
 - e. Select **Update** to activate your change.
2. To pause or resume data collection using the Web Admin console:
 - a. Go to the **Collectors Configuration** page.
 - b. From the list of collectors at the left of the page, select the collector you want to pause or resume.
 - c. Select **Pause** or **Resume**.
No data buffering occurs while collection is paused.
3. To pause or resume data collection by accessing the local collector machine:
 - a. On the **Start** menu, select **Run**.
 - b. Type `services.msc` and select **OK**.
The **Services** window appears.
 - c. Select the **Historian (collector type) Collector** and select **Start** or **Stop**.
 - d. Select **Close**.
4. To pause data collection from the Collector icon:

- a. Select the Windows **Start** button, select Historian 6.0 from the **Programs** menu, and select the appropriate icon for your collector.

The process should start and an application icon display should appear in minimized form on the lower toolbar.

- b. To stop the collector, maximize the icon from the toolbar, type **q**, and press **Enter**.

Pause Data Collection for a Subset of Tags

1. To pause data collection for a subset of tags using Historian Administrator:

- a. From Historian Administrator **Main** page, select the **Tags** link.

The **Tag Maintenance** page appears.

- b. Select one or more tags in the **Tags** section.

The right-hand column displays current parameters.

- c. Locate the **Collection** field in the **Collection** section.

- d. Select the **Disabled** option.

- e. Select **Update**.

2. To pause data collection using the Web Admin console:

- a. Go to the **Tags** page from the **Configuration** page.

- b. Select one or more tags in the **Tags** section.

The **Tag Editor** section displays current parameters.

- c. Locate the **Collection** field in the **Collection** section.

- d. Disable the option.

- e. Select **Update**.

Data collection stops for those tags. To re-activate collection for those tags, select **Enabled** for the **Collection** option and select **Update**.

**Note:**

If the collector is configured to allow online changes, making configuration changes such as the above may cause bad data samples to be recorded as the collector internally restarts. Disable online configuration changes and restart the collector manually if you want to avoid this behavior.

Modify User Privileges for Starting a Collector

To start any collector, a user must have Power User privileges at a minimum. Typically, a user from the Administrator group starts a collector. If running as a service, you can use the local system account. If a user is not a Power User or Administrator, for instance, and you still want to allow that user to start a collector, you can override the user permissions setting in the Windows Registry.

The following example shows how to change the user permissions for a collector (the iFIX collector). While these steps outline the procedure for changing the user permissions for the iFIX collector, note that you must perform these steps individually for each collector that you want to allow the user to start.

To change the permissions in the Windows Registry, you must be an Administrator. After you change the permissions, you can exit the Registry Editor, allow the user to log in again, and then allow that user to restart the collector.

1. On the **Start** menu, select **Run**.
2. Type `regedt32` and select **OK**.
The Registry Editor appears.
3. Navigate to the following registry key:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\iFixCollector
```

4. Right-select the **iFIX Collector** folder and select **Permissions**.
The **Permissions for iFixCollector** window appears.
5. Select the **Users** group in the top portion of the window.
6. Select the **Allow** check box from the **Full Control** permissions, in the bottom portion of the window.
7. Select **Apply**.

About Monitoring Data Collector Performance Statistics

You can evaluate data collector performance by observing information displayed or recorded in the following pages or files:

- Historian Administrator **Main** page and Historian **Messages** page.

For a detailed description of the parameter/option fields and the Alerts and Message Search Windows, refer to *Using Historian Administrator* manual.

- LOG and SHOW files on the data collector local machine.

LOG (.log) files are historical journals of every event affecting operation of the collector. When you troubleshoot a problem in a collector, examining the log files is the best place to begin. The default path for LOG and SHW files is `C:\Proficy Historian Data\LogFiles`. The highest number is the most recent.

SHOW (.shw) files allow you to examine the current configuration of a data collector. This file also details version and system configuration affecting the specific collector. The default path for LOG and SHW files is `C:\Proficy Historian Data\LogFiles`.

If you are upgrading from a previous version of Historian, then the Archives, LogFiles, and BufferFiles destination paths will remain unchanged.

Historian periodically checks for Archives, Bufferfiles, and Logfiles folder disk space availability. If the available disk space is less than configured, then Historian Data Archiver may shutdown.

- Event Viewer on the Historian Server and on the collector local machine.

The Windows Event Viewer logs all system events of interest to an administrator or developer. Each event has an identifying icon, such as Information, Warning, or Error. Select an item to display more detail about the event. Use this information to determine when and why a server fault occurred and when satisfactory operation was restored.

- Historian tag using the source address of the Rate Output Address, Status Output Address, or heartbeat Output Address.

Disabling Rebroadcasting for Historian Data Archiver

The Historian Data Archiver service rebroadcasts collector status reports to all connected clients to ensure they are immediately notified of any changes to their configuration. If you have many collectors (20 or more) pointing to a single Historian archive, you may experience network congestion.

1. Start the Windows Registry Editor.
2. Navigate to the `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc\iHistorian\Services`
`\DataArchiver` key

3. Create a new DWORD called `RouteInterfaceStatusMsg` and set it to 0 (to enable rebroadcasting, set this value to 1).
4. Close the Windows Registry Editor.
5. Restart the Historian Data Archiver service.



Note:

If rebroadcasting is disabled in the Historian Data Archiver service, any programs subscribed to collector status changes using `Collectors.SubscribeStatus = true` will no longer automatically receive collector status messages. To receive collector status messages, periodically read the `Collector.Status` property instead.

Troubleshooting Tag Configuration

To troubleshoot the tag configuration:

- View the Collector SHOW (`DataCollector.shw`) file in `C:\Historian Data\LogFiles\xxxCollector.shw` to review the current Data Collector configuration.
- View the `DataCollector.LOG` file in `C:\Proficy Historian Data\LogFiles\xxxCollector-01.log` to detect operational errors with Tags.
- If you are using aggregate data, such as average, minimum, or maximum, use a chart display such as the trend option or the Excel Add-In to sample and then observe how data is stored.
- If you are not certain about what is happening, turn off Collector Compression and Archive Compression and observe how raw data values flow into the archive. Be sure to export the tag configuration first so you can return to the original configuration.



Note:

If you are upgrading from a previous version of Historian, then the `Archives`, `LogFiles`, and `BufferFiles` destination paths will remain unchanged. By default, `C:\Program Files\Proficy\Proficy Historian\Logfiles\`.


Reviewing the Active Collector Configuration

You can view the active collector configuration via the Historian Administration tool, and you can also view the local Data collector SHOW (`.shw`) file.

1. In Historian Administrator Main page, select the **Collectors** link. The Collector Maintenance page appears.
The **Collector Maintenance** page appears.

2. Select a data collector in the left column. The right column fills with current configuration data.
3. Examine the current configuration settings to verify that they are appropriate.

You can also review the active configuration by examining the local Data Collector SHOW(.SHW) File, as shown below:



```

CalculationCollector.shw - Notepad
File Edit Format View Help
Configuration - [12/19/2002 11:31:30.000 AM]
MSO Library version 1.0 Build (161)
Collector Properties
-----
Collector Name.....: EVEREST_Calculation
Can Browse Source.....: Yes
Can Source Timestamp.....: Yes
Should Adjust Time.....: Yes
Should Queue Writes.....: NO
Source Time Is LOCAL.....: NO
Support ASync Reading.....: Yes
Force Polled.....: NO
Allow On The Fly Tag Updates.....: Yes
Allow Collection Pause/Resume.....: Yes
General #1.....: 10
General #2.....: 4
General #3.....:
General #4.....:
General #5.....:
Status Output Address.....:
Rate Output Address.....:
Heartbeat Output Address.....:
Default TagPrefix.....: 2
Collection delay at Startup.....: 2
Buffering (Minimum Free Disk Space).....: 150
Buffering (Maximum Memory Usage).....: 20
Default Load Balancing.....: NO
Default Collector Compression.....: Yes
Default Collection Type.....: Unsolicited
Default TimeStamp Type.....: Collector
default collection interval.....: 1000
Default Collector Compression Deadband..: 5.50000
Big Spike Multiplier.....: 4
Big Spike Intervals.....: 5
-----

```

4. Scan the contents of the file and verify that the configuration parameters are correct for the application.

If any of the values are not appropriate:

- a. Go back Historian Administrator.
- b. Select the **Collectors** link to display the **Collector Maintenance** page.
- c. Select a collector.
- d. Access the various sections and enter new values as appropriate.
- e. Select **Update**.

The new values are stored in the Data Collector SHW file after 30 seconds.

Collector and Archive Compression

It is possible for collected tags with no compression to appear in Historian as if the collector or archive compression options are enabled. If collector compression occurs, you will notice an increase in the percentage of the Compression value from 0% in the **Collectors** panel of the **System Statistics** page in Historian Administrator. When archive compression occurs, you will notice the **Archive Compression** value and status bar change on the **System Statistics** page.

Collector Compression

For all collectors, except the File collector, you may observe collector compression occurring for your collected data (even though it is not enabled) if bad quality data samples appear in succession. When a succession of bad data quality samples appears, Historian collects only the first sample in the series. No new samples are collected until the data quality changes. Historian does not collect the redundant bad data quality samples, and this is reflected in the Collector Compression percentage statistic.

For a Calculation or Server-to-Server Collector, you may possibly observe collector compression (even though it is not enabled) when calculations fail, producing no results or bad quality data.

Archive Compression

If the **Archive Compression** value on the **System Statistics** page indicates that archive compression is occurring, and you did not enable archive compression for the tags, the reason could be because of internal statistics tags with archive compression enabled.

Data Buffering

During normal operation, the Data Collector sends data and messages to the Historian Server using TCP/IP. The Server responds when it has successfully received the data.

Normal variations in response from the server can leave a small number of messages buffered in memory. When the collector loses its connection, or whenever the server cannot keep up with throughput, the data collector establishes a buffer. During such periods, the data collector continues to write data, caching it in the local file and memory buffer instead of writing it to the server. When the collector reestablishes the connection to the server, it forwards the stored data to the server, clearing the buffer as the server successfully receives the data.

If a collector writing to an archive loses its connection and the disk buffer becomes full, real-time collection does not begin immediately upon the re-established connection to the server. No data is collected from the time that the connection to the archive is re-established until approximately the time it takes for the buffer on the collector to clear.

**Note:**

The Data Buffering feature does not apply to File collectors. The File collector does not process incoming files when the connection to the server is down. When the connection is re-established, processing of incoming files resumes.

If there is not enough free space for a collector to create its buffer files on initial startup, the collector shuts down immediately and sends the following message to the Event Viewer:

```
"[datetime] MessageAdd -MDW_iFIX collector Buffering could not create buffer files. Shutting down."
```

If there is not enough free space for the collector to create its buffer files on startup, the collector shuts down and sends a message to the Event Viewer. The simplest way to prevent this from happening is to free up disk space to allow the collector to start. If this is not possible, you can edit the Registry to change the buffer size.

Editing the Registry to Change the Buffer Size

1. Select **Run** from the **Start** menu.
The **Run** window appears.
2. Type `Regedit` and press **Enter**.
The **Registry Editor** appears.
3. Locate the `ComputerName_OPC1` key, where `ComputerName` is the name of your computer. You can find this key here:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\Historian\Services\OPCCollector\ComputerName_OPC1
```

4. Add a new DWORD value. Enter the name `MinimumDiskFreeBufferSize`, select the decimal option, and set the value to a small number such as 10 or 20. The value that you enter represents the number of MB of buffer space needed.
5. Start the collector.
6. If the Collector does not connect to the Historian Server, check the log file in the logfiles folder on the collector computer. If the log states that Historian "could not create buffer files" then repeat steps 1-5, this time using a smaller number.
7. Once the Collector connects to the Historian Server, the collector should appear in the Admin UI and you can readjust the buffer file size on the bottom of the collector's **General** section.

Setting Up Services Recovery Actions in Windows

Windows allows you to set up recovery actions to take place if a service fails. If you are running Historian Collectors on Windows, set recovery actions to restart the service for your individual collectors.

To set recovery actions for a specific service:

1. Open the **Control Panel**.
2. Double-click the **Administrative Tools** icon.
3. Double-click the **Services** icon in the **Administrative Tools** window.
The **Services** window appears.
4. Right-select the Service you want to set recovery options for.
5. Select **Properties**.
The **Service Properties** window appears.
6. Select **Recovery**.
7. Select the recovery actions you want in the **First attempt failure**, **Second attempt failure** and **Subsequent attempts failure** fields.
For more information on setting Services Recovery Actions, refer to the Microsoft Management Console online Help.

Working with Python Expression Tags

Python Expression Tags in Historian

A Python® expression is typically a single line of Python code which, when executed, evaluates to a single value. It can also be thought of as the right-hand side of a Python assignment operation.

Python Expression Tags are used in cases where you do not want to store a raw data value, but wish to store only derived or calculated values. Historian allows raw data to be pre-processed with Python expressions during collection, so that the data collected for the expression tags contain these derived values.

See www.python.org/ for complete Python documentation.



Note:

This functionality is available only for the Enterprise edition of Historian.

To use a Python Expression Tag in Historian, you must configure a tag as a Python Expression Tag using either Historian File collector or Historian Excel Add-in. You can then use the Python expression on this tag to pre-process raw data before the result is inserted into Historian.

The following collectors support Python Expression Tags:

- Simulation Data Collector
- iFix Data Collector
- OPC Data Collector
- OSI PI Collector
- Windows Performance Collector
- Collector Toolkit

To enable Python Expression support for toolkit-based collectors, copy the following files to the collector executable path:

- python34.dll
- ihcprest140_2_8.dll.dll
- PythonExpressionExtension.dll

For 32-bit collectors, these files are located at C:\Program Files\Proficy\Proficy Historian\x86\Server. For 64-bit collectors, these files are located at C:\Program Files\Proficy\Proficy Historian\x64\Server.

Supported Python Modules

This table lists the available Python modules. Within the approved modules below, certain Python classes, functions, and keywords may not be available for use, for security reasons. For example, the `exec` function cannot be used.



Note:

Python modules not listed in the table are not supported.

Standard Python Modules	Documentation	Needs Importing
<code>builtins</code>	Standard Python documentation	No
<code>datetime</code>	Standard Python documentation	Yes
<code>math</code>	Standard Python documentation	Yes
<code>statistics</code>	Standard Python documentation	Yes
Module part of Historian install	Unit of Measure Python Module.pdf (This document can also be found in the help directory for your Historian installation.)	Yes

Standard Python Modules	Documentation	Needs Importing
uom (unit of measure conversion module)		

Constructing and Adding Python Expression Tags

To configure and use the Python Expression Tag in Historian:

1. [Construct a Python Expression. \(on page 2080\)](#)
2. [Construct the JSON configuration. \(on page 2080\)](#)
3. [Add the Python Expression Tag to Historian. \(on page 2082\)](#)

For examples, see the [Python Expression Tag Examples \(on page 2084\)](#).

Constructing a Python Expression

1. Open a text editor.
2. Construct an expression in Python that takes raw data and produces a calculated value you want to store in Historian.
 - The raw data in your expression is exposed in the Python script as an object with the following properties: `value`, `is_quality_good`, `is_quality_bad`, `timestamp`
 - You can give this object any name you want.
3. Ensure that the expression you create is a valid Python expression (that is, it evaluates to a single value).

For example, we call our object `temp` and we use the `value` property. We create a simple, valid Python expression, taking raw data (`temp.value`) and create a calculated value.

```
temp.value + math.pow(10,temp.value/70)
```

To use this example, `temp.value` must be defined and the Python `math` module must be imported.

Constructing the JSON Configuration

Construct a JSON configuration object that contains the Python expression in the same text editor. This allows you to specify Python modules that you require and to link the variables (parameters) used in the expression to a raw data source.

It is easier to edit your JSON in the Historian Excel Add-In, which you will use later to add the tag to Historian, see [Adding a Python Expression Tag to Historian \(on page 2082\)](#).

The JSON needs to be “*minified*” and it needs to conform to a particular structure. **Example of JSON containing a Python Expression in “Minified” format**

```
{ "imports": [ "math" ], "script": "temp.value +
math.pow(10,temp.value/70)", "parameters": [ { "name": "temp", "source": { "add
```

Here is an example of JSON structure in “*Beautified*” format. The **highlighted** entries are placeholders.

```
{
  "imports": [ "<imported_module0>", "<imported_module1>",
    "<imported_module2>", ... ], "script": "<python_expression>",
  "parameters": [
    {
      "name": "<variable_name>", "source": { "address": "<source_address>",
      "dataType": "<datatype_of_parameter_value_field>"
    }, ...
  ]
}
```

After “`imports`”, list the Python modules you need to import for your Python expression. See [Supported Python Modules \(on page 2079\)](#).

After “`script`”, enter the python expression that you created in [Constructing a Python Expression \(on page 2080\)](#).

Provide values for the following parameters:

Parameter	Description
name	The variable name you gave to the object representing the raw data which will be pre-processed by the expression you created. This variable is exposed in the Python script as an object with the following properties: <code>value</code> , <code>is_quality_good</code> , <code>is_quality_bad</code> , <code>timestamp</code> .
address	The source address used by the collector to access the raw data. This parameter is stipulated in the context of the chosen collector, which must be on the list of collectors (on page 2078) supporting Python Expression Tags.
dataType	The datatype of the <code>\value</code> field for the variable representing the raw data. This allows the Python expression to know the data type on which it is operating. The datatype options are: <code>SingleFloat</code> , <code>DoubleFloat</code> , <code>SingleInteger</code> , <code>DoubleInteger</code> , <code>QuadInteger</code> , <code>UnsignedSingleInteger</code> , <code>UnsignedDoubleInteger</code> , <code>UnsignedQuadInteger</code> ,

Parameter	Description
	FixedString, VariableString, Byte, Boolean. These are the same Historian data types that are supported by the File collector.

Example of JSON containing a Python Expression in “*Beautified*” format

This example uses the Simulation Collector. Your collector might use a different source address.

```
{
  "imports":["math"],
  "script":"temp.value+math.pow(10,temp.value/70)",
  "parameters":[{"name":"temp","source":
{"address":"Simulation00001","dataType":"SingleFloat" } } ]
}
```

It is important to check that your JSON is valid, since no validation will be performed on the JSON at tag creation.

Minified JSON

Once you have constructed this JSON, you need to format it as a “*minified*” string, so that it can be processed in later steps. Minified JSON has no newline characters or comments. There are tools which can help you minify JSON.

For our example, the minified JSON would look like this:

```
{"imports":["math"],"script":"temp.value + math.pow(10,temp.value/70)","parameters":
[{"name":"temp","source":{"address":"Simulation00001","dataType":"SingleFloat"}}]}
```

Pay attention to escape characters in your JSON. If your JSON contains a \ character, you need to escape it. So, \ becomes \\ (since \ is used to escape another \).

Adding a Python Expression Tag to Historian

You can now add a Python Expression Tag to Historian. Ensure the following for your Python Expression Tag:

- CalcType is set to "PythonExpr".
- SourceAddress contains the JSON configuration.

Adding the Python Expression Tag can be done using Historian File collector or Historian Excel Add-in in the same way that you would add a regular tag.

For more information on adding tags, refer to Historian File collector or Historian Excel Add-in.

- *File collector* (especially the *CSV File Formats* and *XML File Formats* sections)

If you add your tag to the Historian via the File collector and using the CSV format, you must enclose the JSON in quotation marks (") to satisfy CSV requirements for a column value containing commas (,).

This means that you will also need to escape any quotation marks (") in the JSON. That is, " becomes "" (as " is used to escape another ").

- *Using the Historian Excel Add-in*

The Historian Excel Add-In has the advantage of being easiest to use for editing your JSON.

Example of Adding a Tag Using the File collector

For this example, we choose to add a Python Expression tag to the Historian using the File collector to import a CSV file.

The file contents look like this:

```
[Tag]
Tagname,CollectorName,CalcType,SourceAddress,DataType,Description
ExampleTag,SimulationCollector,PythonExpr,
"{ \"imports\": [ \"math\" ], \"script\": \"temp.value +
math.pow(10,temp.value/70)\" , \"parameters\": [ { \"name\": \"temp\", \"source\": { \"address\": \"Simulation00001\", \"dataType\"
\": \"SingleFloat\" } } ] }\",
SingleFloat,Python Expression Tag example
```

Note the following:

- The `CalcType` header is included and set to `PythonExpr`.
- The Source Address is set to the minified JSON created in the previous step.
- The `CollectorName` is set to `SimulationCollector`, which is a Simulation Collector. This collector is on the list of collectors supporting Python Expression Tags. Your collector might be called by a different name.

- The quotation marks within the JSON string are escaped with other quotation marks in the CSV file.

For more information, refer to [File collector > CSV file format](#).

Viewing the Python Expression Tag

When viewing a Python Expression Tag using Historian Administrator, note that:

- The Source Address field contains the full applicable JSON configuration, which includes an indication of the source address. Changing this is not recommended.
- The **Browse** button for configuring the Source Address is disabled for Python Expression Tags.

Python Expression Tag Examples

This section provides examples for using Python® Expression Tags.

Using No Python Modules or Functions

In this example, we want to perform gross error detection on a signal "Signal" and clip the values to a range between 0 and 600.

Expression

To solve this, we create the following Python expression.

```
0 if Signal.value<0 else (600 if Signal.value>600 else Signal.value)
```

	Python Datatype	Name	Description
Expression Inputs	SingleFloat	Signal	Represents the signal value.
Expression Result	SingleFloat	Not Applicable	Represents the resulting expression value, with extreme outliers clipped.

Python Modules to Import for this Expression: None. (Only modules contained on the list of [supported modules \(on page 2079\)](#) are available for this expression.)

Constructing the JSON:

Using the created expression, we construct the following JSON. For more information, refer to [Constructing the JSON Configuration \(on page 2080\)](#).

```
"script":"0 if Signal.value<0 else (600 if Signal.value>600 else Signal.value)", "parameters":[
    {
        "name":" Signal",
        "source":{"address":"Simulation00001", "dataType":"SingleFloat"}
    }
]
```

Note that the `address` parameter is stipulated in the context of the chosen collector, which must be on the [list of collectors \(on page 2078\)](#) supporting Python Expression Tags.

In this example, we have used the Simulation Collector. Your collector might use a different source address.

We then transform the above into a minified JSON string:

```
{"script":"0 if Signal.value < 0 else (600 if Signal.value > 600 else Signal.value)","parameters":
  [{"name":"Signal","source":{"address":"Simulation00001","dataType":"SingleFloat"}}]}
```

Adding the Expression Tag to Historian

For this example, we choose to add a Python Expression tag to the Historian using the File collector to import a CSV file. (We could also have added the tag via the Historian Excel Add-In.)

The file contents look like this:

```
[Tag]

Tagname,CollectorName,CalcType,SourceAddress,DataType,DescriptionGEDSignalTag,SimulationCollector,PythonExpr,
    {"script":"","0 if Signal.value < 0 else (600 if Signal.value > 600 else
Signal.value)","parameters":

[{"name":"","Signal","source":{"address":"","Simulation00001","dataType":"","SingleFloat"}}]},
    SingleFloat,Python Expression Tag example
```

Note the following:

- The `CalcType` header is included and set to `PythonExpr`.
- The `Source Address` is set to the minified JSON created in the previous step.

- The `CollectorName` is set to `SimulationCollector`, which is a Simulation Collector. Your collector might be called by a different name.
- The quotation marks within the JSON string are escaped with other quotation marks.

We then import the file, following the instructions specified in [File collector](#).

Using a Built-In Python Function

In this example, we want to calculate the maximum of two temperature values to be collected.

Expression

To solve this, we create the following Python expression:

```
max(ThermocoupleA.value, ThermocoupleB.value)
```

	Python Datatype	Name	Description
Expression Inputs	SingleFloat	ThermocoupleA	Represents a temperature value.
	SingleFloat	ThermocoupleB	Represents a temperature value.
Expression Result	SingleFloat	Not Applicable	Represents the maximum of the two given temperature values

Python Modules to Import for this Expression: None. A built-in Python module from the Python Standard Library is used. (Only modules contained on the list of [supported modules \(on page 2079\)](#) are available to this expression.)

Constructing the JSON

Using the created expression, we construct the following JSON:

```
{
  "script": "max(ThermocoupleA.value, ThermocoupleB.value)",
  "parameters": [
    {
      "name": "ThermocoupleA",
      "source": { "address": "Simulation00001", "dataType": "SingleFloat" }
    },
    {
      "name": "ThermocoupleB",
      "source": { "address": "Simulation00002", "dataType": "SingleFloat" }
    }
  ]
}
```

```

}
]
}

```

Note that the `address` parameter is stipulated in the context of the chosen collector, which must be on the [list of collectors \(on page 2078\)](#) supporting Python Expression Tags. In this example, we have used the Simulation Collector. Your collector might use a different source address.

We then transform the above into a minified JSON string:

```

{"script":"max(ThermocoupleA.value,ThermocoupleB.value)","parameters":[{"name":"ThermocoupleA","source":{"address":"Simulation00001","dataType":"SingleFloat"}},{name":"ThermocoupleB","source":{"address":"Simulation00002","dataType":"SingleFloat"}}]}

```

Adding the Expression Tag to Historian

For this example, we choose to add a Python Expression tag to the Historian using the Historian Excel Add-In. (We could also have added the tag by using via the File collector to import a CSV file.)

Ensure the following for your Python Expression Tag:

- The `CalcType` is set to `PythonExpr`.
- The `SourceAddress` contains the JSON configuration.
- The `CollectorName` is set to the name of the chosen collector, which must be on the list of collectors supporting Python Expression Tags. Your collector might be called by a different name.
- The quotation marks within the JSON string are escaped with other quotation marks in the CSV file.

Otherwise, the tag is added in exactly the same way as for a regular tag.

Using A Python Standard Library Module

In this example we want to calculate a result based on a specific time range for an expression input. We set a supply voltage to zero within prescribed time ranges.

Expression

To solve this, we create the following Python expression:

```

0 if (SupplyVoltage.timestamp.astimezone().time() >= datetime.time(18) and
SupplyVoltage.timestamp.astimezone().time() <= datetime.time(20, 30)) else
SupplyVoltage.value

```

	Python Datatype	Name	Description
Expression Inputs	SingleFloat	SupplyVoltage	Represents the value we wish to transform.
Expression Result	datetime	Not Applicable	Represents the resulting supply voltage, set to zero in the prescribed time ranges.

Python Modules to Import for this Expression: `datetime` module. This module is shipped with Historian.

Constructing the JSON

Using the created expression, we construct the following JSON:

```
{
  "imports":["datetime"],
  "script":"0 if (SupplyVoltage.timestamp.astimezone().time() >= datetime.time(18) and
SupplyVoltage.timestamp.astimezone().time() <= datetime.time(20, 30)) else
SupplyVoltage.value", "parameters":[
  {
    "name":" SupplyVoltage",
    "source":{"address":"Simulation00001", "dataType":"SingleFloat"}
  }
]
}
```

Note that the `address` parameter is stipulated in the context of the chosen collector, which must be on the [list of collectors \(on page 2078\)](#) supporting Python Expression Tags. In this example, we have used the Simulation Collector. Your collector might use a different source address.

We then transform the above into a minified JSON string:

```
{"imports":["datetime"],"script":"0 if (SupplyVoltage.timestamp.astimezone().time() >= datetime.time(18) and
SupplyVoltage.timestamp.astimezone().time() <= datetime.time(20, 30)) else
SupplyVoltage.value", "parameters":[{"name":"SupplyVoltage", "source":
{"address":"Simulation00001", "dataType":"SingleFloat"}}]}
```

Adding the Expression Tag to Historian

For this example, we choose to add a Python Expression tag to the Historian using the Historian Excel Add-In. (We could also have added the tag via the File collector to import a CSV file.)

Ensure the following for your Python Expression Tag:

- The `CalcType` is set to `PythonExpr`.
- The `SourceAddress` contains the JSON configuration.
- The `CollectorName` is set to the name of the chosen collector, which must be on the list of collectors supporting Python Expression Tags. Your collector might be called by a different name.

Otherwise, the tag is added in exactly the same way as for a regular tag.

Using A Python Standard Library Module

In this example we want to calculate a result based on a specific time range for an expression input. We set a supply voltage to zero within prescribed time ranges.

Expression

To solve this, we create the following Python expression:

```
0 if (SupplyVoltage.timestamp.astimezone().time() >= datetime.time(18) and
SupplyVoltage.timestamp.astimezone().time() <= datetime.time(20, 30)) else
SupplyVoltage.value
```

	Python Datatype	Name	Description
Expression Inputs	<code>SingleFloat</code>	<code>SupplyVoltage</code>	Represents the value we wish to transform.
Expression Result	<code>datetime</code>	Not Applicable	Represents the resulting supply voltage, set to zero in the prescribed time ranges.

Python Modules to Import for this Expression: `datetime` module. This module is shipped with Historian.

Constructing the JSON

Using the created expression, we construct the following JSON:

```
{
  "imports":["datetime"],
  "script":"0 if (SupplyVoltage.timestamp.astimezone().time() >= datetime.time(18) and
SupplyVoltage.timestamp.astimezone().time() <= datetime.time(20, 30)) else
SupplyVoltage.value", "parameters":[
```

```
{
  "name": " SupplyVoltage",
  "source": {"address": "Simulation00001", "dataType": "SingleFloat"}
}
]
```

Note that the `address` parameter is stipulated in the context of the chosen collector, which must be on the [list of collectors \(on page 2078\)](#) supporting Python Expression Tags. In this example, we have used the Simulation Collector. Your collector might use a different source address.

We then transform the above into a minified JSON string:

```
{"imports":["datetime"],"script":"0 if (SupplyVoltage.timestamp.astimezone().time() >= datetime.time(18) and SupplyVoltage.timestamp.astimezone().time() <= datetime.time(20, 30)) else SupplyVoltage.value","parameters":[{"name":"SupplyVoltage","source":{"address":"Simulation00001","dataType":"SingleFloat"}}]}
```

Adding the Expression Tag to Historian

For this example, we choose to add a Python Expression tag to the Historian using the Historian Excel Add-In. (We could also have added the tag via the File collector to import a CSV file.)

Ensure the following for your Python Expression Tag:

- The `CalcType` is set to `PythonExpr`.
- The `SourceAddress` contains the JSON configuration.
- The `CollectorName` is set to the name of the chosen collector, which must be on the list of collectors supporting Python Expression Tags. Your collector might be called by a different name.

Otherwise, the tag is added in exactly the same way as for a regular tag.

Using A Historian Python Module

In this example we want to convert a temperature value from Fahrenheit to Celsius.

Expression

To solve this, we create the following Python expression:

```
uom.to_Celsius(Thermocouple.value, uom.Temperature.Fahrenheit)
```

	Python Datatype	Name	Description
Expression Inputs	SingleFloat	Thermocouple	Represents the temperature value in degrees Fahrenheit
Expression Result	SingleFloat	Not Applicable	Represents the temperature value in degrees Celsius

Python Modules to Import for this Expression: uom module. This Python module is shipped with Historian.

(Only modules contained on the list of [supported modules \(on page 2079\)](#) are available to this expression.)

Constructing the JSON

Using the created expression, we construct the following JSON:

```
{
  "imports":["uom"],
  "script":"uom.to_Celsius(Thermocouple.value, uom.Temperature.Fahrenheit)",
  "parameters":[
    {
      "name":" Thermocouple",
      "source":{"address":"Simulation00001", "dataType":"SingleFloat"}
    }
  ]
}
```

Note that the `address` parameter is stipulated in the context of the chosen collector supporting Python Expression Tags. In this example, we have used the **Simulation Collector**. Your collector might use a different source address.

We then transform the above into a minified JSON string:

```
{"imports":["uom"],"script":"uom.to_Celsius(Thermocouple.value,uom.Temperature.Fahrenheit)","parameters":[{"name":"Thermocouple","source":{"address":"Simulation00001","dataType":"SingleFloat"}}]}
```

Adding the Expression Tag to Historian

For this example, we choose to add a Python Expression tag to the Historian using the File collector to import a CSV file. (We could also have added the tag via the Historian Excel Add-In.)

The file contents look like this:

```
[Tag]
TagName,CollectorName,CalcType,SourceAddress,DataType,DescriptionConvertedTempTag,SimulationCollector,PythonExpr,
{"imports":["uom"],"script":"uom.to_Celsius(Thermocouple.value,uom.Temperature.Fahrenheit)",
"parameters":[{"name":"Thermocouple","source":{"address":"Simulation00001","dataType":
"SingleFloat"}}]},
SingleFloat,Python Expression Tag example
Note the following: The CalcType header is included and set to PythonExpr.
```

Note the following:

- The `CalcType` header is included and is set to `PythonExpr`.
- The `SourceAddress` contains the JSON configuration.
- The `CollectorName` is set to the name of the chosen collector, which must be on the list of collectors supporting Python Expression Tags. Your collector might be called by a different name.
- The quotation marks within the JSON string are escaped with other quotation marks in the CSV file.

For more information, see *File collector > CSV File Formats*.

We then import the file, following the instructions in the File collector section.

Using Array/Table Lookup

In this example we want to translate a string representing order of magnitude into a corresponding numerical value using array/table lookup.

This example will be explained by means of a hypothetical collector called `PlantSensorCollector` that is a Python Expression enabled collector. The collector collects a source tag with address `TemperatureSetpoint` of type `VariableString`, having values `'Low'`, `'Medium'`, and `'High'`.

Expression

To solve this, we create the following Python expression:

```
{'Low':100, 'Medium':400, 'High':800}.get(Setpoint.value, 0)
```

	Python Datatype	Name	Description
Expression Inputs	VariableString	Setpoint	Represents the given ordinal string value we wish to transform.
Expression Result	SingleFloat	Not Applicable	Represents the numerical value corresponding to the ordinal string input.

Python Modules to Import for this Expression: None. (Only modules contained on the list of [supported modules \(on page 2079\)](#) are available to this expression.)

Constructing the JSON: Using the created expression, we construct the following JSON:

```
{
  "script": "{ 'Low':100, 'Medium':400, 'High':800 }.get(Setpoint.value, 0)",
  "parameters": [
    {
      "name": " Setpoint",
      "source": { "address": "TemperatureSetpoint", "dataType": "VariableString" }
    }
  ]
}
```

We then transform the above into a minified JSON string:

```
{"script":"{ 'Low':100, 'Medium':400, 'High':800 }.get(Setpoint.value,0)", "parameters":
  [{"name":"Setpoint", "source":{"address":"TemperatureSetpoint", "dataType":"VariableString"}}]}
```

Adding the Expression Tag to Historian: For this example, we choose to add a Python Expression tag to the Historian using the File collector to import a CSV file. (We could also have added the tag via the Historian Excel Add-In.)

The file contents look like this:

```
[Tag]TagName,CollectorName,CalcType,SourceAddress,DataType,DescriptionNumericalTagDerivedFromOrdinalVal,PlantSensorCollector,PythonExpr,
  "{ \"script\": \"{ 'Low':100, 'Medium':400, 'High':800 }.get(Setpoint.value,0) \", \"parameters\":
  [ { \"name\": \"Setpoint\", \"source\": { \"address\": \"TemperatureSetpoint\", \"dataType\": \"VariableString\" } } ] }\",
  VariableString, Python Expression Tag example
```

Note the following:

- The `CalcType` is set to `PythonExpr`.
- The `SourceAddress` contains the JSON configuration.
- The `CollectorName` is set to the name of the chosen collector, which must be on the list of collectors supporting Python Expression Tags. Your collector might be called by a different name.
- The quotation marks within the JSON string are escaped with other quotation marks in the CSV file.

For more information, see *File collector > CSV File Formats*.

We then import the file, following the instructions specified in *File collector*.

Uninstall Collectors

If you want to uninstall collectors, delete all the instances of the collectors that you have created. You can do so using [Configuration Hub \(on page 654\)](#) or [Remote Collector Management \(on page 817\)](#). The following instances of collectors (the ones that were created during the installation of collectors) are deleted automatically:

- The iFIX collector
- The iFIX Alarms & Events collector
- The OPC Classic Data Access collector for CIMPLICITY
- The OPC Classic Alarms and Events collector for CIMPLICITY

Even after you uninstall collectors and Web-based Clients, the corresponding Windows services and registry entries are not removed.

1. Select **Programs / Uninstall a Program** in Control Panel.
2. Select **Historian Collectors**, and then select **Uninstall**.

The collectors are uninstalled.

Troubleshooting Issues with Collectors

This topic contains solutions/workarounds to some of the common issues encountered with Configuration Hub. This list is not comprehensive. If the issue you are facing is not listed on this page, refer to [Troubleshooting the Historian Server \(on page 298\)](#).

Proxy Timeout Error While Adding a Collector Instance

Description

When you attempt to add a collector, sometimes, a proxy error appears even if the error occurs because of an API timeout.

Workaround

1. Access the `historian-httpd.conf` file located at `C:\Program Files\GE\Operations Hub\httpd\conf\app-specific.d`.
2. Increase the timeout value (for example, 250). If the timeout parameter is not available, enter it as follows: `ProxyTimeout <value>`
3. Restart the Proficy Historian Tomcat Server and the Proficy Operations Hub Httpd Reverse Proxy services.

Unable to Use the Windows login User and Password During the Destination Historian Server Configuration When Adding a Collector Instance

Description

During Collector instance creation, for some reason, if you are unable to use the Windows login user and password during the Destination Historian server configuration, you can perform the following workaround.

Workaround

- Edit the **Password** and **UserName** registries and add the predefined user, that is, `<hostname>.admin` and its password in the Collector Manager registry at `Computer\HKEY_LOCAL_MACHINE\SOFTWARE\GE DIGITAL\Historian Remote Management Agents\Collector Manager`.
- Check if the predefined user, that is, `<hostname>.admin` was added to the **Local users & Group**. If not, add the predefined user and its password to the **Local users & Group**. For more information on how to add a user to **Local users & Group**, refer to Adding Users to Windows Security Group.

Receiving a Collector Configuration Error

Description

A single `ihConfigurationGetProperties[-2]` error appears in the `collector.LOG` file.

Workaround

The error most likely occurred as a result of the collector connecting and querying for changes in the tag database immediately, getting a timeout, and then immediately querying again and succeeding.

Polled-based Collector performance improvements leading to "Load on source" and "Increase Overruns"

Description

From Historian 2022 onwards, the performance of polled-based collectors has been enhanced by introducing a higher number of polled threads, set to a default of 4, compared to the previous default of 1. While this enhancement has a positive impact on the collector performance, it may cause a decrease in performance on the source side due to increased load and also cause potential overruns. Therefore, if you are facing any performance issue on the source side, you can modify the number of polled threads using the following workaround.

Workaround

1. Open Registry Editor.
2. Create **REG_NumPolledReadThreads** as a new **DWORD (32-bit) Value** in the following registry paths, and then change its value to 1.

32-bit collector registry path for Proficy products:

```
Computer\HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\Intellution, Inc.\iHistorian\Services
```

32-bit collector registry path:

```
Computer\HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\GE Digital \iHistorian\Services
```

64-bit collector registry path:

```
Computer\HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\iHistorian \Services
```

For example,

iFIX Collector

```
Computer\HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\Intellution, Inc.\iHistorian\Services\iFixCollector
```

Simulation Collector

```
Computer\HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\GE Digital \iHistorian\Services\SimulationCollector
```

OPC Collector

Computer\HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution,
Inc.\Historian OPC Collector

3. Ensure to restart the corresponding collector.

Chapter 15. The Calculation Collector

Overview of the Calculation Collector

Using the Calculation collector, you can perform data calculations on values already in the archiver. It retrieves data from tags in the Historian archive, performs the calculation, and then stores the resulting values into new archive tags. You can then access these tags like you access any other Historian tag.


Features of the Calculation Collector

The Calculation collector performs calculations on the following values:

- Current values of other Historian tags in the same archiver.
- Previous raw samples of other tags in the same archiver.
- Calculated values of other Historian tags in the same archiver, such as minimum, maximum, average, or standard deviation. You can specify a time range for these calculations or perform a filtered query. You can use the resulting single number in a calculation.
- Interpolated values of other Historian tags in the same archiver.
- Any data retrievable using a VBScript, file I/O, ADO, and so on.

Data Flow

The following image shows the data flow in a Calculation collector. The output from a calculation is always a single Historian tag.



Advantages of Using the Calculation Collector

- The Calculation collector can keep a history of the calculated values.
- It can perform thousands of calculations per second. Therefore, it is generally preferred to a VB SDK program performing the same functions.
- It can perform calculations on data stored in the following sources:
 - A SCADA database (such as iFIX)
 - A VB SDK program
 - A Historian collector (using input scaling)
 - By the Calculation collector
 - The Historian OLE DB provider
 - Reporting tools such as Crystal Reports
 - The Historian Excel Add-In

Limitations


- Python Expression Tags are not supported for use together with the Calculation collector. The behavior of the Calculation collector is different from that of Python Expression Tags, which are used in cases where you do not want to store a raw data value, but wish to store only derived values. For more information, refer to [Python Expression Tag Examples \(on page 2084\)](#).
- You cannot store specific numeric qualities or sub-qualities in a calculation formula. You can only set a good or bad data quality in the Calculation collector; that is you can store Good for NonSpecific (when quality > 0 in the calculation formula) or Bad for CalcFailed (when quality = 0 in the calculation formula).
- By design Calculation collector manages good quality values only.

About the Tags Used by the Calculation Collector

The Calculation collector uses the following types of Historian tags in a calculation:

- **One or more source tags:** These tags are used in the calculation formula.
- **One or more trigger tags:** These tags trigger the calculation. Triggers can be [polled \(schedule-based\) \(on page 2112\)](#) or [unsolicited \(event-based\) \(on page 2114\)](#).
- **A single destination tag:** This tag stores the result of the calculation. It is also called a calculation tag. It must be different from the source tags of the calculation. However, a destination tag can be a source tag for another calculation.

The following image shows how you can use the Calculation collector to perform a more complex calculation with several tags and multiple calculations resulting in one output tag. It also shows how the output of one calculation can be used as an input to another.



Workflow for Using the Calculation Collector

After you have added an instance of the Calculation collector, to perform a calculation using the collector, you must perform the following steps:

Step Number	Description	Notes
1	<p>Create a tag administrative security group (on page 291). In addition to defining the iH Tag Admins who have the power to create, modify, and remove tags, you can also define individual tag level security to protect sensitive tags.</p>	<p>This step is required to prevent a user from intentionally or unintentionally launching malicious VBScript code. For example, if a user connected to the data archiver created a calculation tag to file system object, that user could potentially delete all the files on your hard drive. To pre-</p>

Step Number	Description	Notes
		vent this, implement tag-level security.
1	Configure the Calculation collector (on page 2101) .	This step is required only if you want to change the default values for collector-specific parameters.
2	<p>Create the source and destination tags (on page 2099). To do so, you can add a tag manually using Historian Administrator (on page 2057) or the Web Admin console (on page 2059). Or, you can copy a tag (on page 2060).</p> <div data-bbox="613 909 1008 1268" style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note: You cannot browse a Calculation collector through the Add Tags From Collector window in Historian Administrator.</p> </div>	This step is required.
3	Assign a trigger to the destination tag (on page 2114) .	This step is required only if the tag is unsolicited (that is, event-based).
4	Define the calculation formula (on page 2118) .	This step is required.

Configure the Calculation Collector

1. Install [the Historian server \(on page 104\)](#) and [collectors \(on page 142\)](#).
2. Create an instance of the collector using [Configuration Hub \(on page 479\)](#) or the [RemoteCollectorConfigurator utility \(on page 797\)](#).

1. To configure the collector using Configuration Hub:

- a. [Access Configuration Hub \(on page 336\)](#).
- b. Select **Collectors**, and then select the Calculation collector instance that you want to configure.
The fields specific to the collector instance appear in the **DETAILS** section.
- c. Enter values as specified in the following table.

Field	Description
Calculation Timeout (sec)	The maximum time a calculation must be performed before being terminated. The default value is 10 seconds. If the calculation takes longer, it is canceled, and a bad data quality sample is stored in the destination tag with a subquality, calculation error.
Max Recovery Time (hr)	The maximum time, in hours till now, that the collector will attempt to restore data. This is applicable only to event-based tags. The default value is 4 hours. If you want to disable automatic calculation of the tag, set the value of this field to 0.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

- d. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).
- e. Restart the collector.

2. To configure the collector using Historian Administrator:

- a. [Access Historian Administrator \(on page 823\)](#).
- b. On the **Main** page, in the **Collectors** section, double-click the collector that you want to configure. Alternatively, you can select **Collectors**, and then select the collector from the **Collectors** pane.

The **General** section of the collector appears, displaying the properties of the collector.

- c. Select **Configuration**, and then enter values as described in the following table.

Field	Description
Calculation Timeout (sec)	The maximum time a calculation must be performed before being terminated. The default value is 10 seconds. If the calculation takes longer, it is canceled, and a bad data quality sample is stored in the destination tag with a subquality, calculation error.
Max Recovery Time (hr)	The maximum time, in hours till now, that the collector will attempt to restore data. This is applicable only to event-based tags. The default value is 4 hours. If you want to disable automatic calculation of the tag, set the value of this field to 0.

- d. Pause and resume the data collection. Or restart the collector.

The collector instance is configured.

Recalculate Tag Values

Recalculate Tag Values Using Configuration Hub

When the connection between the collector and the Historian server is lost, the collector buffers data. When the connection is lost, the buffered data is sent to the Historian server. When the buffered data arrives, the timestamps are earlier than the most recent calculation timestamp. Since the timestamp is earlier, polled calculations are not performed again with the new data (unlike the unsolicited calculations). Hence, it is possible that calculations performed for tags during and after the connection loss might not be entirely accurate. Therefore, after the Historian server restores a lost connection, you may want to manually recalculate tag values. The recalculated data will use the most accurate values in calculations.



Note:

If you want to disable the automatic recalculation, set the **Max Recovery Time** to 0 in the **Configuration** section of the **Collector Maintenance** page of the collector.

Recalculate Tag Values Manually

When the connection between the collector and the Historian server is lost, the collector buffers data. When the connection is lost, the buffered data is sent to the Historian server. When the buffered data arrives, the timestamps are earlier than the most recent calculation timestamp. Since the timestamp is earlier, polled calculations are not performed again with the new data (unlike the unsolicited calculations). Hence, it is possible that calculations performed for tags during and after the connection loss might not be entirely accurate. Therefore, after the Historian server restores a lost connection, you may want to manually recalculate tag values. The recalculated data will use the most accurate values in calculations.

**Note:**

If you want to disable the automatic recalculation, set the **Max Recovery Time** to 0 in the **Configuration** section of the **Collector Maintenance** page of the collector.

1. [Access Historian Administrator \(on page 823\)](#).
2. On the **Main** page, in the **Collectors** section, double-click the collector whose tag values you want to recalculate. Alternatively, you can select **Collectors**, and then select the collector instance from the **Collectors** section.
The **General** section of the collector appears, displaying the properties of the collector.
3. Select **Recalculate**.
The **Recalculate Tags For <collector name>** window appears.

4. Provide values as described in the following table.

Field	Description
Start Time	Enter the start date and time. Tag values calculated after this date and time will be recalculated.
End Time	Enter the end date and time. Tag values calculated until this date and time will be recalculated.
Tags to Recalculate	Specify whether you want to recalculate values for all the tags added in the collector or just the

Field	Description
	selected tags. If you select Recalculate Selected Tags Only , the Tag Name and Description fields are enabled.
Tag Name and Description	Enter the search criteria to filter out the tags whose values you want to recalculate. These fields are enabled only if you select Recalculate Selected Tags Only . After you select Browse , the search results appear in the Browse Results section.

5. Select **Recalculate**.

A message appears, asking you to confirm that you want to recalculate the data.

6. Select **OK**.

The tags values are recalculated.

Using the Calculation Collector

Write Data to an Arbitrary Tag

If the tags that you want to specify are also used as trigger tags or source tags of a calculation, ensure that the Calculation collector does not read the tag data before you add the tag. To do so:

1. Access the `ShouldPreReadData` registry key under `HKEY_LOCAL_MACHINE\Software\Intellution, Inc.\iHistorian\Services\CalculationCollector\`.
2. Create a DWORD named `ShouldPreReadData`, and set its value to zero.
3. Restart the collector.

You can write data to an arbitrary tag in the Historian archive through the `AddData` function. This function is used in a calculation formula to write values, errors, time stamps and qualities of one or more tags to the Historian archive.

Use the following syntax to write data to an arbitrary tag:

```
errs = AddData(TagNames, Values, Timestamps, Qualities)
```

The following table provides information on the parameters.

Parameter	Description
TagNames	Identifies the names of the tags. A value is required, and must exist in the archive to which you want to send the tag data. You can provide a single tag name or an array of tag names, enclosed in double quotation marks.
Values	Identifies the values of the tags. A value is required, and must be a single value or an array of values, depending on whether the tag name is a single name or an array. Values must be enclosed in double quotation marks. You can enter only a single value for each tag name.
Timestamp	Identifies the timestamp of the tag data. Enter an absolute time value, enclosed in double quotation marks ("24/12/20242:32:15 PM"). If you do not want to enter a value, enter NULL, and the current time will be considered. Do not enter a future timestamp.
Qualities	Identifies the quality of the tag data. Enter an integer from 0 to 100, with 0 indicating bad quality and 100 indicating good quality.

**Tip:**

You can refer to [Examples of Using the AddData Function \(on page 2107\)](#). For information on the status codes and their descriptions, refer to [Status Codes of the AddData Function \(on page 2109\)](#).

Examples of Using the AddData Function

This topic provides examples of using the AddData function.

Writing a Single Tag Value

The following example is used to write a single value, the current time, and a good quality value to a single tag.

```
errs = AddData("Bucket Brigade.UInt4", 9, "Now", 100)
```

Writing an Array of Tags

The following example is used to write an array of tags and their values.

```
Dim Tags(3)
Tags(0) = "Bucket Brigade.Boolean"
```

```
Tags(1) = "Bucket Brigade.Int4"  
Tags(2) = "Bucket Brigade.Real8"  
Tags(3) = "Bucket Brigade.String"  
  
Dim Values(3)  
Values(0) = True  
Values(1) = 5  
Values(2) = 172.3  
Values(3) = "Hello, World"  
  
errs = AddData(Tags, Values, Null, Null)
```

Writing Timestamps and Qualities

The following example is used to write an array of tags and their values in addition to timestamp and quality values.

```
Dim Tags(3)  
Tags(0) = "Bucket Brigade.Boolean"  
Tags(1) = "Bucket Brigade.Int4"  
Tags(2) = "Bucket Brigade.Real8"  
Tags(3) = "Bucket Brigade.String"  
  
Dim Values(3)  
Values(0) = True  
Values(1) = 5  
Values(2) = 172.3  
Values(3) = "Hello, World"  
  
Dim Timestamps(3)  
Timestamps(0) = "Today"  
Timestamps(1) = "Now"  
Timestamps(2) = "Yesterday"  
Timestamps(3) = "24/12/2004 2:32:15 PM"  
  
Dim Qualities(3)  
Qualities(0) = 100  
Qualities(1) = 0  
Qualities(2) = 100
```

```

Qualities(3) = 0

Dim errs

errs = AddData(Tags, Values, Timestamps, Qualities)

```

Status Codes of the AddData Function

This topic describes the status codes that appear when you use the AddData function. These status codes are stored in the `Errs` output variable as an array of status codes, one for each tag. The following table describes the status codes.

Status Code	String	Description
0	<code>ihSTATUS_OK</code>	The values have been successfully written to the tags.
-1	<code>ihSTATUS_FAILED</code>	The operation has failed.
-2	<code>ihSTATUS_API_TIMEOUT</code>	The operation has timed out while connecting to Historian.
-3	<code>ihSTATUS_NOT_CONNECTED</code>	The Calculation collector cannot connect to Historian.
-4	<code>ihSTATUS_INTERFACE_NOT_FOUND</code>	You cannot connect to the Calculation collector.
-5	<code>ihSTATUS_NOT_SUPPORTED</code>	The write operation is not supported.
-6	<code>ihSTATUS_DUPLICATE_DATA</code>	The write operation has created duplicate data in the archive.
-7	<code>ihSTATUS_NOT_VALID_USER</code>	The username used to connect to the Historian archive is not valid.
-8	<code>ihSTATUS_ACCESS_DENIED</code>	The username used to connect to Historian does not have write access to the archive.
-9	<code>ihSTATUS_WRITE_IN_FUTURE</code>	The timestamp that you have entered is set to a time in future.

Status Code	String	Description
-10	ihSTATUS_WRITE_ARCH_OFFLINE	The archive is currently offline.
-11	ihSTATUS_ARCH_READONLY	The archive is set to read-only.
-12	ihSTATUS_WRITE_OUTSIDE_ACTIVE	An attempt has been made to write data to a time before the archive has been created.
-13	ihSTATUS_WRITE_NO_ARCH_AVAIL	No archive is available for writing.
-14	ihSTATUS_INVALID_TAGNAME	The tag names that you have entered do not exist in the archive.
-15	ihSTATUS_LIC_TOO_MANY_TAGS	You have attempted to add more tags than the current license allows.
-16	ihSTATUS_LIC_TOO_MANY_USERS	There are currently too many users connected to the archive.
-17	ihSTATUS_LIC_INVALID_LIC_DLL	The Historian license is expired or invalid.
-18	ihSTATUS_NO_VALUE	You have not entered a tag value.
-19	ihSTATUS_DUPLICATE_INTERFACE	Two collectors with the same name exist.
-20	ihSTATUS_NOT_LICENSED	The Historian license is not activated.
-21	ihSTATUS_CALC_CIRC_REFERENCE	A circular reference has been entered in the calculation formula.
-22	ihSTATUS_BACKUP_EXCEEDED_SPACE	The archive has reached the Minimum Hard Drive Space setting, and no new archives are being created.
-23	ihSTATUS_INVALID_SERVER_VERSION	The archive is not compatible with the Calculation collector.

Status Code	String	Description
-24	ihSTATUS_DATA_RETRIEVAL_- COUNT_EXCEEDED	There are too many data points to retrieve.

Creating Triggers

Types of Triggers

You can create the following types of triggers for a calculation:

- **Polled or scheduled:** Used to trigger a calculation based on a scheduled time interval. For example, you can calculate the average value of tag data collected every hour.

The polled type trigger functions the same as the other collectors. Although Historian internally optimizes calculation execution times, the data for polled tags is timestamped on the data collection interval. For example, if the calculation engine is unable to process the polled triggers as scheduled, the calculations will be executed later, but with data interpolated back to the scheduled time. If there are too many triggers to be processed, some triggers will be dropped and no samples are logged for that calculation time.

For information on creating a polled trigger, refer to [Create a Polled Trigger \(on page 2112\)](#).

- **Unsolicited or event-based:** Used to trigger a calculation based on an event. For example, you can calculate the average value of tag data when the data exceeds a certain value.

When you set an event-based trigger, you must also set up a dependency list of one or more tags. Event-based triggers will keep calculations as up to date as possible. They are also useful when you want to do on-demand calculations. You can use a trigger tag that is written to by an external program or operation.

If you want to perform raw sample replication you would use an event-based trigger. To retrieve data from a tag, use the formula:

```
Result=CurrentValue("Tag1")+CurrentValue("Tag2")
```

If you are using recovery mode, all referenced tags in an unsolicited calculation must be listed as trigger tags because recovery will be performed only for the configured trigger tags.

Event-based triggers have a dependency list of trigger tags. The trigger fires whenever there is a data change for the trigger tag (for example, changes in the quality and value of a trigger tag). The

value of a trigger tag can change when the tag exceeds the collector compression (if you enabled collector compression).

The calculation is processed each time any tag in the dependency list changes. If you have multiple tags in the list and they change even one millisecond apart, then you will have multiple events, and the calculation formula will be processed for each.

However, the following actions do not trigger a calculation:

- Deletion of a tag that is in the dependency list.
- Re-addition of a tag in the dependency list.

The calculation is triggered at the same time as the timestamp of the sample in the trigger tag. The values of all other tags in the formula are interpolated forward to this time so that the timestamps of all input tags are the same. Even if these are sequential events, they have the same timestamp. The calculation time becomes the timestamp for the sample stored in the destination tag.

Event-based triggers have a collection interval. The Calculation collector notifies the archiver not to send notification of changes to trigger tags any faster than the collection interval setting.

For information on creating an unsolicited trigger, refer to [Create an Unsolicited Trigger \(on page 2114\)](#).

Create a Polled Trigger

1. To create a poller trigger using Configuration Hub:
 - a. [Access Configuration Hub \(on page 336\)](#).
 - b. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
 - c. From the list of tags, select the Calculation tag (say, tag 2).
 - d. In the **Collection Options** section, select **Polled** from **Collection Type**, and specify.
 - e. Set the **Collection Interval Value** and **Collection Offset** values. For example, if you want to set a trigger every day, set these values to 24 hours and 8 hours, respectively.
 - f. In the upper left corner of the page select **Save**.
The triggers are created.
2. To create a polled trigger using Historian Administrator:

- a. [Access Historian Administrator \(on page 823\)](#).
- b. Select **Tags**.
- c. In the **Tags** section, select the tag to which you want to apply the trigger.
- d. In the **Collection** section, select **Polled from the Collection Type**.
- e. Set the **Collection Interval** and **Collection Offset** values. For example, if you want to set a trigger every day, set these values to 24 hours and 8 hours, respectively. Depending on the trigger that you want to set, enter the appropriate VBScript code in the **Calculation** pane. For examples, refer to [Examples of Scheduling Polled Triggers \(on page 2113\)](#).
- f. Select **Update**.

Examples of Scheduling Polled Triggers

You can schedule calculations using polled triggers, as shown in the following examples.

Scheduling a Trigger every Monday

Since Monday is the second day of a week, enter the following VBScript code in the **Calculation** pane:

```
Dim curDate curDate=CurrentTime
IF (Weekday(curDate))=2 THEN
Result=50 <Place your calculation here>
END IF
```

Notice that the `CurrentTime` built-in function is used in this example instead of `Now`.

Scheduling a Trigger on the First Day of Every Month

Enter the following VBScript code in the **Calculation** pane:

```
Dim curDate curDate=CurrentTime
IF (day(curDate))=1 THEN
Result=50 <Place your calculation here>
END IF
```

Notice that the `CurrentTime` built-in function is used in this example instead of `Now`.

Scheduling a Trigger on the Last Day of Every Month

Enter the following VBScript code in the **Calculation** pane:

```
Dim curDate curDate=CurrentTime
IF (day(curDate))=1 THEN
```

```
Result=50 <Place your calculation here>
END IF
```

Notice that the `CurrentTime` built-in function is used in this example instead of `Now`.

Example 5: Creating a Controlled Sequence of Polled Tags Using a Collection Offset

A controlled sequence is a calculation that is based on the result of another calculation. The following is an example of how to configure a controlled sequence of polled tags by using the collection offset. The collection offset is greater than 0 in this example.

A tag named `SumOfData` has a Collection Interval of 60 seconds and the Collection Offset of 0 milliseconds.

`SumofData` performs the first calculation:

```
Result = CurrentValue("DataTag1") + CurrentValue("DataTag2")
```

Another tag, named `CorrectedUnits`, uses a Collection Interval of 60 seconds, but a Collection Offset of 1000 milliseconds.

`CorrectedUnits` fires and performs another calculation based on the output of the first calculation:


```
Result = CurrentValue("SumOfData") *.0001
```

Create an Unsolicited Trigger

This topic describes how to create an unsolicited trigger for a calculation, and how to set up a dependency list:


1. Create the tag that you want to use to create a trigger (say, tag1).
 2. Create another tag in the Calculation collector whose value you want to update based on the trigger (say, tag2).
 3. Ensure that the Calculation collector is running.
1. To create an unsolicited trigger using Configuration Hub:
 - a. [Access Configuration Hub \(on page 336\)](#).
 - b. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
 - c. From the list of tags, select the Calculation tag (say, tag 2).

- d. In the **Collection Options** section, select **Unsolicited** from the **Collection Type**, and specify an interval.
 - e. Select Calculation Triggers and select  .
The Calculation Triggers window appears.
 - f. Search for tags or select tags from the list as trigger tags.
 - g. You can remove the selected tags by selecting X from the Selected Tags list.
 - h. Select **Insert Trigger**.
The trigger tag count will be displayed.
 - i. In the upper left corner of the page select **Save**.
The triggers are created.
2. To create an unsolicited trigger using Historian Administrator:
- a. [Access Historian Administrator \(on page 823\)](#).
 - b. Select **Tags**, and then select the tag to which you want to apply the trigger.
 - c. In the **Collection** section, select **Unsolicited from the Collection Type**, and specify an interval.
 - d. Select **Calculation**.
 - e. Select **Add** to add a trigger.
The **Insert Function** window appears.
 - f. In the **Trigger Tag** field, enter the name of the trigger tag that you want to use in the calculation.
The wizard automatically populates the **Trigger Tag** field and updates the **Function Preview** field, as shown in the following figure:



g. Select **Insert**.

The trigger is added to the **Calculation Triggers** section.



In addition, the trigger list appears when using the **Insert Function** window to build a calculation formula for an event based tag.

h. Select **Update**.

The unsolicited trigger is created.

Examples of Scheduling Unsolicited Triggers

Example1: Using One Trigger Tag in a Formula

The following is an example of an event-based calculation with one trigger tag:

```
Result=CurrentValue("Tag2") + CurrentValue("Tag3")
```

You can configure `Tag1`, which is not in the formula, to be the calculation trigger for this example. `Tag2` and `Tag3` are not trigger tags. Trigger tags do not have to reside in the formula. There is no relation between formula tags and trigger tags. However, if you are planning to use recovery mode, you want all formula tags to be triggers.

Example 2: Using Multiple Trigger Tags in a Formula

The following is an example of an event-based calculation with multiple trigger tags:

```
Result=CurrentValue("Tag1") + CurrentValue("Tag2")
```

Configure `Tag1` and `Tag2` to be the calculation triggers for this example.

Example 3: Creating a Controlled Sequence of Unsolicited Tags Using Trigger Tags

A controlled sequence is a calculation that is based on the result of another calculation. The following is an example of how to create a controlled sequence of unsolicited tags using trigger tags. In this example, you create a calculation tag that is based on the result of another calculation tag.

For `CalcTag1`, the calculation is as follows:

```
Result = CurrentValue("TagA") + CurrentValue("TagB")
```

`TagA` and `TagB` are the calculation triggers for `CalcTag1`:

For `CalcTag2`, the calculation is as follows:

```
Result = CurrentValue("CalcTag1") * CurrentValue("TagC")
```

`CalcTag1` is the calculation trigger for `CalcTag2`.

Calculation Formulas

About Calculation Formulas

To perform a calculation using the Calculation collector, you must define the calculation formula. You can do so in one of the following ways:

- [Using the Insert Function wizard \(on page 2123\)](#), which helps you use any of the [built-in functions \(on page 2127\)](#) or [create your own function \(on page 2125\)](#).
- [Entering the syntax of the formula directly in the form of a VBScript code \(on page 2121\)](#).

Before you create calculation formulas, refer to the [general guidelines \(on page 2119\)](#).

There are two predefined global values called Result and Quality. These global values control the value and quality of the output sample. If the Result is not set in the formula, then no sample is stored.

General Guidelines for Defining a Calculation Formula

This section provides guidelines that you must follow when defining a calculation formula.

Identify Time Intensive Calculations

Use the `Calculation Execution Time` property of each tag to identify time-intensive queries. In Historian Administrator, look for the **Execution Time** on the **Calculation** section for an estimate of how long, on average, it takes for the calculation per tag (starting from the time the collector was started).

You can also include that column when you export tags to Excel using the Excel Add-In feature. For information, refer to [Exporting Tags \(on page 2746\)](#).

You can also include that column (`AverageCollectionTime`) when you query the `ihTags` table using the Historian OLE DB Provider. Sorting by this column will let you find them fast.

Troubleshoot Issues with Large Configurations

If the timestamps of your raw samples appear slightly old, do not assume that the collector has stopped working. It is possible that the collector is just running behind.

For instance, if you have a report rate of 15,000, but the newest raw sample that you see is 20-30 minutes old, wait for 1-2 minutes, and review the newest raw sample again. If the collector stopped, the newest raw sample will be unchanged. If it did change, then the engine is still running, but is lagging behind. If that happens, check if the collector overrun count is increasing. If yes, the collector is dropping samples, and you must decrease the load.

Error Handling in VBScript

Start each script with the `On Error Resume Next` statement so that errors are trapped. If you use this statement, the script runs even if a run-time error occurs. You can then implement error handling in your VBScript.

It is a good practice to include statements in your VBScript that catch errors when you run the script. If there is an unhandled error, a value of 0 with a bad data quality is stored. When you catch an error in the VBScript, consider including a statement in your calculation that sets the `Quality=0` when the error occurs. (The 0 value means that the quality is bad.) If you do not specifically include this setting in your script, Historian stores a good data quality point (`Quality=100`), even if an error has occurred in your formula. If `Quality=100` is not appropriate for your application, consider setting the quality to 0.

You cannot use the `On Error GoTo Label` statement for error handling, as it is not supported in VBScript. As a workaround, you can write code in the full Visual Basic language and then place it in a `.DLL` so that you

can call it from within your VBScript using the `CreateObject` function. For examples of calculations that use the `CreateObject` function, refer to [Examples of Calculation Formulas \(on page 2138\)](#).

Unsupported VBScript Functions

You can use any VBScript syntax to build statements in a calculation formula with the exception of the following functions:

- `MsgBox`
- `InputBox`

Milliseconds not Supported in VBScript

The `CDate()` function does not support the conversion of a time string with milliseconds in it. Whenever you use the `CDate()` function, a literal time string, or a time string with a shortcut, do not specify milliseconds in the time criteria. Milliseconds are not supported in VBScript.

You cannot use milliseconds in times passed into built-in functions such as the `PreviousTime` and `NextValue` functions. For example, you cannot loop through raw samples with millisecond precision.

Notes on VBScript Time Functions

Using the VBScript time functions such as `Now`, `Date`, or `Time` can lead to unexpected results, especially in recalculation or recovery scenarios. To avoid these issues, use the `CurrentTime` built-in function provided by Historian, instead of `Now`, `Date`, or `Time`. For example, the VBScript `Now` is always the clock time of the computer and is likely not useful when recalculating or recovering data for times in the past. However, the "Now" time shortcut is equivalent to `CurrentTime` and can be used as input to the other built in functions.

Using Quotation Marks in VBScript

If you want to use quotation marks in a tag name, you must insert a double quotes for each quotation mark that you want to use, as required for proper VBScript syntax. For example, if you want to get the current value of a tag named `TagCost"s`, you must enter:

```
Result = CurrentValue("TagCost""s")
```

In this example, note the double quotation marks that appear before the letter `s` in the `TagCost"s` name in the formula.

Avoiding Circular References in VBScript

Do not use circular references in calculation formulas. For instance, if the tag name is `Calc1`, a formula with a circular reference would be `Result=CurrentValue("Calc1")`. Whether the tag is polled or unsolicited, you get a bad value back using the circular reference.

Uninterrupted Object Method Calls

Object method calls are not interrupted. It is possible to exceed the Calculation Timeout setting if you have a method call that takes a long time to execute. The Calculation Timeout error still occurs, but only after the method completes.

Help for VBScript

You can get detailed Help for VBScript by referencing the Microsoft documentation on the MSDN web site. A *VBScript User's Guide and Language Reference* is available here: <http://msdn.microsoft.com/en-us/library/t0aew7h6.aspx>

Avoiding Deleted Tags

You can reference a deleted tag in a calculation formula, without an error appearing. For instance, you could enter a formula such as `Result=CurrentValue("DeletedTag")`, where `DeletedTag` is the name of the deleted tag. You can do this because when you delete a tag, Historian removes deleted tags from the Tag Database (so you cannot browse for it), but it retains the data for that tag in the archive.

However, it is recommended that you do not reference deleted tag names in your calculation formulas, because if the archive files are removed with the data for the deleted tag, the calculation will not work properly.

Create a Calculation Formula Using a VBScript Code

This topic describes how to create a calculation formula by entering a VBScript code. You can also [create a calculation formula using the Insert Function wizard \(on page 2123\)](#).



Important:

If a tag contains bad data quality, you cannot store its value through a calculation formula. For example, if your VBScript includes: `Result = 7 Quality = 0`, Historian does not store the 7, it stores 0.



Tip:

For examples, refer to [Examples of Scheduling Polled Triggers \(on page 2113\)](#) and [Examples of Scheduling Unsolicited Triggers \(on page 2117\)](#).

Create the tag that you want to use to store the calculation results. You can create the tag manually using [Configuration Hub \(on page 473\)](#), [Historian Administrator \(on page 2057\)](#) or the [Web Admin console \(on page 2059\)](#). Or, you can [copy a tag \(on page 2060\)](#).

1. To create a calculation formula using Configuration Hub:

- a. [Access Configuration Hub \(on page 336\)](#).
- b. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
- c. Select a Calculation tag, right-click or select more options, and then select **Calculation**.
The calculation editor appears.
- d. Enter the VB script in the editor.
- e. To test the function, select .
A message appears, stating whether the syntax is correct.
- f. In the upper-left corner of the page, select **Save**.
The calculation formula is created.

2. To create a calculation formula using Historian Administrator:

- a. [Access Historian Administrator \(on page 823\)](#).
- b. Select **Tags**, select the tag for which you want to create a calculation formula, and then select **Calculation**.
- c. In the **Calculation Triggers** section, select **Add**.
The **Insert Function Wizard** window appears.
- d. Under **Select Function**, in the **Type** field, select **Add A Calculation Trigger**.
- e. Under **Tag Browse Criteria**, enter the search criteria to find the tag.
The search results appear in the **Browse Results** section.
- f. Select the tag that you want to add, and then select **Insert**.
- g. In the **Calculation** field, enter the calculation formula using the VBScript syntax.
- h. To verify that the syntax is correct, select **Test**.
A message appears, stating whether the syntax is correct.

Create a Calculation Formula Using the Pre-built Functions

This topic describes how to create a calculation formula using the pre-built functions. You can also [create a calculation formula using a VBScript code \(on page 2121\)](#).

For information on a list of the available types and associated functions, refer to [Types of Functions Supported \(on page 2135\)](#). For information on each pre-defined function, refer to [Built-In Functions \(on page 2127\)](#). In addition to the built-in functions, you can create [your own customized functions \(on page 2136\)](#).

1. Create the tag that you want to use to store the calculation results. You can create the tag manually using [Configuration Hub \(on page 473\)](#), [Historian Administrator \(on page 2057\)](#) or the [Web Admin console \(on page 2059\)](#). Or, you can [copy a tag \(on page 2060\)](#).
2. Access the advanced options of the collector, and then disable the **On-line Tag Configuration Changes** option using [Historian Administrator \(on page 2057\)](#). In [Configuration Hub \(on page 473\)](#) this property is available in Collector Options section. If you do so, each time you update a calculation formula, the collector does not reload tags.

1. To create a calculation formula using Configuration Hub:

- a. [Access Configuration Hub \(on page 336\)](#).
- b. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
- c. Select a calculation tag, right-click or select more options, and then select **Calculation**.
The calculation editor appears.
- d. In the **CALCULATION** section, remove `Null` (and retain the `Result =`).
- e. In the Calculation editor, place the cursor in the location where you want to insert the pre-built function.
- f. In the **DETAILS** section, under **Pre-Built Functions**, in the **Function Type** field, select a function type.
Depending on the function type you have selected, a list of functions appears in the **Function** field.
- g. In the **Function** field, select a function.
Based on the selected function, the related fields will be displayed.
- h. Enter values in the other fields that appear after selecting a function.

i. In the **Input Tag** field, select , and then select the tag where applicable.
The function preview appears below the calculation editor.

j. Select **Insert Function**.
The function is inserted at the cursor position.

k. To test the function, select .
A message appears, stating whether the syntax is correct.

l. In the upper-left corner of the page, select **Save**.
The calculation formula is created.

2. If you want to create a calculation formula using Historian Administrator:

a. [Access Historian Administrator \(on page 823\)](#).

b. Select **Tags**, select the tag for which you want to create a calculation formula, and then select **Calculation**.

c. In the **Calculation** section, remove `Null` (retain `Result =`).



Tip:

Avoid selecting other tags until you save your changes or you will lose your code changes.

d. Select **Wizard**.
The **Insert Function Wizard** window appears.

e. Under **Select Function**, select values in the available fields, and then select **Insert**.

f. If you want to perform an unsolicited (also called event-based) calculation, in the **Type** field, select **Add A Calculation Trigger**. Search and select the tag that you want to add, and then select **Insert**.

The calculation formula is created.

g. To verify that the syntax is correct, select **Test**.
A message appears, stating whether the syntax is correct.

Create a User-Defined Function

This topic describes how to create your own function to use in a calculation formula. For more information, refer to [User-defined Functions \(on page 2136\)](#). You can also use any of the [built-in functions \(on page 2127\)](#).

Create the tag that you want to use to store the calculation results. You can create the tag manually using [Configuration Hub \(on page 473\)](#), [Historian Administrator \(on page 2057\)](#) or the [Web Admin console \(on page 2059\)](#). Or, you can [copy a tag \(on page 2060\)](#).

1. To create a user-defined function using Configuration Hub:

- a. [Access Configuration Hub \(on page 336\)](#).
- b. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
- c. Select a calculation tag, right-click or select more options, and then select **Calculation**.
The calculation editor appears.
- d. In the **CALCULATION** section, remove `Null` (retain `Result =`).
- e. In the calculation editor, place the cursor in the location where you want to insert the user-defined function.
- f. In the **DETAILS** section, under **User Defined Functions**, select .
The **Add/Edit User Defined Functions (UDF)** window appears.
- g. Select **Add New**.
A function is created with the following naming convention: `UserFunction<number>`. The same function is used in the function editor. You can change the function name by entering the new name in the function editor and selecting **Update UDF**.
- h. Enter the VB script for the function. Or, if you want to use a pre-built function, select the function type and function in the respective fields under **Pre-Built Functions**. And, enter values in the other fields that appear after selecting a function.
The function appears in the function preview below the function editor.
- i. Select **Insert Preview**.
The function is included in the function editor at the cursor position.
- j. To test the function syntax, select .

A message appears, stating whether the function syntax is correct.

- k. Select **Update UDF**.

The user-defined function is created.

- l. To use the function in the calculation formula, select **Insert UDF**.

The function is inserted in the calculation formula at the cursor position.

- m. To test the calculation formula, select .

A message appears, stating whether the syntax is correct.

- n. In the upper-left corner of the page, select **Save**.

The calculation formula is created.

- 2. To create a user-defined function using Historian Administrator:

- a. In Historian Administrator, select **Tags**, select the tag for which you want to create a calculation formula, and then select **Calculation**.

- b. In the **Calculation** section, remove `Null` (retain `Result =`).



Tip:

Avoid selecting other tags until you save your changes or you will lose your code changes.

- c. Select **Functions**.

The **User Defined Functions** window appears.

- d. Select **New**.

The **Edit Function** window appears.

- e. Define the function.

You can build formulas using the wizard, or create it manually by entering functions in the **Edit Function** box. For information, refer to [User-defined Functions \(on page 2136\)](#).

- f. Select **Syntax** to check for errors.

- g. Select **Update**.

Your function appears in the list, and is available for use in other calculations as well.

- h. To use the function, select **Insert Function**.

The function is inserted in your calculation formula.

Built-in Functions

This topic describes the built-in functions that you can use to create a calculation formula. You can also create [your own calculation function \(on page 2136\)](#).



Note:

- In this table, `Time` refers to the actual time; this time can include absolute and relative time shortcuts. Refer to the [Date/Time Shortcuts \(on page 2138\)](#) section for more information.
- You cannot control the timestamp of the stored sample. It is determined by the triggering tag or polling schedule.
- You cannot use microseconds for any of the built-in calculation functions.

For all the functions that retrieve previous values, it is similar to performing a `RawByNumber` query with a count of 1 and direction of backward. A less-than operation (not less-than-or-equal-to) is used on the timestamp to get the sample. Similarly, for all the functions that retrieve next values, it is similar to performing a `RawByNumber` query with a count of 1 and direction of forward. A greater-than operation (not greater-than-or-equal-to) is used on the timestamp to get the sample.

Function Name	Description
<code>CurrentValue(<tag name>)</code>	The value of the tag, interpolated to the calculation execution time. The <code>CurrentValue</code> function returns 0 if the quality is 0 (bad quality). This occurs if you initialized it to 0, or if a previous call failed.
<code>CurrentQuality(<tag name>)</code>	The current quality of the tag (0 for bad quality and 100 for good quality).
<code>CurrentTime</code>	The calculation execution time, which becomes the timestamp of the stored value. For real time processing of polled tags, the calculation execution time is the time when the calculation is triggered. For unsolicited tags, the calculation execution time is the timestamp delivered with the subscription.

Function Name	Description
	<div data-bbox="375 310 1414 485" style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;">  Note: When a calculation is performed, the timestamp of the result is the time that the calculation has begun, not the time that it completed. </div> <p data-bbox="370 520 1414 596">For recovery of polled or unsolicited tags, the calculation execution time is the time when the calculation would have been performed if the collector were running.</p>
Previous-Value(<tag name>, Time)	The tag value of the raw sample prior to the current time.
Previous-Quality(<tag name>, Time)	The quality of the tag (0 for bad quality and 100 for good quality) prior to the current time.
Previous-GoodValue(<tag name>, Time)	The latest good value of the raw sample prior to the current time.
Previous-GoodQuality(<tag name>, Time)	The good quality of the raw sample prior to the current time.
Previous-Time(<tag name>, Time)	The timestamp of the raw sample prior to the current time.
Previous-GoodTime(<tag name>, Time)	The timestamp of the latest good quality of the raw sample prior to the current time.
NextValue(<tag name>, Time)	The value of the raw sample after the current timestamp.

Function Name	Description
NextQuality(<code><tag name></code> , Time)	The quality of the tag (0 for bad quality and 100 for good quality) after the current time.
NextTime(<code><tag name></code> , Time)	The timestamp of the raw sample after the current timestamp.
NextGoodValue(<code><tag name></code> , Time)	The value of the good raw sample after the current time.
NextGoodQuality(<code><tag name></code> , Time)	The good quality of the raw sample after the current time.
NextGoodTime(<code><tag name></code> , Time)	The timestamp of the good raw sample after the current time.
InterpolatedValue(<code><tag name></code> , Time)	The tag value, interpolated to the time that you enter.
Calculation	Unfiltered calculated data query that returns a single value, similar to the Excel Add-In feature. For a list of the calculation mode, refer to Calculation Modes (on page 1073) .
AdvancedCalculation	Unfiltered calculated data query that returns a single value, similar to the Excel Add-In feature. For a list of the calculation mode, refer to Calculation Modes (on page 1073) .
AdvancedFilteredCalculation	Advanced Filtered calculated data query that returns a single value, similar to the Excel Add-In feature.
FilteredCalculation	Filtered calculated data query that returns a single value, similar to the Excel Add-In feature.
LogMessage(<code>string_message</code>)	Allows you to write messages to the Calculation collector or the Server-to-Server collector log file for debugging purposes. The collector log files are located in the <code>Historian\LogFiles</code> folder.

Function Name	Description
	 Note: The <code>LogMessage</code> function is the only function that does not appear in the wizard.
<code>GetMultiFieldValue(Variable, <field name>)</code>	<p>Returns the value of the field that you have specified. The variable contains the current value of all the fields of a multi-field tag. Before using this function, you must read the tag into a variable, using the <code>CurrentValue()</code> function. You can then use the <code>GetMultiFieldValue</code> function to access the value of the field.</p> <p>The value of the field that you enter must be the same as the name of the field in the user defined type. If the field name is not found, a null value is returned.</p>
<code>GetMultiFieldQuality(Variable, <field name>)</code>	<p>Returns the quality (0 for bad quality and 100 for good quality) of the field that you have specified. The variable contains the current value of all the fields of a multi-field tag. Before using this function, you must read the tag into a variable, using the <code>CurrentValue()</code> function. You can then use the <code>GetMultiFieldValue</code> function to access the value of the field.</p> <p>The value of the field that you enter must be the same as the name of the field in the user-defined type. If the field name is not found, a null value is returned.</p> <p>If the user-defined type can store individual quality, you get the field quality. Otherwise, you get the sample quality.</p>
<code>SetMultiFieldValue(Variable, <field name>, Value, Quality)</code>	<p>Sets the value and the quality for the field that you have specified.</p> <p>You can use this function to construct a multifield value containing values for each field, and then use the <code>result=</code> syntax to store the value in Historian.</p>

Counting the Number of Bad Quality Samples

The following example shows how to loop through samples of a tag named C2 to count the number of bad quality samples.

```
Dim count, starttime, endtime, tagquality count=0

StartTime=CurrentTime EndTime=DateAdd("n",-1,StartTime) Do while StartTime>EndTime

TagQuality=PreviousQuality("C2",StartTime)
```

```

startTime=PreviousTime("C2",StartTime) IF TagQuality=0 THEN

count=count + 1

END IF loop Result=count

```

Counting the Number of Collected Digital 1s For a Tag

The following example counts the number of collected digital 1s for a tag so that, for instance, you can determine how many times a pump is turned ON and OFF.

```

Dim count, starttime, endtime,tagquality,TagValue

count=0

StartTime=CurrentTime

EndTime=DateAdd("h",-1,StartTime)

On error resume next

Do while StartTime>=EndTime

TagValue=PreviousValue("FIX.DI.F_CV",StartTime)

TagQuality=PreviousQuality("FIX.DI.F_CV",StartTime)

startime=PreviousTime("FIX.DI.F_CV",StartTime)

IF TagQuality=100 AND TagValue=1 then

count=count + 1

END IF

loop

Result=count

```

Determining the Trigger When Using Multiple Trigger Tags

The following example shows how to determine which tag triggered the calculation, from a list of two possible trigger tags. The example compares the two trigger tags and determines which one has the newest raw sample. This method of getting the newest raw sample can also be used to determine if a remote collector is sending data or is disconnected from the server.

In this example, archive compression is disabled for both of these tags.

```

dim timetag1

dim timetag2

dim tag1

dim tag2

tag1 = "BRAHMS.AI1.F_CV"

tag2 = "BRAHMS.AI2.F_CV"

```

```

' Get the timestamp of the newest raw sample for tag1:
timetag1 = previousTime(tag1, CurrentTime)

' Get the timestamp of the newest raw sample for tag2:
timetag2 = previousTime(tag2, CurrentTime)

if timetag1 > timetag2 then
' If tag1 triggered me, then:
result = 1 else
' If tag2 triggered me, then:
result = 2
end if

```

Using Array or Multifield Data in Calculation

You can create tags of arrays and multifield types and use the Calculation collector, Server-to-Server collector, Server-to-Server distributor with these tags.

Arrays

To use the Array data as input to a calculation formula you can use the name of the array tag like "Array1" or the individual element of the array like "Array1[4]". For example, if you have an array tag "Array1" of floating point values and a calculation tag "FloatCalc1" of float data type, then you can use the array as input to calculate a float value.

```
result = currentvalue("Array1[4]")+5
```

You can use Calculation() function to read the array tag as shown in the following code.

```
Result = Calculation("Array1","Average","Now 1Minute","Now",Quality)
```

In this example, the calculation tag should be an array tag because the average of an array is an array, not a single value. Each element is averaged over the time range. Since an average of an integer or float array is a floating point value, the calculation tag must be a single or double float array.

If you want to find the minimum of array elements in a given time, then use vbscript code to compute and store the result in a Float tag as shown.

```

if CurrentValue("Array1[0]") < CurrentValue("Array1[1]") then
    Result = CurrentValue("Array1[0]")

```

```

else
    Result = CurrentValue("Array1[1]")
end if

```

Multifield

If you have a user-defined type "MySample" with fields "r;FloatVal" and "r;IntVal" you can create `Tag1` and use the value of one field in an Integer Calc Tag. The destination tag is not a multifield tag.

```

result = currentvalue("Tag1.IntVal")+5

```

Storing Array or Multifield data in Calculation tags

Array

If your calculation tag is an array tag, then you can copy the entire array values into it. For example, you can copy the entire values from `Array1` into `Array2` using the given code.

```

result = CurrentValue("Array1")

```

You can take an array value collected from a field device and adjust the values before storing it in another array tag `Array2` using this code:

```

dim x
x=CurrentValue("Array1")
x(1) = x(1)+10
result = x

```

You can simply construct an array value inside your formula and store it in `Array2`, for example:

```

dim MyArray(2)' The 2 is the max index not the size
MyArray(0)=1
MyArray(1)=2
MyArray(2)=3 result = MyArray

```

Multifield

You can have the collector combine collected data into a multifield tag. Create a calculation `Tag1` using the user-defined Type "MySample," then use this formula to fill in the fields:

```

Dim InputValue, myval,x,y

' get the current value of another multifield tag

InputValue = CurrentValue("tag1")

```

```

' get the values of each of the fields
x = GetMultiFieldValue(InputValue, "IntVal")
y = GetMultiFieldValue(InputValue, "floatval")

' store the field values in this tag
SetMultiFieldValue myval,"IntVal",x,100
SetMultiFieldValue myval,"floatval",y,100

Result = myval

```

Using Array or Multifield data to trigger calculation

Array

You can use the array tag as a trigger tag for your float or array calculation tags. For example, you can use `Array1` as a trigger so that when it changes, the `"CalcArray1"` tag will be updated. You cannot use an individual array element such as `"Array1[3]"` as a trigger, you must use the entire array tag as the trigger tag.

Multifield

You can use a multifield tag as a trigger tag by either using the tagname `"Tag1"` or tagname with the field name `"Tag1.FloatVal"`.

Sending Array or Multifield data to a Remote Historian

Array

You can use the Server to Server Collector or Server to Server Distributor to send array data to a destination Historian. If the destination Historian is version 6.0 or later, you can simply browse the tags and add them.

You cannot send an array to the older versions of archiver (Pre 6.0 versions) as these archivers will store the array tags as a blob data type in the destination and you will not be able to read them. However, you can send individual elements of an array to these archivers, for example, `result = currentvalue("Array1 [4]")`.

Multifield

The destination needs to be Historian 6.0 or above to store a multifield tag but you can send individual fields to a pre Historian 6.0 archiver.

For multifield tags, you must create the User Defined Type manually at the destination

You can write an entire multified tag data sample in one write or you can create multiple tags in the destination, one for each field you want to copy. For example, if you have one tag "Tag1" with two fields "FloatVal" and "IntVal" on a source archiver, then you can create two tags ("Tag1.FloatVal" and "Tag1.IntVal") on the destination.



Note:

If you change a field name or add or remove fields you must update your collection and your destination tags.

Reading and writing a Multifield tag using MultiField functions

The following example shows how to read an entire multifield tag, using the `GetMultiFieldValue` function and to write the value to a field in another tag using the `SetMultiFieldValue` function.

```
Dim CurrMultifieldValue

' Read the value of a multi field tag into a variable
CurrMultifieldValue = CurrentValue("MyMultifieldTag")

' Read the field value of multifield tag into the temporary variable
F1 = GetMultiFieldValue(CurrMultifieldValue, "Temperature Field")

' Perform a calculation on the value
Celcius = (F1 32)/ 9* 5

' Set the calculated value to another field of the multifield tag
SetMultiFieldValue(CurrMultifieldValue, "Temperature Field Celcius", Celcius, 100)

result = CurrMultifieldValue
```

Types of Functions Supported

The following table describes the types of actions supported. All the value functions return a single value.

Type of Action	Available Functions for the Action
Insert a value	<ul style="list-style-type: none"> • Current value • Previous value • Next value • Interpolated value

Type of Action	Available Functions for the Action
Insert a calculation	<ul style="list-style-type: none"> • Unfiltered calculation • Filtered calculation
Insert a timestamp	<ul style="list-style-type: none"> • Time shortcut • Previous value timestamp • Next value timestamp • Current time
Check data quality	<ul style="list-style-type: none"> • Current value quality • Previous value quality • Next value quality
Set data quality	<ul style="list-style-type: none"> • Set Quality Good • Set Quality Bad
Add data value	Value
Insert a tag name	Tagname
Insert an alarm calculation	<ul style="list-style-type: none"> • Previous Alarm • Next Alarm • Get Alarm Property • Set Alarm Property • Add Event • New Alarm • Update Alarm • Return to Normal
Insert a multifeild operation	<ul style="list-style-type: none"> • GetMultiFieldValue • GetMultiFieldQuality • SetMultiFieldValue

User-defined Functions

In addition to the [built-in functions \(on page 2127\)](#), you can create custom calculation functions. After you create a custom calculation function, it is available for use with other calculations as well.

Functions are useful as shortcuts for large blocks of source code. By creating a function out of commonly used calculation formulas, you can save time and effort instead of typing a few lines of calculation formula every time you want to perform the same operation, it is compressed to a single line.

The syntax of a function is simple:

```
Function functionname (variable list)
    [calculation formulas]
End Function
```

The operations a function performs are contained within the Function / End Function statements. If you need to send data to the function a tag name, for example you simply create a variable in the function's parameters to receive the data. Multiple variables must be separated by commas. These variables exist only within the function.

The following is an example of a function. This function, named `checkValue()`, looks at a tag and assigns it an alarm if it is over a specified value.

A Function to Assign an Alarm to a Tag Based on a Condition

The following function, named `checkValue`, assigns an alarm to a tag if the tag value reaches a specified value.

```
Function checkValue (tagname,sourcename,value)
    If CurrentValue(tagname) > value Then
        Set AlarmObj = new Alarm
        AlarmObj.SubConditionName = "HI"
        AlarmObj.Severity = 750
        AlarmObj.NewAlarm
        "alarmname", "Simulated", "tagname", "Now"
        checkValue = true
    Else
        checkValue = false
    End If
End Function
```

If you want to use this function, enter the values for tag name, source name, and value, as shown in the following example:

```
alm_set = checkValue("DD098.FluidBalance", "FluidBalance_ALM", 5000)
```

In this example, if the value of the `DD098.FluidBalance` tag exceeds 5000, the function returns a true value, indicating that the alarm was set; the `alm_set` variable will be set to `true`. Otherwise, the `alm_set` variable will be set to `false`.

Date/Time Shortcuts

The following table outlines the date/time shortcuts that you can use in calculation formulas.

Table 374. Date/Time Shortcuts

Shortcut	Description
Now	Now (the time and date that you execute the query)
Today	Today at midnight
Yesterday	Yesterday at midnight
BOY	First day of year at midnight
EOY	Last day of year at midnight
BOM	First day of month at midnight
EOM	Last day of month at midnight

Relative Date/Time Shortcuts

Optionally, you can add or subtract relative times to the following absolute times. You must use them in conjunction with the date/time shortcuts listed in the preceding table (for example, Today+5h+3min instead of 5h3min).

- Second
- Minute
- Hour
- Day
- Week

Converting a Collected Value

The following code sample converts a temperature value from degrees Celsius to degrees Fahrenheit.

```
Result=CurrentValue("Temp F")*(9/5)+32
```

Calculations Inside Formulas

The following code sample contains a calculation within a formula. In this case, we are taking the average of values of the tag `Simulation00001` over the previous hour. Typically, use a polled trigger to schedule the execution of the formula.

```
Result=Calculation("Simulation00001","Average","Now-1hour","Now",Quality)
```

Conditional Calculation

The following code sample stores the value of a tag only if it is 100.

```
IF CurrentQuality("Simulation00001")=100 THEN
Result=CurrentValue("Simulation00001")
END IF
```

Combining Tag Values and Assigning a Trigger

The following code sample adds current values of multiple tags using two calculation triggers.

```
Result=CurrentValue("SERVER1.Simulation00003")+CurrentValue("SERVER1.Simulation00006")
```

The calculation triggers used in the sample are SERVER1.Simulation0003 and SERVER1.Simulation0006. The calculation is triggered if the value of either Server1.Simulation0003 or Server1.Simulation0006 changes.

Using CreateObject in a Formula

The following code sample reads data from another Historian Server using the Historian OLE DB provider, and stores it in a destination tag. When using this example, specify the username and password.

```
'connection and recordset variables
Dim Cnxn
Dim rsCurrentValueFromOtherServer
'open connection
Set Cnxn = CreateObject("ADODB.Connection")
'connect to default server using current username and password
'establish connection
Cnxn.Open "Provider=ihOLEDB.iHistorian.1;User Id=;Password="
'Create and open first Recordset using Connection execute
Set rsCurrentValueFromOtherServer = CreateObject("ADODB.Recordset")
'Get the value from the other server
Set rsCurrentValueFromOtherServer = Cnxn.Execute("select value from ihRawData
where SamplingMode=CurrentValue and tagname = Simulation00001")
'Set the result to the current value of other tag
Result=rsCurrentValueFromOtherServer("Value")
'Clean up
IF rsCurrentValueFromOtherServer.State = adStateOpen THEN
```

```
rsCurrentValueFromOtherServer.Close

END IF

IF Cnxn.State = adStateOpen THEN Cnxn.Close

END IF

Set rsCurrentValueFromOtherServer = Nothing

Set Cnxn = Nothing
```

Using a File

The following code sample shows how to read and write text files during a calculation. You may have data in a file to use as input to a calculation, or you may want to write debug values to a text file instead of using the `LogMessage` function.

```
Dim filesystem, writefile, count,readfile

'need to create a file system object since there is no
'file I/O built into VBScript

Set filesystem = CreateObject("Scripting.FileSystemObject")

'open the text file, or create it if it does not exist
set readfile = filesystem.OpenTextFile("C:\somefile.txt", 1, true)

'try to read from the file

IF readfile.AtEndOfLine <> true THEN

count= readfile.ReadAll

END IF

'add one to the number stored in the count count = count+1

'close the file for reading

readfile.Close

'open the same file but for writing

Set writefile= filesystem.OpenTextFile("C:\somefile.txt", 2, true)

'write the updated count writefile.Write count

'close file for writing

writefile.Close

Result = count
```

Converting a Number to a String

If your device and collector expose data as numeric codes, you can change to a string description. This examples also demonstrates that a calculation can output a string.

```
DIM X

x=CurrentValue ("tag1")
```

```

select case x
case 1
Result="one"
case 2
Result="two"
case else
Result="other"
End select

```

Detecting Recovery Mode Inside a Formula

The following code sample detects the recovery mode or recalculation inside a formula. If there are individual tags, you do not want to perform a recovery.

```

Dim MAXDIFF, TimeDiff

'Maximum difference in timestamps allowed (Must be > 2,
'units = seconds) MAXDIFF = 10

'Calculate time difference
TimeDiff = DateDiff("s", CurrentTime(), Now)

'Compare times, if difference is < MAXDIFF seconds perform calc

If TimeDiff < MAXDIFF Then

'Place calculation to be performed here:

Result = CurrentValue("DENALI.Simulation00001") Else

'Place what is to be done when no calc is performed here

Result = Null

End If

```

Looping Through Data Using the SDK

The following code sample uses the SDK to perform a query on a data set. It determines the minimum raw value over a one-hour time period.

```

on error resume next

Dim MyServer 'As Historian_SDK.Server

Dim I

Dim J

Dim K

Dim strComment

Dim lngInterval

Dim TagCount

```

```
Dim strDataQuality
Dim iDataRecordset
Dim iDataValue
Dim lEndTime, lStartTime, lNumSamples
Dim lNumSeconds, lNumSamplesPerSecond
Dim RawMin
'Instantiate The SDK
Set MyServer = CreateObject("iHistorian_SDK.Server")
'Attempt Connection
If Not MyServer.Connect("DENALI", "administrator","") Then
result = err.description
else
Set iDataRecordset = MyServer.Data.NewRecordset
'Find the number of samples.
'build query
With iDataRecordset
.Criteria.Tagmask = "EIGER.Simulation00001"
.Criteria.StartTime = DateAdd("h",-1,Now)
.Criteria.EndTime = Now
.Criteria.SamplingMode = 4 'RawByTime
.Criteria.Direction = 1 'forward
.Fields.AllFields
'do query
If Not .QueryRecordset Then
result = err.description
End If
'Some Large number so that real samples are less
RawMin = 1000000
For I = 1 To iDataRecordset.Tags.Count
For J = 1 To iDataRecordset.Item(I).Count
Set iDataValue = iDataRecordset.Item(I).Item(J)
' if the value is good data quality
if iDataValue.DataQuality = 1 then
if iDataValue.Value < RawMin then
rawMin = iDataValue.Value
end if
end if
```

```

lNumSamples = lNumSamples + 1
Next
Next
End With
End If
Result = RawMin
'Disconnect from server
MyServer.Disconnect

```

Using an ADO Query

The following code sample uses a query combining Historian data with ADO data. In the example, you convert a collected value, number of barrels per day (`BarrelsUsedToday`), to a dollar amount. The code then obtains the price per barrel (`CostOfBarrel`) from the SQL server, and finally stores the total dollars in an integer tag (`TotalCostToday`).

You can also do this with a linked server and the Historian OLE DB provider, but this example maintains a history of the results.

```

Dim CostOfBarrel, BarrelsUsedToday, TotalCostToday

'Calculate the total number of barrels used over
'the previous 24hours.
BarrelsUsedToday = Calculation("BarrelsUsedTag", "Total", "Now 1Day", "Now", Quality)

'Retrieve cost per barrel used
Dim SQLExpression
Dim Cnxn
Dim rsCurrentValue

SQLExpression = "SELECT Barrel_Cost AS Value1 FROM RawMaterial_Costs WHERE Barrel_Type = CrudeOil and
samplingmode = CurrentValue"

'open connection
Set Cnxn = CreateObject("ADODB.Connection")

'connect to default server using current username and password

'establish connection
Cnxn.Open "Provider=SQLOLEDB.1;User ID=sa; Password=;Initial Catalog=Northwind"

'Create and open first Recordset using Connection execute
Set rsCurrentValue = CreateObject("ADODB.Recordset")

'Get the value from the other server
Set rsCurrentValue= Cnxn.Execute(SQLExpression)

'Set the result to the current value of other tag

```

```

CostOfBarrel = rsCurrentValue("Value1")

'Clean up
If rsCurrentValue.State = adStateOpen then
rsCurrentValue.Close
End If

If Cnxn.State = adStateOpen then
Cnxn.Close
End If

Set rsCurrentValue = Nothing
Set Cnxn = Nothing

'Retrieve number of barrels used
BarrelsUsedToday = Calculation("BarrelsUsed", "Count", "Now 1Day", "Now", Quality)

'Calculate total cost of barrels today
TotalCostToday = CostOfBarrel * BarrelsUsedToday

```

Windows Performance Statistics Physical Memory Usage

The following code sample creates a formula that collects data reflecting private byte usage.

```

`Get a reference to the local data archiver process object

Set RawProc = GetObject("winmgmts:Win32_PerfRawdata_Perfproc_process.name='ihDataArchiver.'")

`Scale the virtual bytes number to a value within
`the tag's EGU range

result =RawProc.PrivateBytes *.001

```

Windows Performance Statistics Virtual Memory Usage

The following code sample creates a formula that collects data reflecting virtual byte usage.

```

`Get a reference to the local data archiver process object

Set RawProc = GetObject("winmgmts:Win32_PerfRawdata_Perfproc_process.name='ihDataArchiver.'")

`Scale the virtual bytes number to a value within the
`tag's EGU range

result =RawProc.VirtualBytes *.0001

```

Determining Collector Downtime

The following code sample determines the amount of downtime, in seconds, that the Calculation collector has experienced over the last day. Downtime occurs when there are two consecutive bad quality data points for the pulse tag. If the last known data point for the pulse tag is bad quality, all the time between

its timestamp and the current time is regarded as downtime. In the following sample, the pulse tag is configured to be polled, with a collection interval of one day.

```
Dim pulseTag, totalDowntime, startTime, endTime

Dim prevTime, prevQuality, lastPrevTime, lastPrevQuality

pulseTag = "calcPulseTag"

totalDowntime = 0

endTime = CurrentTime()

startTime = DateAdd("d", -1, endTime)

lastPrevTime = curTime lastPrevQuality = 0

Do

    'get the timestamp and quality of the tag value previous to the last one we checked

    On Error Resume Next

    prevTime = PreviousTime(pulseTag, lastPrevTime)

    If Err.Number <> 0 Then

        'no more values for this tag exit gracefully

        Exit Do

    End If

    prevQuality = PreviousQuality(pulseTag, lastPrevTime)

    'if we have two consecutive bad data points, add to the downtime

    If prevQuality = 0 And lastPrevQuality = 0 Then

        If prevTime > startTime Then

            totalDowntime = totalDowntime + DateDiff("s", prevTime, lastPrevTime)

        Else

            totalDowntime = totalDowntime + DateDiff("s", startTime, lastPrevTime)

        End If

    End If

    'store the timestamp and quality for comparison with the next values

    lastPrevQuality = prevQuality

    lastPrevTime = prevTime

Loop While lastPrevTime > startTime

Result = totalDowntime
```

Analyzing the Collected Data

The following code sample analyzes the collected data to determine the amount of time that a condition was true and had good quality in the last day.

```
Dim tagName, startTime, endTime

tagName = "testTag"

startTime = "Now 1Day"

endTime = "Now"

Result = CalculationFilter(tagName, "TotalTimeGood", startTime, endTime, 100, tagName, "AfterTime", "Equal", 1)
```

Simulating Demand Polling

To simulate demand polling, create the following tags.

Tag	Description
Polled Tag	A polled tag with a collection interval of the longest period you want between raw samples. Do not enable collector or archive compression. This tag should point to the same source address as the unsolicited tag.
Unsolicited Tag	An unsolicited tag with a 0 or 1 second collection interval. This tag ensures you will be notified whenever changes occur. This tag should point to the same source address as the polled tag.
Combined Tag	<p>An unsolicited calculation tag that is triggered by either the polled tag or the unsolicited tag, and combines the raw samples of both into a single tag. Use a 0 or 1 second collection interval and use the following formula:</p> <pre> dim timetag1 dim timetag2 dim tag1 dim tag2 Dim x tag1 = "T20.di-1.F_CV" tag2 = "t20.T20.DI-1.F_CV" x = DateAdd("s", 1,CurrentTime) ' add 1 second to calc time ' Get the timestamp of the newest raw sample for tag1: timetag1 = previousTime(tag1, x) ' Get the timestamp of the newest raw sample for tag2: timetag2 = previousTime(tag2, x) if timetag1 > timetag2 then ' If tag1 triggered me, then: result = PreviousValue(tag1,CurrentTime) else </pre>

Tag	Description
	<pre>' If tag2 triggered me, then: result = PreviousValue(Tag1, CurrentTime) end if</pre>

Native Alarms and Events Functions

About Native Alarms and Events Functions

In addition to using the calculation wizard to create calculation formulas within your calculation tag, you can enter functions manually. The following sections list the functions available, along with their usage.

Retrieving and Setting Alarm Properties Manually

Alarm and event properties can also be set manually in the Calculation collector.

1. To retrieve alarm properties, append the property name to the alarm object, using the following syntax:

```
variable = AlarmObj.Property
```

Example

The following example retrieves the alarm's severity and places it in a variable named *ALM_Severity*.

```
ALM_Severity = AlarmObj.Severity
```

2. To set alarm properties manually, append the property name to the alarm object and supply a new value for the property using the following syntax:

```
AlarmObj.Propertyname = "Property Name"
```

Important:

The `Set Alarm Property` function will not save changes to the alarm database. A call to `UpdateAlarm` must be made after the `Set Alarm Property` function is called.

Example

The following example sets an alarm's severity to 100, then updates the alarm in the Historian archive.

```
AlarmObj.Severity = 100
AlarmObj.UpdateAlarm "Now"
```

Insert Calculation Functions Manually

In addition to using the Calculation Wizard to create your alarms and events calculations, you can also enter them manually. The following functions are available:

NextAlarm

The `NextAlarm` function returns the next alarm for a tag or source on or after a given time stamp.

Syntax

```
set AlarmObj = NextAlarm (source, condition, timestamp)
```

Example Code

The following example will get the next alarm based on the properties of the current alarm object.

```
Set AlarmObj = NextAlarm (AlarmObj.Source, AlarmObj.ConditionName,
DateAdd("s", 1, AlarmObj.Timestamp))
```

NextAlarmForTag

The `NextAlarmForTag` function is identical to the `NextAlarm` function, but takes a tag name as its input instead of a source.

Syntax

```
Set AlarmObj = NextAlarmForTag (tag name, condition, timestamp)
```

Example Code

The following example will get the next alarm for the tag `SYN4450_Flow` with a `LevelAlarm` condition on or after the current alarm's timestamp.

```
Set AlarmObj = NextAlarmForTag ("SYN4450_Flow", "LevelAlarm", AlarmObj.Timestamp)
```

PreviousAlarm

The `PreviousAlarm` function returns the previous alarm for a tag or source on or before a given timestamp.

Syntax

```
set AlarmObj = PreviousAlarm (source, condition, timestamp)
```

Example Code

The following example will get the previous alarm based on the properties of the current alarm object.

```
Set AlarmObj = NextAlarm (AlarmObj.Source, AlarmObj.ConditionName, AlarmObj.Timestamp)
```

PreviousAlarmForTag

The `PreviousAlarmForTag` function is identical to the `PreviousAlarm` function, but takes a tag name as its input instead of a source.

Syntax

```
Set AlarmObj = PreviousAlarmForTag (tag name, condition, timestamp)
```

Example Code

The following example will get the previous alarm for the tag `SYN4450_Flow` with a `LevelAlarm` condition on or before the current time.

```
Set AlarmObj = PreviousAlarmForTag ("SYN4450_Flow", "LevelAlarm", "Now")
```

AddEvent

The `AddEvent` method will create a new event with the current alarm properties.

Syntax

```
AlarmObj.NewAlarm source, tag, time stamp
```

Example Code

The following example creates a new event for the `Simulation00001` tag on `Simulation` source with a severity of `50`, a message of `Test Message`, and the current time.

```
Set AlarmObj = new Alarm
AlarmObj.Severity = 50
AlarmObj.Message = "Test Message"
AlarmObj.AddEvent "Simulation", "Simulation00001", "Now"
```

NewAlarm

The `NewAlarm` method will create a new alarm, based on the current alarm object properties.

Syntax

```
AlarmObj.NewAlarm source, condition, tag, time stamp
```

Example Code

The following example creates a new alarm for the `Simulation00001` tag on `Simulation` source with a severity of `50`, a condition of `Low Fluid Levels`, and the current time.

```
Set AlarmObj = new Alarm
AlarmObj.Severity = 50
AlarmObj.Message = "SomeMsg"
AlarmObj.NewAlarm "Simulation", "Low Fluid Levels", "Simulation00001", "Now"
```

NextAlarm

The `NextAlarm` function returns the next alarm for a tag or source on or after a given time stamp.

Syntax

```
set AlarmObj = NextAlarm (source, condition, timestamp)
```

Example Code

The following example will get the next alarm based on the properties of the current alarm object.

```
Set AlarmObj = NextAlarm (AlarmObj.Source, AlarmObj.ConditionName,
DateAdd("s", 1, AlarmObj.Timestamp))
```

GetVendorAttribute

The `GetVendorAttribute` method will get the value of the given vendor attribute on the current alarm object and place it into a supplied variable.

Syntax

```
variable = AlarmObj.GetVendorAttribute (Vendor_Attribute)
```

Example Code

The following example retrieves a vendor attribute called `Cause_Comment` from the alarm object, and places it into the `ALM_Cause_Comment` variable.

```
ALM_Cause_Comment = AlarmObj.GetVendorAttribute ("Cause_Comment")
```

SetVendorAttribute

The `SetVendorAttribute` method sets the value of the given vendor attribute on the current alarm object.

Syntax

```
AlarmObj.SetVendorAttribute Vendor_Attribute, Value
```

Example Code

The following example sets values for the vendor attributes `Cause_Comment` and `Status_Code`, then updates the alarm in the Historian archive.

```
AlarmObj.SetVendorAttribute "Cause_Comment", "This alarm was caused by..."  
AlarmObj.SetVendorAttribute "Status_Code", 5032  
AlarmObj.UpdateAlarm "Now"
```



Important:

The `SetVendorAttribute` method will not save changes to the alarm database. A call to `UpdateAlarm` must be made after the `SetVendorAttribute` method is set.

UpdateAlarm

The `UpdateAlarm` function updates the current alarm with whatever changes have been made to an alarm's properties.

Syntax

```
AlarmObj.UpdateAlarm timestamp
```

Example Code

```
AlarmObj.UpdateAlarm "Now"
```

ReturnToNormal

The `ReturnToNormal` method sets the end time for the current alarm.

Syntax

```
AlarmObj.ReturnToNormal timestamp
```

Example Code

The following example sets the end time for the alarm to the current time.

```
AlarmObj.ReturnToNormal "Now"
```

Data Input

Calculation and Server-to-Server Collectors

The Calculation and Server-to-Server collectors have some unique behavior not found in other standard collectors. This section provides details about [Recovery \(on page 2152\)](#) and [Manual Recalculation \(on page 2153\)](#).

Recovery

This feature is unique to Calculation and Server-to-Server collectors. If the calculation engine is not running for a period of time, recovery makes it look like it was running. Recovery can also be used to fill in a hole of time where the collector was not able to communicate with the source archiver.

Recovery is applicable to both unsolicited and polled tags. Messages are also recovered. Comments are not recovered.

Normally, it is impossible to go back to the past and collect data. However, since these collectors are 'deriving' data instead of 'collecting' data, it is possible to recover past data, especially since the source of the derived data is archived in the Historian. It is important to understand that while recovery is possible in the calculation and Server-to-Server collectors, it only makes sense for certain types of calculation formulas.

Intended candidates for data recovery are formulas whose only inputs are Historian tags, since past data for these tags can be interpolated. Formulas that use data from external text files or from ADO via CreateObject will most likely not recover correct data because the inputs are not historized. If you are using these types of formulas, you should turn off recovery for the whole collector or insert VBScript code in the formula of individual tags to detect recovery. An example of this is given in the Historian documentation. A similar approach can be used to set a Max Recovery Time on a tag basis, overriding the collector wide setting.

Even calculation tags using only Historian tags as inputs have some caveats for recovery. If you are deriving calculated data from other calculated data, be sure to set up a trigger tag for each of the tags used in your formula. This way the tags will be processed in chain order. All tags are processed in time order.

The recovery logic is not intended to overcome polled collection overruns. If you configure too much collection, then you will get overruns.

You can control the amount of recovered data using Max Recovery Time configuration setting. You can turn off the recovery by setting it to zero.

Manual Recalculation

The Manual re-calc/re-replicate option is often the best choice for generating past derived data.



Note:

If you perform a server-to-server recalculation on source and destination servers whose clocks are not synchronized, extra data points may appear and original data points may not be recalculated. To ensure this does not occur, ensure the time is synchronized on both source and destination servers.

S2S/S2C collector Backfill procedure

With the Recalculate feature you can recalculate all tags for the time period during and after the connection loss. The recalculated tags will use the most accurate values in calculations.

During the period of connection loss, the collector buffers the data. When the connection is restored, the buffered data is forwarded to the Historian Server. When the buffered data arrives, the timestamps show earlier time than the most recent calculation timestamp.

Since the timestamp is earlier, the polled calculations will not execute again with the new data but the unsolicited calculations will re-trigger. Therefore, it is possible that calculations performed for tags during and after the connection loss might not be entirely accurate.

Run S2C Backfill via Command line

```
ihServerToServerCollector.exe RELOADFILENAME=[file location]
RELOADUSERNAME=[Username] <start time> <end time>
```


Example: C:\Program Files\Proficy\Proficy Historian\x86\Server>ihServerToServerCollector.exe RELOADFILENAME=c:\taglist.txt RELOADUSERNAME=\Administrator 1516875659 1516875785

For multi-instance support, the command requires the interface name as shown in the following example:

Example for Multi-instance Support: C:\Program Files (x86)\GE Digital\Historian Server to Server Collector\Server>ihServerToServerCollector.exe RELOADFILENAME=c:\taglist.txt RELOADUSERNAME=\Administrator 1669462600 1669463200 REG=sekhartest05_To_PredixOFFSS

See the following information about the parameters:

- **RELOADFILENAME:** This is an optional parameter. File name should be absolute path, this file consists of the tag names, for which Backfill should be performed, each tag should be separated by new line. Any discrepancies in the file/no file exists/parameter not provided leads to Backfill all the tags related to the collector at the current time. After the Backfill, file gets deleted.
- **RELOADUSERNAME:** This is an optional parameter. This username is used only when destination server is Historian for auditing purpose, and gets ignored when the destination is cloud.
- **TIMESTAMP:** This parameter accepts Start and end time in seconds in epoch format for which Backfill should happen. <https://www.epochconverter.com/>



```

Administrator: Command Prompt - ihServerToServerCollector.exe RELOADFILE...
Microsoft Windows [Version 6.3.9600]
(c) 2013 Microsoft Corporation. All rights reserved.

C:\Users\Administrator>cd\

C:\>cd "Program Files (x86)\GE Digital\Historian Server to Server Collector"
C:\Program Files (x86)\GE Digital\Historian Server to Server Collector>cd Server

C:\Program Files (x86)\GE Digital\Historian Server to Server Collector\Server>ih
ServerToServerCollector.exe RELOADFILENAME=c:\tmp\noexist.tmp RELOADUSERNAME=Ad
ministrator 1520930410 1520937610
ACK [{"messageId":1,"statusCode":202}] @ Tue Mar 13 16:39:55 2018
ACK [{"messageId":130,"statusCode":202}] @ Tue Mar 13 16:40:26 2018
ACK [{"messageId":371,"statusCode":202}] @ Tue Mar 13 16:40:58 2018
ACK [{"messageId":628,"statusCode":202}] @ Tue Mar 13 16:41:31 2018
ACK [{"messageId":828,"statusCode":202}] @ Tue Mar 13 16:42:02 2018
ACK [{"messageId":1125,"statusCode":202}] @ Tue Mar 13 16:42:33 2018
ACK [{"messageId":1391,"statusCode":202}] @ Tue Mar 13 16:43:04 2018
ACK [{"messageId":1589,"statusCode":202}] @ Tue Mar 13 16:43:35 2018
ACK [{"messageId":1823,"statusCode":202}] @ Tue Mar 13 16:44:06 2018
  
```

How Data Recovery works:

- When the recovery logic is executed, the collector will setup subscriptions for all the trigger tags.
- Next, it will recover data. The collector first determines how long it has been since the last write. It compares the current time to data in the registry key `LastCalcRepWriteTime`, which stores the last time data was written to the archive. The collector compares this to the Max Recovery Time that is specified in the user settings and performs a raw data query on the shorter of these two periods. Then it will take the shorter of these two and do a raw data query for all trigger tags. It will then process the returned samples in sequential order based on time. For example, if the collector was shut down for 8 hours, but Max Recovery Time was 4 hours, only 4 hours of data would be recovered.
- Recovery is performed before real time processing. Once recovery is complete, it will start polling and processing subscriptions in real time. The subscriptions in real time are queued up till the recovery is done.

- Recovery logic will place an end-of-collection marker at the point in time where the collector was shut down. This end-of-collection marker may or may not be there once the recovery is complete. As part of recovery logic, if it calculates a data point exactly at that timestamp where the end-of-collection marker is there, then it will be overwritten with the calculated good data.
- The recovery logic does not write samples to trigger tags or tags that are just in the formula. It is intended to write samples to the calculation tags.
- Messages are added to the log file that indicate when entering and exiting recovery mode.

Examples

The examples below assume the following tag configuration.

- Machine 1:

Runs Data Archiver, iFIX collector (Collector 1), and Calculation collectors.

- Machine 2:

Runs iFIX collector (Collector 2), which collects and sends data to the archiver in Machine 1 (as a Remote Collector).

TagA and TagB are the iFix tags coming from Collector1 and Collector2, respectively. Both of these tags are scanned at a 1-minute poll rate.

The following example demonstrates the recovery function for an unsolicited 1-minute interval calculation tag that has a simple current value function.

Create an event based 1-minute interval Calculation Tag (CalcTag1) in Machine 1 consisting of the following calculation: `Result=CurrentValue (TagA)`

Stop the Calculation collector for 5 minutes and then restart it to trigger data recovery for the 5-minute shutdown period. For the following example, the Calculation collector was stopped at 2002-12-27 17:05:36 and started at 2002-12-27 17:10:48.

Since there is no interruption for the iFIX collector, the raw data query for TagA results the following output:

Raw Data Query for TagA during shutdown period

114) 81 [2002-12-27 17:02:00:00000] Good NonSpecific

115) 72 [2002-12-27 17:03:00:00000] Good NonSpecific

116) 64 [2002-12-27 17:04:00:00000] Good NonSpecific

117) 56 [2002-12-27 17:05:00:00000] Good NonSpecific

118) 39 [2002-12-27 17:06:00:00000] Good NonSpecific

119) 31 [2002-12-27 17:07:00:00000] Good NonSpecific

120) 22 [2002-12-27 17:08:00:00000] Good NonSpecific

121) 14 [2002-12-27 17:09:00:00000] Good NonSpecific

122) 6 [2002-12-27 17:10:00:00000] Good NonSpecific

A raw data query for CalcTag1 during the shutdown period generates the following:

Raw Data Query for CalcTag1 (before recovery)

96) 81 [2002-12-27 17:02:00:00000] Good NonSpecific

97) 72 [2002-12-27 17:03:00:00000] Good NonSpecific

98) 64 [2002-12-27 17:04:00:00000] Good NonSpecific

99) 56 [2002-12-27 17:05:00:00000] Good NonSpecific

100) 0 [2002-12-27 17:05:36:00000] Bad OffLine

Note that an end-of-collection marker is placed at the shutdown point (that is, at 17:05:36) with a bad data quality.

Once the recovery is complete, this is what we see for the recovered CalcTag1. Note that data during the shutdown period is recovered completely. Compare this result set with the one for TagA. Both are the same.

Raw Data Query for CalcTag1 (after recovery)

96) 81 [2002-12-27 17:02:00:00000] Good NonSpecific

97) 72 [2002-12-27 17:03:00:00000] Good NonSpecific

98) 64 [2002-12-27 17:04:00:00000] Good NonSpecific

99) 56 [2002-12-27 17:05:00:00000] Good NonSpecific

100) 0 [2002-12-27 17:05:36:00000] Bad OffLine

101) 39 [2002-12-27 17:06:00:00000] Good NonSpecific

102) 31 [2002-12-27 17:07:00:00000] Good NonSpecific

103) 22 [2002-12-27 17:08:00:00000] Good NonSpecific

104) 14 [2002-12-27 17:09:00:00000] Good NonSpecific

105) 6 [2002-12-27 17:10:00:00000] Good NonSpecific

Also note that the end-of-collection marker is not overwritten by the recovery logic here. If it calculated a data point exactly at the end-of-collection marker, then it would have been overwritten by the calculated good value.

The following example demonstrates the recovery function for an unsolicited calculation tag that has multiple triggers.

Create an event based Calculation Tag (CalcTag2) in Machine 1 consisting of the following calculation:

```
Result=CurrentValue (TagA) + CurrentValue (TagB)
```

where TagA and TagB are both trigger tags, coming from Collector1 and Collector2 respectively. Set the collection offset of 5 seconds for TagA and 10 seconds for TagB, forcing the calculation to be performed twice per minute.

Stop the Calculation collector for 5 minutes, and then restart it to trigger data recovery for this 5-minutes shutdown period. For the following example, the Calculation collector was stopped at 02/18/2003 12:15:33 and started at 02/18/2003 12:21:53.

Since the iFIX collector was not interrupted, a raw data query for TagA and TagB values generates the following output:

Raw Data Query for TagA during the shutdown period

10) 13 [2003-02-18 12:10:05:00000] Good NonSpecific

11) 12 [2003-02-18 12:11:05:00000] Good NonSpecific

12) 11 [2003-02-18 12:12:05:00000] Good NonSpecific

13) 11 [2003-02-18 12:13:05:00000] Good NonSpecific

14) 10 [2003-02-18 12:14:05:00000] Good NonSpecific

15) 18 [2003-02-18 12:15:05:00000] Good NonSpecific

16) 17 [2003-02-18 12:16:05:00000] Good NonSpecific

17) 16 [2003-02-18 12:17:05:00000] Good NonSpecific

18) 16 [2003-02-18 12:18:05:00000] Good NonSpecific

19) 15 [2003-02-18 12:19:05:00000] Good NonSpecific

20) 14 [2003-02-18 12:20:05:00000] Good NonSpecific

21) 13 [2003-02-18 12:21:05:00000] Good NonSpecific

Raw Data Query for TagB during the shutdown period

10) 35 [2003-02-18 12:10:10:00000] Good NonSpecific

11) 34 [2003-02-18 12:11:10:00000] Good NonSpecific

12) 33 [2003-02-18 12:12:10:00000] Good NonSpecific

13) 32 [2003-02-18 12:13:10:00000] Good NonSpecific

14) 31 [2003-02-18 12:14:10:00000] Good NonSpecific

15) 31 [2003-02-18 12:15:10:00000] Good NonSpecific

16) 39 [2003-02-18 12:16:10:00000] Good NonSpecific

17) 38 [2003-02-18 12:17:10:00000] Good NonSpecific

18) 37 [2003-02-18 12:18:10:00000] Good NonSpecific

19) 36 [2003-02-18 12:19:10:00000] Good NonSpecific

20) 36 [2003-02-18 12:20:10:00000] Good NonSpecific

21) 35 [2003-02-18 12:21:10:00000] Good NonSpecific

A raw data query for CalcTag2 during the shutdown period generates the following:

Raw Data Query for CalcTag2 (before recovery)

12) 50 [2003-02-18 12:09:05:00000] Good NonSpecific

13) 50 [2003-02-18 12:09:10:00000] Good NonSpecific

14) 49 [2003-02-18 12:10:05:00000] Good NonSpecific

- 15) 48 [2003-02-18 12:10:10:00000] Good NonSpecific
- 16) 47 [2003-02-18 12:11:05:00000] Good NonSpecific
- 17) 46 [2003-02-18 12:11:10:00000] Good NonSpecific
- 18) 45 [2003-02-18 12:12:05:00000] Good NonSpecific
- 19) 44 [2003-02-18 12:12:10:00000] Good NonSpecific
- 20) 44 [2003-02-18 12:13:05:00000] Good NonSpecific
- 21) 43 [2003-02-18 12:13:10:00000] Good NonSpecific
- 22) 42 [2003-02-18 12:14:05:00000] Good NonSpecific
- 23) 41 [2003-02-18 12:14:10:00000] Good NonSpecific
- 24) 49 [2003-02-18 12:15:05:00000] Good NonSpecific
- 25) 49 [2003-02-18 12:15:10:00000] Good NonSpecific
- 26) 0 [2003-02-18 12:15:11:00000] Bad OffLine

Once data recovery is complete, this is what we see for the recovered data for CalcTag2. Note that data during the shutdown period is completely recovered:

Raw Data Query for CalcTag2 (after recovery)

- 12) 50 [2003-02-18 12:09:05:00000] Good NonSpecific
- 13) 50 [2003-02-18 12:09:10:00000] Good NonSpecific
- 14) 49 [2003-02-18 12:10:05:00000] Good NonSpecific
- 15) 48 [2003-02-18 12:10:10:00000] Good NonSpecific
- 16) 47 [2003-02-18 12:11:05:00000] Good NonSpecific
- 17) 46 [2003-02-18 12:11:10:00000] Good NonSpecific
- 18) 45 [2003-02-18 12:12:05:00000] Good NonSpecific
- 19) 44 [2003-02-18 12:12:10:00000] Good NonSpecific
- 20) 44 [2003-02-18 12:13:05:00000] Good NonSpecific

- 21) 43 [2003-02-18 12:13:10:00000] Good NonSpecific
- 22) 42 [2003-02-18 12:14:05:00000] Good NonSpecific
- 23) 41 [2003-02-18 12:14:10:00000] Good NonSpecific
- 24) 49 [2003-02-18 12:15:05:00000] Good NonSpecific
- 25) 49 [2003-02-18 12:15:10:00000] Good NonSpecific
- 26) 0 [2003-02-18 12:15:11:00000] Bad OffLine
- 27) 48 [2003-02-18 12:16:05:00000] Good NonSpecific
- 28) 56 [2003-02-18 12:16:10:00000] Good NonSpecific
- 29) 55 [2003-02-18 12:17:05:00000] Good NonSpecific
- 30) 54 [2003-02-18 12:17:10:00000] Good NonSpecific
- 31) 54 [2003-02-18 12:18:05:00000] Good NonSpecific
- 32) 53 [2003-02-18 12:18:10:00000] Good NonSpecific
- 33) 52 [2003-02-18 12:19:05:00000] Good NonSpecific
- 34) 51 [2003-02-18 12:19:10:00000] Good NonSpecific
- 35) 50 [2003-02-18 12:20:05:00000] Good NonSpecific
- 36) 50 [2003-02-18 12:20:10:00000] Good NonSpecific
- 37) 49 [2003-02-18 12:21:05:00000] Good NonSpecific
- 38) 48 [2003-02-18 12:21:10:00000] Good NonSpecific
- 39) 47 [2003-02-18 12:22:05:00000] Good NonSpecific
- 40) 46 [2003-02-18 12:22:10:00000] Good NonSpecific

The following example demonstrates the recovery function for an unsolicited calculation tag that has multiple triggers, but for which none of the triggers is in the formula.

TagA and TagB are the iFix tags coming from Collector1 and Collector2, respectively. Both tags are scanned at a 1-minute poll rate. This example uses two more iFix tags, TagC and TagD, coming from Collector1.

Create an event-based Calculation Tag (CalcTag3) in Machine 1 consisting of the following calculation:

```
Result=CurrentValue (TagA) + CurrentValue (TagB)
```

Make sure that the trigger tags for this calculation tag are TagC and TagD, which are not in the formula. Set the collection offset of 5 seconds for TagC and 10 seconds for TagD, forcing the calculation to be performed twice per minute.

Stop the Calculation collector for 5 minutes, and then restart it to trigger data recovery for this 5-minutes shutdown period. For the following example, the Calculation collector was stopped at 02/18/2003 02:24:37 and started at 02/18/2003 02:31:44.

Since the iFIX collector was not interrupted, a raw data query for TagA and TagB values generates the following output:

Raw Data Query for TagA during shutdown period

56) 13 [2003-02-18 14:21:05:00000] Good NonSpecific
 57) 12 [2003-02-18 14:22:05:00000] Good NonSpecific
 58) 11 [2003-02-18 14:23:05:00000] Good NonSpecific
 59) 11 [2003-02-18 14:24:05:00000] Good NonSpecific
 60) 10 [2003-02-18 14:25:05:00000] Good NonSpecific
 61) 19 [2003-02-18 14:26:05:00000] Good NonSpecific
 62) 18 [2003-02-18 14:27:05:00000] Good NonSpecific
 63) 17 [2003-02-18 14:28:05:00000] Good NonSpecific
 64) 16 [2003-02-18 14:29:05:00000] Good NonSpecific
 65) 16 [2003-02-18 14:30:05:00000] Good NonSpecific
 66) 15 [2003-02-18 14:31:05:00000] Good NonSpecific

Raw Data Query for TagB during shutdown period

141) 36 [2003-02-18 14:20:10:00000] Good NonSpecific
 142) 36 [2003-02-18 14:21:10:00000] Good NonSpecific
 143) 35 [2003-02-18 14:22:10:00000] Good NonSpecific

144) 34 [2003-02-18 14:23:10:00000] Good NonSpecific

145) 33 [2003-02-18 14:24:10:00000] Good NonSpecific

146) 32 [2003-02-18 14:25:10:00000] Good NonSpecific

147) 31 [2003-02-18 14:26:10:00000] Good NonSpecific

148) 31 [2003-02-18 14:27:10:00000] Good NonSpecific

149) 39 [2003-02-18 14:28:10:00000] Good NonSpecific

150) 38 [2003-02-18 14:29:10:00000] Good NonSpecific

151) 37 [2003-02-18 14:30:10:00000] Good NonSpecific

152) 36 [2003-02-18 14:31:10:00000] Good NonSpecific

A raw data query for CalcTag3 during the shutdown period generates the following:

Raw Data Query for CalcTag3 (before recovery)

6) 49 [2003-02-18 14:21:05:00000] Good NonSpecific

7) 49 [2003-02-18 14:21:10:00000] Good NonSpecific

8) 48 [2003-02-18 14:22:05:00000] Good NonSpecific

9) 47 [2003-02-18 14:22:10:00000] Good NonSpecific

10) 46 [2003-02-18 14:23:05:00000] Good NonSpecific

11) 45 [2003-02-18 14:23:10:00000] Good NonSpecific

12) 45 [2003-02-18 14:24:05:00000] Good NonSpecific

13) 44 [2003-02-18 14:24:10:00000] Good NonSpecific

14) 0 [2003-02-18 14:24:11:00000] Bad OffLine

A data query for the recovered CalcTag3 values once data recovery is complete generates the following.
Note that data during the shutdown period is completely recovered:

Raw Data Query for CalcTag3 (after recovery)

6) 49 [2003-02-18 14:21:05:00000] Good NonSpecific

- 7) 49 [2003-02-18 14:21:10:00000] Good NonSpecific
- 8) 48 [2003-02-18 14:22:05:00000] Good NonSpecific
- 9) 47 [2003-02-18 14:22:10:00000] Good NonSpecific
- 10) 46 [2003-02-18 14:23:05:00000] Good NonSpecific
- 11) 45 [2003-02-18 14:23:10:00000] Good NonSpecific
- 12) 45 [2003-02-18 14:24:05:00000] Good NonSpecific
- 13) 44 [2003-02-18 14:24:10:00000] Good NonSpecific
- 14) 0 [2003-02-18 14:24:11:00000] Bad OffLine
- 15) 43 [2003-02-18 14:25:05:00000] Good NonSpecific
- 16) 42 [2003-02-18 14:25:10:00000] Good NonSpecific
- 17) 51 [2003-02-18 14:26:05:00000] Good NonSpecific
- 18) 50 [2003-02-18 14:26:10:00000] Good NonSpecific
- 19) 49 [2003-02-18 14:27:05:00000] Good NonSpecific
- 20) 49 [2003-02-18 14:27:10:00000] Good NonSpecific
- 21) 48 [2003-02-18 14:28:05:00000] Good NonSpecific
- 22) 56 [2003-02-18 14:28:10:00000] Good NonSpecific
- 23) 55 [2003-02-18 14:29:05:00000] Good NonSpecific
- 24) 54 [2003-02-18 14:29:10:00000] Good NonSpecific
- 25) 54 [2003-02-18 14:30:05:00000] Good NonSpecific
- 26) 53 [2003-02-18 14:30:10:00000] Good NonSpecific
- 27) 52 [2003-02-18 14:31:05:00000] Good NonSpecific
- 28) 51 [2003-02-18 14:31:10:00000] Good NonSpecific
- 29) 49 [2003-02-18 14:32:05:00000] Good NonSpecific
- 30) 49 [2003-02-18 14:32:10:00000] Good NonSpecific

31) 48 [2003-02-18 14:33:05:00000] Good NonSpecific

32) 47 [2003-02-18 14:33:10:00000] Good NonSpecific

Troubleshoot Calculation Collector

Troubleshooting Calculation collector

If you observe errors with Calculation collector, you should:

1. Examine the collector log files in the `Historian\LogFiles` folder and scan for errors in the log that may explain your problem.
2. Check the connection to the source.
For example, if you lose connection to the source, all tags for that collector stop collecting. What that means is that even if you hard-code the formula results, the collector will not collect them. If you enter a formula such as `result=7` on a polled, 1-second tag in the Server-to-Server Collector, Historian does not log any raw samples to the destination computer. This action occurs even though the result is hardcoded.
3. Ensure that you are following the guidelines described in [General Guidelines for Designing a Calculation Formula \(on page 2119\)](#).



Tip:

use the `LogMessage` function to include messages in your formula when certain points of a calculation executes so that you can isolate errors. Refer to [Writing Messages to the Collector Log File for Debugging Purposes \(on page 2165\)](#) for details.

Unsupported Data Types for Calculation Tags

Calculation tags with Quad Integer and Unsigned Quad Integer data types return bad quality values due a limitation in Visual Basic (VB).

Unsupported Calculations in Calculation collector

Calculation collector supports only the calculations performed using the current value calculation. It does not support other calculations due to a Visual Basic script limitation.

Writing Messages to the Collector Log File for Debugging Purposes

If you want to include debugging messages after certain parts of your formula execute, you can use the `LogMessage` function when creating a formula in the Calculation pane. The syntax of this function is as follows:

```
LogMessage(message_string)
```

where `message_string` is the message that you want to appear in the log file for the Calculation or Server-to-Server Collector. If the `message_string` is not a string variable, use double quotes around the text for `message_string` value. For instance, a properly formatted text string with double quotes would appear like this:

```
LogMessage("This is a message")
```



Note:

The `LogMessage` function does not appear in the wizard.

Importing Calculations with Line Breaks into Historian

You can import calculations with line breaks into Historian when you use the File collector or the Excel Add-in.

1. To create a line break in a .CSV file for the File collector, you insert the `*CR*` character sequence where you want each line break to occur.
2. To create a calculation with multiple lines in Excel, press **Alt+Enter** at the end of each line where you want a line break to occur within a cell.

You can also use the `*CR*` character sequence to denote a line break in the formula.

Example of a .CSV File that Includes a Calculation with Multiple Lines

In the following example the bold `*CR*` characters identify where the line breaks occur in the calculation formula.

```
[Tags]

Tagname,Description,DataType,HiEngineeringUnits,LoEngineeringUnits,Calculation,
CollectorType,CollectorName,CollectionType,CalculationDependencies
CalTag16,Multiline calc tag sample,SingleFloat,35000,0, "multiline calc comment*CR*IF CurrentQuality
(^Fixlab15.simulation00001^)=100 THEN*CR*Result=CurrentValue(^Fixlab15.simulation00002^)
*CR*END IF",Calculation,Fixlab15_Calculation,Unsolicited,Fixlab15.simulation00001
```



Important:

For this example to work, only include three line breaks: one after the word [Tags], one after the word `CalculationDependencies` on line 3, and one at the very end of the example. It is important that the last 4 lines of this example all appear on the same line in the actual .CSV file. The example only includes extra line breaks so that the text is more easily readable, and does not flow off the page.

Recovery Mode

Recovery logic is activated when the Calculation collector and Historian Server reestablish connection after a connection loss. Recovery mode allows the collector to recover data when the connection between the collector and the server is reestablished. Recovery mode produces calculated values for time when the Calculation collector was not running.

When using recovery mode, all referenced tags in an unsolicited calculation must be listed as trigger tags. For more information, refer to [About Recovery Mode \(on page 2503\)](#).

Chapter 16. The CygNet Collector

Overview of the CygNet Collector

The CygNet collector collects data from a CygNet server and stores it in the Historian server.

Topology: The CygNet collector supports a distributed model, where the CygNet server, the collector, and the Historian server are installed on different machines. Typically, however, the collector is installed on the same computer as the CygNet server and sends data to a remote Historian server.

Features:

- You can browse the source for tags and their attributes on a CygNet server that supports browsing.
- Both the polled as well as unsolicited data collection are supported. During unsolicited data collection, when changes to the CygNet tags are detected, they are forwarded to the Historian server. The collector duplicates raw samples from the CygNet server into the Historian data archive.
- The supported timestamp resolution is 100ms.
- The collector support manual recalculation of tag data.
- Floating point, integer, and string data are supported.

Components:

- System API
- Collector Toolkit

How it works:

1. When you browse for tags, the CygNet collector connects with CygNet using the CxScript64.dll API.
2. The collector queries the CygNet faculty service and point service associated with the Current Value service (CVS).
3. The CygNet point value is mapped to the Historian server as a collector tag.
4. The collector stores the Value Historian service (VHS) and points Uniform Data Codes as the tag source address.
5. Once all the CygNet points associated with the selected CVS/VHS have been mapped with the Historian tags, the collector begins querying from VHS to collect data from CygNet.

Supported data types:

The CygNet collector collects analog, digital, and string types of data. The following table provides the data types recommended for use with Historian.

CygNet Data Types	Recommended Data Type in Historian
Analog	Float
Enumeration	Integer
Digital	Boolean
String	Variable String

Supported tag attributes:

- Tagname
- Source Address
- Engineering Unit Description
- Data Type
- Hi Engineering Units and Lo Engineering Units (applicable only to analog and discrete data types)

**Note:**

Although you can browse and query some of these attributes, they are not displayed in the browse interface. These attributes are used when you add a tag, but are not visible to you, regardless of attributes available from the server.

Configuration

Add and Configure a CygNet Collector


A CygNet collector collects data from a CygNet server and stores it in the Historian server. For more information, refer to [Overview of the CygNet Collector \(on page 2167\)](#).

**Note:**

You cannot send data to a cloud destination using a CygNet collector.

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Cygnnet Collector**, and then select **Get Details**.
The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.
6. Select **Next**.
The **Source Configuration** section appears.
7. In the **SERVER SITE** field, enter the host name or IP address of the CygNET server from which you want to collect data.
8. Select **Next**.
The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default; the other options are disabled.
9. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.
If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.
If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: *<Historian server name>_Cygnet*

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must contain the string *Cygnet*.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.


The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

14. Under **COLLECTOR SPECIFIC CONFIGURATION**, configure values as described in the following table.

Field	Description
Re-covery Time	The maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the CygNet server is re-established. This time is calculated as the duration between the current time and the last known write time.

Field	Description
	<p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>By default, this value is set to 0, which means data recovery is not attempted. The maximum value you can provide is 168 hours (that is, 7 days).</p>
Thread Count	The maximum number of threads that you want the collector to use to query data from the CygNet server.
CygNet Debug Mode	<p>The debug mode for the collector. You can enter a value between 0 and 255, where 0 turns off debugging and 255 enables detailed debugging (with query transactions).</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note:</p> <p>Do not turn on debugging for a long period. If you do so, very large log files are created, which can consume a great deal of disk space. We recommend a maximum of 10 minutes.</p> </div>
General Optimized	Indicates whether you want to apply optimization on the tag data reads.
Service-Site	Identifies the CygNet site or data source from which the CygNet collector collects data. A value is required.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
<p>For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632).</p>	

15. If needed, enter values in [the other sections common to all collectors \(on page 579\)](#).
16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.


17. If needed, restart the collector.

Specify the tags (on page 357) whose data you want to collect using the collector.

Configure the CygNet Collector Using Historian Administrator

1. Access [Historian Administrator](#) (on page 823).
2. Select **Collectors**, and then select the CygNet collector instance that you want to configure.
3. Select **Configuration**.

The **Configuration** section appears.



4. Enter values as specified in the following table.

Field	Description
Recovery Time	<p>The maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the CygNet server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>By default, this value is set to 0, which means data recovery is not attempted. The maximum value you can provide is 168 hours (that is, 7 days).</p>
Thread Count	<p>The maximum number of threads that you want to use to query data from the CygNet server.</p>
CygNet Debug Mode	<p>The debug mode for the collector. You can enter a value between 0 and 255, where 0 turns off debugging and 255 enables detailed debugging (with query transactions).</p> <div data-bbox="667 1062 1417 1329" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: Do not turn on debugging for a long period. If you do so, very large log files are created, which can consume a great deal of disk space. We recommend maximum 10 minutes.</p> </div>
General Optimized	<p>Indicates whether you want to apply optimization on the tag data reads.</p>
ServiceSite	<p>Identifies the CygNet site or data source from which the CygNet collector collects data. A value is required.</p>

**Note:**

You can also modify these parameters in the registry under HKEY_LOCAL_MACHINE \SOFTWARE\GE Digital\iHistorian\Services\CygNetCollector. The following table provides the mapping between the parameters in the Registry and the UI.

 Registry Parameters	Parameters in the UI
General2	Recovery Time
General3	Thread Count
General4	CygNet Debug Mode
General5	General Optimized

For a list of the general parameters, refer to [General Parameters of a Collector \(on page 814\)](#).

5. Select **Update**.
6. Restart the collector.
The collector is configured.

Specifying Tags for Data Collection


Add Tags for the Data Store Using Configuration Hub

- [Add the collector instance \(on page 357\)](#) using which you want to collect data. Ensure that the collector is running.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, [create it \(on page 370\)](#).

This topic describes how to specify the tags for which you want to collect data by browsing through the tags in the data source. For example, for an iFIX collector, if there are 1,00,000 tags in the iFIX server, you must specify the ones for which you want to collect data. Only then data is collected for those tags.

In addition to adding tags from the data source, you can [create tags manually \(on page 473\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **+**.



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. A value is required.
COLLECTED TYPE	Specify whether you want to browse through all the tags in the data source or only from the tags that you have not added yet. A value is required.
SOURCE TAG NAME	Enter the name of the tag (either completely or partially) to narrow down the search results.
SOURCE TAG DESCRIPTION	Enter the description of the tag (either completely or partially) to narrow down the search results.

5. Select **Search Tags**.

A list of tags that match *all* the criteria that you have specified appears. If a tag is already added, it is disabled.

6. Select the check box corresponding to each tag for which you want to collect data.

Add Tags from Collector Add Manually

COLLECTOR NAME* COLLECTED TYPE* SOURCE TAG NAME SOURCE TAG DESCRIPTION

[Redacted]_Simulation All Source Tags * *

Search Tags

SEARCH RESULTS FOR SOURCE TAGS NAMES

<input type="checkbox"/>	TAG NAME	DESCRIPTION
	Filter	Filter
<input type="checkbox"/>	[Redacted] Simulation.Simulation00001	[Redacted] Simulation.Simulation00001
<input type="checkbox"/>	[Redacted] Simulation.Simulation00002	[Redacted] Simulation.Simulation00002
<input type="checkbox"/>	[Redacted] Simulation.Simulation00003	[Redacted] Simulation.Simulation00003
<input type="checkbox"/>	[Redacted] Simulation.Simulation00004	[Redacted] Simulation.Simulation00004
<input type="checkbox"/>	[Redacted] Simulation.Simulation00005	[Redacted] Simulation.Simulation00005
<input type="checkbox"/>	[Redacted] Simulation.Simulation00006	[Redacted] Simulation.Simulation00006
<input type="checkbox"/>	[Redacted] Simulation.Simulation00007	[Redacted] Simulation.Simulation00007
<input type="checkbox"/>	[Redacted] Simulation.Simulation00008	[Redacted] Simulation.Simulation00008
<input type="checkbox"/>	[Redacted] Simulation.Simulation00009	[Redacted] Simulation.Simulation00009
<input type="checkbox"/>	[Redacted] Simulation.Simulation00010	[Redacted] Simulation.Simulation00010
<input type="checkbox"/>	[Redacted] Simulation.Simulation00011	[Redacted] Simulation.Simulation00011
<input type="checkbox"/>	[Redacted] Simulation.Simulation00012	[Redacted] Simulation.Simulation00012

DATASTORE*
User

7. In the **DATA STORE** field, if you want to store the data in a different data store than the user data store, select the same.

8. Select **Add Tag**.

Data collection begins for the selected tags.

As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.


Specify the Tags for Data Collection Using Historian Administrator

Install the CygNet ODBC driver on the collector machine, which is required for the CygNet collector to connect to the server. Note that the CygNet ODBC driver is not available with Historian.

If your CygNet server supports hierarchical organization of tags in a tree structure, you can use the hierarchy to browse for tags and add them to the collector for data collection.


1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Collectors**, and then select the CygNet collector instance to which you want to add tags.
3. Select **Configuration**.

The **Configuration** section appears.



4. Select **Add Tags**.

The **Add Multiple Tags from Collector** window appears.



5. In the **Collector** field, select the CygNet collector to which you want to add tags.
A hierarchical tree of tags appears in the **Browse Results** section.
6. If you want to view only the tags for which data is not collected, in the **Show Only** field, select **Source Tags Not Collected**. You can search for a tag by entering search criteria in the **Source Tag Name** or **Description** field.
7. Navigate to the node in the tree that you want to browse, and then select **Browse**.

i Tip:

- To browse automatically, select the **Auto Browse** check box. The available tags appear in the **Browse Results** window whenever a node is selected in the tree.
- To show all child elements within a hierarchy, select the **Show All Children** check box. All tags at or below the hierarchical level of the selected node in the tree appear in the **Browse Results** window.

The tags within the selected portion of the CygNet server tag hierarchy appear.

8. Select the tags for which you want to collect data, and then select **Add Selected Tags**.

The tags are added to the collector. They appear in black text in the list of tags.

Disable Bad Offline Values

By default, the CygNet collector adds a bad offline value when the collector is started or when a tag is modified. This topic describes how to disable this feature.

1. Access the following registry key: `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\CygNetCollector\<entry>`
2. Add the `WriteBadOfflineAtStartup (DWORD)` DWORD, and set it to 0 to disable adding bad offline values.

Bad offline values will no longer be added.

Disable Deleting Values Before Recalculation

By default, before recalculating tag values, the CygNet collector deletes any previously stored values. This topic describes how to disable this feature.

1. Access the following registry key: `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\CygNetCollector\<entry>`
2. Add the `DeleteBeforeRecalc (DWORD)` DWORD, and set it to 0.

Previously stored tag values will no longer be deleted before recalculation.

Troubleshooting the CygNet Collector

The CygNet collector generates logs during initialization, configuration, and general operation. You can find them at `C:\Proficy Historian Data\LogFiles`.

Troubleshooting Tips

Troubleshoot the collector by:

- Examining the log files for information.
- Examining the Windows Event Viewer for error/warnings.
- Verifying that the CygNet server is running before you start the collector.
- Verifying that CygNet ODBC Client Tools are installed.

Additional log information can be gathered by using the **CygNet Debug Mode** described above for debugging the CygNet to Collector interface.

Turn on the Debug Mode

1. Access the following folder in the registry: *HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\iHistorian\Services\CygNetCollector\<entry>*
2. Double-click **DebugMode DWORD** .
3. Set **Base** as Decimal.
4. In the **Value data** field, enter 255.
5. Select **OK**.
6. Restart the collector.
7. Close the registry and open the *Proficy OPC Classic HDA server trace log* file.



Note:

- Do not turn on both **CygNet Debug Mode** and **DebugMode** at the same time.
- Do not turn on **CygNet Debug Mode** or the **DebugMode key** for an extended period, 10 minutes should be more than sufficient. Leaving it on will create very large log files and that could use up a great deal of disk space.

CygNet APIs Not Installed

Error message: Error Setting CygNet GlobalFunctions object: 'Class not registered'

Root cause: The CygNet 64 bit APIs are not installed.

Solution: Run the following command to install CxScript64.dll: `regsvr32 "C:\...\8.1.2 Install\CygNet 812\Support64\CxScript64.dll"`

Chapter 17. The File Collector

Overview of the File Collector

The File collector imports CSV and XML files into Historian. Since the files can contain data, tags, tag properties, and messages, the File collector is a very useful tool for importing third-party data into Historian.

Features:

- You can import CSV and XML files.
- The supported timestamp resolution is 1ms.
- Floating point, integer, and string data are supported. Binary data is not supported.
- The collector accepts device timestamps.
- The collector reads data, tags, and messages.
- You can set file specifications and the import interval. The timestamps for data or messages may be at intervals less than the import interval.
- You can create Historian tags.
- You can create Python Expression Tags for those collectors that support them.

Since a File collector is really an import function rather than a data collection operation, standard collector features such as compression, buffering, browsing, start/stop collection are not applicable.



Note:

You can import files using ANSI encoding only.

How it works:

The File collector uses the `ImportFiles` folder for its operations, which is available in the Historian program folder. It is created only after you run the collector. It contains the following subfolders:

Directory	Function
Error	Contains the CSV and XML files that contains errors. These files will not be processed by the collector.
Incoming	Contains files that are to be processed by the collector. All the files that you want to import using the collector must be placed here.
Processed	Contains files that have been imported.

Directory	Function
Working	Contains files that the collector is importing.

1. Place the files that you want to import in the `Incoming` folder.
2. At the beginning of each cycle, the collector processes the files, stores the result in an archive file and moves the files to the `Processed` folder.
3. While processing the files, the collector moves the files to the `Working` folder, and renames the files using the following format: YMDHMS-Data (for example, 010810103246-data.csv).
4. After processing the files, the collector restores the original file names. If an error occurs while processing the files, they are moved to the `Error` folder, and error messages are logged in the `Filecollector_YMDHMS.log` file.
5. After a specified duration has passed, the imported files are deleted from the `Processed` folder. However, files are not deleted from the `Error` folder.

Supported date formats:

System Date Format	Supported Date Format in the XML Files	Supported Date Format in the CSV Files
dd-MMM-yy	<ul style="list-style-type: none"> • dd-MMM-yy • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy 	<ul style="list-style-type: none"> • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yyyy
yyyy-MM-dd	<ul style="list-style-type: none"> • dd-MMM-yy • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy 	<ul style="list-style-type: none"> • dd-MMM-yy • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy
yy/MM/dd	<ul style="list-style-type: none"> • dd-MMM-yy • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy 	<ul style="list-style-type: none"> • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy

System Date Format	Supported Date Format in the XML Files	Supported Date Format in the CSV Files
	<ul style="list-style-type: none"> • MM/dd/yy • M/d/yy • M/d/yyyy 	<ul style="list-style-type: none"> • M/d/yy • M/d/yyyy
MM/dd/yyyy	<ul style="list-style-type: none"> • dd-MMM-yy • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy 	<ul style="list-style-type: none"> • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy
MM/dd/yy	<ul style="list-style-type: none"> • dd-MMM-yy • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy 	<ul style="list-style-type: none"> • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy
M/d/yy	<ul style="list-style-type: none"> • dd-MMM-yy • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy 	<ul style="list-style-type: none"> • dd-MMM-yy • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy
M/d/yyyy	<ul style="list-style-type: none"> • dd-MMM-yy • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy 	<ul style="list-style-type: none"> • yyyy-MM-dd • yy/MM/dd • MM/dd/yyyy • MM/dd/yy • M/d/yy • M/d/yyyy

Configuration

Add and Configure a File Collector

A File collector is used to send data from one Historian server to another one.



Note:

- You cannot send data to a cloud destination using the File collector.
- You can create only one instance of the File collector.

For more information, refer to [Overview of the File Collector \(on page 2181\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.

COLLECTOR NAME	STATUS
Calculation	● Running
Simulation	● Running

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance. The collector will send data to this machine.
5. In the **COLLECTOR TYPE** field, select **File Collector**, and then select **Get Details**.
The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.
6. Select **Next**.
The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default; the other options are disabled.
7. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.
If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.
If the entered credentials are valid, a successful connection message appears.
8. Select **Next**.
The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: `<Historian server name>_File`
9. If needed, modify the value in the **COLLECTOR NAME** field.
The value that you enter:
 - Must be unique.
 - Must not exceed 15 characters.
 - Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
10. In the **RUNNING MODE** field, select one of the following options.
 - **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
 - **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields. If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:
 - iH Security Admins
 - iH Collector Admins
 - iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

11. Select **Add**.


The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

12. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
Scan Interval	The interval, in seconds, after which the collector initiates an import operation. The maximum value that you can enter is 65.
CSV File Spec	The file extension for a CSV file to be imported. You can specify more than one extension type, such as csv, txt, dat.
XML File Spec	The file extension for an XML file to be imported.
Purge Processed (days)	The number of days after which you want the contents of the <code>Processed Files</code> folder to be automatically purged.
Purge Error (days)	The number of days after which you want the contents of the <code>Error Files</code> folder to be automatically purged.

13. Ad needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

14. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

15. If needed, restart the collector.

[Import files using the collector \(on page 2188\)](#).

Configure the File Collector Using Historian Administrator

[Install collectors \(on page 143\)](#), and [create an instance of the collector \(on page 486\)](#).

1. Access Historian Administrator.
2. Select **Collectors**, and then select the File collector instance that you want to configure.
3. Select **Configuration**.

The **Configuration** section appears.

Collector Specific Configuration (File)

Scan Interval (sec)	5
CSV Filespec	csv
XML Filespec	xml
Purge Processed (days)	10
Purge Error (days)	10

Recalculate Add Tags Update Delete

4. Enter values as specified in the following table.

Field	Description
Scan Interval	The interval, in seconds, after which the collector initiates an import operation. The maximum value that you can enter is 65.
CSV File Specification	The file extension for a CSV file to be imported. You can specify more than one extension type, such as csv, txt, dat.
XML File Specification	The file extension for an XML file to be imported.
Purge Processed Files After(days)	The number of days after which you want the contents of the <code>Processed</code> folder to be automatically purged.
Purge Error Files After (days)	The number of days after which you want the contents of the <code>Error</code> folder to be automatically purged.

5. Select **Update**.

- Restart the collector.
The collector is configured.

Import Files

- Configure the collector settings ([on page 486](#)).
- Ensure that the files you want to import are of the [CSV format \(on page 2188\)](#) or the [XML format \(on page 2195\)](#).



Note:

You can import files using ANSI encoding only.

Place the files that you want to import in the `Incoming` folder. By default, this folder is located in the following folder: `C:/Proficy Historian Data/ImportFiles`.

The collector checks the `Incoming` folder every few seconds (based on the duration specified in the **Scan Interval** field while [configuring the collector \(on page 486\)](#)). The files are imported to Historian and are moved to the `Processed` folder. If an error occurs, however, they are moved to the `Error` folder. If that happens, refer to [Troubleshooting the File Collector \(on page 2205\)](#).

CSV File Format

Specify the collector source address and the tag source address fields in the CSV file. Otherwise, the collector and source names are not added to the tags created by the File collector.

The format for a CSV file is as follows:

```
[<command>]
<Header keywords separated by commas>
<values separated by commas>
*Comments
```



Note:

- The order of the values must match the order in the header. For example, if you are importing a tagname, timestamp, value, and quality, use the following syntax:

```
[Data]
Tagname,TimeStamp,Value,DataQuality TIGER.IMPORT_TAG1.F_CV,7/20/01 11:07,1,Good
```



- Data values for a single entry must be placed on a single line.
- You cannot import Last Modified User, Last Modified Date, and Calculation Execution Time fields on a tag.

Refer to the following sections for valid values and examples.

Valid Values for Command

- [Tags]
- [Data]
- [Messages]
- [Alarms]

Valid Values for Header Keywords

DataQuality	Value
Tagname	Description
EngineeringUnits	Comment
DataType	StringLength <div data-bbox="492 1136 1422 1318" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: StringLength is twice the number of characters (ASCII, Single Byte). For example, "ABC" = 6 StringLength. </div>
StoreMilliseconds	CollectorName
CollectorType	SourceAddress <div data-bbox="492 1465 1422 1648" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: A value is required for the source name to be added to tags created by the collector. </div>
CollectorType	CollectionInterval
CollectionOffset	CollectionDisabled
LoadBalancing	TimeStamp

DataQuality	Value
	<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: The timestamp resolution is milliseconds. </div>
Type	TimeZoneBias
HiEngineeringUnits	LoEngineeringUnits
InputScaling	HiScale
LoScale	CollectorCompression
CollectorDeadband-PercentRange	CollectorCompressionTimeout
ArchiveCompression	ArchiveDeadbandPercentRange
ArchiveCompression-Timeout	Timeout
CollectorGeneral1	CollectorGeneral2
CollectorGeneral3	CollectorGeneral4
CollectorGeneral5	ReadSecurityGroup
WriteSecurityGroup	AdministratorSecurityGroup
Calculation	CalculationDependencies
Acked	Condition
SubCondition	EventCategory
Message	Source
Severity	StartTime
EndTime	TimestampType
SpikeLogic	SpikeLogicOverride
InterfaceAbsolute-Deadband	InterfaceAbsoluteDeadbanding
LastModified	LastModifiedUser

DataQuality	Value
ArchiveAbsoluteDeadband	ArchiveAbsoluteDeadbanding
StepValue	Value
SpikeLogic	SpikeLogicOverride
NumberOfElements	CalcType

For alarms and events, only the following header keywords are considered:

- Acked
- Acktime
- Actor
- AlarmID
- Condition
- DataSource
- Enabled
- EndTime
- EventCategory
- ItemID
- Message
- Quality
- Severity
- Source
- StartTime
- SubCondition
- Tagname
- Timestamp

A CSV File that Imports Tags

```
[Tags]
Tagname,Description,DataType,HiEngineeringUnits,LoEngineeringUnits
TIGER.IMPORT_TAG1.F_CV,Import Tag 1,SingleFloat,35000,0
TIGER.IMPORT_TAG2.F_CV,Import Tag 2,SingleFloat,35000,0
TIGER.IMPORT_TAG3.F_CV,Import Tag 3,SingleFloat,35000,0
TIGER.IMPORT_TAG4.F_CV,Import Tag 4,SingleFloat,35000,0
TIGER.IMPORT_TAG5.F_CV,Import Tag 5,SingleFloat,35000,0
```

```
TIGER.IMPORT_TAG6.F_CV,Import Tag 6,SingleFloat,35000,0
TIGER.IMPORT_TAG7.F_CV,Import Tag 7,SingleFloat,35000,0
TIGER.IMPORT_TAG8.F_CV,Import Tag 8,SingleFloat,35000,0
TIGER.IMPORT_TAG9.F_CV,Import Tag 9,SingleFloat,35000,0
TIGER.IMPORT_TAG10.F_CV,Import Tag 10,SingleFloat,35000,0
```

A CSV File that Imports Data and Data Quality

```
[Data]
Tagname,TimeStamp,Value,DataQuality
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:07,1,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:08,2,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:09,3,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:10,4,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:11,5,Bad
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:12,6,Bad
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:13,7,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:14,8,Bad
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:15,9,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:16,10,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:17,11,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:18,12,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:19,13,Bad
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:20,14,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:21,15,Good
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:22,16,Bad
TIGER.IMPORT_TAG1.F_CV,7/20/01 11:23,17,Good
```

A CSV File that Imports Messages

```
[Messages]
TimeStamp,Topic,Username,MessageNumber,MessageString,Substitutions
28-Aug-2002 19:39:30.567,General,User1,0,A Test Message value 2 with milliseconds,,
28-Aug-2002 19:40:00.000,General,User1,0,A Test Message value 0,,
```

A CSV File that Imports Tags with Step Values

```
[Tags]
Tagname,Description,DataType,HiEngineeringUnits,LoEngineeringUnits
TIGER.IMPORT_TAG1.F_CV,Import Tag 1,SingleFloat,35000,0
```

```
TIGER.IMPORT_TAG2.F_CV,Import Tag 2,SingleFloat,35000,0
TIGER.IMPORT_TAG3.F_CV,Import Tag 3,SingleFloat,35000,0
TIGER.IMPORT_TAG4.F_CV,Import Tag 4,SingleFloat,35000,0
TIGER.IMPORT_TAG5.F_CV,Import Tag 5,SingleFloat,35000,0
TIGER.IMPORT_TAG6.F_CV,Import Tag 6,SingleFloat,35000,0
TIGER.IMPORT_TAG7.F_CV,Import Tag 7,SingleFloat,35000,0
TIGER.IMPORT_TAG8.F_CV,Import Tag 8,SingleFloat,35000,0
TIGER.IMPORT_TAG9.F_CV,Import Tag 9,SingleFloat,35000,0
TIGER.IMPORT_TAG10.F_CV,Import Tag 10,SingleFloat,35000,0
```

A CSV File that Imports Alarms

```
[Alarms]
DataSource,Condition,Source,StartTime,TimeStamp
FileCollector,HI,Mixer,3/10/2005 12:52:02,3/10/2005 12:52:02
FileCollector,HIHI,Mixer,3/10/2005 12:52:02,3/10/2005 12:59:12
```

A CSV File that Imports Enumerated Set

```
[EnumeratedSet]
SetName,SetDescription,StateLowValue,StateHighValue,StateDescription,StateName,StateRawValueDataType,
LastModified,LastModifiedUser,AdministerSecurityGroup,NumberOfStatesInThisSet
TestSet5,TestDesc,1,10,State1Desc,State1,DoubleFloat,,,,2
TestSet5,TestDesc,11,20,State2Desc,State2,DoubleFloat,,,,2
```

A CSV File that Imports Array Tags

```
[Tags]
Tagname,Description,DataType,HiEngineeringUnits,LoEngineeringUnits,NumberOfElements
TIGER.IMPORT_TAG1.F_CV,Import Tag 1,SingleFloat,35000,0,-1
TIGER.IMPORT_TAG2.F_CV,Import Tag 2,SingleFloat,35000,0,0
TIGER.IMPORT_TAG3.F_CV,Import Tag 3,SingleFloat,35000,0,-1
TIGER.IMPORT_TAG4.F_CV,Import Tag 4,SingleFloat,35000,0,-1
```

A CSV File that Imports Array Tag Data

```
[Data]
Tagname,TimeStamp,Value,DataQuality
ArrayTag[0],6/11/2013 09:00:00,1,Good
ArrayTag[1],6/11/2013 09:00:00,2,Good
ArrayTag[2],6/11/2013 09:00:00,3,Good
```

```

ArrayTag[3],6/11/2013 09:00:00,4,Good
ArrayTag[0],6/11/2013 09:10:00,5,Good
ArrayTag[1],6/11/2013 09:10:00,6,Good
ArrayTag[2],6/11/2013 09:10:00,7,Good

```

A CSV File that Imports MultiField Tag Data

```

[Data]
Tagname,TimeStamp,Value,DataQuality
MultiField.F1,05-22-2013 14:15:00,4,Good
MultiField.F1,05-22-2013 14:15:01,7,Good
MultiField.F1,05-22-2013 14:15:02,9,Good
MultiField.F2,05-22-2013 14:15:00,241,Good
MultiField.F2,05-22-2013 14:15:01,171,Good
MultiField.F2,05-22-2013 14:15:02,191,Good

```



Note:

Before importing MultiField tag data in this format, you must add the User Defined Type using Historian Administrator and associate that type to the MultiField tag.

Importing s User-Defined Type

The following example allows you to import a user defined type **UDT1** with two fields, **Field1**, **Field2**. After creating, UDT1 associates with a tag called **Mfield**.

```

[UserDefinedType]
UserDefinedTypeName,UserDefinedTypeDescription,FieldName,FieldDescription,FieldDataType,IsMasterField,NumberOfFields
UDT1,UDTdesc,Field1,Fldesc,SingleInteger,FALSE,2
UDT1,UDTdesc,Field2,F2desc,DoubleInteger,FALSE,2

```

```

[Tags]
Tagname,Description,DataType,UserDefinedTypeName
Mfield,mfdesc,MultiField,UDT1

```

A CSV File that Imports Python Expression Tags

```

[Tag]
Tagname,CollectorName,CalcType,SourceAddress,DataType,Description
TagDerivedFromRawValue,SimulationCollector,PythonExpr,"{"imports":["math"],
"script":"tag.value + math.pow(10,tag.value/70)","parameters":[{"name":

```

```
"tag","source":{"address":"Simulation00001","dataType":"SingleFloat"}}",
SingleFloat,Python Expression Tag example
```

**Note:**

- Python Expression tags do not support array or multi-field tags.
- It is important to include the CalcType header and set it to PythonExpr for each Python Expression tag. If the file contains a mix of tags that are Python Expression tags with those that are not, then the tags that are not Python Expression tags must have the CalcType field set to Raw.
- For Python Expression tags, the SourceAddress must contain the tag's minified JSON configuration constructed as described in the topic on Constructing the JSON Configuration for a Python Expression Tag. (Mini-fied JSON has no newline characters or comments. There are tools which can help you minify JSON.)
- Note that the example in the CSV file uses repeated quotation marks (""") in order to escape quotation marks (").
- It is important that your JSON is valid, since no validation will be performed on the JSON at tag creation.

XML File Format

Format to import a List of Tags

```
<Import>
  <TagList>
    <Tag>
      <Tagname> .....</Tagname>
      <Description> Test </Description>
    </Tag>
  </TagList>
</Import>
```

Format to Import Data

```
<Import>
  <Datalist>
    <Tag>
      <Data>
```

```

        <Timestamp>..... </Timestamp>

        <Value>.... </Value>

    </Data>

</Tag>

</Datalist>

</Import>

```

Format to Import Messages

```

<Import>

  <MessageList>

    <Data>

      <Timestamp>..... </Timestamp>

      <Topic>.... </Topic>

      <Username>.... </Username>

      <MessageNumber>.... </MessageNumber>

      <MessageString>.... </MessageString>

      <Substitutions>.... </Substitutions>

    </Data>

  </MessageList>

</Import>

```

The following table provides a list of tag properties that you can import:

DataQuality	Value
Tagname	Description
EngineeringUnits	Comment
DataType	StringLength <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: StringLength is twice the number of characters (ASCII, Single Byte). For example, "ABC" = 6 StringLength.</p> </div>
StoreMilliseconds	CollectorName
CollectorType	SourceAddress

DataQuality	Value
	<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: A value is required for the source name to be added to tags created by the collector. </div>
CollectorType	CollectionInterval
CollectionOffset	CollectionDisabled
LoadBalancing	TimeStamp <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: The timestamp resolution is milliseconds. </div>
Type	TimeZoneBias
HiEngineeringUnits	LoEngineeringUnits
InputScaling	HiScale
LoScale	CollectorCompression
CollectorDeadband-PercentRange	CollectorCompressionTimeout
ArchiveCompression	ArchiveDeadbandPercentRange
ArchiveCompression-Timeout	Timeout
CollectorGeneral1	CollectorGeneral2
CollectorGeneral3	CollectorGeneral4
CollectorGeneral5	ReadSecurityGroup
WriteSecurityGroup	AdministratorSecurityGroup
Calculation	CalculationDependencies
Acked	Condition
SubCondition	EventCategory
Message	Source
Severity	StartTime

DataQuality	Value
EndTime	TimestampType
SpikeLogic	SpikeLogicOverride
InterfaceAbsolute-Deadband	InterfaceAbsoluteDeadbanding
LastModified	LastModifiedUser
ArchiveAbsoluteDead-band	ArchiveAbsoluteDeadbanding
StepValue	Value
SpikeLogic	SpikeLogicOverride
NumberOfElements	CalcType

An XML File that Imports Tags

```

<Import>

  <TagList Version="1.0.71">

    <Tag Name="TIGER.IMPORT_TAG1.F_CV">

      <Tagname>TIGER.IMPORT_TAG1.F_CV</Tagname>

      <Description>Import Tag 1</Description>

      <EngineeringUnits> PSI </EngineeringUnits>

    </Tag>

    <Tag Name="TIGER.IMPORT_TAG11.F_CV">

      <Tagname>TIGER.IMPORT_TAG11.F_CV</Tagname>

      <Description>Import Tag 1</Description>

      <EngineeringUnits> PSI </EngineeringUnits>

    </Tag>

    <Tag Name="TIGER.IMPORT_TAG12.F_CV">

      <Tagname>TIGER.IMPORT_TAG12.F_CV</Tagname>

      <Description>Import Tag 2</Description>

      <EngineeringUnits> PSI </EngineeringUnits>

    </Tag>

    <Tag Name="TIGER.IMPORT_TAG13.F_CV">

      <Tagname>TIGER.IMPORT_TAG13.F_CV</Tagname>

      <Description>Import Tag 3</Description>

      <EngineeringUnits> PSI </EngineeringUnits>
  
```

```

</Tag>
<Tag Name="TIGER.IMPORT_TAG14.F_CV">
  <Tagname>TIGER.IMPORT_TAG14.F_CV</Tagname>
  <Description>Import Tag 4</Description>
  <EngineeringUnits> PSI </EngineeringUnits>
</Tag>
<Tag Name="TIGER.IMPORT_TAG15.F_CV">
  <Tagname>TIGER.IMPORT_TAG15.F_CV</Tagname>
  <Description>Import Tag 5</Description>
  <EngineeringUnits> PSI </EngineeringUnits>
</Tag>
<Tag Name="TIGER.IMPORT_TAG2.F_CV">
  <Tagname>TIGER.IMPORT_TAG2.F_CV</Tagname>
  <Description>Import Tag 2</Description>
  <EngineeringUnits> PSI </EngineeringUnits>
</Tag>
<Tag Name="TIGER.IMPORT_TAG21.F_CV">
  <Tagname>TIGER.IMPORT_TAG21.F_CV</Tagname>
  <Description>Import Tag 1</Description>
  <EngineeringUnits> PSI </EngineeringUnits>
</Tag>
</TagList>
</Import>

```

Example of an XML file that Imports Data and Data Quality

```

<Import>
  <DataList Version="1.0.71">
    <Tag Name="TIGER.IMPORT_TAG1.F_CV">
      <Data>
        <TimeStamp>20-Jul-2001 11:00:18.000</TimeStamp>
        <Value>0</Value>
        <DataQuality>Good</DataQuality>
      </Data>
      <Data>
        <TimeStamp>20-Jul-2001 11:00:36.000</TimeStamp>
        <Value>0</Value>
        <DataQuality>Good</DataQuality>
      </Data>
    </Tag>
  </DataList>
</Import>

```

```

    </Data>
    <Data>
      <TimeStamp>20-Jul-2001 11:00:54.000</TimeStamp>
      <Value>0</Value>
      <DataQuality>Bad</DataQuality>
    </Data>
    <Data>
      <TimeStamp>20-Jul-2001 11:01:12.000</TimeStamp>
      <Value>0</Value>
      <DataQuality>Good</DataQuality>
    </Data>
  </Tag>
</DataList>
</Import>

```

An XML file that Imports Messages

```

<Import>
  <MessageList Version="1.0.71">
    <Data>
      <TimeStamp>28-Aug-2002 19:42:00.000</TimeStamp>
      <Topic>General</Topic>
      <Username>XMLUser</Username>
      <MessageNumber>0</MessageNumber>
      <MessageString>Another test message</MessageString>
      <Substitutions></Substitutions>
    </Data>
    <Data>
      <TimeStamp>28-Aug-2002 19:48:00.000</TimeStamp>
      <Topic>General</Topic>
      <Username>XMLUser</Username>
      <MessageNumber>1</MessageNumber>
      <MessageString>Message One</MessageString>
      <Substitutions></Substitutions>
    </Data>
  </MessageList>
</Import>

```

An XML file that Imports a Tag with a Step Value

```
<Import>
  <TagList Version="1.0.71">
    <Tag Name="TAG6">
      <TagName>TAG6</TagName>
      <StepValue> TRUE </StepValue>
    </Tag>
  </TagList>
</Import>
```

An XML file that Imports Alarms

```
<Import>
  <AlarmList Version="1.0.71">
    <Alarm>
      <Attribute name="Acked" value="false"/>
      <Attribute name="Actor" value="TheActor"/>
      <Attribute name="Condition" value="Condition"/>
      <Attribute name="DataSource" value="File collector"/>
      <Attribute name="Enabled" value="true"/>
      <Attribute name="EndTime" value="12/25/2005 12:47:59.003"/>
      <Attribute name="EventCategory" value="Process"/>
      <Attribute name="Message" value="My message."/>
      <Attribute name="Quality" value="Good"/>
      <Attribute name="Severity" value="250"/>
      <Attribute name="Source" value="SourceXML000003"/>
      <Attribute name="StartTime" value="12/25/2005 12:47:59.003"/>
      <Attribute name="SubCondition" value="Hi"/>
      <Attribute name="TagName" value="TheTagName"/>
      <Attribute name="Timestamp" value="12/09/2005 12:47:59.003"/>
    </Alarm>
    <Alarm>
      <Attribute name="Acked" value="false"/>
      <Attribute name="Actor" value="TheActor"/>
      <Attribute name="Condition" value="Condition"/>
      <Attribute name="DataSource" value="File collector"/>
      <Attribute name="Enabled" value="true"/>
      <Attribute name="EndTime" value="12/25/2005 12:47:59.004"/>
```

```

<Attribute name="EventCategory" value="Process"/>
<Attribute name="Message" value="My message."/>
<Attribute name="Quality" value="Good"/>
<Attribute name="Severity" value="250"/>
<Attribute name="Source" value="SourceXML000004"/>
<Attribute name="StartTime" value="12/25/2005 12:47:59.004"/>
<Attribute name="SubCondition" value="Hi"/>
<Attribute name="TagName" value="TheTagName"/>
<Attribute name="Timestamp" value="12/25/2005 12:47:59.004"/>

</Alarm>

</AlarmList>

</Import>

```

An XML file that Imports Enumerated Set

```

<Import>
  <EnumeratedSetList>
    <EnumeratedSet SetName="TestSet7">
      <EnumeratedState StateName="State1">
        <SetName>TestSet7</SetName>
        <SetDescription>TestDesc</SetDescription>
        <StateLowRawValue>1</StateLowRawValue>
        <StateHighRawValue>10</StateHighRawValue>
        <StateDescription>State1Desc</StateDescription>
        <StateName>State1</StateName>
        <StateRawValueDataType>DoubleFloat</StateRawValueDataType>
        <LastModified>9/17/2012 16:37:48.260000</LastModified>
        <LastModifiedUser>GECORPORATE\312006949</LastModifiedUser>
        <AdministratorSecurityGroup></AdministratorSecurityGroup>
        <NumberOfStatesInThisSet>2</NumberOfStatesInThisSet>
      </EnumeratedState>
      <EnumeratedState StateName="State2">
        <SetName>TestSet7</SetName>
        <SetDescription>TestDesc</SetDescription>
        <StateLowRawValue>11</StateLowRawValue>
        <StateHighRawValue>20</StateHighRawValue>
        <StateDescription>State2Desc</StateDescription>
        <StateName>State2</StateName>
      </EnumeratedState>
    </EnumeratedSet>
  </EnumeratedSetList>
</Import>

```

```

    <StateRawValueDataType>DoubleFloat</StateRawValueDataType>

    <LastModified>9/17/2012 16:37:48.260000</LastModified>

    <LastModifiedUser>GECORPORATE\312006949</LastModifiedUser>

    <AdministratorSecurityGroup></AdministratorSecurityGroup>

    <NumberOfStatesInThisSet>2</NumberOfStatesInThisSet>

  </EnumeratedState>

</EnumeratedSet>

</EnumeratedSetList>

</Import>

```

An XML File that Imports Array Tags

```

<Import>

  <TagList Version="1.0.71">

    <Tag Name="ArrayTag1">

      <Tagname>ArrayTag</Tagname>

      <Description>Import array Tag 1</Description>

      <EngineeringUnits> PSI </EngineeringUnits>

      <NumberOfElements>-1</NumberOfElements>

    </Tag>

    <Tag Name="ArrayTag2">

      <Tagname>ArrayTag2</Tagname>

      <Description>Import array Tag 2</Description>

      <EngineeringUnits> PSI </EngineeringUnits>

      <NumberOfElements>-1</NumberOfElements>

    </Tag>

  </TagList>

</Import>

```

An XML File that Imports Array Tag data

```

<Import>

  <DataList Version="1.0.71">

    <Tag Name="ArrayTag[0]">

      <Data>

        <TimeStamp>11-June-2013 11:00:18.000</TimeStamp>

        <Value>1</Value>

        <DataQuality>Good</DataQuality>

      </Data>

    </Tag>

  </DataList>

</Import>

```

```

    <Data>
      <TimeStamp>11-June-2013 11:01:18.000</TimeStamp>
      <Value>2</Value>
      <DataQuality>Good</DataQuality>
    </Data>
  </Tag>
  <Tag Name="ArrayTag[1]">
    <Data>
      <TimeStamp>11-June-2013 11:00:18.000</TimeStamp>
      <Value>3</Value>
      <DataQuality>Good</DataQuality>
    </Data>
    <Data>
      <TimeStamp>11-June-2013 11:01:18.000</TimeStamp>
      <Value>4</Value>
      <DataQuality>Good</DataQuality>
    </Data>
  </Tag>
</DataList>
</Import>

```

An XML File that Imports Python Expression Tags

```

<Import>
  <TagList Version="1.0.71">
    <Tag Name="TagDerivedFromRawValue">
      <TagName>TagDerivedFromRawValue</TagName>
      <CollectorName>OpcServerCollector</CollectorName>
      <SourceAddress>
        "{ \"imports\": [ \"math\" ], \"script\": \"tag.value + math.pow(10, tag.value/70)\", \"parameters\": [ { \"name\": \"tag\", \"source\": { \"address\": \"IO/READONLY/Temperature\", \"dataType\": \"DoubleFloat\" } } ] }"
      </SourceAddress>
      <CalcType>PythonExpr</CalcType>
      <DataType>DoubleFloat</DataType>
      <Description>Python Expression Tag example</Description>
    </Tag>
  </TagList>
</Import>

```

**Note:**

- Python Expression tags do not support array or multi-field tags.
- It is important to include the CalcType header and set it to PythonExpr for each Python Expression tag. If the file contains a mix of tags that are Python Expression tags with those that are not, then the tags that are not Python Expression tags must have the CalcType field set to Raw.
- For Python Expression tags, the SourceAddress must contain the tag's minified JSON configuration constructed as described in the topic on Constructing the JSON Configuration for a Python Expression Tag. (Mini-fied JSON has no newline characters or comments. There are tools which can help you minify JSON.)
- Note that the example in the CSV file uses repeated quotation marks (""") in order to escape quotation marks (").
- It is important that your JSON is valid, since no validation will be performed on the JSON at tag creation.

Troubleshooting the File Collector

Accessing the Log File

By default, the log file of the collector is saved in the following folder: `C:\Proficy Historian Data\LogFiles`.

If you are experiencing any problems with the collector, use the log file to troubleshoot. The log file sometimes logs errors that are not processed to Historian Administrator. For example, if you have no archives in your system and you attempt to import a .CSV file with formatting errors, the file is not processed and no alerts are sent to Historian Administrator (if there are no archives created, the message database has not been created). But this error does appear in the log file.

Typical Error Messages and Suggested Solutions

Error Message	Troubleshooting Tips
12-Aug-0113:38:00 - Import Line Error: Input past end of file	There is an extra line in the file. Remove it.
12-Aug-0113:38:00 - Error Occurred On Line12: General Format Error	

Error Message	Troubleshooting Tips
10-Aug-01 15:47:02 - Import Line Error: Type mismatch 10-Aug-01 15:47:02 - Error Occurred On Line 2: General Format Error	Two fields were combined into one due to a missing comma. Add a comma.
12-Aug-01 14:18:12 - Invalid Import Field: TimeResolution 12-Aug-01 14:18:12 - zProcessFragment>> Aborted Import Due To Formatting Errors	If an import field is invalid (in this case Time resolution should be StoreMilliseconds), the import will abort.

Identifying Lines in which an Error Occurs

Suppose the log file contains an error description as follows:

```
20-Jul-01 10:1717 - Import Line Error: Input past end of file
20-Jul-01 10:1717 - Error occurred on Line 7:General Format Error
```

The line number in the log is produced by the SDK, not the File collector. This means that the line number is counted relative to the header or field list for each section of the file, ignoring comments and blank lines.

CSV File Import Issues

A CSV file may not be imported if:

- It contains an extra line.
- It contains extra commas on the data line.
- The file size is greater than 10 MB. Ideally, the file size must be between 1 and 2 MB.
- The data in the file goes beyond the Archive Active Hours value (by default, 1 month).
- The first archive is not yet created.

If you view the CSV file using Microsoft Excel, some characters are not visible. We recommend that you use a text editor to examine files that are causing format errors when you attempt to import them.

Troubleshooting Large File Import

To prevent a locked file scenario when building large files for import into the Incoming directory, first build the file under a temporary file name or directory that will be ignored by the File collector, then rename or move the file to the real file name or Import directory when the file is fully built.

Unable to Access Historian Administrator After Installing the File Collector

If you encounter problems in accessing Historian Administrator after installing the File collector, upgrade the Historian Server. On upgrading the File collector from 7.0 SP2\7.0 SP3\7.0 SP4 to 7.0 SP5 or later, you will notice the following:

- The previous version of the collector is in the stopped state and the new version of the collector is in the running state.
- The data collection is stopped for the tags added in the older version.

To avoid this issue:

- Change the collector to the newer version in **Tag properties** for all the tags which were added using the older version of the collector.
- Delete the older version of the collector from the **Collectors** section in Historian Administrator.

File Collector is not available in Admin clients

If the File collector is running, but still not available in Admin clients, then you should register the following DLLs:

32-bit machine

- c:\windows\system32\regsvr32 ihAPICOM.dll
- c:\windows\system32\regsvr32 ihaSDK.dll

64-bit machine

- c:\windows\syswow64\regsvr32 ihAPICOM.dll
- c:\windows\syswow64\regsvr32 ihaSDK.dll

Chapter 18. The HAB Collector

Overview of the HAB Collector

The HAB collector collects data from Habitat, which is a SCADA application that contains real-time data. The collector interacts with the Habitat Sampler application to fetch data from the Habitat database records and stores the data in a Historian server.

Features:

- **Tags as well as alarms data collection:** The collector can collect data for tags as well as alarms. Although a single collector instance can be used for both, we recommend that you use separate collector instances for tags and alarms.
- **High availability:** You can achieve high availability by configuring redundant collector instances connected to redundant Habitat servers. For more information, refer to [High Availability \(on page 2210\)](#).
- **Automatic tag sync:** The HAB collector creates tags automatically in Historian. When additional tags are added in Habitat, or when tags are renamed or deleted, the changes are reflected automatically in Historian. You can, however, choose to do it manually if you want to review the changes first. When you do so, only after you approve the changes, they are reflected in Historian. For more information, refer to [Approve Tag Changes \(on page 2243\)](#).
- **Tag deletion versus disablement:** When a tag is deleted in Habitat, you can choose to delete it in Historian or disable data collection for the tag. For more information, refer to [Configure the HAB Collector for Tags \(on page 2219\)](#) and [Configure the HAB Collector for Alarms \(on page 2230\)](#).
- **Multiple instances:** You can create multiple instances of the HAB collector either on the same machine or on different ones. For example, one instance can collect data for tags with a faster streaming rate, while the other instance can collect data for tags with a slower streaming rate. For each instance, you must create a configuration file. For more information, refer to [Configure the HAB Collector for Tags \(on page 2219\)](#) and [Configure the HAB Collector for Alarms \(on page 2230\)](#).
- **No dependency on an external database:** Since data is stored in archive files, you do not require an external database (especially for alarms data, which is huge).
- **Supported timestamp resolution:** The supported timestamp resolution is 1 second.
- **Unsolicited as well as polled data collection:** For tags, both the polled as well as unsolicited data collection are supported. For alarms, only the unsolicited data collection is supported.
- **Supported data types:** Floating point, integer, string, and binary data are supported.
- The collector accepts device timestamps.

How it works when automatic tag sync is enabled:

1. You specify the site details of Habitat and collection definitions in the configuration file, and start the collector.
2. The collector connects to the Habitat Sampler application.
3. Depending on the key value that you have provided in the configuration file, tags are created in Historian with the following naming convention: *<host name of the Habitat server>.<composite key>.<field name in Habitat>*
4. Data collection begins.
5. When tags are added, renamed, or deleted later in Habitat, the changes are reflected automatically in Historian. No manual steps are required.

How it works when automatic tag sync is disabled:

1. You specify the site details of Habitat and collection definitions in the configuration file, and start the collector.
2. The collector connects to the Habitat Sampler application.
3. Depending on the key value that you have provided in the configuration file, tags in Habitat are listed in the *<collector name>_Tag_Unconfirmed.xml* file under the ProposedTags section. These tags use the following naming convention: *<host name of the Habitat server>.<composite key>.<field name in Habitat>*
4. You [approve the tags \(on page 2243\)](#) that must be created in Historian.
5. The tags that you approve are created in Historian.
6. Data collection begins.
7. When tags are added, renamed, or deleted later in Habitat, you must again [approve these changes \(on page 2243\)](#). Only then they are reflected in Historian.

The tags created in Historian contain the MRID and composite key values of the corresponding Habitat record. Although MRID is constant for a tag, the composite key value can change if there is a change in the transmission/distribution lines. Therefore, the collector uses the MRID value to identify whether a tag is a newly added one or an old one that has been renamed. And the composite key is used in naming the tags created in Historian.

Supported data types:


- Float
- Integer
- String
- Boolean

High Availability

High availability of the Habitat server and the HAB collector provides uninterrupted data collection. You can configure a stand-by Habitat server and/or a second instance of the HAB collector to achieve high availability.


You can choose one of the following types of configuration:

- **Single collector instance and single Habitat server:** In this configuration, a single HAB collector instance collects data from a single Habitat server.




To set up this configuration, [create a collector instance \(on page 489\)](#), and [provide the details of the Habitat site \(on page 2219\)](#) in the configuration file of the collector instance.

- **Redundant collector instances and single Habitat server:** In this configuration, a single Habitat server is connected to two collector instances - one active and the other one standby. If the active collector instance is not available, data is collected by the standby collector instance.




To set up this configuration, [create two instances of the collector \(on page 489\)](#), and [provide and same site details \(on page 2219\)](#) for both of them.

- **Single collector instance and redundant Habitat servers:** In this configuration, a single collector instance is connected to two Habitat servers - one active and the other one is standby. If the active server is down, the standby server accepts requests from the collector and sends data.



To set up this configuration, [create a collector instance \(on page 489\)](#), and [provide the details \(on page 2219\)](#) of the active and standby Habitat servers in the Node1 and Node2 parameters respectively in the configuration file.

- Redundant collector instances and redundant Habitat servers:** In this configuration, two collector instances are connected to two Habitat servers. The active collector instance collects data from the active Habitat server. If the active collector instance is not available, data is collected by the standby collector instance. If the active Habitat server is down, the standby server accepts requests from the active collector instance.



To set up this configuration:

1. [Create two instances of the collector \(on page 489\)](#).
2. For both the instances, [provide the details \(on page 2219\)](#) of the active and standby Habitat servers in the Node1 and Node2 parameters respectively in the configuration file.


In addition to the high availability options provided by the collector and the Habitat server, you can set up data mirroring in the Historian server. For information, refer to [About Data Mirroring \(on page 367\)](#). Or you can [install Historian in a cluster environment \(on page 119\)](#).

Configuration

Add and Configure a HAB Collector

The HAB collector collects data from Habitat, which is a SCADA application that contains real-time data. The collector interacts with the Habitat Sampler application to fetch data from the Habitat database records and stores the data in a Historian server. For more information, refer to [Overview of the HAB Collector \(on page 2208\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. On the right, next to Settings in the main section, select .



The screenshot shows the 'Collectors' configuration page in the Historian interface. The page title is 'Collectors' and it includes a 'DETAILS' tab. The main content area is titled 'Historian Collectors' and 'Offline Configuration Collectors'. It shows a refresh button with a plus sign icon highlighted in a red box, and a settings gear icon. Below this is a table with columns for 'COLLECTOR NAME' and 'STATUS'. The table contains two rows: 'Calculation' with status 'Running' and 'Simulation' with status 'Running'. The right-hand side of the page shows 'No data to display.'

COLLECTOR NAME	STATUS
Calculation	Running
Simulation	Running

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **Hab Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. Enter values as described in the following table.

Field	Description
SERVER SITE	Enter name that you want to assign to the site. A value is required and must be unique. It is used by Habitat to identify the collector instance. By default, this field is populated with a value in the following format: <code><Historian server name>Hab</code>
SERVER 1 (under NODE 1)	Enter the host name or IP address of the Habitat server in the primary site from which you want to collect data. This server acts as the primary/active server from which the collector receives data. A value is required.
SERVER 1 (under NODE 2)	Enter the host name or IP address of the Habitat server in the second/backup site from which you want to collect data. This server acts as a standby server in case server 1 under node 1 fails. A value is required. If you do not have a secondary/backup site, enter the same value as SERVER 1 under node 1.
SERVER 2 (under NODE 1)	Enter the host name or IP address of the Habitat server that you want to use as a standby server in the same site as server 1. This server acts as a standby server in case server 1 under node 2 fails.
SERVER 2 (under NODE 2)	Enter the host name or IP address of the Habitat server in the secondary/backup site from which you want to collect data. This server acts as a standby server in case server 2 under node 1 fails. For example, suppose Machine A and Machine B are in node AB, and Machine X and Machine Y are in node XY. Suppose you

Field	Description
	<p>want to use Machine A as the primary server and the remaining machines as standby servers. In that case, enter values as follows:</p> <ul style="list-style-type: none"> ◦ SERVER 1 (under Node 1): Machine A ◦ SERVER 2 (under Node 1): Machine B ◦ SERVER 1 (under Node 2): Machine X ◦ SERVER 2 (under Node 2): Machine Y <p>If Machine A fails, the Machine B becomes active. If Machine B fails, Machine X becomes active. If Machine X fails, Machine Y becomes active.</p>
SOCKET	<p>The socket number (port number) used by the Habitat Sampler application to connect. Each collector instance can connect to only one socket. The default value is 8040.</p>
RETRY	<p>The duration, in seconds, after which the collector tries to communicate with the site. The default value is 5 seconds.</p>

8. Select **Next**.

The **Destination Configuration** section appears. Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. The other options are disabled because you cannot send data to a cloud destination using the HAB collector.

9. If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears. By default, the **COLLECTOR NAME** field is populated with a value in the following format: `<Historian server name>_Hab`

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.

- Must not contain a space.
 - Must not contain special characters except a hyphen, period, and an underscore.
12. In the **SamplerID** field, enter the user ID to connect to Habitat Sampler.

By default, this field contains the Collector Name. You can first provide the Collector Name and update the Sample ID field as this field will automatically take the Collector Name.

13. In the **RUNNING MODE** field, select one of the following options.
- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled. By default, this option is selected.
 - **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

14. Select **Add**.

The collector instance is added. The fields specific to the collector appear in the **DETAILS** section.

15. Depending on whether you want to configure tags or alarms, select  next to the corresponding field under **Collection Definitions**.

DETAILS	
FIELD	VALUE
<div style="background-color: #f2f2f2; padding: 2px;"> ▼ General </div>	
Collector Name	██████████_Hab
Collector Type	Hab Collector
Description	██████████_Hab
Memory Buffer Size(MB)	20
Minimum Free Space(MB)	150
Total Events Collected	0
Total Events Reported	0
<div style="background-color: #f2f2f2; padding: 2px;"> ▼ Collection Definitions </div>	
Data Collection Definitions	0 
Alarm Collection Definitions	0 

The **Data Collections** or **Alarm Collections** section appears.


16. Select **+**, and then enter values in the available fields for [data collection and/or alarm collection \(on page 495\)](#). You can also copy a collection definition by right-clicking it and selecting **Duplicate**.
17. Under **COLLECTOR SPECIFIC CONFIGURATION**, configure values as described in the following table.

Field	Description
Auto Tag Sync	<p>If you enable this option, the collector creates tags automatically in Historian based on the key value. In addition, any tag changes in Habitat (such as adding, renaming, and deleting tags) will reflect automatically in Historian. No manual steps are required.</p> <p>If you disable this option, any tag changes in Habitat will be captured in the <code><collector name>_Tag_Unconfirmed.xml</code> file. Only after you approve these changes (on page 2243), they are reflected in Historian.</p>
Tag Deletion Type	<p>Specify whether deleted tags in Habitat that you have approved must be deleted or disabled for data collection in Historian. Enter one of the following values:</p>

Field	Description
	<ul style="list-style-type: none"> ◦ DISABLE_TAG (this is the default value) ◦ DELETE_TAG
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

18. As needed, provide values in the [the other sections common to all collectors \(on page 579\)](#).

19. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

20. [Start the collector \(on page 637\)](#).

If you have disabled the automatic tag sync option in the configuration file, tag changes in Habitat (such as adding, renaming, and deleting tags) are captured in the `<collector_name>_tag.xml` file. You must approve the changes so that they are reflected in Historian. To do so:

1. Right-click the HAB collector instance that you have created, and then select **Confirm Queued Tags**.

A list of tags that have been changed appears.

2. Select the check boxes corresponding to the tags whose changes you want to approve, and then select **Confirm**. You can filter the list using the **TAG TYPE** field.

The tag changes are approved. The status of the tags is updated in the `<collector_name>_tag.xml` file (that is, the Confirmed parameter is set to true).

Configure the HAB Collector for Tags

Create an instance of the HAB collector ([on page 489](#)).

A configuration file is created when you install collectors. This file contains the following types of information, which are required for the Sampler application to connect to Habitat.

- **Site parameters:** Contains the location details of Habitat from which you want to collect data. A single site can contain one or two nodes (the two nodes are used for a primary/standby configuration).

A configuration file can contain only one Site section.

- **Collector parameters:** Contains the following parameters:
 - **Automatic tag sync:** If the automatic tag sync option is enabled in the configuration file, when tags are added, renamed, or deleted in Habitat, the changes are reflected automatically in Historian. No manual steps are required; data collection begins automatically depending on the collection definition that you have provided in the configuration file. If, however, the automatic tag sync is disabled, you must approve tag changes, and only then they are reflected in Historian. For more information, refer to [Approve Tag Changes \(on page 2243\)](#). Depending on the collection definition that you have provided in the configuration file, tags are created in Historian, and data collection is initiated.
 - **Tag deletion versus disablement:** For tags deleted in Habitat, you must specify whether they must be deleted in Historian or just disabled for data collection.

A configuration file can contain only one CollectorParameter section.

- **Collection definition parameters:** Specifies which data to collect and how. For example, the Habitat application, database, and the family from which you want to collect data, whether the data is polled or unsolicited (that is, periodic or exception), the mapping between tag properties and the corresponding fields in Habitat, etc. There are two types of collection definition parameters: tag data collection and alarm data collection.

A configuration file can contain multiple DataCollectionDefinition sections. If you do not want to use a collection definition for now, you can set the State parameter to DISABLED.

In addition to tags, you can specify values for these parameters for alarms. We recommend that you create a separate collector instance to collect alarm data. You must then [configure alarms \(on page 2230\)](#) in a separate file.

1. Access the `<collector name>_Config.xml` file. By default, it is located at `C:\Program Files\GE Digital\Historian HAB Collector\Server`.
2. Enter values as specified in the following tables.

Table 375. Site Parameters

Parameter	Description
Name	The name that you want to assign to the site.
Node1	The host name or IP address of the Habitat server (node) in the site from which you want to collect data. This server acts as the primary/active server from which the collector receives data.
Node2	<p>If you want to achieve high availability by connecting to redundant Habitat servers, provide the host names or IP addresses of both the servers - the active server in Node1 and the standby server in Node2.</p> <div data-bbox="669 898 1421 1537" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <p>You can provide the IP addresses of up to four Habitat servers - two of them in Node1 and other two in Node2, separated by commas.</p> <p>For example, if you want to connect to MachineA, MachineB, MachineC, and MachineD, enter:</p> <pre data-bbox="760 1243 1096 1312" style="background-color: #FFF2CC; padding: 5px;"> <Node1>MachineA,MachineB</Node1> <Node2>MachineC,MachineD</Node2> </pre> <p>If you do so, MachineA becomes the active Habitat server, and in case of a failover, MachineB, MachineC, and MachineD each become active servers - one-by-one, in that order.</p> </div> <p>For information on the various ways of achieving high availability, refer to High Availability (on page 2210).</p>
Socket	The socket number (port number) used by the Habitat Sampler application to connect. Each collector instance can connect to only one socket. The default value is 8040.

Parameter	Description
Retry	The duration, in seconds, after which the collector tries to communicate with the site. The default value is 5.

Example:

```
<Site>
  <Name>Site1</Name>
  <Node1>Host1</Node1>
  <Node2>Host2</Node2>
  <Socket>8040</Socket>
  <Retry>5</Retry>
</Site>
```

Table 376. Collector Parameters

Parameter	Description	Valid Values
AutoTagSync	Indicates whether tags must be created initially when the collector is connected to the Habitat Sampler application. It also indicates whether tags must be created, renamed, or deleted later automatically when the corresponding changes are done in Habitat. If you disable this option, you must manually confirm these changes. For example, if 10 tags are added in Habitat, you must confirm which of them must be created in Historian. For instructions, refer to Approve Tag Changes (on page 2243) .	<ul style="list-style-type: none"> ◦ TRUE ◦ FALSE
TagDeletionType	Specifies whether tags deleted in Habitat must be deleted or just disabled for data collection in Historian.	<ul style="list-style-type: none"> ◦ DISABLE_TAG ◦ DELETE_TAG

Example:

```
<CollectorParameter>
  <AutoTagSync>TRUE</AutoTagSync>
  <TagDeletionType>DISABLE_TAG</TagDeletionType>
</CollectorParameter>
```

Table 377. Collection Definition Parameters

Parameter	Description	Valid Values
Name	<p>The name of the collection definition. A value is required and must be unique.</p> <div data-bbox="516 478 959 926" style="border: 1px solid orange; border-radius: 10px; padding: 10px; background-color: #fff9c4;"> <p>! Important: You must not change the name after the collector starts collecting data. If, however, you want to change the name after the collector has started collecting data, refer to FAQs on HAB Collector (on page 2246).</p> </div>	
id	<p>Identifies the collection definition. A value is required and must be unique.</p> <div data-bbox="516 1066 959 1514" style="border: 1px solid orange; border-radius: 10px; padding: 10px; background-color: #fff9c4;"> <p>! Important: You must not change the ID after the collector starts collecting data. If, however, you want to change the ID after the collector has started collecting data, refer to FAQs on HAB Collector (on page 2246).</p> </div>	
Site	<p>The name of the site in Habitat from which you want to collect data. Provide the same value as the one you provided for the Name parameter in the Site section.</p>	

Parameter	Description	Valid Values
Valid	Indicates whether the collection definition is valid.	<ul style="list-style-type: none"> ◦ TRUE: Indicates that the collection definition is valid. ◦ FALSE: Indicates that an error has occurred while processing the collection definition. In this case, the collector also sets the State parameter to DISABLED so that this collection definition is not considered.
State	Indicates whether the collection definition is enabled.	<ul style="list-style-type: none"> ◦ ENABLED: Indicates that the collector is processing the collection definition. ◦ DISABLED: Indicates that this data collection is not being used. You can manually disable a collection definition. Or if an error has occurred while processing the collection definition, the collector automatically sets this parameter to DISABLED.
Application	The name of the Habitat application from which you want to collect data (for example, SCADA).	
Database	The name of the Habitat database from which you want to collect data (for example, SCADAMOM).	
Family	The name of the Habitat family from which you want to collect data (for example, EMS, DTS). A value is required and must be unique.	

Parameter	Description	Valid Values
RecordType	The name of the HDB record from which you want to collect data (for example, ANALOG,POINT,COUNT).	Any record type that contains the composite key and MRID fields (because the collector uses these two fields to create tags).
CollectionType	Indicates whether you want to perform polled or unsolicited data collection.	<ul style="list-style-type: none"> ◦ Polled: Indicates a periodic data collection, where data is collected at a regular time interval (indicated as PERIODIC in Habitat). ◦ Unsolicited: Indicates that data is collected only when values have changed since the last time data was collected (indicated as EXCEPTION in Habitat).
Key	The value that will be used to filter tags for data collection. You can use the wildcard character * to get a range of values. For example, if you want to collect data from all tags that begin with SUBSTN.LAKEVIEW, enter: SUBSTN.LAKEVIEW*.*.*.*	
TagPrefix	The prefix that you want to use for tags. You can provide a different value for each collection definition, which helps you identify tags based on the collection definition.	
TagNameField	The composite key of the record. A value is required. If, however, the composite key is not available, enter any other unique identifier of the record.	
MRIDField	The MRID of the record. A value is required. If, however, MRID is not avail-	

Parameter	Description	Valid Values
	able, enter the composite key or any other unique identifier of the record.	
TagDescField	The description of the tag. A value is required.	
ValueFields	<p>The list of fields in Habitat that contain tag values that you want to collect. A value is required.</p> <p>For example, if tag values are stored in the DIS_ANALOG field in Habitat, respectively, enter:</p> <pre data-bbox="521 785 956 1152"> <TagTemplate> <TagPrefix>GENTAG</TagPrefix> <TagNameField>\$KEY_PLC</TagNameField> <MRID>MRID_PLC</MRID> <ValueFields>DIS_ANALOG</value> <Timestamp>SCTIME_ANALOG</Timestamp> <Quality>DFLAGS_ANALOG</Quality> </TagTemplate> </pre> <p>For the Value parameter, you can enter multiple values, separated by commas. The values will then be concatenated in the corresponding Historian tag (for example, <code><Value>DIS_ANALOG,ESTIMATE_ANALOG SCTIME_ANALOG,DFLAGS_ANALOG</Value></code>).</p> <p>For the Timestamp parameter, you can use a HDB timestamp or custom/alias timestamps.</p> <p>For analog, you can use:</p>	

Parameter	Description	Valid Values
	<ul style="list-style-type: none"> ◦ FIELDTIME: A combination of FLDTIME_ANALOG and FLD-MSEC_ANALOG, in the hour: min:sec: millisec format. ◦ SCADATIME: Used to capture SCTIME_ANALOG in the hour: min:sec: millisec format. ◦ SAMPLETIME: The time at which the data sample was collected in Habitat in the hour: min:sec format. <p>For point, you can use:</p> <ul style="list-style-type: none"> ◦ FIELDTIME: A combination of FLDTIME_POINT and FLD-MSEC_POINT, in the hour: min:sec: millisec format. ◦ SCADATIME: Used to capture SCTIME_POINT in the hour: min:sec: millisec format. ◦ SAMPLETIME: The time at which the data sample was collected in Habitat in the hour: min:sec format. <p>For count, you can use:</p> <ul style="list-style-type: none"> ◦ FIELDTIME: A combination of FLDTIME_COUNT and FLD-MSEC_COUNT, in the hour: min:sec: millisec format. ◦ SAMPLETIME: The time at which the data sample was collected in Habitat in the hour: min:sec format. <p>You can edit the names of these custom/alias timestamps using the reg-</p>	

Parameter	Description	Valid Values
	istry entries FieldTimeCustomFieldName, ScadaTimeCustomFieldName, and SampleTimeCustomFieldName respectively.	
TimestampFields	<p>The name of the property that stores the timestamp of a tag in Habitat. You can use a HDB timestamp or custom/alias timestamps.</p> <p>Examples:</p> <p>For analog, you can use:</p> <ul style="list-style-type: none"> ◦ FIELDTIME: A combination of FLDTIME_ANALOG and FLD-MSEC_ANALOG, in the hour: min:sec: millisec format. ◦ SCADATIME: Used to capture SCTIME_ANALOG in the hour: min:sec: millisec format. ◦ SAMPLETIME: The time at which the data sample was collected in Habitat in the hour: min:sec format. <p>For point, you can use:</p> <ul style="list-style-type: none"> ◦ FIELDTIME: A combination of FLDTIME_POINT and FLD-MSEC_POINT, in the hour: min:sec: millisec format. ◦ SCADATIME: Used to capture SCTIME_POINT in the hour: min:sec: millisec format. ◦ SAMPLETIME: The time at which the data sample was collected in Habitat in the hour: min:sec format. <p>For count, you can use:</p>	

Parameter	Description	Valid Values
	<ul style="list-style-type: none"> ◦ FIELDTIME: A combination of FLDTIME_COUNT and FLD-MSEC_COUNT, in the hour: min:sec: millisec format. ◦ SAMPLETIME: The time at which the data sample was collected in Habitat in the hour: min:sec format. <p>You can edit the names of these custom/alias timestamps using the registry entries FieldTimeCustomFieldName, ScadaTimeCustomFieldName, and SampleTimeCustomFieldName respectively.</p>	
QualityFields	The name of the property that stores the tag quality in Habitat.	
SampleOptions	<p>Contains the following elements:</p> <ul style="list-style-type: none"> ◦ SampleRate: The rate at which you want to collect data. ◦ SampleUnit: The unit of measurement for the sample rate. ◦ Permanent: Indicates whether you want to store the data in buffer files in Habitat in the event of a connection loss. We strongly recommend that you set this parameter to true to prevent loss of data. <p>For example, if you want to collect data every 5 seconds, enter:</p> <pre data-bbox="527 1661 956 1894" style="background-color: #f0f0f0; padding: 5px;"> <SampleOptions> <SampleRate>5</SampleRate> <SampleUnit>sec</SampleUnit> <Permanent>TRUE</Permanent> </SampleOptions> </pre>	<p>Valid values for SampleUnit:</p> <ul style="list-style-type: none"> ◦ sec ◦ min ◦ hour ◦ day ◦ week ◦ month <p>Valid values for Permanent:</p> <ul style="list-style-type: none"> ◦ TRUE ◦ FALSE

Example:

```

<DataCollectionDefinitions>
  <DataCollectionDefinition>
    <Name>ANALOG_HIST</Name>
    <id>1</id>
    <Site>Site1</Site>
    <Valid>TRUE</Valid>
    <Status>DISABLED</Status>
    <Family>DTS1</Family>
    <Application>SCADA1</Application>
    <Database>SCADAMOM1</Database>
    <RecordType>ANALOG</RecordType>
    <CollectionType>Unsolicited</CollectionType>
    <Key>*/Key>
    <TagTemplate>
      <TagPrefix>Collection_1</TagPrefix>
      <TagNameField>$KEY_PLC</TagNameField>
      <MRID>MRID_PLC</MRID>
      <ValueFields>DIS_ANALOG</value>
      <Timestamp>SCTIME_ANALOG</Timestamp>
      <Quality>DFLAGS_ANALOG</Quality>
    </TagTemplate>
    <SampleOptions>
      <SampleRate>5</SampleRate>
      <SampleUnit>sec</SampleUnit>
      <Permanent>FALSE</Permanent>
    </SampleOptions>
  </DataCollectionDefinition>
  <DataCollectionDefinition>
    <Name>ANALOG_HIST</Name>
    <id>2</id>
    <Site>Site1</Site>
    <Valid>TRUE</Valid>
    <Status>ENABLED</Status>
    <Family>DTS2</Family>
    <Application>SCADA2</Application>

```

```

<Database>SCADAMOM2</Database>

<RecordType>ANALOG</RecordType>

<CollectionType>Polled</CollectionType>

<Key>*</Key>

<TagTemplate>

  <TagPrefix>Collection_2</TagPrefix>

  <TagNameField>$KEY_PLC</TagNameField>

  <MRID>MRID_PLC</MRID>

  <ValueFields>DIS_ANALOG</value>

  <Timestamp>SCTIME_ANALOG</Timestamp>

  <Quality>DFLAGS_ANALOG</Quality>

</TagTemplate>

<SampleOptions>

  <SampleRate>5</SampleRate>

  <SampleUnit>sec</SampleUnit>

  <Permanent>TRUE</Permanent>

</SampleOptions>

</DataCollectionDefinition>

</DataCollectionDefinitions>

```

3. Save and close the file.

The HAB collector is configured.

[Start the collector \(on page 2242\).](#)

Configure the HAB Collector for Alarms

[Create an instance of the HAB collector \(on page 489\).](#)

A configuration file is created when you install collectors. This file contains the following types of information, which are required for the Sampler application to connect to Habitat.

- **Site parameters:** Contains the location details of Habitat from which you want to collect data. A single site can contain one or two nodes (the two nodes are used for a primary/standby configuration).

A configuration file can contain only one Site section.

- **Collector parameters:** Contains the following parameters:

- **Automatic tag sync:** If the automatic tag sync option is enabled in the configuration file, when tags are added, renamed, or deleted in Habitat, the changes are reflected automatically in Historian. No manual steps are required; data collection begins automatically depending on the collection definition that you have provided in the configuration file. If, however, the automatic tag sync is disabled, you must approve tag changes, and only then they are reflected in Historian. For more information, refer to [Approve Tag Changes \(on page 2243\)](#). Depending on the collection definition that you have provided in the configuration file, tags are created in Historian, and data collection is initiated.
- **Tag deletion versus disablement:** For tags deleted in Habitat, you must specify whether they must be deleted in Historian or just disabled for data collection.

A configuration file can contain only one CollectorParameter section.

- **Collection definition parameters:** Specifies which data to collect and how. For example, the Habitat application, database, and the family from which you want to collect data, whether the data is polled or unsolicited (that is, periodic or exception), the mapping between tag properties and the corresponding fields in Habitat, etc. There are two types of collection definition parameters: tag data collection and alarm data collection.

A configuration file can contain multiple DataCollectionDefinition sections. If you do not want to use a collection definition for now, you can set the State parameter to DISABLED.

If you have created multiple instances of the collector, you must create one configuration file for each instance.

In addition to alarms, you can specify values for these parameters for tags. We recommend that you create a separate collector instance to collect tag data. You must then [configure tags \(on page 2219\)](#) in a separate file.

1. Access the `<collector name>_Config.xml` file. By default, it is located at `C:\Program Files\GE Digital\Historian HAB Collector\Server`.
2. Enter values as specified in the following tables.

Table 378. Site Parameters

Parameter	Description
Name	The name that you want to assign to the site.
Node1	The host name or IP address of the Habitat server (node) in the site from which you want to collect data. This server acts as the primary/active server from which the collector receives data.

Parameter	Description
Node2	<p>If you want to achieve high availability by connecting to redundant Habitat servers, provide the host names or IP addresses of both the servers - the active server in Node1 and the standby server in Node2.</p> <div data-bbox="669 478 1421 1115" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <p>You can provide the IP addresses of up to four Habitat servers - two of them in Node1 and other two in Node2, separated by commas.</p> <p>For example, if you want to connect to MachineA, MachineB, MachineC, and MachineD, enter:</p> <pre data-bbox="760 808 1404 898" style="background-color: #FFF2CC; padding: 5px;"> <Node1>MachineA,MachineB</Node1> <Node2>MachineC,MachineD</Node2></pre> <p>If you do so, MachineA becomes the active Habitat server, and in case of a failover, MachineB, MachineC, and MachineD each become active servers - one-by-one, in that order.</p> </div> <p>For information on the various ways of achieving high availability, refer to High Availability (on page 2210).</p>
Socket	The socket number (port number) used by the Habitat Sampler application to connect. Each collector instance can connect to only one socket.
Retry	The duration, in seconds, after which the collector tries to communicate with the site. The default value is 5.

Example:

```

<Site>
  <Name>Site1</Name>
  <Node1>Host1</Node1>
  <Node2>Host2</Node2>
  <Socket>8040</Socket>
```

```
<Retry>5</Retry>
</Site>
```

Table 379. Collector Parameters

Parameter	Description	Valid Values
AutoTagSync	<p>Indicates whether tags must be created initially when the collector is connected to the Habitat Sampler application. It also indicates whether tags must be created, renamed, or deleted later automatically when the corresponding changes are done in Habitat.</p> <p>If you disable this option, you must manually confirm these changes. For example, if 10 tags are added in Habitat, you must confirm which of them must be created in Historian. For instructions, refer to Approve Tag Changes (on page 2243).</p>	<ul style="list-style-type: none"> ◦ TRUE ◦ FALSE
TagDeletionType	Specifies whether tags deleted in Habitat must be deleted or just disabled for data collection in Historian.	<ul style="list-style-type: none"> ◦ DISABLE_TAG ◦ DELETE_TAG

Example:

```
<CollectorParameter>
  <AutoTagSync>TRUE</AutoTagSync>
  <TagDeletionType>DISABLE_TAG</TagDeletionType>
</CollectorParameter>
```

Table 380. Collection Definition Parameters

Parameter	Description	Valid Values
Name	<p>The name of the collection definition. A value is required and must be unique.</p> <div style="border: 1px solid orange; border-radius: 10px; padding: 10px; background-color: #fff9c4;"> <p>! Important: You must not change the name after the col-</p> </div>	

Parameter	Description	Valid Values
	<p> lector starts collecting data. If, however, you want to change the name after the collector has started collecting data, refer to FAQs on HAB Collector (on page 2246).</p>	
id	<p>Identifies the collection definition. A value is required and must be unique.</p> <p> Important: You must not change the ID after the collector starts collecting data. If, however, you want to change the ID after the collector has started collecting data, refer to FAQs on HAB Collector (on page 2246).</p>	
Site	<p>The name of the site in Habitat from which you want to collect data. Provide the same value as the one you provided for the Name parameter in the Site section.</p>	
Valid	<p>Indicates whether the collection definition is valid.</p>	<ul style="list-style-type: none"> ◦ TRUE: Indicates that the collection definition is valid. ◦ FALSE: Indicates that an error has occurred while

Parameter	Description	Valid Values
		processing the collection definition. In this case, the collector also sets the State parameter to DISABLED so that this collection definition is not considered.
Status	Indicates whether the collection definition is enabled.	<ul style="list-style-type: none"> ◦ ENABLED: Indicates that the collector is processing the collection definition. ◦ DISABLED: Indicates that this data collection is not being used. You can manually disable a collection definition. Or if an error has occurred while processing the collection definition, the collector automatically sets this parameter to DISABLED.
Application	The name of the Habitat application from which you want to collect data (for example, ALARM).	
Database	The name of the Habitat database from which you want to collect data (for example, ALARMLST).	
Family	The name of the Habitat family from which you want to collect data (for example, EMS, DTS).	

Parameter	Description	Valid Values
	A value is required and must be unique.	
RecordType	The name of the HDB record from which you want to collect data (for example, CIRCLG).	Any record type that contains the composite key and MRID fields (because the collector uses these two fields to create tags).
CollectionType	Indicates the collection type. For alarms, only unsolicited data collection is supported, which indicates that data is collected only when values have changed since the last time data was collected.	Unsolicited (indicated as EXCEPTION in Habitat).
Key	This parameter is not applicable to alarms. Enter *.	
AlarmFilter	<p>The list of options to filter alarm data. It contains the following parameters:</p> <ul style="list-style-type: none"> ◦ Enabled: Enter TRUE or FALSE to specify whether you want to filter alarm data. The default value is TRUE. ◦ Location, Area, Category, Priority, Exception: For each of these parameters, enter the criteria using which you want to filter alarm data. You can enter multiple values separated by commas (for example, LAKEVIEW,RICHVIEW). 	

Parameter	Description	Valid Values
	<p>The default value is *, which indicates that data for that parameter is not filtered.</p> <p>For example, if you want to retrieve only the alarm data related to LAKEVIEW and RICHVIEW, in the area Australia, with priority 3, enter:</p> <pre data-bbox="678 678 1036 1136"> <AlarmFilter> <Enabled>True</Enabled> <Location>LAKEVIEW,RICHVIEW</Location> <Area>Australia</Area> <Category>SCADATOP</Category> <Priority>3</Priority> <Exception>*</Exception> </AlarmFilter> </pre> <p>Note that data is filtered only if the criteria for <i>all</i> the parameters is satisfied.</p> <div data-bbox="667 1308 1036 1860" style="border: 1px solid orange; border-radius: 10px; padding: 10px; background-color: #fff9c4;"> <p>! Important:</p> <p>The property names of the parameters for which you want to filter data must be included in the <Value> parameter under <TagTemplate>. For example, if the location, area, and priority are stored in the LOC_CIRCLG, AREA_</p> </div>	

Parameter	Description	Valid Values
	<p> CIRCLG, and PRIOR_- CIRCLG fields respectively, enter <code><Value>LOC_CIRCLG, AREA_- CIRCLG, PRIOR_CIRCLG</Value></code></p>	
<p>TagNameFields</p>	<p>Determines how the tags created in Historian must be named.</p> <p>For example, if you want the tags to be named after the value in the LOC_CIRCLG field, enter <code><TagNameFields>LOC_CIRCLG</TagNameFields></code>. When you do so, if the value in the LOC_CIRCLG field in Habitat is DOUGLAS, the tag created in Historian will be named <code><TagPrefix value>.<AlarmPrefix value>.DOUGLAS</code>.</p> <p>You can enter multiple values separated by commas.</p> <p>For example, if you want the tags to be named after the values in the LOC_CIRCLG and PRIOR_CIRCLG fields, enter:</p> <pre data-bbox="678 1522 1036 1612"><TagNameFields>LOC_CIRCLG, PRIOR_CIRCLG</TagNameFields></pre> <p>When you do so, if the values in the LOC_CIRCLG and PRIOR_CIRCLG fields are Douglas and 1 respectively, the tag created in Historian will be named <code><TagPre-</code></p>	

Parameter	Description	Valid Values
	fix value>.<AlarmPrefix value>.DOUGLAS.1.	
TagPrefix	The prefix that you want to use for tags. You can provide a different value for each collection definition, which helps you identify tags based on the collection definition.	
TagTemplate	<p>The list of tag properties for which you want to collect data. In Historian, we use the Value tag property.</p> <p>You must map these properties with the corresponding ones in Habitat. For example, if the value of a tag is stored in the TEXT_CIRCLG field in Habitat, enter:</p> <pre data-bbox="678 1150 1036 1377"> <TagTemplate> <Value>TEXT_CIRCLG</value> <Timestamp></Timestamp> <Quality></Quality> </TagTemplate> </pre> <p>For the Value parameter, if you want to collect data from multiple fields, enter them separated by commas. The values will then be concatenated in the corresponding Historian tag (for example, <Value>TEXT_CIRCLG, PRIOR_CIRCLG, TIME_CIRCLG</Value>).</p>	

Parameter	Description	Valid Values
	<p>! Important:</p> <ul style="list-style-type: none"> ◦ Quality is not applicable to alarms. In addition, to provide the timestamp column name, include it in the <Value> element itself separated by a comma. Therefore, do NOT enter values for the <Timestamp> and <Quality> elements, but retain the elements. ◦ If you have provided filter criteria under <AlarmFilter>, enter the names of those fields in the <Value> parameter. 	
SampleOptions	Contains the following elements:	Valid values for SampleUnit: <ul style="list-style-type: none"> ◦ sec ◦ min ◦ hour

Parameter	Description	Valid Values
	<ul style="list-style-type: none"> ◦ SampleRate: The rate at which you want to collect data. ◦ SampleUnit: The unit of measurement for the sample rate. ◦ Permanent: Indicates whether you want to store the data in buffer files in Habitat in the event of a connection loss. We strongly recommend that you set this parameter to true to prevent loss of data. <p>For example, if you want to collect data every 5 seconds, enter:</p> <pre data-bbox="678 1081 1036 1312" style="background-color: #f0f0f0; padding: 5px;"> <SampleOptions> <SampleRate>5</SampleRate> <SampleUnit>sec</SampleUnit> <Permanent>TRUE</Permanent> </SampleOptions></pre>	<ul style="list-style-type: none"> ◦ day ◦ week ◦ month <p>Valid values for Permanent:</p> <ul style="list-style-type: none"> ◦ TRUE ◦ FALSE

Example:

```

<AlarmCollectionDefinitions>
  <AlarmCollectionDefinition>
    <Name>ALARM</Name>
    <id>1</id>
    <Site> Site1</Site>
    <Valid>TRUE</Valid>
    <Status>ENABLED</Status>
    <Family>DTS</Family>
    <Application>ALARM</Application>
    <Database>ALARMLST</Database>
```

```

<RecordType>CIRCLG</RecordType>

<CollectionType>Unsolicited</CollectionType>

<Key>*</Key>

<AlarmFilter>

  <Enabled>True</Enabled>

  <Location>LAKEVIEW,RICHVIEW</Location>

  <Area>Australia</Area>

  <Category>SCADATOP</Category>

  <Priority>3</Priority>

  <Exception>*</Exception>

</AlarmFilter>

<TagNameFields>LOC_CIRCLG</TagNameFields>

<TagPrefix>ALARM.</TagPrefix>

<TagTemplate>

<Value>TEXT_CIRCLG,PRIOR_CIRCLG,LOC_CIRCLG,AREA_CIRCLG</Value>

<Timestamp>SCADATIME</Timestamp>

<Quality></Quality>

</TagTemplate>

<SampleOptions>

  <SampleRate>5</SampleRate>

  <SampleUnit>sec</SampleUnit>

  <Permanent>FALSE</Permanent>

</SampleOptions>

</AlarmCollectionDefinition>

</AlarmCollectionDefinitions>

```

3. Save and close the file.

The HAB collector is configured.

[Start the collector \(on page 2242\).](#)

Start the HAB Collector

Configure the collector for [tags \(on page 2219\)](#) and [alarms \(on page 2230\)](#).

1. Access Windows services.
2. Right-click the HAB collector instance that you want to start, and then select **Start**.

The collector is started, and fetches data from the Habitat site details that you provided in the configuration file.

If you have disabled the automatic tag sync option in the configuration file, tag changes in Habitat (such as adding, renaming, and deleting tags) are captured in the `<collector_name>_tag_Unconfirmed.xml` file. [Approve the changes \(on page 2243\)](#) so that they are reflected in Historian.

**Note:**

If you have enabled the automatic tag sync option, tag changes are automatically reflected in Historian; no manual steps are needed.

Approve Tag Changes

[Start the collector \(on page 2242\)](#).

After you create a collector instance and configure it, you can choose between the following options:

1. **Automatic tag sync:** If you enable this option in the configuration file, the collector creates tags automatically in Historian based on the key value. In addition, any tag changes in Habitat (such as adding, renaming, and deleting tags) will reflect automatically in Historian. No manual steps are required.
2. **Manual tag changes:** If you disable the automatic tag sync option, any tag changes in Habitat will be captured in the `<collector name>_Tag_Unconfirmed.xml` file. Only after you approve these changes, they are reflected in Historian.

This topic describes how to approve tag changes manually if you have disabled the automatic tag sync option. You can do so using Configuration Hub or by updating the `<collector name>_Tag_Unconfirmed.xml` directly.

1. To approve changes using Configuration Hub:
 - a. [Access Configuration Hub \(on page 336\)](#).
 - b. In the **NAVIGATION** section, select **Collectors**.
 - c. Right-click the HAB collector whose changes you want to approve, and then select **Confirm Queued Tags**.
A list of tags that have been changed appears.

- d. Select the check boxes corresponding to the tags whose changes you want to approve, and then select **Confirm**.

The tag changes are approved. The status of the tags is updated in the `<collector_name>_tag.xml` file (that is, the Confirmed parameter is set to true).

2. To approve changes using the `<collector name>_Tag_Unconfirmed.xml` file:

- a. Access the `<collector name>_Tag_Unconfirmed.xml` file. By default, it is located at `C:\Program Files\GE Digital\Historian HAB Collector\Server`.



Note:

This file is named `<collector name>_Tag_Unconfirmed.xml` only if there are changes for you to approve. Otherwise, it is named `<collector name>_Tag.xml`, which indicates that there have been no changes since your last approval.

The file contains a list of tags, each tag listed under one of the following sections:

- **ProposedTags:** Contains a list of tags in Habitat that are supposed to be created in Historian. They will be created after your approval.
- **DeletedTags:** Contains a list of tags deleted in Habitat, but are not yet deleted/disabled in Historian.
- **RenamedTags:** Contains a list of tags that have been renamed in Habitat, but still contain the old names in Historian.

- b. For each tag for which you want the changes to reflect in Historian, set the Confirmed parameter to true.

For example, the following code sample indicates that a tag named SUBSTN.LAKEVIEW.VOLTAGE is created in Habitat, but is not yet created in Historian:

```
<ProposedTags>
  <TAG>
    <TagName value="SUBSTN.LAKEVIEW.VOLTAGE" />
    <CompositeKey value="SUBSTN.LAKEVIEW.T1" />
    <MRID value="D3FR67H-F453-4859-SHDKRIBNSJ345" />
    <SourceAddress value="D3FR67H-F453-4859-SHFURNSOV4853J">
    <CollectionType value="Unsolicited"/>
    <Confirmed value="false">
```

```

</TAG>
</ProposedTags>

```

To create this tag in Historian, set the Confirmed value to true as follows:

```

<ProposedTags>
  <TAG>
    <TagName value="SUBSTN.LAKEVIEW.VOLTAGE" />
    <CompositeKey value="SUBSTN.LAKEVIEW.T1" />
    <MRID value="D3FR67H-F453-4859-SHDKRIBNSJ345" />
    <SourceAddress value="D3FR67H-F453-4859-SHFURNSOV4853J">
    <CollectionType value="Unsolicited"/>
    <Confirmed value="true">
  </TAG>
</ProposedTags>

```

c. Save and close the file.

d. Rename the `<collector name>_Tag_Unconfirmed.xml` file to `<collector name>_Tag.xml`.

The changes are reflected in Historian:

- Newly added tags that you have approved are created in Historian and data collection is initiated for them. They are removed from the ProposedTags section in the file.
- Renamed tags that you have approved are renamed in Historian. They are removed from the RenamedTags section in the file.
- Deleted tags that you have approved are either deleted or disabled for data collection depending on the value for the TagDeletionType parameter in the configuration file. For more information, refer to [Configure the HAB Collector for Tags \(on page 2219\)](#) and [Configure the HAB Collector for Alarms \(on page 2230\)](#). These tags are removed from the DeletedTags section of the `<collector name>_Tag.xml` file.

Delete an Instance of the HAB Collector

Stop the collector from Windows services.

1. Open command prompt.
2. Change to the directory in which the CollectorInstanceUtility file is located. By default, it is located in the following folder: `C:\Program Files\GE Digital\Historian HAB Collector\Server`

3. Run the following command:

```
CollectorInstanceUtility.exe -Delete <collector instance name>
```

where *<collector instance name>* is the name assigned to the collector instance.

For example:

```
CollectorInstanceUtility.exe -Delete Hab1 MyHistServer "C:\Proficiency Historian Data"
```

The collector instance is deleted.

FAQs on HAB Collector

How to change the name or ID of a collection definition after data collection begins?

Suppose you have provided the following information in the configuration file:

```
<Name>ANALOG_HIST</Name>
<id>1</id>
<Key>SUBSTN.KIRKLAND.*.*.*.</Key>
```

Suppose you want to change the name and ID as follows:

```
<Name>ANALOG_HIST_NEW</Name>
<id>3</id>
<Key>SUBSTN.KIRKLAND.*.*.*.</Key>
```

To make these changes:

1. Stop the collector instance:
 - a. Access Windows services.
 - b. Right-click the HAB collector instance that you want to stop, and then select **Stop**.
2. [Update the configuration file \(on page 2219\)](#).
3. Search and select all the tags related to the collection definition, and [remove them \(on page 2063\)](#).



Important:

Do not delete them permanently; just remove them so that the tags and their data will still be available.

4. Start the collector instance.
 - a. Access Windows services.
 - b. Right-click the HAB collector instance that you want to start, and then select **Start**.

Tags will be created based on the new collection definition details. You can also retrieve data for the older tags.

How to split a collection definition into two?

Suppose you have provided the following information in the configuration file:

```
<Name>ANALOG_HIST</Name>
<id>1</id>
<Key>SUBSTN.KIRKLAND.*.*.*</Key>
```

Suppose you want to split the collection definition into two as follows:

```
<Name>ANALOG_HIST</Name>
<id>1</id>
<Key>SUBSTN.KIRKLAND.BUS.*.*.*</Key>
```

```
<Name>ANALOG_HIST_HIST2</Name>
<id>2</id>
<Key>SUBSTN.KIRKLAND.LN.*.*.*</Key>
```

To make these changes:

1. Stop the collector instance:
 - a. Access Windows services.
 - b. Right-click the HAB collector instance that you want to stop, and then select **Stop**.
2. [Update the configuration file \(on page 2219\)](#).
3. Search and select all the tags related to the collection definition, and [remove them \(on page 2063\)](#).



Important:

Do not delete them permanently; just remove them so that the tags and their data will still be available.

4. Start the collector instance.
 - a. Access Windows services.
 - b. Right-click the HAB collector instance that you want to start, and then select **Start**.

Tags will be created based on the new collection definition details. You can also retrieve data for the older tags.

Can I add an alarm filter in a collection definition after data collection begins?

Yes.

Suppose you have the following collection definition:

```
<Name>ALARM</Name>

<id>1</id>

<Site>Site1</Site>

<Valid>TRUE</Valid>

<Status>ENABLED</Status>

<Family>EMS</Family>

<Application>ALARM</Application>

<Database>ALARMLST</Database>

<RecordType>CIRCLG</RecordType>

<CollectionType>Unsolicited</CollectionType>

<Key>*</Key>

<TagNameFields>LOC_CIRCLG</TagNameFields>

<TagPrefix>ALARM.</TagPrefix>

<AlarmFilter>

  <Enabled>TRUE</Enabled>

  <Location>*</Location>

  <Area>*</Area>

  <Category>*</Category>

  <Priority>*</Priority>

  <Exception>*</Exception>

</AlarmFilter>

...
```

Since you have not specified any location, area, etc. in the alarmfilter parameter, tags will be created for all the locations, areas, etc. (that is, no filter is applied).

Suppose you want to filter out the tags for the location Kirkland.

To do so, include the location as follows:

```
<Name>ALARM</Name>

<id>1</id>

<Site>Site1</Site>

<Valid>TRUE</Valid>

<Status>ENABLED</Status>
```

```

<Family>EMS</Family>

<Application>ALARM</Application>

<Database>ALARMLST</Database>

<RecordType>CIRCLG</RecordType>

<CollectionType>Unsolicited</CollectionType>

<Key>*</Key>

<TagNameFields>LOC_CIRCLG</TagNameFields>

<TagPrefix>ALARM.</TagPrefix>

<AlarmFilter>

  <Enabled>TRUE</Enabled>

  <Location>KIRKLAND</Location>

  <Area>*</Area>

  <Category>*</Category>

  <Priority>*</Priority>

  <Exception>*</Exception>

</AlarmFilter>

<TagTemplate>

  <Value>TEXT_CIRCLG, TIME_CIRCLG, PRIOR_CIRCLG, LOC_CIRCLG</Value>

  ...

```

After you restart the collector, data collection will occur only for one tag: ALARM.KIRKLAND even though other tags were created. You can choose to delete these additional tags.

Note that you must also include LOC_CIRCLG in the <Value> parameter as highlighted.

If a tag is renamed and deleted in Habitat, and then if the tag is recreated with the original name in Habitat, will it be created in Historian?

Yes, but only after you perform a few steps.

Suppose a tag named has been renamed in Habitat as follows:

- Original name: A
- New name: B

If automatic tag sync is enabled, the tag in Historian will be renamed automatically. Otherwise, the tag will be renamed only after you [approve the changes \(on page 2243\)](#).

Now, suppose tag B is deleted in Habitat. Depending on the value you have set for the TagDeletionType parameter, tag B will be disabled or deleted in Historian.

Now, suppose a new tag named A is created in Habitat. Accordingly, tag A will be created in Historian only if you perform the following steps:

1. Stop the collector instance:
 - a. Access Windows services.
 - b. Right-click the HAB collector instance that you want to stop, and then select **Stop**.
2. [Remove tag B \(on page 2063\)](#).



Important:

Do not delete the tag permanently; just remove it so that the tag and its data will still be available.

3. Start the collector instance.
 - a. Access Windows services.
 - b. Right-click the HAB collector instance that you want to start, and then select **Start**.

Chapter 19. iFIX Collector

Overview of the iFIX Data Collectors

The iFIX collectors collect data from iFIX and store it in the Historian server. They include:

- The iFIX collector
- The iFIX Alarms and Events collector

They use the Easy Data Access (EDA) protocol to retrieve data from a running iFIX system.

When you install collectors, if iFIX is installed on the same machine as the collectors, instances of the iFIX collectors are created automatically. You can begin using these collectors, or [create more instances \(on page 357\)](#) as needed using Configuration Hub.

Features:

- You can browse the source for tags and their attributes.
- Only the polled data collection is supported; unsolicited collection is not supported. The minimum poll interval is 100ms.
- The supported timestamp resolution is milliseconds or seconds.
- The collector accepts device timestamps.
- Floating point, integer, string, and binary data are supported.
- You can create Python Expression Tags for those collectors that support them.

Supported tag attributes:

- Tagname
- Source Address
- Engineering Unit Description
- Data Type
- Hi Engineering Units
- Lo Engineering Units
- Is Array Tag

About Adding an iFIX Collector Instance

This topic provides guidelines on how to configure the iFIX collector using Configuration Hub based on the running mode of iFIX. It also describes the collector behaviour and recommended configuration in each case.

iFIX Running Mode	Recommended Configuration for the iFIX Collector	Collector Behaviour After You Add the Collector Instance
<p>iFIX is running in service mode and is secured.</p> <p>The iFIX Alarms and Events and the OPC Alarms and Events Servers are running as service.</p>	<p>Configure the iFIX collector services under a user account under which iFIX is running as a service. While adding an instance of the iFIX collector or the iFIX Alarms and Events collector using Configuration Hub, select Service Under Specific User Account.</p>	<ul style="list-style-type: none"> • The iFIX collector starts running as a service. It appears in the collectors list in Configuration Hub. • You can run the collector at a command prompt using the Collector Start action. A shortcut is created in the Windows Start menu so that you can run the collector in the command-line mode. • By default, when not started as an SCU task, the iFIX collector points to the iFIX nodename. You must configure the iFIX node in the Collector Configuration section in Historian Administrator.
<p>iFIX is running as a service and is not secured.</p> <p>The iFIX Alarms and Events and the OPC Alarms and Events servers are running as service.</p>	<p>You can configure the iFIX collector service using a local system account or a specific user account.</p>	<ul style="list-style-type: none"> • The iFIX collector starts running as a service. • You can run the collector at a command prompt using the Collector Start action. A shortcut is created in the Windows Start menu so that you can run the collector in the command-line mode. • By default, when not started as an SCU task, the iFIX collector points to the iFIX nodename. You must con-

iFIX Running Mode	Recommended Configuration for the iFIX Collector	Collector Behaviour After You Add the Collector Instance
		figure the iFIX node in the Collector Configuration section in Historian Administrator.
iFIX is not running as a service mode and is secured.	Configure the iFIX collector services under a user account that is added in the IFIXUSERS group. Do not configure as a local system service. While adding an instance of the iFIX collector or the iFIX Alarms and Events collector using Configuration Hub, select Service Under Specific User Account .	<ul style="list-style-type: none"> • Since Remote Collector Manager tries to start the collector as a service, and iFIX is not running as a service, an error message appears while adding a collector instance. However, the instance is configured successfully although it does not appear in the collectors list in Configuration Hub. • A shortcut is created in the Windows Start menu so that you can run the collector in the command-line mode, and the related registry folder is created. • You must start the collector manually for the first time using the shortcut. It will then connect to the Historian server, and it will then appear in the collectors list in Configuration Hub. • Once connected to server, you can start/stop it at a command prompt.


iFIX Running Mode	Recommended Configuration for the iFIX Collector	Collector Behaviour After You Add the Collector Instance
<p>iFIX is not running as a service mode, and is not secured.</p>	<p>You can configure the iFIX collector service using a local system account or a specific user account.</p>	<ul style="list-style-type: none"> • Since Remote Collector Manager tries to start the collector as a service, and iFIX is not running as a service, an error message appears while adding a collector instance. However, the instance is configured successfully. • A shortcut is created in the Windows Start menu so that you can run the collector in the command-line mode, and the related registry folder is created. • You must start the collector manually for the first time using the shortcut. It will then connect to the Historian server. • Once connected to server, you can start/stop it at a command prompt.
<p>iFIX is not running.</p>	<p>You can configure the iFIX collector service using a local system account or a specific user account, as per the security configuration of iFIX.</p>	<ul style="list-style-type: none"> • Since Remote Collector Manager tries to start the collector as a service, and iFIX is not running as a service, an error message appears while adding a collector instance. However, the instance is configured successfully although it does not appear

iFIX Running Mode	Recommended Configuration for the iFIX Collector	Collector Behaviour After You Add the Collector Instance
		<p>in the collectors list in Configuration Hub.</p> <ul style="list-style-type: none"> • A shortcut is created in the Windows Start menu so that you can run the collector in the command-line mode, and the related registry folder is created. • After you start iFIX, you must start the collector manually for the first time using the shortcut. It will then connect to the Historian server. • Once connected to server, you can start/stop it at a command prompt.

Specify the Tags for Data Collection

1. Access Historian Administrator.
2. Select **Collectors**, and then select the iFIX collector instance to which you want to add tags.
3. Select **Configuration**.

The **Configuration** section appears.



4. Select **Add Tags**.

The **Add Multiple Tags from Collector** window appears.

5. In the **Collector** field, select the collector to which you want to add tags.

A hierarchical tree of tags appears in the **Browse Results** section.

6. If you want to view only the tags for which data is not collected, in the **Show Only** field, select **Source Tags Not Collected**. You can search for a tag by entering search criteria in the **Source Tag Name** or **Description** field.

7. Navigate to the node in the tree that you want to browse, and then select **Browse**.



Tip:

- To browse automatically, select the **Auto Browse** check box. The available tags appear in the **Browse Results** window whenever a node is selected in the tree.
- To show all child elements within a hierarchy, select the **Show All Children** check box. All tags at or below the hierarchical level of the selected node in the tree appear in the **Browse Results** window.

The tags within the selected portion of the iFIX server tag hierarchy appear.

8. Select the tags for which you want to collect data, and then select **Add Selected Tags**.

The tags are added to the collector. They appear in black text in the list of tags.

9.

10. Select fields for each of the blocks that you want included in your browse of the node for tags.
 - a. In the Historian Non-Web Administrator, select the **Block** type from the **Block** window.
 - b. Select the desired check boxes beside the fields.

The **Block** name changes from black to blue, if any of its fields are selected.

11. Select **Update** to apply your selection.
12. Select **Add Tags** at the bottom of the page after you have selected the field.

The **Browse Tags** window appears.

13. Select **Browse** in the **Browse Tags** window to execute the browse operation.

Editing FixTag.dat File

Overview

The most common block and field types are included in the default `FixTags.dat` file. You can edit this file to add or remove block and field types. The `FixTags.dat` file is an XML (eXtensible Markup Language) file. You can edit it with either a text editor like Notepad or with a third-party XML editing tool.

For Historian Non-Web Administrators, the `FixTag.dat` file is typically located in the `Program Files \Proficy\Historian\NonWebAdmin` directory of each individual Historian Non-Web Administrator client. Changes you make to the file apply only to that specific client and are not global to all Historian Non-Web Administrator clients.

Because changes made to one `FixTag.dat` file are not automatically duplicated in other `FixTags.dat` files, it is recommended that you set up a standard procedure to ensure that all such files track changes made in any single file. One suggested method is to keep a master copy. To make a change, edit the master copy, deploy the changed file, and test it. If the change provides the desired effect, copy the new file to the non-web Historian Administrator directories, and save the new file as the master backup copy. All Administrators will then be using the same set of block and field types.

The `FixTags.dat` file has two main sections. The first section lists the configured FIX database block types and their descriptions. The second section lists field extensions for each of the block types defined in the first section. In addition, the second section also has an entry called `Selected`, which can be either `True` or `False`. This is used by Historian Administrator to indicate whether or not that block and field extension combination are included in a browse.

Example of First Section

```
<XML ID="dsoTags"><MYLIST>..<ONEITEM> <VALUE>DI</VALUE> <DATA>DI Digital Input</DATA></ONEITEM>.  
.</MYLIST></XML>
```

Example of Second Section

```
<XML ID="DI"><MYLIST> <ONEITEM> <VALUE>F_CV</VALUE> <DATA>F_CV</DATA> <SELECTED>False</SELECTED> </ONEITEM>
<ONEITEM> <VALUE>B_CUALM</VALUE> <DATA>B_CUALM</DATA> <SELECTED>False</SELECTED> </ONEITEM></MYLIST></XML>
```

To Add a Field Extension to an Existing Block Type Using Notepad

- In the FixTag.dat file, locate the entry that starts with `<XML ID = "**">`, where `**` is the block name (such as AA, AI, DI, etc).
- Copy one of the existing `<ONEITEM>...</ONEITEM>` blocks of text and edit it for your new field. Each field extension is contained in a block of text contained within the text: `<ONEITEM>...</ONEITEM>`.

There are two entries `<VALUE>` and `<DATA>` which comprise the new field extension to be added, and a `<SELECTED>` section, which is either `True` or `False`, depending on whether or not you want the item to be included in the browse.



Note:

The `True` and `False` states change, depending on your selection in Historian Administrator.

An example for the Digital Input (DI) tag is shown below, where we have added the `A_ALMLASTTIME` field, which identifies the last time the block went into alarm.

```
<XML ID="DI"><MYLIST> <ONEITEM> <VALUE>F_CV</VALUE> <DATA>F_CV</DATA> <SELECTED>False</SELECTED> </ONEITEM>
<ONEITEM> <VALUE>A_ALMLASTTIME </VALUE> <DATA>A_ALMLASTTIME </DATA> <SELECTED>False</SELECTED> </ONEITEM>
<ONEITEM> <VALUE>B_CUALM</VALUE> <DATA>B_CUALM</DATA> <SELECTED>False</SELECTED> </ONEITEM></MYLIST>
```

Add a New Database Block Using Notepad



Note:

You must add at least one field.

1. Within the `<XML ID="dsoTags">` and `<MYLIST>` sections, add a new `<ONEITEM>` entry with the tag name and description. There are two entries, `<VALUE>` and `<DATA>`, which will be the new tag name (AA, AI, DI, etc.) to be added and the tag description (e.g., AA Analog Alarm) that will be displayed in Historian Administrator.
2. Create the fields that will be available for the tag. This is similar to modifying the field extensions discussed above, but in this case you must create the `<XML ID = "**">` structure (where `**` is your

tag name.) Again, this is most easily performed by copying and pasting an existing XML ID structure and modifying it for the new tag.



Note:

The XML ID section MUST be placed before the last three lines of the file:

```
</MYLIST>
</XML>
</BlockList>
```

Example: Restarting the iFIX Collector Using a Heartbeat

Many applications commonly use a heartbeat to indicate when a program stops. If you want to use a heartbeat with the iFIX collector, you need to configure it through Historian Administrator and the iFIX Database Manager.

In the iFIX Database Manager, configure this address to an Analog Output (AO) block and use a separate Program (PG) block to check the status of the collector heartbeat output and restart the collector if it stopped. Then, in Historian Administrator, define a Heartbeat Output Address on the **Advanced** section of the Collector Maintenance page for the specified iFIX collector

Once configured and started, the Historian iFIX collector sends a value of 1 to the specified Heartbeat Output Address every 60 seconds. If that heartbeat value is not sent, then iFIX detects this status and restarts the iFIX collector.

If your iFIX database PDB is quite large, you may need to increase the Delay Collection at Startup field on the **Advanced** section of the Collector Maintenance page in Historian Administrator. Doing so prevents excessive collector log entries if Historian cannot obtain a value before it initializes the source address.


In this example, an iFIX collector runs on NODE1 and the heartbeat output address is NODE1.HOA_2.F_CV. We create an Analog Output Block is named HOA_2 and the Program block is named HB_HOA_1 in a new iFIX database. There are two parts to this example: configuration in iFIX and then Historian Administrator.

Part A: Configuration in iFIX

Follow these steps to configure the heartbeat for an iFIX Data Collector:

1. Start iFIX.
2. From the iFIX WorkSpace, open the Database Manager.

3. Select **New** from the **Database** menu.
4. Select **Add** from the **Block** menu. The **Select Block Type** window appears.
5. Select **AO** and select **OK**. The **Analog Output** window appears.
6. Enter HOA_2 as the **Tag Name** and select **Save**.
7. Select **Add** from the **Block** menu. The **Select Block Type** window appears.
8. Select **PG** and select **OK**. The **Program** window appears.
9. Enter HB_HOA_1 as the **Tag Name** for the block.
10. (Optional) Enter a description for the tag name.
11. Enter the programming statements shown in the following figure for lines 0 through



12. Enter the programming statements shown in the following figure for lines 0 through 8.
13. Select **Save**. A message box appears asking you if you want to put the block on scan.
14. Select **No**.
15. Select **Reload** from the **Database** menu in the iFIX Database Manager. The **Reload** window appears
16. Select the database you currently have loaded and select **Reload**. A message box appears to confirm the reload.
17. Select **Yes** to continue.

In about a minute, you should notice the iFIX collector start. The status of the Collector should change on the Collector Maintenance page of Historian Administrator.

Part B: Configuration in Historian Administrator

Follow these steps to configure the heartbeat in Historian Administrator:

1. From Historian Administrator, select on the **Collector Maintenance** page.
2. Select the iFIX collector.
3. Select **Advanced**.
4. Enter `NODE1.HOA_2.F_CV` in the **Heartbeat Output Address** field as shown in the following figure.

The screenshot shows the 'Collector: NODE1' configuration window in Historian Administrator. The 'Advanced' tab is selected. Under 'Collector Options', there are several radio button settings: 'On-line Tag Configuration Changes' (Enabled), 'Browse Source Address Space' (Disabled), 'Synchronize Timestamps To Server' (Disabled), and 'Source / Device Timestamps In' (UTC). A text field for 'Delay Collection At Startup (sec)' contains the value '0'. Under 'Collector Status Outputs', there are three text input fields: 'Rate Output Address' (empty), 'Status Output Address' (empty), and 'Heartbeat Output Address' (containing 'NODE1.HOA_2.F_CV'). At the bottom, there are four buttons: 'Recalculate', 'Add Tags', 'Update', and 'Delete'.

5. Select **Update**.

Using an STK with the iFIX collector

To collect or browse tags with the iFIX collector when you use a system toolkit (STK) or Direct Driver Access (DDA) driver, which is also an STK, you need to edit the Fixtag.dat file to include the block types and field types for the STK. If you use a STK, there is no way to determine which block types the STK loads. Contact your STK vendor for more information.

Example: Using the BR3 STK

The Bristol Babcock BR3 driver uses the 160, 161, 162, and 163 block types. The following example shows how to add a `TYPE_160` block type with three field types (`F_CV`, `F_160`, and `F_XMITCNT`) for the BR3. For each new block type that you add, you need to follow the steps outlined in this example. So, if you want to add new block types for the 161, 162, and 163, you must repeat the steps outlined in this example.

Adding a New Block Type

Within the `<XML ID="dsoTags">` and `<MYLIST>` sections of the `Fixtag.dat` file, add a new `<ONEITEM>` entry for the new block type that you want to display in Historian Administrator. Enter the item name in the `<VALUE>` field and a description in the `<DATA>` field.

The following XML code shows what a `TYPE_160` entry for the BR3 might look like in the first portion of the `Fixtag.dat` file.

```
<ONEITEM>
<VALUE>TYPE_160</VALUE>
<DATA>The 160</DATA>
</ONEITEM>
```

Adding Field Types for a New Block Type

At the end of the `Fixtag.dat` file, before the `</BlockList>` tag, add field types for each new block type that you want to add for the BR3 driver. Each field type is contained in a block of text that starts and ends with these tags: `<ONEITEM>` . . . `</ONEITEM>`. You must enter three values, `<VALUE>`, `<DATA>`, and `<SELECTED>` for each field type that you want to display in Historian Administrator for the specified block type.

The `<VALUE>` and `<DATA>` tags include the new field type you want to add. The `<SELECTED>` tag contains either the word `True` or `False`, depending on whether or not you want the item to be included in the browse. The `True` and `False` states will change, however, depending on your selection in Historian Administrator.

The following XML code shows an example of three field types, `F_CV`, `F_160`, and `F_XMITCNT`, added for the `TYPE_160` block type created for the BR3.

```
<XML ID="TYPE_160">
<MYLIST>
<ONEITEM>
<VALUE>F_CV</VALUE>
<DATA>F_CV</DATA>
```

```

<SELECTED>False</SELECTED>

</ONEITEM>

<ONEITEM>

<VALUE>F_160</VALUE>

<DATA>F_160</DATA>

<SELECTED>False</SELECTED>

</ONEITEM>

<ONEITEM>

<VALUE>F_XMITCNT</VALUE>

<DATA></DATA>

<SELECTED>False</SELECTED>

</ONEITEM>

</MYLIST>

</XML>

```

After you add the block types and item types to the `Fixtag.dat` file and save the file, you can view them in Historian Administrator program.

Setting Up

Upgrading the iFIX Collectors

Before you upgrade the iFIX collectors, back up the collector registry folders. This is because the custom, user-added Registry folders are not retained after you upgrade.


When you upgrade the iFIX collector and the iFIX Alarms and Events collectors, services are created for instances created by the installer in the previous version.

If an iFIX collector instance created in version 9.0 exists, after you upgrade collectors, another instance of the iFIX collector is created. Because of this, the Remote Collector Manager (RCM) will not work correctly. Therefore, if you want to use RCM, you must delete one of the instances. If needed, you can manually create another instance of the iFIX collector using Configuration Hub or the RemoteCollectorConfigurator utility. This is applicable to the iFIX Alarms and Events collector as well.

After upgrading an iFIX collector, if you cannot manage iFIX services using Configuration Hub, refer to [Troubleshooting Remote Collector Management Issues \(on page 820\)](#).

The Configuration Section for iFIX collectors

To access the **Configuration** section for an iFIX collector, select an iFIX collector from the list on the left and select **Configuration**. The following page appears. The [Collector-Specific Configuration \(iFIX\) \(on page 2264\)](#) topic describes the information that appears in this section.



Collector-Specific Configuration (iFIX)

The **Configuration** section displays the following information.

Field	Description
Node Browse Criteria	<p>Displays the mask used to select tags when performing a browse of collector node. The default is the iFIX SCADA or Client node name on which you installed the collector.</p> <p>If you want to browse for tags on other iFIX nodes via FIX networking, you can enter the other node name(s) here, separated by commas with no spaces. You must have the iFIX system configured for networking. For more information, refer to the iFIX product documentation on iFIX networking.</p>

Field	Description
	<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If you have modified iFIX node name, then you must also update the Nodes to Browse list before browsing tags from the iFIX collector. When you browse multiple nodes for tags to add to an iFIX collector, do not use space characters between node names or between the required comma and next node name. All characters after the space are ignored. </div>
Tag Browse Criteria	<p>See Specify the Tags for Data Collection (on page 2255) for more information.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If you need to add block or field types to the list, edit the <code>Fix-Tag.dat</code> file for Historian Administrator you are using. See Editing FixTag.dat File (on page 2257) for more information. </div>

Configuration of iFIX Data Collector-Specific Fields

Adding a Historian tag with the selected database block source address allows you to collect the history of the collector's events per minute. This is very useful for troubleshooting and optimization analysis. The following table outlines the iFIX Data Collector-specific fields.

Field	Description
Rate Output Address	<p>NTF in the iFIX database into which the collector writes the current value of the events/minute output, letting an operator or the HMI/SCADA application know the performance of the collector.</p> <p>Use an iFIX tag for the output address. Enter the address as <code>NODE.TAG.FIELD</code> (for example, <code>MyNode.MySIM_AO.F_CV</code>).</p> <p>This value displays the same statistic as the Report Rate field of the iFIX Data Collector in the System Statistics page of Historian Administrator.</p>
Status Output Address	<p>NTF in the iFIX database into which the collector writes the current value of the collector status (for example, running) output, letting an operator or</p>

Field	Description
	<p>the HMI/SCADA application know the current status of the collector. This address should be connected to a writable text field of at least 8 characters. This value is only updated upon a change in status of the collector</p> <p>Use an iFIX tag for the output address. Enter the address as <code>NODE.TAG.FIELD</code> (for example, <code>MyNode.MyCollector_TX.A_CV</code>).</p> <p>The text string usually displays either <code>Running</code> or <code>Stopped</code> matching the Status column value displayed for the iFIX Data Collector in the System Statistics page of Historian Administrator.</p>
Heartbeat Output Address	<p>Address in the source database into which the collector writes the heartbeat signal output. This address should be connected to a writable analog field.</p> <p>Use an iFIX tag for the output address. Enter the address as <code>NODE.TAG.FIELD</code> (for example, <code>MyNode.MyCollector_AO.F_CV</code>)</p> <p>The iFIX Data Collector writes a value of 1 to this location every 60 seconds while it is running.</p> <p>Many applications use a heartbeat to indicate when something has stopped. For example, you could program the iFIX database to generate an alarm if the heartbeat output address is not written to once every 60 seconds notifying you that the iFIX Data Collector has stopped.</p>


**Note:**

Adding a Historian tag with the selected database block source address allows you to collect the history of the collector's events per minute. This is very useful for troubleshooting and optimization analysis.


Starting an iFIX Collector Instance

To start an instance of the iFIX collector, use one of the following options:

- **Using iFIX SCU:** Add the collector to the iFIX System Configuration (SCU) startup list. The collector then starts automatically whenever you start iFIX. This is the preferred way of starting the collector.
 - To run the default iFIX collector instances (the ones created during the installation of collectors), set the task parameters to `runasdos` as shown in the following image.



- To run additional instances of the iFIX collectors, set the task parameters to `NOSERVICE` `REG=<<CollectorInterfaceName>>`, as shown in the following image for a collector with the interface name `win2019dj2_iFix_1`.



**Note:**

To find out the collector interface name:

- If you have added the iFIX collector using Configuration Hub, the interface name is displayed in the **COLLECTOR NAME** column in the **Collectors** section.
- If you have added the iFIX collector using the RemoteCollectorConfigurator utility, the interface name is the value that you have provided for the InterfaceName parameter while adding the collector instance.

If you set the start-up mode to normal, you can manage the instances using Configuration Hub.

- **As a console application:** From the Windows Start menu, select **Historian iFix Collector > Start iFIX Collector**. Similarly, to start an iFIX Alarms and Events collector, select **Historian iFix Alarms and Events Collector > Start iFIX AE Collector**.
- **Using Configuration Hub:** You can [start collector instances \(on page 637\)](#) and [manage them \(on page 627\)](#) using Configuration Hub. For information on the expected behavior and recommended configuration of the iFIX collectors based on the running mode of iFIX, refer to [About Adding an iFIX Collector Instance \(on page 501\)](#).

Troubleshooting Issues with iFIX and Historian

Running iFIX as a Service with iFIX Workspace Listed in the SCU Task List: Prior to iFIX 5.1, if you have configured iFIX to run as a service, you should not have WORKSPACE.EXE listed as a configured task in the Task Configuration window of the SCU. If WORKSPACE.EXE is listed as a configured task, it may lead to unpredictable results. For example, if you are also running Historian, no servers will appear in the Server Name field of the Configure the Historian Server window and you will not be able to browse Historian tags in the iFIX Expression Editor.

To rectify this, remove WORKSPACE.EXE from the list of configured tasks in the SCU.

iFIX WorkSpace delay when remote session is lost: If the connection between iFIX and a remote Historian session is lost, you may experience a 90 second delay in the iFIX Workspace Configuration environment, chart, or Expression Builder when accessing a pen associated with that Historian session.

In the Run Time Environment, all pens in a chart disappear for 90 seconds when the session to a remote Historian session is lost, even if they are associated with a local Historian server.

Starting iFIX when a remote Historian session is unavailable: If you are using Historian with iFIX, the iFIX Workspace attempts to connect to the Historian Server when it starts up. If a remote Historian server is unavailable, it may take one minute or longer for iFIX Workspace to display for each unavailable server.

Accessing Mission Control when a remote Historian session is lost: If a remote Historian session is lost while you are accessing the **HTC** section of Mission Control in the iFIX Workspace, the **HTC** section may become unresponsive for a minute or longer.

Accessing tags in the iFIX chart after setting OPC "Collector to Made After Restart": If you add tags in Historian Administrator to a Server from an OPC Collector that has Configuration Changes set to Made After Collector Restart, you will be able to see those tags in the iFIX Expression Builder. You can add them to a chart, for example, but they have no collected data until you manually stop and restart the OPC Collector.

Collecting data in an iFIX chart with Time Assigned By Source: If you are retrieving data in an iFIX Chart from a Historian Server, have set the Time Assigned by field to Source, and have collectors running behind the Server time, the chart will display a flatline up to the current time of the local machine.



Note:

You must set Time Assigned by field to Source if you have unsolicited tags getting data from an OPC Collector.

Synchronizing the time on iFIX SCADA Servers and View Clients: To ensure that acknowledgements are not lost or attributed to the wrong alarm, synchronize the clocks on SCADA servers and iFIX View Client machines. If the clocks are not synchronized, alarms generated on the SCADA nodes and acknowledged on the iFIX View Client nodes could have significantly different timestamps. You can synchronize the clocks using the NET TIME command. Refer to the Windows Help system for more information.

The *Historian REST API Reference* manual specifies port 443 in examples and sample code. If you copy and paste the sample code from this Help manual, you must change this port number to your installed port.

If you have a previous install of Historian, and you have installed PHA/PKC 6.0/6.1, you will need to uninstall and then reinstall Historian.

Chapter 20. Migrating iFix Data

Migrating iFix Data to Historian

About Migrating iFix to Historian

The iFIX migration tools are intended for users who are responsible for migrating their Classic or Advanced Historian systems and iFIX Alarms and Events collector data to Historian. This manual assumes that you are familiar with the iFIX and the Advanced Historian or Classic Historian environments.

This manual describes the steps for planning your Historian migration and performing the migration of your data from both the Advanced Historian and Classic Historian environments.

For more information on running iFIX, refer to the *iFIX Help*. If you are planning to implement Electronic Signatures and Electronic Records or Historian Security, it is recommended that you perform migration prior to setting up or initializing these features. If the migration will be a gradual process over time, please refer to *Using Historian in a Regulated Environment*, *Using Historian* and [Implementing Security During Migration \(on page 2274\)](#).

Before You Begin

Before you start migrating your Classic or Advanced Historian data, be aware of the following:

- Confirm that your Historian environment is set up. For more information, refer to the [Getting Started with Historian \(on page 65\)](#) manual.
- Confirm that you have ample disk space on the archive machine. Assume that you need to have at least as much free space as the amount of data that you intend to migrate. For example, if you have 300MB of Advanced Historian data, you need at least 300MB free disk space on the Historian Server to accept that data.
- Do not uninstall Advanced Historian until you have migrated all the data to your Historian. Advanced Historian must be running and must have all its components in place for migration. The Historian Server that you are migrating to does not need to be on the same computer as the Advanced Historian or Classic data that you are migrating.
- Migrating a large amount of data from Advanced or Classic Historian into Historian may take a substantial amount of time, depending on the size of the database and the processing power of your machines. For more information, refer to [Estimating Migration time \(on page 2275\)](#).
- When migrating Historical data from a SCADA node to an Historian Server, it is recommended that you have an iFIX database loaded for the corresponding iFIX historical tags (on the source machine) prior to migration so that descriptions and EGUs can be retrieved.

- When migrating Historical data to Historian, it is recommended that you migrate the data in chronological order from the oldest to the newest. This prevents adding data out of order, which may impact migration performance and disk space usage.
- Migrate collection groups before historical data to maintain collection rates and deadbands.
- For migrating alarms and events data, determine the location and time range of your iFIX alarms logged via Alarm ODBC.

Historian Migration Utilities

Historian provides three utilities that allow you to migrate your existing Classic and Advanced Historian configuration and data into the Historian environment and migrate alarms and events data from iFIX. The Historian migration tools are designed to help you migrate your data quickly and easily. The tools allow you to:

- Select which Advanced Historian tags or Classic Historian archive files to migrate.
- Set up configuration options.
- Migrate data into your Historian system.
- Migrate alarms and events data logged via iFIX Alarm ODBC into your Historian system.

Plan Your Migration Strategy

In order to successfully migrate your data and alarms from existing iFIX or Advanced Historian applications into the Historian system, you should first plan out a sound migration strategy. Consider the following questions when planning your migration:

Questions	Refer to section
How should I be adding tags to the archive?	Adding Tags to the Archive (on page 2272)
Should I compress my data?	Planning Compression (on page 2272)
In what order should I migrate my data?	Recommended Migration Order (on page 2272)
Do I need any security rights to migrate my data?	Implementing Security During Migration (on page 2274)
What if my data is being migrated into an already active Historian system?	Planning Migrations with Online Systems (on page 2273)
Should I account for Daylight Savings Time or Time Zone differences?	Planning Daylight Savings Time (on page 2274)
How long will my migration take?	Estimating Migration Time (on page 2275)

Questions	Refer to section
What if my ADH archives have been moved around or I'm attempting to migrate backups of older ADH archives?	Registering Advanced Historian Archives (on page 2275)
Is there anything I should do after migrating?	After Migrating Your Data (on page 2276)

Adding Tags to the Archive

You must have tags in Historian to hold the migrated data. You can add tags automatically during group migration, data migration, or manually prior to migration using Historian Administrator. When you add tags by migration, you can set the maximum number of tag properties when the migration program has access to the real time database. Having access to the iFIX real time database allows the program to retrieve the Description, HI and LO Engineering Units, and Engineering Unit descriptions. These are not stored in the Classic Historian data or group files.

Migrating group files will add tags for immediate collection. Immediate collection occurs as a result of migrating the collection interval during the process of migrating the group files. Qualifier and phase values are not preserved, deadband values are preserved.

Planning Compression

Collector compression is automatically configured for collection groups that have a configured deadband in HTA when those collection groups are migrated to Historian.

By default, tags are migrated with archive compression turned off. Only archive compression has any effect on migration.

To enable archive compression during migration:

1. Add the tags through Historian Administrator, or, Migrate the historical groups.
2. After the tags are added to Historian, enable archive compression for each tag through Historian Administrator before migrating the Classic Historian data.
3. Subsequent migrated data can then pass through archive compression during migration.

Recommended Migration Order

When migrating historical data to Historian, it is recommended that you migrate the data in a chronological order from oldest to newest. This prevents adding data out of order, which may impact migration performance. It is also recommended that you migrate collection groups before data.

Planning Migrations with Online Systems

Typically, migration is performed after configuring and running new collection. Depending on the amount of data migrated, the process may take hours or days.

Alarm and event migration can take a significant amount of time. You can mitigate the risk of data loss by configuring the alarm collectors before starting the migration. You may also choose to migrate your alarms and events data in blocks of time ranges.

If you are migrating Classic Historian data and decide to select the **Overwrite Existing Tags** option in the **Migration Options** window, the existing Historian tag properties are replaced by the migrated Classic Historian tag properties and some configuration properties are overwritten. If you decide to clear the **Overwrite Existing Tags** option, tag information will not migrate into the Historian tag database. If you are migrating your Historian data into an existing Historian tag database, you may discover that tags with the same name exist in both the Historian database and the iFIX or Advanced Historian database.

**Note:**

Do not attempt to migrate the currently collecting Classic Historian file. If you do, you may receive an **Error -9**.

If you are migrating Advanced Historian data and decide to select the **Allow Updates to Existing Data** option in the Advanced Historian to Historian Migration Utility, the existing Historian tag data will be replaced by migrated Advanced Historian tag data if the data points have the same timestamps. If you decide to clear the Allow Updates to Existing Data option, the data will not be migrated (replaced) where there is existing data with duplicate timestamps in Historian.

Limit Processing Load on Server During Migration

Both data migration utilities provide you with the ability to limit the amount of processing load on the server during migration. This allows your online Historian Server to continue processing data efficiently while migration occurs. By modifying the **Events rate/second** field in the **Classic Historian Migration Options** window or the **Max values/sec** field in the Advanced Historian to Historian Migration Utility, you can specify how much data is sent and therefore how much processing power the Migration Utility receives on your system. The minimum you can set this rate to is 10,000 (or 0, meaning no throttle); the maximum you can set this field to is 100,000.

If you are performing a migration on a computer that is also processing other data or applications, you may want to set the event processing speed lower to allow your other applications to process well. The Historian Classic Migration and Advanced Historian Migration defaults to 10,000 events per second. The

default value allows you to throttle back the Migration Utility to allow for other applications processing, as well as continue running your Migration Utility at a reduced speed. If you are not running other data or applications on your machine and you want to run the Migration Utility at maximum speed, set the Events rate/second or Max Values/sec fields to 0.

**Tip:**

It is recommended that you do not set the events per second past 25,000 or below 10,000 (unless to 0). The higher the events per second, the faster your Migration Utility processes the migration. For example, the migration may take twice as long at 10,000 as it will at 20,000 but it will take less CPU time.

**Note:**

You cannot change this entry while migrating. It must be set prior to or changed after migration.

Implementing Security During Migration

In order to migrate data and alarms into the Historian System, you must be a member of the appropriate predefined Historian Security Groups if you have implemented Historian security. Refer to the Historian Group Rights section for information on the individual groups required for each task.

If any existing Historian Security groups are defined, you must supply a username and password before migrating your data in either the **Migration Options** window (for Classic Historian) or the **Advanced Historian to Historian Migration Utility** window (for Advanced Historian) or in the **Alarm Destination** window (for alarm migration).

Applying Daylight Savings Time

When migrating alarms or Classic Historian data, you can select whether or not you want to apply Daylight Savings Time (DST) bias to timestamps. The Migration Utility converts the timestamps of migrated samples to UTC time (universal time format for storing timestamps) before writing the data to Historian. If you select this option, the Migration Utility will apply the DST offset before converting to UTC time. The timestamps are converted to UTC time by adjusting the time based on the local computer time zone offset and DST setting.

If you enabled DST in your operating system during data or alarm logging, you must select the **Treat as DST Timestamp** option. With Classic Historian, a switch from Daylight Time to Standard Time results in a loss of one hour of data between 1:00:00 and 1:59:59 AM. With Historian, no loss of data occurs when you switch from Daylight Time to Standard Time.

**Note:**

The migration utilities assume that the computer you are migrating your data from and the computer that you are migrating your data to are in the same Time Zone.

Estimating Migration Time

Migrating a large historical database from either Advanced or Classic Historian into Historian may take hours or days, depending on the size of the database and the processing power of your machines.

To estimate migration time, refer to the total file size of the migration files. For Classic Historian migration, it takes approximately one minute to migrate 3 to 8.3 MBs of data. For the quickest migration, it is recommended that you clear the **Migrate Current Alarm** and the **Readback Values** option, if they are not required, in the **Classic Historian Migration Options** window.

For Advanced Historian data, it takes approximately 30 minutes to migrate 100 MB of data. This estimation assumes a default throttling of 10,000 events per second. If you have modified your **Max Values/sec** field in Advanced Historian, your migration time may vary. For more information, refer to [Limit Processing Load on Server During Migration \(on page 2273\)](#).

**Note:**

In addition to migration file size, migration time depends upon the processing power of the computer running the migration utility. It is highly recommended that you select a computer with high processing power to run the migration program.

Alarm migration performance is bounded to the CPU power of both the migrating machine and the alarm archiver machine.

Register Your Advanced Historian Archives

If you have changed the original location of your archives or you have backups of older archives that you wish to migrate, you must enable those archives by registering them.

Use the following guidelines when registering your archives:

- No other archive can hold data in the same time frame.
- Archives must be registered using `PIARTOOL -AR {Full Path of file}`.
- `PIARTOOL -AL` must show that the archive is registered prior to migration.

Note that any unregistered archive will not be migrated.

For more information on registering your archives, refer to step 2 of [Migrating Remote Advanced Historian Data \(on page 2288\)](#).

After Migrating Your Data

After migrating your data, ensure that you are no longer running Historical Collect (HTC). If you have HTC configured to start automatically from the iFIX WorkSpace, remove HTC from the SCU task startup list and replace it with the iFIX collector.

You may choose to do a Historian backup of your newly created Historian archives containing the migrated data.

After migrating your alarms, you may choose to change the data source name of the alarms so they match the data collector and appear as if they were collected along with the real time collector. For more information, see [the Alarms and Events collector \(on page 2390\)](#).

Adding the Historian Toolbar

To configure the toolbar to appear in the WorkSpace:

1. Start iFIX v4.0 or greater. The iFIX WorkSpace appears, if configured so.
2. Select **Toolbars** from the **WorkSpace** menu. The **Toolbars** window appears.
3. Select the **Customize** button. The **Customize Toolbars** window appears.
4. Select the **Import** button. The **Import Toolbars** window appears.
5. Select **Historian**.
6. Select the **Import** button. The **Historian Toolbar** appears.
7. Select the **Close** button to close the **Import Toolbars** window.
8. Select the **Close** button to return to the **WorkSpace**.

Configure Historian Server Buttons

The **Configure Historian Server** button in the **Historian Toolbar** specifies the location of historical data retrieval for the WorkSpace, not the location of the historical data storage. You can view/retrieve data stored on these listed servers while you select a pen for a chart display. The **Configure Historian Servers** window also determines where HDA programs and historical ODBC retrieve data from, which is always the default server.

Migration Checklist

The following is a list of general tasks for migrating your data to an online or new Historian system.

1. Verify that you are familiar with the setup recommendations. [How \(on page 2270\)?](#)
2. Estimate the number of archives that Historian will create during migration and verify that you have enough disk space to accommodate the new archives and backups of those archives. [How \(on page 2270\)?](#)
3. Migrate all collection groups. [How \(on page 2287\)?](#)

If you are migrating to an online Historian system and tags exist in the iFIX database, the collector begins collecting on those tags.

4. Export tag configuration information.
5. Migrate Classic Historical data or, [How \(on page 2278\)?](#)
6. Migrate Advanced Historical data or, [How \(on page 2284\)?](#)
7. Backup the newly created archives. How?
8. Start your collectors if they are not already running.
9. Verify migrated data through one of the following options:
 - iFIX chart
 - Raw data dump into OLE DB
 - Classic Historian log file
 - Data Readback Verification option in the Classic (optional) and Advanced (automatic) Migration utilities.

Migrating Classic Historical Data

About Migrating Classic Historical Data

Historian supplies a utility that allows you to migrate your existing Classic Historian data (used in iFIX) into your Historian database. Before migrating your Classic Historian data, plan your migration thoroughly. Refer to [Plan Your Migration \(on page 2271\)](#) for more information.

Once you have planned your Classic Historian migration, perform the following:

1. Add the Historian Toolbar to the iFIX WorkSpace. [How \(on page 2276\)?](#)
2. Configure Classic Historian Migration Options. [How \(on page 2280\)?](#)
3. Migrate existing groups. [How \(on page 2278\)?](#)
4. Migrate your Classic Historian Data. [How \(on page 2278\)?](#)

Migrating Classic Historian Data to Your Historian Database

The following procedure describes how to migrate Classic Historian data into your Historian database. For more information and tips on migrating data into an online system (one that is currently collecting new data as well), refer to the [Plan Migrations with Online Systems \(on page 2273\)](#).



Note:

When migrating data, Classic Historian nodes must be online with a loaded database so that descriptions and EGU values are retrieved. If the Classic Historian nodes are not online with a loaded database, the migration utility will create tags that may have incorrect descriptions and EGU values.

To migrate Classic Historian data into the Historian:

1. In Classic Historian, select the **Historian Migration Button**, shown in the following figure, to open the **Historian Migration Utility**.



2. Select **Configure Options** from the **Options** menu.
3. Enter or modify any specific configuration information. For more information, refer to the [Configuring Classic Migration Options](#) section.
4. Select **Migrate Collection Groups** from the **File** menu. The Utility prompts you to specify if you would like to migrate all groups.

The Historian Classic Migration Utility connects to the specified server and migrates the groups.



Note:

When migrating groups, Qualifier and Phase parameters are not migrated. If a group is not active, it is still migrated to the Historian. Groups are not preserved in Historian. All tags are added to Historian with the collection rate for the group.

5. Select **Migrate Historical Data** from the **File** menu. The **Select Historical Data File(s)** window appears.
6. Select one or more historical files and select **Open**.

The **Migration Utility** attempts to migrate all selected historical data files. The title bar displays the current file status (1 of 5, for example). Refer to the **Migration Utility** main page for information on the progress of the migration and any encountered errors.

**Note:**

The **Migration Utility** page only displays the most recent lines of the log file. For the full set of logged messages, refer to the log file, typically located in `C:\Program Files (x86)\GE\iFIX\Local\iFIX2IhMigration.Log`.

Migrating Classic Historian 10 Character L24 Files

Classic Historian supported both 10 character and 30 character lab data files (L24). The Historian Migration Utility successfully migrates 30 character L24 files, while 10 character L24 files cannot be successfully migrated.

**Attention:**

Do not attempt to migrate 10 character L24 files.

Comparing Classic Historian Data Plots and Historian Plots

If you compare plots of average, minimum, and maximum data in Classic Historian with similar plots in Historian, you may notice the following differences:

- The sample pens match, but the plot of the average value differs. Classic Historian computes the average during the “*next*” period and Historian computes the average over the “*previous*” period.
- Classic Historian also records the minimum/maximum value from raw data values, whereas Historian uses interpolated values to compute the minimum/maximum value.
- Historian uses interpolated value because Historian works with compressed data. When you work with compressed data, interpolated values let you project what the likely minimum/maximum values were during a given time interval that includes few raw data values due to compression.

Configuring Classic Migration Options

1. Open the **Migration Options** window, by selecting **Configure Options** from the **Options** menu in the Historian Classic Migration Utility.

Figure 9. Classic Historian Migration Options window

The screenshot shows the 'Migration Options' dialog box with the following settings:

- Historian Server Options:**
 - Historian Server: [Redacted]
 - Historian Username: [Empty]
 - Historian Password: [Empty]
 - Event Rate/Sec: 10000
- THISNODE Options:**
 - Substitute Name: [Empty]
- Logfile Options:**
 - Logfile: C:\DYNAMICS\LOCAL\iFix21hMigration.Log
 - Log Migrated Samples
 - Overwrite Logfile
- Tag Add Options:**
 - Overwrite Existing Tags
 - Migrate Current Alarm
- Data Add Options:**
 - Overwrite Existing Values
- Time Options:**
 - Treat as DST timestamp
- Readback Options:**
 - Write values to server
 - Readback Values

The Classic Historian Migration Tool automatically detects the default server and displays the default migration options.

2. Some of the options that you can configure include:
 - [Historian Server Options \(on page 2280\)](#)
 - [THISNODE Options \(on page 2281\)](#)
 - [Tag Add Options \(on page 2281\)](#)
 - [Logfile Options \(on page 2282\)](#)
 - [Readback Options \(on page 2283\)](#)

Historian Server Options

Allows you to set up your server information, limit or expand the application processing time, and input any needed security information. The Historian Server Options include:

Field	Description
Historian Server	The default server (set during installation). If you do not want to write data to the default server, enter the desired server in this field.
Historian Username and Password	If you have created and established Security Groups in your Historian Security Environment, you may need to enter the user name and password here. By default, if you do not supply any information, the current logged in user will be used in security checking. For more information about Historian Security, refer to Implementing Historian Security (on page 251) chapter of the <i>Getting Started</i> manual.
Event rate/sec	Allows you to limit the amount of server load caused by the Migration Utility. By reducing the Events/rate per second field in the Migration Options window, you can allocate more time to real time collection. The default rate is 10,000. For more information, refer to Limit Processing Load on Server During Migration (on page 2273) .

THISNODE Option

Specifies the Node name to use if you are migrating data collected using THISNODE. The utility automatically defaults to the name of the local iFIX node. If you want to change the Node name, enter a different Node name in this field.

Tag Add Options

Allows you to set the following options:

Field	Description
Overwrite Existing Tags	Selecting this option allows Historian to replace certain tag properties if the tags already exist in the Historian tag database.
Migrate Current Alarm	Whether or not the Migration Utility creates a tag and migrates the Current Alarm of each data sample (B_CUALM). Classic Historian paired the B_CUALM tag inside another tag and counted it as one. If this is enabled, the Historian Classic Migration Utility will separate these tags and add them both to the tag database.

Field	Description
	<div data-bbox="537 268 1421 443" style="border: 1px solid #f0e68c; padding: 10px; margin-bottom: 10px;">  Important: If you wish to migrate alarms and events data from iFIX to Historian, use the iFIX Alarms and Events collector Migration Tool. </div> <p>For example:</p> <p>The Classic Historian Tag:</p> <pre data-bbox="532 611 703 636">FIX.TAG1.F_CV</pre> <p>will convert to the Historian Tags:</p> <pre data-bbox="532 741 914 766">FIX.TAG1.F_CV, FIX.TAG1.B_CUALM</pre> <div data-bbox="537 800 1421 1022" style="border: 1px solid #add8e6; padding: 10px; margin-top: 10px;">  Note: If you clear the Migrate Current Alarm check box, the Current Alarm tags are not created and the alarm information is not transferred into Historian. </div>
Data Add Options Overwrite Existing Values	Whether or not the Classic Migration Utility overwrites existing values that have the same timestamp as the values being migrated in an active Historian database during migration.
Time Options Treat as DST Timestamp	Whether the migration should consider Daylight Savings Time (DST) when determining a UTC timestamp for migrated data. The timestamps are converted to UTC time by adjusting the time based on the local computer time zone offset and DST setting. For more information, refer to Managing Daylight Savings Time (on page 2274) .

Logfile Options

Allows you to configure the following options:

Field	Description
Logfile Location	Modify the default location of the <code>iFIX2IhMigration.LOG</code> file.
Log Migrated Samples	Create a log file of all raw samples migrated. This will cause all the values, timestamps, and qualities to appear in the log file.

Field	Description
	<div style="border: 1px solid orange; border-radius: 10px; padding: 10px; background-color: #fff9c4;"> <p> Important: Selecting this option significantly slows the performance of historical data migration.</p> </div>
Overwrite Logfile	Set whether or not the log file gets overwritten with each migration. By default, there is one log file (iFIX2IhMigration.LOG) that is overwritten each time you migrate data. Clearing this option causes the Historian Classic Migration Utility to append to the log file each time you migrate data.

Readback Options

Allows you to set the following options:

Field	Description
Readback Values	<p>Immediately read back samples after they are written. This verifies that the migration was successful. All samples that were written, including bad data quality and shutdown markers, are read back.</p> <div style="border: 1px solid orange; border-radius: 10px; padding: 10px; background-color: #fff9c4;"> <p> Important: Selecting the Readback Values option puts additional load on the archiver and can slow the migration process.</p> </div> <p>If samples are not found during the readback, the Migration Utility sends a message to the migration log file (\dynamics\local\ifix2ihmigration.log). It does not stop the migration.</p>
Write Values to Server	<p>The data writes and tag adds are written to the Archiver.</p> <p>If you want to perform a readback-only migration, clear this option and select the Readback Values option. This allows you to select a specific Classic historical file and perform a readback to confirm that all samples in the Classic file exist in Historian. If samples are not found during the readback, the Migration Utility sends a message to the migration log file (\dynamics\local\ifix2ihmigration.log). It does not stop the migration.</p>

Migrating Advanced Historian Data

Migrating Advance Historian Data

The Advanced Historian to Historian Migration Utility allows you to migrate Advanced Historian data into Historian.

Plan your Advance Historian data migration thoroughly. Refer to [Plan Your Migration \(on page 2271\)](#) for more information and establish your migration options.

1. Add the Historian Toolbar to the iFIX v2.5 or later WorkSpace. [How \(on page 2276\)?](#)
2. Explore the Advanced Migration Utility Options. [How \(on page 2284\)?](#)
3. Use the Classic Historian Migration Utility to migrate historical tag groups. [How \(on page 2287\)?](#)



Important:

If you plan to run the Advanced Historian to Historian Migration Utility on a non-SCADA node, migrate the groups after running the utility. If you try to migrate the groups first, you will not have correct EGU information for the iFIX/Advanced Historian historical tags.

4. Migrate Advanced Historian Local Data. [How \(on page 2284\)?](#)
5. Migrate Advanced Historian Remote Data. [How \(on page 2288\)?](#)

Advanced Historian to Historian Migration Utility

You can open the Advanced Historian to Historian Migration Utility by selecting **Migration Tool for Advanced Historian** from the **Historian** directory in the **Start** menu. Some of the options you can configure include:

- [Advanced Historian Connection Information \(on page 2285\)](#) Displays information for the Advanced Historian machine you are migrating your historical data from.
- [Historian Information \(on page 2285\)](#) Displays the information for the Historian Server that you want to migrate your historical data to.
- [Migration Options \(on page 2285\)](#) Allows you to select all or specific tag masks and set the time range for migration.
- [Migration Status \(on page 2286\)](#) Displays the current status of the migration.
- [Migration History \(on page 2286\)](#) Displays the history of all migrations that have occurred on that machine.

Advance Historian Connection Information

The **Advanced Historian Connection Information** section displays information for the Advanced Historian machine you are migrating your historical files from.

Field	Description
Computer Name	The name of the machine you want to migrate the Advanced Historian data from.
Username and Password	The username and password, if you had Advanced Historian security configured for archives.

Historian Information

The **Historian Information** section displays the information for the Historian Server that you want to migrate your historical data to.

Field	Description
Computer Name	The Historian Server to migrate Advanced Historian tags and data to.
Username and Password	If you have created and established Security Groups in your Historian Security Environment, you may need to enter the username and password here. By default, if you do not supply any information, the current logged in user will be checked. For more information on setting up Historian Security, refer to Implementing Historian Security (on page 251) .

Migration Option

The **Migration Options** section allows you to select all or specific tagmasks and set the time range for migration

Field	Description
Tagname Mask	Specify certain tags for migration only (NODE1:* for instance) or select all tags (*).
Starting Date	Select a starting date for migrating data.
Ending Date	Set an ending date for migrating data.

Field	Description
	 Note: The Migration Utility migrates data up to but not including the specified Ending Date. Carefully select your Ending Date to ensure that you include all required data in the migration.
Configure New Tags As Required	Specify whether the Migration Utility automatically creates tags upon migration, or migrates data only for tags that already exist in the Historian tag database. This allows you to manually create the tags you want to migrate in Historian first, then run the migration only for those tags.
Use Tag Configuration from iFIX	Maintains tag specific configuration for iFIX tags. If you do not select this option, Historian uses its tag configuration default settings when migrating iFIX tags. For example, if you have an EGU set to 25-55 in an iFIX tag and you clear this option, the tag migrates with an EGU of 0-100.
Allow Updates to Existing Data	Allows Historian to replace data if data already exists for the tag at that timestamp.
End of Collection Marker	Write a bad data quality data point for each tag when the migration concludes. Select this option if you do not want your trend applications to display a continuous plot of the last good sample for that Historian tag.

Migration Status

Displays the current status of the migration progress. The **Migration Status** window provides real time migration status including the currently migrating tag and the tag range (2 of 1000) status. **Migration Status** window also allows you to start the migration process and abort it once it has started.

Migration History

Displays a log of what times and tag masks were migrated and the status (success/failure) of that migration. The information displayed in the **Migration History** window is also available in the log file, typically located in the `C:\Historian Data\LogFiles` folder.

Migrating Your Groups

Migrate your groups using the Classic Historian Migration Tool. This allows you to maintain any configured collection rates and deadbands.



Important:

If you plan to run the Advanced Historian to Historian Migration Utility on a non-SCADA node, migrate the groups after running the utility. If you try to migrate the groups first, you will not have correct EGU information for the iFIX/Advanced Historian historical tags.

1. Open the **Classic Migration Utility** from the Historian Toolbar.
2. Select **Configure Options** from the **Options** menu.
3. Select or clear the **Overwrite Existing Tags** option. This is the only option that applies to group migration. For more information, refer to the [Configuring Classic Migration Options \(on page 2280\)](#) section.
4. Select **Migrate Collection Groups** from the **File** menu. The Utility prompts you to specify if you would like to migrate all groups.

The **Historian Classic Migration Utility** connects to the specified server and migrates the groups.



Note:

When migrating groups, Qualifier and Phase parameters are not migrated. If a group is not active, it is still migrated to the Historian with a collection rate.

Migrating Existing Advance Historian Data

When migrating Advanced Historian data, you can only run the migration from a node that either has the Advanced Historian Server or the Advanced Historian client installed. Also, ensure that Automatically Create Archives is enabled in Historian Administrator.

To migrate Advanced Historian data from an existing Advanced Historian node to your Historian Server:



Note:

Before you begin, ensure the client's time is synchronized with the server's time and that there is enough free space on the Historian server to store the migrated data.

1. From the **Start** menu, select the **Migration Tool for Advanced Historian** from the Historian directory.

The [Advanced Historian to Historian Migration Utility \(on page 2284\)](#) window appears.

2. Enter the name of the Computer from which you are migrating the Advanced Historian data.
3. If you configured Advanced Historian security, enter the username and password for security.
4. The **Advanced Historian Migration Tool** automatically detects and displays the default server in the **Historian Connection Information Computer Name** field.

If you want to change the server you migrate data to, enter that server name in the **Computer Name** field of the **Historian Connection Information** section.

5. If necessary, enter a username and password in the **Historian Connection Information Username and Password** fields.

If you do not provide a username and password, security defaults to check the currently logged in user.



Note:

You must have **Write, Tag Administrator**, and **Read** privileges in order to run the migration. It is recommended that Security Administrators run the migration, for best performance.

6. If you do not wish to migrate all tags, enter a tagname mask for selected tags.
7. Select a start and end date from the drop-down calendars.
For more information on estimating migration time, please refer to the [Estimate Migration Time \(on page 2275\)](#) section of this manual.
8. If you want the **Migration Tool** to create tags automatically if they do not exist, leave the **Configure New Tags as Required** option selected.
For more information on this setting, refer to the [Plan Migrations with Online Systems \(on page 2273\)](#) section.
9. If you do not wish to overwrite existing values with migrated values containing the same timestamp, clear the **Allow Updates to Existing Data** option.
10. If you do not want your trend applications to display a continuous plot of the last good sample for that Historian tag, select the **End of Collection** marker.
For more information on this setting, refer to [Migration Options \(on page 2285\)](#).
11. Select the **Start Migration** button.
12. Refer to the **Migration History** window and the log file for information on the success of the tag migration and any errors or problems encountered during migration.
You can re-run the migration utility for any time period.

Migrating Remote Advanced Historian Data

This section describes how to migrate your Advanced Historian Data from a remote machine.

Ensure that you have installed the required software correctly. Refer to the [Recommended Software Installation Order \(on page 2290\)](#) section for more information.

If this procedure is not run as listed, you may experience problems inserting a chart control into the iFIX WorkSpace, running any programs using `fixtools.dll` or `fixhdadll.dll`, or running certain Historian features. Several `*.dll(s)` are replaced by older versions by the Advanced Historian. When Advanced Historian is removed, it replaces the older versions with the originals and Historian works correctly.

1. Ensure that PI services are running on the remote machine.
 - a. Double-click the **Services** icon in the Control Panel.
The **Services** window appears.
 - b. Locate the Services beginning with 'PI'. Start all PI services except the **PI Shutdown** service.
2. Ensure that all needed archives are listed as registered.
 - a. Open the **MSDOS** prompt.
 - b. Navigate to the `Dynamics\AdvancedHistorian\adm` directory.
 - c. Enter ``piartool al'` to list the registered archive files. –
 - d. Register any unregistered archive files that you need to migrate by typing ``piartool ar ` + {fully qualified archive name.} –`

Example - `piartool ar C:\Program Files (x86)\GE\iFIX\archives
\DynamicArchive.001-`
3. On the local machine (machine with Historian loaded), run the Migration Utility.
 - a. From the **Start** menu, select the **Migration Tool for Historian** in the Historian directory.
The [Advanced Historian to Historian Migration Utility \(on page 2284\)](#) appears.
 - b. Enter the name of the remote computer you are migrating the Advanced Historian data from.
 - c. If you configured Advanced Historian security, enter the username and password for security.
 - d. The **Advanced Historian Migration Tool** automatically detects and displays the default server in the **Historian Connection Information Computer Name** field.
If you want to change the server to which you will migrate data, enter that server name in the **Computer Name** field of the **Historian Connection Information** section.

- e. If you have set up security on your Historian Server, enter a username and password in the **Historian Connection Information Username and Password** fields. If you do not provide a username and password, security defaults to check the currently logged in user. If you are already logged into Windows Server 2003 or Windows Serve 2008 with an account with rights to the Historian Server, you do not need to supply a new username and password.

You must have Write, Tag Administrator, and Read privileges in order to run the migration. It is recommended that Security Administrators run the migration, for best performance.

- f. If you do not wish to migrate all tags, enter a tagname mask for selected tags.
- g. Select a start and end date from the drop-down calendars. It is recommended migrating data in two month time blocks, from the oldest data to the newest. For more information on estimating migration time, please refer to the [Estimate Migration Time \(on page 2275\)](#) section of this manual.
- h. If you want the Migration Tool to create tags automatically when they don't exist, leave the **Con-figure New Tags as Required** option selected. For more information on this setting, refer to the [Plan Migrations with Online Systems \(on page 2273\)](#) section.
- i. If you do not wish to overwrite any information in existing tags, clear the **Allow Updates to Existing Data** option.
- j. If you do not want your trend applications to display a continuous plot of the last good sample for that Historian tag, select the **End of Collection** marker. For more information on this setting, refer to [Migration Options \(on page 2285\)](#)
- k. Select the **Start Migration** button.
- l. Refer to the **Migration History** window and the log file for information on the success of the tag migration and any errors or problems encountered during migration.

Recommended Software Installation Order

Before migrating your remote Advanced Historian Data, ensure that you have installed the required software correctly on your local machine. The following installation order is recommended:

1. Install iFIX 4.5 or higher.
2. Reboot your computer.

3. Install Advanced Historian
 - a. Select Custom Installation with ONLY Client install.
 - b. Reboot your computer.
4. Install Historian completely.

Removing Advanced Historian (From Local Machine)

After you have completely migrated your remote Advanced Historian Data, it is recommended that you remove Advanced Historian from your local machine.

1. Stop all PI services from the Control Panel Services window.
 - a. Double-click the **Services Icon** in the Control Panel.
The **Services** window appears.
 - b. Locate the **PI Network Manager Service** and select the **Stop** button.
2. Another window appears asking if you would like all the other services stopped.
Select **Yes**.
3. Locate the **bufserv** service and stop it.
4. Completely remove Advanced Historian using the uninstall feature in the **Add/Remove Programs** window.
5. Reboot your computer.
6. Delete the `\AdvancedHistorian` directory from the Dynamics base path.

**Note:**

You may want to stop **PI Services** again, as detailed in step 1.

7. Use the **AHClean** utility located on the GE Automation web site in the Developers Corner.
8. Run `AHClean.exe` and select the **Clean Registry** button.
9. Reboot your computer.

Migrating iFIX Alarms and Events Collector

Migrating iFIX Alarms and Events collector

The following procedure describes how to migrate iFIX Alarms and Events collector data into your Historian database.

1. Locate and double-click the `ifixalmmig.exe` file in the `C:\Program Files (x86)\GE\iFIX\Local` directory.
2. Set up the [alarm source \(on page 2293\)](#) options:
 - a. From the **Options** menu, choose **Alarm Source**. The **Alarm Source Options** window appears.
 - b. Configure the [ODBC Login \(on page 2293\)](#) information.
 - c. Enter the table name for the database, and select on **Fetch Columns**.
The table's associated columns appear in the **SQL Column Name and iFIX Field Name** table.
For more information, refer to the [Database Configuration \(on page 2293\)](#).
 - d. Configure [Severity Mapping \(on page 2293\)](#).
3. Select **OK**.
4. Set up the [Alarm Destination \(on page 2295\)](#) options:
 - a. From the **Options** menu, choose **Alarm Destination**. The **Alarm Destination Options** window appears.
 - b. Configure the [Historian Server Options \(on page 2295\)](#).
 - c. Configure the [Logfile \(on page 2295\)](#).
 - d. Configure the [Time Options \(on page 2295\)](#).
5. Select **OK**.
6. From the **File** menu, choose **Migrate Alarms**.
7. Select a start and end time for the alarm migration.



Note:

If the ODBC driver does not support the CAST function, it is recommended that you create the DATETIME data type field in your Alarm ODBC table and update the field by combining the ALM_DATELAST and the ALM_TIMELAST using a concatenation and cast or convert function. If the data source does not include a native time, the start and end times will be disabled, and the entire table will be queried. This may result in an "out of resources" state.

See your *Alarm ODBC backend Data Base* documentation for more information.

8. Select **OK**. The window closes, and migration commences.
Activity is logged to both the page and the log file configured in the **Alarm Destination Options** window.
9. Update the datasource name of your migrated alarms to match collected alarms.

iFIX Alarms and Events collector Migration Options Configuration

Configuration of the iFIX Alarms and Events collector Migration tool is contained in two windows. The **Alarm Source Options** window contains configuration for the iFIX system you wish to migrate alarms and events data from. The **Alarm Destination Options** window contains configuration for the Historian archive you wish to migrate alarms and events data to.

In general, configuration of the alarm migration options should match the configuration of your iFIX Alarms and Events collector server. By doing this, your migrated and collected alarms are stored in the same format, easing the development of alarm analysis and reporting applications.

Alarm Source Options

The **Alarm Source Options** window is split into four sections:

- ODBC Login Information
- Attribute Names
- Severity Mapping
- Database Configuration

ODBC Login Information

The following configuration fields are shown in the ODBC Login Information section of the **Alarm Source Options** window. In general, the settings in this section should match the settings used in your iFIX Alarm ODBC Configuration in the iFIX SCU.

Option	Description
Database Type	<p>The type of database your iFIX alarms are stored in. The following options are available:</p> <ul style="list-style-type: none"> • Access • Oracle • SQL Server • Sybase <div data-bbox="820 1663 1416 1879" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: If you are unsure of which database your iFIX alarms are stored in, contact your systems administrator</p> </div>

Option	Description
User Name	The user name required to authenticate with your database.
Password	The password required to authenticate with your database.
Database Identifier	<p>The name of the database your iFIX alarms are stored in. Select the Browse button to bring up the Database IDs Available window.</p> <div data-bbox="820 646 1412 949" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: If you are migrating on a machine other than the machine running Alarm ODBC, you may have to configure a DSN in the control panel before entering it in the Database Identifier.</p> </div>

Attribute Names

Use this section only if you have logged alarm user and/or extension fields AND you want to control the name of the fields created in Historian. If you have changed the default names in the iFIX Real Time Alarms and Events Server, edit the configuration in this section to match.

Option	Description
iFIX Field Name	The iFIX Field name of the alarm.
Attribute Name	The mapped attribute name of the alarm.

Severity Mapping

If you have changed the default severity settings in the real-time AE Server, edit the configuration in this section to match.

Option	Description
Low	The severity to assign to low priority alarms.
Medium	The severity to assign to medium priority alarms.
High	The severity to assign to high priority alarms.

Database Configuration

If you have set up custom column names in the iFIX Alarm ODBC configuration, you may need to map the **SQL Column Names** to **iFIX Field Names**. If you have kept the default column names in the iFIX Alarm ODBC configuration, you should not have to make any changes in this section.

Option	Description
Table Name	Enter the name of the database table in which iFIX Alarms and Events collector data is stored.
Fetch Columns	Selecting this button will fetch all columns from the table.
SQL Column Name	Identifies the name of the column within the database table.
iFIX Field Name	Identifies which iFIX Field name the SQL Column name maps to.
Clear Column Settings	Select to clear all column settings.
Save Column Settings	Select to save all column settings in the window.

SQL columns and their iFIX meanings are automatically matched up when the columns are fetched. You only need to configure iFIX meanings if you have used a non-default column name. If you want to exclude columns from migration to save space in Historian, set the iFIX meaning to blank. For example, if you logged both **Native Time Last** and **Time Last** in Alarm ODBC, you only need to migrate the **Native Time Last** field. Set the iFIX meaning of **Time Last** to blank.

If you use the **Save Column Settings** option, iFIX meanings are saved to `C:\Program Files (x86)\GE\iFIX\local\ifixalmmig.ini`. When working with a different database table, you can erase the iFIX meanings by deleting the `ifix-almmig.ini` file or selecting the **Clear Column Settings** button.



Note:

The Alarms and Events database version must match the SQL Server version that it is running on.

Alarm Destination Options

The **Alarm Destination Options** window has three sections:

- Historian Server Options
- Logfile Options
- Time Options

Historian Server Options

Option	Description
Historian Server	The server name of the Historian server you wish to migrate the iFIX Alarms and Events collector data to.
Historian Username	The username required to authenticate with the Historian server.
Historian Password	The password required to authenticate with the Historian server.

Logfile Options

Option	Description
Logfile Location	Modify the location of the iFIXAlmMigration.Log file.
Overwrite Logfile	Set whether or not the log file gets overwritten with each migration. By default, there is one log file (<code>iFIXAlmMigration.Log</code>) that is appended each time you migrate alarms. Clearing this option causes the iFIX Alarm Migration Utility to overwrite the log file each time you migrate alarms.

Time Options

Option	Description
Treat as DST timestamp	<p>If enabled, the migration utility will treat all timestamps as if they are Daylight Savings Time.</p> <p>Refer to Manage Daylight Savings Time (on page 2274) for more information.</p>

Troubleshoot iFIX Alarms and Events collector

Wrong Data Source Name on Migrated alarms

The data source of an alarm starts as the interface name of the alarms and events collector that sent it. If the alarms and events collector is not associated with a data collector, then the data source is converted to match the data collector's interface name. When migrating alarms, however, the original data source name will be retained. This can cause a disconnect between migrated data and newly collected data, and cause problems when analyzing alarms and events data.

To resolve this issue:

1. Select the **File** menu, then select **Update Alarms**.
2. In the **Old Datasource** field, enter the original data source name.
3. In the **New Datasource** field, enter the new data source name.
4. Select **OK**.

Datetime Column Not Found

iFIX prior to v2.6 did not have a datetime column.

No Columns Returned

If no columns are returned after entering a table name and selecting **Fetch Columns**, you may have incorrectly entered the Alarm ODBC table name. Re-enter the Alarm ODBC table name and select **Fetch Columns**.

Chapter 21. The MQTT Collector

Overview of the MQTT Collector

The MQTT collector collects data published to a topic using an MQTT broker.



Note:

We have tested with the MQTT brokers Mosquitto 2.0.15 and HiveMQ-4.2.1. You can, however, use other MQTT brokers as well.

Supported MQTT versions:

- MQTT V5
- MQTT V3.1.1

Supported data formats:

- Sparkplug B V1.0



Note:

The MQTT collector supports Sparkplug B payload and processes only NDATA or DDATA messages, discarding the other messages.

- KairosDB (that is, the Predix Timeseries format)

Topology: The MQTT collector supports a distributed model, that is, the MQTT broker, the collector, and the Historian server can be installed on the same machine or on different machines.

Features:


- You can subscribe to multiple-level topics using a wildcard.
- Only the unsolicited data collection is supported; polled collection is not supported.
- The timestamp resolution is seconds, milliseconds, and microseconds.
- Array, boolean, floating point, integer, and string data types are supported.

**Note:**

Although the **Recalculate** button in Historian Administrator is enabled, the functionality is not available because the MQTT collector is a non-historic collector (the source broker does not store the historical data).

How it works:

1. The MQTT collector connects to an MQTT broker and subscribes to a topic. You can use username/password-based authentication or certificate-based authentication. Transport Layer Security (TLS) authentication is used for subscribing the data from message broker to avoid middleware attacks so that the data is securely transferred from message broker to the MQTT collector.
2. The collector converts the data from the Sparkplug B v1.0 or the KairosDB format to a Historian-understandable format.
3. It verifies whether the tag is available in Historian; if not, it will add the tag and then add the data samples, and streams the data to the Historian server or a cloud destination.

**KairosDB Message Format:**

```

{
  "body":
  [
    {
      "attributes": {"machine_type": "<value>"},
      "datapoints": [[<value>, <value>, <value>]],
      "name": "<value>"
    }
  ],
  "messageId": "<value>"
}

```

The following table describes these parameters.

JSON Parameter	Description	Required/Optional
machine_type	The name of the machine from which you want to collect data.	Optional
datapoints	Time (in epoch format), value, and quality.	Required
name	The tag name	Required
messageld	The type of the message	Optional

**Note:**

For the parameters marked optional, you need not enter values. However, you must enter the parameter names. For example:

```
{ "body": [{ "attributes": { "machine_type": " " },
"datapoints": [[1558110998983,9547909,3]], "name": "QuadInteger" }], "messageId": " " }
```

Supported Data Types

Source Data Type	Historian Data Type
Array	ihArray
DoubleFloat, DoubleInteger, FixedByte, QuadInteger, SingleFloat	ihDoubleFloat
ByteString, String	ihVariableString
Boolean	ihBool

Configuration

Add and Configure an MQTT Collector

1. Ensure that you have an MQTT broker.

**Note:**


We have tested with the MQTT brokers Mosquitto 2.0.15 and HiveMQ-4.2.1. You can, however, use other MQTT brokers as well.

2. If you want to use username/password-based authentication or certificate-based authentication to connect the MQTT broker and the MQTT collector, configure the authentication in the MQTT broker.
3. If you want to use certificate-based authentication, ensure that the following files are available on your collector machine:
 - CA server root file
 - Private key file
 - Client certificate file

The MQTT collector collects data published to a topic using an MQTT broker. For more information, refer to [Overview of the MQTT Collector \(on page 2298\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **MQTT Collector**, and then select **Get Details**. The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. Enter values as described in the following table.

Field	Description
MQTT BROKER ADDRESS	Enter the host name of the MQTT broker using which you want to collect data. A value is required.
MQTT BROKER PORT	Enter the port number of the MQTT broker. A value is required.
TOPIC	<p>Enter the MQTT topic from which you want to collect data. A value is required. You can enter multiple topics separated by commas.</p> <p>If you want to use the Sparkplug B format, enter a value in the following format: <code>namespace/group_id/message_type/edge_node_id/device_id</code></p> <p>where:</p> <ul style="list-style-type: none"> ◦ <code>namespace</code> is the Sparkplug version. Enter <code>spBv1.0</code>. ◦ <code>group_id</code> is the ID of the group of nodes from which you want to collect data. ◦ <code>message_type</code> is the message type from which you want to collect data. The collector processes data only from NDATA and DDATA message types. ◦ <code>edge_node_id</code> is used to identify the MQTT EoN node within the infrastructure. ◦ <code>device_id</code> a device attached to the MQTT EoN node either physically or logically. <p>You can use the wildcard character <code>#</code> for any of these parameters (except for namespace).</p>
USERNAME	Enter the username to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
PASSWORD	Enter the password to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.

Field	Description
CA SERVER ROOT FILE	Enter the path to the CA server root file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
PRIVATE KEY FILE	Enter the path to the private key file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
CLIENT CERTIFICATE FILE	Enter the path to the client certificate file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
REQUESTED QUALITY OF SERVICE (QoS) LEVEL	<p>Select the quality of service that you want to use while collecting data from an MQTT broker.</p> <ul style="list-style-type: none"> ◦ QoS 0: Indicates that the message is delivered at most once or it is not delivered at all. ◦ QoS 1: Indicates that the message is always delivered at least once. ◦ QoS 2: Indicates that the message is delivered once. <p>For more information, refer to https://www.hivemq.com/blog/mqtt-essentials-part-6-mqtt-quality-of-service-levels/.</p>
MQTT VERSION	Select the version of the MQTT that you want to use.
CLEAN SESSION	<p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ True: Select this option if you do not want to create a new session when the MQTT broker and the collector are disconnected from each other. ◦ False: Select this option if you want to retain the session when the MQTT broker and the collector are disconnected from each other. This ensures that there is no loss of data. If you want to choose this option, ensure that you have selected QoS 1 or QoS 2 in the REQUESTED QUALITY OF SERVICE (QoS) LEVEL field.
SESSION EXPIRY INTERVAL	Enter the duration, in seconds, after which the data will be discarded when connection between the MQTT broker and collector is re-established.

Field	Description
	<p>For example, if you enter 100 in this field, and if the MQTT broker and collector are disconnected for 90 seconds, the data is collected. If, however, the MQTT broker and the collector are disconnected for more than 100 seconds, the data will be discarded.</p> <p>This field is applicable only for MQTT V5 and only if you set the CLEAN SESSION field to False.</p>
CONTENT TYPE	<p>Select the format that you want to use for the payload:</p> <ul style="list-style-type: none"> ◦ JSON: Select this option if you want to use the KairosDB format. ◦ SparkPlug B v1.0: Select this option if you want to use the Sparkplug format.

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.
- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).
 - b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears.

11. If needed, modify the value in the **COLLECTOR NAME** field. The value must be unique, must contain the string `MQTT`, and must not contain a space.

The value that you enter:

- Must be unique.
- Must contain the string `MQTT`.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

14. In the **COLLECTOR SPECIFIC CONFIGURATION** and **INSTANCE CONFIGURATION** sections, configure the values as described in the following table.

COLLECTOR SPECIFIC CONFIGURATION

Field	Description
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

INSTANCE CONFIGURATION


Field	Description
MQTT Broker Address	Enter the host name of the MQTT broker using which you want to collect data. A value is required.
MQTT Broker Topic	<p>Enter the MQTT topic from which you want to collect data. A value is required. You can enter multiple topics separated by commas.</p> <p>If you want to use the Sparkplug B format, enter a value in the following format: <code>namespace/group_id/message_type/edge_node_id/device_id</code></p> <p>where:</p> <ul style="list-style-type: none"> ◦ <code>namespace</code> is the Sparkplug version. Enter <code>spBv1.0</code>. ◦ <code>group_id</code> is the ID of the group of nodes from which you want to collect data. ◦ <code>message_type</code> is the message type from which you want to collect data. The collector processes data only from NDATA and DDATA message types.

Field	Description
	<ul style="list-style-type: none"> ◦ <code>edge_node_id</code> is used to identify the MQTT EoN node within the infrastructure. ◦ <code>device_id</code> a device attached to the MQTT EoN node either physically or logically. <p>You can use the wildcard character # for any of these parameters (except for namespace).</p>
MQTT Brker Port	Enter the port number of the MQTT broker. A value is required.
Username	Enter the username to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
Password	Enter the password to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
CA Server Root File	Enter the path to the CA server root file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
Private Key File	Enter the path to the private key file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
CLIENT Certificate File	Enter the path to the client certificate file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
Requested Quality Of Service (QoS) Level	<p>Select the quality of service that you want to use while collecting data from an MQTT broker.</p> <ul style="list-style-type: none"> ◦ QoS 0: Indicates that the message is delivered at most once or it is not delivered at all. ◦ QoS 1: Indicates that the message is always delivered at least once. ◦ QoS 2: Indicates that the message is delivered once. <p>For more information, refer to https://www.hivemq.com/blog/mqtt-essentials-part-6-mqtt-quality-of-service-levels/.</p>
MQTT Version	Select the version of the MQTT that you want to use.

Field	Description
<p>CLEAN Session</p>	<p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ True: Select this option if you do not want to create a new session when the MQTT broker and the collector are disconnected from each other. ◦ False: Select this option if you want to retain the session when the MQTT broker and the collector are disconnected from each other. This ensures that there is no loss of data. If you want to choose this option, ensure that you have selected QoS 1 or QoS 2 in the REQUESTED QUALITY OF SERVICE (QOS) LEVEL field.
<p>SESSION Expiry Interval</p>	<p>Enter the duration, in seconds, after which the data will be discarded when connection between the MQTT broker and collector is re-established.</p> <p>For example, if you enter 100 in this field, and if the MQTT broker and collector are disconnected for 90 seconds, the data is collected. If, however, the MQTT broker and the collector are disconnected for more than 100 seconds, the data will be discarded.</p> <p>This field is applicable only for MQTT V5 and only if you set the CLEAN SESSION field to False.</p>
<p>Content Type</p>	<p>Select the format that you want to use for the payload:</p> <ul style="list-style-type: none"> ◦ JSON: Select this option if you want to use the KairosDB format. ◦ SparkPlug B v1.0: Select this option if you want to use the Sparkplug format.

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,


- If you have selected **Historian Configuration**, [specify the tags using Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of Historian>\GE Digital\<<collector name>*. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Configure the MQTT Collector Using Historian Administrator

If you want to connect the MQTT collector with an MQTT broker using a username/password-based or a certificate-based authentication, configure the same in the MQTT broker.

1. Access Historian Administrator.
2. Select **Collectors**, and then select the MQTT collector instance that you want to configure.
3. Select **Configuration**.

The **Configuration** section appears.



4. Enter values as specified in the following table.

Field	Description
Source Host Name	The hostname or IP address of the machine on which the MQTT message broker is running.
Source Topic	The topic for which you want to get the data from the message broker.
Source Port	The port number of the machine on which the MQTT message broker is running.
Authentication	The authentication details to connect to the MQTT broker. If you want to use MQTT V3.1.1, enter a value in the following format: <code>username=<value> password=<value> cafile=<path to the CA server root file> certfile=<path</code>

Field	Description
	<p data-bbox="414 275 1409 348"><i>to the client certificate file> privatekeyfile=<path to the private key file> qos=<quality of service value> version=MQTT_V311</i></p> <p data-bbox="414 373 1427 632">If you want to use MQTT V5, enter a value in the following format: <i>username=<val- ue> password=<value> cafile=<path to the CA server root file certfile=<path to the client certificate file> privatekeyfile=<path to the private key file> qos=<quality of service value> version=MQTT_V5 clean-session=<true or false> session-expiry-interval=<interval in seconds> content-type=<json or SparkPlug B v1.0></i></p> <div data-bbox="414 661 1427 846" style="border: 1px solid #00a0c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p data-bbox="430 682 560 724"> Note:</p> <p data-bbox="495 735 1404 814">For information on setting the quality of service value, refer to https://www.hivemq.com/blog/mqtt-essentials-part-6-mqtt-quality-of-service-levels/.</p> </div>

5. Select **Update**.

6. Restart the collector.

The collector is configured.

Chapter 22. The MQTT Sparkplug B Collector

Overview of the MQTT Sparkplug B Collector

The MQTT Sparkplug B collector enables you to connect as a Primary Host application and collect data based on the MQTT Sparkplug B specification (Sparkplug 3.0.0). Specifically, you can subscribe to a topic that was published using the Sparkplug B payload and collect time-series data in a structured and understandable format.

In general, a topic will be published in the following format:

```
Namespace/Groupname/<Message Type>/NodeID/<DeviceID>
```

For example,

```
spBv1.0/MyAdminGroup/NBIRTH/AdminNode1/ABC-12345
```

The table below lists the message types that are sent as a topic:

Message type	Description
NBIRTH	Message to notify the client (MQTT Sparkplug B Collector) that data is sent from a node. This message includes information such as tag information, data types, names, and alias if any.
NDEATH	Message to notify the client (MQTT Sparkplug B Collector) that there is no data to be sent from the node.
DBIRTH	Message to notify the client (MQTT Sparkplug B Collector) that data is sent from a device. This message includes information such as tag information, data types, names, and alias if any.
DDEATH	Message to notify the client (MQTT Sparkplug B Collector) that there are no data to be sent from the device.
NDATA	Message to notify the client (MQTT Sparkplug B Collector) that the actual data (metric) from the node is available to be collected.

Message type	Description
DDATA	Message to notify the client (MQTT Sparkplug B Collector) that the actual data (metric) from the device is available to be collected.
NCMD	Message to notify the Publisher that the client (MQTT Sparkplug B Collector) is receiving NDATA without receiving the NBIRTH payload.
DCMD	Message to notify the Publisher that the client (MQTT Sparkplug B Collector) is receiving DDATA without receiving the DBIRTH payload.
STATE	<p>The collector's state message. This message is sent by the client (MQTT Sparkplug B Collector) to the Publisher through a Broker stating the status of the Collector. If the client is active, the Publisher will send the needed data through the MQTT Broker.</p> <p>Example message format:</p> <p>Topic- <code>spBv1.0/STATE/<hostname></code></p> <p>Payload-</p> <pre>{ online : true, timestamp : 1702879923}</pre> <p>#The payload is in JSON format.</p>

Supported MQTT Versions:

- MQTT V5
- MQTT V3.1.1

Supported data format:

- Sparkplug B V1.0

Topology: The MQTT Sparkplug B collector supports a distributed model, that is, the MQTT broker, the collector, and the Historian server can be installed on the same machine or on different machines.

Features:

- You can subscribe to multiple-level topics based on Sparkplug B payload using a wildcard.
- You can collect time-series data.
- You can specify a device or node from which you need to collect data from.
- You can collect the data more specifically by providing device ID, node ID, and group ID.
- You can configure tag mask as needed by selecting the interfacename, groupid, edge nodeid, deviceid along with delimiter.
- You can select what tags you want to be added in Historian by using Tags to Add mask.
- You can select what tags you do not want to be added in Historian by using Tags to Exclude mask.
- Only the unsolicited data collection is supported; polled collection is not supported.
- The timestamp resolution is seconds, milliseconds, and microseconds.
- Boolean, floating point, integer, and string data types are supported.



Note:

Although the **Recalculate** button in Historian Administrator is enabled, the functionality is not available because the MQTT collector is a non-historic collector (the source broker does not store the historical data).

How it works:

1. The Publisher connects to the MQTT Broker and subscribes to topics. The topics include STATE, NCMD, and DCMD.
2. The MQTT Sparkplug B collector connects to the MQTT broker and subscribes to a topic based on the Device ID and Node Id that you provide while creating an instance. The topics include STATE, NBIRTH, DBIRTH, NDATA, DDATA, NDEATH, and DDEATH.

You can use username/password-based authentication or certificate-based authentication. Transport Layer Security (TLS) authentication is used for subscribing the data from message broker to avoid middleware attacks so that the data is securely transferred from message broker to the MQTT Sparkplug B collector.



Note:

It is recommended to use a certificate based authentication for a secured data transfer.

3. The MQTT Sparkplug B collector publishes the STATE message topic to the MQTT Broker.
4. The MQTT Broker then publishes this topic to the Publisher.

5. When there is data in the Device or Node, the publisher publishes a DBIRTH or NBIRTH message topic to the MQTT Broker.
6. The MQTT Broker then publishes this topic to the MQTT Sparkplug B collector.
7. The Publisher then publishes the DDATA or NDATA to the MQTT Broker.
8. The MQTT Broker publishes the data (metrics) to the MQTT Sparkplug B collector.
9. The collector converts the data from the Sparkplug B v1.0 format to a Historian-understandable format. It verifies tag availability in the Historian and, if not present, adds the tag, then adds the data samples, streaming the data to the Historian server or a cloud destination.


The process explains how the topics and data are published among the Publisher, MQTT Sparkplug B collector, and MQTT Broker. Similarly, when there is no data or a Device or Node is inactive, the Publisher publishes DDEATH or NDEATH message topics to the MQTT Sparkplug B collector through the MQTT Broker.




Note:

Sometimes, the publisher might send DDATA or NDATA without sending the corresponding BIRTH message, in such cases, the MQTT Sparkplug B collect sends the DCMD or NCMD message to the MQTT Broker. The the Broker sends the message to the publisher.

Example Diagram of How Data is Sent among Publisher, Broker, and MQTT Sparkplug B Collector



Example Diagram of How DEATH Topic is Sent among Publisher, Broker, and MQTT Sparkplug B Collector



Sparkplug B Message format:

```
{
  "timestamp": <timestamp>,
  "metrics": [{
    "name": "<metric>",
    "alias": <alias>,
    "timestamp": <timestamp>,
    "dataType": "<data Type>",
    "value": "<value>"
  }],
  "seq": <sequence_number>
}
```

JSON Parameter	Description
timestamp	The time at which the message was published. For example, 1642496400000 (time in milliseconds). Generally, the timestamp format is a 64-bit integer in milliseconds or microseconds since the Unix epoch.
metrics	The metrics or the data that was published. For example, <ul style="list-style-type: none"> • name: BoilerTag1 • alias: BT1Temp • timestamp: 1642496400000 • dataType: Float • value: 80.5

JSON Parameter	Description
seq	The unique sequence number of the message. The first message will have the seq as 0. This will increment by one for every other messages.

Supported Data Types:

Source Data Type	Historian Data Type
DoubleFloat, DoubleInteger, FixedByte, QuadInteger, SingleFloat	ihDoubleFloat
ByteString, String	ihVariableString
Boolean	ihBool

Adding an MQTT Sparkplug B Collector Instance

Add an MQTT Sparkplug B Collector Instance using Configuration Hub

1. Install [the Historian server \(on page 104\)](#) and [collectors \(on page 142\)](#).
2. Ensure that you have an MQTT broker.
3. If you want to use username/password-based authentication or certificate-based authentication to connect the MQTT broker and the MQTT Sparkplug B collector, configure the authentication in the MQTT broker.
4. If you want to use certificate-based authentication, ensure that the following files are available on your collector machine:
 - CA server root file
 - Private key file
 - Client certificate file

This topic describes how to add and configure an MQTT Sparkplug B collector instance using Configuration hub. You can also add and configure an MQTT Sparkplug B collector instance using RemoteCollectorConfigurator.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select  .

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION
Filter	Filter	Filter	Filter	Filter
Simulation	Running	Historian		
SamplePythonCollector	Unknown	Historian		

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

- In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
- In the **COLLECTOR TYPE** field, select **MQTT Sparkplug B Collector**, and then select **Get Details**.

 **Note:**
 The **INSTALLATION DRIVE** and **BASE DATA DIRECTORY** fields cannot be changed. This is the drive location and the data directory folder that you provided during Collectors installation.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are populated with the drive location and the data directory folder.

- Select **Next**.
 The **Source Configuration** section appears.
- Enter the values as described in the following table:

Field	Description
BROKER CONFIGURATION	
BROKER ADDRESS	Enter the host name of the MQTT broker using which you want to collect data. A value is required.
BROKER PORT	Enter the port number of the MQTT broker. A value is required.
CLIENT ID	Enter the client ID of the MQTT Sparkplug B collector is running. This is required if you want to send the data to a cloud destination. If you do not have a client ID set up, by default, the interface name is taken.

Field	Description
PRIMARY HOST ID	Enter the unique host ID of the Collector. The Collector will publish the STATE message topic using this host ID and then the Publisher will subscribe and start publishing the topics to this host ID.
REORDER TIMEOUT	Enter the duration for waiting before sending a CMD message if a sequence is skipped. You can enter the duration in milliseconds.
MQTT VERSION	Select the version of the MQTT that you want to use. The following versions are supported: <ul style="list-style-type: none"> ◦ MQTT_V311 ◦ MQTT_V5
<p>TOPIC: The parameters that need to be included in the topic:</p> <pre style="background-color: #f0f0f0; padding: 5px;">Namespace/Groupname/<Message Type>/NodeID/<DeviceID></pre> <p>You can also use wildcards in the GROUP ID, EDGE NODE ID, and DEVICE ID fields. The following wildcards are supported:</p> <ul style="list-style-type: none"> ◦ + (single-level wildcard): Supported for all the three fields. ◦ # (Multi-level wildcard): Supported for the EDGE NODE ID and DEVICE ID <p>+ (Single-level wildcard): Can be used to subscribe to only one topic level. For example, if you subscribe to a topic <code><Admin>/+/<ABC-123></code>, you will receive messages from all the nodes corresponding to the group and device. That is,</p> <pre style="background-color: #f0f0f0; padding: 5px;"><Admin>/Node1/<ABC-123> <Admin>/Node2/<ABC-123> <Admin>/Node3/<ABC-123> ... <Admin>/Noden/<ABC-123></pre> <p># (Multi-level wildcard): Can be used to subscribe to any number of levels within a topic. For example, if you subscribe to a topic <code><Admin>/#</code>, you will receive messages from all the nodes and devices corresponding to the group,</p>	

Field	Description
<pre> <Admin>/Node1/<ABC-123> <Admin>/Node2/<ABC-123> <Admin>/Node3/<ABC-123> <Admin>/Node1/<ABC-124> <Admin>/Node2/<ABC-124> ... <Admin>/Noden/<Devicen> </pre>	
<p>GROUP ID</p>	<p>Enter the Sparkplug B group name to which you want your collector to subscribe. If this is empty along with the other fields below TOPIC, the collector will subscribe to all the available groups, nodes, and devices.</p>
<p>EDGE NODE ID</p>	<p>Enter the Sparkplug B edge node ID to which you want your collector to subscribe. If this is empty, then the Collector will subscribe to all the edge nodes corresponding to the entered GROUP ID. If the GROUP ID and DEVICE ID are also empty, then the collector will subscribe to all the available groups, nodes and devices.</p>
<p>DEVICE ID</p>	<p>Enter the Sparkplug B device name. If this is empty, the collector subscribes to node messages if a NODE ID is entered, otherwise, if a DEVICE ID is entered, it subscribes to device messages.</p>
<p>TAG CONFIGURATION</p>	
<p>TAG NAME PREFIX FORMAT</p>	
<p>ELEMENT</p>	<p>Enter a prefix to be included in the tag. By using this field, you can clearly identify a tag. For example, you can clearly differentiate the tags that are collected.</p> <p>The following options are available:</p>

Field	Description
	<ul style="list-style-type: none"> ◦ <interfacename> ◦ <groupid> ◦ <edgenodeid> ◦ <deviceid> <p>For example, if all four fields are provided and the interface/collector name is "sparkplug1" and the Topic contains group id = g1 edge node id = n1, device id = d1 then device tags will be created in Historian as "sparkplug1.g1.n1.d1.tag1".</p>
DELIMITER	<p>Enter a delimiter you need to be included in the tag. You can use any special characters as delimiter. However, it is recommended that you use a delimiter that is ideal and clear to be identified. For example, "/", ".", "_".</p> <div data-bbox="862 1010 1419 1142" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: "?" and "*" are not allowed. </div>
PREVIEW	<p>The preview of how the tags will be created and stored based on the TAG PREFIX and the DELIMITER that you selected.</p>
TAG MASK	
TAGS TO ADD	<p>Provide a mask along with wildcard to collect those tags that include the mask you provided and store in Historian. For example, *Pressure*. This will collect all the tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be collected. Similarly, if you enter *Pres?, all the tags that contain "pres" at the beginning will be collected. It can be "Pressure", "Press", or "Pres1".</p>

Field	Description
	<div data-bbox="873 275 1421 621" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px;">  Note: Whenever a new tag is collected, the collector verifies the tag availability in the Historian and, if not present, adds the tag, then adds the data samples, streaming the data to the Historian server or a cloud destination. </div>
TAGS TO EXCLUDE	Provide a mask along with wildcard to exclude those tags that include the mask you provided. For example, *Pressure*. This will exclude all the tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be excluded. Similarly, if you enter *Pres?, all the tags that contain "pres" at the beginning will be excluded. It can be "Pressure", "Press", or "Pres1".
AUTHENTICATION	
USER CREDENTIALS	
USERNAME	Enter the username to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
PASSWORD	Enter the password to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
SSL/TLS	
CA SERVER ROOT FILE	Enter the path to the CA server root file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.

Field	Description
PRIVATE KEY FILE	Enter the path to the private key file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
CLIENT CERTIFICATE FILE	Enter the path to the client certificate file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.

8. Select **Next**.

The **Destination Configuration** section appears.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.
- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).
 - b. If you need to send data to an on-premises Historian server, select **Historian Server**.
If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. After you selected the destination, select **Next**.

The **Collector Initiation** section appears.

11. If needed, modify the value in the **COLLECTOR NAME** field.



Note:

If you will be using the collector in Historian Administrator, the **COLLECTOR NAME** must include Sparkplug B in it.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

14. If needed, enter values in [available fields \(on page 579\)](#).

15. In the upper-left corner of the page, select **Save**.

16. If needed, restart the collector.

- Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,
 - If you have selected **Historian Configuration**, specify the tags using [Configuration Hub \(on page 357\)](#).
 - If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of Historian>\GE Digital\<collector name>*. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.
- If needed, you can [configure the collector instance \(on page 2331\)](#).

Add an MQTT Sparkplug B Collector Instance using RemoteCollector Configurator

1. Install [the Historian server \(on page 104\)](#) and [collectors \(on page 142\)](#).
2. Ensure that you have an MQTT broker.
3. If you want to use username/password-based authentication or certificate-based authentication to connect the MQTT broker and the MQTT Sparkplug B collector, configure the authentication in the MQTT broker.
4. If you want to use certificate-based authentication, ensure that the following files are available on your collector machine:
 - CA server root file
 - Private key file
 - Client certificate file

This topic describes how to add and configure an MQTT Sparkplug B collector instance using RemoteCollectorConfigurator utility. If you want to add an offline collector instance, refer to [Add an Offline Collector Instance \(on page 819\)](#).

1. Run the RemoteCollectorConfigurator.exe file. By default, it is located in the following folder: `C:\Program Files\GE Digital\NonWebCollectorInstantiationTool`. A list of options to manage collector instances appears.
2. Connect to the collector machine by entering 1 or 2, depending on whether collectors are installed locally or on a remote machine.

3. To create a collector instance using the RemoteCollectorConfigurator utility, you need to provide parameters in a JSON format. For this you can create a sample JSON using this tool. To create sample JSON, enter **7**.
4. To create a sample JSON file for MQTT Sparkplug B collector, enter **21**.
5. To set Historian as the destination type, enter **1**.
6. Enter the folder path where you want the sample JSON file to be created. By default, the file will be created in the same folder in which the RemoteCollectorConfigurator utility is located.
A sample JSON file with name **"SampleSparkplugB.json"** is created in the given location.

Sample JSON File

```
{
  "CollectorSystemName": "TESTSYSTEM",
  "DestinationHistorian": "TESTSYSTEM",
  "General1": "HostName=localhost|Port=|ClientId=|PrimaryHostId=|GroupId=test|EdgeNodeId=#|DeviceId=|Username=|Password=|Cafile=|Certfile=|PrivateKeyfile=|Version=MQTT_V311|ReorderTimeout=",
  "General2": "<interfacename>.<groupid>.<edgenodeid>.<deviceid>.",
  "General3": "",
  "General4": "",
  "General5": "",
  "InterfaceDescription": "Sample SparkplugB Collector",
  "InterfaceName": "SampleSparkplugBCollector",
  "InterfaceSubType": "SparkplugB",
  "SourceHistorianUserName": "",
  "SourceHistorianPassword": "",
  "Type": "16",
  "SamplerId": "",
  "MTLSEnable": "false",
  "DataPathDirectory": "C:\\\\Proficiency Historian Data",
  "CollectorDestination": "Historian",
  "DestinationHistorianUserName": "",
  "DestinationHistorianPassword": "",
  "mode": "1",
  "winUserName": "",
  "winPassword": ""
}
```

7. Configure the values as specified the following table:

Table 381.

Field	Description
CollectorSystemName (Mandatory)	Name of the machine on which the Collector is installed.
DestinationHistorian (Mandatory)	Name of the destination Historian machine.
General1	
HostName (mandatory)	MQTT broker Ip or hostname.
Port (mandatory)	MQTT broker port.
ClientID	Unique name to identify the client.
PrimaryHostID (mandatory)	The unique host ID of the Collector. The Collector will publish the STATE message topic using this host ID and then the Publisher will subscribe and start publishing the topics to this host ID.
GroupId (mandatory)	The Sparkplug B group name to which you want your collector to subscribe. If this is empty along with the other fields below TOPIC , the collector will subscribe to all the available groups, nodes, and devices. Use of the wildcard "+" is supported.
EdgeNodeId (mandatory)	The Sparkplug B edge node ID to which you want your collector to subscribe. If this is empty, then the Collector will subscribe to all the edge nodes corresponding to the entered GROUP ID . If the GROUP ID and DEVICE ID are also empty, then the collector will subscribe to all the available groups, nodes and devices. Use of the wildcards "+" and "#" are supported.
DeviceId (mandatory)	The Sparkplug B device name. If this is empty, the collector subscribes to node messages if a NODE ID is entered, otherwise, if a DEVICE ID is

Field	Description
	entered, it subscribes to device messages. Use of the wildcards "+" and "#" are supported.
Username	The username to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
Password	The password to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
Cafile	The path to the CA server root file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
Certfile	The path to the client certificate file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
PrivateKeyfile	The path to the private key file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
ReorderTimeout	Enter the duration for waiting before sending a CMD message if a sequence is skipped. You can enter the duration in milliseconds.
Version	The version of the MQTT that you want to use. That is, MQTT_V311 or MQTT_V5.
General2	
<interfacename>.<groupid>.<edgenodeid>.<deviceid>.	The prefix to be included in the tag. By using this field, you can clearly identify a tag. For example, you can clearly differentiate the tags that are collected.

Field	Description
	<p>The following options are available:</p> <ul style="list-style-type: none"> ◦ <interfacename> ◦ <groupid> ◦ <edgenodeid> ◦ <deviceid> <p>For example, if all four fields provided and the interface / collector name is "sparkplug1" and the Topic contains group id = g1 edge node id = n1, device id = d1 then device tags will be created in Historian as "sparkplug1.g1.n1.d1.tag1".</p>
General3	
<p>"*" Tag include mask field</p>	<p>The mask along with wildcard to collect those tags that include the mask you provided and store in Historian. For example, *Pressure*. This will collect all the tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be collected. Similarly, if you enter *Pres?, all the tags that contain "pres" at the beginning will be collected. It can be "Pressure", "Press", or "Pres1".</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: Whenever a new tag is collected, the collector verifies the tag availability in the Historian and, if not present, adds the tag, then adds the data samples, streaming the data to the Historian server or a cloud destination.</p> </div>
General4	
<p>"" Tag exclude mask field</p>	<p>The mask along with wildcard to exclude those tags that include the mask you provided. For example, *Pressure*. This will exclude all the</p>

Field	Description
	tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be excluded. Similarly, if you enter *Pres?, all the tags that contain "pres" at the beginning will be excluded. It can be "Pressure", "Press", or "Pres1".
General5	
InterfaceDescription	A description of the collector instance.
InterfaceName	A name of the collector instance. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If you will use this collector on Historian Administrator, the name must include Sparkplug B in it. </div>
InterfaceSubType	Sparkplug B. Do not change this field.
SourceHistorianUserName (optional)	username of the source Historian.
SourceHistorianPassword (optional)	password of the source Historian.
Type	16. Do not change this field.
SamplerId (optional)	The ID of the sampler.
MTLSEnable	False.
DataPathDirectory	The directory path where you want the data to be stored. It is recommended to use C:\\Proficiency Historian Data.
CollectorDestination	Historian. Do not change this field.
DestinationHistorianUserName (optional)	username of the destination Historian.
DestinationHistorianPassword (optional)	password of the destination Historian.
Mode	1. Do not change this field.
winUserName (optional)	username of the window user.
winPassword (optional)	password of the window user.

**Note:**

Do not change the case of the keys in the JSON file.

8. Run the `RemoteCollectorConfigurator.exe` file. By default, it is located in the following folder: `C:\Program Files\GE Digital\NonWebCollectorInstantiationTool`.
A list of options to manage collector instances appears.
9. Connect to the collector machine by entering 1 or 2, depending on whether collectors are installed locally or on a remote machine.
10. To create the collector instance, enter 4.
11. To create the instance using the updated JSON file, enter 2.
12. Enter the location where the updated JSON file is saved.
13. On the keyboard, press **Enter**.
The MQTT Sparkplug B collector instance is created.

- [Specify the tags \(on page 357\)](#) whose data you want to collect using the collector.
- If you did not enter a value, modify the offline configuration file of the collector. By default, this file is available in the following location: `<installation folder of Historian>\GE Digital\<collector name>`. For information, refer to [Creating Offline Configuration XML file \(on page 2040\)](#).

Configuring an MQTT Sparkplug B Collector Instance

Configure an MQTT Sparkplug B Collector Instance using Configuration Hub

This topic describes how to configure an MQTT Sparkplug B collector instance using Configuration Hub.

- Ensure that you installed [the Historian server \(on page 104\)](#) and [collectors \(on page 142\)](#).
 - Ensure that you created an MQTT Sparkplug B collector instance, using [RemoteCollectorConfigurator \(on page 2325\)](#) or [Configuration Hub \(on page 519\)](#).
1. [Access Configuration Hub \(on page 336\)](#).
 2. Select **Collectors**, and then select the MQTT Sparkplug B collector instance that you want to configure.
The configurations specific to the collector instance appear in the **DETAILS** section.
 3. In the **COLLECTOR SPECIFIC CONFIGURATION** and **INSTANCE CONFIGURATION** sections, configure the values as described in the following table.

COLLECTOR SPECIFIC CONFIGURATION

Field	Description
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

INSTANCE CONFIGURATION

Field	Description
Broker Address	Enter the host name of the MQTT broker using which you want to collect data. A value is required.
Broker Port	Enter the port number of the MQTT broker. A value is required.
Client ID	Enter the client ID of the MQTT Sparkplug B collector is running. This is required if you want to send the data to a cloud destination. If you do not have a client ID set up, by default, the interface name is taken.
Primary Host ID	Enter the unique host ID of the Collector. The Collector will publish the STATE message topic using this host ID and then the Publisher will subscribe and start publishing the topics to this host ID.
REORDER TIMEOUT	Enter the duration for waiting before sending a CMD message if a sequence is skipped. You can enter the duration in milliseconds.

Field	Description
Group ID	Enter the Sparkplug B group name to which you want your collector to subscribe. If this is empty along with the other fields below TOPIC , the collector will subscribe to all the available groups, nodes, and devices.
Edge Node ID	Enter the Sparkplug B edge node ID to which you want your collector to subscribe. If this is empty, then the Collector will subscribe to all the edge nodes corresponding to the entered GROUP ID . If the GROUP ID and DEVICE ID are also empty, then the collector will subscribe to all the available groups, nodes and devices.
Device ID	Enter the Sparkplug B device name. If this is empty, the collector subscribes to node messages if a NODE ID is entered, otherwise, if a DEVICE ID is entered, it subscribes to device messages.
<p>You can also use wildcards in the GROUP ID, EDGE NODE ID, and DEVICE ID fields. The following wildcards are supported:</p> <ul style="list-style-type: none"> ◦ + (single-level wildcard): Supported for all the three fields. ◦ # (Multi-level wildcard): Supported for the EDGE NODE ID and DEVICE ID <p>+ (Single-level wildcard): Can be used to subscribe to only one topic level. For example, if you subscribe to a topic <code><Admin>/+/<code><ABC-123></code></code>, you will receive messages from all the nodes corresponding to the group and device. That is,</p> <pre data-bbox="293 1486 535 1688" style="background-color: #f0f0f0; padding: 5px;"> <Admin>/Node1/<ABC-123> <Admin>/Node2/<ABC-123> <Admin>/Node3/<ABC-123> ... <Admin>/Noden/<ABC-123> </pre> <p># (Multi-level wildcard): Can be used to subscribe to any number of levels within a topic. For example, if you subscribe to a topic <code><Admin>/#</code>, you will receive messages from all the nodes and devices corresponding to the group,</p>	

Field	Description
<pre> <Admin>/Node1/<ABC-123> <Admin>/Node2/<ABC-123> <Admin>/Node3/<ABC-123> <Admin>/Node1/<ABC-124> <Admin>/Node2/<ABC-124> ... <Admin>/Noden/<Devicen> </pre>	
<p>Tags to Add</p>	<p>Provide a mask along with wildcard to collect those tags that include the mask you provided and store in Historian. For example, *Pressure*. This will collect all the tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be collected. Similarly, if you enter *Pres?, all the tags that contain "pres" at the beginning will be collected. It can be "Pressure", "Press", or "Pres1".</p> <div data-bbox="862 1037 1419 1394" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Whenever a new tag is collected, the collector verifies the tag availability in the Historian and, if not present, adds the tag, then adds the data samples, streaming the data to the Historian server or a cloud destination.</p> </div>
<p>Tags to Exclude</p>	<p>Provide a mask along with wildcard to exclude those tags that include the mask you provided. For example, *Pressure*. This will exclude all the tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be excluded. Similarly, if you enter *Pres?, all the tags that contain "pres" at the beginning will be excluded. It can be "Pressure", "Press", or "Pres1".</p>

Field	Description
Tag Prefix	<p>Enter a prefix to be included in the tag. By using this field, you can clearly identify a tag. For example, you can clearly differentiate the tags that are collected.</p> <p>The following options are available:</p> <ul style="list-style-type: none"> ◦ <interfacename> ◦ <groupid> ◦ <edgenodeid> ◦ <deviceid> <p>For example, if all four fields provided and the interface / collector name is "sparkplug1" and the Topic contains group id = g1 edge node id = n1, device id = d1 then device tags will be created in Historian as "sparkplug1.g1.n1.d1.tag1".</p>
Username	<p>Enter the username to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.</p>
Password	<p>Enter the password to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.</p>
CA Server Root File	<p>Enter the path to the CA server root file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.</p>
Private Key File	<p>Enter the path to the private key file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.</p>
Client Certificate File	<p>Enter the path to the client certificate file to connect to the MQTT broker. A value is required</p>

Field	Description
	if you have configured certificate-based authentication in the MQTT broker.
MQTT Version	Select the version of the MQTT that you want to use. The following versions are supported: <ul style="list-style-type: none"> ◦ MQTT_V311 ◦ MQTT_V5


4. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).
5. Restart the collector.
The collector instance is configured.

Configure an MQTT Sparkplug B Collector Instance using Historian Administrator

- Ensure that you installed [the Historian server \(on page 104\)](#) and [collectors \(on page 142\)](#).
- Ensure that you created an MQTT Sparkplug B collector instance, using [RemoteCollectorConfigurator \(on page 2325\)](#) or [Configuration Hub \(on page 519\)](#).

This topic describes how to configure an added MQTT Sparkplug B collector instance in Historian Administrator.

1. Access [Historian Administrator \(on page 823\)](#).
2. Select **Collectors**, and then select the MQTT Sparkplug B collector instance that you want to configure.



3. In the right-side, below the **Collector: <Name of the Collector Instance>**, select **Configuration**.
The fields specific to the collector instance appear.
4. Enter values as specified in the following table.

Table 382.

Configuration: HostName=localhost Port= ClientId= PrimaryHostId= GroupId= EdgeNodeId= DeviceId= username= password= cafile= certfile= privatekeyfile= version=MQTT_V311 reordertimeout=	
HostName (mandatory)	MQTT broker Ip or hostname.
Port (mandatory)	MQTT broker port.
ClientId	Unique name to identify the client.
PrimaryHostID (mandatory)	The unique host ID of the Collector. The Collector will publish the STATE message topic using this host ID and then the Publisher will sub-

	scribe and start publishing the topics to this host ID.
GroupId (mandatory)	The Sparkplug B group name to which you want your collector to subscribe. If this is empty along with the other fields below TOPIC , the collector will subscribe to all the available groups, nodes, and devices. Use of the wildcard "+" is supported.
EdgeNodeId (mandatory)	The Sparkplug B edge node ID to which you want your collector to subscribe. If this is empty, then the Collector will subscribe to all the edge nodes corresponding to the entered GROUP ID . If the GROUP ID and DEVICE ID are also empty, then the collector will subscribe to all the available groups, nodes and devices. Use of the wildcards "+" and "#" are supported.
DeviceId (mandatory)	The Sparkplug B device name. If this is empty, the collector subscribes to node messages if a NODE ID is entered, otherwise, if a DEVICE ID is entered, it subscribes to device messages. Use of the wildcards "+" and "#" are supported.
username	The username to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
password	The password to connect to the MQTT broker. A value is required if you have configured username/password-based authentication in the MQTT broker.
cafile	The path to the CA server root file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.

certfile	The path to the client certificate file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
privatekeyfile	The path to the private key file to connect to the MQTT broker. A value is required if you have configured certificate-based authentication in the MQTT broker.
version	The version of the MQTT that you want to use. That is, MQTT_V311 or MQTT_V5.
reordertimeout	
TagName Prefix	<p>The prefix to be included in the tag. By using this field, you can clearly identify a tag. For example, you can clearly differentiate the tags that are collected.</p> <p>The following options are available:</p> <ul style="list-style-type: none"> ◦ <interfacename> ◦ <groupid> ◦ <edgenodeid> ◦ <deviceid> <p>For example, if all four fields provided and the interface / collector name is "sparkplug1" and the Topic contains group id = g1 edge node id = n1, device id = d1 then device tags will be created in Historian as "sparkplug1.g1.n1.d1.tag1".</p>
Tag include Mask	The mask along with wildcard to collect those tags that include the mask you provided and store in Historian. For example, *Pressure*. This will collect all the tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be collected. Similarly, if you enter *Pres?, all the tags that con-

	<p>tain "pres" at the beginning will be collected. It can be "Pressure", "Press", or "Pres1".</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Whenever a new tag is collected, the collector verifies the tag availability in the Historian and, if not present, adds the tag, then adds the data samples, streaming the data to the Historian server or a cloud destination.</p> </div>
<p>Tag Exclude Mask</p>	<p>The mask along with wildcard to exclude those tags that include the mask you provided. For example, *Pressure*. This will exclude all the tags that begin with "Pressure". If you enter Pressure*, all the tags that end with "Pressure" will be excluded. Similarly, if you enter *Pres?, all the tags that contain "pres" at the beginning will be excluded. It can be "Pressure", "Press", or "Pres1".</p>

5. After you configure the collector instance, select **Update**.

The instance is updated with the new configuration.

Chapter 23. The ODBC Collector

Overview of the ODBC Collector

The ODBC collector collects data from an application based on an ODBC driver and stores the data in an on-premises Historian Server or a cloud destination. It supports collecting of all the Historian supported data types of data from the ODBC server.

Topology: The ODBC collector supports a distributed model, where the ODBC server, the collector, and the Historian server are installed on different machines. Typically, however, the collector is installed on the same machine as the ODBC server and sends data to a remote Historian server.

Features:

- You can browse the source for tags and their attributes on an ODBC server that supports browsing.
- Only the unsolicited data collection is supported; when changes to the ODBC source tags are detected, they are sent to the Historian server. The minimum poll interval is 100ms. The collector duplicates raw samples from the ODBC server into the Historian data archive.
- The supported timestamp resolution is 1ms.
- Floating point, integer, and string data are supported.


Supported Data Attributes:

Historian Data Type	ODBC Server Data Type
ihByte	Byte
ihFloat	SingleFloat
ihDoubleFloat	DoubleFloat
ihInteger	SingleInteger
ihDoubleInteger	DoubleInteger
ihScaled	Not applicable
ihFixedString	Not applicable
ihVariableString	Not applicable
ihBlob	Not applicable
ihTime	Not applicable

Historian Data Type	ODBC Server Data Type
ihInt64	Not applicable
ihUInt64	Not applicable
ihUInt32	Not applicable
ihUInt16	Not applicable
ihBool	Not applicable

Limitations:

- A single collector instance can collect data from a single ODBC server. To collect data from multiple ODBC servers, you must add multiple instances.
- Only good and bad quality types are supported. OPC Quality and OPC Subquality are not supported.
- If you want a domain user to use the ODBC collector, after you add an instance of a collector, when you later configure it, do not provide values in the **User Name** and **Password** fields. This is because the ODBC driver uses Windows authentication.




Configuration

Add and Configure an ODBC Collector Using Configuration Hub

The ODBC collector collects data from an application based on an ODBC driver. For more information, refer to [Overview of the ODBC Collector \(on page 2341\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **ODBC Collector**, and then select **Get Details**. The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.
6. Select **Next**. The **Source Configuration** section appears.
7. Enter values as described in the following table.

Field	Description
ODBC SERVER	Enter the host name or IP address of the ODBC server from which you want to collect data. A value is required.
USERNAME	Enter the username to connect to the ODBC server. A value is required.
PASSWORD	Enter the password to connect to the ODBC server. A value is required.

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.
- a. If you need to send data to a cloud destination, select the cloud destinations as needed.
 - **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
 - **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
 - **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).
 - b. If you need to send data to an on-premises Historian server, select **Historian Server**.
If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears.

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must contain the string `ODBC`.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.


The collector instance is added. The fields specific to the collector appear in the **DETAILS** section.

14. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.

Field	Description
Recovery Time (hours)	Enter the maximum time, in hours, for which the collector will attempt to recover data after

Field	Description
	<p>the collector is started or when connection between the collector and the ODBC server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>By default, this value is set to 0, which means data recovery is not attempted. The maximum value you can provide is 168 hours (that is, 7 days).</p>
Throttle (Milliseconds)	<p>Enter the frequency, in milliseconds, at which you want the ODBC collector to query the ODBC server for tag data. This will minimize the load on the ODBC server. You can enter a value up to 16 hours.</p> <div data-bbox="862 1079 1419 1260" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: If this field is blank, enter the required minimum value of 100 milliseconds.</p> </div>
MTLS Security	<p>Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.</p>
MTLS Data Encryption	<p>Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).</p>
<p>For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632).</p>	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).
16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,

- If you have selected **Historian Configuration**, specify the tags using Configuration Hub (on page 357).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: `<installation folder of Historian>\GE Digital\<collector name>`. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Configure the ODBC Collector Using Historian Administrator


You can establish a connection between the ODBC collector and an ODBC server, and set the recovery time and throttle value by configuring the ODBC collector.



Note:

ODBC Driver for SQL is required to install the ODBC collector and connect it with the ODBC server. If you install the ODBC collector and the ODBC server on the same machine, install the ODBC Driver for SQL on the same machine as well.

1. Access Historian Administrator.
2. Select **Collectors**, and then select the ODBC collector instance that you want to connect to an ODBC server.
3. Select **Configuration**.
The **Configuration** section appears.



4. Enter values as specified in the following table.

Field	Description
Server Name	The name of the ODBC server database.
User Name	The username of the ODBC server database.
Password	The password of the ODBC server database.
Recovery Time (hours)	<p>The maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the ODBC server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p>

Field	Description
	By default, this value is set to 0, which means data recovery is not attempted. The maximum value you can provide is 168 hours (that is, 7 days).
Throttle (Milliseconds)	<p>The frequency, in milliseconds, at which you want the ODBC collector to query the ODBC server for tag data. This will minimize the load on the ODBC server. You can enter a value up to 16 hours.</p> <div data-bbox="667 621 1419 800" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: If this field is blank, enter the required minimum value of 100 milliseconds. </div>

If you have provided incorrect ODBC server details (that is the server name, username, and password) either in Historian Administrator or in the `ODBC_Mapping.xml` file, the ODBC collector cannot connect with the ODBC server. To fix this issue:

- a. Delete the ODBC collector instance.
- b. Provide values for the following properties in the registry key `HKLM\Softwares\GE Digital\iHistorian\Services\ODBCCollector`:
 - **General1:** ODBC server name
 - **General2:** ODBC server username
 - **General3:** ODBC server password
- c. Ensure that [the mapping file is configured correctly \(on page 2349\)](#).
- d. Restart the collector.

If this workaround is not successful, restart the collector instance.

Map Data Format

For the ODBC collector to interpret the received data accurately, you must map the format and structure of the data between the ODBC server and Historian.

1. Access the ODBC_Mapping.xml file. By default, this file is located at C:\Program Files\GE Digital\Historian ODBC Collector\Server. In the ODBC collector registry path, this file is stored in the Mapping File variable.
2. For each data type in the ODBC server, add an entry in the equivalent Historian data type as described in the following table. If a Historian data type does not have an equivalent ODBC data type, enter *NA*.

Historian Data Type	ODBC Server Data Type
ihByte	Byte
ihFloat	SingleFloat
ihDoubleFloat	DoubleFloat
ihInteger	SingleInteger
ihDoubleInteger	DoubleInteger
ihScaled	*NA*
ihFixedString	*NA*
ihVariableString	*NA*
ihBlob	*NA*
ihTime	*NA*
ihInt64	*NA*
ihUInt64	*NA*
ihUInt32	*NA*
ihUInt16	*NA*
ihBool	*NA*

For example, if the ODBC server contains a Float data type named ID, enter `<ihFloat>ID</ihFloat>`

```
<DataTypeMapping>
  <ihDataTypeUndefined>*NA*</ihDataTypeUndefined>
  <ihScaled>*NA*</ihScaled>
  <ihFloat>ID</ihFloat>
  <ihDoubleFloat>*NA*</ihDoubleFloat>
  <ihInteger>2</ihInteger>
```

```

<ihDoubleInteger>*NA*</ihDoubleInteger>

<ihFixedString>*NA*</ihFixedString>

<ihVariableString>3</ihVariableString>

<ihBlob>*NA*</ihBlob>

<ihTime>*NA*</ihTime>

<ihInt64>*NA*</ihInt64>

<ihUInt64>*NA*</ihUInt64>

<ihUInt32>*NA*</ihUInt32>

<ihUInt16>*NA*</ihUInt16>

<ihByte>*NA*</ihByte>

<ihBool>*NA*</ihBool>

<ihMultiField>*NA*</ihMultiField>

<ihArray>*NA*</ihArray>

</DataTypeMapping>

```

3. In the Quality and SubQuality elements, provide the range of values retrieved from the quality column. For quality elements that are not applicable, enter *NA*.
- For example, if the values from 0 to 97 are considered as bad quality, and if the numbers from 98 to 100 are considered as good quality, provide the values as follows:

```

<Quality>

<ihOPCBad>[0,98)</ihOPCBad>

<ihOPCUncertain>*NA*</ihOPCUncertain>

<ihOPCNA>*NA*</ihOPCNA>

<ihOPCGood>[99,101)</ihOPCGood>

</Quality>

<SubQuality>

<ihOPCNonspecific>*NA*</ihOPCNonspecific>

<ihOPCConfigurationError>*NA*</ihOPCConfigurationError>

<ihOPCNotConnected>*NA*</ihOPCNotConnected>

<ihOPCDeviceFailure>*NA*</ihOPCDeviceFailure>

<ihOPCSensorFailure>*NA*</ihOPCSensorFailure>

<ihOPCCommFailure>*NA*</ihOPCCommFailure>

<ihOPCOutOfService>float</ihOPCOutOfService>

<ihScaledOutOfRange>*NA*</ihScaledOutOfRange>

<ihOffLine>*NA*</ihOffLine>

<ihNoValue>*NA*</ihNoValue>

<ihCalculationError>*NA*</ihCalculationError>

```

```

<ihConditionCollectionHalted>*NA*</ihConditionCollectionHalted>

<ihCalculationTimeout>*NA*</ihCalculationTimeout>

</SubQuality>

```

4. In the TagInfo element, provide the tag details, which are used to browse for tags. Provide the column names available in the ODBC server in the corresponding tag element.

```

<TagInfo>

  <DBName>DB1</DBName> <!--Cannot be *NA*-->

  <TableName>Temperature</TableName> <!--Cannot be *NA*-->

  <TagName>Boiler_Temp</TagName> <!--Cannot be *NA*-->

  <Description>*NA*</Description>

  <EngineeringUnits>*NA*</EngineeringUnits>

  <DataType>*NA*</DataType>

  <MinimumEngineeringUnit>*NA*</MinimumEngineeringUnit>

  <MaximumEngineeringUnit>*NA*</MaximumEngineeringUnit>

</TagInfo>

```



Note:

If you enter *NA* for the DataType element, you can provide only one data type mapping for the DataTypeMapping element and all the remaining elements must be marked *NA*

You can choose to automatically run queries from the info you provide in the TagInfo element. To do so, enter `<Mode>1</Mode>` in the TagInfo element. If you want to provide queries manually, enter `<Mode>0</Mode>` in the TagInfo element.

5. In the DataInfo element, provide the tag data details, which are used to create a query to collect the data.

```

<DataInfo>

  <DBName>DB1</DBName> <!--Cannot be *NA*-->

  <TableName>Temperature</TableName> <!--Cannot be *NA*-->

  <TagName>Boiler_Temperature</TagName> <!--Cannot be *NA*-->

  <Timestamp>10-06-26 02:31:29,573</Timestamp> <!--Cannot be *NA*-->

  <Value>97</Value> <!--Cannot be *NA*-->

  <Quality>good</Quality> <!--Cannot be *NA*-->

  <SubQuality>*NA*</SubQuality>

</DataInfo>

```

You can choose to automatically run queries from the info you provide in the DataInfo element. To do so, enter `<Mode>1</Mode>` in the DataInfo element. If you want to provide queries manually, enter `<Mode>0</Mode>` in the DataInfo element.

6. If you want to provide your own queries, provide them in the following format:

```
<Query>
  <Browse></Browse>
  <ReadData></ReadData>
  <TagCount></TagCount>
</Query>
</Mapping>
```

```
<Query>
<Browse>SELECT [TagName],[Description],[TagType],[Unit],[MinEU],[MaxEU] FROM
  [Runtime].[dbo].[TagHistory]</Browse>
<ReadData>SELECT TagName, [DateTime], Value, Quality, QualityDetail FROM History where History.TagName =
  '?TagName?' AND wwRetrievalMode = 'FULL' AND wwVersion = 'Latest' AND DateTime > '?Start?' ORDER BY
  DateTime ASC</ReadData>
<TagCount>SELECT count(*) from [Runtime].[dbo].[TagHistory]</TagCount>
</Query>
```

Data Recovery



Note:

We recommend that the collector for which the data recovery is intended is in the same time zone as the server. If there is a mismatch, there is a possibility that data recovery will be incomplete.

Automatic Data Recovery

In this mode, data is automatically recovered since the last time data has been collected.

How it works:

1. The collector determines the duration between the current time and the last time data has been written to the Historian data archive, which is stored in the LastSampleWriteTime registry key.
2. It compares this duration with the value in the Recovery Time field specified in [the collector settings \(on page 2347\)](#).
3. It uses the shorter duration to perform a raw data query on all the tags.
4. It then processes the returned samples in chronological order.

For example, if the collector was stopped for 8 hours, but Max Recovery Time was 4 hours, only 4 hours of data would be recovered.

As per the recovery logic, an end-of-collection marker is placed at the point in time where the collector was stopped. This end-of-collection marker may or may not be there after the recovery is complete. As part of the recovery logic, if recovery data point time matches the timestamp of the end-of-collection marker, it is overwritten with the recovered good data.

Manual Data Recovery

In this mode, you can fill gaps in the data, but you cannot fill old data.

To perform a manual recovery:

1. Access Historian Administrator.
2. Select **Collectors**, and then select the ODBC collector instance for which you want to manually recover data.
3. Select **Recalculate**.

The **Recalculate** window appears.

4. Enter start time, end time, and other required information. We recommend that you choose small time intervals to reduce the load on the server and the collector.
5. Select **Recalculate**.

The tag data is recalculated. After the manual recalculation begins, the collector recovers data of the selected tags data from the collector, and sends it to Historian between the start time and end time.

At the time of recovery, if the connection to server is lost, and if the reconnect mechanism is enabled, the collector will try to connect to the server and fetch the data once connection re-establishes.

Manual Data Recovery

Assume that the collector is connected to Historian for the first time today and the archive was created at 10 am. The user initiates manual recalculation from 1am to 2 am. For that time interval, the archives were not even created. With respect to Historian, it is old unknown data and the data write fails. If there is a data gap between 1am and 2 am, manual recalculation successfully fills the data gap.

Reconnect to the ODBC Server Automatically

You can reconnect to the ODBC server automatically as soon as the server is up and running. By default, the collector polls for the server connection every 5 seconds. You can change this interval as well. The collector is stopped until reconnected to the server.

1. Access the following registry key: `HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\iHistorian\Services\ODBCCollector`.
2. Create a DWORD named `EnableReconnect`.
3. Enter the decimal value 1.
4. If you want to change the reconnection interval (from the default value of 5 seconds):
 - a. Create a DWORD named `ReconnectInterval`.
 - b. Enter a decimal value between 5 and 60. This value represents the number of seconds for the collector to wait before trying to reconnect to the ODBC server.
5. Select **OK**, then close the registry.

Troubleshooting the ODBC Collector

The ODBC collector generates logs during initialization, configuration, and general operation. By default, you can find them in the general logging folder, `C:\Proficy Historian Data\LogFiles`.

Troubleshooting Tips

- Ensure that the ODBC server is running before the starting the ODBC collector.
- If the ODBC collector does not start automatically, refer to the Historian log file to view log entries to determine the problem.

The ODBC Collector Cannot Connect to the ODBC Server

If you have provided incorrect ODBC server details (that is the server name, username, and password) either in Historian Administrator or in the `ODBC_Mapping.xml` file, the ODBC collector cannot connect with the ODBC server.

Workaround:

1. Delete the ODBC collector instance.
2. Provide values for the following properties in the registry key `HKLM\Softwares\GE Digital\iHistorian\Services\ODBCCollector`:
 - **General1**: ODBC server name
 - **General2**: ODBC server username
 - **General3**: ODBC server password
3. Ensure that [the mapping file is configured correctly \(on page 2349\)](#).
4. Restart the collector.

If this workaround is not successful, restart the collector instance.

Chapter 24. The OPC Classic DA Collector

Overview of the OPC Classic DA Collector

The OPC Classic Data Access (DA) collector collects data from any OPC 1.0 or OPC 2.0 compliant OPC server (such as CIMPLICITY). The collector automatically determines the capability of the OPC server to which it is connected and supports appropriate features based on this information.

Features:

- You can browse the source for tags and their attributes on an OPC server that supports browsing.
- Both the polled and unsolicited data collection are supported; when changes to the OPC source tags are detected, they are sent to the Historian server. Unsolicited data collection is supported for OPC 2.0 only. The minimum poll interval is 100ms. The collector duplicates raw samples from the OPC server into the Historian data archive.

For unsolicited data collection, if collector compression is disabled, all new values produce an exception. And, the deadband percentage is determined by the collector deadband percent. You can only configure the collector deadband percent by enabling compression.

- The supported timestamp resolution is 1ms.
- Floating point, integer, binary, and string data are supported.
- Python expression tags are supported.
- Device timestamps are accepted.

Supported data types:

The OPC Data Type	Recommended Data Type in Historian
I1 - 16 bit signed integer	Single Integer
I4 - 32 bit signed integer	Double Integer
R4 - 32 bit float	Single Float
R8 - 64 bit double float	Double Float
UI2 - 16 bit unsigned single integer	Unsigned Single Integer
UI4 - 32 bit unsigned double integer	Unsigned Double Integer
UI8 - 64 bit unsigned quad integer	Unsigned Quad Integer
I8 - 64 bit quad integer	Quad Integer

The OPC Data Type	Recommended Data Type in Historian
BSTR	Variable String
BOOL	Boolean
11 - 8 bit single integer	Byte

**Note:**

The collector requests data from the OPC server in the native data type. Then the collector converts the received value to a Historian Data Type before sending it to the data archiver.

Supported tag attributes:

- Tagname
- Source Address
- Engineering Unit Description
- Data Type
- Hi Engineering Units
- Lo Engineering Units
- Is Array Tag

The Engineering Unit Description, Hi Engineering Units and Lo Engineering Units vary based on the OPC server vendor.

**Note:**

While some of these attributes are queried on a browse, they are not shown in the browse interface. These attributes are used when adding a tag, but it is not visible to you if all attributes come from the server or not.


Configuration

Add and Configure an OPC Classic Data Access Collector

The OPC Classic Data Access (DA) collector collects data from any OPC 1.0 or OPC 2.0 compliant OPC Classic server. For more information, refer to [Overview of the OPC Classic DA Collector \(on page 2356\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select **+**.



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **OPC Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. Enter values as described in the following table.

Field	Description
OPC SERVER	Select the machine on which you have installed the OPC Classic DA server from which you want to collect data.

Field	Description
MACHINE NAME	Enter the host name or IP address of the OPC server. This field appears only if you have selected a remote OPC server. A value is required.
OPC DA SERVER PROG ID	Enter the prog ID of the OPC server. This field appears only if you have selected a remote OPC server. A value is required.

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

a. If you need to send data to a cloud destination, select the cloud destinations as needed.

- **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
- **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
- **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: `<system name>_OPC_<OPC server name>`

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.


14. Under **COLLECTOR SPECIFIC CONFIGURATION**, configure values as described in the following table.

Field	Description
OPC Server Prog ID	The program ID of the OPC server from which you want to collect data.
Read Mode	The read mode that you want the collector to use. For information, refer to the documentation of the OPC server that you are using or the OPC specification on the OPC Foundation website.
First Browse Criteria	<p>A comma-separated first-level search criterion for browsing tags from the data source. The top-level and second-level criteria are used together by the AND operation to browse tags.</p> <p>For example, if you enter <code>USGB014</code> in the First Browse Criteria field and <code>F_CV, B_CUALM</code> in the Second Browse Criteria field, it returns all the tags that contain:</p> <ul style="list-style-type: none"> ◦ <code>USGB014</code> -and- ◦ <code>F_CV</code> or <code>B_CUALM</code>
Second Browse Criteria	A comma-separated second-level search criterion for browsing tags from the data source. The top-level and second-level criteria are used together by the AND operation to browse tags.
Threading Model	<p>The type of the threading model selected for the collector. The model selected must match the threading model of the OPC server.</p> <ul style="list-style-type: none"> ◦ Multithreaded: Select this option for better performance. We recommend that you configure your collector to use the default multi-threading model. ◦ Apparent: Select this option for best compatibility. Some OPC servers do not work well with multi-threading. If you experience problems running your collector with multi-threading, use the apartment model.

Field	Description
	The default setting is multi-threaded. For information, refer to the documentation of the OPC server you are using.
Configuration Changes	<p>Indicates whether the collector configuration changes are processed in real time or after restarting the collector.</p> <ul style="list-style-type: none"> ◦ Made On-Line: Select this option to process any configuration changes immediately (after 30 seconds) after you select the Update button. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Note:</p> <ul style="list-style-type: none"> ▪ Some OPC servers cannot handle processing configuration changes online. If you experience any instability with changes made online, use the next option. </div> <ul style="list-style-type: none"> ◦ Made After Collector Restart: Select this option to hold all configuration changes until you manually restart the collector.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,

- If you have selected **Historian Configuration**, [specify the tags for data collection \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of Historian>\GE Digital\<<collector name>*. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Configure the OPC Classic DA Collector Using Historian Administrator

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Collectors**, and then select the OPC Classic DA collector instance that you want to configure.
3. Select **Configuration**.
The **Configuration** section appears.

Collector Specific Configuration (OPC)

OPC Server PROGID

Read Mode

First Browse Criteria

Second Browse Criteria

Threading Model

Configuration Changes

4. Enter values as specified in the following table.

Field	Description
OPC Server Prog ID	The program ID of the OPC server from which you want to collect data.
Read Mode	The read mode that you want the collector to use. For information, refer to the documentation of the OPC server that you are using or the OPC specification on the OPC Foundation website.
First Browse Criteria	<p>A comma-separated first-level search criterion for browsing tags from the data source. The top-level and second-level criteria are used together by the AND operation to browse tags.</p> <p>For example, if you enter <code>USGB014</code> in the First Browse Criteria field and <code>F_CV, B_CUALM</code> in the Second Browse Criteria field, it returns all the tags that contain:</p>

Field	Description
	<ul style="list-style-type: none"> ◦ USGB014 -and- ◦ F_CV or B_CUALM
Second Browse Criteria	<p>A comma-separated second-level search criterion for browsing tags from the data source. The top-level and second-level criteria are used together by the AND operation to browse tags.</p>
Threading Model	<p>The type of the threading model selected for the collector. The model selected must match the threading model of the OPC server.</p> <ul style="list-style-type: none"> ◦ Multithreaded: Select this option for better performance. We recommend that you configure your collector to use the default multi-threading model. ◦ Apparent: Select this option for best compatibility. Some OPC servers do not work well with multi-threading. If you experience problems running your collector with multi-threading, use the apartment model. <p>The default setting is multi-threaded. For information, refer to the documentation of the OPC server you are using.</p>
Configuration Changes	<p>Indicates whether the collector configuration changes are processed in real time or after restarting the collector.</p> <ul style="list-style-type: none"> ◦ Made On-Line: Select this option to process any configuration changes immediately (after 30 seconds) after you select the Update button. <div data-bbox="748 1419 1419 1686" style="border: 1px solid #00a0c0; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Note:</p> <ul style="list-style-type: none"> ▪ Some OPC servers cannot handle processing configuration changes online. If you experience any instability with changes made online, use the next option. </div> <ul style="list-style-type: none"> ◦ Made After Collector Restart: Select this option to hold all configuration changes until you manually restart the collector.

Field	Description
	<div data-bbox="747 260 1421 619" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: Starting and stopping the collector in the General section of the Collector Maintenance page of Historian Administrator does not constitute a manual restart. You must either start and stop the collector from the Services window or the console application. </div> <p data-bbox="662 653 1421 821">To allow configuration changes, you also must enable the On-Line Tag Configuration Changes option on the Advanced section of the Collector Maintenance page of Historian Administrator.</p>

5. Select **Update**.
6. Restart the collector.
The collector is configured.

Configure GE Intelligent Platform Drivers and Deadbands

If you want to add items of different data types to Historian using the OPC Classic DA collector to a GE Intelligent Platform v7.x driver or an OPC server, and you are using deadbands, you must manually modify the source address for each item you add. This is to specify the engineering unit (EGU) range for that item.

1. Access Historian Administrator.
2. Select **Tag Maintenance**, and then select the item that you want to modify.
3. Select **Collection**.
4. In the **Source Address** field, add the following fields:

```
SIGNALCONDITIONING,LOWEGU,HIGHEGU,HARDWAREOPTIONS
```
5. Repeat the steps for each item that you want to modify. If, however, you want all the items to use the same data type, change the settings of the following registry key: `\\HKEY_LOCAL_MACHINE\SOFTWARE\In-tellution\Drivers\SI7\OPC\ItemDefaults`. These values apply to all items not specified by the source address after you restart the driver.

Using Deadbands with the SI7 Driver

When you use the SI7 driver, it sets the global default values for EGU limits used for deadband calculations to the following values:

- 1 Lo EGU = 0
- 1 Hi EGU = 65535
- 1 EGU Span = Hi EGU - Lo EGU = 65535

You may want change the default values for this driver if the items that you add use data types other than Integer (such as Float).

If, however, you want all the items to use the same data type, change the settings for `HiEGU` and `LoEGU` for the following registry key: `\\HKEY_LOCAL_MACHINE\SOFTWARE\In-tellution\Drivers\SI7\OPC\ItemDefaults`. These values apply to all items not specified by the source address after you restart the driver.

Specifying Tags for Data Collection


Add Tags for the Data Store Using Configuration Hub

- [Add the collector instance \(on page 357\)](#) using which you want to collect data. Ensure that the collector is running.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, [create it \(on page 370\)](#).

This topic describes how to specify the tags for which you want to collect data by browsing through the tags in the data source. For example, for an iFIX collector, if there are 1,00,000 tags in the iFIX server, you must specify the ones for which you want to collect data. Only then data is collected for those tags.

In addition to adding tags from the data source, you can [create tags manually \(on page 473\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select  .



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. A value is required.
COLLECTED TYPE	Specify whether you want to browse through all the tags in the data source or only from the tags that you have not added yet. A value is required.
SOURCE TAG NAME	Enter the name of the tag (either completely or partially) to narrow down the search results.
SOURCE TAG DESCRIPTION	Enter the description of the tag (either completely or partially) to narrow down the search results.

5. Select **Search Tags**.

A list of tags that match *all* the criteria that you have specified appears. If a tag is already added, it is disabled.

6. Select the check box corresponding to each tag for which you want to collect data.

Add Tags from Collector
 Add Manually

COLLECTOR NAME*
 COLLECTED TYPE*
 SOURCE TAG NAME
 SOURCE TAG DESCRIPTION

SEARCH RESULTS FOR SOURCE TAGS NAMES

<input type="checkbox"/>	TAG NAME	DESCRIPTION
	<i>Filter</i>	<i>Filter</i>
<input type="checkbox"/>	Simulation.Simulation00001	Simulation.Simulation00001
<input type="checkbox"/>	Simulation.Simulation00002	Simulation.Simulation00002
<input type="checkbox"/>	Simulation.Simulation00003	Simulation.Simulation00003
<input type="checkbox"/>	Simulation.Simulation00004	Simulation.Simulation00004
<input type="checkbox"/>	Simulation.Simulation00005	Simulation.Simulation00005
<input type="checkbox"/>	Simulation.Simulation00006	Simulation.Simulation00006
<input type="checkbox"/>	Simulation.Simulation00007	Simulation.Simulation00007
<input type="checkbox"/>	Simulation.Simulation00008	Simulation.Simulation00008
<input type="checkbox"/>	Simulation.Simulation00009	Simulation.Simulation00009
<input type="checkbox"/>	Simulation.Simulation00010	Simulation.Simulation00010
<input type="checkbox"/>	Simulation.Simulation00011	Simulation.Simulation00011
<input type="checkbox"/>	Simulation.Simulation00012	Simulation.Simulation00012

DATASTORE*

7. In the **DATA STORE** field, if you want to store the data in a different data store than the user data store, select the same.

8. Select **Add Tag**.

Data collection begins for the selected tags.

As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.

Specify Tags for Data Collection Using Historian Administrator

If your OPC server supports hierarchical organization of tags in a tree structure, you can use the hierarchy to browse for tags and add them to the collector for data collection.

1. Access Historian Administrator.
2. Select **Collectors**, and then select the OPC Classic DA collector instance to which you want to add tags.
A hierarchical view of tags appears in the **Browse Results** section.
3. If you want to view only the tags for which data is not collected, in the **Show Only** field, select **Source Tags Not Collected**. You can search for a tag by entering search criteria in the **Source Tag Name** or **Description** field.

4. If you want to search by a tag name or description, enter the value in the **Source Tag Name** or **Description** field.
5. Navigate to the node in the tree you want to browse, and then select **Browse**.

**Tip:**

- To browse automatically, select the **Auto Browse** check box. The available tags appear in the **Browse Results** window whenever a node is selected in the tree.
- To show all child elements within a hierarchy, select the **Show All Children** check box. All tags at or below the hierarchical level of the selected node in the tree appear in the **Browse Results** window.

The tags within the selected portion of the OPC server tag hierarchy appear.

- Some OPC servers do not support data blocks with a length greater than 1. These servers display only the first item in an array instead of showing all of them. For example, an OPC server may contain 3000 analog values from datablock:1 to datablock:3000, but only datablock:1 is displayed.
- If you want to archive data from poll records of a length greater than 1, we recommend that you use the Excel Add-In for Historian to configure a large block of tags (including the missing items), and then add the tags.
- If you are unable to browse items containing a forward slash (/) in your OPC server, you may have to change the default separator in the collector configuration. To do so, modify the registry key `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\OPCCollector\<collector interface name>\OPCBrowseTreeSep` key, and change the string value to a character not available in your OPC server item IDs. Typical values include |, !, or &. Create this key if it does not exist.
- If you are cannot browse readable items in your OPC server, you may need to change the browse access mask used by the collector. To do so, modify the registry key `[HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\OPCCollector\<collector interface name>`, and add the DWORD key `"OPCBrowseAccessRightsMask"=dword:00000003`. Valid values are 0, 1, 2, 3 with 1 being the default. Use 0 or 3 if you are unable to browse readable items. Creating or changing the value takes effect on the next browse attempt and does not require a collector restart.
- Some items such as unsupported data types and user-defined items in simulation servers may not be returned when you browse for tags. However, sometimes, even the items that do not appear in the search results can be added using the **Add Tag Manually** button.

6. Select the tags for which you want to collect data, and then select **Add Selected Tags**. Collected tags will appear in black in the tag list.

The tags are added to the collector. They appear in black text in the list of tags.

OPC Group Creation

It is recommended that you limit the number of OPC groups created by the Historian system to increase performance. To limit the number of OPC groups created on the OPC server, consider grouping Historian tags (collected by the OPC collector) using the least amount of collection intervals possible.

Troubleshooting the OPC Classic DA Collector

Troubleshooting Tips

When reviewing the OPC Classic DA collector log file, or the log messages from Event Viewer:

- If you notice a message that states that Historian could not create the buffer files, then the issue is most likely that you do not have enough free space available for the buffer files.
- If you notice the OPC Classic DA collector connection attempt, a COM initialization attempt, and then a shutdown, the cause of the error is most likely that the collector is trying to start before the OPC server fully starts.
- If you look at the log files and you do not see anything special, aside from a startup attempt and a shutdown message, then begin by assuming that the OPC server is not fully starting. If the workaround for that issue does not appear to work, try adjusting the buffer size.

Issue: The Collector Fails to Start

Possible Causes:

- There is not enough free space for the collector to create its buffer files on startup.
- Historian is trying to run the OPC Collector before the OPC Server fully starts.

Try the workarounds in the following sections.

Issue: Not Enough Space for Buffer Files

Workaround: Try one of the following options:

- Free up the disk space.
- Move the buffer files to a different location.

- Change the buffer size by adding a DWORD `MinimumDiskFreeBufferSize` in the registry under `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\OPCCollector\<collector interface name>`. We recommend setting it to 10 or 20 MB. After you save your changes, restart your machine.

Issue: The Collector does not Connect to the Historian Server

Workaround: Check the `Logfiles` folder on the collector machine. If the log file specifies "could not create buffer files", repeat the workaround in the previous issue.

Issue: The Collector Tries to Start Before the OPC Server Starts

Workaround: Specify a time delay for the collector to start. To do so, add a DWORD named `MachineUpTimeDelay` in the registry under `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\OPCCollector\<collector interface name>`. We recommend that you set its value to 120 seconds first, and restart the collector. If the problem still exists, try increasing the value slightly until the issue is resolved.

Issue: The Collector Becomes Unresponsive After the First Polled Read

Workaround: If the polled reads take more than a few seconds to start:

1. Create a DWORD named `OPCFirstReadMode` in the registry under `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\OPCCollector\<collector interface name>`.
2. Provide one of the following values:
 - 1: Use this value if you want the collector to perform the faster `OPC_DS_CACHE` read on the first poll.
 - 2: Use this value if you want the collector to perform the slower `OPC_DS_DEVICE` read.
3. Restart the collector.

Validating Items Before Adding to Polled Collection Group

To validate items before adding them to the polled collection groups from the collector, create a DWORD named `OPCValidateBeforeAdd` in the registry under `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\OPCCollector\<collector interface name>`, and set the value to 1.

Issues with Browsing for Tags

Workaround:

- Some OPC servers do not support data blocks with a length greater than 1. These servers display only the first item in an array instead of showing all of them. For example, an OPC server may contain 3000 analog values from datablock:1 to datablock:3000, but only datablock:1 is displayed.
- If you want to archive data from poll records of a length greater than 1, we recommend that you use the Excel Add-In for Historian to configure a large block of tags (including the missing items), and then add the tags.
- If you are unable to browse items containing a forward slash (/) in your OPC server, you may have to change the default separator in the collector configuration. To do so, modify the registry key `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc\iHistorian\Services\OPCCollector\<collector interface name>\OPCBrowseTreeSep` key, and change the string value to a character not available in your OPC server item IDs. Typical values include |, !, or &. Create this key if it does not exist.
- If you are cannot browse readable items in your OPC server, you may need to change the browse access mask used by the collector. To do so, modify the registry key `[HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\OPCCollector\<collector interface name>`, and add the DWORD key `"OPCBrowseAccessRightsMask"=dword:00000003`. Valid values are 0, 1, 2, 3 with 1 being the default. Use 0 or 3 if you are unable to browse readable items. Creating or changing the value takes effect on the next browse attempt and does not require a collector restart.
- Some items such as unsupported data types and user-defined items in simulation servers may not be returned when you browse for tags. However, sometimes, even the items that do not appear in the search results can be added using the **Add Tag Manually** button.
- If you connect the collector to a Kepware Redundancy Master with both primary and secondary servers using Industrial Gateway Server (IGS) that share the same channel, device, and tags:
 - After creating a tag in Historian, if you modify the tag's source address, the tag will be considered invalid until the collector is restarted; data is not updated for the tag and the quality is not set to bad.
 - Always restart the Redundancy Master service before restarting the collector.
 - If you add IGS tags to Historian, you cannot delete them in IGS. If you try to do so, the following error message appears in IGS: Rejecting attempt to delete reference object.

To avoid this error, first delete the tags in Historian, and then delete the device in IGS.
 - If you cannot browse IGS for tags, restart the collector.

Chapter 25. The OPC Classic HDA Collector

Overview of the OPC Classic HDA Collector

The OPC Classic Historical Data Access (HDA) collector collects data from any OPC HDA 1.2 - compliant OPC server (such as CIMPLICITY). The collector automatically determines the capability of the OPC server to which it is connected and supports the appropriate features based on this information.

Topology:

The OPC Classic HDA collector and the OPC Classic HDA server support remote connectivity. If the OPC Classic HDA server and the OPC Classic HDA collector are on different machines, ensure that:

- The DCOM setting is provided for both the server and collector machines.
- Before starting the collector, ensure that NT AUTHORITY/SYSTEM has SysAdmin privileges.

Features:

- You can browse the source for tags and their attributes on an OPC server that supports browsing.
- Only unsolicited data collection is supported; when changes to the OPC source tags are detected, they are sent to the Historian server. The minimum poll interval is 100ms. The collector duplicates raw samples from the OPC server into the Historian data archive.

For unsolicited data collection, if collector compression is disabled, all new values produce an exception. And, the deadband percentage is determined by the collector deadband percent. You can only configure the collector deadband percent by enabling compression.



Note:

You must set the Time Assigned by field to Source if you have unsolicited tags getting data from an OPC Classic HDA collector.

- The supported timestamp resolution is 1ms.
- Floating point, integer, binary, and string data are supported.
- Device timestamps are accepted.

Supported data types:

The OPC Data Type	Recommended Data Type in Historian
I1- 16 bit signed integer	Single Integer
I4- 32 bit signed integer	Double Integer
R8- 64 bit double float	Single Float
UI2- 16 bit unsigned single integer	Double Float
UI4- 32 bit unsigned double integer	Unsigned Integer
UI8- 64 bit unsigned quad integer	Unsigned Double Integer
I8- 64 bit quad integer	Quad Integer
BSTR	Variable Sting
BOOL	Boolean
I1- 8 bit single integer	Byte

**Note:**

The OPC Classic HDA collector requests data from the OPC Classic HDA server in the native data type. The OPC Classic HDA collector then converts the received value to a Historian Data Type before sending it to the data archiver.

Supported tag attributes:

- Tagname
- Source Address
- Engineering Unit Description
- Data Type
- Hi Engineering Units
- Lo Engineering Units
- Is Array Tag

The Engineering Unit Description, Hi Engineering Units and Lo Engineering Units vary based on the OPC server vendor.

**Note:**

While some of these attributes are queried on a browse, they are not shown in the browse interface. These attributes are used when adding a tag, but it is not visible to you if all attributes come from the server or not.

Configuration

Add and Configure an OPC Classic HDA Collector

The OPC Classic Historical Data Access (HDA) collector collects data from any OPC HDA 1.2 - compliant OPC Classic HDA server. For more information, refer to [Configure the OPC Classic HDA Collector Using Historian Administrator \(on page 2380\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
3. In the upper-right corner of the main section, select **+**.

The screenshot shows the 'Collectors' page in the Configuration Hub. The page title is 'Collectors' and it is part of the 'Data Stores-win1...' application. The main content area is titled 'Historian Collectors' and 'Offline Configuration Collectors'. It shows a table with two columns: 'COLLECTOR NAME' and 'STATUS'. The table contains two entries: 'Calculation' and 'Simulation', both with a status of 'Running'. A red box highlights the '+' icon in the upper right corner of the main section, indicating where to click to add a new collector instance.

COLLECTOR NAME	STATUS
Calculation	Running
Simulation	Running

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.

5. In the **COLLECTOR TYPE** field, select **OPC HDA Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. Enter values as described in the following table.

Field	Description
OPC HDA SERVER	Select the machine on which you have installed the OPC Classic HDA server from which you want to collect data.
MACHINE NAME	Enter the host name or IP address of the OPC server. This field appears only if you have selected a remote OPC server. A value is required.
OPC DA SERVER PROG ID	Enter the prog ID of the OPC server. This field appears only if you have selected a remote OPC server. A value is required.

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

- a. If you need to send data to a cloud destination, select the cloud destinations as needed.

- **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
- **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
- **MQTT**- Select this if you need to send data to any of the following cloud destination.

- Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
- AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
- Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears.

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must contain the string `OPCHDA`.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account**: Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). By default, this option is selected, and the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account**: Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.


13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

- As needed, under **COLLECTOR SPECIFIC CONFIGURATION**, configure values as described in the following table.

Field	Description
Recovery Time	<p>It indicates the maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the OPC server is re-established. This time is calculated as the duration between the current time and the last known write time.</p> <p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>You can enter a value between 1 and 150.</p>
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

- As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).
- In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

Specify the tags whose data you want to collect using the collector. In the **CHOOSE CONFIGURATION** field,

- If you have selected **Historian Configuration**, [specify the tags using Configuration Hub \(on page 357\)](#).
- If you have selected **Offline Configuration**, modify the offline configuration file of the collector. By default, the file is available in the following location: *<installation folder of Historian>\GE Digital\<<collector name>*. For information, refer to [Offline Configuration for Collectors \(on page 2039\)](#). This option is applicable only if you have selected a cloud destination.

Configure the OPC Classic HDA Collector Using Historian Administrator

1. [Access Historian Administrator \(on page 823\)](#).
2. Select **Collectors**, and then select the OPC Classic HDA collector instance that you want to configure.
3. Select **Configuration**.
The **Configuration** section appears.

General | Configuration | **Tags** | Advanced | Performance | Redundancy

Collector Specific Configuration (Custom)

OPC HDA Server

Recovery Time (Hr)

Recalculate Add Tags Update Delete

4. Enter values as specified in the following table.

Field	Description
OPC HDA Server	The program ID of the OPC server from which you want to collect data.
Recovery Time	The maximum time, in hours, for which the collector will attempt to recover data after the collector is started or when connection between the collector and the OPC server is re-established. This time is calculated as the duration between the current time and the last known write time.

Field	Description
	<p>Continuous data collection is resumed only after the previous data has been recovered.</p> <p>You can enter a value between 1 and 150.</p>

5. Select **Update**.
6. Restart the collector.
The collector is configured.

Specifying Tags for Data Collection


Add Tags for the Data Store Using Configuration Hub

- [Add the collector instance \(on page 357\)](#) using which you want to collect data. Ensure that the collector is running.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, [create it \(on page 370\)](#).

This topic describes how to specify the tags for which you want to collect data by browsing through the tags in the data source. For example, for an iFIX collector, if there are 1,00,000 tags in the iFIX server, you must specify the ones for which you want to collect data. Only then data is collected for those tags.

In addition to adding tags from the data source, you can [create tags manually \(on page 473\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **+**.



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. A value is required.
COLLECTED TYPE	Specify whether you want to browse through all the tags in the data source or only from the tags that you have not added yet. A value is required.
SOURCE TAG NAME	Enter the name of the tag (either completely or partially) to narrow down the search results.
SOURCE TAG DESCRIPTION	Enter the description of the tag (either completely or partially) to narrow down the search results.

5. Select **Search Tags**.

A list of tags that match *all* the criteria that you have specified appears. If a tag is already added, it is disabled.

6. Select the check box corresponding to each tag for which you want to collect data.

Add Tags from Collector
 Add Manually

COLLECTOR NAME*
[Redacted]_Simulation

COLLECTED TYPE*
All Source Tags

SOURCE TAG NAME
*

SOURCE TAG DESCRIPTION
*

[Search Tags](#)

SEARCH RESULTS FOR SOURCE TAGS NAMES

	TAG NAME	DESCRIPTION
<input type="checkbox"/>	<i>Filter</i>	<i>Filter</i>
<input type="checkbox"/>	Simulation.Simulation00001	Simulation.Simulation00001
<input type="checkbox"/>	Simulation.Simulation00002	Simulation.Simulation00002
<input type="checkbox"/>	Simulation.Simulation00003	Simulation.Simulation00003
<input type="checkbox"/>	Simulation.Simulation00004	Simulation.Simulation00004
<input type="checkbox"/>	Simulation.Simulation00005	Simulation.Simulation00005
<input type="checkbox"/>	Simulation.Simulation00006	Simulation.Simulation00006
<input type="checkbox"/>	Simulation.Simulation00007	Simulation.Simulation00007
<input type="checkbox"/>	Simulation.Simulation00008	Simulation.Simulation00008
<input type="checkbox"/>	Simulation.Simulation00009	Simulation.Simulation00009
<input type="checkbox"/>	Simulation.Simulation00010	Simulation.Simulation00010
<input type="checkbox"/>	Simulation.Simulation00011	Simulation.Simulation00011
<input type="checkbox"/>	Simulation.Simulation00012	Simulation.Simulation00012

DATAS TORE*
User

7. In the **DATA STORE** field, if you want to store the data in a different data store than the user data store, select the same.
8. Select **Add Tag**.
Data collection begins for the selected tags.

As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.

Specify the Tags for Data Collection Using Historian Administrator

If your OPC server supports hierarchical organization of tags in a tree structure, you can use the hierarchy to browse for tags and add them to the collector for data collection.

1. Access Historian Administrator.
2. Select **Collectors**, and then select the OPC Classic HDA collector instance to which you want to add tags.
3. Select **Configuration**.
The **Configuration** section appears.

General | Configuration | **Tags** | Advanced | Performance | Redundancy


Collector Specific Configuration (Custom)

OPC HDA Server

Recovery Time (Hr)

4. Select **Add Tags**.

The **Add Multiple Tags from Collector** window appears.



5. In the **Collector** field, select the OPC Classic HDA collector to which you want to add tags. A hierarchical tree of tags appears in the **Browse Results** section.
6. If you want to view only the tags for which data is not collected, in the **Show Only** field, select **Source Tags Not Collected**. You can search for a tag by entering search criteria in the **Source Tag Name** or **Description** field.
7. Navigate to the node in the tree that you want to browse, and then select **Browse**.

**Tip:**

- To browse automatically, select the **Auto Browse** check box. The available tags appear in the **Browse Results** window whenever a node is selected in the tree.
- To show all child elements within a hierarchy, select the **Show All Children** check box. All tags at or below the hierarchical level of the selected node in the tree appear in the **Browse Results** window.

The tags within the selected portion of the OPC Classic HDA server tag hierarchy appear.

8. Select the tags for which you want to collect data, and then select **Add Selected Tags**. The tags are added to the collector. They appear in black text in the list of tags.

Data Recovery

**Note:**

We recommend that the collector for which the data recovery is intended is in the same time zone as the server. If there is a mismatch, there is a possibility that data recovery will be incomplete.

Automatic Data Recovery

In this mode, data is automatically recovered since the last time data has been collected.

How it works:

1. The collector determines the duration between the current time and the last time data has been written to the Historian data archive, which is stored in the LastSampleWriteTime registry key.
2. It compares this duration with the value in the Recovery Time field specified in [the collector settings \(on page 2347\)](#).
3. It uses the shorter duration to perform a raw data query on all the tags.
4. It then processes the returned samples in chronological order.

For example, if the collector was stopped for 8 hours, but Max Recovery Time was 4 hours, only 4 hours of data would be recovered.

As per the recovery logic, an end-of-collection marker is placed at the point in time where the collector was stopped. This end-of-collection marker may or may not be there after the recovery is complete. As part of the recovery logic, if recovery data point time matches the timestamp of the end-of-collection marker, it is overwritten with the recovered good data.

Manual Data Recovery

In this mode, you can fill gaps in the data, but you cannot fill old data.

To perform a manual recovery:

1. Access Historian Administrator.
2. Select **Collectors**, and then select the OPC Classic HDA collector instance for which you want to manually recover data.
3. Select **Recalculate**.

The **Recalculate** window appears.

4. Enter start time, end time, and other required information. We recommend that you choose small time intervals to reduce the load on the server and the collector.
5. Select **Recalculate**.

The tag data is recalculated. After the manual recalculation begins, the collector recovers data of the selected tags data from the collector, and sends it to Historian between the start time and end time.

At the time of recovery, if the connection to server is lost, and if the reconnect mechanism is enabled, the collector will try to connect to the server and fetch the data once connection re-establishes.

Manual Data Recovery

Assume that the collector is connected to Historian for the first time today and the archive was created at 10 am. The user initiates manual recalculation from 1am to 2 am. For that time interval, the archives were not even created. With respect to Historian, it is old unknown data and the data write fails. If there is a data gap between 1am and 2 am, manual recalculation successfully fills the data gap.

Reconnect to the OPC HDA Server Automatically

You can reconnect to the OPC Classic HDA server automatically as soon as the server is up and running. By default, the collector polls for the server connection every 5 seconds. You can change this interval as well. The collector is stopped until reconnected to the server.

1. Access the following registry key: `HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\iHistorian\Services\OPCHDACollector`.
2. Locate the Key created with the ProgID of the OPC Classic HDA server.
3. Create a DWORD named `EnableOPCHDAReconnect`.
4. Enter the decimal value 1.
5. If you want to change the reconnection interval (from the default value of 5 seconds):
 - a. Create a DWORD named `ReconnectInterval`.
 - b. Enter a decimal value between 5 and 60. This value represents the number of seconds for the collector to wait before trying to reconnect to the OPC server.
6. Select **OK**, then close the registry.

Troubleshooting the OPC Classic HDA Collector

The OPC Classic HDA collector generates log files during initialization, configuration, and general operation. By default, they are available in the following folder: `C:\Proficy Historian Data\LogFiles`.

If you encounter issues with the collector:

- Verify that the OPC Classic HDA server is running before the OPC Classic HDA collector starts up.
- If the OPC Classic HDA collector does not start automatically, refer to the log file to identify the issue.
- Enable the `CreateOfflineArchives` option in the destination Historian as the OPC Classic HDA collector sends the old data.

Chapter 26. The OPC Classic Alarms and Events Collector

About the OPC Classic Alarms and Events Collector

The OPC Classic Alarms and Events collector collects alarms and events data from an OPC Classic Alarms and Events server (such as CIMPLICITY), and stores it alongside Historian process data.

The OPC Classic Alarms and Events collector does not support pre-processing raw data with Python Expression Tags during collection.

About Event Types, Categories, and Conditions

The OPC Classic Alarms and Events collector captures all event types, categories, sub-categories, and conditions sent to it by the OPC Alarms and Events server.

Event Types

Three basic types of events are sent by an OPC Alarms and Events server: Condition, Simple, and Tracking. Each of these types has its own categories, sub-categories, and conditions. For example, a Condition event may have a Level category, which itself may have several conditions, such as LO LO, LO, HI, and HI HI.

Condition

Condition events record the transition of states in an alarm. For example, a condition event could be recorded for an alarm when the level changes from LO to HI HI.

Tracking

Tracking events are not associated with conditions, but rather track activity between the OPC Alarms and Events server and an OPC client. For example, if an operator acknowledges an alarm, a tracking event is recorded.

Simple

Simple events record everything not covered by Condition or Tracking events. For example, if a device were to fail, a simple event would be recorded.

Event Categories

Event categories are used to group similar event types and are configured on the OPC Alarms and Events server. For example, you might set up categories for System Events, Process Events, and Batch Events.

You might likewise set up categories for different areas of your process, such as Premix, Dry Mix, or Bake. Categories can hold multiple event types, and a given source can generate events for multiple categories.

**Note:**

Category names must be unique within the OPC Alarms and Events server.

Event Conditions

Conditions are named states of alarms and events within the OPC Alarms and Events server. Conditions can include LO LO, LO, HI, and HI HI, as well as SYSTEM_FAILURE, LIMIT EXCEEDED, NORMAL STATE, and others. Conditions may also contain sub-conditions, which help to narrow down the event conditions further. Refer to your OPC server documentation for a complete listing of its conditions.

For more information, refer to your OPC server documentation.

About Event Attributes

Events usually also include attributes, which give greater detail to the status of the event. Attributes vary from server to server; user-defined attributes as well as vendor-defined attributes may be configured on your OPC Alarms and Events server.

Some common attributes are:

- Start time
- End time
- Acknowledgement status
- Acknowledgement time
- Operator name
- Data Source
- Quality
- Severity

Historian archives all event attributes sent to it by the OPC Alarms and Events server. Consult your OPC Alarms and Events server documentation for more information.

Workflow for Using the OPC Alarms and Events Collector

To use the OPC Classic Alarms and Events collector, you must perform the following tasks.

Number	Task	Notes
1	Install the collector (on page 142).	This step is required. This will place the collector binaries on the machines.
2	Add an instance (on page 357) of the OPC Classic Alarms and Events collector.	This step is required.
3	Configure the general options of the OPC Classic Alarms and Events collector by accessing the collector using Historian Administrator.	This step is required.
4	Configure the collector-specific options of the OPC Classic Alarms and Events collector.	This step is required.
5	Specify the filtering options for the alarms and events data (on page 2393).	This step is required.

Configure the OPC Alarms and Events Collector

The following table provides the OPC Classic Alarms and Events collector-specific configuration fields.

1. Access Historian Administrator.
2. Access the OPC Classic Alarms and Events collector, and then select **Configuration**.
3. Provide values as specified in the following table.

Field	Description
OPC Server PROGID	The PROGID of the OPC Alarms and Events server.
Link to Data Collector	The data collector to link to the alarms and events. This allows you to join alarms and events data with tag data when querying the Historian database for data. This is usually located on the same server as the OPC Alarms and Events server.

Field	Description
Filtering	Enables or disables filtering of the alarms and events data. For information, refer to Filter Alarms and Events Data (on page 2393) .
Show Last Alarms	Displays the last 10 collected alarms and events data points.
Close Alarms	Opens the Close Alarms window.



Important:

Although the collector will function properly with no associated data collector, alarms and events data will not be associated with tag data from the data collector if it is not specified in this field. As a result, queries through the Excel Add-in or the OLE DB provider will not be able to join tag and alarm data.

Filter Alarms and Events Data

By default, the OPC Classic Alarms and Events collector collects all the alarms and events data sent to it, and archive it. This ensures that all your alarms and events data will be archived, without any special configuration. If you archive all of your alarms and events data, it can impact the amount of storage required for Historian to operate. Therefore, you may want to specify which alarms and events data you want the OPC Classic Alarms and Events collector to collect. Alarms and Events filtering works on an inclusive model. If filtering is not enabled, all the alarms and events data is collected. If filtering is enabled, then data for only the selected alarms and events is collected.

This topic describes how to apply the various types of filters.

1. Access Historian Administrator.
2. Select **Collectors**.
3. Select the OPC Classic Alarms and Events collector instance that you want to configure.
4. Select **Configuration**.
5. In the **Filtering** section, select **Enabled**.
6. Select **Filters**.
7. Select the filter criterion as described in the following table.

Filtering Option	Description	Procedure
Severity range	Includes alarms between a low and high filter range. For example, filter alarms whose severity range is between 100 and 200.	<ol style="list-style-type: none"> a. Select the Filter by Severity Range check box. b. Enter a range of values in the Collect From and To boxes.
Event Type	Include events based on a selected type (on page 2390) .	<ol style="list-style-type: none"> a. Select the Filter by Event Type check box. b. Select the type of events you want to filter.
Area	Includes alarms and events based a user-defined process area. This is useful if you only want to collect alarms from specific process areas. This option works only if you have defined areas in the alarms and events server.	<ol style="list-style-type: none"> a. Select the Filter by Area check box. b. Select Edit. c. Select the areas by which you want to filter, and then select Copy. To add an area manually, enter the area you want to filter by in the Area box and select Copy.
Source	Includes alarms and events data based on the alarm source. This is useful if you only want to collect alarms from specific parts of your process.	<ol style="list-style-type: none"> a. Select the Filter by Source check box. b. Select Edit. c. Select the sources using which you want to filter, and then select Copy. To add a source manually, enter the source you want to filter by in the Source box and select Copy.

Filtering Option	Description	Procedure
Event Category	Includes events based on a selected category (on page 2390) .	<ol style="list-style-type: none"> a. Select the Filter by Event Category check box. b. Select Edit. c. In the Choose Event Category box, select an event category. d. In the Categories Available box, select the categories using which you want to filter data. To add a category manually, enter the category you want to filter by in the Category box, and then select Copy.



Note:

You can filter alarms and events by the event category only if the **Filter by Event Type** check box is selected for respective event category. For example, if you want to receive only alarms, enable the **Collect Condition Events** option in **Event Type**, and add the Event Category tag in the **Filter by Event Category** section. This is because alarms belong to the Event Category tag, and the Event Category tag belongs to the Event Type condition. For other mappings, refer to [iFIX Message Mappings](#).

8. Select **Update**.

The filtering options you have specified are saved.

Chapter 27. OPC Classic HDA Server

About OPC Classic HDA

About OPC Classic Historical Data Access (HDA)

OPC Classic HDA is widespread standard, which provides specifications to retrieve and analyze historical process data. This data is typically stored in a process data archive, database, or a remote terminal unit (RTU). You can analyze this data for trending, fault prediction, performance assessment, and so on.


Advantages of Using OPC Classic HDA

- With OPC Classic HDA, the exchange of historical data between an application and any data archive is consistent. Therefore, OPC HDA client applications that implement trends, reports, or spreadsheets can retrieve historical process data from Historian and other OPC Classic HDA servers.
- The OPC Classic HDA specifications are based on Microsoft's Object Linking and Embedding (OLE) and Distributed Component Object Model (DCOM) technologies. Therefore, OPC is endorsed by Microsoft.
- You can configure DCOM client and server software programs to run on the same computer node or distributed across a network of computers.
- The OPC Classic HDA is created to allow various automation applications to communicate with one another based on the historical data, regardless of the manufacturer. This allows greater flexibility and reliability when setting up automation systems.
- The OPC Classic HDA server specification provides a common view of automation information managed by the system for which the server was written.
- Developing OPC Classic-compliant applications is simplified because only one I/O interface is required.
- Using OPC-compliant applications increases the flexibility of your automation processes because they can also communicate with devices other than those specified by the applications' developers.
- Multiple OPC Classic HDA compliant client applications can communicate with an OPC Classic HDA server simultaneously.

For more information on OPC Classic HDA, visit [the OPC Foundation's website](#).

Data Flow

The following diagram shows the data flow between the OPC Classic HDA clients, the OPC Classic HDA server, and Proficy Historian.



About the Historian OPC Classic HDA Server

The Historian OPC Classic HDA server retrieves historical process data from Proficy Historian, and sends it to OPC Classic HDA clients. It dynamically updates the clients when tags are added and/or deleted in Historian. Clients that comply with this specification can connect to the OPC Classic HDA server to retrieve data from Historian.

Features of the OPC Classic HDA Server

- The server complies with the OPC HDA Server specification 1.2.0.
- You can browse for all the tags available in Historian.
- You can convert Historian timestamps, data types, and qualities to OPC HDA timestamps, data types, and qualities, respectively.
- You can automatically reconnect to the Historian server when connection is lost.
- You can connect multiple instances of the OPC Classic HDA clients to the same server without any additional configuration. The OPC Classic HDA server has been tested with the following OPC Classic HDA clients:
 - OPC Foundation HDA Sample client. You can download this client from www.opcfoundation.org
 - Advosol HDA test client. You can download this client from <http://www.advosol.com/t-free-tools.aspx>

Limitations

- The OPC Classic HDA server supports only synchronous read raw interface.

Setting Up

Set Up the Historian OPC Classic HDA Server

- Install the HDA server and Historian Administrator. For instructions, refer to [Install Client Tools \(on page 150\)](#).
- Disconnect and reconnect all the OPC HDA clients.

1. Access Historian Administrator.
2. Select **Browse for Server**, and select the Historian server that you want to connect with the OPC Classic HDA server.
3. Select **Set Selected Server as Target of HDA Server**, and then select **OK**.

The selected server is set as the target Historian server.

4. Configure any external OPC HDA clients to connect to the OPC Classic HDA server. You can connect multiple instances of the clients to a single server.

When an OPC HDA client tries to connect to the Historian OPC Classic HDA server, and if an instance of the server is not available, the instance is started, and the client connects to the running instance of the server. The Historian OPC Classic HDA server continues to run as long as there are clients connected to it.



Note:

The OPC Classic HDA server uses Proficy.Historian.HDA as the program ID (ProgID).

If you have installed the OPC Classic HDA server on a remote machine, enable the firewall.

Enable Tag-Level Security

1. Access Registry, and go to the following path: `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\HDAServer`
2. In the **TargetHistorianServer** registry key, enter details in following format:

`MachineName,UserName,Password,Timeout`

Turn On Debug Mode for Trace Log Files

The Trace Logging feature logs communications with the OPC Classic HDA server into an html file. Advanced users can use this log file to trace a history of communication events with the OPC Classic HDA collector server. It is designed for use by the support personnel only to assist in diagnosing issues with the Historian OPC Classic HDA server. By default, the log file is located in the following folder: `C:\Proficy Historian Data\LogFiles`.

The log file contains the following information:

- The date and time when an event has occurred.
- Errors and exceptions in parameters passed by an OPC HDA client.
- The status of an OPC HDA client.

For an example trace log file, refer to [Example Trace Log File \(on page 2403\)](#).

1. Access Registry, and then access the following key folder:
 - For Windows 32-bit: `HKEY_LOCAL_MACHINE\CLASSES_ROOT\SOFTWARE\Intellution,inc\iHistorian\HDAServer\`
 - For Windows 64-bit: `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\HDAServer\`
2. Modify values for **DebugMode DWORD** as follows, and then select **OK**:
 - a. In the **Base** box, select **Decimal**.
 - b. In the **Value** box, enter 255.

The debug mode is turned on for the trace logs.

Browse Large Number of Collectors and Tags

In the OPC UA HDA server, the flat address space is used by default. This type of model is used to browse a small number of tags. If you want to browse a large number of collectors and tags, enable the hierarchical address space.

1. Access Registry, and then go to the following key folder: .
 - For Windows (32-bit): `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\HDAServer\`
 - For Windows (62-bit): `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\HDAServer\`
2. Create a DWORD named `HierarchicalAddressSpace`.
3. In the **Value** box, enter 255.

**Note:**

For a flat address space, this value is set to 0.

4. Select **OK**, and then close the Registry.
5. Restart the OPC Classic HDA server by disconnecting and reconnecting all the OPC HDA clients.

Reference

Supported Attributes

The following table provides a list of the attributes supported by the OPC Classic HDA collector.

Historian Property Type	OPC Classic HDA collector Attributes	Data Type	Description
Data Type	OPCHDA_DATA_TYPE	Int16	The data type for the item. For information, refer to Supported Data Types (on page 2400) .
TagDescription	OPCHDA_DESCRIPTION	String	The description of the item.
Engineering Units	OPCHDA_ENG_UNITS	String	The units for the item (for example, kg/sec).
Archiving	OPCHDA_ARCHIVING	Boolean	Indicates whether Historian stores data for this item. The following values are valid: <ul style="list-style-type: none"> • 0: Indicates that data for this item is not stored. • 1: Indicates that data for this item is stored.
ItemID	OPCHDA_ITEMID	String	The Historian tag name. This is used to allow filtering in <code>Create-BrowseMethod</code> .

Supported Data Types

The following table provides a list of data types in Historian and the corresponding ones in the OPC Classic HDA server and the OPC UA HDA server.

Data Type in Proficy Historian	Data Type in the OPC Classic HDA server or the OPC UA HDA server.
Single Integer	VT_I2- 16 bit signed integer
Double Integer	VT_I4- 32 bit signed integer
Quad Integer	VT_I8- 64 bit quad integer
Unsigned Single Integer	VT_UI2- 16 bit unsigned single integer
Unsigned Double Integer	VT_UI4- 32 bit unsigned single integer
Unsigned Quad Integer	VT_UI8- 62 bit quad integer
Byte	VT_I1
Boolean	VT_BOOL
SingleFloat	VT_R4- 32 bit float
Double Float	VT_R8- 64 bit double float
Variable String	VT_BSTR
Fixed String	VT_BSTR
Date	VT_DATE
Blob	VT_BSTR

Supported Quality Values

The following table provides a list of the quality values in Historian and the corresponding ones in the OPC Classic HDA server.

Proficy Historian Quality	OPC Classic HDA Quality	Description
ihOPCGood	OPC_QUALITY_GOOD	Indicates that there is no need for inspection. This quality is returned for the tags that have all the values archived properly.
ihOPCBad	OPC_QUALITY_BAD	Indicates a need for attention. This quality is returned for the tags that had problems during the collection.

Proficy Historian Quality	OPC Classic HDA Quality	Description
ihOPCUncertain	OPC_QUALITY_UNCERTAIN	Indicates a need for inspection. This quality is returned when the data collection time is low and when there is no specific quality value.
ihOPCNA	OPC_QUALITY_BAD	Indicates a need for attention.

Supported Filter Attributes

The following table provides a list of attributes for which filtering is supported by the OPC Classic HDA server, and the corresponding ones in Historian, along with the supported operators for each.

Historian Property Type	OPC Classic HDA server Attributes	Supported Operators
Data Type	OPCHDA_DATA_TYPE	OPC_HDA_EQUAL_TO
Tag Description	OPCHDA_DESCRIPTION	OPC_HDA_EQUAL_TO
Engineering Units	OPCHDA_ENG_UNITS	OPC_HDA_EQUAL_TO
Item ID	OPCHDA_ITEMID	OPC_HDA_EQUAL_TO



Important:

The OPC Classic HDA server filter strings are case-sensitive.

Although filtering is supported for the OPC_HDA_ARCHIVING attribute, do not use the filtering in the OPC Classic HDA clients because the value of this attribute is always true. Instead, you can refer to the log file to trace a history of communication events dealt with by the OPC Classic HDA server. You can also turn on the debug mode to more know more details in the log file. If an invalid filter is passed by an OPC HDA client, the OPC Classic HDA server returns all the available items in the address space.



Tip:

- The wildcard character (*) will return all the tags.
- The wildcard (key*) will return tags which begins with "key".
- The wildcard (key) returns an exact tag name.

Example Trace Log File

The following message illustrates the type of information that the trace log file provides. In this message:

- The black color indicates the status of events.
- The blue color indicates the status of clients.
- The red color indicates errors and exceptions passed by clients.

```

-----
3/5/2009 10:12:19 AM HDA Client is connecting ...
3/5/2009 10:12:20 AM Connected to Historian server : [ES-4FCNR1S]
3/5/2009 10:12:20 AM HDA Client Connected
3/5/2009 10:12:21 AM HDA Address Space Created
3/5/2009 10:12:36 AM HDA Client Disconnected
3/5/2009 11:50:04 AM HDA Client is connecting ...
3/5/2009 11:50:05 AM Connected to Historian server : [ES-4FCNR1S]
3/5/2009 11:50:05 AM HDA Client Connected
3/5/2009 11:50:25 AM Historian Archiver : Tag Added [ES-4FCNR1S.Simulation00261]
3/5/2009 11:50:25 AM Historian Archiver : Tag Added [ES-4FCNR1S.Simulation00262]
3/5/2009 11:50:25 AM Historian Archiver : Tag Added [ES-4FCNR1S.Simulation00264]
3/5/2009 11:50:32 AM HDA Address Space Created
3/5/2009 11:50:59 AM Historian Archiver : Tag Added [ES-4FCNR1S.SimulationString00001]
3/5/2009 11:51:25 AM Historian Archiver : Tag Added [ES-4FCNR1S.SimulationString00002]
3/5/2009 11:51:25 AM Historian Archiver : Tag Added [ES-4FCNR1S.Ramp_20%Noise]
3/5/2009 11:51:25 AM HDA Client Disconnected
3/5/2009 2:34:27 PM HDA Client is connecting ...
3/5/2009 2:34:28 PM Connected to Historian server : [ES-4FCNR1S]
3/5/2009 2:34:28 PM HDA Client Connected
3/5/2009 2:34:28 PM HDA Address Space Created
3/5/2009 2:34:45 PM HDA Client Disconnected
3/5/2009 2:35:06 PM HDA Client is connecting ...
3/5/2009 2:35:07 PM Connected to Historian server : [ES-4FCNR1S]
3/5/2009 2:35:07 PM HDA Client Connected
3/5/2009 2:35:08 PM HDA Address Space Created
3/5/2009 2:35:08 PM HDA Address Space Created
3/5/2009 2:35:08 PM Invalid attribute at index [0]
3/5/2009 2:35:08 PM HDA Address Space Created
3/5/2009 2:35:08 PM Invalid type at index [0]
3/5/2009 2:35:08 PM HDA Address Space Created
3/5/2009 2:36:00 PM HDA Client is connecting ...
3/5/2009 2:36:01 PM Connected to Historian server : [ES-4FCNR1S]
3/5/2009 2:36:01 PM HDA Client Connected
3/5/2009 2:36:11 PM HDA Client is connecting ...
3/5/2009 2:36:11 PM HDA Client Connected
3/5/2009 2:36:12 PM HDA Address Space Created
3/5/2009 2:36:12 PM Invalid attribute at index [0]
3/5/2009 2:36:12 PM HDA Address Space Created
3/5/2009 2:36:12 PM Invalid type at index [0]
-----

```

OPC Classic HDA Aggregates

In the OPC Classic HDA server, an aggregate is a function that is used to process raw data from an OPC Classic HDA server over a given range of time divided into discrete intervals. These aggregates can be further used to for various purposes, such as visualizing the trends in the data.

The standard aggregates supported are:

- Minimum
- Maximum
- Average

The custom aggregates supported are:

- Nearest
- Before
- After
- Proficy Historian Interpolative

Consider the following as a Historian Source for the Minimum, Maximum and Average Aggregates:

Timestamp	Value	Quality	Notes
Jan-01-2002 12:00:00	0	No Data	First archive entry Point Created
Jan-01-2002 12:00:10	10	Raw, Good	
Jan-01-2002 12:00:20	20	Raw, Good	
Jan-01-2002 12:00:30	30	Raw, Good	
Jan-01-2002 12:00:40	40	Raw, Bad	Scan failed, Bad data entered
Jan-01-2002 12:00:50	50	Raw, Good	
Jan-01-2002 12:01:00	60	Raw, Good	
Jan-01-2002 12:01:10	70	Raw, Bad	Value is flagged as questionable
Jan-01-2002 12:01:20	80	Raw, Good	
Jan-01-2002 12:01:30	90	Raw, Good	
NULL	No Data	No more entries, awaiting next scan.	

Consider the following Historian Source for Nearest, Before and After Aggregates:

Timestamp	Value	Quality	Notes
Feb-28-2002 12:01:30	987	Raw, Bad	
Mar-01-2002 12:01:30	98765	Raw, Good	
Mar-02-2002 12:01:30	9876	Raw, Bad	
Jan-01-2002 12:00:00	0	No Data	First archive entry Point Created
Jan-01-2002 12:00:10	10	Raw, Good	
Jan-01-2002 12:00:20	20	Raw, Good	
Jan-01-2002 12:00:30	30	Raw, Good	
Jan-01-2002 12:00:40	40	Raw, Bad	Scan failed, Bad data entered
Jan-01-2002 12:00:50	50	Raw, Good	
Jan-01-2002 12:01:00	60	Raw, Good	
Jan-01-2002 12:01:10	70	Raw, Bad	Value is flagged as questionable
Jan-01-2002 12:01:20	80	Raw, Good	
Jan-01-2002 12:01:30	90	Raw, Good	

Average Aggregate

The purpose of Average aggregation is to find the average value for a given time interval. It adds up the values of all good raw data in a specified time interval. The sum is then divided by the number of good values. Bad values are ignored in the computation.

If the user specifies a time range where no good data exists for an interval, the quality of the aggregate for that interval will be bad, OPCHDA_NODATA.

This aggregate returns the timestamp of the start of the interval.

Example 1

Start: Jan-01-2002 12:00:10 **End:** Jan-01-2002 12:00:20 **Interval:** 00:00:05

Timestamp	Value	Quality
Jan-01-2002 12:00:10	10	Calculated, Good
Jan-01-2002 12:00:15	0	No Data, Bad

Example 2

Start: Jan-01-2002 12:00:35 **End:** Jan-01-2002 12:01:00 **Interval:** 00:00:05

Timestamp	Value	Quality
Jan-01-2002 12:00:35	0	No Data, Bad
Jan-01-2002 12:00:40	0	Bad data in the interval
Jan-01-2002 12:00:45	0	No Data, Bad
Jan-01-2002 12:00:50	50	Calculated, Good
Jan-01-2002 12:00:55	0	No Data, Bad

Maximum Aggregate

The maximum actual time aggregate retrieves the maximum good raw value within the interval [s,e), and returns that value the timestamp of the aggregate will always be the start of the interval for every interval. If the same maximum exists at more than one timestamp, the oldest one is retrieved.

Example 1

Start: Jan-01-2002 12:00:10 **End:** Jan-01-2002 12:00:20 **Interval:** 00:00:05

Timestamp	Value	Quality
Jan-01-2002 12:00:10	10	Raw, Good
Jan-01-2002 12:00:15	0	No Data, Bad

Example 2

Start: Jan-01-2002 12:00:35 **End:** Jan-01-2002 12:01:00 **Interval:** 00:00:05

Timestamp	Value	Quality
Jan-01-02 12:00:35	0	No Data, Bad
Jan-01-02 12:00:40	0	No Data, Bad
Jan-01-02 12:00:45	0	No Data, Bad
Jan-01-02 12:00:50	50	Raw, Good
Jan-01-02 12:00:55	0	No Data, Bad

Minimum Aggregate

The minimum actual time aggregate retrieves the minimum good raw value within the interval [s,e), and returns that value. The timestamp of the aggregate will always be the start of the interval for every interval.

Example 1

Start: Jan-01-2002 12:00:10 **End:** Jan-01-2002 12:00:20 **Interval:** 00:00:05

Timestamp	Value	Quality
Jan-01-02 12:00:35	0	No Data, Bad
Jan-01-02 12:00:40	0	Bad data in the interval
Jan-01-02 12:00:45	0	No Data, Bad
Jan-01-02 12:00:50	50	Raw, Good
Jan-01-02 12:00:55	0	No Data, Bad

Before Aggregate

When the Before aggregate function is called with a timestamp (Start time), the previous valid value before Start time will be fetched. This search is performed between **Start time** and (**Start time – MaxDurationSec**). The call for the aggregation is initiated by the source client. The custom aggregations do not require any interval value. The default value for MaxDurationSec is 100 days.



Note:

To change the value of MaxDurationSec navigate to `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\HDAserver`. Create a string value with name **MaxDurationSec** and provide the value in seconds.

Start: Apr-01-2002 12:00:10 **End:** NA **Interval:** NA

Timestamp	Value	Quality
Mar-01-2002 12:01:30	98765	Raw, Good

After Aggregate

When the After aggregate function is called with a timestamp (Start time), next valid value after 'Start time' will be fetched. This search will happen between **Start time** and (**Start time + MaxDurationSec**).

The call for the aggregation is initiated by the source client. The custom aggregations do not require any interval value. The default value for MaxDurationSec is 100 days.



Note:

To change the value of MaxDurationSec navigate to `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\HDAserver`. Create a string value with name **MaxDurationSec** and provide the value in seconds.

Start: Feb-01-2002 12:00:10 **End:** NA **Interval:** NA

Timestamp	Value	Quality
Mar-01-2002 12:01:30	98765	Raw, Good

Nearest Aggregate

When the Nearest aggregate function is called with a timestamp (Start time), the nearest valid value of Start time will be fetched. This search is performed between **Start time** and (**Start time ±**

MaxDurationSec). The call for the aggregation is initiated by the source client. The custom aggregations do not require any interval value. The default value for MaxDurationSec is 100 days.



Note:

To change the value of MaxDurationSec navigate to `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\HDA Server`. Create a string value with name **MaxDurationSec** and provide the value in seconds.

Start: Feb-01-2002 12:00:10 **End:** NA **Interval:** NA

Timestamp	Value	Quality
Mar-01-2002 12:01:30	98765	Raw, Good

Proficy Historian Interpolative Aggregate

The purpose of the interpolated aggregation is to return meaningful data for a time interval where raw data is not present. The value at a datapoint is estimated based on the raw data present at other datapoints.

For interpolative aggregate to return meaningful data, good values should be present at the boundary conditions.

Chapter 28. OPC UA HDA Server

Overview of the OPC UA HDA Server

About OPC Unified Access (UA) Historical Data Access (HDA)

OPC UA HDA is widespread standard, which provides specifications to retrieve and analyze historical process data. This data is typically stored in a process data archive, database, or a remote terminal unit (RTU). You can analyze this data for trending, fault prediction, performance assessment, and so on.


Advantages of Using OPC UA HDA

- With OPC UA HDA, the exchange of historical data between an application and any data archive is consistent. Therefore, OPC UA HDA client applications that implement trends, reports, or spreadsheets can retrieve historical process data from Historian and other OPC UA HDA servers.
- OPC UA HDA is created to allow various advanced automation applications to communicate with one another based on the historical data, regardless of the manufacturer or the platform/programming language on which they have been created. This allows greater flexibility and reliability when setting up automation systems.
- The OPC UA HDA server specification provides a common view of automation information managed by the system for which the server was written.
- Developing OPC UA-compliant applications is simplified because only one I/O interface is required.
- Using OPC-compliant applications increases the flexibility of your automation processes because they can also communicate with devices other than those specified by the applications' developers.
- Multiple OPC UA HDA compliant client applications can communicate with an OPC UA HDA server simultaneously.

For more information on OPC UA HDA, visit [the OPC Foundation's website](#).

Data Flow

The following diagram shows the data flow between the OPC UA HDA clients, the OPC UA HDA server, and Proficy Historian.



About the Historian OPC UA HDA Server

The Historian OPC UA HDA server retrieves historical process data from Proficy Historian, and sends it to OPC UA HDA clients. It dynamically updates the clients when tags are added and/or deleted in Historian. Clients that comply with this specification can connect to the OPC UA HDA server to retrieve data from Historian.

Features of the OPC UA HDA Server

- The server complies with the OPC HDA Server specification 1.7.2.
- The server can retrieve current data as well as historical data.
- You can browse for all the tags available in Historian.
- You can convert Historian timestamps, data types, and qualities to OPC HDA timestamps, data types, and qualities, respectively.
- You can automatically reconnect to the Historian server when connection is lost.
- You can connect multiple instances of the OPC UA HDA clients to the same server without any additional configuration. The OPC UA HDA server has been tested with the following OPC UA HDA clients; you can, however, use any client that supports the encryption types supported by the OPC UA HDA server:

- OPC UA Client. You can download this client from <https://opcfoundation.org/products/view/opc-ua-client-free-product>.
- Prosys OPC Client. You can download this client from <https://www.prosysopc.com/products/opc-client/>.

Limitations

- The OPC UA HDA server supports only synchronous read raw interface.
- The OPC UA HDA server currently does not support aggregation and alarms and events data. It only supports tag data.
- If you make changes to [the OPC UA HDA server settings \(on page 2416\)](#), restart the OPC UA HDA Server service.

Configuration

Install the OPC UA HDA Server


[Install Historian \(on page 104\)](#).



Note:

You can install Historian and the OPC UA HDA server on the same machine or on different machines.

1. Run the Historian installer.
2. Select **Install Historian OPC UA HDA Server**.
The welcome page appears.
3. Select **Next**.
The license agreement appears.




4. Select the **Accept** check box, and then select **Next**.

The **Where to install the Historian OPC UA HDA Server** page appears, asking you to select the installation drive.

5. Select the installation drive, and then select **Next**. You can retain the default one, or choose a different one.

The **OPC UA HDA Server Attributes** page appears.



6. Provide values as described in the following table, and then select **Next**.

Field	Description
Historian OPCUA HDA Server	Enter the host name or the IP address of the machine on which you want to install the OPC UA HDA server. By default, the local host name appears.
Port Number	Enter the port number that you want the OPC UA HDA server to use.
URI	The URI to access the OPC UA HDA server. This field is disabled and populated with a value in the following format: <code>opc.tcp://<host name>:<port number></code> , where <i><host name></i> and <i><port number></i> are the values that you have entered in the preceding fields.

The **Historian Server Details** page appears.

Historian Server Details.

Historian Server Name : myhistserver

Historian Server User Name :

Historian Server Password :

Cancel Previous Next

7. Provide values as described in the following table, and then select **Next**.

Field	Description
Historian Server Name	Enter the name of the Historian server that you want to connect to the OPC UA HDA server.
Historian Server User Name	Enter the username of the Historian server.
Historian Server Password	Enter the password of the Historian server.

The **You are ready to install** page appears.

8. Select **Install**.

The Historian OPC UA HDA server is installed. Reboot the machine when prompted to do so.

- If you have installed the OPC UA HDA server on a remote machine, enable the firewall.
- Install an OPC UA client.
- Configure the OPC UA HDA server.

The OPC UA HDA Server Workflow

This topic provides the high-level steps to get started with the Historian OPC UA HDA server. These steps are required only for the initial setup. After you perform these steps, you can use an OPC UA HDA client to retrieve and analyze the historical data.

Step Number	Step	Notes
1	Install Historian (on page 104).	This step is required.
2	Install the OPC UA HDA Server (on page 191).	This step is required. You can install Historian and the OPC UA HDA server either on the same machine or on different machines.
3	Configure the OPC UA HDA server settings (on page 2416).	This step is required only if you want to change the default settings or the values you provided while installing the OPC UA HDA server.
4	Install an OPC UA HDA client.	This step is required only if you want to use a third-party OPC UA HDA client.
5	Connect the OPC UA HDA server and the OPC UA HDA client (on page 2420).	This step is required only if you want to use a third-party OPC UA HDA client. In this step, the server and the client exchange certificates to establish a secure connection.
6	Authenticate the user to connect to the OPC UA HDA server (on page 2421).	This step is required only if you want to use a third-party OPC UA HDA client. You can use authentication based on user credentials or a certificate. Anonymous authentication is not supported.

Configure the OPC UA HDA Server Settings

- [Install the OPC UA HDA server \(on page 191\).](#)
- Install an OPC UA client that you want to use with the OPC UA HDA server.

1. Run the `ihistopcuahdaserverconfigtool.exe` file as an administrator. This file is located in the following folder: `<installation drive>:\Program Files\GE Digital\Historian OPCUA HDA Server`

The **Proficy Historian OPC UA Server Configuration** window appears.

2. Provide values in the available fields as described in the following table.

Field	Description
Port	Enter the TCP port number on which you want the OPC UA HDA server to run. By default, the value in this field is 48010.
Hostname	Enter the host name of the machine on which you have installed the OPC UA HDA server.
Network Address	Enter the DNS name or IP address of the machine on which you have installed the OPC UA HDA server. The network address must be the computer name or an IP address, as this represents how OPC clients will locate the OPC UA HDA server.
Organization Name	Enter the name of the organization that is deploying the OPC UA HDA server.
Endpoint Uri	Identifies the network endpoint that the OPC clients use to communicate with the OPC UA HDA server. This field is disabled and populated with a value in the following format: <code>opc.tcp://<network address>:<port>/</code> .

Field	Description
Application Url	Identifies a unique identifier for the OPC UA HDA server. This field is disabled and populated with a value in the following format: urn:<host name>:<organization name>:HDAServer).
Machine Name	Enter the name of the machine on which Historian is installed.
UserName	Enter the username to connect to the Historian server.
Password	Enter the password to connect to the Historian server.

3. Select **Model**.

The **Model** section appears.

4. If you want to access the Historian model using an OPC UA HDA client:

a. Select the **Yes, I want to use a model** check box.

b. Under **Web-based Clients Configuration**, in the **Server Name** and **Port** fields, enter the host name (or IP address) and public HTTPS port number respectively of the machine on which you have installed Web-based Clients.

c. Select **Test connection**.

Connection to the machine on which you have installed Web-based Clients is verified, and the **Server Name** and **Port** fields under **Proficy Authentication Configuration** are populated with the corresponding values you provided while installing Web-based Clients.

d. Verify that the server name and port number of the machine on which you have installed Proficy Authentication are correct, and select **Test connection**.

5. Select **Logging**.

The **Logging** section appears.

6. If you want to enable logging, select the **Logging Enabled** check box, and then provide values as described in the following table.

Field	Description	Default Value	Valid Values
No of Log Files	The maximum number of log file backups that you want to retain.	5	1 to 100
Max Entries per Log file	The maximum number of lines that you want in the log file before it is backed up and a new log is created.	100000	1000 to 1000,000,000
Optimize Log Output	Indicates whether the log output is buffered before it is saved to disk.	False	<ul style="list-style-type: none"> ◦ True ◦ False
Application Trace Level	The level of trace information that you want the OPC UA HDA server to log.	Error	<ul style="list-style-type: none"> ◦ None ◦ Error ◦ Warning ◦ Info ◦ Debug
Stack Log Level	The level of trace information that you want the OPC UA HDA stack to log.	Error	<ul style="list-style-type: none"> ◦ None ◦ Error ◦ Warning ◦ Info ◦ Debug
Log File Path	The path of the log file. You can provide a folder other than the default one; the log file will be created in that folder.	<installation drive>:\ProgramData\GEDigitalUA\logs\UaSdkCppBundle-Source\HDAServer.log	

7. Select **Security**, and provide values as described in the following table.

Field	Description
Allow secure communication with data privacy (SignAndEncrypt)	If you select this option, all communication is kept private, and the OPC clients are authenticated.
Allow secure communication without data privacy (SingOnly)	If you select this option, all communication is visible, but the OPC clients are authenticated.
Allow communication with no security (None)	If you select this option, a certificate is not used for communication between OPC clients and the OPC UA HDA server. This option is not recommended; you can use it only in a non-production environment.
Basic256Sha256	This policy is acceptable and more likely to be supported by older versions of the OPC UA HDA clients.
Aes128Sha256RsaOaep	This policy is secure and is faster than the most secure policies. However, older versions of the OPC UA HDA clients do not support it.
Aes256Sha256RsaPss	This policy is the more secure one. However, older versions of the OPC UA HDA clients do not support it.
Basic128Rsa15	This policy has theoretical problems and is not recommended.
Basic256	This policy has known vulnerabilities and must not be used unless absolutely necessary.

8. Restart the OPC UA HDA Server service.

Establish a connection between the OPC UA HDA server and the OPC UA client that you want to use (on page 2420).

Connect the OPC UA HDA Server and the OPC UA HDA Client

Configure the OPC UA HDA server settings (on page 2416).

To establish a connection between the OPC UA HDA server and an OPC UA client:

1. The OPC UA HDA server sends a certificate to the OPC UA client.
2. The OPC UA client sends a certificate to the OPC UA HDA server.

This topic describes how to perform these steps.

1. Start the OPC UA HDA server. To do so, run the Historian OPC UA HDA Server service.
2. Access the OPC UA client application, and create a connection with the endpoint URL that you provided while [configuring the OPC UA HDA server settings \(on page 2416\)](#).
3. Select the security settings that you want to use for the OPC UA client.

The OPC UA HDA server sends the server certificate to the OPC UA client. A message appears, asking you to accept the server certificate.

4. Accept the server certificate.

The OPC UA client sends a certificate to the OPC UA HDA server. However, an error message appears, stating that verifying the certificate has failed. This happens because, by default, the client certificate is rejected.

5. Accept the client certificate:

- a. In the **Proficy Historian OPC UA Server Configuration** window, select **Trust List**.

The client certificate appears. A  icon appears next to the certificate, indicating that it is rejected.

- b. Select the row containing the client certificate, and then select **Trust Certificate**.

A message appears, asking you to confirm that you want to trust the client certificate.

- c. Select **Yes**.

A  icon appears next to the certificate, indicating that it is trusted.

6. Access the OPC UA HDA client, and process the connection that you have created.

A message appears, asking you to accept the server certificate.

7. Accept the server certificate.

Connection between the OPC UA HDA server and the OPC UA HDA client is established.

[Authenticate the user who will use the OPC UA HDA client \(on page 2421\)](#).

Authenticate a User to Connect to the OPC UA HDA Server

[Connect the OPC UA HDA server and the OPC UA HDA client \(on page 2420\)](#).

You can authenticate a user based on one of the following methods:

- **User credentials:** In this method, you will use the credentials of a Historian user. When you do so, the OPC UA HDA server validates the credentials by connecting to the Historian server, and then grants access.



Note:

The user is authenticated regardless of whether the Historian server is part of a stand-alone or a distributed Historian system.

- **Certificate:** In this method, you will provide a trusted certificate and a private key of the OPC UA HDA server. The server validates that the certificate is the same as the user certificate stored in the server, and then grants access.



Tip:

You can generate a self-signed certificate and its keys using the **Proficy Historian OPC UA Server Configuration** tool, which is provided with the OPC UA HDA server.

Anonymous authentication is not supported.

1. Access the OPC UA HDA client.
2. If you want to authenticate a user using the user credentials, select the appropriate option in the user authentication window, and then enter the username and password of the Historian user.
3. If you want to authenticate a user using a certificate:
 - a. Select the appropriate option in the user authentication window.
 - b. Provide the certificate and the private key (which are stored in the .der and .pem formats respectively). If needed, enter a password for the private key.

The user is authenticated. A list of Historian tags appears in the OPC UA HDA client. These tags are represented as models in the client, categorized based on the data type. The OPC UA HDA server collects tag data from Historian, and sends it to the client. You can now use the client to access a trend chart of the tag data and analyze it.

Supported Attributes

The following table provides a list of the attributes supported by the OPC UA HDA server:

Historian Property Type	OPC UA HDA Attributes	Data Type	Description
Engineering Units	OpcUa_Range	String	The units for the item (for example, kg/sec).
Engineering Units Range	OpcUa_EUInformation	Int16	The upper and lower range of the engineering units.
Data Type	OPCHDA_DATA_TYPE	Int16	The data type for the item. For information, refer to Supported Data Types (on page 2400) .
TagDescription	OPCHDA_DESCRIPTION	String	The description of the item.

Supported Data Types

The following table provides a list of data types in Historian and the corresponding ones in the OPC Classic HDA server and the OPC UA HDA server.

Data Type in Proficy Historian	Data Type in the OPC Classic HDA server or the OPC UA HDA server.
Single Integer	VT_I2- 16 bit signed integer
Double Integer	VT_I4- 32 bit signed integer
Quad Integer	VT_I8- 64 bit quad integer
Unsigned Single Integer	VT_UI2- 16 bit unsigned single integer
Unsigned Double Integer	VT_UI4- 32 bit unsigned single integer
Unsigned Quad Integer	VT_UI8- 62 bit quad integer
Byte	VT_I1
Boolean	VT_BOOL
SingleFloat	VT_R4- 32 bit float
Double Float	VT_R8- 64 bit double float
Variable String	VT_BSTR

Data Type in Proficiency Historian	Data Type in the OPC Classic HDA server or the OPC UA HDA server.
Fixed String	VT_BSTR
Date	VT_DATE
Blob	VT_BSTR

Supported Quality Values

The following table provides a list of the quality values in Historian and the corresponding ones in the OPC UA HDA server.

Proficiency Historian Quality	OPC Classic HDA Quality	Description
ihOPCGood	OPC_QUALITY_GOOD	Indicates that there is no need for inspection. This quality is returned for the tags that have all the values archived properly.
ihOPCBad	OPC_QUALITY_BAD	Indicates a need for attention. This quality is returned for the tags that had problems during the collection.

Troubleshooting OPC UA HDA Server Issues

Unable to Connect to the Server

Issue: When you attempt to connect to the OPC UA HDA server from an OPC UA HDA client, a message appears, stating that you cannot connect to the server.

Diagnostics:

- Ensure that user authentication for the OPC UA HDA server is based on either user credentials or certificates. Anonymous authentication is not supported.
- If you have selected authentication based on user credentials, ensure that you have entered the correct credentials of the Historian server.

Unable to See the Latest Historian Model Changes in the OPC UA HDA Client

Issue: Changes to the Historian model are not reflected in the OPC UA HDA client.

Diagnostics:

- Ensure that you have selected the **Yes, I want to use a model** check box and tested that the OPC UA HDA server machine is connected with the machines on which you have installed Web-based Clients and Proficy Authentication. These settings are in the **Model** section in the **Proficy Historian OPC UA Server Configuration** window. For instructions, refer to [Configure the OPC UA HDA Server Settings \(on page 2416\)](#).
- Restart the OPC UA HDA Server service.

Chapter 29. The OPC UA DA Collector

Overview of the OPC UA DA Collector

The OPC UA Data Access (DA) collector gathers and collects data from a OPC UA 1.0-compliant OPC UA DA server (such as CIMPLICITY). The collector automatically determines the capability of the OPC UA DA server to which it is connected, and supports the appropriate features based on this information.

Features:

- You can browse the source for tags and their attributes on an OPC server that supports browsing.
- Both the polled and unsolicited data collection are supported; when changes to the OPC source tags are detected, they are sent to the Historian server. Unsolicited data collection is supported for OPC 2.0 only. The minimum poll interval is 100ms. The collector duplicates raw samples from the OPC server into the Historian data archive.

For unsolicited data collection, if collector compression is disabled, all new values produce an exception. And, the deadband percentage is determined by the collector deadband percent. You can only configure the collector deadband percent by enabling compression.

- The supported timestamp resolution is 1ms.
- Floating point, integer, binary, and string data are supported.
- Python expression tags are supported.
- Device timestamps are accepted.

Supported data types:

OPC UA DA Collector Data Type	Recommended Data Type in Historian
<code>OpcUaType_Null</code>	<code>ihTKVariableString</code>
<code>OpcUaType_Boolean</code>	<code>ihTKBool</code>
<code>OpcUaType_SByte</code>	<code>ihTKByte</code>
<code>OpcUaType_Byte</code>	<code>ihTKByte</code>
<code>OpcUaType_Int16</code>	<code>ihTKInteger</code>
<code>OpcUaType_UInt16</code>	<code>ihTKUInt16</code>
<code>OpcUaType_Int32</code>	<code>ihTKDoubleInteger</code>
<code>OpcUaType_UInt32</code>	<code>ihTKUInt32</code>

OPC UA DA Collector Data Type	Recommended Data Type in Historian
OpcUaType_Int64	ihTKInt64
OpcUaType_UInt64	ihTKUInt64
OpcUaType_Float	ihTKFloat
OpcUaType_Double	ihTKDoubleFloat
OpcUaType_DateTime	ihTKVariableString
OpcUaType_Guid	ihTKDataTypeUndefined
OpcUaType_StatusCode	ihTKDataTypeUndefined
OpcUaType_String	ihTKVariableString
OpcUaType_ByteString	ihTKDataTypeUndefined
OpcUaType_XmlElement	ihTKDataTypeUndefined
OpcUaType_NodeId	ihTKDataTypeUndefined
OpcUaType_ExpandedNodeId	ihTKDataTypeUndefined
OpcUaType_DiagnosticInfo	ihTKDataTypeUndefined
OpcUaType_QualifiedName	ihTKDataTypeUndefined
OpcUaType_LocalizedText	ihTKDataTypeUndefined
OpcUaType_ExtensionObject	ihTKDataTypeUndefined
OpcUaType_DataValue	ihTKDataTypeUndefined

Supported tag attributes:

- Tagname
- Source Address
- Engineering Unit Description
- Data Type
- Hi Engineering Units
- Lo Engineering Units
- Is Array Tag

The Engineering Unit Description, Hi Engineering Units and Lo Engineering Units vary based on the OPC server vendor.

**Note:**

While some of these attributes are queried on a browse, they are not shown in the browse interface. These attributes are used when adding a tag, but it is not visible to you if all attributes come from the server or not.


Configuration

Add and Configure an OPC UA Data Access Collector

The OPC UA Data Access (DA) collector gathers and collects data from a OPC UA 1.0-compliant OPC UA DA server. For more information, refer to [Configure an OPC UA DA Collector Using Historian Administrator \(on page 2432\)](#).

This topic describes how to add a collector instance using Configuration Hub. You can also [add a collector instance using the RemoteCollectorConfigurator utility \(on page 797\)](#), which does not require you to install Web-based Clients.

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**. A list of collectors in the default system appears.
3. In the upper-right corner of the main section, select .



The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

4. In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
5. In the **COLLECTOR TYPE** field, select **OPC UA DA Collector**, and then select **Get Details**.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are disabled and populated.

6. Select **Next**.

The **Source Configuration** section appears.

7. In the **OPC UA SERVER URI** field, enter the URI to connect to the OPC server in the following format:

```
opc.tcp://<host name or IP address of the OPC UA server>:<port number>
```

8. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

9. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

- a. If you need to send data to a cloud destination, select the cloud destinations as needed.

- **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
- **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
- **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

- b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

10. Select **Next**.

The **Collector Initiation** section appears. The **COLLECTOR NAME** field is populated with a value in the following format: `<Historian server name>_OPCUACollector_<number>`

11. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must contain the string `OPCUACollector`.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

12. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

13. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

14. In the **COLLECTOR SPECIFIC CONFIGURATION** section, configure values as described in the following table.


Field	Description
OPC UA Server URL	The URI to connect to the OPC UA server. Enter a value in the following format: <code>opc.tcp://<host name or IP address of the OPC UA server>:<port number></code>

Field	Description
Secured Connectivity	<p>Indicates whether you want a secured connection between the OPC UA server and the collector. By default, this field is set to false.</p> <p>You can establish a secured connectivity in one of the following ways:</p> <ul style="list-style-type: none"> ◦ Using certificates: To use certificates, switch off the User Security toggle. ◦ Using user authentication: To use user authentication, switch on the User Security toggle.
User Security	<p>This field is enabled only if you have enabled secured connectivity. Switch on this toggle if you want to use user authentication to connect to the OPC server. When you do so, the User Name and Password fields are enabled. You can either enter the user credentials in these fields, or you can use the values in the <code>ClientConfig.ini</code> file. For instructions, refer to Connect with the OPC UA DA Server Securely (on page 2434).</p>
Username	<p>This field is enabled only if you have set the secured connectivity to true and switched on the User Security toggle. Enter the username that you want to use to connect to the OPC server. If you do not provide a value, the username from the <code>ClientConfig.ini</code> file is considered.</p>
Password	<p>This field is enabled only if you have set the secured connectivity to true and selected the Enable User Security check box. Enter the password that you want to use to connect to the OPC server. If you do not provide a value, the password from the <code>ClientConfig.ini</code> file is considered.</p>
MTLS Security	<p>Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.</p>
MTLS Data Encryption	<p>Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).</p>

Field	Description
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

15. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).

16. In the upper-left corner of the page, select **Save**.



The changes to the collector instance are saved.

17. If needed, restart the collector.

If you have enabled secured connection, [establish a secured connection between the OPC server and the collector \(on page 2434\)](#).

Configure an OPC UA DA Collector Using Historian Administrator

1. Access Historian Administrator.
2. Select **Collectors**, and then select the OPC UA DA collector instance that you want to configure.
3. Select **Configuration**.

The **Configuration** section appears.

Collector: 70SP4TOLATEST_OPCUACollector

General
Configuration
Tags
Advanced
Performance
Redundancy

Collector Specific Configuration (Custom)

OPCUA Server Uri

Secured Connectivity

Enable User Security

User Name

Password

4. Enter values as specified in the following table.

Field	Description
OPCUA Server Uri	<p>The Unified Resource Identifier (URI) of the OPC UA DA server from which you want to collect data. Enter a value in the following format: <code>opc:tcp://<host name of the OPC server>:<port number></code>. By default, the local host is considered.</p> <div style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Note: The URI is a superset of the Uniform Resource Locator (URL).</p> </div>
Secured Connectivity	<p>Indicates whether you want a secured connection between the OPC server and the collector. By default, this field is set to false.</p>
Connectivity	<p>You can establish a secured connectivity in one of the following ways:</p> <ul style="list-style-type: none"> ◦ Using certificates: To use certificates, clear the Enable User Security check box. ◦ Using user authentication: To use user authentication, select the Enable User Security check box.
Enable User Security	<p>This field is enabled only if you have enabled secured connectivity. Select this check box if you want to use user authentication to connect to the OPC server. When you do so, the User Name and Password fields are enabled. You can either enter the user credentials in these fields, or you can use the values in the <code>ClientConfig.ini</code> file.</p>

Field	Description
Security	
User Name	This field appears only if you have enabled secured connectivity and selected the Enable User Security check box. Enter the username that you want to use to connect to the OPC server. If you do not provide a value, the username from the <code>ClientConfig.ini</code> file is considered.
Password	This field appears only if you have enabled secured connectivity and selected the Enable User Security check box. Enter the password that you want to use to connect to the OPC server. If you do not provide a value, the password from the <code>ClientConfig.ini</code> file is considered.

5. Select **Update**.
6. Restart the collector.
The collector is configured.

If you have enabled secured connection, [establish a secured connection between the OPC server and the collector \(on page 2434\)](#).

Add a Client Certificate to the Trusted List

If you have enabled secured connectivity between the OPC UA DA server and the collector, you must add a client certificate to the OPC UA DA server's trusted certificates list.

While [configuring the collector settings \(on page 2432\)](#), ensure that the **Secured Connectivity** field is set to true.

1. Start the OPC UA DA server in a secured mode.
2. Access the installation folder of the server. Normally, it is inside the `ProgramFiles` folder.
3. In the `Rejected` folder, copy the client certificate, and paste it into the trusted certificates folder.
To locate the trusted certificates folder, refer to your OPC UA DA server documentation.
4. Restart the collector.

Connect with the OPC UA DA Server Securely

This topic describes how to establish a secured connection between your OPC UA DA server and the collector.

All the security related configuration for OPC UA collector to establish secured connectivity to OPC UA server will be done by using ClientConfig.ini file. This file is located in C:\Program Files\GE Digital\Historian. The OPC UA DA Collector\Server64 ClientConfig.ini file has options to select Trust Certificate type, Security Policy, Security Mode, Username and Password. There are default values provided, however these can be configured accordingly.

1. Access the ClientConfig.ini file. By default, it is located at <Installation Drive> :
 \Program Files\GE Digital\Historian OPC UA DA Collector\Server64.
2. Enter values as specified in the following table.

Parameter	Description
ApplicationName	Enter OPCUACollector.
TrustCertificate	Enter one of the following values: <ul style="list-style-type: none"> ◦ 0: Enter this value if want no trust. ◦ 1: Enter this value if you want to trust temporarily. ◦ 2: Enter this value if you want to trust permanently. If you enter this value, you must copy the server certificate in the trusted certificate list of the collector.
SecurityPolicy	The security policy that you want to use. A value is required only if the value for theTrustCertificate parameter is 2. Enter one of the following values: <ul style="list-style-type: none"> ◦ 0: Does not use a security policy. ◦ 1: Uses the Basic128Rsa15 policy. This policy has theoretical problems and is not recommended. ◦ 2: Uses the Basic 256 policy. This policy has known vulnerabilities and must not be used unless absolutely necessary. ◦ 3: Uses the Aes256Sha256RsaPss policy. This policy is the more secure one. However, older versions of the OPC UA HDA clients do not support it. ◦ 4: Uses the Aes128Sha256RsaOaep policy. This policy is secure and is faster

Parameter	Description
	<p>than the most secure policies. However, older versions of the OPC UA HDA clients do not support it.</p> <ul style="list-style-type: none"> ◦ 5: Uses the Basic256Sha256 policy. This policy is acceptable and more likely to be supported by older versions of the OPC UA HDA clients.
SecurityMode	<p>The security mode that you want to use. Enter one of the following values:</p> <ul style="list-style-type: none"> ◦ 0: Enter this value if you want to allow communication without security. If you select this option, a certificate is not used for communication between the server and the collector. This option is not recommended; you can use it only in a non-production environment. ◦ 1: Enter this value if you want to allow secure communication without data privacy. If you select this option, all communication is visible, but the collector is authenticated. ◦ 2: Enter this value if you want to allow secure communication with data privacy. If you select this option, all communication is kept private, and the collector is authenticated.
CertificateTrustListLocation	Enter the path to the trusted certificates folder in the OPC server.
CertificateRevocationListLocation	Enter the path to the revoked certificates folder in the OPC server.
IssuersCertificatesLocation	Enter the path to the issuer certificates folder in the OPC server.
IssuersRevocationListLocation	Enter the path to the

Parameter	Description
ClientCertificate	
ClientPrivateKey	
RetryInitialConnect	Enter <code>true</code> or <code>false</code> to specify whether to reconnect to the OPC server automatically if the collector fails to connect to the server initially.
AutomaticReconnect	Enter <code>true</code> or <code>false</code> to specify whether to reconnect to the OPC server automatically if the collector fails to connect to the server subsequently (after the initial connection).
Username	Enter the username that you want to use to connect to the server.
Password	Enter the password that you want to use to connect to the server.

Sample ClientConfig.ini File

```

ApplicationName = OPCUACollector

TrustCertificate = 2

SecurityPolicy = 4

SecurityMode = 1

CertificateTrustListLocation =/[ApplicationPath]/pkiclient/trusted/certs/
CertificateRevocationListLocation =/[ApplicationPath]/pkiclient/trusted/crl/
IssuersCertificatesLocation =/[ApplicationPath]/pkiclient/issuers/certs/
IssuersRevocationListLocation =/[ApplicationPath]/pkiclient/issuers/crl/
ClientCertificate =/[ApplicationPath]/pkiclient/own/certs/uaclientcpp.der
ClientPrivateKey =/[ApplicationPath]/pkiclient/own/private/uaclientcpp.pem

RetryInitialConnect           =true
AutomaticReconnect           =true

Username =admin
Password =admin

```

Working with the Collector


Add Tags for the Data Store Using Configuration Hub

- [Add the collector instance \(on page 357\)](#) using which you want to collect data. Ensure that the collector is running.
- By default, the tag data is stored in the user data store, which is created automatically when you set up Configuration Hub. If, however, you want to store the data in a different data store, [create it \(on page 370\)](#).

This topic describes how to specify the tags for which you want to collect data by browsing through the tags in the data source. For example, for an iFIX collector, if there are 1,00,000 tags in the iFIX server, you must specify the ones for which you want to collect data. Only then data is collected for those tags.

In addition to adding tags from the data source, you can [create tags manually \(on page 473\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
3. Select **+**.



The **Add Tag-<system name>** page appears. The **Add Tags from Collector** option is selected by default.

4. Enter values as described in the following table.

Field	Description
COLLECTOR NAME	Select the collector instance that you want to use to collect data. A value is required.
COLLECTED TYPE	Specify whether you want to browse through all the tags in the data source or only from the tags that you have not added yet. A value is required.

Field	Description
SOURCE TAG NAME	Enter the name of the tag (either completely or partially) to narrow down the search results.
SOURCE TAG DESCRIPTION	Enter the description of the tag (either completely or partially) to narrow down the search results.

5. Select **Search Tags**.

A list of tags that match *all* the criteria that you have specified appears. If a tag is already added, it is disabled.

6. Select the check box corresponding to each tag for which you want to collect data.

Add Tags from Collector Add Manually

COLLECTOR NAME* COLLECTED TYPE* SOURCE TAG NAME SOURCE TAG DESCRIPTION

[Redacted]_Simulation All Source Tags * *

Search Tags

SEARCH RESULTS FOR SOURCE TAGS NAMES

TAG NAME	DESCRIPTION
<input type="checkbox"/>	<i>Filter</i>
<input type="checkbox"/>	<i>Filter</i>
<input type="checkbox"/>	Simulation.Simulation00001
<input type="checkbox"/>	Simulation.Simulation00002
<input type="checkbox"/>	Simulation.Simulation00003
<input type="checkbox"/>	Simulation.Simulation00004
<input type="checkbox"/>	Simulation.Simulation00005
<input type="checkbox"/>	Simulation.Simulation00006
<input type="checkbox"/>	Simulation.Simulation00007
<input type="checkbox"/>	Simulation.Simulation00008
<input type="checkbox"/>	Simulation.Simulation00009
<input type="checkbox"/>	Simulation.Simulation00010
<input type="checkbox"/>	Simulation.Simulation00011
<input type="checkbox"/>	Simulation.Simulation00012

DATASTORE*
User

7. In the **DATA STORE** field, if you want to store the data in a different data store than the user data store, select the same.


8. Select **Add Tag**.

Data collection begins for the selected tags.

As needed, configure each tag by providing values for the tag properties. For information on the delta query modes, refer to Counter Delta Queries.

Specify the Tags for Data Collection

If your OPC server supports hierarchical organization of tags in a tree structure, you can use the hierarchy to browse for tags and add them to the collector for data collection.



1. Access Historian Administrator.
2. Select **Collectors**, and then select the OPC UA DA collector instance to which you want to add tags. A hierarchical view of tags appears in the **Browse Results** section.
3. If you want to view only the tags for which data is not collected, in the **Show Only** field, select **Source Tags Not Collected**. You can search for a tag by entering search criteria in the **Source Tag Name** or **Description** field.
4. If you want to search by a tag name or description, enter the value in the **Source Tag Name** or **Description** field.
5. Navigate to the node in the tree you want to browse, and then select **Browse**.

**Tip:**

- To browse automatically, select the **Auto Browse** check box. The available tags appear in the **Browse Results** window whenever a node is selected in the tree.
- To show all child elements within a hierarchy, select the **Show All Children** check box. All tags at or below the hierarchical level of the selected node in the tree appear in the **Browse Results** window.

The tags within the selected portion of the OPC server tag hierarchy appear.

- Some OPC servers do not support data blocks with a length greater than 1. These servers display only the first item in an array instead of showing all of them. For example, an OPC server may contain 3000 analog values from datablock:1 to datablock:3000, but only datablock:1 is displayed.
 - If you want to archive data from poll records of a length greater than 1, we recommend that you use the Excel Add-In for Historian to configure a large block of tags (including the missing items), and then add the tags.
 - If you are unable to browse items containing a forward slash (/) in your OPC server, you may have to change the default separator in the collector configuration. To do so, modify the registry key `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc\iHistorian\Services\OPCCollector\<collector interface name>\OPCBrowseTreeSep` key, and change the string value to a character not available in your OPC server item IDs. Typical values include |, !, or &. Create this key if it does not exist.
 - If you are cannot browse readable items in your OPC server, you may need to change the browse access mask used by the collector. To do so, modify the registry key `[HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\OPCCollector\<collector interface name>`, and add the DWORD key `"OPCBrowseAccessRightsMask"=dword:00000003`. Valid values are 0, 1, 2, 3 with 1 being the default. Use 0 or 3 if you are unable to browse readable items. Creating or changing the value takes effect on the next browse attempt and does not require a collector restart.
 - Some items such as unsupported data types and user-defined items in simulation servers may not be returned when you browse for tags. However, sometimes, even the items that do not appear in the search results can be added using the **Add Tag Manually** button.
6. Select the tags for which you want to collect data, and then select **Add Selected Tags**. Collected tags will appear in black in the tag list.
- The tags are added to the collector. They appear in black text in the list of tags.

About OPC UA DA Collector Groups

It is a best practice to limit the number of OPC UA DA collector groups created by the Historian system to increase performance. To limit the number of OPC UA DA collector groups created on the OPC UA DA server, group Historian tags collected by the OPC UA DA collector using the fewest number of collection intervals possible.

Troubleshooting the Collector

The OPC UA DA collector generates log files during initialization, configuration, and general operation. By default, you can find them at `C:\Proficy Historian Data\LogFiles`.

Troubleshooting Tips

If the collector does not connect to the OPC server, or if tags are not displayed:

- Ensure that [the certificate is added to Trusted list \(on page 2434\)](#).
- Ensure that [you have provided a valid username and password \(on page 2432\)](#).
- Restart the collector whenever there is any change made to the configuration using Historian Administrator or in the `ClientConfig.ini` file.
- Check that secured Connectivity is true and Enable User security is checked to have connection with User Authentication.
- Ensure that the OPC server supports the security policy and the security mode if you see the following error message in the log file: Matching of secure endpoint not available between server and collector.
- Ensure that the `RetryInitialConnect` and `AutomaticReconnect` parameters are set to true in the `ClientConfig.ini` file.

Chapter 30. OSI PI Collector

Overview of the OSI PI Collector

The OSI PI collector collects data samples from an OSI PI data server and stores it in the Historian Server or a cloud destination. You can collect data directly from the OSI PI Data Archive v3.2 or later via OSI PI AOSI PI v1.3.4 or later.

Topology: This collector supports a distributed model, where the PI Data Server, the collector, and Proficy Historian are installed on different machines. The OSI PI collector must be installed on the same machine as the OSI PI Data Archive.

The OSI PI collector uses unsolicited collection, whereby changes to the OSI PI archives are detected, and are forwarded to the Historian server. The collector is intended to duplicate raw samples from the OSI PI Data Archive in an Historian data archive. You can specifically request the collector to transfer values from the OSI PI snapshot cache (as seen in the previous version of OSI PI Collectors), however, it is recommended to transfer the values directly from the PI archives to the Historian archives.

One OSI PI collector instance can collect data from a single OSI PI data archiver. To collect from multiple OSI PI data archives to an Historian archive, you must configure multiple OSI PI collector instances.

Features

- You can browse the source for tags and their attributes. Tag browsing performance with OSI PI has been confirmed as satisfactory up to 130,000 tags. Beyond that threshold, OSI PI may take a long time to return the large number of tags. In such a case, it is recommended that the tags be exported from PI to an Excel work sheet and then uploaded to Historian.
- Only the unsolicited data collection is supported; polled collection is not supported.
- The supported timestamp resolution is milliseconds or seconds.
- The collector accepts device timestamps.
- You can create Python Expression Tags for those collectors that support them.
- Floating point, integer, string, and enumerated data are supported; Binary and array data is not supported. You can configure the OSI PI collector to automatically handle updates of digital states in Historian as enumerated sets without restarting the OSI PI collector. For instructions, refer to [Configuring Auto-synchronization of Digital States \(on page 2453\)](#).

If digital states are renamed or deleted in the OSI PI collector, the corresponding enumerated sets in Historian are not automatically renamed or deleted without restarting the PI collector. Unused enumerated sets cannot be automatically deleted, because the PI server does not notify

the collector about the rename or delete activity. Therefore, you must manually [rename \(on page 2453\)](#)/[delete \(on page 2454\)](#) digital states.



Note:

In some instances, OSI PI digital tags, which are created as enumerated tags in Historian, can contain values from the PI System digital set, rather than their assigned digital set. In these instances, the System digital values will be reflected as 0 with BAD quality in Historian.

Before You Begin

Software Requirements

If you are using Historian 7.0 SP4, the following configuration is required:

- OSI PI Data Archive (version 3.2\3.3\3.4)
- OSI PI v1.3.4 or greater
- OSI PI SDK (About PI-SDK) v1.4.2 or greater



Note:

The OSI PI SDK is required for running OSI PI Collector, however, the OSI PI SDK does not ship with Historian. If the OSI PI SDK is not installed, the OSI PI Collector will not start. If you install the OSI PI Collector on a machine that does not contain your PI Server, be sure to install the OSI PI SDK on the machine with the OSI PI Collector.

- Historian 3.0 or greater

If you are using 7.0 SP5, the following configuration is required:

- OSI PI AF Server version 2015 R2 SP1 or greater
- OSI PI Data Archiver v 3.4.380 or greater
- OSI PI AF SDK 2.7.0 or greater



Note:

The OSI PI AF SDK is required for running OSI PI Collector or PI Distributor, however, the OSI PI AF SDK does not ship with Historian. If the OSI PI AF SDK is not installed, the OSI PI Collector or PI Distributor will not start. If you install the OSI PI Collector or PI Distributor on a machine that does not contain your PI Server, be sure to install the OSI PI AF SDK on



the machine with the OSI PI Collector and the PI Distributor. PI SDK is no longer supported with the 7.0 SP5 version of the PI Collector. If you are using the OSI PI Collector or PI Distributor from the 7.0 SP5 (or greater) installer, the PI AF SDK or greater is now required.

The PI AF Software Development Kit (PI AF SDK or AFSDK) is installed with the PI AF Client and provides programmatic access to PI Server data (PI Data Archive and AF).

- About-PI SDK utility

Hardware Requirements

There are no additional hardware requirements for the OSI PI Collector or PI Distributor.

Configuring the OSI PI Data Archive

By default, no specific configuration is required for the OSI PI Data Archive to allow the OSI PI Collector to collect data and archive it to the Historian Server or Predix Cloud. However, a user with read permissions must be configured in the OSI PI data server for the OSI PI Collector.



Note:

The OSI PI Collector reads data directly from the OSI PI archives and attempts to maintain a near real-time operation. It has been tested up to 25,000 events per second. However, performance is dependent on hardware and network capabilities, so if the collector begins to fall significantly behind real-time, it may be more suitable to partition the data retrieval into two or more collectors.

Upgrading and Using the PI Snapshot Collection

In some scenarios you may wish to run the collector in the same way as in the previous versions (Pre-6.0) of PI Collector. For example, you may upgrade from an older version of the collector and still want to retain the existing, original behavior.

If this is not the case then you do not need to configure anything and may skip this section.

Use the following steps where you want to retain the existing original behavior.

To configure the newly added OSI PI Collector to retrieve data from the OSI PI snapshot cache:


1. Run the Registry Editor (`regedit.exe`).
2. Navigate to `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\PICollector`.
3. In the case of a 64-bit system this may be found at `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\Services\PICollector`

4. If you have multiple collectors, each would have to be configured to allow for snapshot operation, and the key would be the name of the other collector.
5. Locate the registry key name `General15`.
6. Change it from `Archive` to `Snapshot`.
7. Restart the Historian PI Collector service from the **Windows services** control panel.

The latest log file will indicate that the collector is using the snapshot database for collection. Refer to [OSI PI Collector Troubleshooting \(on page 2455\)](#), for information about tracing operational issues with the OSI PI Collector log files.

To configure existing OSI PI Collector to retrieve data from the OSI PI snapshot cache

1. Access Historian Administrator.
2. Select the **Collectors** page.
3. Select the **OSI PI Collector**.
4. Select **Configuration**.
5. In the **Data Source** field, enter the data source as snapshot.



The screenshot shows the configuration interface for an OSI PI Collector. At the top, the collector name is displayed as `Collector: [redacted]_PICollector1`. Below this, there are several tabs: **General**, **Configuration** (which is selected and highlighted with a dashed border), **Tags**, **Advanced**, **Performance**, and **Redundancy**. The main area is titled **Collector Specific Configuration (PICollector)** and contains the following fields:

PI Server	<input type="text"/>
PI Username	<input type="text" value="piadmin"/>
PI Password	<input type="password"/>
Max Recovery Time (hr)	<input type="text" value="4"/>
Data Source	<input type="text" value="snapshot"/>

OSI PI Collector Configuration

This section describes details about how to configure an OSI PI Collector.

Configuring the OSI PI Collector

1. Start Historian Administrator.
2. Select the **Collectors** page.

3. Select the OSI PI Collector instance you wish to configure.
4. If the collector is not listed in the available collectors list, you must start the collectors manually from the Windows Service Control Panel to register it.
 - a. Open the Windows services control panel on the machine that contains the OSI PI collector
 - b. Find the service name Historian OSI PI Collector.
 - c. Select it and select **Start** on the top of the **Services** panel.
As it is not configured it may start and then promptly stop- this is not an issue. The current step is solely to register it in Historian.
 - d. Continue from Step 1 if is not listed in Historian Administrator once restarted, refer to [OSI PI Collector Troubleshooting \(on page 2455\)](#).
5. Configure the OSI PI Collector's **General** options.
 - a. (Optional) Enter a description for your OSI PI Collector.
 - b. (Optional) In the **Computer Name** field, enter the host name of the computer your collector is running on.
 - c. (Optional) If you want to change the default settings for memory usage and free disk space, change the values in the **Memory Buffer Size** and **Minimum Free Space** fields.
6. Configure the OSI PI Collector-specific options.
 - a. Select **Configuration**.
 - b. In the **PI Server** field, enter the OSI PI server name. For example, `localhost`.
 - c. In the `PI User name` field, enter the OSI PI user name. For example, `PiAdmin`.
 - d. If required, enter the OSI PI password into the **PI Password** field.
This field can be left blank if no password is assigned for the OSI PI user.

**Note:**

If you change the PI Server name, user name or password fields, you must restart the collector service before the new configuration will take effect.

**Note:**

If the username and password are provided with the PI Collector, it uses explicit login to connect to the PI Server. If the username and password are not provided,



then we use the implicit login functionality of PI SDK. In this scenario, either it would look for PI Trust or PI Mapping to connect to the PI Server.

- e. In the **Max Recovery Time (hr)** field, enter a new Maximum Recovery Time. By default, the maximum recovery time is 4 hours.
7. Configure the default collection options.
 - a. Select **Tags**.
 - b. Enter a prefix to add to OSI PI Tags in Historian, for example: `PI_`.
 - c. Enter a value for the `Collection Interval`.

The default collection interval is 1 second. Note that polled collection is not supported.
 8. Configure the collector's advanced settings.
 - a. To delay collection when the collector starts up, enter a value into the **Delay Collection at Startup (sec)** field.

OSI PI Collector-specific Field Descriptions

The following figure shows the OSI PI Collector configured to collect data from an OSI PI archive on `localhost`, logging in as the `piadmin` user. It is also configured for a maximum recovery time of 4 hours.

Collector Specific Configuration (PICollector)

PI Server

PI Username

PI Password

Max Recovery Time (hr)

The following table describes the OSI PI Collector-specific configuration fields.

This field...	Indicates...
PI Server	The name of the computer that OSI PI is running on. This should match the server entry in the OSIsoft About PI-SDK utility.
PI Username	The user name required to connect to the OSI PI Data Archive. PI trusts are not supported and an explicit PI user must be set.
PI Password	The password required to authenticate with the OSI PI Data Archive. If no password is configured for the OSI PI user, this field can be left blank.
MaxRecovery Time (hr)	The Maximum Recovery time in hours.

Tag Attributes Available in Browse

You can specify tags for collection in Historian Administrator for the OSI PI Collector or OSI PI Distributor by browsing or by adding tags manually. The following table outlines the tag attributes available when browsing:

Historian Tag Browse Attribute	OSI PI Tag Attribute
Browse Source Address	Tag
Description Property	Descriptor
Engineering Unit Description	Engunits
Hi Engineering Units	Zero+span
Lo Engineering Units	Zero

When entering tags manually, it is important to match the Historian tag data type with the data type of the OSI PI tag. See [OSI PI Collector and Distributor Supported Data Types \(on page 2451\)](#).

Regardless of how you add tags to Historian, you should match the timestamp resolution. If your OSI PI tag is using timestamps with milliseconds, then configure your Historian tag to store timestamps with millisecond resolution as well.

The OSI PI distributor reads data from the Historian tag displayed in the **Tag Source Address** field, and sends it to the OSI PI tag name displayed in the **Spare 1** field. To control the source and destination tags, change the **Tag Source Address** and **Spare 1** fields.

Configuring Recovery Mode

Recovery logic is activated when the OSI PI Collector and OSI PI Data Archive reestablish a connection after a connection loss, or when the OSI PI Collector is started. The OSI PI Collector will attempt to recover all data samples between the current time and the last known write time, up to a maximum number of hours configured for the collector. Continuous collection resumes only after the previous data has been recovered.

The default recovery time available is 4 hours. You can disable recovery mode by setting the **Maximum Recovery Time** to 0 hours.

To configure a maximum recovery time:

1. Start Historian Administrator.
2. Access the **Collectors** page.
3. Select **OSI PI Collector**.
4. Select **Configuration**.
5. In the **Maximum Recovery Time (hr)** field, enter a Maximum Recovery Time, in hours. If this field is left blank, the Maximum Recovery Time will be set to 4 hours.

OSI PI Collector and Distributor Supported Data Types

The following table maps OSI PI data types to their Historian data type equivalents:

OSI PI Tag Types	Recommended Historian Data Type
INT32	Single Integer, Double Integer
FLOAT16, FLOAT32	Float
FLOAT64	Double Float
PISTRING	Variable String
DIGITAL	Single Integer The accompanying digital states are transferred from OSI PI into Historian upon initialization of the collector.

Data Quality Mapping

Data quality mapping from Historian to OSI PI Data Archive is restricted to `good/bad`. OSI PI's subtypes are not currently mapped by Historian.

OSI PI Collector - Notes

Time Stamps Not Modified by Historian

The Historian OSI PI collector does not modify the time stamps placed on data samples by the OSI PI Data Archive. As a result, if your system clocks are not synchronized on both your OSI PI Data Archive server and Historian server, it is possible that Historian may receive data samples in the future or in the past.

PITimestamp Data Type not Supported

The `PITimestamp` data type is not supported by the OSI PI Collector. If you attempt to collect a tag with the `PITimestamp` data type, an error will be logged and the value will not be collected.

PI Digital States/Enumerations

Upon manual startup of the OSI PI collector (that is, a restart via the services control panel), the PI Digital States are imported into Historian. When enumeration tags are subsequently configured (digital tags in OSI PI), the matching enumeration is set as well and data will then be matched against the enumeration.

For a PI digital tag, we create a Historian enumerated tag and for a PI digital set. If the PI tag contains values from its enumerated set, then its values are written correctly in the Historian tag. But, in some special cases, the PI tag may contain values from a special set (System set). Historian does not support these values as we cannot assign two enumerated sets to one tag. In these cases, the values are written as `0- Bad quality`.



Note:

To update the enumerations, see [Configuring Auto-synchronization of Digital States \(on page 2453\)](#).

Connecting to an OSI PI Collective

The Historian PI Collector has the ability to connect to an OSI PI Collective (PI redundancy). This allows data to be moved to Historian to prevent data loss.

Starting and Stopping the OSI PI Collector

The OSI PI Collector runs as a Windows service and can be controlled through the **Services** control panel. You must have Administrator rights to access the **Services** control panel.

To Modify the OSI PI Collector Service:

1. Select **Start > Settings > Control Panel**.
2. Double-click the **Administrative Tools** control panel to open it.
3. Double-click the **Services** control panel to open it.
4. Double-click the **Historian PI Collector** service.
5. To configure the Historian PI Collector service to start when Windows starts, set the **Startup Type** to **Automatic**.

To configure the Historian PI Collector service to start manually, set the **Startup Type** to **Manual**.

- To start the service, select the **Start** button. To stop the service, select the **Stop** button. Other options are available in the **Services** control panel. For more information, refer to *Windows* documentation.

Configuring Auto-synchronization of Digital States

Auto-synchronization with the `SynchInterval` Registry Key

The Historian OSI PI Collector allows transferring digital sets from the PI Server to Historian as enumerated sets. The digital sets from the PI Server are transferred to Historian not only during collector startup but also with the frequency of the Synch Interval.

Auto-synchronization of digital states can be configured with the `SynchInterval` Registry Key. The frequency at which the OSI PI Collector fetches the digital set from the PI server to Historian is determined by the value configured for this key, which is specified in minutes.

Values for the `SynchInterval` Registry Key

The default value of this key is `0`, which indicates there is no synchronization of the digital set.

Set this registry key to a value greater than `0` if you want the OSI PI Collector to automatically fetch the digital set from the PI Server to Historian.

For example, the OSI PI Collector fetches the digital set from the PI server to Historian every 10 minutes if the value configured in this key is `10`.



Note:

- The collector must be restarted to apply the change in the value of this registry key.
- This key is available for all Historian Collectors, but it is functional only in the OSI PI Collector.
- Digital sets from the PI Server are transferred to Historian only during collector startup.

Renaming Digital States

If digital states are renamed in the PI Collector, the corresponding enumerated sets in Historian are not automatically renamed without a restart of the PI collector. Unused enumerated sets cannot be automatically deleted, because the PI Server does not notify the PI collector about rename activity.

When a digital state is renamed, a new enumerated set is created. There will therefore be two enumerated sets for the same digital set, one of which has the old name and one of which has the new name. The old enumerated set is redundant as it will not get any data if no tag is assigned to it. The tag association is also lost.

To address this:

- Manually assign the new enumerated set to the applicable tag in Historian. It will then be synchronized to represent the data for the renamed digital state.
- Go to the Historian VB admin and delete the unused enumerated set at the Historian side.

For example, consider the following situation, where `PHSite1.PumpStatus` in Historian is assigned to `Tag1`:

PI Server	Historian
<code>Site1.PumpStatus</code>	<code>PHSite1.PumpStatus</code>
<code>ON= 0</code>	<code>OFF= 0</code>
<code>OFF= 1</code>	<code>ON= 1</code>

If the digital state `Site1.PumpStatus` is renamed to `SiteLodha.PumpStatus`, a new enumerated set `PHSiteLodha.PumpStatus` is created at the Historian side.

The old enumerated set on the Historian side `PHSite1.PumpStatus` will not show any data, but it will exist redundantly inside **Historian**.

To address this:

- Manually assign `Tag1` (applicable tag in Historian) to `PHSiteLodha.PumpStatus`.
- Go to the **Historian** VB admin and manually delete the old enumerated `PHSite1.Pump Status`.

Deleting Digital States

If digital states are deleted in the PI Collector, the corresponding enumerated sets in Historian are not automatically deleted without a restart of the PI collector. Unused enumerated sets cannot be automatically deleted, because the PI server does not notify the PI collector about delete activity.

To address this:

- Go to Historian Administrator and delete the unused enumerated set at the Historian side.

For example, consider the following situation, where `PHSite1.PumpStatus` in Historian is assigned to `Tag1`:

PI Server	Historian
Site1.PumpStatus	PHSite1.PumpStatus
ON= 0	OFF= 0
OFF= 1	ON= 1

If the digital state `Site1.PumpStatus` is deleted, then the enumerated set `PHSite1.PumpStatus` remains at the Historian side.

To address this:

- Go to Historian Administrator and delete the `PHSite1.PumpStatus` enumerated set, on the Historian side.

OSI PI Collector Troubleshooting

Tracing Operational Issues with OSI PI Collector Log Files

The OSI PI Collector generates logs during initialization, configuration, and general operation. These can be found in the general logging folder ([Historian Data folder]\LogFiles). Log files for the OSI PI Collector begin with `PICollector` and have a sequence number for each collector restart.

The first response to an issue should be an examination of the latest log file, as it will contain details on:

1. Configuration of the collector.
2. Initialization and connection to the OSI PI server.
3. Addition and removal of tags.
4. Reconnection and recovery of data.

OSI PI tags cannot be browsed, collector logs indicate SDK connection issues

The OSI PI server used must be an entry in the About-PI SDK utility. If there is an issue with collecting tag information and/or enumeration information, please confirm that the OSI PI server that is set in the collector configuration has an entry in the About PI-SDK, and that it is accessible from the About PI-SDK utility.

OSI PI Collector overrun problems - missing blocks of values, or is missing values

If the OSI PI Collector is unable to maintain updates from the OSI PI archiver and therefore is missing values, you may experience overrun problems. An overrun occurs when the data source is changing tag values faster than the collector collecting values, which causes it to consistently remain behind the

archiver updates. If this is the case then the collector is running against the hardware and/or network limits and you may consider partitioning the tags into two or more sets, each with independent collectors.

Startup issue when data source is Snapshot

Historian OSI PI Collector fails to start as a service when you enter Snapshot as the **Data Source** in the **Configuration** section of the collector.

To start the collector:

1. Open command prompt as Administrator.
2. Navigate to the location where Historian installed.
3. Navigate to the path `Program Files (x86)\GE Digital\Historian OSI Pi Collector\Server`
4. Enter the following command:

```
ihPiCollector.exe noservice
```

The Collector starts from the CLI interface.

Chapter 31. OSI PI Distributor

OSI PI Distributor

Overview of the OSI PI Distributor

The Historian OSI PI Distributor gathers data from Historian, and writes it to an OSI PI data server. Data can be written directly to the OSI PI Data Archive v3.2 or greater, via the OSI PI v 1.3.4 or greater. Typically, the distributor is installed on the Historian server, distributing data to a remote OSI PI Data archive.

The OSI PI Distributor uses unsolicited distribution, whereby changes in Historian tags values are detected, and are forwarded to a remote OSI PI data server. The distributor is intended to duplicate data from an Historian archive to an OSI PI data archive.

One OSI PI Distributor can distribute data to a single OSI PI data archive. To distribute to multiple OSI PI archives from an Historian archive, you need to configure multiple OSI PI distributors. You can also configure multiple OSI PI distributors to a single OSI PI data archive.

**Note:**

The OSI PI Distributor can only write data to PI Archive. It cannot write data to PI Snapshot.

OSI PI Distributor Features

Feature	Capability
Browse Source For Tags	Yes
Browse Source For Tag Attributes	Yes
Polled Collection	No
Minimum Poll Interval	N/A
Unsolicited Collection	Yes
Time stamp Resolution	milliseconds or seconds
Accept Device Time stamps	Yes
Floating Point Data	Yes
Integer Data	Yes

Feature	Capability
String Data	Yes
Binary Data	No
Array Data	No
Collector Status Outputs	Yes

Getting Started

Before you begin using the OSI PI Distributor, you should read the [System Requirements \(on page 2458\)](#) and [About Configuring OSI PI Data Archiver for OSI PI Distributor \(on page 2458\)](#) topics.

System Requirements

The following software is required to use the PI Distributor:

- OSI PI Data Archive v 3.2 or greater
- OSI PI v 1.3.4 or greater
- Historian 3.0 or greater

About Configuring OSI PI Data Archiver for OSI PI Distributor

In order for the OSI PI Distributor to write data to the OSI PI data archiver, make the following configuration changes to the OSI PI data server:

- Before using the OSI PI Distributor, you must create writable tags in the OSI PI data archive.
- In order for the OSI PI Distributor to write data to a OSI PI data archive, the destination tags must first be given write access in OSI PI. Consult your OSI PI documentation for more details.
- The OSI PI user must have write privileges.

In addition to making the destination OSI PI data tags writable, you must also ensure that the OSI PI user the OSI PI Distributor is logging into the OSI PI data server has write access to the OSI PI data archive. If PI Trust or PI Mapping security is used, the corresponding PI users/Identities/Groups must also have write access to the OSI PI data archive. Consult your OSI PI documentation for more details.

Configuring Multiple OSI PI Distributors to use Registry Keys



Note:

This procedure is for advanced Windows users only. If you are not familiar with Windows Registry editing, contact your Network Administrator for assistance.

To configure Multiple OSI PI Distributors to use Registry Keys

1. From a command prompt, run the Registry Editor (`regedit.exe`).
2. Navigate to `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\PIDistributor` 3.
3. Create a new key and give it a unique name. For example, `AlbPI01`.
4. Edit the new registry key and add a string value named `InterfaceName`.
5. In the `InterfaceName` value, enter a name for the OSI PI Server's interface.
The string *"OSI PI"* is reserved, and should not be used.
6. Add a second string value to the new key named `Historian NodeName`.
7. In the `Historian NodeName` value, enter the name of the Historian archive server to which the new distributor will be sending data.
8. Close the Registry Editor.
9. Open a command window.
10. From the command prompt, run the OSI PI Distributor and command it to use the new registry key, with the `-multiple` and `REG=` parameters.

For example, if you named the registry key `AlbPI01`, you would use the following command:

```
iHPIDistributor.exe -multiple REG=AlbPI01
```



Note:

On a 64-bit Windows Operating System, all 32-bit components (such as collectors, Client Tools, and APIs) related registry keys will be located here:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intellution, Inc.\iHistorian\
```

OSI PI Distributor Configuration

Configuring an OSI PI Distributor

To configure an OSI PI Distributor:

1. Start Historian Administrator.
2. Select the **Collectors** page.
3. Select the OSI PI Distributor you want to configure.
4. Configure the OSI PI Distributor's **General** options.
 - a. Enter a description for your OSI PI Distributor.
 - b. In the **Computer Name** field, enter the hostname of the computer your distributor is running on, for example, `localhost`.
 - c. If you wish to set limits on memory usage and free disk space, change the values in the **Memory Buffer Size** and **Minimum Free Space** fields.
5. Configure the OSI PI Distributor-specific options:
 - a. Select **Configuration**.
 - b. In the **PI Server** field, enter the name of the machine where the OSI PI server is running. For example, `localhost`.
 - c. In the **PI Username** field, enter the OSI PI user name. For example, `PIAdmin`.
 - d. Enter the OSI PI password into the **OSI PI Password** field. The password is required to authenticate the OSI PI Data Archive.
If no password is configured for the OSI PI user, this field can be left blank. Passwords are case-sensitive.
 - e. In the **Max Recovery Time (hr)** field, enter a new maximum recovery time, in hours.
Recovery logic is activated when the OSI PI Distributor and Historian re-establish a connection after a connection loss, or when the distributor is restarted. The OSI PI Distributor will attempt to recover all data samples between the current time and the last known write time, up to a maximum number of hours configured for the distributor. New distribution resumes only after the previous data has been recovered.

The default recovery time available is 4 hours. You can disable recovery mode by setting the **Maximum Recovery Time** to 0 hours.
6. Configure the default distribution options.
 - a. Select **Tags**.
 - b. Enter a prefix to add to OSI PI tags in Historian. For example, `PI_`
 - c. Enter a value for the Collection Interval. The default collection interval is 1 second.
7. Configure the distributor's advanced settings.
To delay distribution when the distributor starts up, enter a value into the **Delay Collection at Startup (sec)** field.

Tag Attributes Available in Browse

You can specify tags for collection in Historian Administrator for the OSI PI Collector or OSI PI Distributor by browsing or by adding tags manually. The following table outlines the tag attributes available when browsing:

Historian Tag Browse Attribute	OSI PI Tag Attribute
Browse Source Address	Tag
Description Property	Descriptor
Engineering Unit Description	Engunits
Hi Engineering Units	Zero+span
Lo Engineering Units	Zero

When entering tags manually, it is important to match the Historian tag data type with the data type of the OSI PI tag. See [OSI PI Collector and Distributor Supported Data Types \(on page 2451\)](#).

Regardless of how you add tags to Historian, you should match the timestamp resolution. If your OSI PI tag is using timestamps with milliseconds, then configure your Historian tag to store timestamps with millisecond resolution as well.

The OSI PI distributor reads data from the Historian tag displayed in the **Tag Source Address** field, and sends it to the OSI PI tag name displayed in the **Spare 1** field. To control the source and destination tags, change the **Tag Source Address** and **Spare 1** fields.

OSI PI Collector and Distributor Supported Data Types

The following table maps OSI PI data types to their Historian data type equivalents:

OSI PI Tag Types	Recommended Historian Data Type
INT32	Single Integer, Double Integer
FLOAT16, FLOAT32	Float
FLOAT64	Double Float
PISTRING	Variable String

OSI PI Tag Types	Recommended Historian Data Type
DIGITAL	<p data-bbox="381 325 560 352">Single Integer</p> <p data-bbox="381 394 1398 466">The accompanying digital states are transferred from OSI PI into Historian upon initialization of the collector.</p>

Data Quality Mapping

Data quality mapping from Historian to OSI PI Data Archive is restricted to `good/bad`. OSI PI's subtypes are not currently mapped by Historian.

Starting and Stopping the OSI PI Distributor Service

The OSI PI Distributor runs as a Windows service and can be controlled through the **Services** control panel. You must have Administrator rights to access the **Services** control panel.

To start/stop the OSI PI Distributor service

1. Select **Start > Settings > Control Panel**.
2. Double-click the **Administrative Tools** control panel to open it.
3. Double-click the **Services** control panel to open it
4. Double-click the **Historian PI Distributor** service.
5. To configure the Historian PI Collector service to start when Windows starts, set the **Startup Type** to **Automatic**.
To configure the Historian PI Distributor service to start manually, set the **Startup Type** to **Manual**.
6. To start the service, select the **Start** button. To stop the service, select the **Stop** button.
The other options are available in the **Services** control panel. For more information, refer to *Windows* documentation.

Chapter 32. The Python Collector

Overview of the Python Collector

Using the Python collector, you can execute Python scripts and store the resulting values in Historian tags. You can retrieve this data from the Historian archive, perform the calculations written in Python script, and store the resulting values in new Historian tags. Also, you can run multiple Python scripts simultaneously.



Note:

You can use the Python Collector either Configuration Hub or Historian Administrator. However, for a seamless usage and experience, it is recommended to use the Python collector in Configuration Hub.

Features:

- You can perform data calculations on values that are already in the archiver.
- You can run the Python-based scripts to compute values.
- You can retrieve the resulting values stored in Historian using any of the Historian clients.
- You can run multiple Python scripts at the same time.
- You can verify a Python script and check for errors before executing it.
- The supported timestamp resolution is 1ms.
- Each tag can have its own Python script stored under the tag source address. The computed value for the `Result` variable within the Python script is stored in the associated Python tag.
- Both the polled and unsolicited data collection are supported.
- Integer, string and other data types are supported. For more information, refer to [Supported Data Types \(on page 2464\)](#).
- The collector accepts device timestamps.
- The collector reads data and tags.

Limitations:

- Historian tags used in the `CurrentValue` function cannot contain % in the tag name. For example, `CurrentValue('Simulation.Sin_1%Noise')` will result in an error. Therefore, before using a tag in a Python script, rename it so that it does not contain %.

Supported Data Types

The Python collector supports integer, string, and other data types. This topic lists all the data types that are supported by the Python collector.

Data Type	Data Type in Python Collector
int, long	Single Integer, Double Integer
float	Single Float, Double Float
bool	boolean
Byte	Byte
str	Variable String
Sequence types: list, tuple	Array of numeric type or strings
Mapping data type: dictionary	Multifield (user defined types)

Install the Python Collector

1. Install [the Historian server \(on page 104\)](#) and [collectors \(on page 142\)](#).
2. Install Python 3.8 on the same machine on which you have installed collectors.

1. Add the following entries to update the Python collector's registry:

- In the following location, include the path to the Python install lib folder:

```
Computer\HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\GE Digital\iHistorian
\CollectorServiceExtensions\PythonExpressions\PythonPath
```

- In addition, add the path to the Python 3.8 lib folder or any custom modules to Python path. This path can also include location of any custom modules or functions (global functions or variables to be used from within the python tag calculation/script).

Examples:

```
C:\Program Files (x86)\GE Digital\Historian Python Expressions\Python38\lib
```

```
C:\Program Files (x86)\GE Digital\Historian Python Expressions\Python38\user
```

```
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\Lib
```

```
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\Lib\site-packages
```

```
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\DLLs
```

You can also configure Python library path using Configuration Hub. For more information, refer to [Configure Python Library path using Configuration Hub](#).

- Update any default modules to be used for python tags to key:

```
DefaultModuleImports
```

Add a Python Collector Instance, either using [Configuration Hub \(on page 556\)](#) or [RemoteCollectorConfigurator \(on page 2467\)](#).


Adding a Python Collector Instance

Add a Python Collector Instance using Configuration Hub

- [Install Python Collector \(on page 2464\)](#).

This topic describes how to add a Python collector instance using Configuration hub.

- [Access Configuration Hub \(on page 336\)](#).
- In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Collectors**.
A list of collectors in the default system appears.
- In the upper-right corner of the main section, select .



The screenshot shows the 'Historian Collectors' interface. At the top, it says 'Offline Configuration Collectors'. On the right, it indicates 'Refreshed on 12/11/2023, 2:54:00 PM' with a refresh icon and a plus icon. Below this is a table with columns for Collector Name, Status, Configuration, Machine, and Version. Each column has a 'Filter' option. The table contains two rows of data:

COLLECTOR NAME	STATUS	CONFIGURATION	MACHINE	VERSION
Simulation	● Running	Historian		
PythonCollector	● Running	Historian		

The **Add Collector Instance: <system name>** window appears, displaying the **Collector Selection** section. The **MACHINE NAME** field contains a list of machines on which you have installed collectors.

- In the **MACHINE NAME** field, select the machine in which you want to add a collector instance.
- In the **COLLECTOR TYPE** field, select **Python Collector**, and then select **Get Details**.

**Note:**

The **INSTALLATION DRIVE** and **BASE DATA DIRECTORY** fields cannot be changed. This is the drive location and the data directory folder that you provided during Collectors installation.

The **INSTALLATION DRIVE** and **DATA DIRECTORY** fields are populated with the drive location and the data directory folder.

6. Select **Next**.

The **Destination Configuration** section appears. The collector machine name provided by you is selected as the **Source Configuration** by default.

Under **CHOOSE DESTINATION**, the **Historian Server** option is selected by default. In addition, the **DESTINATION HISTORIAN SERVER** field is disabled and populated with the collector machine name.

7. Select the destination to which you want to send data, and then enter the values in the corresponding fields. You can send data to an on-premises Historian server or to a cloud destination.

a. If you need to send data to a cloud destination, select the cloud destinations as needed.

- **Predix Timeseries**- Select this if you need to send data to Predix cloud. For more information, refer to [Predix Cloud \(on page 621\)](#).
- **Azure IoT Hub**- Select this if you need to send data to Azure Cloud in KairosDB format. For more information, refer to [Azure IoT Hub \(KairosDB format\) \(on page 608\)](#).
- **MQTT**- Select this if you need to send data to any of the following cloud destination.
 - Alibaba cloud. For more information, refer to [Alibaba Cloud \(on page 587\)](#).
 - AWS cloud. For more information, refer to [AWS Cloud \(on page 594\)](#).
 - Google cloud. For more information, refer to [Google Cloud \(on page 614\)](#).

b. If you need to send data to an on-premises Historian server, select **Historian Server**.

If you created security groups or enabled a strict client/collector authentication, enter the **USERNAME** and **PASSWORD** of the on-premises Historian server that you created during the installation of the collector.

If you entered the **USERNAME** and **PASSWORD**, select **Test Connection**. This will help you to test if the Historian server that you are trying to connect is valid or if the credentials that you entered are valid.

If the entered credentials are valid, a successful connection message appears.

8. After you selected the destination, select **Next**.

The **Collector Initiation** section appears.

9. If needed, modify the value in the **COLLECTOR NAME** field.

The value that you enter:

- Must be unique.
- Must not exceed 15 characters.
- Must not contain a space.
- Must not contain special characters except a hyphen, period, and an underscore.

10. In the **RUNNING MODE** field, select one of the following options.

- **Service - Local System Account:** Select this option if you want to run the collector as a Windows service using the credentials of the local user (that is, the currently logged-in user). If you select this option, the **USERNAME** and **PASSWORD** fields are disabled.
- **Service Under Specific User Account:** Select this option if you want to run the collector as a Windows service using a specific user account. If you select this option, you must enter values in the **USERNAME** and **PASSWORD** fields.

If you have enabled the **Enforce Strict Collector Authentication** option in Historian Administrator, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

You can also configure the collector to start automatically when you start the computer.

11. Select **Add**.

The collector instance is added. The fields specific to the collector section appear in the **DETAILS** section.

[Specify the tags \(on page 357\)](#) whose data you want to collect using the collector.

Add a Python Collector Instance using RemoteCollectorConfigurator

- [Install Python Collector \(on page 2464\)](#).
- If the destination of a collector is an Azure IoT Hub device, ensure that the device is running.

Before you begin using a collector, you must add an instance of the collector. You can add multiple instances of the same collector or instances of multiple collectors where you have installed the collectors.

This topic describes how to add a collector instance using the RemoteCollectorConfigurator utility. If you want to add an offline collector instance, refer to [Add an Offline Collector Instance \(on page 819\)](#).

1. If you want to use an interactive UI:

- a. Run the RemoteCollectorConfigurator.exe file. By default, it is located in the following folder: C:\Program Files\GE Digital\NonWebCollectorInstantiationTool.
A list of options to manage collector instances appears.
- b. Connect to the collector machine by entering 1 or 2, depending on whether collectors are installed locally or on a remote machine.
- c. Enter 4.
You are prompted to choose between entering the installation parameters manually and providing a JSON file.
- d. If you want to manually enter the parameters and values, enter 1, and then run the following command:

```
{ "<parameter>": "<value>", "<parameter>": "<value>" }
```

If you want to use a JSON file containing the installation parameters and values, enter 2, and then enter the path to the JSON file that you have created. Instead of manually creating the JSON file, you can use the RemoteCollectorConfigurator utility to [generate it automatically \(on page 796\)](#).

You can leave the Historian username and password blank if there are no Historian security user groups.

2. If you want to use the Command Prompt window:

- a. Access the installation folder of the RemoteCollectorConfigurator utility. By default, it is C:\Program Files\GE Digital\NonWebCollectorInstantiationTool.
- b. Run Command Prompt in this location.
- c. If you want to manually enter the installation parameters and values, run the following command:

```
RemoteCollectorConfigurator.exe "<Destination Historian>" "<Destination Historian username>"  
"<Destination Historian password>" InterfaceCreateViaCmd "{ \"<parameter>\": \"<value>\",  
\"<parameter>\": \"<value>\" }
```

If you want to use a JSON file containing the installation parameters and values, run the following command:

```
RemoteCollectorConfigurator.exe "<Destination Historian>" "<Destination Historian username>"
"<Destination Historian password>" InterfaceCreateViaFile "<path to the JSON file>"
```

Instead of manually creating the JSON file, you can use the RemoteCollectorConfigurator utility to [generate it automatically \(on page 796\)](#).

If ih security groups are available, you must enter the Windows username and password of the destination Historian. If you have enabled the **Enforce Strict Collector Authentication** option, you must provide the credentials of a user who is added to at least one of the following security groups:

- iH Security Admins
- iH Collector Admins
- iH Tag Admins

For information on the parameters, refer to [Collector Instance Parameters \(on page 801\)](#).

Sample JSON file

```
{
  "CollectorSystemName": "TESTSYSTEM",
  "DestinationHistorian": "TESTSYSTEM",
  "General1": "10",
  "General2": "4",
  "General3": "",
  "General4": "",
  "General5": "",
  "InterfaceDescription": "Sample Python Collector",
  "InterfaceName": "SamplePythonCollector",
  "InterfaceSubType": "Python",
  "Type": "8",
  "DataPathDirectory": "C:\\\\Proficy Historian Data",
  "CollectorDestination": "Historian",
  "DestinationHistorianUserName": "",
  "DestinationHistorianPassword": "",
  "Mode": "1",
  "WinUserName": "",
  "WinPassword": ""
}
```

```
}

```

The collector instance is added.

- [Specify the tags \(on page 357\)](#) whose data you want to collect using the collector.
- If you did not enter a value, modify the offline configuration file of the collector. By default, this file is available in the following location: `<installation folder of Historian>\GE Digital\<collector name>`. For information, refer to [Creating Offline Configuration XML file \(on page 2040\)](#).

Configuring the Python Collector

Configure the Python Collector using Configuration Hub

Before you begin, [install the Python collector \(on page 2464\)](#) and [add an instance \(on page 556\)](#) of the collector.

1. [Access Configuration Hub \(on page 336\)](#).
2. Select **Collectors**, and then select the Python Collector instance that you want to configure. The fields specific to the collector instance appear in the **DETAILS** section.
3. In the **COLLECTOR SPECIFIC CONFIGURATION** section, enter values as specified in the following table.


Field	Description
Calculation Timeout (sec)	This is not supported for the Python collector.
Max Recovery Time (hr)	The maximum time, in hours till now, that the collector will attempt to restore data. This is applicable only to event-based tags. The default value is 4 hours. If you want to disable automatic calculation of the tag, set the value of this field to 0.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).

Field	Description
	For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .

- As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).
- Restart the collector.
The collector instance is configured.

Configure the Python Collector using Historian Administrator

- Access [Historian Administrator \(on page 823\)](#).
- Select **Collectors**, and then select the Python Collector instance that you want to configure.



- In right-side, below the **Collector: <Name of the Collector Instance>**, select **Configuration**.
The fields specific to the collector instance appear.
- Enter values as specified in the following table.


Field	Description
Calculation Timeout (sec)	This is not supported for the Python collector.
Max Recovery Time (hr)	<p>The maximum time, in hours till now, that the collector will attempt to restore data. This is applicable only to event-based tags. The default value is 4 hours.</p> <p>If you want to disable automatic calculation of the tag, set the value of this field to 0.</p>

5. Select **Update**.

Configure Python Library Path using Configuration Hub

If you want to configure additional paths for Python library or if you want to include paths that contain additional, custom or third-party modules, you can add those path to the registry using Configuration Hub. This topic describes how to configure additional Python Library path using Configuration Hub.

1. [Access Configuration Hub \(on page 336\)](#).
2. Select **Collectors**, and then select the Python Collector instance that you want to configure. The fields specific to the collector instance appear in the **DETAILS** section.
3. In the **INSTANCE CONFIGURATION** section, select . The **Update Python Library Path** window appears.



4. In **PYTHON LIBRARY PATH** enter the library path(s) as needed.

 **Note:**

While entering multiple paths, ensure to separate the library paths using semicolons.

For example,

```
C:\Program Files (x86)\GE Digital\Historian Python Expressions38\Python38\lib;
C:\Program Files (x86)\GE Digital\Historian Python Expressions38\Python38\user;
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\Lib;
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\Lib\site-packages;
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\DLLs;
```

5. Select **Apply**
The library paths are added to the registry.
6. For the changes to take effect, restart the collector instance.

Using the Python Collector

Write Data to an Arbitrary Tag

You can write data to an arbitrary tag in the Historian archive through the `Historian.AddData` function. This function is used in a python script to write values, time stamps and qualities of one or more tags to the Historian archive.

Use the following syntax to write data to an arbitrary tag:

```
Historian.AddData(TagNames, Values, Timestamps, Qualities)
```

The following table provides information on the parameters.

Parameter	Description
TagNames	Identifies the names of the tags. A value is required, and must exist in the archive to which you want to send the tag data. You can provide a single tag name or an array of tag names, enclosed in double quotation marks.
Values	Identifies the values of the tags. A value is required, and must be a single value or an array of values, depending on whether the tag name is a single name or an array. Values must be enclosed in double quotation marks. You can enter only a single value for each tag name.
TimeStamps	Identifies the timestamp of the tag data. Enter an absolute time value, enclosed in double quotation marks. All times are provided as string in standard ISO 8601 format.
Qualities	Identifies the quality of the tag data. Enter an integer from 0 to 100, with 0 indicating bad quality and 100 indicating good quality.

Example of using AddData Function

```
from datetime import datetime
tags = ["TestTag1", "TestTag2", "TestTag3"]
values = ["111", "222", "333"]
datetime_str = Historian.CurrentTime()
datetime_object = datetime.strptime(datetime_str, '%m/%d/%y %H:%M:%S.%f')
```

```
times = [datetime_object.isoformat(),datetime_object.isoformat(), datetime_object.isoformat()]
Historian.AddData(tags, values,times, "")
Result=1
```

Create Triggers

About Calculation Triggers

You can create the following types of triggers for a calculation:

- **Polled or scheduled:** Used to trigger a calculation based on a scheduled time interval. For example, you can calculate the average value of tag data collected every hour.

The polled type trigger functions the same as the other collectors. Although Historian internally optimizes calculation execution times, the data for polled tags is timestamped on the data collection interval. For example, if the calculation engine is unable to process the polled triggers as scheduled, the calculations will be executed later, but with data interpolated back to the scheduled time. If there are too many triggers to be processed, some triggers will be dropped and no samples are logged for that calculation time.

For information on creating a polled trigger, refer to [create a polled trigger \(on page 2476\)](#).

- **Unsolicited or event-based:** Used to trigger a calculation based on an event. For example, you can calculate the average value of tag data when the data exceeds a certain value.

When you set an event-based trigger, you must also set up a dependency list of one or more tags. Event-based triggers will keep calculations as up to date as possible. They are also useful when you want to do on-demand calculations. You can use a trigger tag that is written to by an external program or operation.

If you want to perform raw sample replication you would use an event-based trigger. To retrieve data from a tag, use the formula:

```
Result=Historian.CurrentValue('Tag1')+Historian.CurrentValue('Tag2')
```

If you are using recovery mode, all referenced tags in an unsolicited calculation must be listed as trigger tags because recovery will be performed only for the configured trigger tags.

Event-based triggers have a dependency list of trigger tags. The trigger fires whenever there is a data change for the trigger tag (for example, changes in the quality and value of a trigger tag). The

value of a trigger tag can change when the tag exceeds the collector compression (if you enabled collector compression).

The calculation is processed each time any tag in the dependency list changes. If you have multiple tags in the list and they change even one millisecond apart, then you will have multiple events, and the calculation formula will be processed for each.

However, the following actions do not trigger a calculation:

- Deletion of a tag that is in the dependency list.
- Re-addition of a tag in the dependency list.

The calculation is triggered at the same time as the timestamp of the sample in the trigger tag. The values of all other tags in the formula are interpolated forward to this time so that the timestamps of all input tags are the same. Even if these are sequential events, they have the same timestamp. The calculation time becomes the timestamp for the sample stored in the destination tag.

Event-based triggers have a collection interval. The Python Collector notifies the archiver not to send notification of changes to trigger tags any faster than the collection interval setting.


For information on creating an unsolicited trigger, refer to [create an unsolicited trigger \(on page 2477\)](#).

Create a Polled Trigger

1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
3. From the list of tags, select the Python collector tag (say, SamplePythonCollector).

<input type="checkbox"/>	TAG NAME	DESCRIPTION	COLLECTOR NAME	LAST 10 VALUES	D.	TAG ALL..	IS STALE
	<i>Filter</i>	<i>Filter</i>	<i>Filter</i>				<i>Filter</i>
<input type="checkbox"/>	f(x) Python_2		SamplePythonCollector			● On	False
<input type="checkbox"/>	f(x) Python_3_tag		SamplePythonCollector			● On	False
<input checked="" type="checkbox"/>	f(x) SamplePythonCollector		SamplePythonCollector			○ On	False
<input type="checkbox"/>	f(x) Test_Python_Tag		SamplePythonCollector			● On	False
<input type="checkbox"/>	f(x) Test_Python_tag2		SamplePythonCollector			● On	False


4. In **DETAILS**, in the **Collection Options** section, select **Polled** from **Collection Type**.




5. Set the **Collection Interval Value** and **Collection Offset** values. For example, if you want to set a trigger every day, set these values to 24 hours and 8 hours, respectively.
6. In the upper left corner of the page select **Save**.
The triggers are created.

Create an Unsolicited Trigger


1. [Access Configuration Hub \(on page 336\)](#).
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
3. From the list of tags, select the Python collector tag (say, SamplePythonCollector).




4. In **DETAILS**, in the **Collection Options** section, select **Unsolicited** from **Collection Type**.



5. Select Calculation Triggers and select  .
The Calculation Triggers window appears.
6. Search for tags or select tags from the list as trigger tags.
7. You can remove the selected tags by selecting X from the Selected Tags list.



8. Select **Insert Trigger**.
The trigger tag count will be displayed.



9. In the upper left corner of the page select **Save**.
The triggers are created.

About Calculations

About Calculations using Python Collector

To perform a calculation using the Python Collector, you must define the Python script. You can define the Python script in one of the following ways:



Note:

To seamlessly create Python script, it is recommended to use Configuration Hub instead of Historian Administrator.

- Using pre-built functions ([on page 2478](#)).
- Using third-party or custom Python modules ([on page 2481](#)).


Create Python Script using Built-in Functions

This topic describes how to create a Python script using the pre-built functions. For more information on the built-in functions, refer to [available functions \(on page 2483\)](#).


1. [Access Configuration Hub \(on page 336\)](#)
2. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
3. Select a Python collector tag, right-click or select more options, and then select **Calculation**.

<input type="checkbox"/>	▼ TAG NAME	▼ DESCRIPTION	▼ COLLECTOR NAME	LAST 10 VALUES	D.	TAG ALL...	▼ IS STALE	
	Filter	Filter	Filter				Filter	Step Value
	Filter	Filter	Filter				Filter	Created By
<input checked="" type="checkbox"/>	fw Python_Sample_Calculation_Tag		SamplePythonCollector	On			false	Trend
<input type="checkbox"/>	fw Calculation_sample_tag		SamplePythonCollector	On			false	View Last 10 Values
<input type="checkbox"/>	fw Python_2		SamplePythonCollector	On			False	Calculation
<input type="checkbox"/>	fw Python_3_tag		SamplePythonCollector	On			False	View Aliases
<input type="checkbox"/>	fw SamplePythonCollector		SamplePythonCollector	On			False	Rename
<input type="checkbox"/>	fw Tag_2_Test		SamplePythonCollector	On			False	Rename Permanently
<input type="checkbox"/>	fw Test_Python_12		SamplePythonCollector	On			False	Copy
<input type="checkbox"/>	fw Test_Python_Tag		SamplePythonCollector	On			False	Browse Activity Log
<input type="checkbox"/>	fw Test_Python_tag2		SamplePythonCollector	On			False	Toggle Data Collection
								Remove Tag From System
								Delete

The **PYTHON SCRIPT** editor appears.



4. In the scripting section, remove `Null` (and retain the `Result =`).
5. In the **DETAILS** section, under **Pre-Built Functions**, in the **Function Type** field, select a function type.
Depending on the function type you have selected, a list of functions appears in the **Function** field.
6. In the **Function** field, select a function.
Based on the selected function, the related fields will be displayed.
7. Enter values in the other fields that appear after selecting a function.
8. In the **Input Tag** field, select , and then select the tag where applicable.
The **Tag Browser Criteria** window appears.



9. Select **Apply**.
The selected tag is added as the input tag.

10. Select **Insert Function**.

The screenshot shows a code editor window titled "SYNTAX: PYTHON SCRIPT". The editor contains a single line of Python code: `Result=Historian.AddData ('Python_2',0,'2023-12-13T13:31:50.322Z',100)`. Below the editor, there is a "FUNCTION PREVIEW" section that displays the same code: `Historian.AddData ('Python_2',0,'2023-12-13T13:31:50.322Z',100)`. In the bottom right corner of the editor, there is a blue button labeled "Insert Function".

The function is inserted at the cursor position and the function preview appears below the calculation editor.

11. To test the function, select .

A message appears, stating whether the syntax is correct.

12. In the upper-left corner of the page, select **Save**.

The Python script is created.

Create Python Script by Importing Third-party or Custom Python Modules or Functions

This topic describes how to create a Python script by importing custom or third-party Python modules or functions.

1. In the same machine where you installed Python 3.8, install the needed modules or create your own functions.
2. After you install the modules, for the collector to recognize the modules, update the following path to include the location where you installed the modules or created your own functions:

```
Computer\HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\GE
Digital\iHistorian\CollectorServiceExtensions\PythonExpressions\PythonPath
```

After you update the path, the changes are reflected as follows:


```
C:\Program Files (x86)\GE Digital\Historian Python Expressions\Python38\lib
C:\Program Files (x86)\GE Digital\Historian Python Expressions\Python38\user
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\Lib
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\Lib\site-packages
```

You can also configure Python library path using Configuration Hub. For more information, refer to [Configure Python Library path using Configuration Hub](#).

3. [Access Configuration Hub \(on page 336\)](#)
4. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
5. Select a Python collector tag, right-click or select more options, and then select **Calculation**.

<input type="checkbox"/>	TAG NAME	DESCRIPTION	COLLECTOR NAME	LAST 10 VALUES	D.	TAG ALL	IS STALE	
Filter	Filter	Filter	Filter	Filter				Step Value Created By
<input checked="" type="checkbox"/>	fw Python_Sample_Calculation_Tag		SamplePythonCollector	On			false	
<input type="checkbox"/>	fw Calculation_sample_tag		SamplePythonCollector	On			false	
<input type="checkbox"/>	fw Python_2		SamplePythonCollector	On			False	
<input type="checkbox"/>	fw Python_3_tag		SamplePythonCollector	On			False	
<input type="checkbox"/>	fw SamplePythonCollector		SamplePythonCollector	On			False	
<input type="checkbox"/>	fw Tag_2_Test		SamplePythonCollector	On			False	
<input type="checkbox"/>	fw Test_Python_12		SamplePythonCollector	On			False	
<input type="checkbox"/>	fw Test_Python_Tag		SamplePythonCollector	On			False	
<input type="checkbox"/>	fw Test_Python_tag2		SamplePythonCollector	On			False	

The **PYTHON SCRIPT** editor appears.



6. In the scripting section, remove `Null` (and retain the `Result =`).

7. In the scripting section, to import the custom or third-party functions/modules, enter the script in the following format:

```
import mymodule

Result=mymodule.myfunction()

#Example

import SimulationCalculation

Result=SimulationCalculation.GetInteger()
```

8. To test the function, select .

A message appears, stating whether the syntax is correct.

9. In the upper-left corner of the page, select **Save**.

The Python script is created.

After few seconds, the added script takes effect.

Available Functions

This topic describes the built-in functions that you can use to create a calculation formula. You can also [use third-party or custom Python modules in the script \(on page 2481\)](#).

Function Type	Function	Description	Example
Add Data	<code>Historian.AddData(tags, values,times)</code>	Write data to a tag in the Historian archive.	<code>Result=Historian.AddData ('Python_Sample_Calculation',0,'2023-12-13T15:13:44.536Z',100)</code>
Check Data Quality	<code>Historian.CurrentQuality('tag name')</code>	The current quality of the tag (0 for bad quality and 100 for good quality).	<code>Result=Historian.CurrentQuality('Tag')</code>
Check Data Quality	<code>Historian.InterpolatedQuality('tag name','time')</code>	The current quality of the interpolated tag.	<code>Result=Historian.InterpolatedQuality('Tag1','2023-12-13T16:32:03.626Z')</code>
Check Data Quality	<code>Historian.NextGoodQuality('tag name','time')</code>	The good quality of the raw sample after the time. Time is provided	<code>Result=Historian.NextGoodQuality('Tag1','2023-12-13T16:34:19.154Z')</code>

Function Type	Function	Description	Example
		as string in standard ISO 8601 format.	
Check Data Quality	<code>Historian.NextQuality('tag name', 'time')</code>	The quality of the tag (0 for bad quality and 100 for good quality) after the time. Time is provided as string in standard ISO 8601 format.	<code>Result=Historian.NextQuality('Tag2', '2023-12-13T16:35:41-.709Z')</code>
Check Data Quality	<code>Historian.PreviousGoodQuality('tag name', 'time')</code>	The good quality of the raw sample prior to the time. Time is provided as string in standard ISO 8601 format.	<code>Result=Historian.PreviousGoodQuality('Tag3', '2023-12-13T16:36:47-.736Z')</code>
Check Data Quality	<code>Historian.PreviousQuality('tag name', 'time')</code>	The quality of the tag (0 for bad quality and 100 for good quality) prior to the time specified. Time is provided as string in standard ISO 8601 format.	<pre>datetime_str = Historian.CurrentTime() datetime_object = datetime.strptime(datetime_str, '%m/%d/%y %H:%M:%S.%f') Result=Historian.PreviousQuality('Test_Sim.Simulation00001',datetime_object.isoformat())</pre>
Insert A Calculation- Non-filtered Calculation	<code>Historian.Calculation('tag name', 'CalculationMode', 'StartTime', 'EndTime')</code>	Unfiltered calculated data query that returns a single value, similar to the Excel Add-In feature. For a list of the calculation mode, refer to calculation modes (on page 1073) . All times are provided as string in standard ISO 8601 format.	<pre>from datetime import datetime, timedelta datetime_str = Historian.CurrentTime() endTime = datetime.strptime(datetime_str, '%m/%d/%y %H:%M:%S.%f') startTime = endTime - timedelta(hours=0,minutes =0,seconds=10)</pre>

Function Type	Function	Description	Example
			<pre>Result=Historian.Calculati on('Test_Sim.Simulation000 02','Average', startTime.isoformat(), endTime.isoformat())</pre>
<p>Insert A Calculation- Filtered</p>	<pre>Historian. Calcula- tionFilter('tag name', 'CalculationMode', 'StartTime', 'End- Time', 'FilterTag- name', 'FilterMode', 'FilterComparison', 'FilterValue')</pre>	<p>Filtered calculated da- ta query that returns a single value, similar to the Excel Add-In feature. All times are provided as string in standard ISO 8601 format.</p>	<pre>from datetime import datetime, timedelta datetime_str = Historian.CurrentTime() endTime = datetime.strptime(datetim e_str, '%m/%d/%y %H:%M:%S.%f') startTime = endTime - timedelta(hours=0, minutes=0,seconds=1) Result=Historian.Calculati onFilter('Test_Sim.Simulat ion00004','Average', startTime.isoformat(), endTime.isoformat(),'Test _Sim.Simulation00006','Aft erTime','GreaterThan','10 0')</pre>
<p>Insert A Calculation Quality- Non-filtered Cal- culation</p>	<pre>Historian.Calculation- Quality('tag name', 'CalculationMode', 'StartTime', 'End- Time')</pre>	<p>Unfiltered calculated da- ta query that returns the quality of resulting val- ue. For a list of the cal- culation mode, refer to calculation modes (on page 1073). All times are provided as string in standard ISO 8601 for- mat.</p>	<pre>Result=Histori- an.CalculationQuali- ty('Python_2','Aver- age','2023-12-13T16:54:27- .296Z','2023-12-13T16:54:28- .296Z')</pre>

Function Type	Function	Description	Example
Insert A Calculation Quality- Filtered Calculation	<pre>Historian.Calculation- FilterQuality('tag name', 'Calculation- Mode', 'StartTime', 'EndTime', 'FilterTag- name', 'FilterMode', 'FilterComparison', 'FilterValue')</pre>	Filtered calculated data query that returns the quality of value. All times are provided as string in standard ISO 8601 format.	<pre>Result=Historian.Cal- culationFilterQual- ity('Tag', 'Aver- age', '2023-12-13T16:56:08- .123Z', '2023-12-13T16:56:09- .123Z', 'Tag', 'After- Time', 'Equal', '')</pre>
Insert A Tagname	<pre>'Tag'</pre>	The selected tag name.	<pre>Result='Python_3_tag'</pre>
Insert A Timestamp	<pre>Historian.Current- Time()</pre>	<p>The calculation execution time, which becomes the timestamp of the stored value. The result is returned as a string.</p> <p>For real-time processing of polled tags, the calculation execution time is the time when the calculation is triggered. For unsolicited tags, the calculation execution time is the timestamp delivered with the subscription.</p> <div data-bbox="824 1486 1107 1854" style="border: 1px solid #00a0c0; border-radius: 10px; padding: 10px; background-color: #e0f2f7;"> <p> Note: When a calculation is performed, the timestamp of the result is the time that the calculation has</p> </div>	<pre>The result is returned as a string. Format of timestamp is: "%m/%d/%y %H:%M:%S.%f" Example: "04/11/23 22:09:40.000" #Example to convert string timestamp to Python datetime object: from datetime import datetime datetime_str = Historian.CurrentTime() datetime_object = datetime.strptime(datetim e_str, '%m/%d/%y %H:%M:%S.%f')</pre>

Function Type	Function	Description	Example
		<p> begun, not the time that it completed.</p> <p>For recovery of polled or unsolicited tags, the calculation execution time is the time when the calculation would have been performed if the collector were running.</p>	
Insert A Timestamp	<pre>Historian.NextGoodTime('tag name', 'time')</pre>	The timestamp of the good raw sample after the time. Time is provided as string in standard ISO 8601 format.	<pre>Result=Historian.NextGoodTime('Tag', '2023-12-13T17:54:44-.223Z')</pre>
Insert A Timestamp	<pre>Historian.NextTime('tag name', 'time')</pre>	The timestamp of the raw sample after the timestamp. Time is provided as string in standard ISO 8601 format.	<pre>Result=Historian.NextTime('Tag', '2023-12-13T17:56:21.726Z')</pre>
Insert A Timestamp	<pre>Historian.PreviousGoodTime('tag name', 'time')</pre>	The timestamp of the latest good quality of the raw sample prior to the time. Time is provided as string in standard ISO 8601 format.	<pre>Result=Historian.PreviousGoodTime('Tag', '2023-12-13T17:57:45.308Z')</pre>
Insert A Timestamp	<pre>Historian.PreviousTime('tag name', 'time')</pre>	The timestamp of the raw sample prior to the time. Time is provided as string in standard ISO 8601 format.	<pre>Result=Historian.PreviousTime('Test_Sim.Simulation00001', '2023-03-27T16:02:08.070557')</pre>

Function Type	Function	Description	Example
Insert A Timestamp	<code>'time shortcut'</code>	The timestamp.value as a string format, in ISO 8601 format.	<code>Result=Historian.CurrentValue('Test_Simulation00001')</code>
Insert A Value	<code>Historian.CurrentValue('tag name')</code>	The value of the tag, interpolated to the calculation execution time. The <code>CurrentValue</code> function returns 0 if the quality is 0 (bad quality). This occurs if you initialized it to 0, or if a previous call failed.	<code>Result=Historian.CurrentValue('Test_Simulation00001')</code>
Insert A Value	<code>Historian.InterpolatedValue('tag name', 'time')</code>	The tag value, interpolated to the time that you enter. Time is provided as string in standard ISO 8601 format.	<code>Result=Historian.InterpolatedValue('Tag', '2023-12-13T18:05:29.367Z')</code>
Insert A Value	<code>Historian.NextGoodValue('tag name', 'time')</code>	The value of the good raw sample after the time. Time is provided as string in standard ISO 8601 format.	<code>Result=Historian.NextGoodValue('Tag', '2023-12-13T18:06:41.622Z')</code>
Insert A Value	<code>Historian.NextValue('tag name', 'time')</code>	The value of the raw sample after the timestamp. Time is provided as string in standard ISO 8601 format.	<code>Result=Historian.NextValue('Tag', '2023-12-13T18:07:44.369Z')</code>
Insert A Value	<code>Historian.PreviousGoodValue('tag name', 'time')</code>	The latest good value of the raw sample prior to the time. Time is provided as string in standard ISO 8601 format.	<pre>from datetime import datetime, timedelta from time import time # Getting today's date and time</pre>

Function Type	Function	Description	Example
			<pre> todays_Date = datetime.now() # subtract 1 minute from current time timeToQuery = todays_Date - timedelta(hours=0,minutes =1,seconds=0) Result=Historian.Previous GoodValue('Test_Sim.Simula tion00001',timeToQuery.iso format()) </pre>
<p>Insert A Value</p>	<pre> Historian.PreviousVal- ue('tag name', 'time') </pre>	<p>The tag value of the raw sample prior to the time specified.</p> <p>Time is provided as string in standard ISO 8601 format.</p>	<pre> datetime_str = Historian.CurrentTime() datetime_object = datetime.strptime(datetim e_str, '%m/%d/%y %H:%M:%S.%f') Result=Historian.PreviousV alue('Test_Sim.Simulation0 0001',datetime_object.isof ormat()) </pre>
<p>Insert An Advanced Calculation- Non-filtered Calculation</p>	<pre> Historian.Advanced- Calculation('Tag- name', 'Calculation- Mode', 'Criteria- String' 'StartTime', 'EndTime') </pre>	<p>Unfiltered calculated data query with criteria string that returns a single value. All times are provided as string in standard ISO 8601 format.</p>	<pre> Result=Histori- an.AdvancedCalcula- tion('Tag', 'Aver- age', '', '2023-12-13T18:15:22- .189Z', '2023-12-13T17:15:23- .189Z') </pre>
<p>Insert An Advanced Calculation- Filtered Calculation</p>	<pre> Historian.AdvancedCal- culationFilter('Tag- name', 'Calculation- Mode', 'Criteria- </pre>	<p>Filtered calculated data query with criteria string that returns a single value. All times are provid-</p>	<pre> Result=Historian.Ad- vancedCalculation- Filter('Tag', 'Aver- age', '', '2023-12-13T18:16:29- </pre>

Function Type	Function	Description	Example
	<pre>String', 'StartTime', 'EndTime', 'FilterTag- name', 'FilterMode', 'FilterComparison', 'FilterValue')</pre>	<p>ed as string in standard ISO 8601 format.</p>	<pre>.333Z', '2023-12-13T18:16:30- .333Z', 'Tag', 'After- Time', 'Equal', '')</pre>
<p>Insert An Advanced Calculation Quality- Non-filtered Calculation</p>	<pre>Historian.AdvancedCal- culationQuality('Tag- name', 'Calculation- Mode', 'Criteria- String', 'StartTime', 'EndTime')</pre>	<p>Unfiltered calculated data query with criteria string that returns the quality of value. All times are provided as string in standard ISO 8601 format.</p>	<pre>Result=Historian.Ad- vancedCalculation- Quality('Tag', 'Aver- age', '', '2023-12-13T18:18:32- .238Z', '2023-12-13T18:18:33- .238Z')</pre>
<p>Insert An Advanced Calculation Quality- Filtered Calculation</p>	<pre>Historian.AdvancedCal- culationFilterQuality ('TagName', 'Calcula- tionMode', 'Criteria- String', 'StartTime', 'EndTime', 'FilterTag- name', 'FilterMode', 'FilterComparison', 'FilterValue')</pre>	<p>Filtered calculated data query with criteria string that returns the quality of value. All times are provided as string in standard ISO 8601 format.</p>	<pre>Result=Histori- an.AdvancedCalcu- lationFilterQual- ity('Tag', 'Aver- age', '', '2023-12-13T18:20:19- .954Z', '2023-12-13T18:20:20- .954Z', 'Tag', 'After- Time', 'Equal', '')</pre>
<p>NA</p>	<pre>Historian.LogMes- sage(string_message)</pre>	<p>Allows you to write messages to the collector log file for debugging purposes. The collector log files are located in the</p> <pre>Proficy Historian Data\LogFiles\LogFiles</pre> <p>folder.</p>	<pre>Result=Historian.Log- Message(test_message)</pre>

Examples of using Calculation Functions

Examples: Using the Built-in Functions

Retrieving the Current value

You can use the current value function to retrieve the current value of an existing Historian tag.

```
Result=Historian.CurrentValue('Tag1')
```

Get the current value of two tags and return the greater value of the two value:

Return the Greater Value of Two Tags

```
x=Historian.CurrentValue('Tag1')
y=Historian.CurrentValue('Tag2')

if x > y:
    Result= x
else:
    Result= y
```

Add the Values of Two Tags

```
Result=Historian.CurrentValue('Tag1')+Historian.CurrentValue('Tag2')
```

Examples: Custom or Third-party Python Modules

To use additional Python modules, install them over Python 3.8.

For example, to install NumPy:

1. Run the following command:

```
Pip install numpy
```

2. Add the site packages to the Python path as follows:

```
Computer\HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\GE
Digital\iHistorian\CollectorServiceExtensions\PythonExpressions\PythonPath
```

After you do so, the changes are reflected as follows:

```
C:\Program Files (x86)\GE Digital\Historian Python Expressions\Python38\lib
C:\Program Files (x86)\GE Digital\Historian Python Expressions\Python38\user
```

```
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\Lib
```

```
C:\Users\Administrator\AppData\Local\Programs\Python\Python38-32\Lib\site-packages
```

Retrieve the Age of the First Person from a List Using a REST API

```
import requests

import json

api_url = https://myRestAPIURL/

response = requests.get(api_url)

json_data = json.loads(response.text)

Results=json_data["results"][0]

dateOfBirth =Results["dateofbirth"]

age = dateOfBirth["age"]

Result=age
```

Returns the following result:

```
{
  "results": [
    {
      "gender": "female",
      "name": {
        "title": "Mrs",
        "first": "Lumi",
        "last": "Tikkanen"
      },
      "dateofbirth": {
        "date": "1982-01-08T21:23:26.095Z",
        "age": 39
      },
      "phone": "08-609-184",
      "cell": "049-127-63-22"
    }
  ]
}
```

Calculate the Sum of all Values in a Column in an SQL Database

```
import pyodbc

conn = pyodbc.connect('Driver={ODBC Driver 17 for SQL Server};'

                        'Server=MySQLServer;'

                        'Database=MyDB;'

                        'Trusted_Connection=yes;')

cursor = conn.cursor()

cursor.execute('SELECT column1 FROM Table_1')

sum = 0;

for i in cursor:

    sum = sum + i.column1

Result = sum

conn.close()
```

Calculate a Score Using Linear Regression in NumPy

```
import numpy as np

from sklearn.linear_model import LinearRegression

X = np.array([[2, 7], [10, 4], [5, 7], [2, 3]])

y = np.dot(X, np.array([1, 2])) + 3

reg = LinearRegression().fit(X, y)

Result = reg.score(X, y)
```

Reading Data from a File Using Pandas

To read the data using Pandas, you must create:

- Training dataset using 80% of the data
- Linear regression model using the training data
- Return the coefficient of the model

```
import pandas as pd

import numpy as np

from sklearn import linear_model
```

```

data = pd.read_csv("C:\\myFile.csv")
data = data[["Column1","Column2"]]
train = data[:int((len(data)*0.8))]

regressionLine = linear_model.LinearRegression()

train_x = np.array(train[["Column1"]])
train_y = np.array(train[["Column2"]])

regressionLine.fit(train_x,train_y)

Result=regressionLine.coef_[0][0]

```

Mathematical Optimization

The Rosenbrock function to perform mathematical optimization is defined in SciPy as follows:

```
sum(100.0*(x[1:] - x[:-1])**2.0)**2.0 + (1 - x[:-1])**2.0)
```

```

import numpy as np
from scipy.optimize import rosen

a = 0.2 * np.arange(9)

Result=rosen(a)

```

Calculating the Determinant of a Matrix using SciPy

```

#calculate the determinant of a square matrix

import numpy as np
from scipy import linalg

A = np.array([[1,2,4], [4,3,7], [2,7,3]])

Result=linalg.det(A)

```

Creating a Data Frame from an Array and Calculating the Sum of all Elements

```

import numpy as np
import pandas as pd

df = pd.DataFrame(np.array([[1, 2, 3], [4, 5, 6]]))

Result=float(df.sum().sum())

```

Generating a Random Value

```
from random import seed

from random import random

seed(10)

Result=random()*random()
```

Example: Storing Current Values of Arrays

You can store the current value of array of strings into another array tag. You can use the below calculation/script, in this example, the CurrentValue function returns the result as a python list that will be stored into the appropriate historian array type:

```
Result = Historian.CurrentValue('Test_Sim.SimulationArrayString')
```



Note:

When you convert a value to boolean type, you must store the results as `Result = bool(Historian.CurrentValue('TP.Simulation00001'))`

You can take an array value collected from a field device and adjust the values before storing it in another array tag Array2 using the below calculation/script:

```
x= Historian.CurrentValue("Array1")

x(1) = x(1)+10

Result = x
```

You can use Calculation() function to read the array tag as shown below:

```
from datetime import datetime, timedelta

datetime_str = Historian.CurrentTime()

endTime = datetime.strptime(datetime_str, '%m/%d/%y %H:%M:%S.%f')

startTime = endTime - timedelta(hours=0,minutes=0,seconds=1)

Result=Historian.Calculation('Test_Sim.SimulationArray00001','Average', startTime.isoformat(), endTime.isoformat())
```



Note:

When you import numpy values, it is recommended to include the string data type, failing to include will cause the code to incorrectly read the numpy values. The below code will fail with



error: Msg="Unable to set result for Result" if the tag using this script is set as an array of integers. Testing the function will pass but running the calculation will fail.

```
import numpy as np

randnums= np.random.randint(1,101,5)

Result=randnums
```

Example: Storing Dictionary Data as Multifield Data

Dictionary data type in Python (key/value pairs) can be stored in Historian as a Multifield (User Defined Type).



Note:

If you want to store the data quality of multifield elements, store the result into a Historian tag that matches the data type of the field. Copying a multifield into a dictionary type only stores the field name and data.

Maximum array elements that can be copied to python tuple are 10. If more elements are available in the source in Historian, read each element in your python calculation.

For example, create a Multifield called "MySample" in Historian with three fields named: Field1, Field2, Field3. Once it is created, add a Python tag with the same multifield data type, and use below script to update its values:

```
thisdict = {
    "Field1": 11.55,
    "Field2": 22.8,
    "Field3": 33.55,
}
Result = thisdict
```

OR

```
thisdict = {
    "Field1": "1",
    "Field2": "2",
    "Field3": "3",
}
Result = thisdict
```

Using the value of a field within the python script, if you have a user-defined type MySample with fields Field1 and Field2, you can create Tag1 and use the value of one field in the Python Tag. The destination tag is not a multifield tag.

```
sampleDict = Historian.CurrentValue('TestMF')
Result = sampleDict['Field3']

OR

Result = Historian.CurrentValue('TestMF.Field1')+5

OR

thisdict = {
    "brand": "BrandNew",
    "model": "BrandModel",
    "year": 1964
}
Result = thisdict["year"]
```

Storing the current value of a multifield tag into another tag whose data type is the same user defined multifield type

Below example stores the current value of a multifield tag into another tag whose data type is same as the user defined multifield type. CurrentValue function returns the result as a python dictionary (key value pairs of string data type).

```
Result = Historian.CurrentValue('TestMFString')
```

Example: Storing Python Integer List in Historian

Python lists and tuples can be stored in Historian as arrays of either numeric or string data types. Historian creates the arrays as python lists

Maximum array elements copies to python list is 10. If more elements are in the source in historian, read each element in your python calculation.

To store python integer list in historian, create a Single Integer array type and use the below calculation/script:

```
import array as arr
a = arr.array('i', [2, 4, 6, 8])
Result = a
```

OR

```
tuple = (11,22,33)
Result = tuple
```

Example: Storing Python String List in Historian

Python lists and tuples can be stored in Historian as arrays of either numeric or string data types. Historian creates the arrays as python lists

Maximum array elements copied to python list is 10. If more elements are in the source in historian, read each element in your python calculation.

to store python string list in historian, create a variable string tag of array type and use the below calculation/script:

```
mylist = ["gauge", "valve", "rotor"]
Result = mylist
```

OR

```
thistuple = ('Motor', 'Shaft', 'Rotor', 'Stator')
Result = thistuple
```

Example: Use Historian Data as Input to a Python Script

You can use the Historian Array data as input to a python script, to use the Historian Array data as input, you can use the name of the array tag like "Array1" or the individual element of the array like "Array1[4]". For example, if you have an array tag "Array1" of floating point values and a calculation tag "FloatCalc1" of float data type, then you can use the array as input to calculate a float value.

```
Result=Historian.CurrentValue("Array1[4]")+5
```

Chapter 33. Server-to-Server Collector

Overview

Overview of the Server-to-Server Collector

The Historian Server-to-Server collector allows you to collect data and messages from a source Historian server to a destination Historian server, a Predix Time Series instance, an Azure IoT HUB instance, or an MQTT endpoint such as AWS IoT Core. The Server-to-Server collector includes many of the features of the Calculation collector. The primary difference is that the Server-to-Server collector stores the result in a destination tag on the destination server, whereas the Calculation collector reads and writes to the same server.

The Server-to-Server collector can also run as a stand-alone component where both the source and destination Historian databases are on remote machines.

When a time-based or an event-based trigger of a destination tag occurs:

1. The calculation formula for the destination tag is executed.

This typically involves fetching data from one or more tags on the source server.

2. A raw sample or calculation error is determined.

You can use conditional logic in your calculation formula to determine if a sample should be sent to the destination.

3. The raw sample is delivered to the destination server, utilizing store and forward when necessary.


Message replication, if enabled, is event-based. Messages and alerts are sent to the destination server as they happen.

The destination tag is fundamentally a different tag than the source tag. Therefore:

- When a tag is added by browsing, only certain tag properties are copied from the source tag to the destination tag. Consider what properties are necessary for your application and configure them manually. For information on which properties are copied, refer to [Tag Properties that are Copied \(on page 2508\)](#).
- If you change a tag property on the source tag (EGU Limits, descriptions, and so on), the property does not automatically change on the destination tag. You can manually change the properties of a destination tag.


Data Flow in Multiple Server-to-Server Collectors

The following image shows that you can use multiple Server-to-Server collectors in an application to pass data from multiple nodes to one node and that a server can be a source and a destination at the same time. Each Historian server is forwarding a different set of tags.



Data Flow in Bi-directional Server-to-Server Collectors

You can configure bi-directional data collection, where each collector collects a different set of tags. The following figure shows bi-directional server-to-server data collection.

**Note:**

You cannot collect the same tag in both directions. This is not a way to perform bi-directional synchronization of a tag.

Features

Feature	Capability
Browse Source for Tags	Yes
Browse Source for Tag Attributes	Yes
Polled Collection	No
Minimum Poll Interval	No
Unsolicited Collection	Yes
Timestamp Resolution	Yes - 100 milliseconds
Data Compression	Yes
Accept Device Timestamps	Yes
Floating Data Point	Yes
Integer Data	Yes
String Data	Yes
Binary Data	No
Allows VB scripting	No

Feature	Capability
Python Expression Tags	No

Licensing

When the destination server is Proficy Historian, the Server-to-Server collector requires licensing on the destination machine. This means that the destination Historian server must be licensed for the Historian Enterprise edition, have the Enterprise Collectors option licensed, or be a Historian Edge server. It is similar to any other collector. The destination machine will have the Server-to-Server listed in its collector list.

Interface Name

Historian uses the following naming convention for the Server-to-Server collector interface name:

```
<source Historian server>_To_<destination Historian server>
```

Best Practices

- We recommend that you install the Server-to-Server collector on the source Historian machine. When you do so, the collector can preserve the collected data (store and forward) even if the collector and the destination server become disconnected.
- Collection on a tag-by-tag basis is preferred, according to scheduled poll times or upon data changes. One sample is collected for each trigger.
- The Server-to-Server collector can perform calculations on multiple input tags as long as the input tags are on the same source Historian.
- Use polled triggers to perform scheduled data transformations like daily or hourly averages. Use unsolicited triggers to replicate data in real time, as it changes.
- Use event-based triggers to replicate data throughout the day. The samples can be held in an outgoing store and forward buffer when necessary. You cannot schedule batch replication of raw samples. For example, you cannot, at the end of the day, send all raw samples for tags to the destination.
- All input source tags for the calculations must originate from the source archiver. For instance, you cannot directly add a tag from `server1` plus a tag from `server2` and place the result on `server2`. You could, however, collect tags from `server1` to `server2`, and then use the Calculation collector or the Server-to-Server collector to accomplish this. This requires two Server-to-Server collectors, one running on each machine. You could also use the Historian OLE DB provider.

Limitations

- If you enable alarm replication, the alarm data is sent to the destination server. However, alarm filtering is not available in the Server-to-Server collector.
- You cannot configure bi-directional message replication.

About Recovery Mode

Normally, the Server-to-Server collector operates in a real-time mode. A real-time mode is when the collector is polling data or has subscribed to events and triggers calculations based on these events occurring in real-time. Messages are also sent as they occur. Recovery mode allows you to recover tag and alarm data when the connection between the collector and the source server is re-established. After a connection loss, the [configuration settings \(on page 2506\)](#) for the Server-to-Server collector determine how much tag and alarm data is recovered and if messages are included in the recovery.

When Does Recovery Occur?

Recovery mode executes:

- When the collector is started.
- When the collector is resumed after a pause.
- When there is an on-the-fly change (similar to a pause and resume). Only tags in the new tag configuration are recovered.
- When there has not been a collector stop and start, but the connection to the source Historian is restored.

What Happens When Recovery Occurs?

In recovery mode, after connecting to the source Historian, the collector will:

- Set up subscriptions for all alarms and trigger tags.
- Perform recovery in chronological order (oldest to newest).
- Perform message recovery, if enabled.
- Begin polling and processing subscriptions in real-time mode.

The following items are recovered:

- **Event-based tags:** This includes the data from the last write time until now. The system retrieves all tags.
- **Messages:** The system checks for new messages and verifies errors. Once the system verifies a connection to the destination, it sends the messages one at a time.
- **Alarm data:** This includes all alarm data from the last write time until now.

**Note:**

Alarm recovery uses a different write time than tag recovery. Alarm recovery starts from the time of the last alarm is replicated to the destination.

If your formula contains tags not in the trigger list or dependencies exist among tags (for example, if a calculation tag is a trigger for another calculation tag), you might not recover all data.

About Collection of Raw Samples

To minimize the effect of missing samples, we recommend that you view collected data on the destination with interpolated queries rather than raw data queries.

Here are some suggestions about how best to configure your system when you want raw samples of collected tags to match on the source and the destination. This is often not achievable, but here are some tips:

- Use the formula `Result=CurrentValue("TriggerTag")`.
- Do not use collector compression on the destination tag.
- Use archive compression on the destination if it is set on the source.

The reason for this is that unsolicited triggers occur based on value changes, not based on what is stored in the archive. A value change may not be stored on the destination if archive compression is being used. It is up to the destination tag to apply the archive compression before the value is stored.

- Use event-based triggers with `0 ms` collection intervals.
- In the Server-to-Server collector, disable the **Synchronize Timestamps to Server** option in the **Advanced** section in the collector configuration in Historian Administrator.

Using the Collector

Workflow for Using the Server-to-Server Collector

To use the Server-to-Server collector, you must perform the following tasks:

Number	Task	Notes
1	Install the collectors (on page 142) on the machine on which you want to run the collector.	This step is required. This will place the collector binaries on the machine.
2	Install Remote Management Agents (on page 187).	This step is required to manage collectors installed on a remote machine.
3	Add an instance (on page 357) of the Server-to-Server collector using Configuration Hub.	This step is required.
4	Configure the Server-to-Server collector (on page 2506) using Historian Administrator.	This step is required only if you want to change the default values.
5	Create a destination tag. You can do so by browsing for the tag (on page 2064) , adding it manually (on page 2056) , or copying a tag (on page 2060) .	This step is required. If configured, the tag will contain a prefix.
6	Assign a trigger to the tag that you have created, similar to assigning a trigger for the Calculation collector.	This step is optional. The trigger can be scheduled (polled) or unsolicited (event-based). When you use an event-based trigger, you must also set up a dependency list of one or more tags. For more information, refer to Create a Polled Trigger (on page 2112) and Create an Unsolicited Trigger (on page 2114) .
7	Create a formula similar to creating a formula for the Calculation collector. For instructions, refer to About Calculation Formulas (on page 2118) .	This step is optional. You can expect thousands of tags per second to be processed, depending on your calculation formula. However, the destination server has a limited number

Number	Task	Notes
		<p>of incoming events per second, which is shared by all the collectors.</p> <p>For instance, for a polled collection, you can expect to perform hundreds of calculations per second. Polled calculations, using calculated data functions, are slower than unsolicited calculations using the CurrentValue() function.</p>

Configure the Server-to-Server Collector Instance

1. Access Historian Administrator.
2. Select the Server-to-Server collector from the list of collectors, and then select **Configuration**.
The **Collector Specific Configuration (ServerToServer)** section appears.

Collector Specific Configuration (ServerToServer)

Source Server

Alarm Replication

Message Replication

Calculation Timeout (sec)

Max Recovery Time (hr)

Add Prefix To Messages

3. Provide values as specified in the following table, and then select **Update**.

Field	Description
Alarm Replication	Indicates whether you want to enable or disable alarm replication. If you enable alarm replication, all collected alarm data will be transferred from the source server to the destination server. If you enable alarm replication, you also enable alarm recovery. However, if you set the Max Recovery Time value to zero, alarm recovery does not happen.
Message Replication	Indicates whether you to want to enable or disable message replication. If you enable message replication, messages will be transferred from the source server to the destination server. You can use this data for audits. If you enable message replication, you also enable message recov-

Field	Description
	ery. However, if you set the Max Recovery Time value to zero, message recovery does not happen.
Calculation Timeout (sec)	The maximum time allowed for a tag's calculation formula to execute before being terminated. The default value is 10 seconds.
Max Recovery Time (hr)	The maximum duration, in hours, for which the collector will attempt to restore data during recovery logic. The default value is 4 hours.
Add Prefix to Messages	<p>The prefix to identify replicated messages on the destination.</p> <p>Alarms and events data will automatically have a prefix added to it with the following syntax:</p> <pre>MachineName_Datasource</pre> <p>For example, if your alarm is forwarded from the server <code>Almserver12</code> with a data source named <code>OPCAE</code>, the prefix will be <code>Almserver12_OPCAE</code>.</p>

The Server-to-Server collector is configured.

Tag Properties that are Copied

Tag Properties that are Copied

When you add a tag by choosing from the S2S Collector browse list, only certain tag properties are copied from the source tag to the destination tag. If you intend to copy raw samples from the source to the destination, after you add the tag, be sure to set these properties to their desired values. See *Tag Properties Copied to the Destination Tag* described below.

Important tag properties that do not automatically copy over when you add the tag include:

- Input scaling settings

Since the output of the source tag is the input to the destination tag, you actually want to match the EGU limits on the source to input limits on the destination, if you are using Input Scaling.

- Timestamp resolution

Make sure that the timestamp resolution properties match. For example, do not use the second timestamp resolution on the destination tag, if your source tag uses millisecond timestamp resolution. If your source tag uses millisecond timestamp resolution, then you also want to set your destination tag to also use millisecond timestamp resolution.

The following table describes the tag properties in Historian Administrator Tags page that are copied when the destination tag is created via select from the browse. If a property is not listed in this table, it is not copied.

Tab Name	Properties Copied
General	Description EGUDescription
Collection	Data Type DataLength
Scaling0	HiEGU LoEGU InputScaling HiScale LoScale
Compression	ArchiveCompression ArchiveDeadband(%)

Examples of Data Collection

Raw Samples Collection Example

This topic describes how to collect raw samples using the Server-to-Server collector. The tag names are the same on the source and destination. In this example, you add a tag manually, and give it a tag name on the destination server (representing the meaning of the calculated value).

1. Using Historian Administrator, [browse the Server-to-Server collector for tags \(on page 2064\)](#) on the remote server.
2. Select a tag.
The collector creates a tag on the destination with the tagname to hold the collected data. The formula of the created tag is `Result=CurrentValue` and the source is the trigger.

Advanced Collection Example

In this example, you calculate a value (such as an hourly average of a source tag) or add two source tags together.

1. Using Historian Administrator, add a tag manually to the destination, as shown in the following image:

2. In the **Tags** section, select **Collection**.
3. In the **Collection Type** box, select **Polled**.
4. Set the **Collection Interval** to 1 hour.
5. Select **Calculation**.
6. In the **Calculation** section, enter the name of the tag, or use the **Insert Function Wizard** to browse and select the tagname. Then, build your calculation formula.
The following figure shows an example of inserting a calculated value for a tag with the **Insert Function Wizard**.

Insert Function Wizard

Select Function

Type:

Function:

Tag Browse Criteria

Tag Name:

Description:

Specify Function Details

Input Tag:

Calculation:

Start Time:

End Time:

Browse Results (1,650)


Tagname	Description
FIXLAB48.AI00002.B_CUALM	FIXLAB48.AI00002.B_CUALM
FIXLAB48.AI00002.F_CV	FIXLAB48.AI00002.F_CV
FIXLAB48.AI00003.B_CUALM	FIXLAB48.AI00003.B_CUALM
FIXLAB48.AI00003.F_CV	FIXLAB48.AI00003.F_CV
FIXLAB48.AI00004.B_CUALM	FIXLAB48.AI00004.B_CUALM
FIXLAB48.AI00004.F_CV	FIXLAB48.AI00004.F_CV
FIXLAB48.AI00005.B_CUALM	FIXLAB48.AI00005.B_CUALM
FIXLAB48.AI00005.F_CV	FIXLAB48.AI00005.F_CV
FIXLAB48.AI00006.B_CUALM	FIXLAB48.AI00006.B_CUALM
FIXLAB48.AI00006.F_CV	FIXLAB48.AI00006.F_CV
FIXLAB48.AI00007.B_CUALM	FIXLAB48.AI00007.B_CUALM
FIXLAB48.AI00007.F_CV	FIXLAB48.AI00007.F_CV
FIXLAB48.AI00008.B_CUALM	FIXLAB48.AI00008.B_CUALM
FIXLAB48.AI00008.F_CV	FIXLAB48.AI00008.F_CV
FIXLAB48.AI00009.B_CUALM	FIXLAB48.AI00009.B_CUALM
FIXLAB48.AI00009.F_CV	FIXLAB48.AI00009.F_CV

Function Preview

`Calculation("FIXLAB48.AI00005.F_CV";"Average";"Now - 1Hour";"Now";Quality)`

7. Select **Insert**.

The **Tag Maintenance** page appears, showing the formula in the **Calculation** section.



8. Select **Update** to save your changes.

A message appears, asking you if you want to test the formula.

9. Select **Yes**.

The Server-to-Server collector will begin processing the created tag upon the next collector reload.

Creating Calculation Formulas

About Calculation Formulas

To perform a calculation using the Calculation collector, you must define the calculation formula. You can do so in one of the following ways:

- Using the [Insert Function wizard \(on page 2123\)](#), which helps you use any of the [built-in functions \(on page 2127\)](#) or create your own function [\(on page 2125\)](#).
- Entering the syntax of the formula directly in the form of a VBScript code [\(on page 2121\)](#).

Before you create calculation formulas, refer to the [general guidelines \(on page 2119\)](#).

There are two predefined global values called Result and Quality. These global values control the value and quality of the output sample. If the Result is not set in the formula, then no sample is stored.

General Guidelines for Defining a Calculation Formula

This section provides guidelines that you must follow when defining a calculation formula.

Identify Time Intensive Calculations

Use the `Calculation Execution Time` property of each tag to identify time-intensive queries. In Historian Administrator, look for the **Execution Time** on the **Calculation** section for an estimate of how long, on average, it takes for the calculation per tag (starting from the time the collector was started).

You can also include that column when you export tags to Excel using the Excel Add-In feature. For information, refer to [Exporting Tags \(on page 2746\)](#).

You can also include that column (`AverageCollectionTime`) when you query the `ihTags` table using the Historian OLE DB Provider. Sorting by this column will let you find them fast.

Troubleshoot Issues with Large Configurations

If the timestamps of your raw samples appear slightly old, do not assume that the collector has stopped working. It is possible that the collector is just running behind.

For instance, if you have a report rate of 15,000, but the newest raw sample that you see is 20-30 minutes old, wait for 1-2 minutes, and review the newest raw sample again. If the collector stopped, the newest raw sample will be unchanged. If it did change, then the engine is still running, but is lagging behind. If that happens, check if the collector overrun count is increasing. If yes, the collector is dropping samples, and you must decrease the load.

Error Handling in VBScript

Start each script with the `On Error Resume Next` statement so that errors are trapped. If you use this statement, the script runs even if a run-time error occurs. You can then implement error handling in your VBScript.

It is a good practice to include statements in your VBScript that catch errors when you run the script. If there is an unhandled error, a value of 0 with a bad data quality is stored. When you catch an error in the VBScript, consider including a statement in your calculation that sets the `Quality=0` when the error occurs. (The 0 value means that the quality is bad.) If you do not specifically include this setting in your script, Historian stores a good data quality point (`Quality=100`), even if an error has occurred in your formula. If `Quality=100` is not appropriate for your application, consider setting the quality to 0.

You cannot use the On Error `GoTo` Label statement for error handling, as it is not supported in VBScript. As a workaround, you can write code in the full Visual Basic language and then place it in a `.DLL` so that you can call it from within your VBScript using the `CreateObject` function. For examples of calculations that use the `CreateObject` function, refer to [Examples of Calculation Formulas \(on page 2138\)](#).

Unsupported VBScript Functions

You can use any VBScript syntax to build statements in a calculation formula with the exception of the following functions:

- `MsgBox`
- `InputBox`

Milliseconds not Supported in VBScript

The `CDate()` function does not support the conversion of a time string with milliseconds in it. Whenever you use the `CDate()` function, a literal time string, or a time string with a shortcut, do not specify milliseconds in the time criteria. Milliseconds are not supported in VBScript.

You cannot use milliseconds in times passed into built-in functions such as the `PreviousTime` and `NextValue` functions. For example, you cannot loop through raw samples with millisecond precision.

Notes on VBScript Time Functions

Using the VBScript time functions such as `Now`, `Date`, or `Time` can lead to unexpected results, especially in recalculation or recovery scenarios. To avoid these issues, use the `CurrentTime` built-in function provided by Historian, instead of `Now`, `Date`, or `Time`. For example, the VBScript `Now` is always the clock time of the computer and is likely not useful when recalculating or recovering data for times in the past. However, the "Now" time shortcut is equivalent to `CurrentTime` and can be used as input to the other built-in functions.

Using Quotation Marks in VBScript

If you want to use quotation marks in a tag name, you must insert a double quotes for each quotation mark that you want to use, as required for proper VBScript syntax. For example, if you want to get the current value of a tag named `TagCost"s`, you must enter:

```
Result = CurrentValue("TagCost""s")
```

In this example, note the double quotation marks that appear before the letter `s` in the `TagCost"s` name in the formula.

Avoiding Circular References in VBScript

Do not use circular references in calculation formulas. For instance, if the tag name is `Calc1`, a formula with a circular reference would be `Result=CurrentValue("Calc1")`. Whether the tag is polled or unsolicited, you get a bad value back using the circular reference.

Uninterrupted Object Method Calls

Object method calls are not interrupted. It is possible to exceed the Calculation Timeout setting if you have a method call that takes a long time to execute. The Calculation Timeout error still occurs, but only after the method completes.

Help for VBScript

You can get detailed Help for VBScript by referencing the Microsoft documentation on the MSDN web site. A *VBScript User's Guide and Language Reference* is available here: <http://msdn.microsoft.com/en-us/library/t0aew7h6.aspx>

Avoiding Deleted Tags

You can reference a deleted tag in a calculation formula, without an error appearing. For instance, you could enter a formula such as `Result=CurrentValue("DeletedTag")`, where `DeletedTag` is the name of the deleted tag. You can do this because when you delete a tag, Historian removes deleted tags from the Tag Database (so you cannot browse for it), but it retains the data for that tag in the archive.

However, it is recommended that you do not reference deleted tag names in your calculation formulas, because if the archive files are removed with the data for the deleted tag, the calculation will not work properly.

Create a Calculation Formula Using a VBScript Code

This topic describes how to create a calculation formula by entering a VBScript code. You can also [create a calculation formula using the Insert Function wizard \(on page 2123\)](#).



Important:

If a tag contains bad data quality, you cannot store its value through a calculation formula. For example, if your VBScript includes: `Result = 7 Quality = 0`, Historian does not store the 7, it stores 0.

**Tip:**

For examples, refer to [Examples of Scheduling Polled Triggers \(on page 2113\)](#) and [Examples of Scheduling Unsolicited Triggers \(on page 2117\)](#).

Create the tag that you want to use to store the calculation results. You can create the tag manually using [Configuration Hub \(on page 473\)](#), [Historian Administrator \(on page 2057\)](#) or the [Web Admin console \(on page 2059\)](#). Or, you can [copy a tag \(on page 2060\)](#).

1. To create a calculation formula using Configuration Hub:

- a. [Access Configuration Hub \(on page 336\)](#).
- b. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
- c. Select a Calculation tag, right-click or select more options, and then select **Calculation**.
The calculation editor appears.
- d. Enter the VB script in the editor.
- e. To test the function, select .
A message appears, stating whether the syntax is correct.
- f. In the upper-left corner of the page, select **Save**.
The calculation formula is created.

2. To create a calculation formula using Historian Administrator:

- a. [Access Historian Administrator \(on page 823\)](#).
- b. Select **Tags**, select the tag for which you want to create a calculation formula, and then select **Calculation**.
- c. In the **Calculation Triggers** section, select **Add**.
The **Insert Function Wizard** window appears.
- d. Under **Select Function**, in the **Type** field, select **Add A Calculation Trigger**.
- e. Under **Tag Browse Criteria**, enter the search criteria to find the tag.
The search results appear in the **Browse Results** section.
- f. Select the tag that you want to add, and then select **Insert**.

g. In the **Calculation** field, enter the calculation formula using the VBScript syntax.

h. To verify that the syntax is correct, select **Test**.

A message appears, stating whether the syntax is correct.

Built-in Functions

This topic describes the built-in functions that you can use to create a calculation formula. You can also create [your own calculation function \(on page 2136\)](#).



Note:

- In this table, `Time` refers to the actual time; this time can include absolute and relative time shortcuts. Refer to the [Date/Time Shortcuts \(on page 2138\)](#) section for more information.
- You cannot control the timestamp of the stored sample. It is determined by the triggering tag or polling schedule.
- You cannot use microseconds for any of the built-in calculation functions.

For all the functions that retrieve previous values, it is similar to performing a `RawByNumber` query with a count of 1 and direction of backward. A less-than operation (not less-than-or-equal-to) is used on the timestamp to get the sample. Similarly, for all the functions that retrieve next values, it is similar to performing a `RawByNumber` query with a count of 1 and direction of forward. A greater-than operation (not greater-than-or-equal-to) is used on the timestamp to get the sample.

Function Name	Description
<code>CurrentValue(<tag name>)</code>	The value of the tag, interpolated to the calculation execution time. The <code>CurrentValue</code> function returns 0 if the quality is 0 (bad quality). This occurs if you initialized it to 0, or if a previous call failed.
<code>CurrentQuality(<tag name>)</code>	The current quality of the tag (0 for bad quality and 100 for good quality).
<code>CurrentTime</code>	The calculation execution time, which becomes the timestamp of the stored value.

Function Name	Description
	<p>For real time processing of polled tags, the calculation execution time is the time when the calculation is triggered. For unsolicited tags, the calculation execution time is the timestamp delivered with the subscription.</p> <div data-bbox="375 470 1419 646" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: When a calculation is performed, the timestamp of the result is the time that the calculation has begun, not the time that it completed.</p> </div> <p>For recovery of polled or unsolicited tags, the calculation execution time is the time when the calculation would have been performed if the collector were running.</p>
Previous-Value(<tag name>, Time)	The tag value of the raw sample prior to the current time.
Previous-Quality(<tag name>, Time)	The quality of the tag (0 for bad quality and 100 for good quality) prior to the current time.
Previous-GoodValue(<tag name>, Time)	The latest good value of the raw sample prior to the current time.
Previous-GoodQuality(<tag name>, Time)	The good quality of the raw sample prior to the current time.
Previous-Time(<tag name>, Time)	The timestamp of the raw sample prior to the current time.
Previous-GoodTime(<tag name>, Time)	The timestamp of the latest good quality of the raw sample prior to the current time.

Function Name	Description
NextValue(<tag name>, Time)	The value of the raw sample after the current timestamp.
NextQuality(<tag name>, Time)	The quality of the tag (0 for bad quality and 100 for good quality) after the current time.
NextTime(<tag name>, Time)	The timestamp of the raw sample after the current timestamp.
NextGoodValue(<tag name>, Time)	The value of the good raw sample after the current time.
NextGoodQuality(<tag name>, Time)	The good quality of the raw sample after the current time.
NextGoodTime(<tag name>, Time)	The timestamp of the good raw sample after the current time.
InterpolatedValue(<tag name>, Time)	The tag value, interpolated to the time that you enter.
Calculation	Unfiltered calculated data query that returns a single value, similar to the Excel Add-In feature. For a list of the calculation mode, refer to Calculation Modes (on page 1073) .
AdvancedCalculation	Unfiltered calculated data query that returns a single value, similar to the Excel Add-In feature. For a list of the calculation mode, refer to Calculation Modes (on page 1073) .
AdvancedFilteredCalculation	Advanced Filtered calculated data query that returns a single value, similar to the Excel Add-In feature.
FilteredCalculation	Filtered calculated data query that returns a single value, similar to the Excel Add-In feature.

Function Name	Description
<code>LogMessage(string_message)</code>	<p>Allows you to write messages to the Calculation collector or the Server-to-Server collector log file for debugging purposes. The collector log files are located in the <code>Historian\LogFiles</code> folder.</p> <div style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note: The <code>LogMessage</code> function is the only function that does not appear in the wizard.</p> </div>
<code>GetMultiFieldValue(Variable, <field name>)</code>	<p>Returns the value of the field that you have specified. The variable contains the current value of all the fields of a multi-field tag. Before using this function, you must read the tag into a variable, using the <code>CurrentValue()</code> function. You can then use the <code>GetMultiFieldValue</code> function to access the value of the field.</p> <p>The value of the field that you enter must be the same as the name of the field in the user defined type. If the field name is not found, a null value is returned.</p>
<code>GetMultiFieldQuality(Variable, <field name>)</code>	<p>Returns the quality (0 for bad quality and 100 for good quality) of the field that you have specified. The variable contains the current value of all the fields of a multi-field tag. Before using this function, you must read the tag into a variable, using the <code>CurrentValue()</code> function. You can then use the <code>GetMultiFieldValue</code> function to access the value of the field.</p> <p>The value of the field that you enter must be the same as the name of the field in the user-defined type. If the field name is not found, a null value is returned.</p> <p>If the user-defined type can store individual quality, you get the field quality. Otherwise, you get the sample quality.</p>
<code>SetMultiFieldValue(Variable, <field name>, Value, Quality)</code>	<p>Sets the value and the quality for the field that you have specified.</p> <p>You can use this function to construct a multifold value containing values for each field, and then use the <code>result=</code> syntax to store the value in Historian.</p>

Counting the Number of Bad Quality Samples

The following example shows how to loop through samples of a tag named C2 to count the number of bad quality samples.

```

Dim count, starttime, endtime, tagquality count=0
StartTime=CurrentTime EndTime=DateAdd("n",-1,StartTime) Do while StartTime>EndTime
TagQuality=PreviousQuality("C2",StartTime)
starttime=PreviousTime("C2",StartTime) IF TagQuality=0 THEN
count=count + 1
END IF loop Result=count

```

Counting the Number of Collected Digital 1s For a Tag

The following example counts the number of collected digital 1s for a tag so that, for instance, you can determine how many times a pump is turned ON and OFF.

```

Dim count, starttime, endtime,tagquality,TagValue
count=0
StartTime=CurrentTime
EndTime=DateAdd("h",-1,StartTime)
On error resume next
Do while StartTime>=EndTime
TagValue=PreviousValue("FIX.DI.F_CV",StartTime)
TagQuality=PreviousQuality("FIX.DI.F_CV",StartTime)
starttime=PreviousTime("FIX.DI.F_CV",StartTime)
IF TagQuality=100 AND TagValue=1 then
count=count + 1
END IF
loop
Result=count

```

Determining the Trigger When Using Multiple Trigger Tags

The following example shows how to determine which tag triggered the calculation, from a list of two possible trigger tags. The example compares the two trigger tags and determines which one has the newest raw sample. This method of getting the newest raw sample can also be used to determine if a remote collector is sending data or is disconnected from the server.

In this example, archive compression is disabled for both of these tags.

```

dim timetag1
dim timetag2
dim tag1
dim tag2

```

```

tag1 = "BRAHMS.AI1.F_CV"
tag2 = "BRAHMS.AI2.F_CV"

' Get the timestamp of the newest raw sample for tag1:
timetag1 = previousTime(tag1, CurrentTime)

' Get the timestamp of the newest raw sample for tag2:
timetag2 = previousTime(tag2, CurrentTime)

if timetag1 > timetag2 then
' If tag1 triggered me, then:
result = 1 else
' If tag2 triggered me, then:
result = 2
end if

```

Using Array or Multifield Data in Calculation

You can create tags of arrays and multifield types and use the Calculation collector, Server-to-Server collector, Server-to-Server distributor with these tags.

Arrays

To use the Array data as input to a calculation formula you can use the name of the array tag like "Array1" or the individual element of the array like "Array1[4]". For example, if you have an array tag "Array1" of floating point values and a calculation tag "FloatCalc1" of float data type, then you can use the array as input to calculate a float value.

```
result = currentvalue("Array1[4]")+5
```

You can use Calculation() function to read the array tag as shown in the following code.

```
Result = Calculation("Array1","Average","Now 1Minute","Now",Quality)
```

In this example, the calculation tag should be an array tag because the average of an array is an array, not a single value. Each element is averaged over the time range. Since an average of an integer or float array is a floating point value, the calculation tag must be a single or double float array.

If you want to find the minimum of array elements in a given time, then use vbscript code to compute and store the result in a Float tag as shown.

```

if CurrentValue("Array1[0]") < CurrentValue("Array1[1]") then
    Result = CurrentValue("Array1[0]")
else
    Result = CurrentValue("Array1[1]")
end if

```

Multifield

If you have a user-defined type "MySample" with fields "r;FloatVal" and "r;IntVal" you can create `Tag1` and use the value of one field in an Integer Calc Tag. The destination tag is not a multifield tag.

```

result = currentvalue("Tag1.IntVal")+5

```

Storing Array or Multifield data in Calculation tags

Array

If your calculation tag is an array tag, then you can copy the entire array values into it. For example, you can copy the entire values from `Array1` into `Array2` using the given code.

```

result = CurrentValue("Array1")

```

You can take an array value collected from a field device and adjust the values before storing it in another array tag `Array2` using this code:

```

dim x
x=CurrentValue("Array1")
x(1) = x(1)+10
result = x

```

You can simply construct an array value inside your formula and store it in `Array2`, for example:

```

dim MyArray(2)' The 2 is the max index not the size
MyArray(0)=1
MyArray(1)=2
MyArray(2)=3 result = MyArray

```

Multifield

You can have the collector combine collected data into a multifield tag. Create a calculation `Tag1` using the user-defined Type "MySample," then use this formula to fill in the fields:

```

Dim InputValue, myval,x,y

```

```

' get the current value of another multifield tag
InputValue = CurrentValue("tag1")

' get the values of each of the fields
x = GetMultiFieldValue(InputValue, "IntVal")
y = GetMultiFieldValue(InputValue, "floatval")

' store the field values in this tag
SetMultiFieldValue myval,"IntVal",x,100
SetMultiFieldValue myval,"floatval",y,100

Result = myval

```

Using Array or Multifield data to trigger calculation

Array

You can use the array tag as a trigger tag for your float or array calculation tags. For example, you can use `Array1` as a trigger so that when it changes, the `"CalcArray1"` tag will be updated. You cannot use an individual array element such as `"Array1[3]"` as a trigger, you must use the entire array tag as the trigger tag.

Multifield

You can use a multifield tag as a trigger tag by either using the tagname `"Tag1"` or tagname with the field name `"Tag1.FloatVal"`.

Sending Array or Multifield data to a Remote Historian

Array

You can use the Server to Server Collector or Server to Server Distributor to send array data to a destination Historian. If the destination Historian is version 6.0 or later, you can simply browse the tags and add them.

You cannot send an array to the older versions of archiver (Pre 6.0 versions) as these archivers will store the array tags as a blob data type in the destination and you will not be able to read them. However, you can send individual elements of an array to these archivers, for example, `result = currentvalue("Array1 [4]")`.

Multifield

The destination needs to be Historian 6.0 or above to store a multifield tag but you can send individual fields to a pre Historian 6.0 archiver.

For multifold tags, you must create the User Defined Type manually at the destination

You can write an entire multifold tag data sample in one write or you can create multiple tags in the destination, one for each field you want to copy. For example, if you have one tag "Tag1" with two fields "FloatVal" and "IntVal" on a source archiver, then you can create two tags ("Tag1.FloatVal" and "Tag1.IntVal") on the destination.



Note:

If you change a field name or add or remove fields you must update your collection and your destination tags.

Reading and writing a Multifold tag using MultiField functions

The following example shows how to read an entire multifold tag, using the `GetMultiFieldValue` function and to write the value to a field in another tag using the `SetMultiFieldValue` function.

```
Dim CurrMultifieldValue

' Read the value of a multi field tag into a variable
CurrMultifieldValue = CurrentValue("MyMultifieldTag")

' Read the field value of multifold tag into the temporary variable
F1 = GetMultiFieldValue(CurrMultifieldValue, "Temperature Field")

' Perform a calculation on the value
Celcius = (F1 32)/ 9* 5

' Set the calculated value to another field of the multifold tag
SetMultiFieldValue(CurrMultifieldValue, "Temperature Field Celcius", Celcius, 100)
result = CurrMultifieldValue
```

User-defined Functions

In addition to the [built-in functions \(on page 2127\)](#), you can create custom calculation functions. After you create a custom calculation function, it is available for use with other calculations as well.

Functions are useful as shortcuts for large blocks of source code. By creating a function out of commonly used calculation formulas, you can save time and effort instead of typing a few lines of calculation formula every time you want to perform the same operation, it is compressed to a single line.

The syntax of a function is simple:

```
Function functionname (variable list)

    [calculation formulas]

End Function
```

The operations a function performs are contained within the Function / End Function statements. If you need to send data to the function a tag name, for example you simply create a variable in the function's parameters to receive the data. Multiple variables must be separated by commas. These variables exist only within the function.

The following is an example of a function. This function, named `checkValue()`, looks at a tag and assigns it an alarm if it is over a specified value.

A Function to Assign an Alarm to a Tag Based on a Condition

The following function, named `checkValue`, assigns an alarm to a tag if the tag value reaches a specified value.

```
Function checkValue (tagname,sourcename,value)

    If CurrentValue(tagname) > value Then

        Set AlarmObj = new Alarm

        AlarmObj.SubConditionName = "HI"

        AlarmObj.Severity = 750

        AlarmObj.NewAlarm

        "alarmname", "Simulated", "tagname", "Now"

        checkValue = true

    Else

        checkValue = false

    End If

End Function
```

If you want to use this function, enter the values for tag name, source name, and value, as shown in the following example:

```
alm_set = checkValue("DD098.FluidBalance","FluidBalance_ALM",5000)
```

In this example, if the value of the DD098.FluidBalance tag exceeds 5000, the function returns a true value, indicating that the alarm was set; the `alm_set` variable will be set to `true`. Otherwise, the `alm_set` variable will be set to `false`.

Create a User-Defined Function

This topic describes how to create your own function to use in a calculation formula. For more information, refer to [User-defined Functions \(on page 2136\)](#). You can also use any of the [built-in functions \(on page 2127\)](#).

Create the tag that you want to use to store the calculation results. You can create the tag manually using [Configuration Hub \(on page 473\)](#), [Historian Administrator \(on page 2057\)](#) or the [Web Admin console \(on page 2059\)](#). Or, you can [copy a tag \(on page 2060\)](#).

1. To create a user-defined function using Configuration Hub:

- a. [Access Configuration Hub \(on page 336\)](#).
- b. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
- c. Select a calculation tag, right-click or select more options, and then select **Calculation**.
The calculation editor appears.
- d. In the **CALCULATION** section, remove `Null` (retain `Result =`).
- e. In the calculation editor, place the cursor in the location where you want to insert the user-defined function.
- f. In the **DETAILS** section, under **User Defined Functions**, select .
The **Add/Edit User Defined Functions (UDF)** window appears.
- g. Select **Add New**.
A function is created with the following naming convention: `UserFunction<number>`. The same function is used in the function editor. You can change the function name by entering the new name in the function editor and selecting **Update UDF**.
- h. Enter the VB script for the function. Or, if you want to use a pre-built function, select the function type and function in the respective fields under **Pre-Built Functions**. And, enter values in the other fields that appear after selecting a function.
The function appears in the function preview below the function editor.
- i. Select **Insert Preview**.
The function is included in the function editor at the cursor position.
- j. To test the function syntax, select .

A message appears, stating whether the function syntax is correct.

- k. Select **Update UDF**.

The user-defined function is created.

- l. To use the function in the calculation formula, select **Insert UDF**.

The function is inserted in the calculation formula at the cursor position.

- m. To test the calculation formula, select .

A message appears, stating whether the syntax is correct.

- n. In the upper-left corner of the page, select **Save**.

The calculation formula is created.

- 2. To create a user-defined function using Historian Administrator:

- a. In Historian Administrator, select **Tags**, select the tag for which you want to create a calculation formula, and then select **Calculation**.

- b. In the **Calculation** section, remove `Null` (retain `Result =`).



Tip:

Avoid selecting other tags until you save your changes or you will lose your code changes.

- c. Select **Functions**.

The **User Defined Functions** window appears.

- d. Select **New**.

The **Edit Function** window appears.

- e. Define the function.

You can build formulas using the wizard, or create it manually by entering functions in the **Edit Function** box. For information, refer to [User-defined Functions \(on page 2136\)](#).

- f. Select **Syntax** to check for errors.

- g. Select **Update**.

Your function appears in the list, and is available for use in other calculations as well.

- h. To use the function, select **Insert Function**.

The function is inserted in your calculation formula.

Date/Time Shortcuts

The following table outlines the date/time shortcuts that you can use in calculation formulas.

Table 383. Date/Time Shortcuts

Shortcut	Description
Now	Now (the time and date that you execute the query)
Today	Today at midnight
Yesterday	Yesterday at midnight
BOY	First day of year at midnight
EOY	Last day of year at midnight
BOM	First day of month at midnight
EOM	Last day of month at midnight

Relative Date/Time Shortcuts

Optionally, you can add or subtract relative times to the following absolute times. You must use them in conjunction with the date/time shortcuts listed in the preceding table (for example, Today+5h+3min instead of 5h3min).

- Second
- Minute
- Hour
- Day
- Week

Create a Calculation Formula Using the Pre-built Functions

This topic describes how to create a calculation formula using the pre-built functions. You can also [create a calculation formula using a VBScript code \(on page 2121\)](#).

For information on a list of the available types and associated functions, refer to [Types of Functions Supported \(on page 2135\)](#). For information on each pre-defined function, refer to [Built-In Functions \(on page 2127\)](#). In addition to the built-in functions, you can create [your own customized functions \(on page 2136\)](#).

1. Create the tag that you want to use to store the calculation results. You can create the tag manually using [Configuration Hub \(on page 473\)](#), [Historian Administrator \(on page 2057\)](#) or the [Web Admin console \(on page 2059\)](#). Or, you can [copy a tag \(on page 2060\)](#).
2. Access the advanced options of the collector, and then disable the **On-line Tag Configuration Changes** option using [Historian Administrator \(on page 2057\)](#). In [Configuration Hub \(on page 473\)](#) this property is available in Collector Options section. If you do so, each time you update a calculation formula, the collector does not reload tags.

1. To create a calculation formula using Configuration Hub:

- a. [Access Configuration Hub \(on page 336\)](#).
- b. In the **NAVIGATION** section, under the Configuration Hub plugin for Historian, select **Tags**.
A list of tags appears.
- c. Select a calculation tag, right-click or select more options, and then select **Calculation**.
The calculation editor appears.
- d. In the **CALCULATION** section, remove `Null` (and retain the `Result =`).
- e. In the Calculation editor, place the cursor in the location where you want to insert the pre-built function.
- f. In the **DETAILS** section, under **Pre-Built Functions**, in the **Function Type** field, select a function type.
Depending on the function type you have selected, a list of functions appears in the **Function** field.
- g. In the **Function** field, select a function.
Based on the selected function, the related fields will be displayed.
- h. Enter values in the other fields that appear after selecting a function.
- i. In the **Input Tag** field, select  , and then select the tag where applicable.
The function preview appears below the calculation editor.
- j. Select **Insert Function**.
The function is inserted at the cursor position.
- k. To test the function, select .

A message appears, stating whether the syntax is correct.

- I. In the upper-left corner of the page, select **Save**.
The calculation formula is created.
2. If you want to create a calculation formula using Historian Administrator:
 - a. [Access Historian Administrator \(on page 823\)](#).
 - b. Select **Tags**, select the tag for which you want to create a calculation formula, and then select **Calculation**.
 - c. In the **Calculation** section, remove `Null` (retain `Result =`).

**Tip:**

Avoid selecting other tags until you save your changes or you will lose your code changes.

- d. Select **Wizard**.
The **Insert Function Wizard** window appears.
- e. Under **Select Function**, select values in the available fields, and then select **Insert**.
- f. If you want to perform an unsolicited (also called event-based) calculation, in the **Type** field, select **Add A Calculation Trigger**. Search and select the tag that you want to add, and then select **Insert**.
The calculation formula is created.
- g. To verify that the syntax is correct, select **Test**.
A message appears, stating whether the syntax is correct.

Types of Functions Supported

The following table describes the types of actions supported. All the value functions return a single value.

Type of Action	Available Functions for the Action
Insert a value	<ul style="list-style-type: none"> • Current value • Previous value • Next value • Interpolated value

Type of Action	Available Functions for the Action
Insert a calculation	<ul style="list-style-type: none"> • Unfiltered calculation • Filtered calculation
Insert a timestamp	<ul style="list-style-type: none"> • Time shortcut • Previous value timestamp • Next value timestamp • Current time
Check data quality	<ul style="list-style-type: none"> • Current value quality • Previous value quality • Next value quality
Set data quality	<ul style="list-style-type: none"> • Set Quality Good • Set Quality Bad
Add data value	Value
Insert a tag name	Tagname
Insert an alarm calculation	<ul style="list-style-type: none"> • Previous Alarm • Next Alarm • Get Alarm Property • Set Alarm Property • Add Event • New Alarm • Update Alarm • Return to Normal
Insert a multifield operation	<ul style="list-style-type: none"> • GetMultiFieldValue • GetMultiFieldQuality • SetMultiFieldValue

Data Input

Calculation and Server-to-Server Collectors

The Calculation and Server-to-Server collectors have some unique behavior not found in other standard collectors. This section provides details about [Recovery \(on page 2152\)](#) and [Manual Recalculation \(on page 2153\)](#).

Recovery

This feature is unique to Calculation and Server-to-Server collectors. If the calculation engine is not running for a period of time, recovery makes it look like it was running. Recovery can also be used to fill in a hole of time where the collector was not able to communicate with the source archiver.

Recovery is applicable to both unsolicited and polled tags. Messages are also recovered. Comments are not recovered.

Normally, it is impossible to go back to the past and collect data. However, since these collectors are 'deriving' data instead of 'collecting' data, it is possible to recover past data, especially since the source of the derived data is archived in the Historian. It is important to understand that while recovery is possible in the calculation and Server-to-Server collectors, it only makes sense for certain types of calculation formulas.

Intended candidates for data recovery are formulas whose only inputs are Historian tags, since past data for these tags can be interpolated. Formulas that use data from external text files or from ADO via CreateObject will most likely not recover correct data because the inputs are not historized. If you are using these types of formulas, you should turn off recovery for the whole collector or insert VBScript code in the formula of individual tags to detect recovery. An example of this is given in the Historian documentation. A similar approach can be used to set a Max Recovery Time on a tag basis, overriding the collector wide setting.

Even calculation tags using only Historian tags as inputs have some caveats for recovery. If you are deriving calculated data from other calculated data, be sure to set up a trigger tag for each of the tags used in your formula. This way the tags will be processed in chain order. All tags are processed in time order.

The recovery logic is not intended to overcome polled collection overruns. If you configure too much collection, then you will get overruns.

You can control the amount of recovered data using Max Recovery Time configuration setting. You can turn off the recovery by setting it to zero.

Manual Recalculation

The Manual re-calc/re-replicate option is often the best choice for generating past derived data.

**Note:**

If you perform a server-to-server recalculation on source and destination servers whose clocks are not synchronized, extra data points may appear and original data points may not be



recalculated. To ensure this does not occur, ensure the time is synchronized on both source and destination servers.

S2S/S2C collector Backfill procedure

With the Recalculate feature you can recalculate all tags for the time period during and after the connection loss. The recalculated tags will use the most accurate values in calculations.

During the period of connection loss, the collector buffers the data. When the connection is restored, the buffered data is forwarded to the Historian Server. When the buffered data arrives, the timestamps show earlier time than the most recent calculation timestamp.

Since the timestamp is earlier, the polled calculations will not execute again with the new data but the unsolicited calculations will re-trigger. Therefore, it is possible that calculations performed for tags during and after the connection loss might be not be entirely accurate.

Run S2C Backfill via Command line

```
ihServerToServerCollector.exe RELOADFILENAME=[file location]
RELOADUSERNAME=[Username] <start time> <end time>
```

Example: C:\Program Files\Proficy\Proficy Historian\x86\Server>ihServerToServerCollector.exe
RELOADFILENAME=c:\taglist.txt RELOADUSERNAME=\Administrator 1516875659 1516875785

For multi-instance support, the command requires the interface name as shown in the following example:

Example for Multi-instance Support: C:\Program Files (x86)\GE Digital\Historian Server to Server
Collector\Server>ihServerToServerCollector.exe RELOADFILENAME=c:\taglist.txt RELOADUSERNAME=
\Administrator 1669462600 1669463200 REG=sekhartest05_To_PredixOFFSS

See the following information about the parameters:

- RELOADFILENAME: This is an optional parameter. File name should be absolute path, this file consists of the tag names, for which Backfill should be performed, each tag should be separated by new line. Any discrepancies in the file/no file exists/parameter not provided leads to Backfill all the tags related to the collector at the current time. After the Backfill, file gets deleted.
- RELOADUSERNAME: This is an optional parameter. This username is used only when destination server is Historian for auditing purpose, and gets ignored when the destination is cloud.

- **TIMESTAMP:** This parameter accepts Start and end time in seconds in epoch format for which Backfill should happen. <https://www.epochconverter.com/>

```

Administrator: Command Prompt - ihServerToServerCollector.exe RELOADFILE...
Microsoft Windows [Version 6.3.9600]
(c) 2013 Microsoft Corporation. All rights reserved.

C:\Users\Administrator>cd\

C:\>cd "Program Files (x86)\GE Digital\Historian Server to Server Collector"

C:\Program Files (x86)\GE Digital\Historian Server to Server Collector>cd Server

C:\Program Files (x86)\GE Digital\Historian Server to Server Collector\Server>ih
ServerToServerCollector.exe RELOADFILENAME=c:\tmp\noexist.tmp RELOADUSERNAME=\Ad
ministrator 1520930410 1520937610
ACK [{"messageId":1,"statusCode":202}] @ Tue Mar 13 16:39:55 2018
ACK [{"messageId":130,"statusCode":202}] @ Tue Mar 13 16:40:26 2018
ACK [{"messageId":371,"statusCode":202}] @ Tue Mar 13 16:40:58 2018
ACK [{"messageId":628,"statusCode":202}] @ Tue Mar 13 16:41:31 2018
ACK [{"messageId":828,"statusCode":202}] @ Tue Mar 13 16:42:02 2018
ACK [{"messageId":1125,"statusCode":202}] @ Tue Mar 13 16:42:33 2018
ACK [{"messageId":1391,"statusCode":202}] @ Tue Mar 13 16:43:04 2018
ACK [{"messageId":1589,"statusCode":202}] @ Tue Mar 13 16:43:35 2018
ACK [{"messageId":1823,"statusCode":202}] @ Tue Mar 13 16:44:06 2018

```

How Data Recovery works:

- When the recovery logic is executed, the collector will setup subscriptions for all the trigger tags.
- Next, it will recover data. The collector first determines how long it has been since the last write. It compares the current time to data in the registry key `LastCalcRepWriteTime`, which stores the last time data was written to the archive. The collector compares this to the Max Recovery Time that is specified in the user settings and performs a raw data query on the shorter of these two periods. Then it will take the shorter of these two and do a raw data query for all trigger tags. It will then process the returned samples in sequential order based on time. For example, if the collector was shut down for 8 hours, but Max Recovery Time was 4 hours, only 4 hours of data would be recovered.
- Recovery is performed before real time processing. Once recovery is complete, it will start polling and processing subscriptions in real time. The subscriptions in real time are queued up till the recovery is done.
- Recovery logic will place an end-of-collection marker at the point in time where the collector was shut down. This end-of-collection marker may or may not be there once the recovery is complete. As part of recovery logic, if it calculates a data point exactly at that timestamp where the end-of-collection marker is there, then it will be overwritten with the calculated good data.
- The recovery logic does not write samples to trigger tags or tags that are just in the formula. It is intended to write samples to the calculation tags.
- Messages are added to the log file that indicate when entering and exiting recovery mode.

Examples

The examples below assume the following tag configuration.

- Machine 1:

Runs Data Archiver, iFIX collector (Collector 1), and Calculation collectors.

- Machine 2:

Runs iFIX collector (Collector 2), which collects and sends data to the archiver in Machine 1 (as a Remote Collector).

TagA and TagB are the iFix tags coming from Collector1 and Collector2, respectively. Both of these tags are scanned at a 1-minute poll rate.

The following example demonstrates the recovery function for an unsolicited 1-minute interval calculation tag that has a simple current value function.

Create an event based 1-minute interval Calculation Tag (CalcTag1) in Machine 1 consisting of the following calculation: `Result=CurrentValue (TagA)`

Stop the Calculation collector for 5 minutes and then restart it to trigger data recovery for the 5-minute shutdown period. For the following example, the Calculation collector was stopped at 2002-12-27 17:05:36 and started at 2002-12-27 17:10:48.

Since there is no interruption for the iFIX collector, the raw data query for TagA results the following output:

Raw Data Query for TagA during shutdown period

114) 81 [2002-12-27 17:02:00:00000] Good NonSpecific
115) 72 [2002-12-27 17:03:00:00000] Good NonSpecific
116) 64 [2002-12-27 17:04:00:00000] Good NonSpecific
117) 56 [2002-12-27 17:05:00:00000] Good NonSpecific
118) 39 [2002-12-27 17:06:00:00000] Good NonSpecific
119) 31 [2002-12-27 17:07:00:00000] Good NonSpecific
120) 22 [2002-12-27 17:08:00:00000] Good NonSpecific
121) 14 [2002-12-27 17:09:00:00000] Good NonSpecific

122) 6 [2002-12-27 17:10:00:00000] Good NonSpecific

A raw data query for CalcTag1 during the shutdown period generates the following:

Raw Data Query for CalcTag1 (before recovery)

96) 81 [2002-12-27 17:02:00:00000] Good NonSpecific

97) 72 [2002-12-27 17:03:00:00000] Good NonSpecific

98) 64 [2002-12-27 17:04:00:00000] Good NonSpecific

99) 56 [2002-12-27 17:05:00:00000] Good NonSpecific

100) 0 [2002-12-27 17:05:36:00000] Bad OffLine

Note that an end-of-collection marker is placed at the shutdown point (that is, at 17:05:36) with a bad data quality.

Once the recovery is complete, this is what we see for the recovered CalcTag1. Note that data during the shutdown period is recovered completely. Compare this result set with the one for TagA. Both are the same.

Raw Data Query for CalcTag1 (after recovery)

96) 81 [2002-12-27 17:02:00:00000] Good NonSpecific

97) 72 [2002-12-27 17:03:00:00000] Good NonSpecific

98) 64 [2002-12-27 17:04:00:00000] Good NonSpecific

99) 56 [2002-12-27 17:05:00:00000] Good NonSpecific

100) 0 [2002-12-27 17:05:36:00000] Bad OffLine

101) 39 [2002-12-27 17:06:00:00000] Good NonSpecific

102) 31 [2002-12-27 17:07:00:00000] Good NonSpecific

103) 22 [2002-12-27 17:08:00:00000] Good NonSpecific

104) 14 [2002-12-27 17:09:00:00000] Good NonSpecific

105) 6 [2002-12-27 17:10:00:00000] Good NonSpecific

Also note that the end-of-collection marker is not overwritten by the recovery logic here. If it calculated a data point exactly at the end-of-collection marker, then it would have been overwritten by the calculated good value.

The following example demonstrates the recovery function for an unsolicited calculation tag that has multiple triggers.

Create an event based Calculation Tag (CalcTag2) in Machine 1 consisting of the following calculation:

```
Result=CurrentValue (TagA) + CurrentValue (TagB)
```

where TagA and TagB are both trigger tags, coming from Collector1 and Collector2 respectively. Set the collection offset of 5 seconds for TagA and 10 seconds for TagB, forcing the calculation to be performed twice per minute.

Stop the Calculation collector for 5 minutes, and then restart it to trigger data recovery for this 5-minutes shutdown period. For the following example, the Calculation collector was stopped at 02/18/2003 12:15:33 and started at 02/18/2003 12:21:53.

Since the iFIX collector was not interrupted, a raw data query for TagA and TagB values generates the following output:

Raw Data Query for TagA during the shutdown period

- 10) 13 [2003-02-18 12:10:05:00000] Good NonSpecific
- 11) 12 [2003-02-18 12:11:05:00000] Good NonSpecific
- 12) 11 [2003-02-18 12:12:05:00000] Good NonSpecific
- 13) 11 [2003-02-18 12:13:05:00000] Good NonSpecific
- 14) 10 [2003-02-18 12:14:05:00000] Good NonSpecific
- 15) 18 [2003-02-18 12:15:05:00000] Good NonSpecific
- 16) 17 [2003-02-18 12:16:05:00000] Good NonSpecific
- 17) 16 [2003-02-18 12:17:05:00000] Good NonSpecific
- 18) 16 [2003-02-18 12:18:05:00000] Good NonSpecific
- 19) 15 [2003-02-18 12:19:05:00000] Good NonSpecific
- 20) 14 [2003-02-18 12:20:05:00000] Good NonSpecific

21) 13 [2003-02-18 12:21:05:00000] Good NonSpecific

Raw Data Query for TagB during the shutdown period

10) 35 [2003-02-18 12:10:10:00000] Good NonSpecific

11) 34 [2003-02-18 12:11:10:00000] Good NonSpecific

12) 33 [2003-02-18 12:12:10:00000] Good NonSpecific

13) 32 [2003-02-18 12:13:10:00000] Good NonSpecific

14) 31 [2003-02-18 12:14:10:00000] Good NonSpecific

15) 31 [2003-02-18 12:15:10:00000] Good NonSpecific

16) 39 [2003-02-18 12:16:10:00000] Good NonSpecific

17) 38 [2003-02-18 12:17:10:00000] Good NonSpecific

18) 37 [2003-02-18 12:18:10:00000] Good NonSpecific

19) 36 [2003-02-18 12:19:10:00000] Good NonSpecific

20) 36 [2003-02-18 12:20:10:00000] Good NonSpecific

21) 35 [2003-02-18 12:21:10:00000] Good NonSpecific

A raw data query for CalcTag2 during the shutdown period generates the following:

Raw Data Query for CalcTag2 (before recovery)

12) 50 [2003-02-18 12:09:05:00000] Good NonSpecific

13) 50 [2003-02-18 12:09:10:00000] Good NonSpecific

14) 49 [2003-02-18 12:10:05:00000] Good NonSpecific

15) 48 [2003-02-18 12:10:10:00000] Good NonSpecific

16) 47 [2003-02-18 12:11:05:00000] Good NonSpecific

17) 46 [2003-02-18 12:11:10:00000] Good NonSpecific

18) 45 [2003-02-18 12:12:05:00000] Good NonSpecific

19) 44 [2003-02-18 12:12:10:00000] Good NonSpecific

- 20) 44 [2003-02-18 12:13:05:00000] Good NonSpecific
- 21) 43 [2003-02-18 12:13:10:00000] Good NonSpecific
- 22) 42 [2003-02-18 12:14:05:00000] Good NonSpecific
- 23) 41 [2003-02-18 12:14:10:00000] Good NonSpecific
- 24) 49 [2003-02-18 12:15:05:00000] Good NonSpecific
- 25) 49 [2003-02-18 12:15:10:00000] Good NonSpecific
- 26) 0 [2003-02-18 12:15:11:00000] Bad OffLine

Once data recovery is complete, this is what we see for the recovered data for CalcTag2. Note that data during the shutdown period is completely recovered:

Raw Data Query for CalcTag2 (after recovery)

- 12) 50 [2003-02-18 12:09:05:00000] Good NonSpecific
- 13) 50 [2003-02-18 12:09:10:00000] Good NonSpecific
- 14) 49 [2003-02-18 12:10:05:00000] Good NonSpecific
- 15) 48 [2003-02-18 12:10:10:00000] Good NonSpecific
- 16) 47 [2003-02-18 12:11:05:00000] Good NonSpecific
- 17) 46 [2003-02-18 12:11:10:00000] Good NonSpecific
- 18) 45 [2003-02-18 12:12:05:00000] Good NonSpecific
- 19) 44 [2003-02-18 12:12:10:00000] Good NonSpecific
- 20) 44 [2003-02-18 12:13:05:00000] Good NonSpecific
- 21) 43 [2003-02-18 12:13:10:00000] Good NonSpecific
- 22) 42 [2003-02-18 12:14:05:00000] Good NonSpecific
- 23) 41 [2003-02-18 12:14:10:00000] Good NonSpecific
- 24) 49 [2003-02-18 12:15:05:00000] Good NonSpecific
- 25) 49 [2003-02-18 12:15:10:00000] Good NonSpecific

- 26) 0 [2003-02-18 12:15:11:00000] Bad OffLine
- 27) 48 [2003-02-18 12:16:05:00000] Good NonSpecific
- 28) 56 [2003-02-18 12:16:10:00000] Good NonSpecific
- 29) 55 [2003-02-18 12:17:05:00000] Good NonSpecific
- 30) 54 [2003-02-18 12:17:10:00000] Good NonSpecific
- 31) 54 [2003-02-18 12:18:05:00000] Good NonSpecific
- 32) 53 [2003-02-18 12:18:10:00000] Good NonSpecific
- 33) 52 [2003-02-18 12:19:05:00000] Good NonSpecific
- 34) 51 [2003-02-18 12:19:10:00000] Good NonSpecific
- 35) 50 [2003-02-18 12:20:05:00000] Good NonSpecific
- 36) 50 [2003-02-18 12:20:10:00000] Good NonSpecific
- 37) 49 [2003-02-18 12:21:05:00000] Good NonSpecific
- 38) 48 [2003-02-18 12:21:10:00000] Good NonSpecific
- 39) 47 [2003-02-18 12:22:05:00000] Good NonSpecific
- 40) 46 [2003-02-18 12:22:10:00000] Good NonSpecific

The following example demonstrates the recovery function for an unsolicited calculation tag that has multiple triggers, but for which none of the triggers is in the formula.

TagA and TagB are the iFix tags coming from Collector1 and Collector2, respectively. Both tags are scanned at a 1-minute poll rate. This example uses two more iFix tags, TagC and TagD, coming from Collector1.

Create an event-based Calculation Tag (CalcTag3) in Machine 1 consisting of the following calculation:

```
Result=CurrentValue (TagA) + CurrentValue (TagB)
```

Make sure that the trigger tags for this calculation tag are TagC and TagD, which are not in the formula. Set the collection offset of 5 seconds for TagC and 10 seconds for TagD, forcing the calculation to be performed twice per minute.

Stop the Calculation collector for 5 minutes, and then restart it to trigger data recovery for this 5-minutes shutdown period. For the following example, the Calculation collector was stopped at 02/18/2003 02:24:37 and started at 02/18/2003 02:31:44.

Since the iFIX collector was not interrupted, a raw data query for TagA and TagB values generates the following output:

Raw Data Query for TagA during shutdown period

56) 13 [2003-02-18 14:21:05:00000] Good NonSpecific
57) 12 [2003-02-18 14:22:05:00000] Good NonSpecific
58) 11 [2003-02-18 14:23:05:00000] Good NonSpecific
59) 11 [2003-02-18 14:24:05:00000] Good NonSpecific
60) 10 [2003-02-18 14:25:05:00000] Good NonSpecific
61) 19 [2003-02-18 14:26:05:00000] Good NonSpecific
62) 18 [2003-02-18 14:27:05:00000] Good NonSpecific
63) 17 [2003-02-18 14:28:05:00000] Good NonSpecific
64) 16 [2003-02-18 14:29:05:00000] Good NonSpecific
65) 16 [2003-02-18 14:30:05:00000] Good NonSpecific
66) 15 [2003-02-18 14:31:05:00000] Good NonSpecific

Raw Data Query for TagB during shutdown period

141) 36 [2003-02-18 14:20:10:00000] Good NonSpecific
142) 36 [2003-02-18 14:21:10:00000] Good NonSpecific
143) 35 [2003-02-18 14:22:10:00000] Good NonSpecific
144) 34 [2003-02-18 14:23:10:00000] Good NonSpecific
145) 33 [2003-02-18 14:24:10:00000] Good NonSpecific
146) 32 [2003-02-18 14:25:10:00000] Good NonSpecific
147) 31 [2003-02-18 14:26:10:00000] Good NonSpecific

148) 31 [2003-02-18 14:27:10:00000] Good NonSpecific

149) 39 [2003-02-18 14:28:10:00000] Good NonSpecific

150) 38 [2003-02-18 14:29:10:00000] Good NonSpecific

151) 37 [2003-02-18 14:30:10:00000] Good NonSpecific

152) 36 [2003-02-18 14:31:10:00000] Good NonSpecific

A raw data query for CalcTag3 during the shutdown period generates the following:

Raw Data Query for CalcTag3 (before recovery)

6) 49 [2003-02-18 14:21:05:00000] Good NonSpecific

7) 49 [2003-02-18 14:21:10:00000] Good NonSpecific

8) 48 [2003-02-18 14:22:05:00000] Good NonSpecific

9) 47 [2003-02-18 14:22:10:00000] Good NonSpecific

10) 46 [2003-02-18 14:23:05:00000] Good NonSpecific

11) 45 [2003-02-18 14:23:10:00000] Good NonSpecific

12) 45 [2003-02-18 14:24:05:00000] Good NonSpecific

13) 44 [2003-02-18 14:24:10:00000] Good NonSpecific

14) 0 [2003-02-18 14:24:11:00000] Bad OffLine

A data query for the recovered CalcTag3 values once data recovery is complete generates the following.

Note that data during the shutdown period is completely recovered:

Raw Data Query for CalcTag3 (after recovery)

6) 49 [2003-02-18 14:21:05:00000] Good NonSpecific

7) 49 [2003-02-18 14:21:10:00000] Good NonSpecific

8) 48 [2003-02-18 14:22:05:00000] Good NonSpecific

9) 47 [2003-02-18 14:22:10:00000] Good NonSpecific

10) 46 [2003-02-18 14:23:05:00000] Good NonSpecific

- 11) 45 [2003-02-18 14:23:10:00000] Good NonSpecific
- 12) 45 [2003-02-18 14:24:05:00000] Good NonSpecific
- 13) 44 [2003-02-18 14:24:10:00000] Good NonSpecific
- 14) 0 [2003-02-18 14:24:11:00000] Bad OffLine
- 15) 43 [2003-02-18 14:25:05:00000] Good NonSpecific
- 16) 42 [2003-02-18 14:25:10:00000] Good NonSpecific
- 17) 51 [2003-02-18 14:26:05:00000] Good NonSpecific
- 18) 50 [2003-02-18 14:26:10:00000] Good NonSpecific
- 19) 49 [2003-02-18 14:27:05:00000] Good NonSpecific
- 20) 49 [2003-02-18 14:27:10:00000] Good NonSpecific
- 21) 48 [2003-02-18 14:28:05:00000] Good NonSpecific
- 22) 56 [2003-02-18 14:28:10:00000] Good NonSpecific
- 23) 55 [2003-02-18 14:29:05:00000] Good NonSpecific
- 24) 54 [2003-02-18 14:29:10:00000] Good NonSpecific
- 25) 54 [2003-02-18 14:30:05:00000] Good NonSpecific
- 26) 53 [2003-02-18 14:30:10:00000] Good NonSpecific
- 27) 52 [2003-02-18 14:31:05:00000] Good NonSpecific
- 28) 51 [2003-02-18 14:31:10:00000] Good NonSpecific
- 29) 49 [2003-02-18 14:32:05:00000] Good NonSpecific
- 30) 49 [2003-02-18 14:32:10:00000] Good NonSpecific
- 31) 48 [2003-02-18 14:33:05:00000] Good NonSpecific
- 32) 47 [2003-02-18 14:33:10:00000] Good NonSpecific

Examples of Calculation Formulas

Converting a Collected Value

The following code sample converts a temperature value from degrees Celsius to degrees Fahrenheit.

```
Result=CurrentValue("Temp F")*(9/5)+32
```

Calculations Inside Formulas

The following code sample contains a calculation within a formula. In this case, we are taking the average of values of the tag `Simulation00001` over the previous hour. Typically, use a polled trigger to schedule the execution of the formula.

```
Result=Calculation("Simulation00001","Average","Now-1hour","Now",Quality)
```

Conditional Calculation

The following code sample stores the value of a tag only if it is 100.

```
IF CurrentQuality("Simulation00001")=100 THEN
Result=CurrentValue("Simulation00001")
END IF
```

Combining Tag Values and Assigning a Trigger

The following code sample adds current values of multiple tags using two calculation triggers.

```
Result=CurrentValue("SERVER1.Simulation00003")+CurrentValue("SERVER1.Simulation00006")
```

The calculation triggers used in the sample are `SERVER1.Simulation0003` and `SERVER1.Simulation0006`. The calculation is triggered if the value of either `Server1.Simulation0003` or `Server1.Simulation0006` changes.

Using CreateObject in a Formula

The following code sample reads data from another Historian Server using the Historian OLE DB provider, and stores it in a destination tag. When using this example, specify the username and password.

```
'connection and recordset variables
Dim Cnxn
Dim rsCurrentValueFromOtherServer
'open connection
Set Cnxn = CreateObject("ADODB.Connection")
```

```
'connect to default server using current username and password
'establish connection
Cnxn.Open "Provider=ihOLEDB.iHistorian.1;User Id=;Password="
'Create and open first Recordset using Connection execute
Set rsCurrentValueFromOtherServer = CreateObject("ADODB.Recordset")
'Get the value from the other server
Set rsCurrentValueFromOtherServer = Cnxn.Execute("select value from ihRawData
where SamplingMode=CurrentValue and tagname = Simulation00001")
'Set the result to the current value of other tag
Result=rsCurrentValueFromOtherServer("Value")
'Clean up
IF rsCurrentValueFromOtherServer.State = adStateOpen THEN
rsCurrentValueFromOtherServer.Close
END IF
IF Cnxn.State = adStateOpen THEN Cnxn.Close
END IF
Set rsCurrentValueFromOtherServer = Nothing
Set Cnxn = Nothing
```

Using a File

The following code sample shows how to read and write text files during a calculation. You may have data in a file to use as input to a calculation, or you may want to write debug values to a text file instead of using the `LogMessage` function.

```
Dim filesystem, writefile, count,readfile
'need to create a file system object since there is no
'file I/O built into VBScript
Set filesystem = CreateObject("Scripting.FileSystemObject")
'open the text file, or create it if it does not exist
set readfile = filesystem.OpenTextFile("C:\somefile.txt", 1, true)
'try to read from the file
IF readfile.AtEndOfLine <> true THEN
count= readfile.ReadAll
END IF
'add one to the number stored in the count count = count+1
'close the file for reading
readfile.Close
'open the same file but for writing
```

```

Set writefile= filesystem.OpenTextFile("C:\somefile.txt", 2, true)

'write the updated count writefile.Write count

'close file for writing

writefile.Close

Result = count

```

Converting a Number to a String

If your device and collector expose data as numeric codes, you can change to a string description. This examples also demonstrates that a calculation can output a string.

```

DIM X

x=CurrentValue ("tag1")

select case x

case 1

Result="one"

case 2

Result="two"

case else

Result="other"

End select

```

Detecting Recovery Mode Inside a Formula

The following code sample detects the recovery mode or recalculation inside a formula. If there are individual tags, you do not want to perform a recovery.

```

Dim MAXDIFF, TimeDiff

'Maximum difference in timestamps allowed (Must be > 2,
'units = seconds) MAXDIFF = 10

'Calculate time difference

TimeDiff = DateDiff("s", CurrentTime(), Now)

'Compare times, if difference is < MAXDIFF seconds perform calc

If TimeDiff < MAXDIFF Then

'Place calculation to be performed here:

Result = CurrentValue("DENALI.Simulation00001") Else

'Place what is to be done when no calc is performed here

Result = Null

End If

```

Looping Through Data Using the SDK

The following code sample uses the SDK to perform a query on a data set. It determines the minimum raw value over a one-hour time period.

```
on error resume next

Dim MyServer 'As Historian_SDK.Server

Dim I

Dim J

Dim K

Dim strComment

Dim lngInterval

Dim TagCount

Dim strDataQuality

Dim iDataRecordset

Dim iDataValue

Dim lEndTime, lStartTime, lNumSamples

Dim lNumSeconds, lNumSamplesPerSecond

Dim RawMin

'Instantiate The SDK

Set MyServer = CreateObject("iHistorian_SDK.Server")

'Attempt Connection

If Not MyServer.Connect("DENALI", "administrator","") Then

result = err.description

else

Set iDataRecordset = MyServer.Data.NewRecordset

'Find the number of samples.

'build query

With iDataRecordset

.Criteria.Tagmask = "EIGER.Simulation00001"

.Criteria.StartTime = DateAdd("h",-1,Now)

.Criteria.EndTime = Now

.Criteria.SamplingMode = 4 'RawByTime

.Criteria.Direction = 1 'forward

.Fields.AllFields

'do query

If Not .QueryRecordset Then

result = err.description
```

```

End If

'Some Large number so that real samples are less
RawMin = 1000000

For I = 1 To iDataRecordset.Tags.Count
For J = 1 To iDataRecordset.Item(I).Count
Set iDataValue = iDataRecordset.Item(I).Item(J)

' if the value is good data quality
if iDataValue.DataQuality = 1 then
if iDataValue.Value < RawMin then

rawMin = iDataValue.Value

end if

end if

lNumSamples = lNumSamples + 1

Next

Next

End With

End If

Result = RawMin

'Disconnect from server
MyServer.Disconnect

```

Using an ADO Query

The following code sample uses a query combining Historian data with ADO data. In the example, you convert a collected value, number of barrels per day (`BarrelsUsedToday`), to a dollar amount. The code then obtains the price per barrel (`CostOfBarrel`) from the SQL server, and finally stores the total dollars in an integer tag (`TotalCostToday`).

You can also do this with a linked server and the Historian OLE DB provider, but this example maintains a history of the results.

```

Dim CostOfBarrel, BarrelsUsedToday, TotalCostToday

'Calculate the total number of barrels used over
'the previous 24hours.

BarrelsUsedToday = Calculation("BarrelsUsedTag", "Total", "Now 1Day", "Now", Quality)

'Retrieve cost per barrel used

Dim SQLExpression

Dim Cnxn

Dim rsCurrentValue

```

```

SQLExpression = "SELECT Barrel_Cost AS Value1 FROM RawMaterial_Costs WHERE Barrel_Type = CrudeOil and
samplingmode = CurrentValue"

'open connection

Set Cnxn = CreateObject("ADODB.Connection")

'connect to default server using current username and password

'establish connection

Cnxn.Open "Provider=SQLOLEDB.1;User ID=sa; Password=;Initial Catalog=Northwind"

'Create and open first Recordset using Connection execute

Set rsCurrentValue = CreateObject("ADODB.Recordset")

'Get the value from the other server

Set rsCurrentValue= Cnxn.Execute(SQLExpression)

'Set the result to the current value of other tag

CostOfBarrel = rsCurrentValue("Value1")

'Clean up

If rsCurrentValue.State = adStateOpen then

rsCurrentValue.Close

End If

If Cnxn.State = adStateOpen then

Cnxn.Close

End If

Set rsCurrentValue = Nothing

Set Cnxn = Nothing

'Retrieve number of barrels used

BarrelsUsedToday = Calculation("BarrelsUsed", "Count", "Now 1Day", "Now", Quality)

'Calculate total cost of barrels today

TotalCostToday = CostOfBarrel * BarrelsUsedToday

```

Windows Performance Statistics Physical Memory Usage

The following code sample creates a formula that collects data reflecting private byte usage.

```

`Get a reference to the local data archiver process object

Set RawProc = GetObject("winmgmts:Win32_PerfRawdata_Perfproc_process.name='ihDataArchiver.'")

`Scale the virtual bytes number to a value within

`the tag's EGU range

result =RawProc.PrivateBytes *.001

```

Windows Performance Statistics Virtual Memory Usage

The following code sample creates a formula that collects data reflecting virtual byte usage.

```
`Get a reference to the local data archiver process object

    Set RawProc = GetObject("winmgmts:Win32_PerfRawdata_Perfproc_process.name='ihDataArchiver.'")

`Scale the virtual bytes number to a value within the

`tag's EGU range

result =RawProc.VirtualBytes *.0001
```

Determining Collector Downtime

The following code sample determines the amount of downtime, in seconds, that the Calculation collector has experienced over the last day. Downtime occurs when there are two consecutive bad quality data points for the pulse tag. If the last known data point for the pulse tag is bad quality, all the time between its timestamp and the current time is regarded as downtime. In the following sample, the pulse tag is configured to be polled, with a collection interval of one day.

```
Dim pulseTag, totalDowntime, startTime, endTime

Dim prevTime, prevQuality, lastPrevTime, lastPrevQuality

pulseTag = "calcPulseTag"

totalDowntime = 0

endTime = CurrentTime()

startTime = DateAdd("d", -1, endTime)

lastPrevTime = curTime lastPrevQuality = 0

Do

    'get the timestamp and quality of the tag value previous to the last one we checked

    On Error Resume Next

    prevTime = PreviousTime(pulseTag, lastPrevTime)

    If Err.Number <> 0 Then

        'no more values for this tag exit gracefully

        Exit Do

    End If

    prevQuality = PreviousQuality(pulseTag, lastPrevTime)

    'if we have two consecutive bad data points, add to the downtime

    If prevQuality = 0 And lastPrevQuality = 0 Then

        If prevTime > startTime Then

            totalDowntime = totalDowntime + DateDiff("s", prevTime, lastPrevTime)

        Else

            totalDowntime = totalDowntime + DateDiff("s", startTime, lastPrevTime)
```

```

End If
End If

'store the timestamp and quality for comparison with the next values
lastPrevQuality = prevQuality

lastPrevTime = prevTime

Loop While lastPrevTime > startTime
Result = totalDownTime

```

Analyzing the Collected Data

The following code sample analyzes the collected data to determine the amount of time that a condition was true and had good quality in the last day.

```

Dim tagName, startTime, endTime

tagName = "testTag"

startTime = "Now 1Day"

endTime = "Now"

Result = CalculationFilter(tagName, "TotalTimeGood", startTime, endTime, 100, tagName, "AfterTime", "Equal", 1)

```

Simulating Demand Polling

To simulate demand polling, create the following tags.


Tag	Description
Polled Tag	A polled tag with a collection interval of the longest period you want between raw samples. Do not enable collector or archive compression. This tag should point to the same source address as the unsolicited tag.
Unsolicited Tag	An unsolicited tag with a 0 or 1 second collection interval. This tag ensures you will be notified whenever changes occur. This tag should point to the same source address as the polled tag.
Combined Tag	An unsolicited calculation tag that is triggered by either the polled tag or the unsolicited tag, and combines the raw samples of both into a single tag. Use a 0 or 1 second collection interval and use the following formula: <pre> dim timetag1 dim timetag2 dim tag1 dim tag2 Dim x </pre>

Tag	Description
	<pre>tag1 = "T20.di-1.F_CV" tag2 = "t20.T20.DI-1.F_CV" x = DateAdd("s", 1,CurrentTime) ' add 1 second to calc time ' Get the timestamp of the newest raw sample for tag1: timetag1 = previousTime(tag1, x) ' Get the timestamp of the newest raw sample for tag2: timetag2 = previousTime(tag2, x) if timetag1 > timetag2 then ' If tag1 triggered me, then: result = PreviousValue(tag1,CurrentTime) else ' If tag2 triggered me, then: result = PreviousValue(Tag1, CurrentTime) end if</pre>

Chapter 34. The Server-to-Server Distributor

Overview of the Server-to-Server Distributor

The Historian Server-to-Server distributor is used to send data from a smaller Historian server to a larger, centralized Historian server. You can then use this data for reporting and analytics.



You can use either the Server-to-Server collector or the Server-to-Server distributor to send data to a central Historian. However, using the Server-to-Server distributor has the following advantages:

- It simplifies the process of configuring tags at the destination Historian.
- It provides more flexibility at the SCADA level for tag configuration compared to the Server-to-Server collector.
- It allows you to manage tags both from the source and destination Historian servers, whereas the Server-to-Server collector allows you to manage tags only from the destination Historian server.

You cannot, however, use the Server-to-Server distributor to send data to a cloud destination. Use the Server-to-Server collector for this purpose.

Features

- You can browse the source for tags and their attributes.
- Only the unsolicited data collection is supported; polled collection is not supported.
- The supported timestamp resolution is 100 milliseconds.
- The collector accepts device timestamps.
- The collector supports data compression.
- Floating point, integer, and string data are supported.

Limitations

- The Server-to-Server distributor forwards only raw data samples, messages, and alarms. It does not perform any calculations on the data.

Workflow for Using the Server-to-Server Distributor

To use the Server-to-Server distributor, you must perform the following tasks:

Number	Task	Notes
1	Install the collectors (on page 142) on the source Historian server.	This step is required. This will place the collector binaries on the machines.
2	Add an instance of the Server-to-Server distributor (on page 563) on the source Historian server.	This step is required.
3	Start the Server-to-Server distributor (on page 637) .	This step is required.
4	Configure the Server-to-Server distributor (on page 563) .	This step is required only if you want to change the default values.
5	Create a destination tag. You can do so by browsing for the tag (on page 672) , adding it manually (on page 473) , or copying a tag (on page 700) .	This step is required. The naming convention of the tag is <code>nodename.<name of the tag></code> . If configured, the tag will contain a prefix.

Configure the Server-to-Server Distributor

1. [Access Historian Administrator \(on page 822\)](#) on the source Historian server.
2. Select the Server-to-Server distributor from the list of collectors, and then select **Configuration**. The **Collector Specific Configuration (ServerToServerDistributor)** section appears.

Collector Specific Configuration (ServerToServerDistributor)

Source Server

Alarm Replication

Message Replication

Calculation Timeout (sec)

Max Recovery Time (hr)

Add Prefix To Messages

3. Provide values as specified in the following table, and then select **Update**.

Field	Description
Source Server	The source Historian server that you want to use.
Alarm Replication	Indicates whether you want all the alarm data to be transferred from the source server to the destination server. If you enable alarm replication, you must also enable alarm recovery. However, if you set the Max Recovery Time value to zero, alarm recovery does not happen.
Message Replication	Indicates whether you want message data to be transferred from the source server to the destination server. If you enable message replication, you must also enable message recovery. However, if you set the Max Recovery Time value to zero, message recovery does not happen.
Calculation Timeout (sec)	The maximum time allowed for a tag's calculation formula to execute before being terminated. The default value is 10 seconds.
Max Recovery Time (hr)	The maximum duration, in hours, for which the collector will attempt to restore data during recovery logic. The default value is 4 hours.
Add Prefix to Messages	The prefix to identify replicated messages on the destination. Alarms and events data will automatically have a prefix added to it with the following syntax: <code>MachineName_Datasource</code>

Field	Description
	For example, if your alarm is forwarded from the server <code>Almserver12</code> with a data source named <code>OPCAE</code> , the prefix will be <code>Almserver12_OPCAЕ</code> .

The Server-to-Server distributor is configured.

Chapter 35. The Simulation Collector

Overview of the Simulation Collector

The Simulation collector generates random numbers and string patterns for demonstration purposes. You can configure the number of tags that you want to generate.

Features:

- The collector generates random scaled values between 0 and 32,767. It uses the high and low engineering units fields of each tag to scale the 0 to 32,767 pre-set values into appropriate engineering units.
- The collector also provides five-string simulation tags that generate random alphanumeric data.
- In addition to generating random values, the collector can generate sequential values for some tags. For a list of such tags, refer to [Tags with Sequential Values \(on page 2560\)](#).
- You can import browse for tags and their attributes.
- The supported timestamp resolution is 1ms.
- Floating point, integer, and string data are supported. Binary data is not supported.
- You can create Python Expression tags.
- Only polled data collection is supported with a minimum poll interval of 100ms.



Note:

You can create more simulation string tags by manually adding string tags with the following naming convention to the collector: `CollectorName.Simulation.StringXXXX`

Supported Tag Attributes:

- Tagname
- Data Type
- Hi Engineering Units
- Lo Engineering Units
- Hi Scale
- Lo Scale

Configuration

Configure the Simulation Collector Using Configuration Hub

[Install collectors \(on page 143\)](#), and [create an instance of the collector \(on page 567\)](#).

1. [Access Configuration Hub \(on page 336\)](#).
2. Select **Collectors**, and then select the File collector instance that you want to configure.
The fields specific to the collector instance appear in the **DETAILS** section.
3. Enter values as specified in the following table.

Field	Description
Number of Tags	The number of Historian tags that you want the create for the collector.
Function Period (seconds)	The period, in seconds, of the <code>SIN,STEP</code> , and <code>RAMP</code> functions implemented in the collector.
MTLS Security	Indicates whether you want to use Mutual TLS (MTLS) protocol to enforce a secure and strong authentication mechanism.
MTLS Data Encryption	Indicates whether you want to encrypt the data that the collector shares to the data archiver (DA).
For more information on how to enable MTLS Security, refer to Enable MTLS Security (on page 632) .	

4. As needed, enter values in [the other sections common to all collectors \(on page 579\)](#).
5. Restart the collector.
The collector instance is configured.

Configure the Simulation Collector Using Historian Administrator

[Install collectors \(on page 143\)](#), and [create an instance of the collector \(on page 567\)](#).

1. Access [Historian Administrator \(on page 823\)](#).
2. Select **Collectors**, and then select the Simulation collector instance that you want to configure.
The fields specific to the collector instance appear.

Collector Specific Configuration (Simulation)

Number of Tags

Function Period (seconds)

3. Enter values as specified in the following table.

Field	Description
Number of Tags	The number of Historian tags that you want the create for the collector.
Function Period (seconds)	The period, in seconds, of the <code>SIN,STEP</code> , and <code>RAMP</code> functions implemented in the collector.

4. As needed, enter values in [the other sections \(on page 579\)](#).

5. Restart the collector.

The collector instance is configured.

Tags with Sequential Values

In addition to generating random values, the Simulation collector generates sequential values. The following table provides a list of tags for which the collector generates sequential values. All the tags have a range of 0 to 1000.

Tags	Description
Constant	Maintains a constant value.

Tags	Description
Constant_1%Noise	Same as Constant, but produces 1% random noise.
Constant_5%Noise	Same as Constant, but produces 5% random noise.
Constant_20%Noise	Same as Constant, but produces 20% random noise.
Ramp	Steadily increases value every polling period to create a smooth upward trend.
Ramp_1%Noise	Same as the Ramp tag, but produces 1% random noise.
Ramp_5%Noise	Same as Ramp tag, but produces 5% random noise.
Ramp_20%Noise	Same as Ramp tag, but produces 20% random noise.
Sin	Produces a Sine wave centered on a value of 500.
Sin_1%Noise	Same as Sine tag, but produces 1% random noise.
Sin_5%Noise	Same as Sine tag but produces 5% random noise.
Sin_20%Noise	Same as Sine tag but produces 20% random noise.
Step	Produces a step trend centered on a value of 500.
Step_1%Noise	Same as Step tag, but produces 1% noise.
Step_5%Noise	Same as Step tag, but produces 5% noise.
Step_20%Noise	Same as Step tag, but produces 20% noise.

Chapter 36. Windows Performance Collector

Windows Performance Collector

Overview of the Windows Performance Collector

The Windows Performance Collector collects Windows performance counter data and sends it to the Historian server for archival. The data collected can be used to monitor and assess the performance and efficiency of the computer running the Historian software and also assess the status of the Historian Archiver and other system statistics derived by the Historian counters. You can collect almost any Windows performance counter that is visible in Windows Performance Monitor and thereby determine if there are any issues with the operating system or the computer that affects the performance.

While both the Windows Performance Monitor and Windows Performance Collector can collect the performance counters data, the collector provides the advantage of storing it in Historian archives, making it easy to view in Historian clients and compare to other data stored in Historian. The archived values can be viewed as the Last 10 Values in Historian Administrator or included in an Excel report together with other Historian data.

You can also use this collector to collect performance data from other GE Intelligent Platforms products such as CIMPLICITY, iFIX, and also Historian's own performance counters.

The Windows Performance Collector collects polled data only and creates Historian tags with the data type that best matches the data type of the performance counter being collected.

Windows Performance Collector - Requirements

To use a Windows Performance Collector, you require Historian 6.0 or higher installed on the following machines:

- The computer running the collector.
- The computer running Data Archiver.
- The computer running the Administrator.

The Windows Performance Collector can only collect performance counters from the local computer it is running on. You can run only one Windows Performance collector on a computer.

Windows Performance Collector Feature Summary

The following table outlines the features of the Windows Performance Collector.

Feature	Capability
Minimum Poll Interval	Yes- 1 second
Unsolicited Collection	No
Timestamp Resolution	Yes- 1 millisecond
Accept Device Timestamps	No
Floating Point Data	Yes
Integer Data	Yes
String Data	Yes
Binary Data	No
Collector Compression	Yes
Reads data, tags	Yes
Start/stop collection from the system	Yes
Condition based Collection Support	No
Python Expression Tags	Yes

**Note:**

Though the Minimum Poll Interval supported by the Windows Performance Collector is 1 second, it is recommended to set the interval to 5 seconds when adding large number of tags for proper collection of data.

Windows Performance Collector Configuration


Understanding Windows Performance Collector Tag Hierarchy

The Windows Performance Collector provides the ability to browse performance tags hierarchically. This hierarchy is different from the hierarchy of the Windows Performance Monitor.

The Windows Performance Collector displays Objects, Instances, and Counters. When you select an Object, its Instances appear in a folder structure under the specific Object. The Objects are displayed as they are added. They are not displayed in an alphabetical order as they are created dynamically. The Counters are displayed on the right. If no counters exist for a particular Instance, they are not displayed.

The following figure provides an example of the hierarchy:

Figure 10. Windows Performance Collector Browse Criteria Screen



In the Windows Performance Collector, while you are collecting data, if any of the counters of any application or process stops running, the collector does not stop showing that particular instance but will continue running it with zero values for that particular Counter. It does not update these counters dynamically.

The Configuration Section for Windows Performance Collector

To access the **Configuration** section for a Windows Performance collector, select the Windows Performance Collector from the list of collectors and select **Configuration**. The following figure appears.

Collector: 2k3sys1_WindowsPerfMon

General | Configuration | Tags | Advanced | Performance | Redundancy

Collector Specific Configuration (Custom)

General 1	<input type="text"/>
General 2	<input type="text"/>
General 3	<input type="text"/>
General 4	<input type="text"/>
General 5	<input type="text"/>



Note:

The fields, General 1 through General 5 are reserved for future use.

Chapter 37. The Wonderware Collector

Overview of the Wonderware Collector

The Wonderware Collector gathers data samples from a Wonderware Historian 2014 R2 Server application and stores the corresponding data entries in the Historian Server.



Note:

Wonderware is a registered trademark of Schneider Electric Software.

This collector supports collecting of analog, digital and string types of data from the Wonderware Historian Server. This collector supports a distributed model, where the Wonderware Historian Server, the Historian Data Collector, and GE Historian software are installed on different machines. Typically, however, the collector is installed on the same computer as the Wonderware Data Archiver and sends data to a remote GE Historian server.

The Wonderware Collector uses unsolicited collection, whereby changes to the Wonderware tags are detected, and are forwarded to the Historian server. Raw samples from the Wonderware Collector are duplicated into the GE Historian data archive.


One Wonderware Collector can collect data from a single Wonderware Historian server. To collect from multiple Wonderware Historian servers to an Historian archiver, you must install multiple collectors.



Note:

The ODBC Driver for the SQL Server is required for the Historian Data Collector for Wonderware installation; however, the ODBC Driver for SQL does not ship with Historian. If the ODBC Driver for SQL is not installed, the Historian Data Collector for Wonderware will not connect to the Wonderware server. If you install the Historian Data Collector for Wonderware on a machine that does not contain the Wonderware server, be sure to install the ODBC Driver for SQL on the machine with the Historian Data Collector for Wonderware.

Limitations: If you want a domain user to use the Wonderware Collector, after you add an instance of a collector, when you later configure it, do not provide values in the **User Name** and **Password** fields. This is because ODBC Driver uses Windows authentication.



Installation Prerequisites

The Historian Data Collector for Wonderware requires the installation of the SQL server native client (`sqlncli.msi`), which can be downloaded from the following link:

<https://support.microsoft.com/en-us/kb/2726013>

Wonderware Collector Features

The following table outlines the features of the Wonderware Collector.

Feature	Capability
Browse Source for Tags	Yes*(on a Wonderware server that supports browsing)
Browse Source for Tag Attributes	Yes
Polled Collection	No


Feature	Capability
Minimum Poll Interval	100 ms (milliseconds)
Unsolicited Collection	Yes
Time stamp Resolution	1 ms
Floating Point Data	Yes
Integer Data	Yes
String Data	Yes
Python Expression Tags	No
Time Assigned	<div data-bbox="901 724 1624 894" style="border: 1px solid #0070C0; border-radius: 5px; padding: 5px;">  Note: You must set this field to Source as the Wonderware Collector only supports unsolicited tags. </div>

Hierarchical Tags Available in Browse

The Schneider Electric Wonderware server supports the hierarchical organization of your tags in a tree structure. Historian uses the server's hierarchy allowing you to browse the Wonderware Collector in the Non-Web Administrator mode.

To browse for data collector tags in a hierarchy:

1. Browse your Wonderware data source for new Wonderware data tags.
2. From the **Collector** list, select the Wonderware Collector you wish to browse. A hierarchical tree appears in the **Browse Results** window.



- To limit the displayed tags to only those that are not collected, from the **Show Only** list select **Source Tags Not Collected** from the drop-down menu.
- To limit the displayed tags to match a tag name or tag description, enter the value to match in the **Source Tag Name** or **Description** text boxes.
- Navigate to the node in the tree you want to browse, and then select **Browse**. The tags within the selected portion of the Wonderware tag hierarchy will be displayed
- Select the tag(s) you want to add to Historian, and select **Add Selected Tags**. Collected tags appear in black text in the tag list.

**Note:**

If Wonderware Collector encounters null value at the time of collecting data, it will be ignored and that specific sample will not be sent to the Historian server.


Supported Data Types for Wonderware Collector

The following table lists the data types recommended for use with Historian.

Data Types	Recommended Historian Data Types
Analog- EuroFloat	Double Float
Analog- MSFloat	Double Float
Analog- MSDouble	Double Float
Analog- Integer	Double Integer
Discrete	Single Integer
String	Variable String

Configuring Wonderware Collector

To access the **Configuration** section for the Wonderware Collector, select the Wonderware Collector from the list on the left of the Administrator Tool **Collectors** section and then select **Configuration**. A page similar to the following appears:



Collector-Specific Configuration for the Wonderware Collector

Enter the value for the Wonderware Collector-specific field parameters:

Field	Description
Server Name	Wonderware Server InSQL Database Server name.
User Name	Wonderware Server InSQL Database User name, for example, wwUser.
Password	Wonderware Server InSQL Database password, for example, XXXXXX.
Recovery Time (hours)	<p>Recovery logic is activated when the Wonderware Collector and Wonderware Historian re-establish a connection after a connection loss, or when the Wonderware Collector is started.</p> <p>The Wonderware Collector attempts to recover all data samples between the current time and the last known write time, up to a maximum number of hours configured for the collector. Continuous collection resumes only after the previous data has been recovered.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: The default recovery time is 0 hours. </div>
Throttle (Milliseconds)	<p>Frequency of Wonderware data polling.</p> <p>To minimize the load on the Wonderware Server, the configurable throttling option is provided by the Wonderware Collector. By default, the Wonderware Collector tries to query the tag data every 100 milliseconds based on the collection interval time. You can change this value to any time between 100 milliseconds to 16 hours.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: If Throttle field is blank, enter the required minimum value of 100 milliseconds. </div>

Data Recovery



Note:

We recommend that the collector for which the data recovery is intended is in the same time zone as the server. If there is a mismatch, there is a possibility that data recovery will be incomplete.

Automatic Data Recovery

In this mode, data is automatically recovered since the last time data has been collected.

How it works:

1. The collector determines the duration between the current time and the last time data has been written to the Historian data archive, which is stored in the LastSampleWriteTime registry key.
2. It compares this duration with the value in the Recovery Time field specified in [the collector settings \(on page 2347\)](#).
3. It uses the shorter duration to perform a raw data query on all the tags.
4. It then processes the returned samples in chronological order.

For example, if the collector was stopped for 8 hours, but Max Recovery Time was 4 hours, only 4 hours of data would be recovered.

As per the recovery logic, an end-of-collection marker is placed at the point in time where the collector was stopped. This end-of-collection marker may or may not be there after the recovery is complete. As part of the recovery logic, if recovery data point time matches the timestamp of the end-of-collection marker, it is overwritten with the recovered good data.

Manual Data Recovery

In this mode, you can fill gaps in the data, but you cannot fill old data.

To perform a manual recovery:

1. Access Historian Administrator.
2. Select **Collectors**, and then select the OPC Classic HDA collector instance for which you want to manually recover data.
3. Select **Recalculate**.

The **Recalculate** window appears.

4. Enter start time, end time, and other required information. We recommend that you choose small time intervals to reduce the load on the server and the collector.
5. Select **Recalculate**.

The tag data is recalculated. After the manual recalculation begins, the collector recovers data of the selected tags data from the collector, and sends it to Historian between the start time and end time.

At the time of recovery, if the connection to server is lost, and if the reconnect mechanism is enabled, the collector will try to connect to the server and fetch the data once connection re-establishes.

Manual Data Recovery

Assume that the collector is connected to Historian for the first time today and the archive was created at 10 am. The user initiates manual recalculation from 1am to 2 am. For that time interval, the archives were not even created. With respect to Historian, it is old unknown data and the data write fails. If there is a data gap between 1am and 2 am, manual recalculation successfully fills the data gap.

Initiating Manual Recovery

Manual recovery can be performed from Historian Administrator. Manual recalculate is done for filling the data gaps but not for filling old data.

It is advised to keep the Wonderware Collector in the same time zone as the Wonderware server. If there is a mismatch, there is a possibility that auto recovery of data will be incomplete.

To initiate manual recovery:

1. In Historian Administrator, select the Wonderware Collector.
2. Select **Recalculate**. The **Recalculate** window appears.
3. Enter the start and end time and choose all or selected tags based on the criteria from Recalculate window.
4. Select **Recalculate**.

Once manual recalculate starts, the collector recovers selected tags data from Wonderware server to GE Historian between start time and end time.

It is advised to choose small time intervals, so that the load on Wonderware server/collector will be reduced.



Note:

At the time of recovery, if the connection to Wonderware Server is lost, and if the reconnect mechanism is enabled, the collector will try to connect to the server and pull the data once connection reestablishes.

Example:

Assume that the Collector connected to GE historian for the first time today and the archive was created at 10 am. The user initiates manual recalculation from 1am to 2am.

For that time interval, the archives were not even created. With respect to Historian it is old unknown data and the data write fails.

If there is a data gap between 1pm to 2 pm, manual recalculation successfully fills the data gap.

Reconnecting to the Wonderware Server

The Wonderware Collector supports auto-reconnect to the Wonderware Server. If the connectivity between the Wonderware server and the collector is down due to network connectivity issues, the collector will auto-reconnect to the server when the server is back and running. The collector polls for the server connection for a set time of every 5 seconds. The collector shuts down when the reconnect functionality is disabled.

To enable Auto-Reconnect to the Wonderware Server:

1. From the Start menu, select **Run** and type `Regedit`, then, select **OK**.
The Registry Editor appears.
2. Open the key folder: `HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\iHistorian\Services\WonderwareCollector`.
3. Create a new DWORD labelled, **EnableReconnect**.
4. Enter the decimal value 1.
5. Select **OK**, then close the Registry Editor.
6. Restart the Historian Data Collector for Wonderware for the change to take effect.



Important:

If this registry is not created and set to a value of 1, then the auto-reconnect functionality will not be enabled.

To configure the timer:

- a. From the **Start** menu, select **Run** and type **Regedit**. Then, select **OK**. The **Registry Editor** appears.
- b. Open the key folder: `HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\iHistorian\Services\WonderwareCollector`.
- c. Create a new DWORD labelled, `ReconnectInterval`.
- d. Enter a decimal value greater than 5. This value represents the number of seconds for the collector to wait before trying to re-connect to the Wonderware Server.
- e. Select **OK**, and then edit the Registry Editor. Min Value = 5 seconds (default) Max Value = 60 seconds

- f. Select **OK**, and then edit the Registry Editor.
- g. Restart the Wonderware Collector for the change to take effect.

Troubleshooting the Wonderware Collector

The Wonderware Collector generates logs during initialization, configuration, and general operation. These can be found in the general logging folder `C:\Proficy Historian Data\LogFiles`.

Troubleshooting Tips

- Be sure to run the Wonderware server before the Historian Data Collector starts up.
- If the Wonderware Collector does not start automatically, refer to the Historian log file to view log entries to determine the problem.

Chapter 38. OLE DB Provider

Overview of the OLE DB Provider

OLE DB is a collection of standard COM-based interfaces defined by Microsoft that abstract standard SQL commands into native API access for any data source. OLE DB adds tremendous value to Historian by providing simple access to data from within the SQL environment, without the need for complex scripting.

The Historian OLE DB provider is a data access mechanism that allows you to query Historian data using SQL statements or other client reporting tools.

Supported Applications: Using the OLE DB provider, you can create reports and integrate Historian with the following applications:

- Microsoft Power BI
- Seagate Crystal Reports v8.0, and above (v11.0 or above required for use with Historian Alarms and Events)
- VisiconX with iFIX v4.0 and later
- Microsoft Excel 2003 and later
- Visual Basic v6.0, Service Pack 5
- Visual Basic for Applications (VBA) v6.0
- Microsoft SQL Server v7, Service Pack 3
- Microsoft SQL Server 2008, or SQL Server Express 2008
- Oracle 8.x and above



Note:

Other OLE DB clients are likely to work with the OLE DB provider, but have not been tested.

Components: When you install the OLE DB provider on the Historian server machine, the following items are available:

- The `ihSQL.exe` file: The Historian Interactive SQL tool.
- The `Samples` folder: Contains sample reports for Crystal Reports, Microsoft Excel, Microsoft Visual Basic, iFIX, and Oracle.
- The `ihOLEDB.dll` file: A dynamic-link library file to support the OLE DB provider on 32-bit and 64-bit operating systems. This file is located in the `WINDOWS\SysWOW64` and `WINDOWS\System32` folders.

If you install the OLE DB provider on a client computer, some of these items may not be available. These items may also appear differently, depending upon the number of archivers you installed.

Limitations: The OLE DB provider has read-only access. You cannot insert, update, or delete data in archives using the OLE DB provider.

Setting Up

Install Client Tools


When you install Client Tools, the following components are installed by default:

- Client Tools
- Historian Administrator
- OLE DB provider (driver and samples)
- The OPC Classic HDA server
- User API and SDK
- Historian Client Access API
- Collector Toolkit

This topic describes how to install Client Tools using the installer. You can also [install it at a command prompt \(on page 153\)](#).

1. Run the `InstallLauncher.exe` file.
2. Select **Install Client Tools**.

The **Select Features** page appears, displaying a list of components that you can install with Client Tools.



By default, the check boxes for components such as **Historian Administrator**, **HDA Server**, **OLE DB**, and **User API and SDK** are selected. If you do not want to install them at this time, clear the check boxes. You cannot, however, clear the **Proficy Historian Client Tools** check box.

 **Important:**


If you are reinstalling, you must select all of the previously installed components. If you do not do so, the component will be uninstalled.

By default, the **Historian Excel Add-in 64-bit** check box is cleared. If you want to install Excel Add-In along with Client Tools installation, select the check box.

 **Note:**

If using certain versions of Windows (like Windows 10 or Windows 2019), you may receive an error message while installing Excel Add-In, stating that some of the DLL files are not registered. You can ignore these messages.

The **Historian Server Security** page appears.



3. Select the user account that should be granted the access to administer Historian.

You are provided with the following options:

Option	Description
<p>All Users</p>	<p>If you select this option, all local, including domain user accounts will have the administrator access of the Historian server. If needed, to control access, you can configure security groups after installation.</p>
<p>Specific User</p>	<p>If you select this option, the user that you select will have the administrator access of the Historian server. If needed, you can grant a restricted or administrator access to other users after installation.</p>

4. Select **Next**.
5. When you are asked to reboot your system, select **Yes**.

Client Tools, along with the selected components, are installed in the following folder: *<installation drive>:\Program Files\Proficy\Proficy Historian\x86\<tool name>*. If you have selected HDA Server, Microsoft .NET Framework 4.5 and the OPC Core Components 3.00 redistributable are installed as well.

Connect to a Historian Server

1. [Install Client Tools \(on page 150\)](#), which will automatically install the OLE DB provider.
2. [Initialize the COM library](#) on the machine on which you have installed the OLE DB provider.

This topic provides basic steps to connect the OLE DB provider to a Historian server so that you can import the data. For instructions specific to a client, refer to:

- [Import Historian Data into Power BI Desktop \(on page 2580\)](#)
- [Import Historian Data into Crystal Reports \(on page 2588\)](#)
- [Import Historian data into Microsoft Excel \(on page 2592\)](#)

1. To connect an OLE DB client to a local Historian server, run the following command:

```
Provider=iHOLEDB.iHistorian.1
```

2. To connect an OLE DB client to a remote Historian server, run the following command:

```
Provider=iHOLEDB.iHistorian.1;PersistSecurity Info=False;
USER ID=[<Historian server username>];
Password=[<Historian server password>];
Data Source=[<network name of your Historian server>]
```

Working with Clients

Power BI Desktop


Import Historian Data into Power BI Desktop

Microsoft Power BI Desktop is an application that transforms and visualizes data. Using this application, you can connect to multiple data sources and combine the data into a data model.

This topic describes how to import Historian data into Power BI Desktop.

1. Access Power BI Desktop.
2. Select **Get Data > Other > OLE DB**, and then select **Connect**.


The **From OLE DB** window appears.



The screenshot shows the 'From OLE DB' dialog box. At the top, there is a title bar with a close button (X). Below the title, the text 'From OLE DB' is displayed. Underneath, there is a label 'Connection string (non-credential properties)' followed by a text input field. To the right of the input field is a 'Build' button. Below this, there is a section titled 'Advanced options' with a downward-pointing arrow. Under 'Advanced options', there is a label 'SQL statement (optional)' followed by a large text area for entering the SQL statement. At the bottom right of the dialog, there are two buttons: 'OK' (highlighted in yellow) and 'Cancel'.


3. Select **Build**.

The **Data Link Properties** window appears, displaying a list of the Historian OLE DB providers in the **Provider** section.



4. Select **Next**.

The **Connection** section appears.



5. Leave the default values as is, and select **Test Connection**.

After the connection succeeds, the connection string is populated in the **From OLE DB** window.

**Important:**

Do not use the connection string that is populated. If you do so, an error occurs.

6. Change the connection string to `provider="ihOLEDB.iHistorian.1";mode=Read`

The screenshot shows a dialog box titled "From OLE DB". It has a close button (X) in the top right corner. Below the title, there is a section for "Connection string (non-credential properties)" with a help icon. A text input field contains the connection string: `provider="ihOLEDB.iHistorian.1";mode=Read`. To the right of the input field is a "Build" button. Below the input field, there is a link for "Advanced options". At the bottom right, there are "OK" and "Cancel" buttons.


7. Select **OK**.

The **OLE DB Provider** window appears.

8. In the **Database** section, enter the credentials to connect to the Historian server, and then select **Connect**.

The screenshot shows a dialog box titled "OLEDB provider" with a close button (X) in the top right corner. On the left, there is a sidebar with three options: "Default or Custom", "Windows", and "Database" (which is highlighted). The main area displays the connection string: `mode=Read;provider=ihOLEDB.iHistorian.1`. Below this, there is a message: "Use a username and password to access a data source with an OLE DB provider." There are three input fields: "User name", "Password" (with masked characters), and "Credential connection string properties (optional)". At the bottom, there are "Back", "Connect", and "Cancel" buttons.


A list of Historian table appears in the **Navigator** section.



If an error message appears after entering the credentials, restart your machine.

9. Select the table whose data you want to import, and then select **Load**.

10. Select .



Data from the selected Historian table appears.

You can now [create a Power BI report](#) and then [publish it](#).

Working with VisiconX

Using the OLE DB provider with VisiconX, you can:

- Use tables or SQL queries.
- Insert multiple controls into a picture to the same or different servers.
- Provide a username and password or be prompted when opening a picture.

1. Access the Historian OLE DB provider from VisiconX. For instructions, refer to [Using VisiconX](#).
2. To make all the VisiconX controls use synchronous (SYNC) executes:

- a. Access the `FixUserPreferences.ini` file in the `Dynamics/Local` folder.

- b. Add the following lines to the end of the file:

```
[VisiconX]
RUNASYNC=FALSE
```

- c. Save the file, and restart the collector.


Access the iFIX Sample Picture

To use iFIX with VisiconX, edit the `FixUserPreferences.ini` configuration file.

The `HistoricalAnimation.grf` file contains an iFIX sample picture with the VisiconX controls. It is located in the `Historian\Samples\iFIX` folder.

1. Copy the `HistoricalAnimation.grf` file to your `Dynamics/Pic` folder.
2. Start iFIX.
3. Open **iFIX Workspace**.
4. Double-click the **Pictures** folder.
5. Double-click the **HistoricalAnimation** picture.

The picture appears in the workspace.



You can now perform the following tasks:

- Modify the picture.
- Switch between the configure and run modes.
- Follow the steps on the picture.
- View the properties of the VisiconX controls.
- Change the properties.



Note:

You can have multiple VisiconX controls that each link to different Historian servers.

Create a Background Schedule to Run Crystal Reports

In iFIX, you can create a background schedule that runs Crystal reports. This topic contains a sample Visual Basic code to create a background schedule:

```
Private ReportFileName
Private CrystalReport

Private Sub KKTimer_OnTimeOut(ByVal lTimerId As Long)

Set CrystalApplication = CreateObject("Crystal.CRPE.Application")
Set CrystalReport = CrystalApplication.OpenReport("C:\Program Files (x86)\GE\iFIX\APP\RTtemplate.rpt")

CrystalReport.Printout False
```

```

Set CrystalReport = Nothing

Set CrystalApplication = Nothing

End Sub

```

Working with Oracle

You can import Historian data into Oracle by using an ADO program. A sample program is provided in the `Historian/Samples/Oracle` folder.

Use SQL WorkSheet to test that Oracle imported the data and created the tables properly.

Crystal Reports

Crystal Reports allows you to create reports easily through its experts and wizards. When working with Crystal Reports, remember that:

- Crystal does not support the `SET` command. You must use a `WHERE` clause in a `SELECT` statement to specify query parameters.
- A single report can only retrieve data from one server, but you can create subreports from different servers within a report.
- The Crystal Reports application does not display milliseconds in timestamps.
- If you want to create a report on numeric data in the Value or Quality column in the `ihRawData` table, you may want to convert all Variant data types to Float data types so that Crystal displays them correctly in the report. Refer to [Format Decimal Point Precision \(on page 2590\)](#) for instructions.
- Analysis of the `ihTrend` and `ihAlarm` tables in Crystal Reports is not supported.

Table 384. Crystal Reports Samples

File Name	Description
<code>SimpleCrystal80Report.rpt</code>	Contains values cast from Variant to Float .
<code>MultipleServers-Subreport.rpt</code>	Contains data from two servers by using a subreport.
<code>iFIX1_CHART_OLEDB.rpt</code>	Contains data from iFIX Sample System converted from the iFIX Historical ODBC driver to OLE DB.

Table 384. Crystal Reports Samples (continued)

File Name	Description
iFIX1_CROSSTAB_OLED- B.rpt	Contains data from iFIX Sample System converted from the iFIX Historical ODBC driver to OLE DB.
iFIX1_DAILY_OLED- B.rpt	Contains data from iFIX Sample System converted from the iFIX Historical ODBC driver to OLE DB.

Connect to the Historian Server

To generate reports in Crystal Reports, you must ensure that the Historian Server name is correct. By default, this server name is T20.

1. Open the report file in Crystal Reports.
2. Select the **Database** menu.
3. If the **Database** menu does not appear automatically:
 - a. Wait for approximately 90 seconds for the connection timeout to occur.
After the 90-second timeout, the **Data Link Properties** window appears. Although it may appear as if Crystal Reports has stopped working or is frozen before the timeout occurs, this functionality is as expected.
 - b. Change the **Data Source** field.
You can leave this field empty to use the default Historian server or enter a specific Historian server name.
 - c. Select **OK**.
 - d. Skip the next step.
4. If the **Database** menu appears automatically:
 - a. Select **Database > Set Location**.
The **Set Location** window appears.
 - b. Select **Set Location**.
The **Data Explorer** window appears.
 - c. Select a source, and then select **Set**.
 - d. Select **Done**.

The Historian server is connected with Crystal Reports.

Create a Crystal Report

Ensure that Crystal Reports is integrated with the Historian server whose data you want to analyze. For instructions, refer to [Connect to the Historian Server \(on page 2588\)](#).

This topic describes how to import Historian table data into Crystal Reports and create a report.

1. In Crystal Reports, select **File > New**.
The **Crystal Reports Gallery** window appears.
2. Select **Using the Report Expert > Standard Report Expert**, and then select **OK**.
The **Standard Report Expert** appears.
3. Select **Database**.
The **Data Explorer** appears.
4. Open the **More Data Sources** folder, and then open the **OLE DB** folder.
5. Select **Make New Connection > Add**.
The **Data Link Properties** window appears.
6. Select **Historian OLE DB Provider > Next**.
The **Connection** section appears.
7. Leave these fields empty to use the default server and currently logged-in user. Otherwise, do the following:
 - a. Enter the name of the Historian server in the **Data Source** field.
 - b. Clear the **Blank Password** check box.
 - c. Enter a Windows username and password.
8. Select **OK**.
The Historian OLE DB provider tables appear in the **Data Explorer**.
9. Select the table that you want to query, select **Add**, and then select **Close** to exit the **Data Explorer** window.
10. In the **Fields** section of the **Standard Report Explorer** window, select a field that you want to report on, and then select **Add** to move the field into the **Fields to display** list.

**Note:**

If you want to create a report on numeric data in the Value or Quality column in the `ihRawData` table, you may want to convert all Variant data types to Float data types so that Crystal displays them correctly in the report. Refer to [Format Decimal Point Precision \(on page 2590\)](#) for instructions.

11. Repeat the previous step for each field that you want to add, and then select **Finish**.
The Crystal Report is generated.


Format Decimal Point Precision

Connect to the OLE DB provider, and add the Historian database tables.

To format decimal point precision in your reports, you must convert Variant data types to Float data types in Crystal Reports. For instance, if retrieving the Value column from the ihRawData table, you must convert the values to Float. You need not perform these steps if you are working with strings.

1. Access **Standard Report Expert**, and then select **Fields**.

The **Fields** section appears.




2. Select **Formula**.
The **Formula Name** window appears.
3. Enter a name for the formula.
The **Formula Editor** section appears.

**Tip:**

You can also access the **Formula Editor** section by selecting **Insert > Field Object**. Right-click the formula fields, and then select **New**.

4. In the **Formula** field, enter the following text :

```
if numerictext({ihRawData.Value}) then cdbl({ihRawData.Value}) else
0
```



5. Select **Save**.

You can now use the formula as a normal numeric column instead of the **Value** column in the report.

Change the Date and Time Format

This topic describes how to format the date/time column of Historian tables in Crystal Reports. When formatting timestamps, note that milliseconds do not appear in Crystal Reports.

1. Select a field in a column that contains timestamps.
2. Right-click the field, and then select **Format Field**.
The **Format Editor** window appears.
3. Select **Date/Time**, and specify the date format that you want to use.

4. Select **OK**.

The timestamps are updated to display the new format.

Microsoft Excel

With Excel, you can import a snapshot of Historian data at a single point in time. You can choose Historian as a data source in Excel. You can specify the connection settings [manually \(on page 2592\)](#) or [using a UDL file \(on page 2593\)](#).

After you import the data, you can create and edit SQL queries in Excel.

When to Use Excel Instead of the Historian Excel Add-In

Use the Excel Add-In when you want to get data into Microsoft Office 2003, 2007 or 2010 (32-bit/64-bit). Use the Historian OLE DB provider with Excel, instead of the Excel Add-In, when you want to do any of the following:

- Perform advanced filtering, sorting, and joining of data.
- Obtain detailed information from the ihTrend table.
- Run calculations using the SQL aggregate functions.
- Perform advanced summaries.

Table 385. Microsoft Excel Samples

File Name	Description
ihOLEDB_LASTHOUR.XLS	One-sheet report that uses auto-refresh to display the last hour of data using relative shortcuts.
ihTags.odc	Data source file that retrieves the ihTags table from the default server.
iHistorian.udl	Sample universal data link (.UDL) file that connects to the default Historian server with the currently logged-in user.

These sample are found in the following folder: `Historian\Samples\Excel`

Import Historian Data Into Excel Manually

This topic describes how to import Historian data into Excel by providing the connection details manually. You can also import the data [by creating a UDL file \(on page 2593\)](#) or [by using the sample UDL file \(on page 2595\)](#).

1. Open an Excel worksheet.
2. Select **Data > Import External Data > Import Data**.
The **Select Data Source** window appears.
3. Select **My DataSources > +Connect to New Data Source.odc > Open**.
The **Data Connection Wizard** appears.
4. Select **Other/Advanced** from the list of data sources to which you can connect, and then select **Next**.
The **Data Link Properties** window appears.
5. Select **Historian OLE DB Provider** from the **OLE DB Provider** list, and then select **Next**.
The **Connection** section appears in the **Data Link Properties** window.
6. Leave these fields empty to use the default server and the currently logged-in user. Otherwise, do the following:
 - a. Enter the name of the Historian server in the **Data Source** field.
 - b. Clear the **Blank Password** check box.
 - c. Enter a Windows username and password.
 - d. Select the **Allow Saving Password** check box if applicable.
7. Select **Test Connection** to confirm that the data source, username, and password provide a successful connection, and then select **OK**.
The **Select Database and Table** page appears in the wizard.
8. Select the table that you want to query, and then select **Next**.
The **Save Data Connection File and Finish** page appears in the wizard.
9. Accept the default settings, and select **Finish**.
The **Import Data** window appears.

**Note:**

If you want to run a specific SQL command instead of the default table command setting, refer to [Edit SQL Queries in Excel \(on page 2595\)](#).

10. Select **OK** to import the column data from the selected table.
Historian data populates the current spreadsheet.

Import Historian Data Into Excel by Creating a UDL File

This topic describes how to create a UDL file with connection information and then import Historian data into Excel using the UDL file. You can also provide the connection details [manually \(on page 2592\)](#) or [using the sample UDL file \(on page 2595\)](#).

1. Create a UDL file with connection details:

- a. Create a text document.

We recommend that you use the **My Data Sources** folder in the **My Documents** folder.

- b. Rename the file extension .UDL.

- c. Double-click the .UDL file.

The **Data Link Properties** window appears.

- d. Select **Provider > Historian OLE DB Provider > Next**.

The **Connection** section appears in the **Data Link Properties** window.

2. Leave these fields empty to use the default server and the currently logged-in user. Otherwise, do the following:

- a. Enter the name of the Historian server in the **Data Source** field.

- b. Clear the **Blank Password** check box.

- c. Enter a Windows username and password.

- d. Select the **Allow Saving Password** check box if applicable.

3. Select **Test Connection** to confirm that the data source, username, and password provide a successful connection, and then select **OK**.

The **Select Database and Table** page appears in the wizard.

4. Select **Data > Import External Data > Import Data**.

The **Select Data Source** window appears.

5. Select the .UDL file that you have created, and then select **Open**.

The **Select Table** window appears.

6. Select the table that you want to query, and then select **OK**.

The **Import Data** window appears.



Note:

If you want to run a SQL command instead of the default table command setting, refer to [Edit SQL Queries in Excel \(on page 2595\)](#).

7. Select **OK** to import the column data from the selected table.

Historian data is imported into the spreadsheet.

Import Historian Data into Excel Using the Sample UDL File

With the sample universal data link (.UDL) file, you can specify the connection information so that Excel can connect to the tables in the OLE DB provider and import data using the default server and the currently logged-in user.

This topic describes how to import Historian data into an Excel spreadsheet using the sample .UDL file. You can also import Historian data by providing the connection details [manually \(on page 2592\)](#) or by [creating a .UDL file \(on page 2593\)](#).

1. Open an Excel spreadsheet.
2. Select **Data > Import External Data > Import Data**.
The **Select Data Source** window appears.
3. Select the `Historian.udl` file in the `Historian\Samples\Excel` folder, and then select **Open**.
The **Select Table** window appears.
4. Select the table that you want to query, and then select **OK**.
The **Import Data** window appears.

**Note:**

If you want to run a SQL command instead of the default table command setting, refer to [Edit SQL Queries in Excel \(on page 2595\)](#).

5. Select **OK**.
Historian data appears in the spreadsheet.

Edit SQL Queries in Excel

By default, data import functionality in Excel selects all columns from the specified Historian table using the default query parameters. This command is the equivalent of running the SQL command `SELECT * FROM TABLE_NAME`, where `TABLE_NAME` is the name of the table that you want to query.

You can change the query by issuing a different SQL query if you are familiar with SQL syntax. Refer to the Microsoft Excel documentation for more information.

If you are unsure if the SQL syntax is correct, you can test your SQL query outside of Excel using the Historian Interactive SQL application. See [Historian Interactive SQL Application \(on page 2606\)](#) for more details.

Format Date and Time

This topic describes how to format the date/time column for Historian tables in Excel if you need to display a specific date format. For more specific information on formatting spreadsheets, refer to the Microsoft Excel online Help.

1. Right-click the heading of the column that you want to format.
2. Select **Format Cells > Number**.
3. Select **Date**.
4. In the **Type** field, select the date format that you want to use.
To display milliseconds, instead of selecting the **Date** category, select **Custom**, and then enter `dd-mm-yy hh:mm:ss.000` in the **Type** field.
5. Select **OK**.
The date and time format is set.

Refresh Data

After you import Historian data into an Excel worksheet, you can refresh it to get the most updated data. This feature is most useful when using relative start times, such as `Now - 2h`. You can also set a refresh interval to refresh data automatically.

1. Open the Excel worksheet into which you have imported the Historian data.
2. Select **External Data > Refresh Data**



Tip:

If the **External Data** toolbar is not available, select **View > Toolbars**.

The data is refreshed.

3. To automatically set refresh intervals, select **Data Range Properties**, and provide the interval at which you want to refresh data automatically.

Data is refreshed automatically at the interval that you have specified.

Visual Basic and ADO

You can access the OLE DB provider using Microsoft ActiveX Data Objects (ADO). This approach is more generic than using the Historian SDK.

Visual Basic supports asynchronous (ASYNCR) connections. You can open multiple ADO connections to the same data source from within a Visual Basic program. You are limited to one server per connection,

and one username and password. A different user can make another connection to the same server, however, by using a different username and password.

We recommend that you use client-side cursors instead of server-side cursors in Visual Basic. If you use a server-side cursor, the `RowCount` property on the `recordset` object will always be `-1` instead of the actual row count.

Table 386. Visual Basic and ADO Samples

File Name	Description
SimpleADOExample.vbp	Visual Basic project file that uses a simple ADO example with a connect string.
modSimpleADOExample.bas	File that is part of the SimpleADOExample.vbp project file.
iholedb_data-boundgrid.vbp	Visual Basic project file that displays a data-bound grid example that fetches data from the ihRawData table.
frmMain.frm	File that is part of the iholedb_databoundgrid.vbp project file.
frmMain.frx	File that is part of the iholedb_databoundgrid.vbp project file.

These samples are available in the following folder: `Historian\Samples\VB`

Retrieve Milliseconds

Use the following code to retrieve timestamps to a resolution of milliseconds.

```
Public Function Time_To_String_With_Milliseconds(TheTime As Double) As String

Dim Temp As String

Dim TimeFraction As Double

Dim Msc As Long

Dim TempTime As Date

On Error GoTo errc

If TheTime = 0 Then

Time_To_String_With_Milliseconds = ""

Exit Function

End If
```

```

TimeFraction = TheTime * 86400#
TimeFraction = TimeFraction - Fix(TimeFraction)

Msc = CLng(TimeFraction * 1000)

TempTime = TheTime - (TimeFraction / 86400#)
If Msc = 1000 Then
Msc = 0
TempTime = DateAdd("s", 1, TempTime)
End If

Time_To_String_With_Milliseconds = LCase(Format$(TempTime, "dd-mmm-yyyy hh:nn:ss") + "." + Format$(Msc, "000"))

errc:
End Function

```

Set a Maximum Limit to Records

Use the following example code to set a maximum limit to the number of rows returned in your query:

```

SET rstTitles = New ADODB.Recordset
rstTitles.MaxRecords = 10
strSQLTitles = "SELECT Tagname FROM ihTags"
rstTitles.Open strSQLTitles, strCnxn, adOpenStatic, adLockReadOnly, adCmdText

```

Use Parameterized Queries

Use the following example code to use parameterized queries:

```

Private Sub SampleParameterizedQuery()

    Dim ihConnectionString As String

    Dim ihRecordSet      As ADODB.Recordset

    Dim ihConnection    As ADODB.Connection

    Dim ihParameter     As ADODB.Parameter

    Dim ihCommand       As ADODB.Command

    'Set Up the Historian Connect String...

    Set ihConnectionString = "Provider=ihOLEDB.iHistorian.1;User Id=;Password="

    'Create Our Other Objects...

```

```
Set ihConnection = CreateObject("ADODB.Connection")
Set ihRecordSet = CreateObject("ADODB.Recordset")
Set ihCommand = CreateObject("ADODB.Command")

'Open the Connection to the Historian Archiver...
ihConnection.ConnectionString = ihConnectString
ihConnection.Open

'Set up the Command Object
With ihCommand

    'Set the Active Connection to the Historian Connection Opened Above..
    .ActiveConnection = ihConnection

    'Set the Command Text to a Parameterized Sql Statement...
    .CommandText = "select * from ihTags where datatype = ?"

    'Set the Type of the Command...
    .CommandType = adCmdText

    'Refresh Our Parameter List...
    .Parameters.Refresh
End With

'Create a Single Parameter Object...
Set ihParameter = ihCommand.CreateParameter("Temp", adChar, adParamInput, 100)
'Set the Parameters Value...
ihParameter.Value = "SingleFloat"
'Add the Parameter to the Command Object...
ihCommand.Parameters.Append ihParameter

'Run the Command!
Set ihRecordSet = ihCommand.Execute

End Sub
```

For more information, refer to [Parameterized SQL Queries \(on page 2636\)](#).

Proficy Real-Time Information Portal

Proficy Real-Time Information Portal is a web-based tool for accessing, analyzing, and visualizing production information. It has sophisticated trending and reporting capabilities that take advantage of the vast archival and retrieval capabilities of Historian.

In Proficy Real Time Information Portal, parameters are used to build SQL queries that you can reuse with different values. In the place of a constant value in a SQL query, you can use a parameter, which takes a dynamic value at execution time. Parameterized SQL queries are driven by Proficy Real Time Information Portal components such as list boxes, combo boxes, or grids.

The SQL Query Builder application in Proficy Real Time Information Portal is used to define a parameterized query.

To define a parameterized query: In the **Specify Selected Item Wizard** or **Specify Criterion Wizard**, in the **Parameter** field, enter the name of the parameter.

The following conditions apply when you define a parameterized query:

- Parameter names must be unique.
- A question mark (?) is appended to the parameter name, and the parameter is enclosed in parentheses. For example, the parameter `temperature` becomes `{temperature?}`.
- You can specify a default value for the parameter.
- You can also select a data type for the parameter. By default, the data type is set to `char`. However, you can select `int`, `date`, `num`, or `char` as the type of database column.

Linked Servers in Microsoft SQL Server

If you want to relate Historian data with other data in SQL Server tables such as batch events, iFIX Alarms and Events collector, iDownTime data, and any other information that is available in a relational database, you can use the OLE DB provider as a linked server in Microsoft SQL Server. You can also use the OLE DB provider as a linked server if you do not want to duplicate data with an import.

With linked servers, when you query data from Historian, the SQL server fetches the requested data from Historian at the time the query is executed. Data is not duplicated because nothing is imported or stored in the SQL server. The data is simply returned as part of a query, just as any other query on a SQL Server database would return data.

Another advantage of using the OLE DB provider as a linked server is that you do not need to install Historian in the client machines. For example, a client tool such as Microsoft Query Analyzer can be used to retrieve Historian product data over the network on a computer with no Historian software installed.

Configure the OLE DB Provider as a Linked Server Manually

The following steps are necessary in order to access a linked server via the `OPENQUERY` statement.

This topic describes how to configure the OLE DB provider as a linked server manually. You can also [configure it automatically \(on page 2601\)](#).

1. From the **Start** menu, open the **SQL Server Enterprise Manager**.
2. Select an SQL server, and open the `Security` folder.
3. Right-click the `Linked Servers` folder, and select **New Linked Server**.
The **Linked Server Properties** window appears.
4. Enter a name for the linked server, such as `iHist`.
5. In the **Provider Name** field, select **Historian OLE DB Provider**.
6. In the **Data Source** field, enter the name of the Historian server, and then select **Provider Options**.
The **Provider Options** window appears.



Note:

- Select the **Level Zero Only** option only if using older versions of SQL server. For better performance while executing small queries, select the **Allow in Process** option. Clear the option if larger queries are to be executed.
- For configuring the Historian 64-bit OLE DB provider as a linked server, the **Allow in Process** option is mandatory.

7. Select **OK**.
8. If Historian security is enabled, enter a Historian username and password.
9. For SQL Server 2008 (32-bit/64-bit), follow these steps:
 - a. Select **Security**.
 - b. Select the **Be made using this security context** option.
 - c. Enter a Historian username and password in the **Remote Login** and **With Password** fields.
10. Select **OK**.
The linked server is created.

Configure the OLE DB Provider as a Linked Server Automatically

Configure a linked server and options using **Enterprise Manager**, as described in [Configuring the Historian OLE DB provider as a Linked Server \(on page 2601\)](#). Then, since the options **Allow In Process** and **Level Zero Only** apply to all linked servers that use the provider, you can create additional linked server definitions to other Historian servers using the `sp_addlinkedserver` stored procedure.

This topic describes how to configure the OLE DB provider as a linked server automatically using the `sp_addlinkedserver` system stored procedure from Microsoft SQL Server. You can also [configure it manually \(on page 2601\)](#).

1. To configure a linked server definition, use the following example code:

```
EXEC sp_addlinkedserver @server='MYSERVER_LS', @srvproduct='',  
@provider='iHOLEDB.iHistorian.1', @datasrc='MY_SERVER'
```

2. To search for linked server definitions, use the following example code:

```
EXEC sp_linkedservers
```

3. To delete linked server definitions, use the following example code:

```
EXEC sp_dropserver 'MYSERVER_LS', 'droplogins'
```

Access a Linked Server

Configure a linked server and options using **Enterprise Manager**, as described in [Configuring the Historian OLE DB provider as a Linked Server \(on page 2601\)](#).

This topic describes how to access the OLE DB provider as a linked server in an SQL server using the following methods:

- **OPENQUERY**: This is the recommended method of accessing data by means of a linked server. To use this method, you must first configure a linked server definition. You can then use that linked server name in the `OPENQUERY` command.
- **Four-Part Name Syntax**: To use this method, you must first configure a linked server definition. You can then use that linked server name in the four-part name syntax.
- **OPENROWSET** and **OPENDATASOURCE**: These methods are considered adhoc methods of accessing data. They are recommended only for infrequently accessed data. When using either method, you must specify the data source, username, and password in each query instead of configuring it once in a linked server definition. If you want to limit the number of users to a defined set of servers and usernames, you can disable all methods of adhoc access by selecting the **Disallow Adhoc Accesses** option in the **Provider Options** window.

**Note:**

You cannot use `OPENQUERY` to access the `ihTrend` table. Use four-part name syntax to access the `ihTrend` table.

1. To fetch a list of Historian tags, run the following query:

```
SELECT * FROM OPENQUERY(iHist,'SELECT * FROM ihTags')
```

2. To fetch tag values from Historian, use the following example code:

```
SELECT TagName, TimeStamp, Value, Quality FROM OPENQUERY (iHist,'
SET
StartTime=yesterday-12Day, EndTime=Today, IntervalMilliseconds=1Hour, SamplingMode=Calculated,
CalculationMode=Maximum
SELECT * FROM ihRawData WHERE TagName LIKE *simulation00001')
```

3. To access the ihTrend table from a linked server, run the following query:

```
SELECT * FROM iHist...[SELECT timestamp, *.value FROM ihTrend]
```

Although the four-part name syntax works with all tables, it is only necessary to use it with the ihTrend table, because the ihTrend table does not work with `OPENQUERY`.

4. To use `OPENROWSET` with an SQL query, use the following example code:

```
SELECT * FROM OPENROWSET('iHOLEDB.iHistorian.1',
'MY_SERVER';'',',', 'SET starttime="2002-01-30 10:00:00", endtime="2002
```



Note:

This example uses double quotes around date and time because single quotes do not work inside the overall single-quoted query. It is important for you to use double quotes in this scenario.

5. To access a table, use the following example code:

```
SELECT * FROM OPENDATASOURCE('iHOLEDB.iHistorian.1', 'Data Source=MY_SERVER')...ihTags
```

6. To use `OPENDATASOURCE` with an SQL query and security, use the following example code:

```
SELECT * FROM OPENDATASOURCE('iHOLEDB.iHistorian.1',
'Data Source=MY_SERVER;User ID=user1;Password=thepassword')...[SE
```

7. To join Historian data with iFIX data logged with AlarmODBC, use the following example code, which determines the last date and time a specific analog tag was raised as an alarm. The date and time are then used to collect the data from the previous hour leading up to the alarm. You can use this example to determine if the value spiked into the alarm or slowly approached the alarm limit.

```
declare @var1 as varchar(300)
declare @iHistServer as varchar(10)
```

```

declare @Tagname as varchar(40)

declare @HistTagname as varchar(50)

declare @AlarmStatus as varchar(10)

declare @Node as varchar(8)

declare @StartDt as varchar(30)

declare @EndDt as varchar(30)

declare @queryDt as varchar(30)

SET @iHistServer = 'iHistMY_SERVER'

SET @Node = 'MY_SCADA'

SET @Tagname = 'Simulation00001'

SET @HistTagname = 'MY_SERVER.' + @Tagname

SET @AlarmStatus = 'HIHI'

SET @queryDt= DATEADD(day, -1, CURRENT_TIMESTAMP)

SET @EndDt = (SELECT TOP 1 DateTimeLast FROM AlarmODBC WHERE AlarmStatus = @AlarmStatus AND Node = @Node and
Tagname =

SET @StartDt = DATEADD(hour, -1, @EndDt)

set @var1 = 'SELECT * FROM OPENQUERY

('+ @iHistServer + ','SET StartTime="'+ @StartDt +'", EndTime="'+ @Enddt +'

SELECT Tagname, TimeStamp, Value, Quality FROM ihRawData WHERE TagName = '+ @HistTagname +''')' exec (@var1)

```

8. To access linked server data using a stored procedure, use the following example code, which interfaces with the alarm's ODBC table to get the last alarm time for a specified tag in the past 24 hours. It then uses this time to retrieve data for the tag from one hour leading up to the time the alarm occurred.

The input parameters are the linked Historian server name, tag name, alarm status, and SCADA node name on which the alarm was created. This example uses a sim tag in the Historian database rather than setting up a collector to an iFIX SCADA node. Preferably, an iFIX tag name must be concatenated with the node and field (`node.tagname.fieldname`).

- a. To execute a stored procedure, use the following example code:

```
EXEC alarmhist 'iHistMY_SERVER', 'simulation00001', 'HIHI', 'MY_SCADA'
```

- b. When you create the stored procedure in **Enterprise Manager**, include the following lines before the create procedure command to avoid an error:

```
SET ANSI_NULLS ON

GO

(@iHistServer varchar(10),

@Tagname varchar(40),
```

```

@AlarmStatus varchar(10),

@Node varchar(8))

AS

declare @var1 as varchar(400)

declare @HistTagname as varchar(50)

declare @StartDt as varchar(30)

declare @EndDt as varchar(30)

declare @queryDt as varchar(30)

declare @count as int

declare @CalculationMode as varchar(20)

SET @HistTagname = 'MY_SERVER.' + @Tagname

SET @queryDt= DATEADD(day, -1, CURRENT_TIMESTAMP)

SET @count = (SELECT COUNT(*) FROM AlarmODBC WHERE AlarmStatus = @AlarmStatus AND Node = @Node AND

Tagname = @Tagname

If @count > 0

BEGIN

If @AlarmStatus = 'HIHI' or @AlarmStatus = 'HI'

BEGIN

SET @CalculationMode = 'Maximum'

END

ELSE

BEGIN

SET @CalculationMode = 'Minimum'

END

SET @EndDt = (SELECT TOP 1 DateTimeLast FROM AlarmODBC WHERE AlarmStatus = @AlarmStatus AND Node =

@Node AND Tagname =

SET @StartDt = DATEADD(hour, -1, @EndDt)

SET @var1 = 'SELECT * FROM OPENQUERY

('+ @iHistServer + ','SET StartTime="'+ @StartDt + "',

EndTime="'+ @EndDt + "', IntervalMilliseconds=60000,

SamplingMode=Calculated,CalculationMode='+ @CalculationMode +

SELECT Tagname, TimeStamp, Value, Quality FROM ihRawData WHERE TagName = '+' @HistTagname +''')'

print (@var1)

exec (@var1)


END

GO

```

About Working with Queries

Using the Historian Interactive SQL application (`ihSQL.exe`), you can run an SQL query and display the results of the query in the same window. It is useful if you want to test a query using the OLE DB provider.



It can open and save SQL queries and can show multiple windows, each containing a query request to the same server or different servers. For instance, you might want to open more than one window to compare two different time periods on the same server, or the same time period on different servers.


The Historian Interactive SQL application allows you to access data quickly and efficiently. Using this application, you can:

- Test SQL syntax before using it in an application.
- Troubleshoot OLE DB connections or Historian errors.
- Perform more complex searching or filtering of data than you can in the Historian SDK and administration applications.
- Retrieve data from any available Historian server.
- Save and access queries.
- Export query results to Microsoft Excel.

The Historian Interactive SQL application toolbar provides quick access to common functions such as:

- Executing queries
- Switching to a new Historian server
- Exporting query results to Microsoft Excel
- Saving a query
- Printing query results

The following figure shows the toolbar for the Historian Interactive SQL application, outlining what each button does.



Access the Historian Interactive SQL Application

When you start the application, you can log in to the default server or another Historian server.

1. From the **Start** menu, select **Programs > Historian > Historian Interactive SQL**.



Important:

The first time you use `ihSQL.exe`, you may need to select **Run As Administrator**. Otherwise, you may not be able to log in.

The **Historian Interactive SQL Login** window appears.



2. Select a Historian server, and then enter the username, password, and domain to connect to the server. If you do not enter user credentials, the currently logged-in user is considered.
3. Select **OK**.

A new session of the Historian Interactive SQL application appears, and it is connected to the server that you have specified. The session begins with the default values for [SET variables \(on page 2630\)](#).




Note:

If modifications or additions are made to the list of available Historian servers using any of the Historian clients (Excel, non-web Administrator, or iFIX WorkSpace: Expression Builder and iFIX Migration Tools), those settings are global for any Historian clients running on that computer.

Run a Query

You can run a query against the data that is contained in the Historian database tables. A query is a `SET` or `SELECT` statement, or a combination of both of these SQL statements. When you execute a `SELECT` or `SET` statement in the Historian Interactive SQL application, you can execute only one `SET` and one `SELECT` statement per query.

1. [Access the Historian Interactive SQL application \(on page 2607\)](#).
2. If you want to run a saved query, select **File > Open**, and then select the query that you want to run.
3. If you want to run a new query, enter your query in the **Query Entry** field.



The screenshot shows the 'Historian Interactive SQL - [MY_SERVER]' window. The query entered is: `SELECT tagname, timestamp, value, quality from ihRawData WHERE IntervalMilliseconds=3600000 AND CalculationMode=Average AND TimeStamp>=Now-1h ORDER BY TimeStamp, Tagname`. The results are displayed in a table with the following data:

	tagname	timestamp	value	quality
1	MY_SERVER.Simulation00001	11-Feb-2002 17:10:13.523	53,730.89	100.00
2	MY_SERVER.Simulation00002	11-Feb-2002 17:10:13.523	63,814.20	100.00
3	MY_SERVER.Simulation00003	11-Feb-2002 17:10:13.523	197,936.95	100.00
4	MY_SERVER.Simulation00004	11-Feb-2002 17:10:13.523	104,739.52	100.00
5	MY_SERVER.Simulation00005	11-Feb-2002 17:10:13.523	150,138.86	100.00
6	MY_SERVER.Simulation00006	11-Feb-2002 17:10:13.523	136,716.81	100.00
7	MY_SERVER.Simulation00007	11-Feb-2002 17:10:13.523	47,993.41	100.00
8	MY_SERVER.Simulation00008	11-Feb-2002 17:10:13.523	82,852.87	100.00

4. Select  or press Ctrl+E.
The query results appear.

Connect to a Server

The Historian Interactive SQL application allows you to make multiple connections to the same server or different servers. This allows you to look at data from different servers.

1. [Access the Historian Interactive SQL application \(on page 2607\).](#)
2. Select **File > New**.

The **Historian Interactive SQL Login** window appears.



The 'Historian Interactive SQL Login' dialog box features the 'Proficy* Historian Interactive SQL' logo. It contains the following fields and controls:

- Server:** A dropdown menu with a browse button (...).
- UserName:** A text input field.
- Password:** A text input field.
- Domain:** A text input field.
- Buttons:** OK, Help, and Cancel.

3. Select a Historian server, and then enter the username, password, and domain to connect to the server. If you do not enter user credentials, the currently logged-in user is considered.
4. Select **OK**.

A new session of the Historian Interactive SQL application appears, and it is connected to the server that you have specified. The session begins with the default values for **SET variables** (on page 2630).




Note:

If modifications or additions are made to the list of available Historian servers using any of the Historian clients (Excel, non-web Administrator, or iFIX WorkSpace: Expression Builder and iFIX Migration Tools), those settings are global for any Historian clients running on that computer.

Save a Query

When you save a query, it is saved as an .SQL file in the current working directory. You can later open the query in the Historian Interactive SQL application or in other client applications.

1. Access the Historian Interactive SQL application (on page 2607).
2. Enter your query into the **Query Entry** field.



3. Select **File > Save**.
The **Save Query to File** window appears.
4. Enter a name for the query.

**Important:**

Use the .SQL file extension.

5. Select

The query is saved in the working directory.

Export Query Results to Excel

1. Run the query that you want to export ([on page 2608](#)).

2. Select

The query results are exported to an Excel spreadsheet.

	A	B	C	D	E	F
1	tagname	timestamp	value	quality	samplingmode	direction
2	MY_SERVER.Simulation00001	55:15.7	53,730.89	100	Calculated	Forward
3	MY_SERVER.Simulation00001	56:15.7	53,730.89	100	Calculated	Forward
4	MY_SERVER.Simulation00001	57:15.7	53,730.89	100	Calculated	Forward
5	MY_SERVER.Simulation00001	58:15.7	53,730.89	100	Calculated	Forward
6	MY_SERVER.Simulation00001	59:15.7	53,730.89	100	Calculated	Forward
7	MY_SERVER.Simulation00001	00:15.7	53,730.89	100	Calculated	Forward
8	MY_SERVER.Simulation00001	01:15.7	53,730.89	100	Calculated	Forward
9	MY_SERVER.Simulation00001	02:15.7	53,730.89	100	Calculated	Forward
10	MY_SERVER.Simulation00001	03:15.7	53,730.89	100	Calculated	Forward
11	MY_SERVER.Simulation00001	04:15.7	53,730.89	100	Calculated	Forward
12	MY_SERVER.Simulation00001	05:15.7	53,730.89	100	Calculated	Forward
13	MY_SERVER.Simulation00001	06:15.7	53,730.89	100	Calculated	Forward
14	MY_SERVER.Simulation00001	07:15.7	53,730.89	100	Calculated	Forward
15	MY_SERVER.Simulation00001	08:15.7	53,730.89	100	Calculated	Forward
16	MY_SERVER.Simulation00001	09:15.7	53,730.89	100	Calculated	Forward
17	MY_SERVER.Simulation00001	10:15.7	53,730.89	100	Calculated	Forward

Format the date and time ([on page 2596](#)) so that they appear correctly.

Optimize the Query Performance

To optimize query performance, follow these guidelines:

- Perform `GROUP BY` on the server whenever available. For instance, Crystal Reports gives you the option to group on the server as opposed to the client.
- Use `DISTINCT` to eliminate duplicate rows.
- Be specific when specifying tag names. For instance, when using wildcards, be as specific as possible.
- Limit the duration between start and end times.
- Get as precise a data type as possible to improve storage efficiency and allow reporting tools such as Power BI or Crystal Reports to properly format the data in reports.
- Do not rely on `TOP` or `ROWCOUNT` to optimize performance because they do not change the load on the archive or network but instead they just limit what is returned to the caller.

Supported SQL Syntax

The OLE DB provider supports the `SET` and `SELECT` statements in SQL queries. The following conditions apply for the supported SQL syntax:

- The supported statements follow the standard SQL-92 conventions.
- Adhering to SQL standards, these statements are not case-sensitive.
- The OLE DB provider does not allow SQL inserts, updates, deletes, or commits; therefore, there is no event notification. You can only retrieve and analyze data.
- String data types are not supported.

Some reporting packages, such as Crystal Reports, hide the SQL syntax by allowing you to use experts and wizards. However, familiarity with SQL syntax may help you in troubleshooting and tuning your SQL commands.

The following figure shows a `SELECT` statement.



With a `SELECT` statement, you can specify the Historian table and columns from which you want to retrieve data. The OLE DB provider establishes the server name at connection time. You can filter the data returned from `SELECT` by specifying a filter option in the `WHERE` clause.

Supported SELECT Statements Syntax

`SELECT` statements allow you to retrieve data from the Historian database for reporting and analysis. The `SELECT` statements that the OLE DB provider supports follow standard SQL-92 conventions. You can use `SELECT` statements to retrieve information from any of the columns in any of the Historian tables. The `SELECT` statement returns a snapshot of data at the given time of the query.

The order that you specify the columns in the `SELECT` statement controls how the data is returned. For more information on the tables and each of the columns in each table, refer to [Historian Database Tables \(on page 2647\)](#).



Note:

To query tag names with spaces in them, you must enclose the full tag name in double quotes. For example, to query the `Copy of 5vkn391s.Simulation00001` tag from the `ihTrend` table, use the following query: `SELECT "Copy of 5vkn391s.Simulation00001" from ihTrend.`

WHERE Clauses

You can use a `WHERE` clause to specify search conditions in a `SELECT` statement. You can specify a condition for any column in the table using the `WHERE` clause.

For example, you can search all rows of data in the `ihTags` table, where the `DataType` column equals `SingleFloat`. In another instance, you can find all tags that belong to a particular collector. Or, you can search for all tags with a certain poll rate, or range of poll rates, or ones with polling disabled.

You can provide maximum 200 conditions in a `SELECT` statement.

For more information on the columns for each individual Historian table, refer to [Historian Database Tables \(on page 2647\)](#).

Example 1: Search for All Single Float Tags

```
SELECT* FROM ihtags WHERE datatype=singlefloat
```

Example 2: Specify Query Parameters to Obtain String Data

```
SELECT* FROM ihrawdata WHERE tagname=SimulationString00001
AND samplingmode=interpolated
AND IntervalMilliseconds=1H
```

In this example, you change the `SamplingMode` column from the default value of `Calculated` to `Interpolated` in order to retrieve string data.

Example 3: Use a WHERE Clause to Specify a Time Range

```
SELECT* FROM ihmessages WHERE timestamp>bom
```

Example 4: Use a Complex WHERE Clause to Find All Tags With a Specific Name and Description Pattern

```
SELECT* FROM ihtags
WHERE(tagname LIKE '*001*' AND description LIKE '*sim*')
OR (tagname LIKE '*02*'
AND (description LIKE '*sec*' OR description LIKE '*sim*'))
AND (timestamptype=source OR timestamptype=collector)
```

For more information on building complex `WHERE` clauses, see Logical Operators and Parenthetical Expressions.

ORDER BY

If you do not specify `ORDER BY`, the output of the row order cannot be assumed. For example, if you want to order the rows returned from the `ihCollectors` table by the `CollectorName` column, you must include that column name in `ORDER BY`.

As a more common example, when requesting timestamps with data, use the `Timestamp` column with `ORDER BY` to ensure that the samples are sorted in order by time.

`ORDER BY` sorts the returned records by one or more specified columns in either ascending or descending order. By default, the ascending order is considered. You can order results by one or more columns. If you sort by multiple columns, the sorting priority begins with the first column listed in the query, and then the next column, and so on.

Abbre- viation	Description
ASC	Specifies that the values must be sorted in ascending order, from lowest value to highest value.
DESC	Specifies that the values must be sorted in descending order, from highest value to lowest value.

The OLE DB provider treats `Null` values as the lowest possible values. It processes `ORDER BY` before it performs any `RowCount` truncation.

Example 1: Retrieve Collectors in Descending Order Sorted by the Collectorname Column

```
SELECT * FROM ihcollectors ORDER BY collectorname DESC
```

Example 2: Retrieve Messages in Ascending Order Sorted by Timestamp and Other Columns

```
SELECT * FROM ihmessages
WHERE timestamp>='5-oct-2001 00:00:00'
AND timestamp<='18-jan-2002 00:00:00'
ORDER BY timestamp, topic, username, messagenumber, messagestring
```

TOP

With the `TOP` predicate, you can limit the number of rows returned to a specified number or percentage of rows. And then, enter the rest of the query. Typically, you include `ORDER BY` in the query to sort the rows in a specified order.

When you select the top number or top percentage of rows, the returned value is limited by the `RowCount`. For instance, suppose you want the top 30 percent of rows from a query that can return a possible 10,000 rows, but the `RowCount` is set to 1000. The percentage logic processes the 3000 rows first, then it reduces the number to 1000 rows, as specified by `RowCount`. The final result returns 1000 rows, even though the top 30 percent is processed first. Use a `SET` statement or `WHERE` clause to change or disable the `RowCount` behavior.

Example 1: Return the Top 40 Tags in Alphabetical Order

```
SELECT TOP 40 * FROM ihtags ORDER BY Tagname
```

Example 2: Return the Top 10 Most Recent Messages

```
SELECT TOP 10 timestamp, topic, username, messagestring FROM
ihmessages WHERE timestamp<Now ORDER BY timestamp DESC
```

Example 3: Return the Top 10 Percent, RowCount Disabled

```
SET rowcount=0
SELECT TOP 10 PERCENT timestamp, topic, username, messagestring
FROM ihmessages WHERE timestamp<Now
ORDER BY timestamp DESC
```

LIKE

Use the `LIKE` expression when searching for column data similar to a specified text string. By using wildcards, you can specify the text strings that you want to search. You can use the wildcard before and/or after the text that you want to search for. Use an asterisk (*) for multiple unknown characters in a search string. Use a question mark (?) for a single unknown character.



Note:

You can also use a percentage (%) to select all tags that contain a specific string in the tag name and an underscore (_) to select all tags when you are unsure of only one character in the tag name. You must enclose these wildcard characters in single quotes (for example, '%' or '_') when you use them in Historian tag names, but do not use single quotes if you want them to be treated as wildcards in SQL.

Example 1: Use LIKE With Multiple Character Replacement

```
SELECT * FROM ihtags WHERE tagname LIKE *.Simulation*

ORDER BY tagname

SELECT * FROM ihtags WHERE tagname LIKE %.Simulation%
```

Example 2: Use LIKE With Single Character Replacement

```
SELECT * FROM ihtags WHERE tagname LIKE MYSERVER.Simulation0000?

ORDER BY tagname

SELECT * FROM ihtags WHERE tagname LIKE MYSERVER.Simulation0000'_'

ORDER BY tagname
```

AS

Use `AS` when you want to control the name of an output column. You can use `AS` in all columns and tables except the `ihTrend` table. In the `ihTrend` table, you can only use `AS` with the `TimeStamp` column.

Example: Set the Output Column Name

```
SELECT status, collectorname AS Name, collectortype,
status AS 'The Status', collectordescription FROM ihcollectors
```

DISTINCT

`DISTINCT` eliminates duplicate rows when all columns are equal. Floating-point values, however, may not compare as expected, depending on the precision. For example, if the

numbers to the right of the decimal point are not equal for all values, similar columns are not eliminated. The columns must be exactly equal to be eliminated.

Example 1: Retrieve the Set of Unique Data Types Used in an Archive

```
SELECT DISTINCT datatype FROM ihtags
```

Example 2: Retrieve the Set of Tags With Raw Data Samples on a Specific Date

```
SELECT DISTINCT tagname FROM ihRawData WHERE samplingmode=rawbytime
AND timestamp>='11/28/2001' AND timestamp<='11/29/2001'
```

GROUP BY

GROUP BY combines records with identical values in the specified field list into a single record. Then, you can compute an aggregate value for the grouped records. The aggregate column does not exist in the actual table. Another calculated column is created with the results.

Example: Group Messages by User Name and Topic

```
SELECT username, topic, COUNT(*) FROM ihmessages
WHERE timestamp >= '1-dec-2001 00:00:00'
AND timestamp <= '7-dec-2001 00:00:00'
GROUP BY username, topic ORDER BY username, topic
```

SQL Aggregate Functions

SQL aggregate functions perform a calculation on a set of values in a column and return a single value. For instance, when comparing multiple tags, you can retrieve the minimum (**MIN**) of the returned minimum values. You usually use aggregate functions with the **GROUP BY** clause, but it is not required. For more information, see Group By.

Table 387. Supported Aggregate Functions

Function	Description
AVG	Returns the average of the values in a group. Null values are ignored.
COUNT	Returns the number of items in a group. Null values are not ignored.
MAX	Returns the maximum value in a group. Null values are ignored.
MIN	Returns the minimum value in a group. Null values are ignored.

Table 387. Supported Aggregate Functions (continued)

Function	Description
SUM	Returns the sum of all the values in a group. SUM can be used with numeric columns only. Null values are ignored.
STDEV	Returns the statistical standard deviation of all values in a group. Null values are ignored.
STDEV- VP	Returns the statistical standard deviation for the population for all values in a group. Null values are ignored.
VAR	Returns the statistical variance of all values in a group. Null values are ignored.
VARP	Returns the statistical variance for the population for all values in a group. Null values are ignored.

STDEV, STDEV, VAR, and VARP

If a variance is defined as the deviation from an average data set value, and N is the number of values in the data set, then the following equations apply:

```
VAR = (Sum of Variances)^2 / (N - 1)
VARP = (Sum of Variances)^2 / (N)
STDEV = SquareRoot (VAR)
STDEV = SquareRoot (VARP)
```

Example 1: Retrieve the Total Number of Tags

```
SELECT COUNT(*) FROM ihTags
```

Example 2: Calculate Values for Multiple Tags

```
FROM ihrawdata WHERE tagname LIKE '*0001*'
AND timestamp>='28-dec-2001 00:00'
AND timestamp<='29-dec-2001 00:00'
AND samplingmode=interpolated
AND intervalmilliseconds=1h GROUP BY tagname ORDER BY tagname
```

The following figure displays the results of this query. Note the column names (**Sum of value**, **Avg of value**, **Min of value**, and **Max of value**) returned for the calculated columns.

Historian Interactive SQL - [MY_SERVER]

```
SELECT tagname, count(*), sum(Value), Avg(Value), Min(Value), Max(Value) from ihRawData
WHERE tagname like "0001*" AND timestamp="28-nov-2001 00:00" AND timestamp<="29-nov-2001 00:00" AND
SamplingMode=interpolated AND IntervalMilliseconds=1h GROUP BY tagname ORDER BY tagname
```

	tagname	Count	Sum of value	Avg of value	Min of value	Max of value
1	MY_SERVER.Simulation00001	24	1,467,097.98	61,129.08	0.00	195,489.40
2	MY_SERVER.Simulation00010	24	1,819,879.75	75,828.32	0.00	177,160.00
3	MY_SERVER.Simulation00011	24	1,667,360.44	69,473.35	0.00	197,192.30
4	MY_SERVER.Simulation00012	24	1,280,159.93	53,340.00	0.00	168,804.00
5	MY_SERVER.Simulation00013	24	1,603,918.59	66,829.94	0.00	195,904.40
6	MY_SERVER.Simulation00014	24	2,062,276.05	85,928.17	0.00	198,425.30
7	MY_SERVER.Simulation00015	24	2,049,800.13	85,408.34	0.00	194,622.60
8	MY_SERVER.Simulation00016	24	1,645,503.09	68,562.63	0.00	191,515.90
9	MY_SERVER.Simulation00017	24	1,645,930.36	68,580.43	0.00	191,845.50
10	MY_SERVER.Simulation00018	24	2,095,065.18	87,294.38	0.00	199,377.40
11	MY_SERVER.Simulation00019	24	2,156,987.20	89,874.47	0.00	189,227.00

Query Complete. 1/16/2002 10:53 PM

Conversion Functions

The Historian OLE DB provider generally returns data with the `VARIANT` data type. Some OLE DB clients may not understand `VARIANT` data, however, and will require the data to be returned as an integer, float, or string data type. To accommodate this, the OLE DB provider includes the functions described in the following table.

Table 388. Conversion Functions

Function	Description
<code>to_double</code> (<i>column</i>)	Converts the specified <i>column</i> to a double float data type.
<code>to_integer</code> (<i>column</i>)	Converts the specified <i>column</i> to a single integer data type.
<code>to_string</code> (<i>column</i>)	Converts the specified <i>column</i> to a string data type.



Note:

- You must edit the SQL statement manually to add conversion functions.
- You can also use the fully qualified column name (for example, `ihRawData.value`).
- Conversion functions are not available in `WHERE` or `JOIN (ON)` clauses.
- Conversion functions cannot be used within aggregate functions.

Example: Convert Values to Double Float

```
select timestamp, to_double(value), quality from ihRawData
```

JOIN

A table join is an operation that combines rows from two or more tables. You can join as many tables as you want within one `JOIN` statement. When you use a table `JOIN` in a `SELECT` statement, you must specify the column name and table when selecting the columns that you want to compare. The syntax for table joins follows standard SQL language format.

Table 389. Supported Join Operations

Supported Join Feature	Description
Inner Join	Combines records from two tables whenever there are matching values.
Left Join or Left Outer Join	Returns all of the rows from the left (first) of two tables, even if there are no matching values for records in the right (second) table.
Right Join or Right Outer Join	Returns all of the rows from the right (second) of two tables even if there are no matching values for records in the left (first) table.
Full Join or Outer Join	Returns all rows in both the left and right tables. Any time a row has no match in the other table, <code>SELECT</code> list columns from the other table contain null values. When there is a match between the tables, the entire result set row contains data values from the base tables.
Cross Join	Returns all rows from the left table. Each row from the left table is combined with all rows from the right table.

Table 389. Supported Join Operations (continued)

Supported Join Feature	Description
Old Join syntax	Simply selects columns from multiple tables using the <code>WHERE</code> clause without using the <code>JOIN</code> keyword.

Table joins are a powerful tool when organizing and analyzing data. A few examples are included in this section. However, refer to the documentation for your third-party reporting software for more complete information on building more complex queries.

JOIN Operations Rules

The following rules apply when working with `JOIN` operations for the Historian OLE DB provider:

- You cannot join a table with itself.
- You cannot join any table with the `ihTrend` or `ihQuerySettings` tables.

The following examples display different types of joins with the `ihComments` table. Comments themselves are not usually that useful unless they are combined with data, as you do with the `JOIN` statements in the following examples.

Example 1: Perform an Inner Join to Retrieve Only Data With Associated Comments

```
SELECT d.timestamp, d.tagname, d.value, c.username, c.comment
FROM ihrawdata d INNER JOIN ihcomments c
ON c.tagname=d.tagname AND c.timestamp=d.timestamp
WHERE d.tagname LIKE '*0001*'
ORDER BY d.timestamp, d.tagname, c.username, c.comment
```

Example 2: Perform a Left Outer Join to Retrieve All Data With and Without Comments

```
SELECT d.timestamp, d.tagname, d.value, c.comment FROM ihrawdata d
LEFT OUTER JOIN ihcomments c
ON c.tagname=d.tagname AND c.timestamp=d.timestamp
WHERE d.tagname LIKE '*0001*' ORDER BY d.timestamp, d.tagname
```

Example 3: Perform a Right Outer Join to Retrieve All Comments and Their Accompanying Data

```
SELECT d.tagname, d.timestamp, d.value, c.comment FROM ihrawdata d
RIGHT OUTER JOIN ihcomments c
ON c.tagname=d.tagname AND c.timestamp=d.timestamp
WHERE d.tagname LIKE '*0001*' ORDER BY d.tagname, d.timestamp
```

Example 4: Perform a Cross Join

```
SELECT * FROM ihCollectors CROSS JOIN ihArchives
```

Example 5: Perform a Cross Join (Older Syntax)

```
SELECT ihTags.Tagname, iharchives.Filename FROM ihTags, ihArchives
```

Example 6: Join the ihMessages and ihArchives Tables

This example uses `SET StartTime` before the `SELECT` statement. The `SET` statement is necessary because the timestamp criteria in `SELECT` do not narrow down the time range for the `ihMessages` table until after the results have been collected and the join takes place.

```
SET starttime='1-jan-2000'
SELECT a.starttime, a.endtime, m.*
FROM ihmessages m JOIN iharchives a
ON m.timestamp>=a.starttime
AND m.timestamp<=a.endtime WHERE a.iscurrent=true
```

Example 7: Interleave Data and Messages by Timestamp

```
SELECT d.timestamp, m.timestamp, d.tagname, m.messagestring,
d.value FROM ihRawData d FULL OUTER JOIN ihMessages m
ON d.timestamp=m.timestamp WHERE d.tagname=simulation00001
AND d.timestamp>='30-nov-2001 00:00:00'
AND d.timestamp<='06-dec-2001 00:00:00'
```

Example 8: Retrieve the Greatest Values Across All Simulation Tags

In the following example, we join the `ihRawData` and `ihTags` tables, because the `ihRawData` table does not contain the `CollectorType` column.

```
SELECT TOP 300 ihRawData.tagname, ihRawData.timestamp,
ihRawData.value, ihRawData.Quality FROM ihRawData
INNER JOIN ihTags ON ihRawdata.Tagname = ihTags.Tagname
```

```

WHERE ihRawData.tagname LIKE simulation*

AND ihRawData.timestamp>=11/28/2001

AND ihRawData.timestamp<=11/29/2001

AND ihRawData.samplingmode=interpolated AND ihRawData.intervalmilliseconds=1H

AND ihTags.datatype!=FixedString

AND ihTags.datatype!=variablestring

AND ihRawData.quality>0

ORDER BY value DESC, timestamp DESC

```

Example 9: Join the ihComments and ihRawData Tables

```

SET starttime='28-nov-2001 08:00', endtime='29-nov-2001 09:00',

samplingmode=interpolated, intervalmilliseconds=6m

SELECT d.tagname, d.timestamp, d.value, c.storedontimestamp, c.username,

c.datatypehint, c.comment FROM ihcomments c

FULL OUTER JOIN ihrawdata d ON c.tagname=d.tagname

AND c.timestamp=d.timestamp

WHERE d.tagname LIKE '*0001*'

ORDER BY d.tagname, d.timestamp,c.storedontimestamp, c.datatypehint,

c.username, c.comment

```

Example 10: Report by Tag Description

In the following example, we join the `ihRawData` and `ihTags` tables to get the `Description` column from the `ihTags` table.

```

SELECT d.timestamp, t.description, d.value, d.quality

FROM ihrawdata d INNER JOIN ihtags t ON d.tagname=t.tagname

WHERE d.tagname LIKE '*0001' ORDER BY d.timestamp, t.description

```

Example 11: Join Three Tables

```

SELECT ihTags.Tagname, ihTags.Description, ihRawData.TimeStamp,

ihRawData.Value, ihRawData.SamplingMode, ihComments.Comment

FROM ihTags ihTags, ihRawData ihRawData, ihComments ihComments

WHERE ihTags.Tagname = ihRawData.Tagname

AND ihRawData.Tagname = ihComments.Tagname

AND ihRawData.TimeStamp = ihComments.TimeStamp

AND ihRawData.TimeStamp >= {ts '2002-03-01 09:39:00.000'}

AND ihRawData.TimeStamp <= {ts '2002-03-01 09:41:00.000'}

AND ihRawData.SamplingMode = 'RawByTime'

```

```
AND ihTags.Tagname LIKE '%TestTag1%'
```

Example 12: Perform a Right Join (Older Syntax)

```
SELECT ihTags.Tagname, ihTags.CollectionInterval, ihCollectors.CollectorName,
ihCollectors.DefaultCollectionInterval
FROM ihTzzz|
```

Example 13: Perform a Left Join (Older Syntax)

```
SELECT ihTags.Tagname, ihTags.CollectionInterval, ihCollectors.CollectorName,
ihCollectors.DefaultCollectionInterval
FROM ihTags ihTags, ihCollectors ihCollectors
WHERE
ihTags.CollectionInterval *=ihCollectors.DefaultCollectionInterval
AND ihTags.Tagname LIKE '%TestTag%'
```

Quotation Marks

You must use quotation marks when you specify a string that contains a space, a comma, or a reserved word. Reserved words are defined by the SQL-92 conventions. Single and double quotes are equivalent in queries.

Example: Use Quotes When a Text String Contains a Space

```
SELECT * FROM ihtags WHERE comment LIKE 'alert message'
```

Timestamp Formats

Timestamps appear not just in the `TimeStamp` columns, but also in columns such as the `StartTime`, `EndTime`, and `LastModified` columns. You can use the date and/or time in a SQL statement that contains a timestamp. Valid date and time formats are as follows:

- System short date and time.
- SQL date and time.
- ODBC date and time.

The time format for system short timestamps is the same as the time format defined in the Windows Control Panel.

When entering a query you should use a period as the decimal separator to separate seconds from milliseconds or microseconds.

When using the SQL date and time, you should always use the English abbreviations for the desired month.

If you enter only a start time, the end time is assumed to be now. For example, if you enter `starttime > yesterday` in a `WHERE` clause, the end time for the query is now, even if you previously set an end time.

If you enter only an end time, the start time is December 31, 1969, 19:00:00.001. If you use this as the start time, you can overload the Historian server and the provider. For example, if you use `timestamp < now`, you might cause an overload.

Example 1: Use the System Short Date and Time

```
SET starttime='02/01/2002 11:00:00'
```

Example 2: Use the SQL Date and Time

```
SET starttime='14-sep-2001 11:00:00'
```

Example 3: Use the ODBC Date and Time

```
SET starttime={ts '2002-06-20 15:34:08'}
```

Example 4: Set the Start Time to 4 AM Today

```
SET starttime='04:00:00'
```

Example 5: Set the Start Time in Milliseconds

```
SET starttime='7/12/2011 12:03:16.183'
```

Example 6: Set the Start Time in Microseconds

```
SET starttime='7/12/2011 12:03:16.178439'
```

Date and Time Shortcuts

Time Segment	Meaning
<code>now</code>	Now (the time and date that you execute the query)
<code>today</code>	Today at midnight
<code>yesterday</code>	Yesterday at midnight
<code>mon</code>	The previous Monday at midnight
<code>tues</code>	The previous Tuesday at midnight
<code>wed</code>	The previous Wednesday at midnight

Time Segment	Meaning
thurs	The previous Thursday at midnight
fri	The previous Friday at midnight
sat	The previous Saturday at midnight
sun	The previous Sunday at midnight
boy	First day of year at midnight
eoym	Last day of year at midnight
bom	First day of month at midnight
ecom	Last day of month at midnight

Example 1: Set the Start Time to the First Day of the Month

```
SET starttime=bom
```

Example 2: Retrieve Messages Dated Today

```
SELECT * FROM ihmessages WHERE timestamp>=today
```

Relative Date and Time Shortcuts

Optionally, you can add or subtract relative time shortcuts to the absolute times.

Table 390. Relative Date and Time Shortcuts

Time Segment	Meaning
s	Second
m	Minute
h	Hour
d	Day
w	Week
micro	Microsecond

You can use relative time shortcuts when defining time intervals. For instance, use these shortcuts when you specify a value for the `IntervalMilliseconds` column.



Note:

You cannot use relative time shortcuts to add or subtract microseconds to or from absolute times.

Example 1: Set the Start Time to 10 Days Before Yesterday and End Time to Today

```
SET starttime=yesterday-10d, endtime=today
SELECT * FROM ihQuerySettings
```

Example 2: Retrieve the Previous 24 Hours of Messages

```
SELECT * FROM ihMessages WHERE timestamp>=Now-24h
```

Example 3: Select Data Starting at 1AM Yesterday and Ending Now

```
SELECT * FROM ihrawdata WHERE timestamp>=yesterday+1h AND timestamp<=now
```

Example 4: Retrieve Raw Data With a 1 Hour (3600000 Milliseconds) Interval Between Returned Samples

```
SELECT * FROM ihrawdata WHERE intervalmilliseconds=1h
```

Example 5: Retrieve Raw Data With a 100 Microseconds Interval Between Returned Samples

```
SELECT * FROM ihrawdata WHERE intervalmilliseconds=100micro
and starttime>= '7/12/2011 12:03:16.100000' and endtime<='
```

Example 6: Retrieve This Week's Output to Date

```
SET starttime=Sun, endtime=Now, intervalmilliseconds=1d, samplingmode=rawbytime
SELECT tagname, SUM(value) FROM ihRawData WHERE tagname LIKE *00* GROUP BY tagname
```

Comparison Operators

Table 391. Expression Comparisons

Comparison Symbol	Meaning
<	Less Than
>	Greater Than
<=	Less Than or Equal
>=	Greater Than or Equal
=	Equal

Table 391. Expression Comparisons (continued)

Comparison Symbol	Meaning
<code>!=</code>	Not Equal
<code>!></code>	Not Greater Than
<code>!<</code>	Not Less Than
<code>BETWEEN x AND y</code>	Between the values <code>x</code> and <code>y</code> inclusive, where <code>x</code> and <code>y</code> are numeric values

A literal on the left side of the comparison operator is not supported. For example, this statement would fail:

```
SELECT DISTINCT tagname FROM ihRawData WHERE 50>Value
```

But the following statement succeeds since the `Value` column is to the left of the `>` operator:

```
SELECT DISTINCT tagname FROM ihRawData WHERE Value>50
```

Example 1: Retrieve Tags with a High EGU Greater Than 300

```
SELECT DISTINCT tagname, loengineeringunits, hiengineeringunits
FROM ihTags WHERE hiengineeringunits > 300
```

Example 2: Retrieve Tags with a Specific Description

```
SELECT tagname, description FROM ihTags WHERE description = "aa"
```

Example 3: Retrieve All Samples Where the Value Exceeds Query Supplied Values

```
SELECT timestamp, tagname, value FROM ihRawData
WHERE samplingmode=rawbytime AND value>75
```

Example 4: Retrieve All Samples Where the Value is Between Query Supplied Values

```
SELECT timestamp, tagname, value FROM ihRawData
WHERE samplingmode=lab AND value BETWEEN 25 AND 75
```

Example 5: Retrieve All Tag Names Starting with an A or B

```
SELECT * FROM ihtags WHERE tagname < 'C'
```

Logical Operators

The following logic operators are supported:

- AND
- OR
- NOT

Example 1: Use the AND Logical Operator

```
SELECT * FROM ihTags WHERE Tagname LIKE 'Simulation*'
AND CollectionInterval<3000
```

Example 2: Use the OR Logical Operator

```
SELECT * FROM ihTags WHERE Tagname LIKE 'ComputerName.Simulation*'
OR tagname LIKE '*String'
```

Example 3: Use the NOT Logical Operator

```
SELECT * FROM ihTags WHERE NOT Datatype=SingleFloat
```

Example 4: Use the NOT Logical Operator With a LIKE Expression

```
SELECT * FROM ihTags WHERE Tagname NOT LIKE '*String'
```

Parenthetical Expressions

Parentheses control the order of evaluation of the logical operators in an expression. The OLE DB provider supports parentheses in a `WHERE` clause. You can use multiple sets of parentheses, and nest parenthetical expressions.

Example 1: Use Parentheses

```
SELECT * FROM ihTags
WHERE (tagname LIKE '*001' AND description="aa") OR tagname LIKE '*002'
```

Example 2: Use Parentheses with Logical Operators and Timestamps

```
SELECT * FROM ihRawData WHERE tagname=Simulation00001 AND
(timestamp=>Tu AND timestamp<=Wed OR timestamp>=Fri AND time
```

Example 3: Use Multiple Sets of Parentheses

```
SELECT * FROM ihtags
WHERE (tagname LIKE '*001*' AND description LIKE '*sim*') OR
(tagname LIKE '*02*' AND (description LIKE '*sec*' OR description LIKE '*sim*'))
```

Supported SET Statement Syntax

The use of `SET` statements is not mandatory because you can also specify query parameters in a `WHERE` clause. However, `SET` statements can make your queries more readable. By using `SET` statements, you can

save time by simplifying `SELECT` queries, because you do not have to retype query parameters each time you issue a new `SELECT` statement. The `SET` parameters persist for the entire session.

With a `SET` statement, you can define various defaults for your queries to use, such as:

- The start date and time of the selected data
- The end date and time
- The calculation mode
- The number of rows returned
- The data sampling mode

For more information, refer to [ihQuerySettings Table \(on page 2709\)](#).

When entering numbers, do not use a thousands separator. For example, if you want to set a collection interval to 7,000 milliseconds, use the following code:

```
SET IntervalMilliseconds = 7000
```

Correct SET Without Comma to Separate Thousands Place

Multiple `SET` statements in the same command are not supported. Combine multiple variables in the same `SET` statement.

Correct:

```
SET starttime=yesterday-10d, endtime=today, samplingmode=interpolated
```

Incorrect:

```
SET starttime=yesterday-10d
SET endtime=today
SET samplingmode=interpolated
```

SET Variables

The following table outlines the supported SQL variables and settings that you can use in a `SET` statement. If you do not change any variables using the `SET` statement or a `WHERE` clause in your `SELECT` statement, the default session variables are considered. You can apply any of the variables described in the following table to the current session. In turn, these settings are used when retrieving information from the Historian database tables. `SET` variables persist from statement to statement.

Some session variables that you define with the `SET` statement accept abbreviations. You must type at least the abbreviation for the statement to work. For instance, for the `CalculationMode` setting, you can

enter the abbreviation `Interp` for the `Interpolated` setting. The accepted abbreviations are highlighted in bold in the following table.

Table 392. SET Statement Variables

Variable	Description	Default Setting
Start- Time	<p>A valid date and time string, such as:</p> <ul style="list-style-type: none"> • <code>StartTime = '14-sep-200111:00:00'</code> • <code>StartTime = Now -1h</code> • <code>StartTime = '02/01/199811:00:00'</code> • <code>StartTime = {ts '2002-06-20 15:34:08'}</code> • <code>StartTime = '7/12/201112:03:16.100000'</code> 	Two hours prior to execution of the query.
End- Time	<p>A valid date and time string, such as:</p> <p><code>EndTime = '14-sep-200112:00:00'</code></p>	The current time that you execute the query.
Sam- pling- Mode	<p>String that represents the mode of sampling data from the archive:</p> <ul style="list-style-type: none"> • <code>CurrentValue</code> • <code>Interpolated</code> • <code>InterpolatedtoRaw</code> • <code>RawByTime</code> • <code>RawByNumber</code> • <code>Calculated</code> • <code>Lab</code> • <code>LabtoRaw</code> • <code>Trend</code> • <code>TrendtoRaw</code> • <code>Trend2</code> • <code>TrendtoRaw2</code> • <code>RawByFilterToggle</code> 	<code>Calculated</code>
Di- rec- tion	<p>String that represents the direction of data sampling from the archive, beginning at the start time. <code>Direction</code> applies to the <code>RawByTime</code> and <code>RawByNumber</code> sampling modes:</p>	<code>Forward</code>

Table 392. SET Statement Variables (continued)

Variable	Description	Default Setting
	<ul style="list-style-type: none"> • Forward • Backward 	
Num- ber- Of- Sam- ples	<p>Any positive integer that represents the number of samples from the archive to retrieve. Do not enter a thousands separator. For example, enter 1000 and not 1,000.</p> <p>Samples are evenly spaced within the time range defined by start and end times for most sampling modes. For the <code>RawByNumber</code> sampling mode, the <code>NumberOfSamples</code> attribute determines the maximum number of values to retrieve. For the <code>RawByTime</code> sampling mode, the <code>NumberOfSamples</code> is ignored.</p>	0 (use <code>IntervalMilliseconds</code>)
In- ter- val- Mil- lisc- onds	<p>Any positive integer that represents the interval (in milliseconds) between returned samples.</p> <p>For example:</p> <ul style="list-style-type: none"> • If you run a query with <code>'IntervalMilliseconds = 100'</code>, it returns samples in 100-millisecond intervals. • If you run a query with <code>'IntervalMilliseconds = 100micro'</code>, it returns samples in 100-microsecond intervals. 	60000 (one minute)
Cal- cula- tion- Mode	<p>The <code>CalculationMode</code> column applies only if the <code>SamplingMode</code> is set to <code>Calculated</code>. It represents the type of calculation to perform on archive data:</p> <ul style="list-style-type: none"> • Average • StandardDeviation • Total • Minimum • MaximumCount • RawAverage • RawStandardDeviation • RawTotal • MinimumTime • MaximumTime • Count • TimeGood • FirstRawValue 	Average

Table 392. SET Statement Variables (continued)

Variable	Description	Default Setting
	<ul style="list-style-type: none"> • FirstRawTime • LastRawValue • LastRawTime • TagStats 	
FilterTag	<p>A valid tagname used to define the filter. For example:</p> <pre>FilterTag = 'SimulationString00001'</pre> <p>You can specify only a single tag ID can be specified in the FilterTag. Wildcards are not supported. FilterTag is used in conjunction with FilterValue, FilterComparisonMode, and FilterMode.</p>	An empty space (meaning FilterTag is not used)
FilterMode	<p>String that represents the type of time filter:</p> <ul style="list-style-type: none"> • ExactTime • BeforeTime • AfterTime • BeforeAndAfterTime <p>For example, AfterTime indicates that the filter condition should be True starting at the timestamp of the archive value that triggered the True condition and leading up to the timestamp of the archive value that triggered the False condition. FilterMode is used in conjunction with FilterValue, FilterComparisonMode, and FilterTag.</p>	BeforeTime
FilterComparisonMode	<p>String that represents the type of comparison to be made on the filter comparison value:</p> <ul style="list-style-type: none"> • Equal • EqualFirst • EqualLast • NotEqual • LessThan • GreaterThan • LessThanEqual • GreaterThanEqual • AllBitsSet 	Equal

Table 392. SET Statement Variables (continued)

Variable	Description	Default Setting
	<ul style="list-style-type: none"> • AnyBitSet • AnyBitNotSet • AllBitsNotSet <p>If you enter <code>FilterTag</code> and <code>FilterComparisonValue</code> in the <code>SET</code> statement, time periods are filtered from the results where the filter condition is <code>False</code>. <code>FilterComparisonMode</code> is used in conjunction with <code>FilterValue</code>, <code>FilterMode</code>, and <code>FilterTag</code>.</p>	
<p>FilterExpression</p>	<p>An expression that includes multiple filter conditions. You can use <code>FilterExpression</code> instead of <code>FilterTag</code>, <code>FilterComparisonMode</code>, and <code>FilterValue</code>.</p> <p>Example:</p> <pre>FilterExpression = 'BatchID=B1'</pre> <p>While using <code>FilterExpression</code>, the expression is passed within single quotes, and for complex expressions we write the conditions within parentheses. There is no maximum length for <code>FilterExpression</code>.</p>	
<p>FilterValue</p>	<p>String that represents the value with which to compare the filter tag to determine the appropriate filter times. Wildcards are not supported. Do not use a comma for the thousands separator.</p> <p>For example:</p> <pre>FilterValue = 'ABCD-1086031382099'</pre> <p>The <code>FilterValue</code> is used in conjunction with <code>FilterComparisonMode</code>, <code>FilterMode</code>, and <code>FilterTag</code>.</p>	<p>An empty space (meaning filtering is not used)</p>
<p>TimeZone</p>	<p>String that represents the type of time zone that should be applied to timestamps:</p> <ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT) <p>For example, an explicit bias number of <code>300</code> represents 300 minutes from GMT.</p> <div style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Note: Time zones are not supported on Windows 9x computers.</p> </div>	<p>Client</p>

Table 392. SET Statement Variables (continued)

Variable	Description	Default Setting
Daylight-Saving-Time	Indicates whether Daylight Saving Time logic should be applied to timestamps. Valid values: <ul style="list-style-type: none"> • True • False 	Date and time settings in your Windows Control Panel
RowCount	A number that indicates the maximum number of rows that can be returned. 0 indicates there is no limit to the number of rows returned.	5000

SET Statements and Variables Examples

If you do not change any variables using the `SET` statement or a `WHERE` clause in your `SELECT` statement, the default session variables are considered. For instance, if you do not specify a start and end time for your collected data, the data output from a `SELECT` statement will be the last two hours prior to execution of the query.

For example, if you want to `SELECT` all of the messages from the `ihMessages` table for the last day, you must explicitly state that you want the messages from the last day in the query. Otherwise, only the messages from the last two hours are displayed when you run the query, since that is the default setting.

`SET` statement variables persist during a session until changed. You can combine the `SET` statement on the same line as the `SELECT` statement.

Perform a Simple SET

```
SET samplingmode=currentvalue
```

Perform Multiple SETs

```
SET starttime='14-sep-2001 11:00:00', endtime='14-sep-2001 12:00:00',
samplingmode=interpolated, intervalmilliseconds=
```

Prepare for a RawByTime Query

```
SET starttime='14-sep-2001 11:00:00', endtime='14-sep-2001 12:00:00',
samplingmode=rawbytime
```

Prepare for a RawByNumber Query

```
SET starttime='14-sep-2001 11:00:00', samplingmode=rawbynumber,
numberofsamples=10, direction=backward
```

Prepare for One Hour Minimums

```
SET starttime='15-sep-2001 00:00:00', endtime='16-sep-2001 00:00:00',
samplingmode=calculated, intervalmilliseconds=36
```

Prepare for a Filtered Data Query

```
SET starttime='14-sep-2001 11:00:00', endtime='14-sep-2001 12:00:00',
samplingmode=current, filtertag='MY_SERVER.simul
```

Throttle Results with a SET Statement

```
SET ROWCOUNT = 4
SELECT Tagname FROM ihTags
```

Combined SET and SELECT Statements

The OLE DB provider allows you to execute one `SELECT` statement and one `SET` statement per query. Enter a space or a line break to indicate the end of a statement in a query. You do not need to use a semicolon (;) at the end of the line or statement.

Use SET and SELECT Statements on the Same Line

```
SET samplingmode=interpolated SELECT * FROM ihquerysettings
```

Use SET and SELECT Statements on Different Lines

```
SET samplingmode=calculated, starttime=yesterday, endtime=today
SELECT * FROM ihquerysettings
```

Parameterized SQL Queries

Parameterized SQL queries allow you to place parameters in an SQL query instead of a constant value. A parameter takes a value only when the query is executed, which allows the query to be reused with different values and for different purposes. Parameterized SQL statements are available in some analysis clients and Historian SDK.

For example, the following query contains a parameter for the collector name:

```
SELECT* FROM ihtags WHERE collectorname=? ORDER BY tagname
```

If your analysis client passes the parameter `iFIX_Albany` along with the query, it looks like follows when executed in Historian:

```
SELECT* FROM ihtags WHERE collectorname='iFIX_Albany' ORDER BY tagname
```

The advantage of using parameterized SQL queries is that you can prepare them ahead of time and reuse them for similar applications without having to create distinct SQL queries for each case. For instance, you can use the previous example in any context where you want to get tags from a collector. You can also use parameterized queries with dynamic data, where you do not know what the values will be until the statement is executed.

If your analysis client supports parameterized queries, it will automatically pass the parameter data along with a named query for Historian to process. In the case of multiple parameters, the analysis client will read the named query, and order the parameters to match.



Note:

You cannot use parameters to substitute table names or columns in a query.

Multiple Parameters

To create a query with multiple parameters, place a question mark (?) for every parameter whose value you want to substitute in the query. For example, if you want an SQL query to match two `WHERE` conditions, `collectorname` and `tagname`, use the following parameterized query:

```
SELECT* FROM ihtags WHERE collectorname=? AND tagname like ? ORDER BY tagname
```

When executed, the parameterized SQL query will add the parameters as they are received from the analysis application. In the previous example, the `collectorname` parameter would be received first, followed by the `tagname` parameter. Your analysis client will order the parameters based on the query it is running.



Note:

If you want to enter wildcard data in your parameterized queries, include the wildcard characters as part of the parameter. For instance, in the previous example, if you want to find any tagnames with the string `iFIX` in them, pass it the `*iFIX*` parameter.

Optimize the Query Performance

To optimize query performance, follow these guidelines:

- Perform `GROUP BY` on the server whenever available. For instance, Crystal Reports gives you the option to group on the server as opposed to the client.
- Use `DISTINCT` to eliminate duplicate rows.
- Be specific when specifying tag names. For instance, when using wildcards, be as specific as possible.
- Limit the duration between start and end times.
- Get as precise a data type as possible to improve storage efficiency and allow reporting tools such as Power BI or Crystal Reports to properly format the data in reports.
- Do not rely on `TOP` or `ROWCOUNT` to optimize performance because they do not change the load on the archive or network but instead they just limit what is returned to the caller.

Troubleshooting and Frequently Asked Questions

Troubleshooting

The following sections outline what to do if the following problems occur:

- [Cannot Connect With the Historian Interactive SQL Application \(on page 2638\)](#)
- [Cannot Log Into the Historian Interactive SQL Application \(on page 2639\)](#)
- [Cannot Get Historian OLE DB provider Data \(on page 2639\)](#)
- [Samples Do Not Run \(on page 2640\)](#)
- [Time Zones Do Not Work \(on page 2640\)](#)
- [Cannot Get String Data From the ihRawData Table \(on page 2640\)](#)
- [Timestamps Include Only the Previous Two Hours \(on page 2641\)](#)
- [Row Count Less Than Expected \(on page 2641\)](#)
- [Linked Server Not Working \(on page 2641\)](#)
- [SET Not Applied to SELECT When Using a Linked Server \(on page 2641\)](#)
- [Client Crashes When Using Historian OLE DB provider \(on page 2641\)](#)

The sections that follow the answers to this list describe frequently asked questions. These answers may help you when you are first configuring and using the Historian OLE DB provider.

Cannot Connect With the Historian Interactive SQL Application

When the OLE DB provider connects to the archiver, a connection message is generated and logged to the archiver messages list. If you are having problems connecting with the Historian Interactive SQL application (`ihSQL.exe`), you will either not see a connection message or see a connection error instead.

If you suspect that you are having problems connecting to the archiver, follow these steps:

1. Open Historian Administrator.

2. Select **Messages**.

The message fields appear in the main window.

3. In the **Priority** group box, select the **All** option.

4. In the **Topic** drop-down list, select **All Topics**.

5. Select **Search**.

A list of messages appears on the right side of the window.

6. Scroll through the list of connection messages and look for any missing connections or connection errors.

Connections denied due to security display the user name passed to the archiver. For example, the message would be similar to this:

```
Unknown(\kmcckenna) failed login at 03/01/2002 04:30:58.415 PM.
```

Cannot Log Into the Historian Interactive SQL Application

When you use `ihSQL.exe` for the first time, you may need to select **Run As Administrator**. If you do not do this the first time you use `ihSQL.exe`, you may not be able to log in. After this, you do not need to select **Run as Administrator**.

Cannot Get Historian OLE DB provider Data

If you cannot get data and you suspect there is a security problem with Historian, follow these steps to confirm that the Historian OLE DB provider is working:

1. Open the Historian Interactive SQL application and connect to the OLE DB provider.

2. Enter the following command:

```
SELECT * FROM ihQuerySettings
```

3. Select the **Execute Query** button.

4. Confirm that data appears in the bottom half of the window:

- If one row of data returns, then the provider is installed and working correctly, but you may have security problems between the provider and the server. You must use a valid Historian username and password.
- If no rows return, then there is a connection problem between the client and the OLE DB provider.

The `ihQuerySettings` data is internal to the OLE DB provider and does not use any Historian security. Browsing the tables and columns also is unaffected by Historian security and is another way to confirm the connection between the client and provider.

Samples Do Not Run

If you follow the recommended installation procedures, you should not have any difficulty in running the sample reports. If you do encounter any problems, they are likely to relate to the locations of files.

For example, if you are using Crystal Reports, check that you changed the server name. If the server name is incorrect, the data links will not update correctly. See [Changing the Server Name \(on page 2588\)](#) for directions on how to change it.

Time Zones Do Not Work

If you are using Windows 9x, times zones are not supported on this operating system. Returned data displays the client time zone.

If you are expecting a server or explicit bias time zone and a client time zone displays, check the defaults in the `ihQuerySettings` table. By default, the `TimeZone` column is set to `Client`. See [Supported SET Statement Syntax \(on page 2629\)](#) for more information on setting defaults using a `SET` statement, or see [WHERE Clauses](#) for information on specifying a time zone in the `SELECT` statement.

Cannot Get String Data From the ihRawData Table

The Historian OLE DB provider, by default, does not return string data types in the `ihRawData` table. This is because the default `SamplingMode` value is `Calculated`. You have to change the `SamplingMode` value to `Interpolated` using the `SET` statement or a `WHERE` clause.

For example, this query does not return interpolated data:

```
SELECT * FROM ihRawData
WHERE tagname = simulationstring00001
```

However, this query does:

```
SELECT * FROM ihRawData
WHERE tagname = simulationstring00001 AND
samplingmode = interpolated
```

And so does this query:

```
SET samplingmode=interpolated
SELECT * FROM ihRawData
WHERE tagname = simulationstring00001
```

Timestamps Include Only the Previous Two Hours

By default, the data returned only includes data from two hours prior to the execution of the query. If you want to change the time frame of the data query, you need to specify a start and end time in a `SET` statement, or use a `WHERE` clause to specify a date and time period.

Row Count Less Than Expected

By default, all queries return up to a maximum of 5,000 rows. If you want to change the maximum number of rows returned, you can specify another `RowCount` value in a `SET` statement, or use the `TOP` predicate in your `SELECT` statement.

If you specify `RowCount=0` in the `SET` statement, the `RowCount` limit is disabled. However, the `RowCount` is not actually unlimited. It can be constrained by other factors such as the time interval, or by using the `TOP` predicate in your `SELECT` statement.

Linked Server Not Working

Check that you selected the **Select the Level Zero Only** and **Allow in Process** options in the **Provider Options** window. You may have forgotten to set them when you were creating your linked server. These are the only two options that should be selected.

SET Not Applied to SELECT When Using a Linked Server

Make sure that the `SET` and `SELECT` statements are combined in the same query. If you open the connection and only perform the `SET`, as shown below, the `SET` parameters only get applied for the duration of the connection.

```
SELECT * FROM OPENQUERY(linkedserver, 'SET SamplingMode=interpolated')
```

The `SamplingMode` option in the previous example does not get applied to the next `OPENQUERY` that you perform with a `SELECT` statement. The `SET` statement only gets applied to the query if it is included with the `SELECT` statement. See [Use OPENQUERY to Access a Linked Server](#) for examples of how to include the `SET` statement with a `SELECT` statement.

Client Crashes When Using Historian OLE DB provider

Ensure that your client is initializing `COM` in `Apartment` threaded mode.

Frequently Asked Questions

The following sections outline some of the most frequently asked questions when using the Historian OLE DB provider. These questions include:

How Are Historian Calculation Modes and SQL Aggregate Functions Different?

You can extract calculated data from Historian by setting the `SamplingMode` column to `Calculated` and the `CalculationMode` column to the desired calculation mode type. You can use SQL aggregate functions to perform a calculation on a set of values, possibly calculated data, for the same tag or different tags and return a single value.

For instance, when comparing multiple tags you could retrieve the minimum (`MIN`) value of each tag. By setting calculation modes, Historian Administrator only calculates the minimum for each tag over a given time period. By using aggregate functions, the Historian OLE DB provider calculates the minimum value across all tags (all rows in a table), in other words, the minimum of all minimum tag values.

How Are the `ihTrend` and `ihRawData` Tables Different?

Typically, you use the `ihTrend` table when you want to compare multiple tags at the same time. The OLE DB provider needs to synchronize all the returned data by time, so it takes more time to query the `ihTrend` table than to query the `ihRawData` table. You can retrieve multiple tags from the `ihRawData` table, but the tags are not synchronized.

Can I Run Multiple Applications Using the OLE DB provider?

Yes. For instance, you can use the OLE DB provider to access data using Crystal Reports and VisiconX at the same time.

Can I Retrieve Data From Multiple Servers?

Yes. The OLE DB provider can have connections to multiple servers at the same time. Each is regarded as a separate session.

You cannot mix multiple servers in the same `SELECT` statement, except indirectly in a linked server in Microsoft SQL Server. Crystal Reports allows you to create subreports inside of a report. Each report gets its own data source (which would be a Historian server) and its own `SELECT` query. However, the reports cannot share data. You can have multiple VisiconX data controls in one picture, each going to a different server.

For instance, say you run iFIX and Crystal Reports at the same time. From the VisiconX page, establish a connection to the Historian OLE DB provider and perform a query on `Server1`. Next, run a report from Crystal Reports connecting to the same provider, but with

a connection to a different server, Server2. After you run the report and go back to the VisiconX page, you will notice that VisiconX is still connected to Server1. If you refresh the control, it uses the same settings and server as it did before. The provider maintains these two sessions separately, each with its own `SET` parameters.

So, in general, you can access multiple servers, but the data from each server remains independent. You must work with linked servers in Microsoft SQL Server to combine data from multiple servers.

What is a Session?

A session is defined as an OLE DB connection. You can run multiple server connections to the OLE DB provider. Each is regarded as a separate session.

You can have multiple sessions with multiple clients, such as Crystal Reports and iFIX. Multiple sessions between a client computer and a server computer count as one licensed session.

How Do the > and >= Operators Work With Timestamps?

The > and >= comparison operators, when used with `timestamp`, return the same values. For example, this SQL statement...

```
SELECT * FROM ihRawData WHERE tagname=simulation00001 AND
timestamp>='4/1/2001 01:50:00' AND
timestamp<='4/1/2001 04:00:00' AND
samplingmode=lab
```

...returns exactly the same first result as this statement:

```
SELECT * FROM ihRawData WHERE tagname=simulation00001 AND
timestamp > '4/1/2001 01:50:00' AND
timestamp <= '4/1/2001 04:00:00' AND samplingmode=lab
```

The first result is timestamped at 1:51:00.

How Do I Throttle Query Results?

The default maximum row count is 5,000. If you want to throttle the number of rows that you return in a single query, you can do one of the following:

- Use the `SET` statement to specify the `RowCount` to a specific number of rows.
- Use the `TOP` predicate to specify the top number or top percentage of rows that you want to return.
- Use the `MaxRecords` property on the `recordset` object in ADO.

When Should I Use Excel Instead of the Historian Excel Add-In?

Use the Excel Add-In when you want to get data into Microsoft Office 2003, 2007 or 2010 (32-bit or 64-bit). Use Excel with the Historian OLE DB provider when you want to perform advanced filtering, sorting, and joining of data. For other features that you might to perform with Excel and the Historian OLE DB provider, see [Microsoft Excel \(on page 2592\)](#).

Why Is the Raw Sample at the Start Time Not Returned?

Historian OLE DB provider does not return raw samples with timestamps that match the start time. If you want to include the start time, you need to set the start time to a time earlier than the first raw sample desired.



Note:

This only applies to `RawByTime` sampling mode and not `RawByNumber`.

For example, if you want to return raw samples starting at 11/28/2001 18:25:00 you can use 1/28/2001 18:24:59 as the start time. For example, you would enter the following SQL command:

```
SELECT TimeStamp, Tagname, Value FROM ihRawData
WHERE (SamplingMode = 'RawByTime') AND
(TimeStamp >= {ts '11/28/2001 18:24:59'})
ORDER BY TimeStamp ASC
```

If your timestamps are using millisecond resolution, you can retrieve timestamps starting at 11/28/2001 18:24:59.999 to prevent any sample prior to 18:50:00 from being returned.

What Username and Password Is Used if Not Specified in the Connect String?

If you leave a username and password empty in the connect string, then the user that owns the process, usually the currently logged-in user, is passed to the archiver for validation. For example, this statement leaves the username and password empty:

```
ConnectionString="Provider=ihOLEDB.iHistorian.1;User Id;;Password="
```

This statement also leaves the username and password empty:

```
ConnectionString="Provider=ihOLEDB.iHistorian.1"
```

If you saved username and password information in Historian Administrator or the iFIX Workspace for connecting to that server, that information is not used by the OLE DB provider.

What Is an Array Tag?

Historian allows you to store a set of values with a single timestamp and single quality and then read the elements back individually or as an array.

On retrieval, if you specify only the tag name, then all elements are returned. If you want to retrieve only an element, you can specify `<TagName>[n]` where *n* is the element number you want to retrieve.

In an array tag:

- The size of the array tag does not need to be configured. The Data Archiver will store the number of elements that were written.
- The maximum number of elements that an array tag can store is 10000. If this limit is exceeded, Historian does not accept any further elements.
- All calculation modes except `TagStats` are supported by array tags. The calculation mode is applied on array elements and not on the array. For example, if you do a minimum on a three-element array, this works like three individual tags. The minimum of element [0] over time is computed and returned as the minimum of element [0]. The Data Archiver does not compute the minimum of element [0], [1], [2] at a single point in time and return that as the minimum of the array.
- When a normal tag is converted to an array tag, on data retrieval, the data of the normal tag cannot be retrieved.

You can query both an array tag and an element of the tag. Each element of the array tag will be displayed in a separate row and they all will have the same timestamp.

What Is a User-Defined Type?

Historian gives you the ability to create a new user-defined data type which includes multiple fields of any data type and then create Historian tags of that type. All the regular tag operations can be performed on this tag. You can perform raw and calculated queries on the collected data.

What Is Not Supported?

A frequently asked question that may also relate to troubleshooting is what functions are not supported by Historian OLE DB provider. Some of these unsupported items include:

- Concatenation in SQL statements. For example, this syntax does not work:

```
SELECT * FROM ihtags WHERE tagname= "MY_SERVER." + ihtags.Tagname
```

- Calculation in SQL statements. For example, this syntax does not work:

```
SELECT * FROM ihtags WHERE ihrawdata.value * 2 > ihtags.LoEngineeringUnits
```

- SQL inserts, updates, deletes, or commits.
- Ordering by columns not specified in the `SELECT` statement.
- The semicolon (;) as a separator between `SET` and `SELECT` statements (which is commonly used in DTS and Oracle). Only a space or line break is necessary.
- Nested `SELECT` statements.
- The `UCASE` macro or other similar SQL syntax.
- `ASYNC` executes in ADO and Visual Basic.
- Bookmarks in ADO and Visual Basic.
- Table creation in SQL.
- The `UNION` statement in SQL.
- The `HAVING` clause in a `SELECT` statement.
- Using comments in a query.
- The `DISTINCT` clause in aggregate functions. For example, this syntax does not work:

```
SELECT Topic, count(DISTINCT *), sum(DISTINCT messagenumber), avg(DISTINCT messagenumber) FROM
ihmessages GROUP BY topic ORDER BY Topic
```

- A literal on the left side of a comparison operator. SQL-92 standards support this feature, but GE Intelligent Platforms does not currently support it. For example, this syntax does not work:

```
SELECT DISTINCT tagname FROM ihRawData WHERE 50>Value
```

- Analysis of the `ihTrend` table in Crystal Reports or the Microsoft SQL Server DTS application.
- Command or connect timeouts (`Connection.ConnectTimeout`, `Connection.CommandTimeout`, or `Command.CommandTimeout`) in Visual Basic. For example, this syntax does not work:

```
SET adoConn = New ADODB.Connection
adoConn.ConnectionString = "Provider=ihOLEDB.iHistorian.1;User Id=;Password="
adoConn.ConnectionTimeout = 5 ' does nothing
adoConn.CommandTimeout = 5 ' does nothing
```

```

SET cmdTestTimer = New ADODB.Command

SET cmdTestTimer.ActiveConnection = adoConn

cmdTestTimer.CommandText = "SELECT * FROM ihtags"

cmdTestTimer.CommandType = adCmdText

cmdTestTimer.CommandTimeout = 15 ' does nothing

```

Historian Database Tables

The Historian Database Tables

The Historian database tables contain read-only data from the Historian archive.

Table Name	Description
ihTags Table (on page 2651)	Contains Historian tag configuration information.
ihArchives Table (on page 2659)	Contains Historian archive configuration information, plus performance statistics for each archive.
ihCollectors Table (on page 2661)	Contains configuration and status information for each collector connected to the Historian server.
ihMessages Table (on page 2667)	Contains Historian messages such as alerts, informational topics, and connection information contained in the audit log.
ihRawData Table (on page 2670)	Contains collected data for each tag in the Historian server. It contains not just raw data, but also calculated and interpolated data.

Table Name	Description
ihComments Table (on page 2682)	Contains the comments associated with the Historian data.
ihTrend Table (on page 2693)	Another way to look at collected data. Contains a row of data for each unique timestamp. You can use this table to look at your data at a summarized level. You would typically use this table to compare multiple tags with the same timestamp.
ihQuery-Settings Table (on page 2709)	Contains a set of parameters that apply to all queries you make in that session, unless overridden by a <code>WHERE</code> clause.
ihCalculation-Dependencies (on page 2715)	Contains the calculation dependencies for tags.
ihAlarms Table (on page 2716)	Contains collected alarms and events data.
ihEnumeratedSets Table (on page 2720)	Contains information about enumerated sets.
ihEnumerated-	Contains information about enumerated states.

Table Name	Description
States Table (on page 2721)	
ihUser-Defined-Types Table (on page 2722)	Contains information about user-defined data types.
ihFields Table (on page 2723)	Contains information about fields used in user-defined types.

The following conditions apply when using these tables:

- You cannot write/update data in these tables.
- Null values are not supported in any column. A blank space is returned when there is no value provided by the Historian server (instead of a `Null` field).
- Almost all columns in these tables support comparison operators except for the following:
 - `SamplingMode`
 - `Direction`
 - `NumberOfSamples`
 - `IntervalMilliseconds`
 - `CalculationMode`
 - `FilterTag`
 - `FilterMode`
 - `FilterComparisonMode`
 - `FilterValue`
 - `FilterExpression`
 - `TimeZone`
 - `DaylightSavingTime`
 - `RowCount`

These columns only support the `=` comparison operator.

Historian Security Groups and the Database Tables

A user with membership in the iH Readers security group can access any table in the Historian OLE DB provider, even the `ihArchives` and `ihCollectors` tables. Members of the iH Readers group have read-only access to these tables.

Since the Historian OLE DB provider only supports read-only access to data and does not allow `INSERT` or `UPDATE` operations, no users can make changes to the data in these tables. This includes members of the iH Readers security group and even security administrators in the iH Security Admins security group.

For more information on Historian group rights, refer to Chapter 5 in the *Getting Started with Historian* manual.

Input Data and Historian Archive Data in Table Columns

There are two types of column data in the Historian OLE DB provider tables: input data and Historian archive data. Input data contains settings stored in the Historian OLE DB provider and has nothing to do with the data stored in the Historian archives. Historian archive data is the data retrieved from the Historian server.

While most columns contain Historian archive data, there are a few columns that contain input data. The following columns, no matter what table they appear in, contain input data and do not originate from the Historian archives:

- `SamplingMode`
- `Direction`
- `NumberOfSamples`
- `IntervalMilliseconds`
- `CalculationMode`
- `FilterTag`
- `FilterMode`
- `FilterComparisonMode`
- `FilterValue`
- `FilterExpression`
- `TimeZone`
- `DaylightSavingsTime`
- `RowCount`

The columns in the previous list are used in a `WHERE` clause to specify query parameters for retrieved data.

About the Table Descriptions

The following sections describe each table, list each column in the table, and list the data type and description for each column. The following table outlines the data types that are used throughout this chapter.

Table 393. Column Data Types

Data Type	Format of Data
VT_BOOL	Boolean
VT_BSTR	String
VT_DBTimeStamp	Date and Time
VT_I4	Integer
VT_R4	Float
VT_R8	Double Float
VT_UI1	Short Integer
VT_VARIANT	Numeric or String

Also included after each table description are examples of SQL statements used with the specified database table. These examples are only provided to get you started with creating SQL statements with the Historian OLE DB provider. For more detailed information on creating SQL queries, refer to your reporting software documentation.

ihTags Table

The `ihTags` table contains the set of tag names and the properties of each tag. Each row in the table represents one tag.

Column Name	Data Type	Description
Tagname	VT_- BSTR	Tagname property of the tag.

Column Name	Data Type	Description
		 Note: There is no length limit for Historian tag names in the Data Archiver. However, different client applications may have their own limits.
Description	VT_- BSTR	User description of the tag.
EngUnits	VT_- BSTR	Engineering units description of the tag.
Comment	VT_- BSTR	User comment associated with the selected tag.
DataType	VT_- BSTR	The data type of the tag: <ul style="list-style-type: none"> • Scaled • SingleFloat • DoubleFloat • SingleInteger • DoubleInteger • Quad Integer • Unsigned Single Integer • Unsigned Double Integer • Unsigned Quad Integer • Byte • Boolean • FixedString • VariableString • BLOB The data type returned in this column is the data type that you defined in Historian Administrator application.
FixedStringLength	VT_UI1	Zero unless the data type is <code>FixedString</code> . If the data type is <code>FixedString</code> , this number represents the maximum length of the string value.
CollectorName	VT_- BSTR	Name of the collector responsible for collecting data for the specified tag.

Column Name	Data Type	Description
SourceAddress	VT_- BSTR	Address used to identify the tag at the data source. For iFIX systems, this is the NTF (<code>Node.Tag.Field</code>).
CollectionType	VT_- BSTR	Type of collection used to acquire data for the tag: <ul style="list-style-type: none"> • Unsolicited: The collector accepts data from the source whenever the source presents the data. • Polled: The collector acquires data from a source on a periodic schedule determined by the collector. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: Not all collectors support unsolicited collection. </div>
CollectionInterval	VT_I4	The time interval, in milliseconds, between readings of data from this tag. For polled collection, this field represents the time between samples. For unsolicited collection, this field represents the minimum time allowed between samples.
CollectionOffset	VT_I4	The time shift from midnight, in milliseconds, for collection of data from this tag.
LoadBalancing	VT_- BOOL	Indicates whether the data collector should automatically shift the phase of sampling to distribute the activity of the processor evenly over the polling cycle. This is sometimes called phase shifting.
TimeStampType	VT_- BSTR	The timestamp type applied to data samples at collection time: <ul style="list-style-type: none"> • Source: The source delivers the timestamp along with the data sample. • Collector: The collector delivers the timestamp along with the collected data.
HiEngineeringUnits	VT_R8	The high end of the engineering units range. Used only for scaled data types and input scaled tags.
LoEngineeringUnits	VT_R8	The low end of the engineering units range. Used only for scaled data types and input scaled tags.

Column Name	Data Type	Description
InputScaling	VT_- BOOL	<p>Indicates whether the measurement should be converted to an engineering units value. When set to <code>False</code>, the measurement is interpreted as a raw measurement.</p> <p>When set to <code>True</code>, the system converts the value to engineering units by scaling the value between the <code>HiScale</code> and <code>LoScale</code> columns. If not enabled, the system assumes the measurement is already converted into engineering units.</p>
HiScale	VT_R8	The high-end value of the input scaling range used for the tag.
LoScale	VT_R8	The low-end value of the input scaling range used for the tag.
CollectorCompression	VT_- BOOL	<p>Indicates whether collector compression is enabled for the tag.</p> <p>Collector compression applies a smoothing filter to incoming data by ignoring incremental changes in values that fall within a deadband centered around the last collected value. The collector passes (to the archiver) any new value that falls outside the deadband and then centers the deadband around the new value.</p>
CollectorDeadbandPercentRange	VT_R4	The current value of the compression deadband.
ArchiveCompression	VT_- BOOL	Indicates whether archive collector compression is enabled for the tag.
ArchiveDeadbandPercentRange	VT_R4	The current value of the archive compression deadband.
CollectorGeneral1	VT_- BSTR	The general (or spare) configuration fields for the tag.
CollectorGeneral2	VT_- BSTR	The general (or spare) configuration fields for the tag.
CollectorGeneral3	VT_- BSTR	The general (or spare) configuration fields for the tag.
CollectorGeneral4	VT_- BSTR	The general (or spare) configuration fields for the tag.

Column Name	Data Type	Description
CollectorGeneral5	VT_- BSTR	The general (or spare) configuration fields for the tag.
ReadSecurityGroup	VT_- BSTR	<p>The name of the Windows security group that controls the reading of data for the tag.</p> <p>Refer to "Implementing Historian Security" in the <i>Getting Started with Historian</i> manual for definitions of the various security levels and groups.</p>
WriteSecurity- Group	VT_- BSTR	<p>The name of the Windows security group that controls the writing of data for the tag.</p> <p>Refer to "Implementing Historian Security" in the <i>Getting Started with Historian</i> manual for definitions of the various security levels and groups.</p>
AdministratorSe- curityGroup	VT_- BSTR	The name of the Windows security group responsible for controlling configuration changes for the tag.
Calculation	VT_- BSTR	The equation for the calculation performed for the tag.
LastModified	VT_DB- TimeS- tamp	The date and time that the tag configuration was last modified. The time structure includes milliseconds.
LastModifiedUser	VT_- BSTR	The username of the Windows user who last modified the tag configuration.
CollectorType	VT_- BSTR	<p>The type of collector responsible for collecting data for the tag:</p> <ul style="list-style-type: none"> • Undefined • iFIX • Simulation • OPC • File • iFIXLabData • ManualEntry • Simulation • Other

Column Name	Data Type	Description
StoreMilliseconds	VT_BOOL	<p>Indicates whether milliseconds are recorded in timestamps.</p> <p>If not enabled, the time resolution is in seconds instead of milliseconds. Maximum data compression is achieved when this option is set to <code>False</code>. This is the optimum setting for most applications.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: StoreMilliseconds returns <code>False</code> in Historian v4.5 and later.</p> </div>
TimeResolution	String	Indicates the timestamp resolution in seconds, milliseconds, or microseconds.
UTCBias	VT_I4	<p>The time zone bias for the tag. Time zone bias is used to indicate the natural time zone of the tag expressed as an offset from UTC (Universal Time Coordinated) in minutes.</p> <p>UTC is the international time standard, the current term for what was commonly referred to as Greenwich Mean Time (GMT).</p>
AverageCollectionTime	VT_I4	The average time it takes to execute the calculation tag since you started the Calculation collector.
CollectionDisabled	VT_I4	Indicates whether collection is enabled (0) or disabled (1) for the tag. The default setting is enabled (0).
CollectorCompressionTimeout	VT_I4	<p>Indicates the maximum amount of time the collector will wait between sending samples to the archiver. This time is kept per tag, as different tags report to the archiver at different times.</p> <p>This value should be in increments of your collection interval, and not less.</p> <p>Ideally, this field is used for polled data values. It can be used with unsolicited data, but when you do so, you are dependent on the data source for the value to change. With unsolicited data, since Historian only records the value when it changes, the actual time before the timeout might exceed the compression timeout.</p>

Column Name	Data Type	Description
ArchiveCompressionTimeout	VT_I4	Indicates the maximum amount of time from the last stored point before another point is stored, if the value does not exceed the archive compression deadband. The data archiver treats the incoming sample after the timeout occurs as if it exceeded compression. It then stores the pending sample.
TimeZone	VT_- BSTR	The type of time zone used: <ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT)
DaylightSavingTime	VT_- BOOL	Indicates whether Daylight Saving Time logic should be applied to timestamps.
RowCount	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates there is no limit to the number of rows returned.
InterfaceAbsoluteDeadbanding	VT_- BOOL	Indicates whether absolute collector deadband is enabled for this tag.
InterfaceAbsoluteDeadband	VT_R8	Indicates the value for absolute collector deadband.
ArchiveAbsoluteDeadbanding	VT_- BOOL	Indicates whether absolute archive deadband is enabled for this tag.
ArchiveAbsoluteDeadband	VT_R8	Indicates the value for absolute archive deadband.
SpikeLogic	VT_- BOOL	Indicates whether Spike Logic is enabled for the tag.
SpikeLogicOverride	VT_- BOOL	Indicates whether the Spike Logic setting for this tag overrides the collector.
StepValue	VT_- BOOL	Indicates whether the <code>StepValue</code> property is enabled for the tag.
EnumeratedSetName	VT_- BSTR	Indicates the enumerated set name associated with a tag. You can get more information about the set via the <code>ihEnumeratedSet</code> table.

Column Name	Data Type	Description
DataStoreName	VT_- BSTR	Indicates the name of the data store the tag belongs to.
NumberOfElements	VT_I4	Indicates whether the tag is an array tag. If set to -1, the tag is an array tag. If set to 0, the tag is not an array tag. Since the size of the array is dynamic, there is no single number of elements that can be returned.
CalcType	Enum	Indicates whether the tag is an analytical tag or a normal tag.
IsAlias	VT_- BOOL	Indicates whether the tag has an alias or not.

ihTags Examples

Tasks that you might want to perform on the `ihTags` table are outlined in the following examples.

Example 1: Find All Tags That Belong to a Specific Collector

```
SELECT * FROM ihtags WHERE collectorname=MYCOMPUTER_Simulation ORDER BY tagname
```

Example 2: Find All Tags With a Specific Poll Rate, a Range of Poll Rates, or Polling Disabled

```
SELECT * FROM ihtags WHERE CollectionInterval=500  
OR (CollectionInterval>=1000 AND CollectionInterval<=1200)  
OR CollectionInterval=0
```

Example 3: Retrieve All Tags Collected by Each Collector

```
SELECT collectorname, tagname FROM ihtags ORDER BY collectorname
```

Example 4: Retrieve All Tags With a Specific Poll Rate

```
SELECT tagname FROM ihtags WHERE collectioninterval=1000
```

Example 5: Retrieve All Tags With Subsecond Collection

```
SELECT tagname FROM ihtags  
WHERE collectioninterval BETWEEN 1 AND 999
```

Example 6: Retrieve All Tags with Polling Disabled

```
SELECT tagname, collectioninterval FROM ihtags
WHERE collectioninterval=0
```

Example 7: Count the Number of Tags and Group by Collector Name

```
SELECT collectorname, COUNT(*) FROM ihTags GROUP BY collectorname
```

Example 8: Count the Number of Tags and Group by Collector Type

```
SELECT ihCollectors.collectortype, COUNT(*)
FROM ihTags INNER JOIN ihCollectors
WHERE ihTags.collectorname=ihCollectors.collectorname
GROUP BY ihcollectors.collectortype
```

Example 9: Retrieve Tags Associated With a Specific Enumerated Set

```
SELECT * FROM ihtags
WHERE EnumeratedSetName='ExampleSet'
```

ihArchives Table

Historian archives are stored as data files, each of which contains data gathered during a specific period of time.

The `ihArchives` table contains Historian archive configuration information and performance statistics for each archive. Each row in this table represents one archive. The following table describes the columns of the `ihArchives` table.

Table 394. ihArchives Table

Column Name	Data Type	Description
Archive-Name	VT_BSTR	Name of the archive for the current server if the authenticated user is a member of Historian Administrators group.
ArchiveStatus	VT_BSTR	The status of the specified archive: <ul style="list-style-type: none"> • Undefined • Empty • NotEmpty

Table 394. ihArchives Table (continued)

Column Name	Data Type	Description
FileName	VT_BSTR	The file name for the specified archive. The file name must be specified in the context of the Historian server drives and directories.
IsCurrent	VT_BOOL	Indicates whether the specified archive is the newest archive that new data currently flows into.
IsReadOnly	VT_BOOL	Indicates whether the read-only status is set for the specified archive.
FileSize-Current-Disk	VT_I4	The actual space on the hard disk (in MB) for the specified archive.
FileSize-Current	VT_I4	The size of the archive file that is currently being used (in MB) for the specified archive.
FileSize-Target	VT_I4	The target size of the specified archive file (in MB).
StartTime	VT_DB-TimeStamp	The start time of the specified archive. This represents the earliest timestamp (including date and time) for any tag contained in the archive.
EndTime	VT_DB-TimeStamp	The end time of the specified archive. This represents the latest timestamp (including date and time) for any tag contained in the archive.
LastBackup	VT_DB-TimeStamp	The date and time the most recent online backup was performed on this archive.
LastBackupUser	VT_BSTR	The name of the user who performed the most recent online backup.
LastModified	VT_DB-TimeStamp	The date and time that the archive was last modified. The time structure includes milliseconds.
LastModifiedUser	VT_BSTR	The username of the Windows user who last modified the archive.
TimeZone	VT_BSTR	The type of time zone used:

Table 394. ihArchives Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT).
Daylight-SavingTime	VT_BOOL	Indicates whether Daylight Saving Time logic should be applied to timestamps.
RowCount	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates there is no limit to the number of rows returned.
DataStore-Name	VT_BSTR	Indicates the name of the data store the tag belongs to.

ihArchives Examples

A task that you might want to perform on the `ihArchives` table is retrieving and recording the state of the archives and archive sizes when an event happens. Recording conditions when an event happens is useful in troubleshooting.

Sample SQL statements for the `ihArchives` table are outlined in the following examples.

Example 1: Retrieve the Archive List Sorted by StartTime

```
SELECT archivename, starttime, endtime
FROM iharchives ORDER BY starttime
```

Example 2: Retrieve All Properties of the Current Archive

```
SELECT * FROM iharchives WHERE iscurrent=true
```

ihCollectors Table

The `ihCollectors` table contains the configuration and status information for each collector connected to the Historian server. Each row in this table represents a collector that is connected to the archiver. The following table describes the columns of the `ihCollectors` table.

Table 395. ihCollectors Table

Column Name	Data Type	Description
CollectorName	VT_- BSTR	The name of the collector. The collector name is unique in a specific Historian server.
CollectorDescription	VT_- BSTR	The user description for the collector.
Comment	VT_- BSTR	The user comment associated with the collector.
ComputerName	VT_- BSTR	The name of the Windows computer on which the collector is running.
Status	VT_- BSTR	The status of the specified collector: <ul style="list-style-type: none"> • Unknown • Starting • Running • Stopping • Stopped
CollectorType	VT_- BSTR	The type of collector responsible for collecting data for the tag: <ul style="list-style-type: none"> • Undefined • iFIX • Simulation • OPC • OPC AE • File • iFIXLabData • ManualEntry • Simulation • Calculation • ServerToServer • Other

Table 395. ihCollectors Table (continued)

Column Name	Data Type	Description
MaximumDiskFree- BufferSize	VT_ I4	The maximum size (in MB) of the disk buffer for outgoing data.
MaximumMemory- BufferSize	VT_ I4	The maximum size of the memory buffer (in MB) for outgoing data. The memory buffer stores data during short-term or momentary interruptions of the server connection. The disk buffer handles long-duration outages.
ShouldAdjustTime	VT_ BOOL	If the data source supplies the timestamps, this value is <code>False</code> . If the collector supplies the timestamps, this value is <code>True</code> . <div data-bbox="506 821 1422 1087" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: This column does not change collector times to match the server time. It indicates whether an increment of time is added or subtracted to compensate for the relative difference between the server and collector clocks, independent of time zone differences.</p> </div>
ShouldQueueWrites	VT_ BOOL	Indicates whether queue writes are allowed.
CanBrowseSource	VT_ BOOL	If <code>True</code> , this column indicates that the collector can browse its source for tags.
CanSourceTime- stamp	VT_ BOOL	Indicates whether the data source can provide timestamps along with the data.
StatusOutputAd- dress	VT_ BSTR	An address or tagname in the data source to output current collector status.
RateOutputAddress	VT_ BSTR	An address or tagname in the data source into which the collector writes the current value of the events per minute output.
HeartbeatOutput- Address	VT_ BSTR	The address in the source database into which the collector writes the heart-beat signal output.
CollectorGeneral1	VT_ BSTR	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral1</code> column is not user-defined, and is different for each collector.

Table 395. ihCollectors Table (continued)

Column Name	Data Type	Description
CollectorGeneral2	VT_- BSTR	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral2</code> column is not user-defined, and is different for each collector.
CollectorGeneral3	VT_- BSTR	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral3</code> column is not user-defined, and is different for each collector.
CollectorGeneral4	VT_- BSTR	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral4</code> column is not user-defined, and is different for each collector.
CollectorGeneral5	VT_- BSTR	The general (or spare) configuration fields for the collector. The <code>CollectorGeneral5</code> column is not user-defined, and is different for each collector.
LastModified	VT_- DB- Time- S- tamp	The date and time that the collector configuration was last modified. The time structure includes milliseconds.
LastModifiedUser	VT_- BSTR	The username of the Windows user who last modified the collector configuration.
SourceTimeInLocalTime	VT_- BOOL	For data source timestamps only. Indicates whether the timestamps use local time. If the value is <code>False</code> , UTC time is used.
CollectionDelay	VT_- I4	The length of time, in seconds, that the collector should delay collection at startup (to allow the data source time to initialize).
DefaultTagPrefix	VT_- BSTR	The prefix that is automatically applied to all tagnames added by the specified collector.
DefaultCollectionInterval	VT_- I4	The collection interval, in milliseconds, for tags added by the collector.
DefaultCollectionType	VT_- BSTR	Type of collection used to acquire data for tags added by the collector: <ul style="list-style-type: none"> • Unsolicited: The collector accepts data from the source whenever the source presents the data. • Polled: The collector acquires data from a source on a periodic schedule determined by the collector.

Table 395. ihCollectors Table (continued)

Column Name	Data Type	Description
		 Note: Not all collectors support unsolicited type collection.
DefaultTimeStamp- Type	VT_- BSTR	<p>Type of timestamp applied to data samples at collection time for tags added by the collector:</p> <ul style="list-style-type: none"> • Source: The source delivers the timestamp along with the data sample. • Collector: The collector delivers the timestamp along with the collected data.
DefaultCollector- Compression	VT_- BOOL	Indicates whether default collector compression is enabled for tags added by the collector.
DefaultCollector- CompressionDead- band	VT_- R4	The default collector compression deadband for tags added by the collector.
DefaultCollector- CompressionTime- out	VT_- I4	The default collector compression timeout value.
DisableOnTheFly- Changes	VT_- BOOL	<p>Indicates whether a user can make on-the-fly changes to this tag. When enabled (<code>True</code>) you can make changes to this tag without having to restart the collector.</p> <p>When disabled (<code>False</code>), any changes you make to this tag do not affect collection until you restart the collector.</p>
DefaultSpikeLogic	VT_- BOOL	Indicates whether Spike Logic is enabled.
DefaultSpikeMul- tiplier	VT_- R4	The default Spike Logic multiplier.
DefaultSpikeIn- terval	VT_- I4	The default Spike Logic interval.

Table 395. ihCollectors Table (continued)

Column Name	Data Type	Description
RedundancyEnabled	VT_- BOOL	Indicates whether collector redundancy is enabled.
PrincipalCollector	VT_- BSTR	Indicates the primary collector.
IsActiveRedundantCollector	VT_- BOOL	Indicates whether the current collector is active.
FailoverOnCollectorStatus	VT_- BOOL	Indicates whether the collector is set to fail over on an unknown collector status.
FailoverOnBadQuality	VT_- BOOL	Indicates whether the collector is set to fail over on bad data quality received from the watchdog tag.
FailoverOnValue	VT_- BOOL	Indicates whether the collector is set to fail over on a change in value.
FailoverValueChangeType	VT_- I4	The value for the <code>FailoverOnValue</code> option.
WatchdogValueMaxUnchangedPeriod	VT_- I4	The maximum period for an unchanged value.
WatchdogTagName	VT_- BSTR	The watchdog tag name.
TimeZone	VT_- BSTR	The type of time zone used: <ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT)
DaylightSavingTime	VT_- BOOL	Indicates whether Daylight Saving Time logic should be applied to timestamps.
RowCount	VT_- I4	The maximum number of rows that can be returned. A value of 0 indicates there is no limit to the number of rows returned.

ihCollectors Examples

One task that you might want to perform on the `ihCollectors` table could be retrieving and recording the state of the collectors when an event happens. Recording conditions when an event happens is useful in troubleshooting.

Sample SQL statements for the `ihCollectors` table are outlined in the following examples.

Example 1: Retrieve All Collectors With Status Information

```
SELECT collectorname, collectordescription AS desc, status
FROM ihcollectors
```

Example 2: Retrieve All Collectors Not Running

```
SELECT collectorname, collectordescription AS desc, status
FROM ihcollectors WHERE status!=running
```

ihMessages Table

The `ihMessages` table contains Historian messages such as alerts, informational topics, and connection information contained in the audit log. Each row in this table represents a message. The following table describes the columns of the `ihMessages` table.

Table 396. ihMessages Table

Column Name	Data Type	Description
TimeS- tamp	VT_- DB- Time- Stamp	The date and time that the message was created.
TimeS- tampSe- conds	VT_- DB- Time- Stamp	The date and time that the message was created.
Mi- crosec- onds	VT_I4	The microsecond portion of the date and time for the message.

Table 396. ihMessages Table (continued)

Column Name	Data Type	Description
Topic	VT_- BSTR	The topic name of the message: <ul style="list-style-type: none"> • AlertTopics • AllTopics • ConfigurationAudit • Connections • General • MessageTopicMax • MessageTopics • Performance • ServiceControl • Security • Undefined
User- name	VT_- BSTR	Name of the Windows user who generated the message, or who the message is associated with.
Mes- sage- Number	VT_I4	Message number for the message. A message number is a unique identifier associated with the message template.
Mes- sage- String	VT_- BSTR	Translated text of the message, including any substitutions. Messages generally include translated fixed text and variable substitutions such as timestamps, usernames, and tagnames.
Time- Zone	VT_- BSTR	The type of time zone used: <ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT)
Day- light- Saving- Time	VT_- BOOL	Indicates whether Daylight Saving Time logic should be applied to timestamps.

Table 396. ihMessages Table (continued)

Column Name	Data Type	Description
Row Count	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates there is no limit to the number of rows returned.

ihMessages Examples

One task that you might want to perform on the `ihMessages` table is retrieving a history of alerts and messages, with timestamps and user information. For instance, you might want to query the alerts for a day, or all messages associated with a particular username.

Sample SQL statements for the `ihMessages` table are outlined in the following examples.

Example 1: Retrieve All Messages and Alerts for Today

```
SELECT * FROM ihmessages WHERE timestamp>=today
```

Example 2: Retrieve All Alert Messages for a Specific User and Time

```
SELECT * FROM ihmessages
WHERE timestamp>'12-sep-2001 02:00:00'
AND topic=AlertTopics
AND username='DataArchiver' ORDER BY timestamp
```

Example 3: Retrieve All Messages in Your Archive

```
SELECT * FROM ihMessages WHERE timestamp <= Now
```

Example 4: Retrieve All Messages for a Specific User

```
SELECT * FROM ihMessages WHERE username=operator1
AND timestamp<=Now
```

Example 5: Count All Messages by a Specific User

```
SELECT username, COUNT(*) FROM ihMessages
WHERE timestamp <=Now GROUP BY username
```

ihRawData Table

The `ihRawData` table contains any collected data for each tag contained in the Historian server. It contains not just raw data, but also calculated data and interpolated data. This table is the one typically used for reporting.

There is one row in the `ihRawData` table for each combination of tagname and timestamp. For instance, you can have two rows for the same tag, each with different timestamps. You can retrieve data for more than one tag name in a simple query.

The following table describes the columns of the `ihRawData` table.

Table 397. ihRawData Table

Column Name	Data Type	Description
TagName	VT_BSTR	Tagname property of the tag. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: There is no length limit for Historian tag names in the Data Archiver. However, different client applications may have their own limits. </div>
Timestamp	VT_DBTimeStamp	The date and time for the data sample.
TimestampSecs	VT_DBTimeStamp	The date and time for the data sample.
Microseconds	VT_DBTimeStamp	The microsecond interval for the data sample.
Value	VT_VARIANT	The value of the data.
Quality	VT_VARIANT	For non-raw sampled data, this column displays the percentage of good quality samples in the interval. For instance, a value of 100 means all samples in the interval are good.

Table 397. ihRawData Table (continued)

Column Name	Data Type	Description
		<p>For raw sampled data, data values are:</p> <ul style="list-style-type: none"> • Good • Bad • Uncertain • Not Available • Really Unknown <p>This column also includes the subquality of the data value, if it exists:</p> <ul style="list-style-type: none"> • NonSpecific • ConfigError • NotConnected • DeviceFail • SensorFail • LastKnownValue • CommFailure • OutOfService • ScaledOutOfRange • OffLine • NoValue • Really Unknown
OPC-Quality-Valid	VT_BSTR	Indicates whether the OPCQuality column contains valid real OPC quality. A value of 0 indicates that you should ignore the OPCQuality field, and a value of 1 indicates that the OPCQuality column contains valid real OPC quality.
OPC-Quality	VT_I4	Indicates the OPC quality as delivered by the OPC server to the Historian OPC collector. The exact meaning of the bits depends on the OPC specification and the OPC server documentation. Typically, a value of 0 represents bad quality, and a value of 192 represents good quality.

Table 397. ihRawData Table (continued)

Column Name	Data Type	Description
Sampling-Mode	VT_BSTR	<p>The mode used to sample data from the archive:</p> <ul style="list-style-type: none"> • CurrentValue: Retrieves the current value. Time frame criteria are ignored. • Interpolated: Retrieves evenly spaced interpolated values based on <code>interval</code> or <code>NumberOfSamples</code> and the time frame criteria. • RawByTime: Retrieves raw archive values based on time frame criteria. • RawByNumber: Retrieves raw archive values based on the <code>StartTime</code>, <code>NumberOfSamples</code>, and <code>Direction</code> criteria. <div style="border: 1px solid #00a0c0; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Note: <code>EndTime</code> criteria are ignored for this sampling mode.</p> </div> <ul style="list-style-type: none"> • RawByFilterToggle: Returns filtered time ranges. The values returned are <code>0</code> and <code>1</code>. If the value is <code>1</code>, then the condition is true and <code>0</code> means false. This sampling mode is used with the time range and filter tag conditions. The result starts with a starting timestamp and ends with an ending timestamp. • Calculated: Retrieves evenly spaced calculated values based on <code>NumberOfSamples</code>, <code>interval</code>, the time frame criteria, and the <code>CalculationMode</code> criteria. • Lab: Returns actual collected values without interpolation. • Trend: Returns raw minimum and raw maximum values for each specified interval. Use this sampling mode to maximize performance when retrieving data points for plotting. If the sampling period does not evenly divide by the interval length, Historian ignores any leftover values at the end, rather than putting them into a smaller interval. • Trend2: Returns raw minimum and raw maximum values for each specified interval. Use this sampling mode to maximize performance when retrieving data points for plotting. Also, if the sampling period does not evenly divide by the interval length, Historian creates as many intervals of the interval length as will fit into the sampling period, and then creates a remainder interval from whatever time is left. This sampling mode is more suitable than the <code>Trend</code> mode for analysis of minimums and maximums and for plotting programs that can handle unevenly spaced data.

Table 397. ihRawData Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • <code>InterpolatedtoRaw</code>: Provides raw data in place of interpolated data when the number of samples is less than the available samples. • <code>TrendtoRaw</code>: This sampling mode almost always produces the same results as the <code>Trend</code> mode. The exception is that when the number of samples requested is greater than the number of raw data points, this mode returns all available raw data points with no further processing. <code>TrendtoRaw</code> is therefore used instead of <code>Trend</code> when the number of actual data samples is less than the requested number of samples. • <code>TrendtoRaw2</code>: This sampling mode almost always produces the same results as the <code>Trend2</code> mode. The exception is that when the number of samples requested is greater than the number of raw data points, this mode returns all available raw data points with no further processing. <code>TrendtoRaw2</code> is therefore used instead of <code>Trend2</code> when the number of actual data samples is less than the requested number of samples. • <code>LabtoRaw</code>: Provides raw data for the selected calculated data when the number of samples is less than the available samples.
Direction	VT_BSTR	The direction (forward or backward from the start time) of data sampling from the archive.
Number of Samples	VT_I4	<p>Number of samples from the archive to retrieve.</p> <p>Samples will be evenly spaced within the time range defined by the start and end times for most sampling modes. For the <code>RawByNumber</code> mode, this column determines the maximum number of values to retrieve. For the <code>RawByTime</code> mode, this value is ignored.</p> <div data-bbox="407 1493 1419 1667" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: The <code>NumberOfSamples</code> and <code>IntervalMilliseconds</code> columns are mutually exclusive. If <code>NumberOfSamples</code> is used, <code>IntervalMilliseconds</code> is not used.</p> </div>
IntervalMil-	VT_I4	For non-raw sampled data, this column represents a positive integer for the time interval (in milliseconds) between returned samples.

Table 397. ihRawData Table (continued)

Column Name	Data Type	Description
IntervalMilliseconds		<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: The <code>NumberOfSamples</code> and <code>IntervalMilliseconds</code> columns are mutually exclusive. If <code>NumberOfSamples</code> is used, <code>IntervalMilliseconds</code> is not used. </div>
CalculationMode	VT_BSTR	This column applies only if the <code>SamplingMode</code> is set to <code>Calculated</code> . It represents the type of calculation to perform on archive data: <ul style="list-style-type: none"> • <code>Average</code> • <code>Count</code> • <code>Maximum</code> • <code>MaximumTime</code> • <code>Minimum</code> • <code>MinimumTime</code> • <code>StandardDeviation</code> • <code>Total</code> • <code>RawAverage</code> • <code>RawStandardDeviation</code> • <code>RawTotal</code> • <code>TimeGood</code> • <code>FirstRawValue</code> • <code>FirstRawTime</code> • <code>LastRawValue</code> • <code>LastRawTime</code> • <code>TagStats</code>
FilterTag	VT_BSTR	Tagname used to define the filter, if specified. Only a single tag can be specified, and wildcards are not supported.
FilterMode	VT_BSTR	The type of time filter: <ul style="list-style-type: none"> • <code>ExactTime</code>: Retrieves data for the exact times that the filter condition is <code>True</code>. • <code>BeforeTime</code>: Retrieves data from the time of the last <code>False</code> filter condition to the time of the next <code>True</code> condition.

Table 397. ihRawData Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • <code>AfterTime</code>: Retrieves data from the time of the last <code>True</code> filter condition to the next <code>False</code> condition. • <code>BeforeAndAfterTime</code>: Retrieves data from the time of the last <code>False</code> filter condition to the next <code>False</code> condition. <p>This mode defines how time periods before and after transitions in the filter condition should be handled.</p> <p>For example, <code>AfterTime</code> indicates that the filter condition should be <code>True</code> starting at the timestamp of the archive value that triggered the <code>True</code> condition and leading up to the timestamp of the archive value that triggered the <code>False</code> condition.</p>
Filter- Com- parison- Mode	VT_BSTR	<p>The type of comparison to be made on the filter comparison value:</p> <ul style="list-style-type: none"> • <code>Equal</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the comparison value. • <code>EqualFirst</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the first comparison value. • <code>EqualLast</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the last comparison value. • <code>NotEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is not equal to the comparison value. • <code>LessThan</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is less than the comparison value. • <code>GreaterThan</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is greater than the comparison value. • <code>LessThanEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is less than or equal to the comparison value. • <code>GreaterThanEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is greater than or equal to the comparison value. • <code>AllBitsSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is equal to all the bits in the condition. It is represented as <code>^</code> to be used in <code>FilterExpression</code>.

Table 397. ihRawData Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • <code>AnyBitSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is equal to any of the bits in the condition. It is represented as <code>~</code> to be used in <code>FilterExpression</code>. • <code>AnyBitNotSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is not equal to any one of the bits in the condition. It is represented as <code>!~</code> to be used in <code>FilterExpression</code>. • <code>AllBitsNotSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is not equal to all the bits in the condition. It is represented as <code>!^</code> to be used in <code>FilterExpression</code>. <p>This column defines how archive values for the <code>FilterTag</code> value should be compared to the <code>FilterValue</code> value to establish the state of the filter condition. If <code>FilterTag</code> and <code>FilterComparisonValue</code> values are specified, time periods are filtered from the results where the filter condition is <code>False</code>.</p>
FilterValue	VT_BSTR	The value with which to compare the <code>FilterTag</code> value to determine appropriate filter times.
FilterExpression	VT_BSTR	<p>An expression which includes one or more filter conditions. The type of conditions used are:</p> <ul style="list-style-type: none"> • AND • OR • Combination of <code>AND</code> and <code>OR</code> <p><code>FilterExpression</code> can be used instead of the <code>FilterTag</code>, <code>FilterComparisonMode</code> and <code>FilterValue</code> parameters. While using <code>FilterExpression</code>, the expression is passed within single quotes. For complex expressions, write the conditions within parentheses. There is no maximum length for the <code>FilterExpression</code> value, but if called using OLE DB or Excel, those tools may have their own limitations.</p>
TimeZone	VT_BSTR	The type of time zone used:

Table 397. ihRawData Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT)
Daylight-Saving-Time	VT_BOOL	Indicates whether Daylight Saving Time logic should be applied to timestamps.
Row-Count	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned.

The `ihRawData` table can generate a large number of rows if not used with caution. You can easily generate queries which take a very long time to complete and put stress on the archiver and generate network traffic.

ihRawData Examples

Tasks that you might want to perform on the `ihRawData` table are outlined in the following examples.

Example 1: Retrieve All Samples With a Value Outside the Query Supplied Values

```
SELECT * FROM ihRawData WHERE value<140000 OR value>150000
```

Example 2: Retrieve All Bad Samples (Raw Data)

```
SELECT * FROM ihRawData WHERE quality NOT LIKE good*
AND samplingmode=RawbyTime
```

Example 3: Count Bad Samples (Raw Data)

```
SELECT COUNT(*) FROM ihRawData WHERE quality NOT LIKE good*
AND samplingmode=RawbyTime
```

Example 4: Retrieve All Bad Samples Over the Last Day (Interpolated Data)

```
SELECT timestamp, tagname, value, quality FROM ihRawData
WHERE samplingmode=rawbytime
AND Quality NOT LIKE good*
AND timestamp>=Now-24H
```

Example 5: Use an Explicit Time Zone

```
SELECT * FROM ihRawData WHERE timezone=300
```

Example 6: Perform a Simple Sequence of Events

```
SELECT timestamp, tagname, value, quality FROM ihrawdata
WHERE samplingmode=rawbytime ORDER BY timestamp
```

Example 7: Report the Busiest Tags

```
SELECT tagname, value FROM ihRawData
WHERE samplingmode=calculated
AND calculationmode=count
AND numberofsamples=1
AND timestamp>='07/30/2002 10:00:00'
AND timestamp<='07/30/2002 11:00:00' order by value descending
```

Example 8: Retrieve All Bad Samples Over the Last Day

```
SELECT timestamp, tagname, value, quality FROM ihRawData
WHERE samplingmode=rawbytime
AND Quality NOT LIKE good*
AND timestamp>=Now-24H
```

Example 9: Retrieve All Bad Samples, Ignore End of Collection Markers

```
SELECT timestamp, tagname, value, quality FROM ihRawData
WHERE samplingmode=rawbytime
AND Quality NOT LIKE good*
AND quality NOT LIKE 'bad offline' AND timestamp>=Now-24H
```

Example 10: Count Bad Samples, Ignore End of Collection Markers

```
SELECT COUNT(*) FROM ihRawData WHERE samplingmode=rawbytime
AND Quality NOT LIKE good* and Quality NOT LIKE 'bad offline'
AND timestamp>=Now-24H
```

Example 11: Obtain All Raw Samples With Comments From Yesterday

```
SELECT ihRawData.Tagname, ihRawData.TimeStamp, ihRawData.Value
FROM ihRawData
INNER JOIN ihComments ON ihComments.Tagname = ihRawData.Tagname
AND ihComments.Timestamp = ihRawData.Timestamp
AND ihComments.Comment = "The comment" WHERE samplingmode=rawbytime
AND ihComments.Timestamp > Yesterday
AND ihComments.Timestamp < Today
```

Example 12: Determine the Number of Milliseconds Per Interval With Good Data

```
SELECT timestamp, tagname, value as TimeGood, quality, intervalmilliseconds FROM ihRawData
WHERE tagname=Denali.Simulation00001
AND samplingmode=calculated
AND calculationmode=timegood
AND intervalmilliseconds=10s
AND timestamp>='1/20/2003 13:18:00'
AND timestamp<='1/20/2003 13:20:00'
```

Example 13: Retrieve Raw Minimum and Maximum Values Per Interval

In this example, you use the data retrieved from the query (with the `Trend` sampling mode) to plot points.

```
SELECT timestamp, tagname, value, quality
FROM ihRawData
WHERE tagname=dFloatTag5
AND samplingmode=trend
AND intervalmilliseconds=24h
AND timestamp>='1/01/2003 07:00:00'
AND timestamp<='1/10/2003 12:00:00'
```

Example 14: Retrieve Data with Native Values and Tags Associated With Enumerated Sets

If the `enumnativevalue` query modifier is not set, the data is retrieved with string values by default. If it is set, the raw values are retrieved. These values are then retrieved by default for the current session and will only change when you open a new session.

```
SELECT * from ihrawdata
WHERE samplingmode='rawbytime' and tagname=mytag AND criteriastring='#enumnativevalue'

SELECT timestamp,value,quality from ihrawdata WHERE tagname = MyTag AND samplingmode=Interpolated and numberofsamples=6
and criteriastring='#enumnativevalue'

SET criteriastring='#enumnativevalue'

SELECT * from ihrawdata
WHERE samplingmode='rawbytime' and tagname=mytag
```

Example 15: Retrieve Average Values for Enumerated Sets

```
SET criteriastring='#enumnativevalue'

SELECT * from ihrawdata
WHERE tagname LIKE Call AND samplingmode=calculated AND calculationmode=average
```

ihHabAlarms Table

The `ihHabAlarms` table contains alarm data collected from Habitat by the HAB collector. This data is stored in the Historian archive files.

Column Name	Data Type	Description
<code>tagname</code>	<code>VT_BSTR</code>	The tagname property of the tag.
<code>time-stamp</code>	<code>VT_DB-TimeStamp</code>	The date and time for the data sample (based on the timestamp of collector)
<code>time-stampseconds</code>	<code>VT_I4</code>	The date and time for the data sample.

Column Name	Data Type	Description
microseconds	VT_I4	The microsecond interval for the data sample.
sampling-mode	VT_BSTR	The mode used to retrieve data from the archive. Only the RawByTime sampling mode is used for alarms. It retrieves raw archive values for a time period.
quality	VT_BSTR	The quality of the tag data. For raw sampled data, the valid data values is Good.
text	VT_BSTR	The alarms message
location	VT_BSTR	The substation or location as defined in the Habitat database
priority	VT_BSTR	The alarm priority as defined in the Habitat database
category	VT_BSTR	The alarm category as defined in the Habitat database
exception	VT_BSTR	The alarm exception as defined in the Habitat database
area	VT_BSTR	The alarm area as defined in the Habitat database
field-time	VT_DB- TimeS- tamp	The field time of the alarm message (if available)
fmil-lisec	VT_I4	The milliseconds part of the field time
fnanosec	VT_I4	The nanoseconds part of the field time
time	VT_DB- TimeS- tamp	The time of the alarm generated in Habitat (mapped to TIME_CIRCLG)
timefmt	VT_I4	
tnanosec	VT_I4	The nanoseconds part of the alarms time
rowcount	VT_I4	The maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned.

ihComments Table

The `ihComments` table contains the annotations associated with the collected data. There is a separate row of data in the `ihComments` table for each comment associated with a tag. For instance, you can have five rows that contain the same tag and timestamp, but each contain a different comment value.

It is possible to have different data types of annotations. Comments are most often strings, but can be binary numbers or BLOBs. Only string comments are returned in the `ihComments` table.

The following table describes the columns of the `ihComments` table.

Table 398. ihComments Table

Column Name	Data Type	Description
Tagname	VT_BSTR	Tagname property of the tag. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: There is no length limit for Historian tag names in the Data Archiver. However, different client applications may have their own limits. </div>
TimeStamp	VT_DBTimeStamp	The date and time that the data was generated.
TimeStampSeconds	VT_DBTimeStamp	The date and time that the data was generated.
Microseconds	VT_I4	The microsecond portion of the date and time.
StoredOnTimeStamp	VT_DBTimeStamp	The date and time that the comment was generated.
StoredOnTimeStamp	VT_DBTimeStamp	The time that the comment was added to the archive.
SuppliedUsername	VT_BSTR	The username of the currently logged-in Windows user at the

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		time that the comment was entered.
Username	VT_BSTR	Username provided along with the comment.
Comment	VT_BSTR	The actual comment.
DataTypeHint	VT_BSTR	<p>Name of the data type for the comment:</p> <ul style="list-style-type: none"> • String • Read-only • Optional
SamplingMode	VT_BSTR	<p>The mode used to sample data from the archive:</p> <ul style="list-style-type: none"> • CurrentValue: Retrieves the current value. Time frame criteria are ignored. • Interpolated: Retrieves evenly spaced interpolated values based on interval or <code>NumberOfSamples</code> and time frame criteria. • RawByTime: Retrieves raw archive values based on time frame criteria. • RawByNumber: Retrieves raw archive values based on the <code>StartTime</code>, <code>NumberOfSamples</code>, and <code>Direction</code> criteria.

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		<div data-bbox="1105 323 1421 590" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-bottom: 10px;">  Note: EndTime criteria are ignored for this sampling mode. </div> <ul style="list-style-type: none"> <li data-bbox="1084 625 1427 1104">• RawByFilterToggle: Returns filtered time ranges. The values returned are 0 and 1. If the value is 1, then the condition is true and 0 means false. This sampling mode is used with the time range and FilterTag conditions. Results have starting and ending timestamps. <li data-bbox="1084 1121 1427 1373">• Calculated: Retrieves evenly spaced calculated values based on NumberOfSamples, interval, time frame, and CalculationMode criteria. <li data-bbox="1084 1390 1427 1507">• Lab: Returns actual collected values without interpolation. <li data-bbox="1084 1524 1427 1822">• Trend: Returns raw minimums and maximums for each specified interval. Use this mode to maximize performance when retrieving data points for plotting. If the sampling

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		<p>period does not evenly divide by the interval length, Historian ignores any left-over values at the end instead of putting them into a smaller interval.</p> <ul style="list-style-type: none"> • <code>Trend2</code>: Returns raw minimum and maximum values for each specified interval. Use this mode to maximize performance when retrieving data points for plotting. If the sampling period does not evenly divide by the interval length, Historian creates as many intervals of the interval length as will fit into the sampling period, and then creates a remainder interval from whatever time is left. This sampling mode is more suitable than the <code>Trend</code> mode for analysis of minimums and maximums and for plotting programs that can handle unevenly spaced data. • <code>InterpolatedtoRaw</code>: Provides raw data in place of interpolated data when the number of samples requested is less than the

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		<p>number of available samples.</p> <ul style="list-style-type: none"> • TrendtoRaw: This mode almost always produces the same results as the Trend mode. The exception is that when a greater number of samples are requested than the number of raw data points, this mode returns all available raw data points with no further processing. This mode is therefore used instead of Trend when the number of actual data samples is less than the requested number of samples. • TrendtoRaw2: This sampling mode almost always produces the same results as the Trend2 mode. The exception is that when a greater number of samples are requested than the number of raw data points, this mode returns all available raw data points with no further processing. This mode is therefore used instead of Trend2 when the number of actual data samples is

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		<p>less than the requested number of samples.</p> <ul style="list-style-type: none"> • <code>LabtoRaw</code>: Provides raw data for the selected calculated data when the number of samples is less than the number of available samples.
<code>Direction</code>	<code>VT_BSTR</code>	The direction (forward or backward from the start time) of data sampling from the archive.
<code>NumberOfSamples</code>	<code>VT_I4</code>	<p>Number of samples from the archive to retrieve.</p> <p>Samples will be evenly spaced within the time range defined by start and end times for most sampling modes. For the <code>RawByNumber</code> mode, this column determines the maximum number of values to retrieve. For the <code>RawByTime</code> mode, this value is ignored.</p> <div data-bbox="1024 1356 1422 1713" style="border: 1px solid #00a0c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note:</p> <p>The <code>NumberOfSamples</code> and <code>IntervalMilliseconds</code> columns are mutually exclusive. If <code>NumberOfSamples</code> is used, <code>IntervalMilliseconds</code> is not used.</p> </div>
<code>IntervalMilliseconds</code>	<code>VT_I4</code>	For non-raw sampled data, this column represents a positive integer for the time interval (in

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		milliseconds) between returned samples. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: The <code>NumberOfSamples</code> and <code>IntervalMilliseconds</code> columns are mutually exclusive. If <code>NumberOfSamples</code> is used, <code>IntervalMilliseconds</code> is not used. </div>
<code>CalculationMode</code>	<code>VT_BSTR</code>	The calculation mode, if used.
<code>FilterTag</code>	<code>VT_BSTR</code>	Tagname used to define the filter, if specified. Only a single tag can be specified, and wildcards are not supported.
<code>FilterMode</code>	<code>VT_BSTR</code>	The type of time filter: <ul style="list-style-type: none"> • <code>ExactTime</code>: Retrieves data for the exact times that the filter condition is <code>True</code>. • <code>BeforeTime</code>: Retrieves data from the time of the last <code>False</code> filter condition to the time of the next <code>True</code> condition. • <code>AfterTime</code>: Retrieves data from the time of the last <code>True</code> filter condition to the time of the next <code>False</code> condition. • <code>BeforeAndAfterTime</code>: Retrieves data from the time

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		<p>of the last <code>False</code> filter condition to the time of the next <code>False</code> condition.</p> <p>The <code>FilterMode</code> defines how time periods before and after transitions in the filter condition should be handled.</p> <p>For example, <code>AfterTime</code> indicates that the filter condition should be <code>True</code> starting at the timestamp of the archive value that triggered the <code>True</code> condition and ending at the timestamp of the archive value that triggered the <code>False</code> condition.</p>
<code>FilterComparisonMode</code>	<code>VT_BSTR</code>	<p>The type of comparison to be made on the filter comparison value:</p> <ul style="list-style-type: none"> • <code>Equal</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the comparison value. • <code>EqualFirst</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the first comparison value. • <code>EqualLast</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the last comparison value. • <code>NotEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code>

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		<p>value is not equal to the comparison value.</p> <ul style="list-style-type: none"> • LessThan: Filter condition is <code>True</code> when the <code>FilterTag</code> value is less than the comparison value. • GreaterThan: Filter condition is <code>True</code> when the <code>FilterTag</code> value is greater than the comparison value. • LessThanEqual: Filter condition is <code>True</code> when the <code>FilterTag</code> value is less than or equal to the comparison value. • GreaterThanEqual: Filter condition is <code>True</code> when the <code>FilterTag</code> value is greater than or equal to the comparison value. • AllBitsSet: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is equal to all the bits in the condition. It is represented as <code>^</code> to be used in <code>FilterExpression</code>. • AnyBitSet: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is equal to any of the bits in the condition. It is represented as <code>~</code> to be used in <code>FilterExpression</code>.

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • <code>AnyBitNotSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is not equal to any one of the bits in the condition. It is represented as <code>!~</code> to be used in <code>FilterExpression</code>. • <code>AllBitsNotSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is not equal to all the bits in the condition. It is represented as <code>!^</code> to be used in <code>FilterExpression</code>. <p>This column defines how archive <code>FilterTag</code> values should be compared to <code>FilterValue</code> values to establish the state of the filter condition. If <code>FilterTag</code> and <code>FilterComparisonValue</code> values are specified, time periods are filtered from the results where the filter condition is <code>False</code>.</p>
<code>FilterValue</code>	<code>VT_BSTR</code>	The value with which to compare the <code>FilterTag</code> value to determine appropriate filter times.
<code>FilterExpression</code>	<code>VT_BSTR</code>	<p>An expression which includes one or more filter conditions. The type of conditions used are:</p> <ul style="list-style-type: none"> • <code>AND</code> • <code>OR</code> • Combination of <code>AND</code> and <code>OR</code>

Table 398. ihComments Table (continued)

Column Name	Data Type	Description
		<p>This column can be used instead of the <code>FilterTag</code>, <code>FilterComparisonMode</code>, and <code>FilterValue</code> columns. While using <code>FilterExpression</code>, the expression is passed within single quotes, and for complex expressions you write the conditions within parentheses. There is no maximum length for <code>FilterExpression</code>, but if called using OLE DB or Excel, these tools may have their own limitations.</p>
<code>TimeZone</code>	<code>VT_BSTR</code>	<p>The type of time zone used:</p> <ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT)
<code>DaylightSavingTime</code>	<code>VT_BOOL</code>	<p>Indicates whether Daylight Saving Time logic should be applied to timestamps.</p>
<code>RowCount</code>	<code>VT_I4</code>	<p>Indicates the maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned.</p>

ihComments Examples

Example SQL statements for the `ihComments` table are outlined in the following examples.

Example 1: Retrieve All Comments for a Specific Tag for This Month

```
SELECT * FROM ihcomments WHERE tagname LIKE '*001'
AND timestamp>bom
```

Example 2: Retrieve Comments That Contain a Substring

```
SELECT * FROM ihcomments WHERE comment LIKE '*abc*'
```

Example 3: Retrieve All Comments in an Archive

```
SELECT * FROM ihComments WHERE timestamp<=Now
AND samplingmode=rawbytime
```

ihTrend Table

The `ihTrend` table allows you to compare multiple tags for the same timestamp. It contains a row of data for each unique timestamp, but with columns from one or more tags. The column names are dynamic and determined by the returned tag names. The `ihTrend` table is similar to a pivot table or, for instance, a cross-tab report that you can create in Crystal Reports.

The `ihTrend` table can store up to 100 columns in a returned set. This allows you to compare `Value` columns with up to 99 tags for a single timestamp, or `Value` and `Quality` columns with up to 49 tags.



Note:

Currently, you cannot analyze the `ihTrend` table in Crystal Reports or the Microsoft SQL Server DTS application.

The following table describes the columns of the `ihTrend` table, including all possible tag columns. Different queries on this table can produce different column results.



Note:

In all column names in the following table, `TagID` is used as a placeholder for the actual tag name.

Table 399. IhTrend Table

Column Name	Data Type	Description
TimeStamp	VT_DBTimeStamp	The date and time that the trend was generated.
TimeSampleSeconds	VT_DBTimeStamp	The date and time for the data sample.
Microseconds	VT_I4	The microsecond interval for the data sample.
SamplingMode	VT_BSTR	<p>The mode of sampling data from the archive:</p> <ul style="list-style-type: none"> • CurrentValue: Retrieves the current value. Time frame criteria are ignored. • Interpolated: Retrieves evenly spaced interpolated values based on interval or NumberOfSamples and time frame criteria. • RawByTime: Retrieves raw archive values based on time frame criteria. • RawByNumber: Retrieves raw archive values based on the StartTime, NumberOfSamples, and Direction criteria. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Note: EndTime criteria are ignored for this mode.</p> </div> <ul style="list-style-type: none"> • RawByFilterToggle: Returns filtered time ranges. The values returned are 0 and 1. If the value is 1, then the condition is true and 0 means false. This mode is used with the time range and FilterTag conditions. Results start and end with timestamps. • Calculated: Retrieves evenly spaced calculated values based on NumberOfSamples, interval, time frame, and CalculationMode criteria. • Lab: Returns actual collected values without interpolation. • Trend: Returns the raw minimums and maximums for each specified interval. Use this mode to maximize performance when retrieving data points for plotting. If the sampling period does not evenly divide by the interval length, His-

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
		<p>torian ignores any leftover values at the end instead of putting them into a smaller interval.</p> <ul style="list-style-type: none"> • Trend2: Returns the raw minimums and maximums for each specified interval. Use this mode to maximize performance when retrieving data points for plotting. If the sampling period does not evenly divide by the interval length, Historian puts leftover values into a remainder interval. This mode is more suitable than the Trend mode for analysis of minimums and maximums and for plotting programs that can handle unevenly spaced data. • InterpolatedtoRaw: Provides raw data in place of interpolated data when the number of samples is less than the number of available samples. • TrendtoRaw: This mode almost always produces the same results as the Trend mode. The exception is that when the number of samples requested is greater than the number of raw data points, this mode returns all available raw data points with no further processing. This mode is therefore used instead of Trend when the number of actual data samples is less than the requested number of samples. • TrendtoRaw2: This mode almost always produces the same results as the Trend2 mode. The exception is that when the number of samples requested is greater than the number of raw data points, this mode returns all available raw data points with no further processing. This mode is therefore used instead of Trend2 when the number of actual data samples is less than the requested number of samples. • LabtoRaw: Provides raw data for the selected calculated data when the number of requested samples is less than the number of available samples.
Direction	VT_BSTR	The direction (forward or backward from the start time) of data sampling from the archive.
Number-OfSamples	VT_I4	<p>Number of samples to retrieve from the archive.</p> <p>Samples will be evenly spaced within the start and end times defined for most sampling modes. For the RawByNumber mode, this column determines the maximum number of values to retrieve. For the RawByTime mode, this column is ignored.</p>

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
		<div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: The <code>NumberOfSamples</code> and <code>IntervalMilliseconds</code> columns are mutually exclusive. If <code>NumberOfSamples</code> is used, <code>IntervalMilliseconds</code> is not used. </div>
IntervalMilliseconds	VT_I4	For non-row sampled data, this column represents a positive integer for the time interval (in milliseconds) between returned samples. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF; margin-top: 10px;">  Note: The <code>NumberOfSamples</code> and <code>IntervalMilliseconds</code> columns are mutually exclusive. If <code>NumberOfSamples</code> is used, <code>IntervalMilliseconds</code> is not used. </div>
CalculationMode	VT_BSTR	This column applies only if the <code>SamplingMode</code> is set to <code>Calculated</code> . It represents the type of calculation to perform on archive data: <ul style="list-style-type: none"> • <code>Average</code> • <code>Count</code> • <code>Maximum</code> • <code>MaximumTime</code> • <code>Minimum</code> • <code>MinimumTime</code> • <code>StandardDeviation</code> • <code>Total</code> • <code>RawAverage</code> • <code>RawStandardDeviation</code> • <code>RawTotal</code> • <code>TimeGood</code> • <code>FirstRawValue</code> • <code>FirstRawTime</code> • <code>LastRawValue</code> • <code>LastRawTime</code> • <code>TagStats</code>
FilterTag	VT_BSTR	Tagname used to define the filter, if specified. Only a single tag can be specified. Wildcards are not supported.

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
Filter-Mode	VT_BSTR	<p>The type of time filter:</p> <ul style="list-style-type: none"> • <code>ExactTime</code>: Retrieves data for the exact times that the filter condition is <code>True</code>. • <code>BeforeTime</code>: Retrieves data from the time of the last <code>False</code> filter condition to the time of the next <code>True</code> condition. • <code>AfterTime</code>: Retrieves data from the time of the last <code>True</code> filter condition to the time of the next <code>False</code> condition. • <code>BeforeAndAfterTime</code>: Retrieves data from the time of the last <code>False</code> filter condition to the time of the next <code>False</code> condition. <p>This value defines how time periods before and after transitions in the filter condition should be handled.</p> <p>For example, <code>AfterTime</code> indicates that the filter condition should be <code>True</code> starting at the timestamp of the archive value that triggered the <code>True</code> condition and ending at the timestamp of the archive value that triggered the <code>False</code> condition.</p>
Filter-ComparisonMode	VT_BSTR	<p>The type of comparison to be made on the filter comparison value:</p> <ul style="list-style-type: none"> • <code>Equal</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the comparison value. • <code>EqualFirst</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the first comparison value. • <code>EqualLast</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the last comparison value. • <code>NotEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is not equal to the comparison value. • <code>LessThan</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is less than the comparison value. • <code>GreaterThan</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is greater than the comparison value. • <code>LessThanEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is less than or equal to the comparison value. • <code>GreaterThanEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is greater than or equal to the comparison value.

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • <code>AllBitsSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is equal to all the bits in the condition. It is represented as <code>^</code> to be used in <code>FilterExpression</code>. • <code>AnyBitSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is equal to any of the bits in the condition. It is represented as <code>-</code> to be used in <code>FilterExpression</code>. • <code>AnyBitNotSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is not equal to any one of the bits in the condition. It is represented as <code>!~</code> to be used in <code>FilterExpression</code>. • <code>AllBitsNotSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is not equal to all the bits in the condition. It is represented as <code>!^</code> to be used in <code>FilterExpression</code>. <p>This column defines how archive values for the <code>FilterTag</code> value should be compared to the <code>FilterValue</code> value to establish the state of the filter condition. If <code>FilterTag</code> and <code>FilterComparisonValue</code> values are specified, time periods are filtered from the results where the filter condition is <code>False</code>.</p>
Filter-Value	VT_BSTR	The value with which to compare the <code>FilterTag</code> value to determine appropriate filter times.
Filter-Expression	VT_BSTR	<p>An expression which includes one or more filter conditions. The type of conditions used are:</p> <ul style="list-style-type: none"> • AND • OR • Combination of AND and OR <p>This column can be used instead of the <code>FilterTag</code>, <code>FilterComparisonMode</code>, and <code>FilterValue</code> columns. While using <code>FilterExpression</code>, the expression is passed within single quotes. For complex expressions, you write the conditions within parentheses. There is no maximum length for <code>FilterExpression</code>, but if called using OLE DB or Excel, these tools may have their own limitations.</p>
TimeZone	VT_BSTR	The type of time zone used:

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT)
Daylight-Saving-Time	VT_BOOL	Indicates whether Daylight Saving Time logic should be applied to timestamps.
RowCount	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned.
Tag-ID.Value	VT_- VARIANT	The value of the data for the specified tag ID.
Tag-ID.Quality	VT_- VARIANT	<p>For non-raw sampled data, this column displays the percentage of good quality samples in the interval. For instance, a value of 100 means all samples in the interval are good.</p> <p>For raw sampled data, data values are:</p> <ul style="list-style-type: none"> • Good • Bad • Uncertain • Not Available • Really Unknown <p>This column also includes the subquality of the data value, if it exists:</p> <ul style="list-style-type: none"> • NonSpecific • ConfigError • NotConnected • DeviceFail • SensorFail • LastKnownValue • CommFailure • OutOfService

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • ScaledOutOfRange • OffLine • NoValue • Really Unknown
Tag- ID.Tag- name	VT_BSTR	Tagname property of the specified tag ID.
Tag- ID.De- scrip- tion	VT_BSTR	User description for the specified tag ID.
Tag- ID.EngU- nits	VT_BSTR	Engineering unit description for the specified tag ID.
Tag- ID.Com- ment	VT_BSTR	User comment associated with the specified tag ID.
Tag- ID.Data- Type	VT_BSTR	<p>The data type for the specified tag ID:</p> <ul style="list-style-type: none"> • Scaled • SingleFloat • DoubleFloat • SingleInteger • DoubleInteger • QuadInteger • UnsignedSingleInteger • UnsignedDoubleInteger • UnsignedQuadInteger • FixedString • VariableString • Byte • Boolean

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • BLOB • Time • Undefined <p>The data type returned in this column is the data type that you defined in Historian Administrator application.</p>
Tag- ID.Fixed- String- Length	VT_UI1	This value is 0 unless the data type is FixedString. If the data type is FixedString, this number represents the maximum length of the string value.
Tag- ID.Col- lector- Name	VT_BSTR	The name of the collector responsible for collecting data for the specified tag ID.
Tag- ID.Source- Address	VT_BSTR	The address used to identify the specified tag ID at the data source. For iFIX systems, this is the NTF (Node.Tag.Field).
Tag- ID.Col- lection- Type	VT_BSTR	<p>Type of collection used to acquire data for the tag:</p> <ul style="list-style-type: none"> • Unsolicited: The collector accepts data from the source whenever the source presents the data. • Polled: The collector acquires data from a source on a periodic schedule determined by the collector. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: Not all collectors support unsolicited collection. </div>
Tag- ID.Col- lection- Interval	VT_I4	<p>The time interval, in milliseconds, between readings of data from this tag.</p> <p>For polled collection, this field represents the time between samples. For unsolicited collection, this field represents the minimum time allowed between samples.</p>

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
Tag- ID.Col- lection- Offset	VT_I4	The time shift from midnight, in milliseconds, for collection of data from this tag.
Tag- ID.Load- Balanc- ing	VT_BOOL	Indicates whether the data collector should automatically shift the phase of sampling to distribute the activity of the processor evenly over the polling cycle for the specified tag ID. This is sometimes called phase shifting.
Tag- ID.Time- Stamp- Type	VT_BSTR	The timestamp type applied to data samples at collection time: <ul style="list-style-type: none"> • Source: The source delivers the timestamp along with the data sample. • Collector: The collector delivers the timestamp along with the collected data.
Tag- ID.Hi- Engi- neering- Units	VT_R8	The high end of the engineering units range. Used only for scaled data types and input scaled tags.
Tag- ID.Lo- Engi- neering- Units	VT_R8	The low end of the engineering units range. Used only for scaled data types and input scaled tags.
Tag- ID.In- putScal- ing	VT_BOOL	Indicates whether the measurement should be converted to an engineering units value. When set to <code>False</code> , the measurement is interpreted as a raw measurement. When set to <code>True</code> , the system converts the value to engineering units by scaling the value between the <code>HiScale</code> and <code>LoScale</code> values. If not enabled, the system assumes the measurement is already converted into engineering units.
Tag- ID.HiS- cale	VT_R8	The high-end value of the input scaling range used for the tag.

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
Tag- ID.LoScale	VT_R8	The low-end value of the input scaling range used for the tag.
Tag- ID.Collector- Compression	VT_BOOL	Indicates whether collector compression is enabled for the specified tag ID. Collector compression applies a smoothing filter to incoming data by ignoring incremental changes in values that fall within a deadband centered around the last collected value. The collector passes (to the archiver) any new value that falls outside the deadband and then centers the deadband around the new value.
Tag- ID.Collector- Deadband- Percent- Range	VT_R4	The current value of the compression deadband.
Tag- ID.Archive- Compression	VT_BOOL	Indicates whether archive collector compression is enabled for the tag.
Tag- ID.Archive- Deadband- Percent- Range	VT_R4	The current value of the archive compression deadband.
Tag- ID.Collector- General	VT_BSTR	The general (or spare) configuration fields for the specified tag ID.

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
Tag- ID.Col- lector- General2	VT_BSTR	The general (or spare) configuration fields for the specified tag ID.
Tag- ID.Col- lector- General3	VT_BSTR	The general (or spare) configuration fields for the specified tag ID.
Tag- ID.Col- lector- General4	VT_BSTR	The general (or spare) configuration fields for the specified tag ID.
Tag- ID.Col- lector- General5	VT_BSTR	The general (or spare) configuration fields for the specified tag ID.
Tag- ID.Read- Securi- tyGroup	VT_BSTR	The name of the Windows security group that controls the reading of data for the specified tag ID. Refer to "Implementing Historian Security" in the <i>Getting Started with Historian</i> manual for definitions of the various security levels and groups.
Tag- ID.Write- Securi- tyGroup	VT_BSTR	The name of the Windows security group that controls the writing of data for the specified tag ID. Refer to "Implementing Historian Security" in the <i>Getting Started with Historian</i> manual for definitions of the various security levels and groups.
Tag- ID.Ad- minis- trator- Securi- tyGroup	VT_BSTR	The name of the Windows security group responsible for controlling configuration changes for the specified tag ID.

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
Tag- ID.Cal- culation	VT_BSTR	The equation for the calculation performed for the specified tag ID.
Tag- ID.Last- Modified	VT_DB- TimeS- tamp	The date and time that the tag configuration was last modified. The time structure includes milliseconds.
Tag- ID.Last- Modi- fiedUser	VT_BSTR	The username of the Windows user who last modified the tag configuration.
Tag- ID.Col- lector- Type	VT_BSTR	<p>The type of collector responsible for collecting data for the specified tag ID:</p> <ul style="list-style-type: none"> • Undefined • iFIX • Simulation • OPC • File • iFIXLabData • ManualEntry • Simulation • Other
TagID.S- toreMil- lisc- onds	VT_BOOL	<p>Indicates whether time resolution in milliseconds is enabled for the specified tag ID.</p> <p>If not enabled, time resolution is in seconds instead of milliseconds. Maximum data compression is achieved when this value is set to <code>False</code>. This is the optimum setting for most applications.</p>
Tag- ID.UTCbias	VT_I4	<p>The time zone bias for the specified tag ID. Time zone bias is used to indicate the natural time zone of the tag expressed as an offset from UTC (Universal Time Coordinated) in minutes.</p> <p>UTC is the international time standard, the current term for what was commonly referred to as Greenwich Mean Time (GMT).</p>

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
Tag-ID.AverageCollectionTime	VT_I4	The average time it takes to execute the calculation tag since you started the Calculation collector for the specified tag ID.
Tag-ID.CollectionDisabled	VT_I4	Indicates whether collection is enabled (0) or disabled (1) for the specified tag ID. The default setting is enabled (0).
Tag-ID.CollectorCompressionTimeout	VT_I4	<p>Indicates the maximum amount of time the collector will wait between sending samples to the archiver. This time is kept per tag, as different tags report to the archiver at different times.</p> <p>This value should be in increments of your collection interval, and not less.</p> <p>Ideally, this field is used for polled data values. It can be used with unsolicited data, but when you do so, you are dependent on the data source for the value to change. With unsolicited data, since Historian only records the value when it changes, the actual time before the timeout might exceed the compression timeout.</p>
Tag-ID.ArchiveCompressionTimeout	VT_I4	Indicates the maximum amount of time from the last stored point before another point is stored, if the value does not exceed the archive compression deadband for the specified tag ID.
Tag-ID.InterfaceAbsoluteDeadbanding	VT_BOOL	Indicates whether absolute collector deadband is enabled for the specified tag ID.
Tag-ID.In-	VT_R8	Indicates the value for absolute collector deadband.

Table 399. IhTrend Table (continued)

Column Name	Data Type	Description
terface-AbsoluteDeadband		
Tag-ID.ArchiveAbsoluteDeadbanding	VT_BOOL	Indicates whether absolute archive deadband is enabled for the specified tag ID.
Tag-ID.ArchiveAbsoluteDeadband	VT_R8	Indicates the value for absolute archive deadband.
Tag-ID.SpikeLogic	VT_BOOL	Indicates whether Spike Logic is enabled on the collector.
Tag-ID.SpikeLogicOverride	VT_BOOL	Indicates whether the Spike Logic setting for the specified tag ID overrides the collector setting (<code>True</code>) or the collector setting is used (<code>False</code>).

Use care when building queries against the `ihTrend` table. Because a query to this table compares multiple tags at the same time, it takes longer to query the `ihTrend` table than it does the `ihRawData` table. The `ihTrend` table can be quite large, so be sure to either use the default start and end times, or define a specific time interval. See [Query Performance Optimization \(on page 2611\)](#) for more ideas on how to optimize your query of the `ihTrend` table.

ihTrend Examples

Example SQL statements for the `ihTrend` table are outlined in the following examples.

Example 1: Retrieve Value and Quality of the First 50 Tags

```
SELECT timestamp, *.value, *.quality FROM ihtrend
```

Example 2: Retrieve Value of the First 100 Tags

```
SELECT timestamp, *.value FROM ihTrend
```

Example 3: Retrieve Values of All Tags That Match a Specific Pattern

```
SELECT timestamp, *0001.value FROM ihtrend ORDER BY MY_SERVER.Simulation00001.Value
```

Example 4: Retrieve Hourly Interpolated Values of TagNames That Match *0001

```
SET samplingmode=interp, intervalmilliseconds=1h  
SELECT timestamp, *0001.value FROM ihtrend  
ORDER BY Simulation00001.value DESC, timestamp DESC
```

Example 5: Retrieve Maximum Values of All TagNames That Match *0001

The following example shows how to use a `TagName` (`simulation.00001.Value`) in a `WHERE` clause.

```
SELECT timestamp, *0001.value FROM ihtrend  
WHERE timestamp>='28-nov-2001 00:00'  
AND timestamp<='29-nov-2001 00:00:00'  
AND samplingmode=calc  
AND intervalmilliseconds=1h  
AND calculationmode=max  
AND simulation00001.Value > 1000 ORDER BY timestamp
```

Example 6: Select Interpolated Values for All Single Float Tags

The following example shows how to select interpolated values for all single float tags, without doing a `JOIN` with the `ihTags` table to retrieve the `DataType` property.

```
SELECT timestamp, *.value, *.description FROM ihtrend  
WHERE timestamp>='28-nov-2001 00:00'  
AND timestamp<='29-nov-2001 00:00:00'  
AND samplingmode=calculated  
AND intervalmilliseconds=2h  
AND *.datatype = singlefloat ORDER BY timestamp
```

Example 7: Select Interpolated Data for TagNames That Match sim*

The following example shows how to sort the returned rows by a `TagName` , `simulation.00001.Value`.

```
SET starttime='28-nov-2001 00:00', endtime='29-nov-2001 00:00:00', samplingmode=interp, intervalmilliseconds=1h
SELECT timestamp, sim*.*, sim*.description, sim*.lastmodifieduser FROM ihtrend
WHERE sim*.description LIKE '*sim*'
AND sim*.description like '*first*'
AND *.datatype = singlefloat
ORDER BY simulation00001.value DESC, timestamp
```

ihQuerySettings Table

The `ihQuerySettings` table contains the current session settings. These settings are applied to all queries you make in a session, unless overridden with a `WHERE` clause. This table displays settings stored in the provider, and has nothing to do with the data stored in the archives.

The `ihQuerySettings` table provides a convenient way to display all your session settings. You cannot, however, write or update settings in this table. This table contains only one row with the settings for the current session. The only way to change these parameters is by using the `SET` statement.

The following table describes the columns of the `ihQuerySettings` table.

Table 400. ihQuerySettings Table

Column Name	Data Type	Description
StartTime	VT_-DB-TimeStamp	The start time of the query. This represents the earliest timestamp for any tag contained in the query. If no <code>StartTime</code> value is specified, the start time is two hours prior to execution of the query.
EndTime	VT_-DB-TimeStamp	The end time of the query. This represents the latest timestamp for any tag contained in the query. If no <code>EndTime</code> value is specified, the end time is the time that you execute the query.

Table 400. ihQuerySettings Table (continued)

Column Name	Data Type	Description
Sampling Mode	VT_-BSTR	<p>The mode of sampling data from the archive:</p> <ul style="list-style-type: none"> • CurrentValue: Retrieves the current value. Time frame criteria are ignored. • Interpolated: Retrieves evenly spaced interpolated values based on <code>Interval</code> or <code>NumberOfSamples</code> and time frame criteria. • RawByTime: Retrieves raw archive values based on time frame criteria. • RawByNumber: Retrieves raw archive values based on the <code>StartTime</code>, <code>NumberOfSamples</code>, and <code>Direction</code> criteria. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin: 10px 0;"> <p> Note: <code>EndTime</code> criteria are ignored for this mode.</p> </div> <ul style="list-style-type: none"> • RawByFilterToggle: Returns filtered time ranges. The values returned are <code>0</code> and <code>1</code>. If the value is <code>1</code>, then the condition is true and <code>0</code> means false. This mode is used with the time range and <code>FilterTag</code> conditions. Results start and end with timestamps. • Calculated: Retrieves evenly spaced calculated values based on <code>NumberOfSamples</code>, <code>Interval</code>, time frame, and <code>CalculationMode</code> criteria. • Lab: Returns actual collected values without interpolation. • Trend: Returns the raw minimums and maximums for each specified interval. Use this mode to maximize performance when retrieving data points for plotting. If the sampling period does not evenly divide by the interval length, Historian ignores any leftover values at the end instead of putting them into a smaller interval. • Trend2: Returns the raw minimums and maximums for each specified interval. Use this mode to maximize performance when retrieving data points for plotting. If the sampling period does not evenly divide by the interval length, Historian puts leftover values into a remainder interval. This mode is more suitable than the <code>Trend</code> mode for analysis of minimums and maximums and for plotting programs that can handle unevenly spaced data. • InterpolatedtoRaw: Provides raw data in place of interpolated data when the number of samples is less than the number of available samples. • TrendtoRaw: This mode almost always produces the same results as the <code>Trend</code> mode. The exception is that when the number of samples requested is greater than the number of raw data points, this mode returns all available raw data points with no

Table 400. ihQuerySettings Table (continued)

Column Name	Data Type	Description
		<p>further processing. This mode is therefore used instead of <code>Trend</code> when the number of actual data samples is less than the requested number of samples.</p> <ul style="list-style-type: none"> • <code>TrendtoRaw2</code>: This mode almost always produces the same results as the <code>Trend2</code> mode. The exception is that when the number of samples requested is greater than the number of raw data points, this mode returns all available raw data points with no further processing. This mode is therefore used instead of <code>Trend2</code> when the number of actual data samples is less than the requested number of samples. • <code>LabtoRaw</code>: Provides raw data for the selected calculated data when the number of requested samples is less than the number of available samples. <p><code>Calculated</code> is the default setting.</p>
Direction	VT_-BSTR	<p>The direction (<code>Forward</code> or <code>Backward</code> from the start time) of data sampling from the archive. The default value is <code>Forward</code>.</p>
NumberOfSamples	VT_-I4	<p>Number of samples to retrieve from the archive.</p> <p>Samples will be evenly spaced within the specified start and end times defined for most sampling modes. For the <code>RawByNumber</code> mode, this column determines the maximum number of values to retrieve. For the <code>RawByTime</code> mode, this column is ignored.</p> <div data-bbox="354 1297 1416 1478" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: The <code>NumberOfSamples</code> and <code>IntervalMilliseconds</code> columns are mutually exclusive. If <code>NumberOfSamples</code> is used, <code>IntervalMilliseconds</code> is not used.</p> </div>
IntervalMilliseconds	VT_-I4	<p>For non-raw sampled data, this column represents a positive integer for the time interval (in milliseconds) between returned samples.</p> <div data-bbox="354 1612 1416 1793" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: The <code>NumberOfSamples</code> and <code>IntervalMilliseconds</code> columns are mutually exclusive. If <code>IntervalMilliseconds</code> is used, <code>NumberOfSamples</code> is not used.</p> </div>
Calculation	VT_-BSTR	<p>This column applies only if the <code>SamplingMode</code> is set to <code>Calculated</code>. It represents the type of calculation to perform on archive data:</p>

Table 400. ihQuerySettings Table (continued)

Column Name	Data Type	Description
tion-Mode		<ul style="list-style-type: none"> • Average • Count • Maximum • MaximumTime • Minimum • MinimumTime • OPCQOr and OPCQAnd • StandardDeviation • StateCount • StateTime • Total • RawAverage • RawStandardDeviation • RawTotal • TimeGood • FirstRawValue • FirstRawTime • LastRawValue • LastRawTime • TagStats <p>The default value is Average.</p>
Filter-Tag	VT_-BSTR	<p>Tagname used to define the filter, if specified. Only a single tag can be specified. Wildcards are not supported.</p>
Filter-Mode	VT_-BSTR	<p>The type of time filter:</p> <ul style="list-style-type: none"> • ExactTime: Retrieves data for the exact times that the filter condition is True. • BeforeTime: Retrieves data from the time of the last False filter condition to the time of the next True condition.

Table 400. ihQuerySettings Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • <code>AfterTime</code>: Retrieves data from the time of the last <code>True</code> filter condition to the time of the next <code>False</code> condition. • <code>BeforeAndAfterTime</code>: Retrieves data from the time of the last <code>False</code> filter condition to the time of the next <code>False</code> condition. <p>This value defines how time periods before and after transitions in the filter condition should be handled.</p> <p>For example, <code>AfterTime</code> indicates that the filter condition should be <code>True</code> starting at the timestamp of the archive value that triggered the <code>True</code> condition and ending at the timestamp of the archive value that triggered the <code>False</code> condition.</p>
FilterComparisonMode	VT_-BSTR	<p>The type of comparison to be made on the filter comparison value:</p> <ul style="list-style-type: none"> • <code>Equal</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the comparison value. • <code>EqualFirst</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the first comparison value. • <code>EqualLast</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is equal to the last comparison value. • <code>NotEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is not equal to the comparison value. • <code>LessThan</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is less than the comparison value. • <code>GreaterThan</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is greater than the comparison value. • <code>LessThanEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is less than or equal to the comparison value. • <code>GreaterThanEqual</code>: Filter condition is <code>True</code> when the <code>FilterTag</code> value is greater than or equal to the comparison value. • <code>AllBitsSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is equal to all the bits in the condition. It is represented as <code>^</code> to be used in <code>FilterExpression</code>. • <code>AnyBitSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is equal to any of the bits in the condition. It is represented as <code>~</code> to be used in <code>FilterExpression</code>.

Table 400. ihQuerySettings Table (continued)

Column Name	Data Type	Description
		<ul style="list-style-type: none"> • <code>AnyBitNotSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is not equal to any one of the bits in the condition. It is represented as <code>!~</code> to be used in <code>FilterExpression</code>. • <code>AllBitsNotSet</code>: Filter condition is <code>True</code> when the binary <code>FilterTag</code> value is not equal to all the bits in the condition. It is represented as <code>!^</code> to be used in <code>FilterExpression</code>. <p>This option defines how archive values for the <code>FilterTag</code> value should be compared to the <code>FilterValue</code> value to establish the state of the filter condition. If <code>FilterTag</code> and <code>FilterComparisonValue</code> values are specified, time periods are filtered from the results where the filter condition is <code>False</code>.</p>
FilterValue	VT_- BSTR	The value with which to compare the <code>FilterTag</code> value to determine appropriate filter times.
FilterExpression	VT_- BSTR	<p>An expression which includes one or more filter conditions. The type of conditions used are:</p> <ul style="list-style-type: none"> • <code>AND</code> • <code>OR</code> • Combination of <code>AND</code> and <code>OR</code> <p>This column can be used instead of the <code>FilterTag</code>, <code>FilterComparisonMode</code>, and <code>FilterValue</code> columns. While using <code>FilterExpression</code>, the expression is passed within single quotes. For complex expressions, you write the conditions within parentheses. There is no maximum length for this value, but if called using OLE DB or Excel, these tools may have their own limitations.</p>
TimeZone	VT_- BSTR	<p>The type of time zone used:</p> <ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT)
Daylight	VT_- BOOL	Indicates whether Daylight Saving Time logic should be applied to timestamps.

Table 400. ihQuerySettings Table (continued)

Column Name	Data Type	Description
SavingTime		
RowCount	VT_ I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned. If the query result contains more rows than the <code>RowCount</code> value, the Historian OLE DB provider truncates the extra rows. The truncation is performed last. For instance, if you use <code>ORDER BY</code> in your <code>SELECT</code> statement, the truncation occurs after the rows are ordered.
AlarmType	VT_ BSTR	Indicates the alarm type: <ul style="list-style-type: none"> • Alarms • Alarm_History • Events

ihQuerySettings Examples

Example SQL statements for the `ihQuerySettings` table are outlined in the following examples.

Example 1: Show All Settings for the Current Session

```
SELECT * FROM ihquerysettings
```

Example 2: Show the Selected Session Settings

```
SELECT starttime, endtime FROM ihquerysettings
```

ihCalculationDependencies Table

The `ihCalculationDependencies` table contains the calculation and server-to-server tags and their triggers. The following table describes the columns of the `ihCalculationDependencies` table.

Table 401. ihCalculationDependencies Table

Column Name	Data Type	Description
Tagname	VT_- BSTR	A calculation or server-to-server tag with unsolicited collection and at least one dependent tag.
DependentTagName	VT_- BSTR	A dependent tagname. If a tag has multiple dependent tags, there are multiple rows in the table for that tagname.
RowCount	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned.

ihCalculationDependencies Examples

Example SQL statements for the `ihCalculationDependencies` table are outlined in the following examples.

Example 1: Show the Dependencies for a Specific Tag

```
SELECT * FROM ihcalculationdependencies WHERE tagname = c1
```

Example 2: Show the Dependencies for a Specific Dependent Tag

```
SELECT * FROM ihcalculationdependencies
WHERE dependenttagname=brahms.a11.f_cv
```

ihAlarms Table

The `ihAlarms` table contains collected alarms and events data. The following table describes the columns of the `ihAlarms` table.



CAUTION:

When you perform joins of the `ihRawData` and `ihAlarms` tables, you can easily construct queries that temporarily consume all your system resources. Although this scenario typically does not affect data collection, it can interfere with data analysis. To avoid this issue, always define a start and end time for the query to limit the number of rows returned.

Table 402. ihAlarms Table

Column Name	Data Type	Description
AlarmID	VT_I4	The unique ID of the alarm or event in the Historian alarm database.
ItemID	VT_BSTR	The OPC ItemID of the alarm. This contains the source address of the data access tag with which the alarm is associated. This can contain a NULL value if an alarm is not associated with a tag.
Source	VT_BSTR	The unique identifier used by the OPC AE Collector for the alarm or event.
DataSource	VT_BSTR	The collector interface name associated with the alarm or event.
Tagname	VT_BSTR	The Historian tag name associated with the alarm. This value is NULL unless the tag is also collected by Historian.
AlarmType	VT_BSTR	The alarm type: <ul style="list-style-type: none"> • Alarms: In Historian, the full life cycle of an alarm is stored as a single record in the alarm archive. • Alarm_History: The separate transitions for all alarms. One row per transition is returned. • Events: The simple and tracking events.
EventCategory	VT_BSTR	The OPC event category of the alarm or event.
Condition	VT_BSTR	The OPC condition of the alarm. Does not apply to event data. This value combined with the Source value comprises an alarm.
SubCondition	VT_BSTR	The OPC subcondition of the alarm. Does not apply to event data. This value represents the state of the alarm.
StartTime	VT_DBTimeStamp	The start time or timestamp of the alarm or event.
EndTime	VT_DBTimeStamp	The end time of the alarm. Does not apply to event data.

Table 402. ihAlarms Table (continued)

Column Name	Data Type	Description
AckTime	VT_DB- TimeS- tamp	The time the alarm was acknowledged. Does not apply to event data.
Microsec- onds	VT_I4	The microsecond portion of the date and time.
Message	VT_BSTR	The message attached to the alarm or event.
Acked	VT_BOOL	Stores the acknowledgement status of the alarm. If the alarm is acknowledged, this is set to <code>TRUE</code> .
Severity	VT_I4	The severity of the alarm or event. Stored as an integer value with a range of 1–1000.
Actor	VT_BSTR	The operator who acknowledged the alarm, or caused the tracking event.
Quality	VT_- VARIANT	The quality of the alarm or event. Stored as a string, with values of <code>GOOD</code> or <code>BAD</code> .
TimeZone	VT_BSTR	The type of time zone used: <ul style="list-style-type: none"> • Client • Server • Explicit bias number (number of minutes from GMT)
Daylight- SavingTime	VT_BOOL	Indicates whether Daylight Saving Time logic should be applied to timestamps.
RowCount	VT_I4	The maximum number of rows returned by the current query.
User-De- fined Variable #X	VT_- VARIANT	User-defined variables. This is a dynamic list of columns that varies based on the collectors running on the Historian system.

**Note:**

Additional fields may be added by third-party products such as iFIX. Please consult the relevant product documentation for further information.

ihAlarms Examples

Example 1: Show All Alarms for the Last Two Hours, Including Vendor Attributes

```
SELECT * FROM ihAlarms

SELECT * FROM ihAlarms WHERE alarmtype = alarms //same as above
```

Example 2: Show Alarm History

```
SELECT * FROM ihAlarms WHERE alarmtype = alarm_history
```

Example 3: Show Tracking and System Events

```
SELECT * FROM ihAlarms WHERE alarmtype = events
```

Example 4: Return All Closed Events and Associated Tag Data

```
SELECT

alarmid, ihalarms.tagname, ihalarms.starttime, ihalarms.endTime, ihrawdata.timestamp, ihrawdata.value

FROM ihalarms, ihrawdata

WHERE ihalarms.tagname=ihrawdata.tagname

AND ihalarms.starttime <= ihrawdata.timestamp

AND ihalarms.endtime >= ihRawdata.timestamp

AND ihalarms.subcondition == "OK"

OR ihalarms.quality = "Bad"

ORDER BY ihalarms.starttime
```



Note:

When you join data from the ihRawData and ihAlarms tables, be sure to specify a timestamp range.

Example 5: Return All Open Alarms and Associated Tag Data

```
SELECT

alarmid, ihalarms.tagname, ihalarms.starttime, ihalarms.endTime, ihrawdata.timestamp, ihrawdata.value

FROM ihalarms, ihrawdata

WHERE ihalarms.tagname=ihrawdata.tagname

AND ihalarms.starttime <= ihrawdata.timestamp

AND ihalarms.endtime >= ihRawdata.timestamp

AND ihalarms.subcondition <> "OK"

AND ihalarms.quality = "Good"
```

```
ORDER BY ihalarms.starttime
```

**Note:**

When you join data from the `ihRawData` and `ihAlarms` tables, be sure to specify a timestamp range.

ihEnumeratedSets Table

The `ihEnumeratedSets` table contains information about enumerated sets that are defined in the system. The following table describes the columns of the `ihEnumeratedSets` table.

Table 403. ihEnumeratedSets Table

Column Name	Data Type	Description
SetName	VT_BSTR	The name of the set.
Description	VT_BSTR	The description of the set.
NumberOfStates	VT_I4	The number of states a set contains.
NumberOfTag-References	VT_I4	The number of tags with which a set is associated.
SetDataType	VT_BSTR	The data type of the set.
Administrator-SecurityGroup	VT_BSTR	The security group to which the set belongs.
LastModified-User	VT_BSTR	Indicates which user last modified the set.
LastModified-Time	VT_DB-TimeStamp	Indicates the last time the set was modified.
RowCount	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned.

ihEnumeratedSets Examples

Sample SQL statements for the `ihEnumeratedSets` table are outlined in the following examples.

Example 1: Retrieve All Sets By Using Integer States

```
SELECT * FROM ihEnumeratedSets
WHERE SetDataType='integer'
```

Example 2: Retrieve a Set By Name From Sets

```
SELECT * FROM ihEnumeratedSets
WHERE setname like PLC1
```

ihEnumeratedStates Table

The `ihEnumeratedStates` table contains information about enumerated sets that are defined in the system. The following table describes the columns of the `ihEnumeratedStates` table.

Table 404. ihEnumeratedStates Table

Column Name	Data Type	Description
SetName	VT_BSTR	The name of the set.
Description	VT_BSTR	The description of the set.
NumberOfStates	VT_I4	The number of states a set contains.
NumberOfTag-References	VT_I4	The number of tags with which a set is associated.
SetDataType	VT_BSTR	The data type of the set.
Administrator-SecurityGroup	VT_BSTR	The security group to which the set belongs.
LastModified-User	VT_BSTR	Indicates which user last modified the set.
LastModified-Time	VT_DB-TimeStamp	Indicates the last time the set was modified.
RowCount	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned.

ihEnumeratedStates Examples

Sample SQL statements for the `ihEnumeratedStates` table are outlined in the following examples.

Example 1: Retrieve All States That Belong to a Specific Set

```
SELECT * FROM ihEnumeratedStates
WHERE setname=plcset1 order by statelowvalue ascending
```

Example 2: Retrieve All States From a Specific Set

```
SELECT * FROM ihEnumeratedStates
WHERE setname = 'setname'
```

ihUserDefinedTypes Table

The `ihUserDefinedTypes` table contains information about user-defined data types in the system.

Use this table to see the set of types and get information about each field in the data type.

The following table describes the columns of the `ihUserDefinedTypes` table.

Table 405. ihUserDefinedTypes Table

Column Name	Data Type	Description
TypeName	VT_BSTR	The name of the user-defined type.
DataType	VT_BSTR	The data type of the user-defined type.
Description	VT_BSTR	The description of the user-defined type.
StoreField- Quality	VT_BOOL	Indicates whether the field-level quality is stored.
NumberOfFields	VT_I4	The number of fields a user-defined type contains.
NumberOfTag- References	VT_I4	The number of tags with which a user-defined type is associated.
Administrator- SecurityGroup	VT_BSTR	The security group to which the user-defined type belongs.
LastModified- User	VT_BSTR	Indicates which user last modified the user-defined type.

Table 405. ihUserDefinedTypes Table (continued)

Column Name	Data Type	Description
LastModified- Time	VT_DB- TimeS- tamp	Indicates the last time the user-defined type was modified.
RowCount	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned.

ihUserDefinedTypes Examples

Sample SQL statements for the `ihUserDefinedType` table are outlined in the following examples.

Example 1: Retrieve All User-Defined Types

```
SELECT * FROM ihuserdefinedtypes
```

Example 2: Retrieve a User-Defined Type By Name

```
SELECT * FROM ihuserdefinedtypes WHERE typename LIKE New
```

ihFields Table

The `ihFields` table contains information about field elements that are specified in user-defined data types. The following table describes the columns of the `ihFields` table.

Table 406. ihFields Table

Column Name	Data Type	Description
TypeName	VT_- BSTR	The name of the user-defined type.
FieldName	VT_- BSTR	The name of the field.
Descrip- tion	VT_- BSTR	The description of the field.
FieldVal- ueDataType	VT_- BSTR	The data type of the field.

Table 406. ihFields Table (continued)

Column Name	Data Type	Description
Master-Field	VT_BOOL	Indicates whether the field is a master field.
RowCount	VT_I4	Indicates the maximum number of rows that can be returned. A value of 0 indicates that there is no limit to the number of rows returned.

ihFields Examples

Sample SQL statements for the `ihFields` table are outlined in the following examples.

Example: Retrieve All Fields for a Specific Type

```
SELECT * FROM ihfields WHERE typename='MyUserDefinedType'
```

Chapter 39. The Excel Add-In for Historian

Overview of the Excel Add-In for Historian

The Excel Add-In for Historian enhances the power and benefits of using the Historian data archiving and retrieval system.

Features:

- You can add tags to Historian by generating a tag worksheet using the standard Excel tools, editing the parameters, and then importing the information in bulk directly into Historian.
- You can export tag parameters from Excel, make bulk changes using similar techniques, and then import the changes back into Historian.
- You can retrieve selected data from any archive file and include it in a customized report.
- You can plot the data in any of the standard chart formats.
- You can calculate derived variables from raw data values.
- You can perform mathematical functions to smooth or characterize data.
- You can import, export, and modify tags, data, and messages – all with familiar Excel commands, macros, and computational techniques.
- You can create dynamic reports that you can share among users.

Excel Add-In window Conventions

The Excel Add-In uses several conventions in its windows that allow you to take full advantage of the features of the Historian Excel Add-In:

- You can select tags, times, and events either by cell references or by manually entering the values.
- Many windows support selecting multiple statistics or attributes. You can select multiple items in a list using one of the following methods:
 - Dragging the mouse over multiple items.
 - Pressing the Shift key and selecting the ends of a contiguous range.
 - Pressing the Control key and selecting multiple individual items.
- Specifying an output cell is optional. If you do not specify an output cell, the active cell is used as the starting point for output. When you specify an output cell, that cell is used as the starting point for output. If you select a range for an output cell, the top left cell in the range is used as the starting point for output.
- Specifying an output range determines how many data points are retrieved from a given query. It is important for these functions to specify whether you want the data points to be sorted in ascending or descending order by selecting the appropriate option.

- When you specify an output range or an output cell, ensure that the active cells are not the same cells that you specified with tag name cell references. Otherwise, it will lead to circular cell referencing and incorrect values.
- Specifying data retrieval into rows or columns determines how multiple attributes or statistics are displayed in the worksheet.
- Specifying data retrieval into rows or columns only applies when the window inserts a single function into the worksheet. When you select a multi-cell output range, the orientation of that range determines whether the requested data is returned into rows or columns.
- Excel does not support the use of the right and left arrow keys of the keyboard to move between characters in text boxes and fields in the windows.
- If no parameters in an Excel formula change, the formula does not recalculate unless you edit the formula. For example, if you change a Hi Scale value from 100 to 50 and then import a tag, the Hi Scale field will still display 100 when looking at the tag information.
- When retrieving data, leave at least one blank line at the top of the output display for the column header labels. If you do not, the header labels will not appear.
- When you retrieve data for more than one tag, if you choose to display the timestamp in the output, then the timestamp will be displayed only once and the parameter values of the selected tags will be shown based on the orientation selected.
- In several fields, an underscore appears at the right side of the field. If you select the underscore, the window instantly changes to a minimized display. You can return to the original display by selecting the box again. The purpose of this feature is to allow you to see an unobstructed view of your worksheet or other windows as you work your way through the window and to allow you to select a cell or range of cells in the worksheet.

Setting Up

Install the Historian Excel Add-in Using the Installer

Install one of the following 32-bit or 64-bit Microsoft® Excel® applications:

- Microsoft® Excel® 2019
- Microsoft® Excel® 2016
- Microsoft® Excel® 2013
- Microsoft® Excel® 2010

You can install Excel Add-In separately or during Client Tools installation. This topic describes how to install Excel Add-In separately using the installer. You can also [install it at a command prompt \(on page](#)

195). However, if installing via a command prompt, do not install the Excel Add-In on the machine that you have installed the Historian Administrator or data archiver.

1. Run the `InstallLauncher.exe` file.
2. Select **Install Excel Add-in for Historian**.

The installer runs through the installation steps.



Note:

If using certain versions of Windows (like Windows 10 or Windows 2019), you may receive an error message, stating that some of the DLL files are not registered. You can ignore these messages.

3. When prompted to reboot your system, select **Yes**.

Excel Add-In is installed.

[Activate Excel Add-In \(on page 197\)](#).

Install the Historian Excel Add-in at a Command Prompt

1. Install one of the following 32-bit or 64-bit Microsoft® Excel® applications:
 - Microsoft® Excel® 2019
 - Microsoft® Excel® 2016
 - Microsoft® Excel® 2013
 - Microsoft® Excel® 2010
2. [Install Excel Add-in using the installer \(on page 195\)](#) on your machine:
 - a. Open the Command Prompt as an Administrator. (From the Start menu, right-click the Command Prompt app, and select Run as Administrator.)
 - b. On the Historian install media, navigate to the Excel folder.
 - c. Run the following command line: `setup.exe -r`.
 - d. When the install runs, select the Excel option and leave the other options greyed out as they cannot be removed.

When you run this install, a template file named `setup.iss` is created at `C:\Windows`. This file stores the installation options that you have provided during the installation.

After completing the installation, you can then use this `.iss` file to install Excel Add-in at a command prompt on other machines.

On the other Client machine where you want to install the Excel Add-in, place a copy of the **setup.iss** on the local directory and open a Command Prompt (Run as Administrator). Run the silent install with following command:

```
setup.exe /s
```

If your iss file is not called **setup.iss** or is in different directory than setup.exe you need to add the flag: /f1. For example:

```
setup.exe /s /sms /f1"C:\Temp\setup.iss
```

Wait for few minutes (probably 3-5 minutes) for the install to complete.

You can install Excel Add-In separately or during Client Tools installation. However, do not install Excel Add-In on the machine on which you have installed Historian Administrator or data archiver.

1. Copy the `setup.iss` file to each machine on which you want to install Excel Add-in at a command prompt.
2. In the folder that contains the `setup.iss` file, run the following command: `setup.exe /s /sms`
The installer runs through the installation steps.



Note:

If using certain versions of Windows (like Windows 10 or Windows 2019), you may receive an error message, stating that some of the DLL files are not registered. You can ignore these messages.

3. When prompted to reboot your system, select **Yes**.

Excel Add-In is installed.


[Activate Excel Add-In \(on page 197\)](#).

Activate Excel Add-In

[Install Excel Add-In \(on page 195\)](#).

1. Open a new Microsoft Excel worksheet.
2. Select **File > Options**.
The **Excel Options** window appears.
3. Select **Add-Ins**.
4. In the **Manage** box, select **Excel Add-ins**, and then select **Go**.


The **Add-Ins** window appears.



5. Select the **Proficy Historian Add-In** and **Proficy_Historian_Helper** check boxes, and then select **OK**.

If the **Proficy Historian Add-In** and **Proficy_Historian_Helper** check boxes do not appear, select **Browse** to locate the `Historian.xla` file for the check boxes to appear. This file is created if you have installed Microsoft Excel after installing Excel Add-In. By default, the `Historian.xla` file is located in the `C:\Program Files\Proficy\Historian` or `C:\Program Files (x86)\Proficy\Historian` folder.

Excel Add-In is now ready to use and the **Proficy Historian** menu is now available in the Microsoft Excel toolbar.



Querying Data

Query Current Values

You can query the following types of data using the add-in:

- **Current values:** Retrieves the most recently updated value of one or more tags or process variables.



Note:

If you attempt to perform a query with two worksheets open, the add-in may become unstable and unresponsive. This is a known Microsoft Excel issue. To avoid this issue, work with only one Excel spreadsheet at a time.

- **Raw data:** Raw data values are the values actually stored in the archive, after applying collector and archive compression, but before applying any interpolation, smoothing, or other signal processing calculations. Querying raw data retrieves these values for a selected tag.

In addition, you can query [filtered data \(on page 2732\)](#) and [calculated data \(on page 2734\)](#).

1. Open an Excel worksheet.
2. If you want to query current values, select **Historian > Query Current Value**. If you want to query raw data, select **Historian > Query Raw Data**.

The **Historian Current Value Query** or the **Historian Raw Data Query** window appears.

3. Select the Historian server from the drop-down list box. If you do not specify a server, the default server is considered.



Tip:

To set the selected server as default, ensure that the **Set Server to Default** option is enabled.

4. Select a tag on your worksheet, and then place the cursor in the **Tag Name** field.
Optionally, you can select the tag from the **Advance Tag Search** window. For more information, refer to [Advanced Tag Search \(on page 2744\)](#).
The tag name is automatically entered. You can also enter a tag name manually in the **Tag Name** field.
5. Enter values as described in the following table.

Field	Description
Query Type	Select the type of data search: <ul style="list-style-type: none"> ◦ By Time: Using this option, you can search for data values between a start time and an end time. You can also use relative time entries to this field. ◦ By Number Forward: Using this option, you can search for a number of values after a specified time. Enter values into the After Time and Number of Values fields. ◦ By Number Backward: Using this option, you can search for a number of values before a specified time. Enter values in the Values Before Time and Number of Values fields.
Query Criteria String	Enter the query criteria along with the # symbol. For example, if the query criteria string is to retrieve only good data quality values, enter #ONLYGOOD. For more information, see Query Modifiers (on page 2738) .
Output Display	Select one or more parameters for the output.
Output Range	Select a range of cells in a single row or column to determine where the returned data is placed.
Rows or Columns	Select either Columns or Rows for the output display. Selecting Columns displays a table of values with parameters arranged in columns with header labels at the top. Selecting Rows rotates the table 90 degrees.
Ascending or Descending	Specify the order of the retrieved data.

6. Select **OK**.

The query returns a number of data points based on the number of rows or columns specified in the output range. If all the data points do not appear, select enough rows or columns to display all the data.



Note:

For an array tag, each element is displayed in separate rows with the tag name and index.

Query Filtered Data

You can filter tag data based on a specific batch ID, lot number, or product code. You can also filter data that meets certain limits (for example, all the data points in which the temperature exceeds a certain value).

When querying filtered data, you can use a **Filter Expression** instead of **FilterTag**, **FilterMode**, and **FilterValue** parameters. You can use multiple filter conditions in the filter expression. For more information and examples on filter expression, refer to *Advanced Topics*.



Note:

Do not use the **Desc** option for the **Output Range** in the **Filtered Data Query** window. Using this option may cause the Excel Add-In to become unstable. If you use this option and find that Excel is unstable, try minimizing the Excel application window, expose the **Filtered Data Query** window, and close the window. Excel should then function normally.

1. Open an Excel worksheet.
2. Select **Historian > Query Filtered Data**.
The **Historian Filtered Data Query** window appears.
3. Select the Historian server from the drop-down list box. If you do not specify a server, the default server is considered.



Tip:

To set the selected server as default, ensure that the **Set Server to Default** option is enabled.

4. Select a tag on your worksheet, and then place the cursor in the **Tag Name** field.
If entering multiple tag names manually, separate each tag name with a colon. If your tag name has a colon within it, then select the tag names via cell references only.

Do not use wildcards in this field. If you use a tag mask instead of a tagname, Historian only returns the first possible match.

Optionally, you can select the tag from the **Advance Tag Search** window. For more information, refer to [Advanced Tag Search \(on page 2744\)](#).

The tag name is automatically entered. You can also enter a tag name manually in the **Tag Name** field.

5. Enter values as specified in the following table.

Field	Description
Query Time	Enter the start time and end time for the query. You can also use relative time entries.
Query Criteria String	Enter the query criteria along with the # symbol. For example, if the query criteria string is to retrieve only good data quality values, enter #ONLYGOOD. For more information, see Query Modifiers (on page 2738) .
Sampling Type	Select the sampling type. For information, refer to Sampling Types (on page 2781) .
Calculation Field	Select a calculation algorithm. This field is enabled only if you select Calculated Sampling in the Sampling Type field.
Sampling Interval	<p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ By Interval: Using this option, you can query the data for a specific interval. option displays two entry fields, and . Enter values in both. For example, if you want to query the data for 10-minute intervals, enter 10 in the Interval field, and select Minutes in the Time Unit field. ◦ By Samples: Using this option, you can query the data for a specific number of samples. For example, to query 100 samples, enter 100 in the Number of Samples field.
State Value	Enter the state value. This field is enabled only if you selected Calculated in the Sampling Type field and if you selected State Count or State Time in the Calculation Field field.
Output Display	Select one or more parameters for the output.
Filter Definition	Enter the filter parameters in the available fields.
Output Range	Select a range of cells in a single row or column to determine where the returned data is placed.
Rows or Columns	Select either Columns or Rows for the output display. Selecting Columns displays a table of values with parameters arranged in columns with header labels at the top. Selecting Rows rotates the table 90 degrees.
Ascending or Descending	Specify the order of the retrieved data.

6. Select **OK**.

The query returns a number of data points based on the number of rows or columns specified in the output range. If all the data points do not appear, select enough rows or columns to display all the data.

**Note:**

- For an array tag, each element is displayed in separate rows with the tag name and index.
- The **TagStats Calculation** mode is not supported.

Querying Calculated Data

You can query data that is the result of performing calculations on raw data.

**Note:**

If you attempt to perform a query with two worksheets open, the add-in may become unstable and unresponsive. This is a known Microsoft Excel issue. To avoid this issue, work with only one Excel spreadsheet at a time.

1. Open an Excel worksheet.
2. Select **Historian > Query Calculated Value**.
The **Historian Calculated Query** window appears.
3. Select the Historian server from the drop-down list box. If you do not specify a server, the default server is considered.

**Tip:**

To set the selected server as default, ensure that the **Set Server to Default** option is enabled.

4. Select a tag on your worksheet, and then place the cursor in the **Tag Name** field.
Optionally, you can select the tag from the **Advance Tag Search** window. For more information, refer to [Advanced Tag Search \(on page 2744\)](#).
The tag name is automatically entered. You can also enter a tag name manually in the **Tag Name** field.
5. Enter values as described in the following table.

Field	Description
Query Time	Enter the start time and end time for the query. You can also use relative time entries.
Query Criteria String	Enter the query criteria along with the # symbol. For example, if the query criteria string is to retrieve only good data quality values, enter #ONLYGOOD. For more information, see Query Modifiers (on page 2738) .
Sampling Type	Select the sampling type. For information, refer to Sampling Types (on page 2781) .
Calculation	Select a calculation algorithm. This field is enabled only if you select Calculated Sampling in the Sampling Type field.
Sampling Interval	<p>Select one of the following options:</p> <ul style="list-style-type: none"> ◦ By Interval: Using this option, you can query the data for a specific interval. option displays two entry fields, and . Enter values in both. For example, if you want to query the data for 10-minute intervals, enter 10 in the Interval field, and select Minutes in the Time Unit field. ◦ By Samples: Using this option, you can query the data for a specific number of samples. For example, to query 100 samples, enter 100 in the Number of Samples field.
State Value	Enter the state value. This field is enabled only if you selected Calculated in the Sampling Type field and if you selected State Count or State Time in the Calculation Field field.
Output Display	Select one or more parameters for the output.
Output Range	Select a range of cells in a single row or column to determine where the returned data is placed.
Rows or Columns	Select either Columns or Rows for the output display. Selecting Columns displays a table of values with parameters arranged in columns with header labels at the top. Selecting Rows rotates the table 90 degrees.
Ascending or Descending	Specify the order of the retrieved data.

6. Select **OK**.

The query returns a number of data points based on the number of rows or columns specified in the output range. If all the data points do not appear, select enough rows or columns to display all the data.



Note:

- For an array tag, each element is displayed in separate rows with the tag name and index.
- The **TagStats Calculation** mode is not supported.

Query Alarms and Events Data Using the Excel Add-In

Querying Alarms and Events data in the Excel Add-In retrieves alarms and events data according to your Query Criteria. Three query types are available: Alarm, Alarm history, and Events.



Note:

You cannot use an OPC alarms and events server with FIX32 SCADA systems. To collect alarm data from these systems, you can use a proxy for alarms through an iFIX node with an OPC alarms and events server. The OPC Classic Alarms and Events collector of Proficy Historian can then collect the data. For more information, refer to [Using the OPC AE Collector with FIX32 SCADA Systems \(on page 1225\)](#).

1. Open an Excel worksheet.
2. Select **Historian > Query Alarms & Events**.
The **Query Alarms & Events** window appears.
3. Enter values as described in the following table.

Field	Description
Server	Select the SQL server that contains the alarms and events data.
Query Type	Select one of the following values: <ul style="list-style-type: none"> ◦ Alarms: In Historian, an alarm's entire life cycle is stored as a single record in the alarm archive. Thus, when retrieving from the archive, the entire life cycle of an alarm will be returned in a single record. ◦ Alarm History: Each change in the alarm's state will be returned in a single record. ◦ Events: One row per event is returned.

Field	Description
Query Criteria	Enter the criteria that you want to use in the query. For example, you may want to include alarms where the Alarm ID is equal to a specific Alarm ID occurring after a specific start time. In addition, you can specify which attributes must be displayed and how the results must be sorted in the spreadsheet.
Output Range	Select a range of cells in a single row or column to determine where the returned data must be placed.
Output Orientation	Select either Columns or Rows for the output display. Selecting Columns displays a table of values with parameters arranged in columns with header labels at the top. Selecting Rows rotates the table 90 degrees.
Maximum Results	Enter the maximum number of results for the query to return. <div data-bbox="669 892 1421 1071" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: An Excel spreadsheet can display up to 255 columns and 32,767 rows. </div>
Output Display	Specify the attributes that you want to display in the spreadsheet.
Output Sorting	Select the parameter using which you want to sort the results: <ul style="list-style-type: none"> ◦ Alarm Time: Sorts the data by the start time. The results appear in the reverse chronological order. ◦ Custom Sort: Allows you to select the field using which you want to sort the results. ◦ None: The results are not sorted at all. They are returned in the order they are received from the alarms and events database.

4. Select **OK**.

The query results appear.

Modify a Query

You can change query parameters such as tag name, start time, end time, and so on. You cannot, however, narrow down the output range. For example, you cannot reduce the number in the

NumberOfSamples field, or you cannot change the **Output Orientation** to values that result in fewer rows or columns.

1. Open an Excel worksheet.
2. Access the query that you want to modify.
3. In the **Add-In** drop-down list box, select **Edit Query** or  icon. Or you can double-click any cell that has the query formula.
The **Edit Query** window appears.
4. Modify the query, and then select **OK**.

Query Modifiers

Query modifiers are used to retrieve data that has been stored in the archive. They are used along with sampling and calculation modes to get a specific set of data.

If you want to use a query modifier, when you create or modify a query, in the **Query Criteria String** field, enter #, and then enter the query modifier. For example, if you want to retrieve only good data quality values, enter #ONLYGOOD.

Query Modifier	Results
ONLYGOOD	<p>Excludes bad and uncertain data quality values from retrieval and calculations.</p> <p>Although you can use this modifier with any sampling or calculation mode, it is most useful with raw and current value queries. All the calculation modes such as minimum or average exclude bad values by default, so this modifier is not required in those cases.</p>
INCLUD- EREPLACED	<p>Normally, when you query raw data, any values that have been replaced with a different value for the same timestamp are not returned.</p> <p>The INCLUDEREPLACED modifier is used to specify that you want replaced values to be returned, in addition to the updated values. However, you cannot query only the replaced data and the retrievable values that have replaced the other values. You can query all currently visible data and get the data that has been replaced.</p> <p>This modifier is only useful with the rawbytime or rawbynumber retrieval. Do not use it with any other sampling or calculation mode.</p>

Query Modifier	Results
<p><code>INCLUDED- ELETED</code></p>	<p>Retrieves the value that was previously deleted. Data that has been deleted from the archiver is never actually removed but is marked as hidden. Use the <code>INCLUDED- ELETED</code> modifier to retrieve the values that were deleted, in addition to the current values.</p> <p>This modifier is only useful with the <code>rawbytime</code> or <code>rawbynumber</code> retrieval. Do not use it with any other sampling or calculation mode.</p>
<p><code>ONLYIF- CONNECTED</code> and <code>ON- LYIFUPTO- DATE</code></p>	<p>Retrieve bad data if the collector is not currently connected and sending data to the archiver. You can use these modifiers with any sampling or calculation mode.</p> <p>The bad data is not stored in the IHA file but is only returned in the query. If the collector reconnects and flushes data and you run the query again, the actual stored data is returned in the following situations:</p> <ul style="list-style-type: none"> • Collector loses connection to the archiver • Collector crashes • Collector compression is used and no value exceeds the deadband
<p><code>ONLYRAW</code></p>	<p>Retrieves only the raw samples. It does not add interpolated or lab sampled values at the beginning of each interval during calculated retrieval such as average, minimum, or maximum.</p> <p>Normally, a data query for minimum value will interpolate a value at the start of each interval and use that together with any raw samples to determine the minimum value in the interval. Interpolation is necessary because some intervals may not have any raw samples stored.</p> <p>Use this query modifier with calculation modes only, not with raw or sampled retrieval like interpolated modes.</p>
<p><code>LABSAM- PLING</code></p>	<p>Affects the calculation modes that interpolate a value at the start of each interval. Instead of using interpolation, lab sampling is used. When querying highly compressed data, you may have intervals with no raw samples stored.</p> <p>For example, an average from 2 pm to 6 pm on a one-hour interval will interpolate a value at 2 pm, 3 pm, 4 pm, and 5 pm, and uses those in addition to any stored samples to compute averages. When you specify <code>LABSAMPLING</code>, the lab sampling mode is used instead of the interpolated sampling mode to determine these hourly values. A lab sampled average is used when querying a tag that never ramps up but changes in a step pattern such as a state value or a set point. Use this query modifier with calculation modes only, not raw or sampled retrieval like interpolated modes.</p>

Query Modifier	Results
<p>ENUM- NATIVE- VALUE</p>	<p>Retrieves the native, numeric values such as 1 or 2 instead of string values such as on/off for the data that has enumerated states associated with it.</p> <p>You can use this modifier with any sampling or calculation mode.</p>
<p>INCLUDE- BAD</p>	<p>Normally, when you query calculated data from Historian, only good data quality raw samples are considered. INCLUDEBAD modifier includes bad data quality values in calculations.</p> <p>You can use this modifier with any sampling or calculation mode.</p>
<p>FILTERIN- CLUDEBAD</p>	<p>Normally, while filtering, we use only good data quality values. When we use FILTERINCLUDE- BAD, the bad data quality values are considered when filtering to determine time ranges. This modifier is not always recommended.</p>
<p>USE- MASTER- FIELDTIME</p>	<p>Returns the value of all the fields at the same timestamp of the master field time, in each interval returned. It is used only for the multi-field tags.</p>
<p>HON- ORENDTIME</p>	<p>Normally, a query keeps searching through archives until the required number of samples has been located, or until it gets to the first or last archive. However, there are cases where you would want to specify a time limit as well. For example, you may want to output the returned data for a RawByNumber query in a trend page, in which case there is no need to return data that would be off page.</p> <p>If you want to specify a time limit, provide an end time in your RawByNumber query and include the HONORENDTIME query modifier. Since RawByNumber has direction (backward or forward), the end time must be older than the start time for a backward direction or later than the start time for a forward direction. Use this query modifier only with the RawByNumber sampling mode.</p>
<p>EXAMINE- FEW</p>	<p>Queries using calculation modes normally loop through every raw sample, between the given start time and end time, to compute the calculated values.</p> <p>When using FirstRawValue, FirstRawTime, LastRawValue, and LastRawTime calculation modes, we can use only the raw sample near each interval boundary and achieve the same result. The EXAMINEFEW query modifier enables this. If you are using one of these calculation modes, you may experience better read performance using the EXAMINEFEW query modifier.</p> <p>Using this query modifier is recommended when:</p>

Query Modifier	Results
	<ul style="list-style-type: none"> • The time interval is great than 1 minute. • The collection interval is greater than 1 second. • The data node size is greater than the default 1400 bytes. • The data type of the tags is String or Blob. Query performance varies depending on all of the above factors. <p>Use this query modifier only with <code>FirstRawValue</code>, <code>FirstRawTime</code>, <code>LastRawValue</code>, and <code>LastRawTime</code> calculation modes.</p>

Access Archive Statistics

You can access a list of selected statistics about an archive file. You can specify the server, the archive file name, and the type of information you want to access (such as start time, end time, file name, target file size, current file size, current or read-only status, last backup time, and last backup users). You can also specify a range of cells for the display.

1. Open an Excel worksheet.
2. Select **Historian > Administration > List Archives**.
The **Historian Archive List** window appears.
3. Select a server from the drop-down list. If you do not specify a server, the default server is considered.
4. Enter values as described in the following table.

Field	Description
Archive Name	<p>Enter a archive name. Do not use wildcards in this field.</p> <div style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Tip: To return details for more than one item, specify a substring in the Archive Name field that exists in each archive you want listed. For example, if you have archive files named from <code>Hero5_-Archive001</code> to <code>Hero5_Archive010</code>, enter</p> </div>

Field	Description
	 Hero5_Archive to return the details for all those archives.
Output Display	Select one or more parameters for the output display.
Output Range	Select a range of cells in a single row or column to determine where the returned data is placed.

5. Select **Asc** or **Desc** to sort the archives in ascending or descending order.
6. Select either **Columns** or **Rows** for the output display.

 **Note:**
 When selecting multiple tags, the orientation of the return data is based on the orientation of the selected tags and the Row/Col selection is ignored.

7. Select **OK**.
 The statistics of the selected archives appear.

Access Collector Statistics

You can access a list of selected statistics of a collector instance. You can specify the server, the collector instance, and the type of information you want to access. You can also specify the range of cells for the display.

1. Open an Excel worksheet.
2. Select **Historian > Administration > List Collectors**.
 The **Historian Collector List** window appears.
3. Select a server from the drop-down list. If you do not specify a server, the default server is considered.
4. Enter values as described in the following table.

Field	Description
Collector Name	Enter a collector instance name. Do not use wildcards in this field.

Field	Description
	<div style="border: 1px solid #add8e6; border-radius: 10px; padding: 10px;">  Tip: To return details for more than one item, specify a substring in the Collector Name field that exists in each collector you want listed. For example, if you have collectors named from <code>Hero5_Collector0001</code> to <code>Hero5_Collector010</code>, enter <code>Hero5_Collector</code> to return the details for all those collectors. </div>
Output Display	Select one or more parameters for the output display.
Output Range	Select a range of cells in a single row or column to determine where the returned data is placed.

5. Select either **Columns** or **Rows** for the output display.



Note:

When selecting multiple tags, the orientation of the return data is based on the orientation of the selected tags and the Row/Col selection is ignored.

6. Select **OK**.

The statistics of the selected collector instances appear.

Managing Tags

Search for a Tag (Basic)

You can search for tags and perform actions on them.

This topic describes how to perform a basic search of tags. You can also [perform an advanced search \(on page 2744\)](#).

1. Open an Excel worksheet.
2. Select **Historian > Search Tags**.

The **Historian Tag Search** window appears.

3. In the **Server** field, select a server from the drop-down list. If you do not specify a server, the default server is considered.
4. In the **Tag Mask**, enter a wildcard character to search for tags (for example, *).
5. Select **Search**.

The **Historian Tag Search** window is populated with a tag list.

6. Move tags from the left section to the right section to add them to the search query.
7. Use the **Search Display** section to choose whether you want to display tag names or tag description. It also displays the number of tags returned.
8. Use the **Output With** to choose whether the output shows the names of the selected tags or the cell computation formulas.

You can use the **Output with Formula** to place a dynamic formula in the worksheet instead of just copying the selected tag names. When you do so, the list of tags returned are dynamic based on the tag mask criteria. This is useful when selecting a cell reference for the tag mask as opposed to typing in a tag mask directly in the window.

9. Use the **Output Range** field to determine where in the worksheet the output data must appear.
10. Use the **Output Display** section to select the type of data to be displayed.
11. Select **OK** to apply your choices and initiate the query.

A list of tags appears based on your search criteria.

Search for a Tag (Advanced)

You can search for tags and perform actions on them.

This topic describes how to perform a advanced search of tags. You can also [perform a basic search \(on page 2743\)](#).

When you perform an advanced search, the most recently used search criteria are saved in a file named `DefaultSearchCriteria.xml` in `c:\user- s\\AppData`. These criteria are automatically loaded into the window the next time you access the Excel worksheet. You can reuse or modify the criteria rather than entering them each time. If you want to reset your criteria, delete the XML file.

While performing an advanced search, you can:

- Add multiple search criteria.
- Modify the existing criteria.
- Delete the unwanted search criteria from the list.
- Save the criteria to a file and reuse it.
- View the details of a tag in the search results.

1. Open an Excel worksheet.
2. Select **Historian > Search Tags > Advanced Tag Search**.
3. In the **Tag Criteria** field, specify one or more [tag criteria \(on page 2784\)](#).
4. Provide values in the **Tag Criteria Value** field.
5. Select **Add Criteria**.

The criteria are listed in the **Search Criteria** section.
6. Select **Search**.

All tags that satisfy the query criteria are displayed in the **Available** section.
7. Move tags from the **Available List** section.
8. To modify the **Tag Criteria Value** already entered:
 - a. Double-click the criteria from the list.
 - b. Change the **Tag Criteria Value**.
 - c. Select **Update Criteria**. The criteria value is updated with the new value.
9. To delete the search criteria from the list, select the criteria from the list, and then select **Delete**.
10. To save a search criteria list to be reused:
 - a. Create your search criteria list.
 - b. Select **Save**.

The **Save As** window appears.
 - c. Enter the file name, and select **Save**.

Your criteria list is saved.
11. To load an existing criteria list:
 - a. Select **Load**.


The **Open** window appears.
 - b. Choose the XML file you saved earlier, and then select **Open**.

The criteria list is loaded to the **Advanced Tag Search** window.
12. To view the tag attributes, double-click the tag from the available section or from the selected section.

The **Tag Attributes** window appears with the attribute details.
13. Select **OK**.

Export Tags

You can export tags from a Historian server into an Excel worksheet or to another system (either local or remote). After you export tags into an Excel worksheet, you can [add/modify tags \(on page 2747\)](#) in bulk, and then [import them \(on page 2748\)](#).



Note:

You cannot enter more than 32,767 characters in a single cell in an Excel worksheet.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Export Tags**.
The **Export Tags from Historian** window appears.
3. Select a server from the drop-down list. If you do not select a server, the add-in uses the default server.
4. Enter values as described in the following table.

Field	Description
<p>Filter Criteria</p>	<p>Enter the name or description of the tag you want to export. You can use a tag mask to select a group of tags. To select a tag, use cell references instead of manually typing them.</p> <div data-bbox="873 1606 922 1656" data-label="Image"> </div> <p>Note: You cannot export multiple tags when tagnames are read from multiple cells. If you specify a range of tagnames to read from multiple cells in the Tag</p>

Field	Description
	 Mask or Tag Name(s) fields, only the first tag in the range will be exported.
Collector	Enter the collector name.
Data Type	Enter the data type.

5. Select one or more field names from the list in the right hand window. Always include tag names in the list of fields to export.
6. In the **Export Options** section, specify whether you want to export tags into a new Excel worksheet, a CSV file, or an XML file. If you select CSV or XML, you must also enter a path and file name for the destination file.
7. Select **OK**.
The data is exported.

Add/Modify Tags

Using the add-in, you can add tags to Historian or modify existing tags. To do so, include the tags in an Excel worksheet either automatically or manually, and then import them in bulk into Historian.

This can be a very convenient mechanism when you are working with large numbers of tags. If any conflicting names or parameters occur, an error occurs; you can then resolve the conflict and try again.

1. Create a tags worksheet in Excel either manually or automatically (using macros or any other tools).
Since Historian requires information about each tag that varies with the type of the tag, ensure that you have included all the required information in the worksheet before attempting to import it into Historian. To determine what specific tag information is required, refer to the documentation provided with your SCADA application.
2. [Import the tags into Historian \(on page 2748\)](#).



Note:

If any errors on the import occur, a window appears, specifying the issues encountered during the import. If an error occurs with any line of the import, the whole import is aborted.

Import Tags

In an Excel worksheet, [add/modify the tags that you want to import \(on page 2747\)](#).

Using the add-in, you can add tags to Historian or modify existing tags. To do so, include the tags in an Excel worksheet either automatically or manually, and then import them in bulk into Historian (either local or remote).

For example, with the Excel Add-In you can successfully import unsolicited tags without a calculation dependency (trigger), which you cannot do using Historian Administrator. Similarly, you can import circular references, which you cannot do using Historian Administrator.



Note:

Do not add or update the following spare configurations as the data may get corrupted or overwritten:

- The **Spare 1** field for OSI PI Distributor. OSI PI distributor reads data from the Historian tag displayed in the **Tag Source Address** field and sends it to the OSI PI tag name displayed in the **Spare 1** field.
- The **Spare 5** field for the Server-to-Server collector and the Server-to-Server distributor because it is only used for internal purposes.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Import Tags**.

A message appears.

3. Select **Yes** to initiate the operation.

A message appears, confirming that the import is complete.

4. Select **OK**.

If errors occur, a window appears detailing the issues encountered during the import. If an error occurs with any line of the import, the whole import operation is aborted.

If you export all the fields and attempt to import the read-only fields **LastModified** and **LastModifiedUser**, you may receive the following error message: Import failed, Error with Import Header. To avoid this issue, export the tags without selecting the read-only fields, and then import the tags.

Rename Tags

To rename a tag, you must be a member of the administrator's group with tag-level security.

When you rename a tag, you can choose between the following options:

- **Rename using an alias:** In this case, the old name is called the tag alias. You can retrieve tag data using the tag alias as well. When you copy a tag, the tag alias is captured as well to aid in an audit trail.
- **Rename permanently:** In this case, the old name is no longer captured. Therefore, you can create another tag with this old name. You cannot store and forward data using the old name. This implies that data for the tag is collected separately for the new name.

1. [Export the tags \(on page 2746\)](#) that you want to rename.



Important:

You must only include tag name in the list of fields to export.

2. In the Excel worksheet, to the right of the **Tagname** column, insert a column named **New Tagname**.
3. For each tag that you want to rename, enter the new name in the **New Tagname** column.



Important:

You must specify a tag name in all the rows of the **New Tagname** column. If you do not want to rename any of those exported tags, you must delete that row.

4. If you want to rename the tags permanently, to the right of the **New Tagname** column, insert a column named **Permanent Rename**.
5. For each tag that you want to rename permanently, enter `TRUE` in the **Permanent Rename** column. For the remaining tags, enter `FALSE`.
6. Select **Historian > Administration > Rename Tags**.
A message appears, asking you to confirm that you want to rename the tags.
7. Select **Yes**.
The tags are renamed.

Working with Array Tags

Historian allows you to store a set of values with a single timestamp and then read the elements back individually or as an array tag. In Historian, we can modify a tag to an array tag by specifying the `NumberOfElements` as `-1`. Where `NumberOfElements` indicates the tag is an array tag. If the `NumberOfElements` is `-1`, then the tag is an array tag.

Tags with zero `NumberOfElements` are not array tags. Since the size of the array is dynamic there is no single number of elements that can be returned. In Excel Add-in each element of the array tag is displayed in separate rows with tagname with index (`Tag-name[]`) and values. You can perform all operations that you use for a tag on an Array tag. You can export, import and query an array tag or an array element.

**Note:**

- Array tags do not support Enumerated set.
- **TagStats Calculation Mode** is not supported.

Importing and Exporting Data

Import Tag Data

The **Import Data** command is the converse of the **Export Data** command. It moves selected information from your current worksheet into the specified Server in the same way the **Import Tags** command functions.

**Note:**

If you use the **Active Hours** setting while importing data using the Excel Add-In, note that if the first tags imported are not within the **Active Hours** settings, no subsequent tags will be returned on that import (even if they are within the set active hours).

1. Select **Administration** and then select **Import Data** from the **Historian** menu.
A message box appears.
2. Select **Yes** to initiate the operation. If successful, a window appears confirming the completion of the import function.
Select **OK** to close the window. If errors occur on the import, a window appears detailing the issues encountered in the import. If an error occurs in any line of the import, the whole import is aborted.

Import Alarms and Events Data into a Spreadsheet

Using the Historian Excel add-in, you can import alarms and events data into a spreadsheet. It helps you include alarms and events data into the Historian archive that is not normally collected by Historian or when you are migrating data from an older system into Historian.

**Note:**

- The Excel worksheet must contain at least the source and timestamp columns.
- If an error occurs while importing data, the whole operation is aborted.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Import Alarms**.
The alarms and events data is imported.

Export Tag Data

The Export Data function allows you to move values from the Historian Server to your Excel worksheet or to another system in the same way you move tag information with Export Tags.

**Note:**

Before importing or exporting tags, data, or messages, you should be aware of a convention used with the Historian application. The Server is the reference point for all import and export functions. If you want to move tag information from the Server into your worksheet, you must use the **Export Tags** command. Conversely, if you want to move data from your worksheet to the server, you must use the **Import Data** command.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Export Raw Data**.
The **Export Data from Historian** window appears.
3. If you want to specify a server, select a server from the drop down list. If you do not specify a server, the Add-In uses the default server.
4. Select a tag on your worksheet or enter the tag names manually.

**Note:**

If your tag name has a colon within it, then you should select the tag names via cell references only.

5. Optionally, you can select the tag name from the **Advance Tag Search** window.
See [Search for a Tag \(Advanced\) \(on page 2744\)](#)
6. In the **Query Criteria String**, enter the query criteria along with the # symbol.

For example, if the query criteria string is to retrieve only good data quality values, then you should specify `#ONLYGOOD` as the **Query Criteria String**. See [Query Modifiers \(on page 2738\)](#).

7. In the **Query Time** section enter values of time in the **Start Time** and **End Time** fields.
You can also use relative time entries to this field. See [Relative Time Entries \(on page 2777\)](#).
8. In the **Sampling Type** section, select a type from the drop-down list.
9. The **Calculation** field is active only after you select **Calculated Sampling** as the **Sample Type**.
Select a **Calculation Algorithm** type from the drop-down list.
10. In the **Sampling Interval** section, select either the **By Interval** or **By Samples** option.
The **By Interval** option displays two entry fields, **Interval** and **Time Unit**. Enter values in both. For example, to sample at 10 minute intervals, enter 10 in the interval field and select Minutes in the Time Unit field. The **By Samples** option displays a **Number of Samples** field.

To specify a number of samples for the data query, enter a number in this field. For example, to query 100 samples, enter 100 in this field.
11. In the **Filter Definition** section, enter filter parameters in the fields for **Filter Tag**, **Filter Comparison**, **Include Date Where Value Is Equal To**, and **Include Times**.
These fields are optional. If you do not enter any values, the query returns all values without filtering.
12. In the **Fields To Export** section, select one or more fields.
To select multiple individual tags, press the **Control** key and select the tagnames. To select a sequence of tags, press the **Shift** key and select the first and last tagname of the sequence.
13. In the **Export Options** section, select one of three options:
 - **To New Worksheet**
 - **To CSV File** or
 - **To XML File**
14. If you select **To CSV File** or **To XML File**, you must enter a file name and path for the new file in the **File Name** field.
15. Select **OK** to initiate the export. Select **Cancel** to abort the operation and close the window.

Export Alarms and Events Data from a Spreadsheet

Using the Historian Excel add-in, you can export alarms and events data into a new worksheet or into a CSV or an XML file.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Export Alarms**.
The **Historian Alarm Export** window appears.
3. Enter values as described in the following table.

Field	Description
Server	Select the SQL server that contains the alarms and events data.
Query Type	Select one of the following values: <ul style="list-style-type: none"> ◦ Alarms: In Historian, an alarm's entire life cycle is stored as a single record in the alarm archive. Thus, when retrieving from the archive, the entire life cycle of an alarm will be returned in a single record. ◦ Alarm History: Each change in the alarm's state will be returned in a single record. ◦ Events: One row per event is returned.
Query Criteria	Enter the criteria that you want to use in the query. For example, you may want to include alarms where the Alarm ID is equal to a specific Alarm ID occurring after a specific start time. In addition, you can specify which attributes must be displayed and how the results must be sorted in the spreadsheet.
Output Range	Select a range of cells in a single row or column to determine where the returned data must be placed.
Output Orientation	Select either Columns or Rows for the output display. Selecting Columns displays a table of values with parameters arranged in columns with header labels at the top. Selecting Rows rotates the table 90 degrees.
Maximum Results	Enter the maximum number of results for the query to return. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: An Excel spreadsheet can display up to 255 columns and 32,767 rows. </div>
Output Display	Specify the attributes that you want to display in the spreadsheet.
Output Sorting	Select the parameter using which you want to sort the results:

Field	Description
	<ul style="list-style-type: none"> ◦ Alarm Time: Sorts the data by the start time. The results appear in the reverse chronological order. ◦ Custom Sort: Allows you to select the field using which you want to sort the results. ◦ None: The results are not sorted at all. They are returned in the order they are received from the alarms and events database.
Export Options	<p>Select the format in to which you want to export the data:</p> <ul style="list-style-type: none"> ◦ To New Worksheet: Exports the data to a new Excel worksheet. ◦ To CSV File: Exports the data with comma separated values to a new file. ◦ To XML File: Exports the data to a new XML file.

4. Select **OK**.

The data is exported.

Working with Messages

Search for Messages

You can search the archive for selected types of messages generated during a specific time period and to display selected fields from those messages. When you do so, a dynamic formula is placed in the worksheet, using which you can build a dynamic message report that you can build, save, and reuse.

1. Open an Excel worksheet.

2. Select **Historian > Administration > Search Messages**.

The **Historian Message Search** window appears.

3. Select a server from the drop-down list. If you do not specify a server, the default server is used.

4. Enter values as described in the following table.

Field	Description
Topic	Select one of the message types from the drop-down list.
Query Times	Enter values for the start time and end time.

Field	Description
Search String	Enter a search string for the text of messages. You need not enter * for wildcards.
Output Display	Select one or more parameters for the output display. Select a name to select it.
Output Range	Select a range of cells in a single row or column to determine where the returned data is placed.
Asc or Desc	Specify whether you want to sort the messages in ascending or descending order. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;">  Note: When selecting multiple tags, the orientation of the return data is based on the orientation of the selected tags and the Row/Col selection is ignored. </div>

5. Select **OK**.

A list of messages appear based on the search criteria.

Import Messages

You can import all the messages from an Excel worksheet into a Historian server. You can, however, only add messages to Historian; you cannot modify or remove them.

1. Open an Excel worksheet.

2. Select **Historian > Administration > Import Messages**.

A message appears, asking you to confirm that you want to import messages.

3. Select **Yes** to execute the import. A window appears when the operation is complete. Select **OK** to close the window.

A message appears, stating that the import is successful. If, however, an error occurs in any line of the import, the whole import is aborted.

Export Messages

You can export messages from a Historian server to your worksheet, a CSV file, or an XML file.

You can specify which fields of the messages are exported, such as timestamp, topic, message string, message number, substitutions, or username.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Export Messages**.
The **Export Messages From Historian** window appears.
3. Select a server from the drop-down list box. If you do not specify a server, the default server is considered.
4. Enter values as described in the following table.

Field	Description
Topic	Select one of six types of messages from the drop-down list box.
Filter Criteria	Enter values for the start time, end time, and search text string in the corresponding fields.
Fields to Export	Select one or more field names from the list that you want to export.
Export Options	Specify whether you want to export messages to a new worksheet, a CSV file, or an XML file. For a CSV or an XML file, you must enter a file name and path for the new file in the File Name field.

5. Select **OK**.
The messages that meet the search criteria are exported.

Managing Enumerated Sets

Before You Begin

[Export the enumerated sets into an Excel worksheet \(on page 2758\)](#).

Before importing enumerated sets into Historian from an Excel worksheet, you can perform the following actions:

- [Add sets \(on page 2757\)](#)
- [Delete sets \(on page 2757\)](#)
- [Modify set description \(on page 2757\)](#)
- [Add states \(on page 2757\)](#)
- [Modify states \(on page 2758\)](#)
- [Delete states \(on page 2758\)](#)

To add sets:

1. Enter details in the following columns in the Excel worksheet.

- **SetName**
- **SetDescription**
- **StateName**
- **StateDescription**
- **StateLowValue**
- **StateHighValue**
- **StateRawValueDataType**
- **NumberOfStatesInThisSet**

We recommend that you fill the columns in the aforementioned sequence.

2. Select **Import Enumerated Sets**.

To delete sets:

1. Select the row that contains the state you want to delete.
2. Right-click the row, and then select **Delete**.

To modify the description of a set:

Place the cursor in the **StateDescription** cell and modify the description.

You cannot modify the name of the set. If you change the name of the set, it is considered a new set.

To add states:

1. Select the set to which you want to add a set.
2. Add the name of the set in the **SetName** column.

The name match the set you selected.

3. Enter the details in the **SetDescription**, **StateName**, **StateDescription**, **StateLowValue**, **StateHighValue**, and **StateRawValueDataType** columns.
4. Enter the total number of states in the **NumberOfStatesInThisSet** column.

Ensure that this value is the same for the current state and existing states in the set. For example, if a state has two states already and you are adding a third state, the number of states for all the three states must be changed to three.

A new state is added to the set.

To modify states:

1. Modify the values of each state.

The states are modified.

To delete states:

1. Select the row that contains the state you want to delete.
2. Right-click the row, and then select **Delete**.

The state is deleted.

What to do Next

[Import the enumerated sets \(on page 2759\)](#).

Export Enumerated Sets

You can export enumerated sets in bulk into an Excel worksheet, [add/modify/delete them \(on page 2756\)](#), and then [import them \(on page 2759\)](#) into Historian.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Export Enumerated Sets**.
The **Historian Export Tags** window appears.
3. Select a server from the drop-down list box. If you do not select a server, the default server is considered.
4. Enter values as described in the following table.

Field	Description
Filter Criteria	In the EnumeratedSet Mask/EnumeratedSet Name field, search for the sets set you want to export. You can enter a set name or name mask (or description and a description mask (*) criteria). All the sets matching the criteria appear.
Export Options	Specify whether you want to export the enumerated sets into an Excel worksheet, a CSV file, or an XML file. For a CSV or XML file, you must also enter a path and file name for the destination file.

5. Select **OK**.

A message appears, stating that the export is successful.

6. Select **OK**.

[Add/modify/delete enumerated sets \(on page 2756\)](#) as needed, and then [import them \(on page 2759\)](#) into Historian.

Import Enumerated Sets

[Export the enumerated sets \(on page 2758\)](#) and [add/modify/delete them \(on page 2756\)](#) as needed.

You can create or modify enumerated sets in the Historian server by importing them from an Excel worksheet.

1. Open an Excel worksheet.

2. Select **Historian > Administration > Import Enumerated Sets**.

A message appears, asking you to confirm that you want to import the enumerated sets.

3. Select **Yes**.

A message appears, confirming that importing the enumerated sets is successful.

4. Select **OK**.

Rename Enumerated Sets

1. [Export the enumerated sets \(on page 2758\)](#) that you want to rename.

2. In the exported worksheet, remove all the fields except **setname**.

3. Change **setname** to **EnumeratedSetName** in the header.

4. To the right of the **EnumeratedSetName** column, insert a column named **NewEnumeratedSetName**.

5. In the **NewEnumeratedSetName** column, enter a new name for each enumerated set that you want to rename.



Important:

If you do not want to rename any of the exported enumerated sets, delete that row from the spreadsheet and rename the remaining enumerated sets.

6. Select **Historian > Administration > Rename Enumerated Sets**.

The **Proficy Historian Rename Enumerated Sets** window appears.

7. Select **Yes**.

The enumerated sets are renamed.

Managing User-Defined Types

Before importing a User Defined Type set into Historian from an Excel Worksheet, you can perform the following actions:

- [Add a User Defined Type \(on page 2760\)](#)
- [Modify a User Defined Type \(on page 2760\)](#)
- [Add fields \(on page 2760\)](#)
- [Modify fields \(on page 2761\)](#)
- [Delete fields \(on page 2761\)](#)

To add User Defined Types:

1. Enter details into the columns in the excel worksheet.



Note:

The columns are listed here according to the way they appear in the Excel worksheet. However, it is recommended to fill the columns in the following sequence: UserDefinedTypeName, User-DefinedTypeDescription, FieldName, FieldDescription, FieldDatatype, IsMasterField, NumberOfFields, StoredFieldQualities and AdminSecurityGroup.

2. Select **Import UserDefinedTypes** to import the types.

To modify the description of a User Defined Type:

1. Select in the **User Defined Type Description** cell and modify the description.



Note:

You cannot modify the name of the type. If you change the name of the type, it is considered as a new type.

2. Select the **Import User Defined Types** to import the types.

To add fields:

1. Select the UserDefinedType to which you wish to add a field.
2. Add the name of the type in the UserDefinedTypeName column. The name should be same as the type selected by you.

3. Enter the details in the UserDefinedTypeDescription, FieldName, FieldDescription, FieldDatatype, IsMasterField, NumberOfFields, StoredFieldQualities and AdminSecurityGroup columns.
4. In the NumberOfFields column, enter the total number of fields. Ensure that this value is the same for the current field and existing fields in the user defined type.

For example, if a UserDefinedType has two fields already and you are adding a third field, the number of fields for all the three fields should be changed to three. A new field is added to the UserDefinedType on import.

To modify fields:

1. Select the field you wish to modify by selecting the row in the Excel worksheet.
2. Modify the values by selecting in the respective columns. The field/fields are modified on import.

To delete fields:

1. Select the row that has the field you wish to delete.
2. Right-select the row and select Delete. Alternatively, you can also use the Delete key on your keyboard.
3. Select the **Import UserDefinedTypes** to update your changes.

Export User-Defined Types

You need to have appropriate security permissions to import and export a user defined type. For more information, refer to *Getting Started with Historian Guide > Implementing Historian Security* for the definition of the various security levels and groups.

You can export user-defined types in bulk into an Excel worksheet, [add/modify/delete them \(on page 2760\)](#)[add/modify/delete them \(on page 2756\)](#), and then [import them \(on page 2762\)](#) into Historian.

1. Open an Excel worksheet.
2. Select **Historian > Administration > Export User Defined Types**.
The **Historian Export User Defined Types** window appears.
3. Select a server from the drop-down list. If you do not select a server, the default server is considered.
4. Enter values as described in the following table.

Field	Description
Filter Criteria	In the UserDefinedType Mask/UserDefined-Type Name field, search for the sets set you

Field	Description
	want to export. You can use * for a wildcard search.
Export Options	Specify whether you want to export the user-defined types to an Excel worksheet, a CSV file, or an XML file. For a CSV or an XML file, you must also enter a path and file name for the destination file.

5. Select **OK**.

The user-defined types are exported.

Import User-Defined Types

Export the user-defined types ([on page 2761](#)) and [add/modify/delete them \(on page 2760\)](#).

You can create or modify user-defined data types in an Excel worksheet and then import them into Historian.

1. Open an Excel worksheet.

2. Select **Historian > Administration > Import MultiField Source Addresses**.

A message box appears asking you to confirm whether to import the sets.

A message appears, asking you confirm that you want to import the user-defined types.

3. Select **Yes**.

The user-defined types are imported.

Reference

Excel Add-In Options

Field	Description
Internal vs. External References	Choosing Use External References allows your application to reference cells in other worksheets and workbooks in addition to the current one. If you choose Use Internal References instead, you can only access cells in the current worksheet. The default setting is Use External References .
Automatically Update Links to Add- In (Yes/No)	Add-In functions are maintained as worksheet links. If users who share worksheets do not have Microsoft Office installed the same way, it is necessary to turn this feature on. When on, this feature automatically re-establishes

Field	Description
	<p>any formula links that may be broken due to differences among users in Microsoft Office installation. The default setting enables this feature.</p> <p>The Auto Update feature allows sharing of worksheets. You must, however, install the Excel Add-In in the exact same Microsoft Office Library Path as the other worksheets if you want to use the sharing feature.</p> <p>When opening a worksheet with links to another worksheet, you may receive a message prompting you to update all linked information in the workbook (Yes) or keep the existing information (No). It is recommended that you select No and keep the existing information. The links will be automatically updated for your worksheet. Save your worksheet after the links have been updated.</p>
Show/Hide Header Labels	This option lets you display or suppress the column header labels that are automatically placed in the worksheet when entering formulas throughout the Historian windows. The default setting is Show Labels .
Color	Allows you to select the header name color from the drop-down list: black, blue, red, green, magenta, cyan, or yellow.
Assign Default Server	This window shows the current server assignment. You can modify the setting by selecting the Edit button and accessing the Historian Server Managers window. This window allows you to save user connection information, add or connect to a new server, delete a server, and modify the default server.
Adjust Column Widths	This option lets you automatically adjust the width of columns in your worksheet as formulas are inserted by Historian windows. Select Adjust Header Column Width to modify the width of header labels; select Adjust Data Column Width to modify the data column widths to accommodate the data values. Enabling these options usually makes the worksheet much more readable. However, doing so can sometimes make the worksheet calculate too much when building a large report. In such cases, disable the automatic feature and adjust individual columns manually.
Save/Default/Cancel	These action buttons let you apply your choices of options. Select Save to apply the settings you entered, select Default to select default settings for all options, and select Cancel to close the window.

Reports

You can generate a wide range of custom reports. You can use all the standard, familiar Excel tools and techniques to access the Historian archives and build reports and charts of all types to fit your specific needs. You can use the sample reports included with Historian almost as is – just change the tags to fit your application. As an alternative, use the setup worksheets as a starting point and adapt them to your particular situation.

Defining Reports

You can define a report so that Excel recalculates the worksheet whenever the contents of specific cells, such as start times or dates, change. In this way, the report generates a dynamic snapshot of process performance, updated regularly in real time. You can also manually initiate recalculation at anytime.

Building Dynamic Reports

The primary rule to follow in building a dynamic report is to use formulas with cell references that contain variable information rather than fixed data, so that recalculation produces new data each time it occurs. You then initiate recalculation by changing certain inputs manually or automatically.

Sharing Reports

You can share any Excel reports you develop with the Historian Excel Add-In as you would any other Excel workbook. For each client using the worksheets, set up the Excel Add-In for Historian.

Using the Sample Reports

The Historian application includes three typical sample reports that demonstrate the power and ease-of-use of the Excel Add-In. Use them directly in your application or modify them to fit your requirements.

The three sample Excel reports are built using tags from the Simulation collector. You must create an instance of the Simulation collector and start it in order for these reports to work. The `Historian Batch Report Sample.xls` file also uses Batch ID and Product ID tags from the Simulation collector. These are Simulation Collector points that are configured to store string data types.

To ensure that the sample reports work correctly, you must add the string tags. These are the last five tags in the tag collector list. Add the string tags in Historian Administrator by browsing the Simulation collector and adding all of the tags by selecting the **Add All Tags** check box. Alternatively, you can run the `Add Tags to Simulation Collector.bat` batch file in the `Historian\Server` directory of the machine that has the Simulation collector.


In addition, when you create an instance of the Simulation collector, it prompts you for the number of simulation tags it should create (but you must still add the tags for collection using one of the two methods above). The default is 1000. Do not enter a value less than 30.

When opening a sample Excel report, you may receive a message prompting you to update all linked information in the workbook or keep the existing information. It is recommended that you select No (that is, keep the existing information). The links will be automatically updated for your worksheet. Save your worksheet after the links have been updated.


Historian Statistical Analysis Sample Report

For a specific duration, this report calculates a number of statistical properties of a tag, such as the average, maximum, minimum, standard deviation, 2 sigma and 3 sigma control limits, and correlation coefficients for other tags. It displays charts of various types for several of these variables.

The chart at the lower left is a plot of the main variable vs. time with sigma control limits indicated by the straight lines. The two charts to the right are scatter diagrams that show the correlation between the main variable and two other variables. The chart at the top right is a histogram of data values of the main variable that shows how the data points are distributed.



The following figure shows the worksheet associated with the sample report that contains the data used to generate the report.




Daily Performance Sample Report

This sample report shows how the measured values and selected statistical properties of specified tags have varied in the last 24 hours. This sample is an example of a typical daily performance report in an industrial plant.

Historian Daily Report Sample							
For: 18-Aug-2001							
	TIGER.Simulation0001	TIGER.Simulation0002	TIGER.Simulation0003	TIGER.Simulation0004	TIGER.Simulation0005	TIGER.Simulation0006	TIGER.Simulation0007
	TIGER.Simulation0001	TIGER.Simulation0002	TIGER.Simulation0003	TIGER.Simulation0004	TIGER.Simulation0005	TIGER.Simulation0006	TIGER.Simulation0007
	Maximum	Maximum	Minimum	Maximum	Minimum	StandardDeviation	Count
7:00	199957.28	199761.95	12.21	199981.69	18.31	57050.91	3600.0
8:00	199969.48	199951.17	24.41	199987.80	18.31	57907.26	3600.0
9:00	199969.48	199847.41	54.93	199957.28	36.62	57451.76	3600.0
10:00	199957.28	199981.69	67.14	199823.00	189.21	57638.78	3600.0
11:00	199981.69	199993.89	36.62	199938.97	42.73	57334.71	3600.0
12:00	199945.06	199902.34	0.00	199981.69	103.76	57779.99	3600.0
13:00	199869.61	199902.34	36.62	199969.48	73.24	58555.56	2995.0
14:00	199869.61	199932.86	42.73	199975.58	18.31	57235.52	3600.0
15:00	199969.48	199993.89	6.10	199914.55	12.21	57998.48	3600.0
16:00	199963.38	199993.89	42.73	199993.89	61.04	57853.26	3600.0
17:00	199975.58	199926.75	24.41	200000.00	18.31	56965.60	3600.0
18:00	200000.00	199932.86	12.21	199823.00	36.62	56999.84	3600.0
19:00	199975.58	199920.66	48.83	199969.48	18.31	57462.40	3600.0
20:00	199957.28	199993.89	12.21	199981.69	24.41	57373.37	3600.0
21:00	200000.00	200000.00	24.41	199987.80	6.10	57509.65	3600.0
22:00	199951.17	200000.00	30.52	199993.89	73.24	57914.51	3600.0
23:00	199957.28	199816.89	12.21	199981.69	18.31	57068.75	3600.0
0:00	199969.48	199951.17	24.41	199987.80	18.31	58169.76	3600.0
1:00	199969.48	199969.48	54.93	199957.28	36.62	57433.42	3600.0
2:00	199804.69	199981.69	67.14	199823.00	189.21	57912.77	3600.0
3:00	199981.69	199993.89	36.62	199938.97	42.73	57802.84	3600.0
4:00	199945.06	199902.34	0.00	199981.69	103.76	57436.26	3600.0
5:00	200000.00	200000.00	30.52	199975.58	85.45	57837.37	3600.0
6:00	199993.89	199993.89	24.41	199963.38	0.00	58223.36	3600.0
Average	199954.73	199943.54	30.26	199953.71	51.88	57621.50	3574.0
Std Dev	47.55	63.54	19.34	54.20	51.54	415.21	123.5
Min	199804.69	199761.95	0.00	199823.00	0.00	56965.60	2995.0
Max	200000.00	200000.00	67.14	200000.00	189.21	58555.56	3600.0

The report shown in the following image is a collection of chart plots of the data displayed in the report of the previous image.



The following figure shows the worksheet used to set up the Daily Sample Report. Edit the worksheet to adapt this report to your application.

The screenshot shows an Excel spreadsheet titled "Historian Daily Report Sample.xls". The "Configuration For Daily Report" section includes the following fields:

- Report Date:** 18-Aug-01 (entered)
- Production Day Start Time (hrs):** 6 (entered)
- Start Time:** 18-Aug-01 06:00 (calculated)
- End Time:** 19-Aug-01 06:00 (calculated)

Two callout boxes provide instructions:


- One points to the start time fields, stating: "Enter the report date and the start time of your production day. A value of '6' indicates a 6:00AM start time, and a value of '6.5' indicates at 6:30AM start time."
- Another points to the tag list, stating: "Enter the list of tagnames to analyze in the report. Note that a formula is currently being used to search for tags from the simulation collector. Delete the entire formula covering the 15 tags and descriptions before entering your own tagnames to analyze in the report."

The table below lists 15 tags with their descriptions and selected statistics:


Tags	Tagname	Description	Eng Units	Statistic
Tag1	TIGER.Simulation00001	TIGER.Simulation00001		Maximum
Tag2	TIGER.Simulation00002	TIGER.Simulation00002		Maximum
Tag3	TIGER.Simulation00003	TIGER.Simulation00003		Minimum
Tag4	TIGER.Simulation00004	TIGER.Simulation00004		Maximum
Tag5	TIGER.Simulation00005	TIGER.Simulation00005		Minimum
Tag6	TIGER.Simulation00006	TIGER.Simulation00006		StandardDeviation
Tag7	TIGER.Simulation00007	TIGER.Simulation00007		Count
Tag8	TIGER.Simulation00008	TIGER.Simulation00008		Minimum
Tag9	TIGER.Simulation00009	TIGER.Simulation00009		Maximum
Tag10	TIGER.Simulation00010	TIGER.Simulation00010		Minimum
Tag11	TIGER.Simulation00011	TIGER.Simulation00011		Average
Tag12	TIGER.Simulation00012	TIGER.Simulation00012		Total
Tag13	TIGER.Simulation00013	TIGER.Simulation00013		Average
Tag14	TIGER.Simulation00014	TIGER.Simulation00014		Maximum
Tag15	TIGER.Simulation00015	TIGER.Simulation00015		Maximum

Batch Sample Report

This is an example of a report that might be used with a batch type of industrial process. The table at the top of the report shows the batch identification, the start and end times, product name, and computed statistics for several process variables. The charts show how selected process parameters varied during the batch cycle.



This is the configuration worksheet used to generate the report shown in the previous image. Modify this worksheet to adapt it to your requirements.



Troubleshooting the Excel Add-In Sample Reports

If you follow the recommended installation procedures, you should not have any difficulty in running the sample reports. If you do encounter any problems, they are likely to relate to the locations of files and the links to those files.

When opening a sample Excel report, you may receive a message prompting you to update all linked information in the workbook or keep the existing information. We recommend that you select No (that is, keep the existing information). The links will be automatically updated for your worksheet. Save your worksheet after the links have been updated.

For problems in the worksheets themselves, refer to Excel online Help for assistance.

Running a Report Using Visual Basic

The following Visual Basic example shows you how to create a hidden instance of Microsoft Excel, open a preconfigured Historian report in that instance, and then print the report to the default printer. To use the example, you must modify the path of the .XLA and .XLS files. The paths that you need to edit are in bold font in the following example.

To use this example, you must have the privileges to run the collector as a Windows service and a default printer must be installed. If Historian security is enabled, you must be a member of the iH Readers group. Tag-level security can override this privilege.

You can trigger this example to run on an event basis or on a polled basis. Most likely, you would run this example on an event basis. However, you can run it on a polled basis using Windows Task Scheduler.

```
Sub CreateExcelObjects()

Dim xlApp As Excel.Application Dim wkbNewBook As Excel.Workbook Dim wksSheet As Excel.Worksheet Dim strBookName As String

' Create new hidden instance of Excel. Set xlApp = New Excel.Application

' Open the preconfigured Historian Excel Add-in report.

Workbooks.Open "C:\Program Files\Microsoft Office\Office11\Library\iHistorian.xla"

Set wkbNewBook = Workbooks.Open("c:\test\ih.xls", 0, False)

'xlApp.Visible = True

With wkbNewBook

For Each wksSheet In .Worksheets

Select Case wksSheet.Name Case "tag1" wksSheet.Select

.RefreshAll

.PrintOut End Select Next wksSheet

.Close False

End With

Set wkbNewBook = Nothing xlApp.Quit

Set xlApp = Nothing

End Sub
```

Array Formulas for the Historian Excel Add-In

In Excel, an array formula is a data request that inputs a set of parameters and returns results. The Historian Excel Add-In uses the following array formulas:

```
ihSearchTags

(pServer,pTagMask,pDescriptionMask,pCollector,pArraySize,pSort,pRowCol,Parameters())

ihQueryData

(pServer-,pTagName,pStartTime,pEndTime,pSamplingMode,pCalculationMode,pSamplingInterval,pNumberOfSamples,pDirection,pFilterTag,pFilterMode,pFilterComparisonMo ())

ihQueryData3
```

```
(pServer,pTagName,pStartTime,pEndTime,pSamplingMode,pCalculationMode,pSamplingInterval,pNumberOfSamples,pDirection,pFilterTag,pFilterMode,pFilterComparisonMo ())

ihQueryMessages

(pServer,pTopic,pStartTime,pEndTime,pSearchText,pArraySize,pSort,pRowCol,Parameters())

ihListArchives

(pServer,pArchiveNameMask,pArraySize,pSort,pRowCol,Parameters())

ihListCollectors

(pServer,pCollectorNameMask,pArraySize,pSort,pRowCol,Parameters())
```

When inserting an array formula, you cannot overwrite part of the range of another array formula in your worksheet. The range includes cells without data displayed. An error message appears if you try to do so. Reselect a different output range to insert the formula.

Array Formula Parameters

The following table describes the parameters for the array formulas for the add-in.

Parameter	Description
pArchiveNameMask	A search mask you can use to browse the archivers. Use standard Windows wildcard characters.
pArraySize	The number of cells that the array spans.
pCalculationMode	The type of the calculation mode (on page 1073) .
pCollector	The collector or collector mask that you want to query.
pCollectorNameMask	A search mask for browsing collectors. Use standard Windows wildcard characters.

Parameter	Description
pDescriptionMask	A search mask for browsing tag descriptions. Use standard Windows wildcard characters.
pDirection	The direction (forward/backward from the start time) of data sampling from the archive.
pEndTime	The end time used to refine your query.
pFilterComparisonMode	<p>The type of comparison to be made on the filter comparison value:</p> <ul style="list-style-type: none"> • Equal: Filter condition is True when the <code>FilterTag</code> is equal to the comparison value. • EqualFirst: Filter condition is True when the <code>FilterTag</code> is equal to the first comparison value. • EqualLast: Filter condition is True when the <code>FilterTag</code> is equal to the last comparison value. • NotEqual: Filter condition is True when the <code>FilterTag</code> is NOT equal to the comparison value. • LessThan: Filter condition is True when the <code>FilterTag</code> is less than the comparison value. • GreaterThan: Filter condition is True when the <code>FilterTag</code> is greater than the comparison value. • LessThanEqual: Filter condition is True when the <code>FilterTag</code> is less than or equal to the comparison value. • GreaterThanEqual: Filter condition is True when the <code>FilterTag</code> is greater than or equal to the comparison value. • AllBitsSet: Filter condition is True when the binary value of the <code>FilterTag</code> is equal to all the bits in the condition. It is represented as <code>^</code> to be used in Filter Expression. • AnyBitSet: Filter condition is True when the binary value of the <code>FilterTag</code> is equal to any of the bits in the condition. It is represented as <code>~</code> to be used in Filter Expression. • AnyBitNotSet: Filter condition is True when the binary value of the <code>FilterTag</code> is not equal to any one of the bits in the condition. It is represented as <code>!~</code> to be used in Filter Expression. • AllBitsNotSet: Filter condition is True when the binary value of the <code>FilterTag</code> is not equal to all the bits in the condition. It is represented as <code>!^</code> to be used in Filter Expression.

Parameter	Description
pFilterComparisonValue	The value to compare the filter tag with when applying the appropriate filter to the DataRecordset query (to determine the appropriate filter times).
pFilterExpression	<p>An expression that includes multiple filter conditions. The type of conditions used are:</p> <ul style="list-style-type: none"> • AND condition • OR condition • Combination of both AND and OR <p>You can use a filter expression instead of FilterTag, FilterComparisonMode and FilterValue parameters. While using FilterExpression, the expression is passed within single quotes, and for complex expressions, enclose the conditions in parentheses. There is no maximum length for a filter expression.</p>
pFilterMode	<p>The type of the time filter:</p> <ul style="list-style-type: none"> • ExactTime: Retrieves data for the exact times that the filter condition is True (only True). • BeforeTime: Retrieves data from the time of the last False filter condition up until the time of the True condition (False until True). • AfterTime: Retrieves data from the time of the True filter condition up until the time of the next False condition (True until False). • BeforeAndAfterTime: Retrieves data from the time of the last False filter condition up until the time of next False condition (While True). • The FilterMode: Defines how time periods before and after transitions in the filter condition should be handled. <p>For example, AfterTime indicates that the filter condition should be True starting at the timestamp of the archive value that triggered the True condition and leading up to the timestamp of the archive value that triggered the False condition.</p>
pFilterTag	The single tagname used when applying the filter criteria.

Parameter	Description
pNumberOfSamples	<p>Number of samples from the archive to retrieve.</p> <p>Samples will be evenly spaced within the time range defined by start time and end time for most sampling modes. For the <code>RawByNumber</code> sampling mode, the <code>NumberOfSamples</code> column determines the maximum number of values to retrieve. For the <code>RawByTime</code> sampling mode, the <code>NumberOfSamples</code> is ignored.</p>
pRowCol	The sorting criteria used: 0 for columns and 1 for rows.
pSamplingInterval	For non-raw sampled data, this column represents a positive integer for the time interval (in milliseconds) between returned samples.
pSamplingMode	The type of the sampling mode (on page 1044) used by the query.
pSearchText	The text or mask that you want to search for in the message.
pServer	Name of the server from which you are retrieving data. If you are running Excel on the same server from which you are retrieving data, you need not enter a string, as the default server is used.
pSort	The sorting criteria used for the rows or columns: 0 for descending and 1 for ascending.
pStartTime	The start time used to refine your query.
pTagMask	A search mask for browsing tagnames. Use standard Windows wildcard characters.
pTagName	The tagname or tagname mask that you want to query.
pTopic	<p>The message topic:</p> <ul style="list-style-type: none"> • Connections • Configuration

Parameter	Description
	<ul style="list-style-type: none"> • General • Services • Performance • Security
Parameters()	Output display of the array formula. This field can include be one or more parameters.

Relative Time Entries

When entering the Start and End times for Excel Add-in queries and exports, you can already enter them as exact literal dates and times such as `"1/28/14 09:00:00"` in the query windows like **Query Calculated Data**, or you can use a cell reference to an exact time, or use an Excel function such as `=Now()` or `=Today()`. Apart from the mentioned ways, you can use relative time entries using a base value and an offset value as described in the following tables.

For example, you can use `Yesterday+8H` for 8am yesterday or `Now-15m` for 15 minutes before the current time. The typical use of a relative time entry, is to type the time values using a base and an offset into the start and end time of the **Query** window or the **Export** window, instead of having to put `=Now()` or `=Today()` in a cell and making a cell reference to that, or use the base `Monday` to produce weekly reports.

Base Values

Base Value	Description
Now	The current date and time.
Today	The current date at midnight.
Yesterday	The previous day at midnight.
Sunday	Today or the most recent Sunday at midnight.
Monday	Today or the most recent Monday at midnight.
Tuesday	Today or the most recent Tuesday at midnight.
Wednesday	Today or the most recent Wednesday at midnight.

Base Value	Description
Thursday	Today or the most recent Thursday at midnight.
Friday	Today or the most recent Friday at midnight.
Saturday	Today or the most recent Saturday at midnight.

Offset Values

Offset Value	Description
d	One 24 hour day
h	One hour
m	One minute
s	One second

Filter Parameters for Data Queries

Parameters	Description
Filter Tag	<p>The single tag name used when applying the filter criteria.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: You can enter your filter conditions using Filter tag, Filter Comparison Mode, and Filter Comparison Value or you can put that all that information in a single Filter Expression.</p> </div>
Filter Expression	<p>An expression that includes one or more filter conditions. The types of conditions used are:</p> <ul style="list-style-type: none"> • AND Condition • OR Condition • Combination of both AND and OR <p>FilterExpression can be used instead of FilterTag, FilterComparisonMode and FilterValue parameters. There is no maximum length for a filter expression.</p>
Filter Mode	<p>The type of time filter:</p>

Parameters	Description
	<ul style="list-style-type: none"> • ExactTime – Retrieves data for the exact times that the filter condition is True (only True). • BeforeTime – Retrieves data from the time of the last False filter condition up until the time of the True condition (False until True). • AfterTime – Retrieves data from the time of the True filter condition up until the time of next False condition (True until False). • BeforeAndAfterTime – Retrieves data from the time of the last False filter condition up until the time of next False condition (While True). <p>The Filter Mode defines how time periods before and after transitions in the filter condition should be handled.</p> <p>For example, AfterTime indicates that the filter condition should be True starting at the timestamp of the archive value that triggered the True condition and leading up to the timestamp of the archive value that triggered the False condition.</p>
Filter Com- par- ison Mode	<p>The type of comparison to be made on the filter comparison value:</p> <ul style="list-style-type: none"> • Equal – Filter condition is True when the Filter Tag is equal to the comparison value. • EqualFirst – Filter condition is True when the Filter Tag is equal to the first comparison value. • EqualLast – Filter condition is True when the Filter Tag is equal to the last comparison value. • NotEqual – Filter condition is True when the Filter Tag is NOT equal to the comparison value. • LessThan – Filter condition is True when the Filter Tag is less than the comparison value. • GreaterThan – Filter condition is True when the Filter Tag is greater than the comparison value. • LessThanEqual – Filter condition is True when the Filter Tag is less than or equal to the comparison value. • GreaterThanEqual – Filter condition is True when the Filter Tag is greater than or equal to the comparison value. • AllBitsSet – Filter condition is True when the binary value of the Filter Tag is equal to all the bits in the condition. It is represented as <code><math>\wedge</math></code> to be used in Filter Expression.

Parameters	Description
	<ul style="list-style-type: none"> • AnyBitSet – Filter condition is True when the binary value of the Filter Tag is equal to any of the bits in the condition. It is represented as <code>~</code> to be used in Filter Expression. • AnyBitNotSet – Filter condition is True when the binary value of the Filter Tag is not equal to any one of the bits in the condition. It is represented as <code>!~</code> to be used in Filter Expression. • AllBitsNotSet – Filter condition is True when the binary value of the Filter Tag is not equal to all the bits in the condition. It is represented as <code>!^</code> to be used in Filter Expression. • Alarm Condition – Specifies an alarm condition to filter data by. For example, Level. • Alarm SubCondition – Specifies an alarm sub-condition to filter data by. For example, HIHI. <p>The Filter Comparison Mode defines how archive values for the Filter Tag should be compared to the Filter Value to establish the state of the filter condition. If a Filter Tag and Filter Comparison Value are supplied, time periods are filtered from the results where the filter condition is False.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Filter Comparison Mode is only used if Filter Tag is filled in.</p> </div>
Filter Comparison Value	<p>The value to compare the filter tag with when applying the appropriate filter to the data record set query (to determine the appropriate filter times).</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Filter Comparison Value is only used if Filter Tag is filled in.</p> </div>

Batch IDs

If you had a `BatchID` going into a Historian tag, that `BatchID` will either have a timestamp at the beginning of the batch or at the end of the batch. Different batch systems report the `BatchID` as the batch is started, and other systems do not report the `BatchID` until the batch is finished.

If your `BatchID` is reported at the beginning of a batch, you would need to use the **AfterTime** option because you would want to include all data for a particular `BatchID` after the time the `BatchID` was

reported up until the next `BatchID` was reported. If your `BatchID` was being reported at the end of the batch, you would want to use the **BeforeTime** option because you would want to include all data for a particular `Batch ID` before the time the `Batch ID` was reported back to the previous `BatchID` being reported.

Sampling Types

Interpolated Sampling

Calculates values between two data points using a linear interpolation algorithm.

Calculated Sampling

Computes values using an algorithm selected in the Calculation field.

Lab Sampling

Computes intermediate values between two data points by using the last actual value. This type of sampling displays as a stair step type of curve.

Trend Sampling

Returns the raw minimum and raw maximum value for each specified interval. Use the Trend sampling mode to maximize performance when retrieving data points for plotting. For the Trend sampling mode, if the sampling period does not evenly divide by the interval length, **Historian** ignores any leftover values at the end, rather than putting them into a smaller interval.

InterpolatedtoRaw Sampling

Provides raw data in place of interpolated data when the number of samples fall lesser than the available samples.

TrendtoRaw Sampling

The TrendtoRaw sampling mode almost always produces the same results as the Trend sampling mode. The exception is that, when more samples are requested than there are raw data points, the TrendtoRaw sampling mode returns all of the available raw data points with no further processing. TrendtoRaw is therefore used rather than Trend when the number of actual data samples are fewer than the requested number of samples.

LabtoRaw Sampling

Provides raw data for the selected calculated data over the plot, when the number of samples fall lesser than the available samples.

RawByFilterToggle Sampling

Returns filtered time ranges with values 0 and 1. If the value is 1, then the filter condition is true and 0 means false. This sampling mode is used with the time range and filter tag conditions. The result starts with a starting time stamp and ends with an ending timestamp.

Trend2 Sampling

Returns the raw minimum and raw maximum value for each specified interval. Use the Trend2 sampling mode to maximize performance when retrieving data points for plotting. Also, if the sampling period does not evenly divide by the interval length, Historian creates as many intervals of the interval length as will fit into the sampling period, and then creates a remainder interval from whatever time is left. Trend2 sampling mode is more suitable than Trend sampling mode for analysis of mins and maxes and for plotting programs that can handle unevenly spaced data.

TrendtoRaw2 Sampling

The TrendtoRaw2 sampling mode almost always produces the same results as the Trend2 sampling mode. The exception is that, when more samples are requested than there are raw data points, the TrendtoRaw2 sampling mode returns all of the available raw data points with no further processing. TrendtoRaw2 is therefore used rather than Trend2 when the number of actual data samples are fewer than the requested number of samples.

Calculation Algorithm Types

Average

A time weighted arithmetic mean.

Minimum

The lowest value in the group.

Maximum

The highest value in the group.

Standard Deviation

The square root of the arithmetic mean of deviations from the time- weighted arithmetic mean of all values in the group.

Total

The time-weighted total of all values in the group. Note that Engineering Units are assumed to be in Units/Day. If your Engineering Units were not measured in Units/Day, you must scale your total to the actual time units of the measurement. For example, if the measurement

were in Units/Minute (such as GPM), you would multiply the total number by 1440 (minutes in a day) to scale the value into the correct time units.

Count

The total number of values in the group.

Raw Average

The unweighted arithmetic mean of all values in the group.

Raw Standard Deviation

The square root of the arithmetic mean of deviations from the unweighted arithmetic mean of all values in the group.

Raw Total

The unweighted total of all values in the group.

Time of Minimum Value

The time at which the minimum value occurred. | Time of Maximum Value - the time at which the maximum value occurred.

Time Good

The amount of time (in milliseconds) during the interval when the data quality is good.

State Count

Displays the number of times a tag has transitioned to another state from a previous state. A state transition is counted when the previous good sample is not equal to the state value and the next good sample is equal to state value.

State Time

Displays the duration that a tag was in a given state within an interval.

First Raw Value

Returns the first good raw sample value in the given time interval.

First Raw Time

Returns the time stamp of the first good raw sample in the given time interval.

Last Raw Value

Returns the last good raw sample value in the given time interval.

Last Raw Time

Returns the time stamp of the last good raw sample in the given time interval.

TagStats

Returns the values of multiple calculation modes in a single query.

Delta Positive, Delta Negative, and Delta

Return the delta over a time interval. For more information, refer to:

- [DELTAPOS \(on page 1116\)](#)
- [DELTANEG \(on page 1132\)](#)
- [DELTA \(on page 1141\)](#)

Tag Criteria List

The following table outlines the tag criteria available:

Criteria	Description
Tagname	Tagname or tag mask property of the tag.
Description	User description of the tag.
Data Type	The data type of the tag.
Collector Name	Name of the collector responsible for collecting data for the specified tag.
Collector Type	The type of collector responsible for collecting data for the tag. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 5px; background-color: #E6F2FF;">  Note: Do not use wildcards in this field. </div>
Collection Type	Type of collection used to acquire data for the tag.
Data Store Name	Indicates the name of the data store to which the tag belongs to.
EGU Description	Indicates the engineering units assigned to the tag. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 5px; background-color: #E6F2FF;">  Note: Do not use wildcards in this field. </div>
Comment	Comments that is applied to the tag.

Criteria	Description
	 Note: Do not use wildcards in this field.
Source Address	The address for the selected tag in the data store.  Note: Do not use wildcards in this field.
Collection Interval	The time interval between the readings of data. The value entered is in milliseconds.
Collector Compression	Whether or not collector compression is enabled as a default setting.
Archive Compression	Indicates the current effect of archive data compression.
Last Modified User	The name of the person who last modified the tag configuration parameters.
Enumerated Set Name	Indicates the enumerated set name associated with the tag.

Troubleshooting Issues with the Add-In

Troubleshooting General Imports

- Review the `HistorianSDKErrors.log` file. This file is usually located in the `LogFiles` folder in your Historian program folder. Historian records additional information for some errors in this file. Sometimes, by reviewing this file, you can determine the cause of the error.
- If using Historian security, verify that the user has the appropriate security rights. If the rights are incorrect, log in as a user with the correct privileges or change the rights for the current user.
- Verify that there are no empty rows between valid rows in your spreadsheet. These empty rows can cause issues.
- Note if any errors occur. If an error occurs with any line of the import, Historian aborts the whole import.

Troubleshooting Tag Imports

- If you remove or add Historian servers, and then if you attempt to search for tags, the add-in may not recognize the default server, and may display a message, stating that the default server has not been set. To avoid this issue, close and reopen the **Search Tags** window.
- Make sure that you are not trying to import the Calculation Execution Time, Last Modified, or Last Modified User fields for each tag. These fields are read-only. As such, you can export them but cannot import them.
- Verify that your collector does not contain any duplicate tagnames.
- Verify that the number of tags that you want to import does not exceed the maximum licensed tag count. If it does, you will not be able to import the tags.

Troubleshooting Data Imports

- Ensure that the time stamps of any online archives are not prior to the start time of the oldest online archive.
- Ensure that the time stamps are within the active hours setting in the **Data Store Maintenance** page of Historian Administrator.
- Ensure that the time stamps are not for a time greater than 15 minutes ahead of the system time on the Historian server.
- Ensure that the tags are valid Historian tags. To do this, import your tags before importing their associated data.

Troubleshooting Data or Tag Exports

You cannot export data or tags to a remote path using the add-in.

You can export a 64-bit tag, include it in a report and perform calculations on it. However, there will be a minor precision loss while retrieving the data due to a Visual Basic limitation.

Importing Tags Fails

Description: If you export all the fields and attempt to import the read-only fields **LastModified** and **LastModifiedUser**, you may receive an error message.

Error Message: Import failed, Error with Import Header.

Workaround: Export the tags without selecting the read-only fields, and then import the tags.

Unable to Run Sample Reports

Description: If you follow the recommended installation procedures, you should not have any difficulty in running the sample reports. If you do encounter any problems, they are likely to relate to the locations of files and the links to those files.

Workaround: When opening a sample Excel report, you may receive a message prompting you to update all linked information in the workbook or keep the existing information. We recommend that you select No (that is, keep the existing information). The links will be automatically updated for your worksheet. Save your worksheet after the links have been updated.

For problems in the worksheets themselves, refer to Excel online Help for assistance.

Error Occurs While Inserting an Array Formula

When inserting an array formula, you cannot overwrite part of the range of another array formula in your worksheet. The range includes cells without data displayed. An error message appears if you try to do so. Reselect a different output range to insert the formula.


Chapter 40. The Excel Addin for Operations Hub

Overview of the Excel Add-In for Operations Hub

The Excel Add-in for Operations Hub enhances the benefits of using Operations Hub. It enables you to retrieve the object data that can be used to perform further analysis using Excel features.

Features:

- **Query:** Enables you to perform the model query and to import the data into Excel. You can query historical data based on object types, objects, and data variables.
- **Configuration:** Enables you to connect to Operations Hub and save the server details.
- **About:** Displays the version information of the add-in.
- **Help:** Displays the product documentation for the add-in.
- **Logs:** Opens the folder where you can view the logs.



In addition, you can:

- View the metadata of the selected data variables and objects in Excel.
- Select the data filter options with which you can filter the data to be retrieved.
- Select the output display options for which you want to view the data.

Limitations:

- If you query the data variables of data type string, byte, or array, a null value is returned
- You cannot query current value for an array tag using the Excel Add-In for Operations Hub. .
- If you query the following calculation modes, an error occurs:
 - Minimum Time
 - Maximum Time
 - First Raw Time
 - Last Raw Time
 - Time Good

About Operations Hub

Operations Hub is an end-to-end solution for developing, managing, and delivering applications to leverage the capabilities of big data analytics and the internet of things. Using Operations Hub, you can create applications that will collect and analyze data from a machine or a server, and trigger actions based on certain events.

Operations Hub provides you a user-friendly interface to create components of an application such as queries, database tables (called entities), events, email templates, users, and so on without the need to use your programming skills. You can also design pages and dashboards using these components.

Advantages of using Operations Hub

- Operations Hub is quick, easy, and cost-effective. You do not need programming skills to develop an application.
- The Operations Hub applications use HTML5 and CSS3, and hence, they are platform-independent.
- You can access an application using a computer or a mobile device.
- You can provide controlled access to an application and data, based on user roles.
- You can create entities and queries for a relational database.

For more information about Operations Hub, refer to

https://www.ge.com/digital/documentation/opshub/windows/windows/c_overview_of_app_designer.html

Setting Up

Software Requirements

The following components are required to use Excel Add-in for Operations Hub:

Component	Version	Description
Operations Hub	2.0 and above.	If you have purchased the standard or enterprise license of Historian, you receive a no-cost license for Operations Hub, which enables you to:

Component	Version	Description
		<ul style="list-style-type: none"> • Access to the Historian Analysis run-time application, which is an in-built HTML5 application in Operations Hub. • Perform advanced trend analysis, including inserting annotations. • Define an asset model including tag mapping.
Microsoft Excel	2016 and 2019 (32 bit or 64 bit)	
Historian REST APIs		Historian REST APIs are required to integrate between Historian and Operations Hub. Historian REST APIs are installed automatically when you install Historian Web-based Clients (on page 155) .

Install Excel Add-In for Operations Hub

Install the Historian server ([on page 104](#)) and other [software requirements \(on page 198\)](#).

1. Run the `InstallLauncher.exe` file.
2. Select **Install Excel Add-in for Operations Hub**.
The welcome page appears.
3. Select **Next**.
4. Read and accept the license agreement, and then select **Next**.
5. Select the available disk to install the Excel Add-in for Operations Hub, and then select **Next**.



Note:

We recommend that you select the drive where Microsoft Excel is installed.

6. Provide the details of Operations Hub, and then select **Next**.

Provide the Operations Hub details:

Operations Hub Server:

Operations Hub UAA Server(url):

Cancel Previous Next

The **You are ready to install** page appears.

7. Select **Install**.


Excel Add-In for Operations Hub is installed.

[Copy/export the issuer certificate \(on page 200\)](#), and then [install/import it \(on page 201\)](#).

Copy or Export the Issuer Certificate on Server

[Install Excel Add-In for Operations Hub \(on page 199\)](#).

This topic describes how to copy or export the issuer certificate on Server. If this is not done, you will get an error while querying data as shown in the image below.



1. Navigate to the machine where Operations Hub is installed.
2. Select **Site Information (Not secure)**.
3. Select **Certificate (invalid)**.
The **Certificate** window appears.
4. Select **Certificate Path**.
5. Select the Root CA certificate.
6. Select **Details**.
7. Select **Copy to file**.
The **Certificate Export Wizard** window appears.
8. Select **DER encoded binary X.509(.CER)** format and select **Next**.
9. Select **Browse** to save the certificate file at desired location.
10. Complete the certificate export.

[Install or import the certificate \(on page 201\)](#).

Install/Import the Issuer Certificate

[Copy or export the issuer certificate \(on page 200\)](#) on the machine on which Excel Add-In for Operations Hub is installed.

1. Right-click the certificate, and then select **Install Certificate**.
The **Certificate Import Wizard** page appears
2. Select **Local Machine**, and then, select **Next**.
3. Select **Place all certificates in the following store**.
4. Select **Trusted Root certification Authorities**, and then select **OK**.
5. Select **Next**, and then select **Finish**.
The certificate is imported.

[Configure the Operations Hub server \(on page 202\)](#).

Connect to Operations Hub

To query a model defined in Operations Hub, you must first connect to the Operations Hub server. You will then receive a token from the server, which will be used for authentication.

1. Select **Configuration** menu in Admin.
The **Operations Hub Configuration** window appears.
2. Provide values as described in the following table.

Field	Details
Operations Hub Server	The Operations Hub server name to which you want to connect and get the data.
Operations Hub Proficy Authentication Server (url)	The URL of the Proficy Authentication service of Operations Hub. Example: https://<ophubservername>/uaa



Note:

The **Token Status** field indicates the status of the connection with Operations Hub server.

3. Select **Connect**.
The login page appears.
4. Provide the **User Identifier** and **Password** to connect to Operations Hub.
5. Select **Open UaaAuthSchemeHandler**.
Operations Hub Server to which you are connected and the status of the token appears.
6. Select **Save** to save the Operations Hub server details. The configuration will be retained and used when you open excel add-in again.


Querying an Operations Hub Model

You can query an Operations Hub model using the object types, data variables, and objects:

Item	Description
Object types	Define the structure of the equipment within your model (for example, a car). Object types are represented by  .

Item	Description
Data variables	Define the actual data that is received from a data source - that is, how to use a property in the Views feature. For example, you can define a property to appear as a trend line on a trend chart. For each object type, such as a car, you set up all the data variable names (such as color, speed). Any object associated with this type can reuse them in its own definition. Data variables are represented by  .
Objects	Instances of object types or pieces of equipment (for example, BMW, BENZ). Objects are represented by  .

The following image shows the object types, data variables, and objects in the add-in.



Query Operations Hub Model

1. Access an Excel worksheet.
2. Select the object type from the **Object Type** drop-down list box. Example: Car.

The corresponding data variables and contained types are displayed in the **Data Variables** list for the selected Object Type.

- Optional: Select the **Get Full Object Type Hierarchy** check box to get the complete object type hierarchy for the selected object type in the data variables

**Note:**

Selecting this option might impact the performance and you may experience the delay in retrieving and browsing the object type hierarchy.

- Select the data variables from the **Data Variables** list.

**Note:**

Only one level of the object type hierarchy is displayed. Double-click the object types to browse through the other levels.

**Tip:**

You can right select in the **Data Variables** section to perform the following actions:

- **Check All:** Selects all the data variables.
- **Collapse All:** Collapses the hierarchy.
- **Expand All:** Expands the hierarchy displaying all the data variables.
- **Uncheck All:** Deselects all the data variables.

- Optional: Enter a search criterion in the **Search String** text box and then, select the Search icon to filter the data variables based on the string entered.

**Note:**

'*' can be used as wild card character in the search text box.

The resultant data variables matching the filter string appear in the data variables list.

- Optional: Select the **Auto Search** check box to filter the data variables as you type the string in the **Search String** text box. Note: Auto search option is recommended only when your model has less number data variables.
- Select the objects from the **Objects** list. You can right-select in the **Objects** section to perform the following actions:
 - **Check All:** Selects all the objects.
 - **Uncheck All:** Deselects all the objects.

8. Select **Apply** to apply the selection to query the model.
9. Select **View Selected** to view the metadata of selected data variables and objects. The details will appear on Excel.



Note:

You can continue with building the query returning to the Build Query window by selecting the Query button.

Name	ObjectName	DataVariable			BindingType	Schema			
		Name	SystemAlias	NodeId		Version	SystemName	SystemType	ObjectTypeHierarchy
BMW>Speed	BMW	Speed	HistMachine1	HistMachine1.Ramp_1%Noise	Historical	1	HistMachine1	Historian	Car>Speed
BMW>Mileage	BMW	Mileage	HistMachine1	HistMachine1.Simulation00005	Historical	1	HistMachine1	Historian	Car>Mileage
BMW>Engine_2>Capacity	Engine_2	Capacity	HistMachine2	HistMachine2.Simulation00003	Historical	1	HistMachine2	Historian	Car>Engine>Capacity
BMW>CEAT Tyre>Durability	CEAT Tyre	Durability	HistMachine3	HistMachine3.Simulation00008	Historical	1	HistMachine3	Historian	Car>Tyres>Durability

10. Optional: You can select the **Clear Selections** button to clear all selections.
11. Select the **Data Filter Options** to retrieve the data based on the sampling and calculation modes:
 - Start/End Time: The duration for which you want to retrieve the data.
 - Sampling modes: The sampling mode for the data. It specifies the way data will be retrieved from Historian. Example: CurrentValue, Interpolated, Calculated and RawByTime. For more information, refer to [Sampling Modes \(on page 1044\)](#).
 - Calculation modes: Calculation modes are used when the sampling mode is set to Calculated. The data type of all calculated values will be DoubleFloat except for MinimumTime, MaximumTime, FirstRawTime and LastRawTime which will be a Date. The datatype of the values of FirstRawValue and LastRawValue will be the same as that of the selected tag.

The Calculation Field is active only after you select Calculated Sampling as the Sample Type. You can select a Calculation Algorithm type from the drop-down list.

The calculation modes supported by Historian are supported by Excel Add-in for Operations Hub except Minimum Time, Maximum Time, First Raw Time, Last Raw Time, Time Good, State Count, State Time.



Note:

Minimum Time, Maximum Time, First Raw Time, Last Raw Time, Time Good calculation modes are listed in the Calculation Modes drop-down but are not supported.

For more information, refer to [Calculation Modes \(on page 1085\)](#).

**Note:**

Some of the calculation modes such as Minimum Time, Maximum Time, First Raw Time, Last Raw Time, Time Good are returning bad data upon query.

12. Select the **Data Quality** based on which you want to export the samples.

13. Select the **Data Display Options**

- **Columns:** Select the Columns for which you want the values to be displayed. By default, Node, Node Id (Tag Name) will be selected.
- **Data time to display:** Choose the timestamp format to be displayed.
 - Default: To display the time format as in Operations Hub.
 - Local: To display the time in local time zone.
 - ISO 8601 Format: To display time in ISO 8601 readable format. (Result will include T for the time designator and Z for the zero UTC offset)

**Note:**

When you query for a data variable in a duration which has no data, the Default mode selection displays time value as 0 and Local and ISO 8601 format displays time as 1970 year because, the 0 epoch time converted to local time is 1970.

14. Select **Get Data** to read and display data for the selected data variables in the excel sheet.

Name	Node Id (Tag Name)	Time	Value	Quality
Benz>Mileage	HistMachine1.Simulation00004	1575369343000	173491.625	Good
Benz>Engine_1>Compressor_1>Pressure	HistMachine1.Simulation00004	1575369343000	173491.625	Good
BMW>CEAT Tyre>Durability	HistMachine2.Simulation00008	1575369343000	87215.79688	Good
Benz>MRF Tyre>Durability	HistMachine2.Simulation00003	1575369334000	48927.27344	Good
BMW>Mileage	HistMachine3.Simulation00005	1575369334000	122385.3281	Good

Troubleshooting Issues with the Add-In

Query Error

Error Message: Failed to read objects-by-types. Check the log for details. The request was aborted: Could not create SSL/TLS secure channel.

Workaround: Provide values as described in the following table:

Field	Details
Name	SchUseStrongCrypto
Value	'1'
Type	DWord
Operations Hub Proficy Authentication Server (url)	HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Micro- soft\ .NetFramework\v4.0.30319

Error Occurs if you Query an Object Type with many properties and containment objects

Error Message: Proxy server could not handle the request.

Workaround: Use the on-demand approach.

Blank Login Page Appears

Issue: When Operations Hub Proficy Authentication is opened (logged in) in browser and then if you try to connect to Operations Hub Proficy Authentication from Excel Add-in, sometimes, a blank login page appears.

Workaround: Refresh the browser window which pops up authorize window and then, select **Open UaaAuthSchemeHandler**.

Data Variable Selections are not Retained

Issue: When the data variables are searched and selected from the Object Type hierarchy, previously made selections of data variables (before search) are not retained.

Workaround: Remove the text entered in the **Search** text box and select **Apply** for all the previous selections to be applied.

Error Occurs Even Before Performing an Action

Error Message: Failed to get access_token.

Workaround: Get the token from the Operations Hub Proficy Authentication server by selecting **Configuration** in the add-in.

Chapter 41. Trend Client

Overview of Trend Client

Trend Client provides a simple and intuitive interface to analyze your process and equipment data to:

- Troubleshoot and improve your processes.
- Save operational cost, money, and risk.

Using Trend Client, you can plot trend charts and current-value tables, which help you visualize timeseries data.

To install Trend Client, install [Web-based Clients](#).

Access Trend Client

[Web-based Clients](#).



1. On the desktop, select . Alternatively, you can access the following URL: `https://<Trend Client web server name>/uaa/login#/home`
2. Log in with the credentials you provided while installing Web-based Clients.
The Trend Client home page appears.

Access Help

In the upper-right corner of Trend Client, select .
The Help documentation for Trend Client appears.

Access a Tag

When you search for a tag, you can narrow down the search results further by performing a basic search or an advanced search.



Note:

By default, maximum one million tags are retrieved. If the Historian clients are configured to retrieve more than a million tags, to retrieve all of them, add the `MaxTagsToRetrieve` registry key under `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services`



\DataArchiver\, and then set the maximum number of tags that you want to retrieve. Restart the Historian Data Archiver service for the change to reflect.

1. [Access Trend Client \(on page 2799\)](#).
2. If you want to access all tags, select **Tags > Search**.

The **Tags Search** window appears.

3. If you want to access all tags, select .

A list of all the tags in the Historian server appears. You can filter the list of tags by entering the name or description in the text box.

4. If you want to perform an advanced search:

- a. On the **Tags** page, select **Advance Search**.

The **Advanced Tag Search** window appears.

- b. Expand **Select Tag Criteria**, and enter values in the search criteria.



Note:

Supported wildcard characters in search are * and ?. The following table provides examples of searching using wildcard characters.

Search String	Result
W*	All tags starting with letter W
*e	All tags ending with letter e
W*e	All tags starting and ending with W and e respectively
Tag?	All four letter named tags, where the last letter can be anything
W*0000?	All tag names starting with W and ending with 0000 followed by any single letter

- c. Select **Find Tags**.

A list of tags that match the search criteria appears.



Note:

Do not add or update the following spare configurations as the data may get corrupted or over written:



- The **Spare 1** field for OSI PI Distributor. OSI PI distributor reads data from the Historian tag displayed in the Tag Source Address field and sends it to the OSI PI tag name displayed in the **Spare 1** field.
- The **Spare 5** field for Server to Server Collector and Server to Server Distributor as it is only used for internal purposes.

To analyze the tag data, add it in a [trend chart \(on page 2802\)](#), [current value table \(on page 2803\)](#), [value card \(on page 2803\)](#), or a [text box \(on page 2804\)](#).

Add Tags for Analysis

Before you access the trend chart or value table of a tag, you must add it to the **Tags** section.

1. On the **Tags** page, select **Advance Search**.
The **Advanced Tag Search** window appears.
2. Expand **Select Tag Criteria**, and enter values in the search criteria.



Note:

Supported wildcard characters in search are * and ?. The following table provides examples of searching using wildcard characters.

Search String	Result
W*	All tags starting with letter W
*e	All tags ending with letter e
W*e	All tags starting and ending with W and e respectively
Tag?	All four letter named tags, where the last letter can be anything
W*0000?	All tag names starting with W and ending with 0000 followed by any single letter

3. Select **Find Tags**.
A list of tags that match the search criteria appears.
4. In the row containing each tag that you want to add, select , and then select **Apply**.
The tags appear in the **Summary** and **Tags** sections.


To analyze the tag data, add it in a [trend chart \(on page 2802\)](#), [current value table \(on page 2803\)](#), [value card \(on page 2803\)](#), or a [text box \(on page 2804\)](#).

Creating a Display

Add a Trend Chart

By default, the sample size limit that is plotted on a trend chart is 2000. If you want to change this value:

1. In the upper-right corner of Trend Client, select the drop-down list box, and then select **System Config**.



The **System Configuration** page appears.

2. In the **Analysis Sample Size Limit** field, enter the sample size, and press Enter.

The changes are automatically saved.

Similarly, maximum 30 days of data is plotted on a trend chart; you can change this value.

Trend charts are graphical representations for showing how the value of one or more items changes over time. Trend charts can show information as Line, Area, Scatter, and Statistics Charts.

1. [Access Trend Client \(on page 2799\)](#).
2. Select .
3. [Add tags for analysis \(on page 2801\)](#).
4. Select the tags, and drag and drop them into the chart area.

A trend chart is plotted for the selected tags. A blue dot appears in the row containing each tag in the **Tags** section, indicating that you have added it to the chart.

**Tip:**

By default, the title of the table is Chart <number>. You can rename the title as needed.

You can add more trend charts, or you can add a [current value table \(on page 2803\)](#), [value card \(on page 2803\)](#), or a [text box \(on page 2804\)](#) to the display.

Add a Current Value Table

A current value table provides the current value of each tag, along with the quality, description, units of measurement, and so on.

1. [Access Trend Client \(on page 2799\)](#).

2. Select .

A blank current value table appears.

3. [Add tags for analysis \(on page 2801\)](#).

4. In the **Tags** section, select each tag that you want to include in the current value table, and drag and drop it to the table.

The tags are added to the current value table, displaying the current value, quality, description, and so on.

**Tip:**

By default, the title of the table is Current Values <number>. You can rename the title as needed.

You can add more current value tables, or you can add a [trend chart \(on page 2802\)](#), [value card \(on page 2803\)](#), or a [text box \(on page 2804\)](#) to the display.

Add a Value Card

The value card is a snapshot of the most current value of a tag. Each value card is limited to a single tag.

1. [Access Trend Client \(on page 2799\)](#).

2. Select .

A blank current value card appears.

3. [Add the tag for analysis \(on page 2801\)](#).
4. In the **Tags** section, select the tag that you want to include in the value card, and drag and drop it to the value card.

The tags are added to the value card, displaying the current value, quality, description, timestamp, and so on.



Tip:

By default, the title of the table is Current Values <number>. You can rename the title as needed.

You can add more value cards, or you can add a [trend chart \(on page 2802\)](#), [current value table \(on page 2803\)](#), or a [text box \(on page 2804\)](#) to the display.

Add a Text Box

You can add a text box to enter free-form text to your display. The text box contains standard editing icons.

1. [Access Trend Client \(on page 2799\)](#).

2. Select .

A blank text box appears.

3. Enter text and apply formatting as needed.

You can add more text boxes, or you can add a [trend chart \(on page 2802\)](#), [current value table \(on page 2803\)](#), or a [value card \(on page 2803\)](#) to the display.

Access a Display

1. In the upper-right corner of Trend Client, select .

A list of displays that you have saved appears.

2. Select the display that you want to access.

The display appears in the main section.



Tip:

If you want to remove the legends and statistics, and arrange the items in the display vertically with two elements in each row, select  and then **Column View**. If you want to view only the trend charts, select  and then **Stacked View**.

Provide a Title to a Display

1. [Access Trend Client \(on page 2799\)](#).
2. In the **Click to add title** box, enter the title of the display, and then press Enter.
The name must be unique and must not contain commas.
The title of the display is saved.

Filter Data

After adding tags to a trend chart, table, or a value card, you can filter the data based on certain criteria. You can apply the filter only to a selected item in a display or to all the items.



Note:

You cannot filter data from multiple Historian servers.

This topic describes how to filter data based on tag values. You can also [filter data based on the duration \(on page 2812\)](#).

1. Access the display in which you want to filter data.
2. Select **Filter**.
3. Select the tag, operator, and value in the corresponding drop-down list boxes. For example, suppose you have plotted a tag named Tag1 on a trend chart. If you want to plot only the values greater than 150, select **Tag1, is greater than (>)**, and **150**, respectively.
4. Ensure that the **Enabled** toggle is switched on.
5. As needed, add more conditions by selecting **Add Condition**.
6. If you want to apply the filter only to the selected item, select **Apply**. If you want to apply the filter to all the items in the display, select **Apply to All**.
The data is filtered based on the criteria you have specified.

Change the Sampling Mode

By default, the sampling mode of items in a display is interpolated (1000 samples over the last hour). You can change the sampling mode of data in a display. You can change the mode only to a selected item in a display or to all the items.


You can choose from various [sampling modes](#).

1. Access the display for which you want to change the mode.
2. Select **Mode**.
3. In the **Sampling Mode** field, select the sampling mode that you want to apply.
4. In the **Sample Increment** field, select one of the following options:
 - **By Size**: Select this option if you want each sample to contain a specific number of data points, and then enter the size. You must enter a value less than the value in the **System Configuration** page. Otherwise, an error message appears.
 - **By Time**: Select this option if you want each sample to contain the data points collected in a fixed duration of time.
5. If you want to use the sampling mode only to the selected item, select **Apply**. If you want to use the sampling mode to all the items in the display, select **Apply to All**.
The sampling mode is changed.

Change the Time Zone

By default, the local time zone is used for a display. You can change it to UTC.

1. In the upper-right corner of Trend Client, select the drop-down list box, and then select **System Config**.




The **System Configuration** page appears.

- Under **Time Display**, select the time zone you want to use.
A message appears, confirming that the time zone has been changed.
- Log out of Trend Client, and log in again.
The time zone is changed.

Export Data

- Install Microsoft Excel 2007 or 2010.
- By default, the sample size limit that is plotted on a trend chart is 2000. In addition, you can export data for a maximum duration of 30 days (43200 minutes) or 100,000 data points, whichever option contains less data. And, the default delimiter is a semicolon. If you want to change these default values:

1. In the upper-right corner of Trend Client, select the drop-down list box, and then select **System Config**.



The **System Configuration** page appears.

2. In the **Export Download Settings** section, change the default values as needed. For the delimiter, do not enter a character that is used in xml tags (such as <, >, &).

The changes are automatically saved.

You can export raw tag data or the data in a trend chart.


1. Select the charts with the tag data you want to export.
2. If you want to export raw data, select , and then select **Export Raw Data**. If you want to export trend data, select , and then select **Export Trended Data**.

The data is exported as a CSV file.

Set the Refresh Interval

By default, the content in a display is refreshed every 30 seconds. You can change this value. Remember that decreasing the interval can increase the server load.

1. In the upper-right corner of Trend Client, select the drop-down list box, and then select **System Config**.



The **System Configuration** page appears.


2. In the **Content Refresh Interval**, select the duration, and press Enter.
The refresh interval is changed.

Working with a Trend Chart

Add a Trend Chart

By default, the sample size limit that is plotted on a trend chart is 2000. If you want to change this value:

1. In the upper-right corner of Trend Client, select the drop-down list box, and then select **System Config**.



The **System Configuration** page appears.

2. In the **Analysis Sample Size Limit** field, enter the sample size, and press Enter.

The changes are automatically saved.

Similarly, maximum 30 days of data is plotted on a trend chart; you can change this value.

Trend charts are graphical representations for showing how the value of one or more items changes over time. Trend charts can show information as Line, Area, Scatter, and Statistics Charts.

1. [Access Trend Client \(on page 2799\)](#).
2. Select .
3. [Add tags for analysis \(on page 2801\)](#).
4. Select the tags, and drag and drop them into the chart area.

A trend chart is plotted for the selected tags. A blue dot appears in the row containing each tag in the **Tags** section, indicating that you have added it to the chart.



Tip:


By default, the title of the table is Chart <number>. You can rename the title as needed.

You can add more trend charts, or you can add a [current value table \(on page 2803\)](#), [value card \(on page 2803\)](#), or a [text box \(on page 2804\)](#) to the display.

Switch the Y-Axis of a Trend Chart

You can switch the y-axis to the other side of a trend chart.

In the trend chart, select the drop-down list box that is labelled after the tag name, and then select **Switch Y-Axis**.




The y-axis for the tag is shifted to the other side of the trend chart.


Change the Format of a Trend Chart

You can choose to plot each tag in any of the following formats:


- **Line:**




- **Area:**



• Scatter:




• Statistics:



If you select **Statistics**, a box and whisker chart are displayed in the trend chart. When you pause over, the minimum, maximum, average, standard deviation, and data sample counts within the interval as determined by the Historian Sampling Mode for the chart appear.

1. In the trend chart, select the drop-down list box that is labelled after the tag name, and then select **Edit**.



The **Chart Editor** window appears.

2. For the tag selected in the **Select Series** field, in the **Type** field, select the trend chart format that you want to use.
3. Select **OK**.

The format of the trend chart is changed for the selected tags.

Change the Duration of a Display

By default, the duration used for items in a display is one hour up to the current time. You can choose of the following durations:

- One hour
- Eight hours
- One day

- One week
- One month

In addition, you can set the start and end dates and timezone.

1. Select **Tags**, and then select one of the following durations:

- **1h** (one hour)
- **8h** (eight hours)
- **1d** (one day)
- **1w** (one week)
- **1m** (one month)

The items in the display are plotted for the selected duration.

2. If you want to change the start and end dates:

- a. Select **Time**.
- b. Enter values in the **Start** and **End** fields.
- c. If you want to apply the start and end dates only for the selected item, select **Apply**. If you want to apply the changes to all the items in the display, select **Apply to All**.

Access the Statistics of a Trend Chart

You can access the following statistics of a trend chart:

- First raw value
- Last raw value
- Minimum value
- Maximum value
- Count
- Raw total
- Raw average
- Raw standard deviation

1. Select the trend chart whose statistics you want to access.

2. Select **Statistics**.

The statistics of the trend chart appear.

Change the Sampling Mode of a Trend Chart

1. Select the trend chart whose sampling mode you want to change.

2. After you have added a chart(s), select **Mode** at the top of the page.

3. Select your Historian Sampling Mode from the drop-down menu.
 - If your selection for **Sampling Mode** is **Calculated**, chose your calculation from the drop-down menu.
4. Select the **Sample Increment** from the drop-down menu as either **By Size** or **By Time**.



Note:

Number of samples by size must be equal to or less than the limit defined by your System Administrator; otherwise, a warning message informs you that the data will NOT be retrieved.

5. Select **Apply** to apply to a specific chart, or select **Apply to All** to apply to all the charts in this analysis session.

Change the Scale of a Trend Chart

By default, depending on the minimum and maximum tag values plotted in a trend chart, the upper scale and lower scale of the y-axis are considered. You can, however, choose to enter these scales manually.

1. In the trend chart, select the drop-down list box that is labelled after the tag name, and then select **Edit**.



The **Chart Editor** window appears.

2. For the tag selected in the **Select Series** field, switch the **Auto Scale** toggle.
The **Min** and **Max** fields appear.
3. Enter the lower scale and upper scale values in the **Min** and **Max** field respectively, and then select **OK**.
The scale of the trend chart is changed.

Managing Favorites

Access a Favorite

1. In the upper-right corner of Trend Client, select .

A list of favorites appears.
2. Select the favorite that you want to access.

The favorite appears in the main section.

Export a Favorite


You can share your favorites with another user by exporting the favorites. When you do so, a JSON file is downloaded, containing the details of the favorites. Another user can then [import this JSON file \(on page 2816\)](#) to access your favorites.

- Open the **Action** menu for a single favorite and select on **Export**.

Your JSON file will be saved in your Downloads folder.

1. In the upper-left corner of Trend Client, select .

A list of favorites appears.
2. In the row containing the favorite that you want to export, select , and then select **Export**.



- If you want to export all your favorites, select .
- The favorites are exported as a JSON file.

Share the JSON file with the user who wants to [import the favorites \(on page 2816\)](#).

Import a Favorite

1. Copy the JSON file created by exporting the favorites that you want to import. For information, refer to [Export a Favorite \(on page 2815\)](#).
2. If you want to import the favorites to Trend Client installed on a different Historian server, update the Historian server name in all the tag names in the JSON file.

1. In the favorites section, select .

The **Import Favorites** window appears.

2. Select **Browse**, and select the JSON file that contains the favorites you want to import.
3. Select **OK**.


The favorites are imported.

Delete a Favorite

1. In the upper-left corner of Trend Client, select .

A list of favorites appears.

2. In the row containing the favorite that you want to delete, select , and then select **Delete**.



A message appears, asking you to confirm that you want to delete the favorite.

3. Select **Yes**.

The favorite is deleted.

Chapter 42. Historian Web Admin Console

Overview

Overview of the Web Admin Console

The Web Admin console is a web-based user interface, which you can use to monitor, supervise, archive, retrieve, and control data gather functions from the Historian server, a client, or one or more remote web-based nodes. It contains a diagnostic dashboard and Configuration Manager.

Using the Web Admin console, you can:

- Monitor and troubleshoot the system performance.
- Maintain and configure the Historian System.
- Retrieve and analyze archived information.
- Set up and maintain configuration and other parameters for tags, collectors, and archives.
- Perform specific supervisory and security tasks for the Historian system.

The **WhereTo** page is displayed when you logout and login to the Web Admin console without closing tab or browser.

Workaround: Logout and close the tab or browser and reopen it.

Difference Between the Web Admin Console and Historian Administrator

The following features are available in the Web Admin console and not in Historian Administrator:

- Diagnostic Manager
- Ability to add or configure mirror nodes

The following features are available in Historian Administrator and not in the Web Admin console:

- A single interface to access all the servers.
- Ability to create a calculated tag.
- Ability to assign read/write/admin groups to a tag or a set of tags.
- Ability to define enumerated sets.
- Ability to define user-defined types.
- Ability to configure an OPC HDA server.

**Note:**

Regardless of whether you perform a task using the Web Admin console or Historian Administrator, the changes are reflected in both the applications.

Actions You Can Perform Using the Web Admin Console

- Examine key operating statistics for archives and collectors, and displays them in an interactive user interface.
- Mirror stored data on multiple nodes to provide high levels of data reliability and redundancy. With Data Mirror, you can have continuous data read and write functionality. Data Mirroring gives you:
 - High availability of Historian Server as any of the mirrored nodes can answer read requests.
 - Data Redundancy because data is stored in multiple locations.
- Perform archive maintenance, including:
 - Set archive size.
 - Select options and parameters.
 - Display security parameters.
 - Add and restore archives.
 - Perform routine backup and restoration tasks.
- Perform tag maintenance, including:
 - Add, delete, and copy tags.
 - Search for tags in a data source or in the Historian Database.
 - Start and stop collection on a tag.
 - Configure display, and edit tag parameters and options.
 - Display trend data for selected tags.
- Perform data collector maintenance, including:
 - Add or delete collectors.
 - Configure, display, and edit parameters for all types of collectors.
 - Create calculation formulas.
 - Display performance trends for selected collectors.

Access the Web Admin Console

[Install Historian Web-based Clients \(on page 154\)](#).

1. In a web browser, enter a URL in the following format: `https://<web server name>/historian-visualization/hwa#/home`, where `<web server name>` is the computer name on which you have installed the Web Admin console.


The login page appears.

2. Log in with your username and password.
The Web Admin console appears.

Understanding the Interface

Understand the Historian Interface

The main interface consists of several panels or windows and appears as shown in the following image:



The elements for this interface are defined as follows:

Table 407. Interface Descriptions

Number	Item	Description
1	Dashboard	This link at the top left of the page opens the Historian Dashboard page – the one that you are currently viewing, which displays the overall picture of the system health.
2	Configuration	This link opens the configuration panel. From there, you can view and modify the details of collectors, client services, data stores, tags

Table 407. Interface Descriptions (continued)

Number	Item	Description
		and active jobs. For more information, refer to the Configuration Panel (on page 2830) topic.
3	Auto / Manual Refresh	If Auto Refresh is ON, then the page is refreshed automatically. If Auto Refresh is OFF, then you can manually refresh the page or the individual section of the dashboard by selecting the icon.
4	Data Node	This panel displays the basic information of the nodes (Primary Node & Mirror Nodes) currently available. To view the details of a particular node, select the Details button of the node. The Data Node page appears.
5	Read Sample Rate	This panel gives you the trend of the average read sample rate across all archives in the data store per sample per minute. You can choose the time scales by selecting on the time options provided on the top right area of the page. To scale the panel, select the icon. Receive Rate This panel gives you the trend of the recent rate at which the samples have been received per minute. You can choose the time scales by selecting on the time options provided on the top right area of the page. To scale the panel, select the icon.
6	Collectors	This panel displays the details of all the unhealthy collectors connected to the system. To view the details of a particular collector, select the Details button. The Collector Detail Diagnostics window appears. To view all the collectors in the system select the Show All Collectors button. The Configuration Page appears. For more information on the collector panel, refer to the Collector Statistics topic.
7	Clients	This panels displays the client statistics of the top five read and write clients in the order of the load that they impose on the server. For more information, refer to the Client Statistics topic.
8	Color codes	The Error, Warning, and Information color codes are displayed based on the status of the Data Node, Collectors or Clients.

Client Panel

The Client panel in the Dashboard shows the details of all the connected clients in the system in the order of their fault levels.


IP	Name	Connected On	Last Activity On	Queries/Min	Avg Query Exec Time	Last Query Exec Time	Retrieved Samp/Min	Write Samp/Min
[::ffff:3.234.223.55]	NT AUTHL	12/16/2014 04:15:11 PM	-	0	0	0	0	0
[::ffff:3.234.223.55]	NT AUTHL	12/16/2014 04:15:11 PM	-	0	0	0	0	0
[::ffff:3.234.221.92]	\isa	12/16/2014 04:15:13 PM	-	0	0	0	0	0
[::ffff:3.234.221.92]	\isa	12/16/2014 04:15:13 PM	-	0	0	0	0	0
[::ffff:3.234.223.232]	NT AUTHL	12/16/2014 04:15:30 PM	-	0	0	0	0	0
[::ffff:3.234.223.232]	NT AUTHL	12/16/2014 04:15:30 PM	-	0	0	0	0	0
[::ffff:60.1.1.10]	\isa	12/16/2014 04:15:36 PM	12/16/2014 07:49:01 PM	5	0	0	17	0
[::ffff:60.1.1.10]	DHS\WINL	12/16/2014 04:18:09 PM	-	0	0	0	0	0
[::ffff:60.1.1.10]	WIN-6E5...	12/16/2014 07:49:10 PM	12/16/2014 07:49:14 PM	7	0	0	75	0
[::ffff:60.1.1.10]	WIN-6E5...	12/16/2014 07:49:10 PM	12/16/2014 07:49:14 PM	30	0	0	0	0

Table 408. Client Statistics

Field	Description
Connection	Indicates the status of the current connection.
Machine Name	The host name from where the client is connected.
Log-In User Name	The user name with which the client is connected.
Connected On	The date and time when the connection was established.
Last Activity	On The time when the last read and write request was made.
Queries/Min	The current rate at which the query requests are made.
Average Query Execution Time	The average time taken to execute a query.
Timed Out Reads	The number of timed out read requests made by clients. This counter increments when a query made by a client is taking longer time than "Max Query Time" or returning more samples than specified in the "Max Query Intervals".
Samples Written/Min	The current rate at which the data samples are written.
Details	Select this button to view more client details. To view all the clients, select the Show All Clients button. The All Clients page appears

Client Details

This page, which is accessed from the Client Statistics panel in the dashboard, shows the following additional detail for a client.



Field	Description
Named Client/IP	The name of the client or IP address from where the client is connected.
Last Query Exec Time	The time taken to execute the last query.
Retrieved Samples/Min	The current rate at which the data samples are received. For more information, refer to the Client Statistics topic.


Collector Panel

The Collector panel in the Dashboard shows details of all the collectors whose performance does not meet the required performance status. The collector statistics panel displays data described in the following table. Select the Show All Collectors button to view all the collectors connected to the system. The View All Collectors page is displayed.

Field	Description
Connection	Indicates the status of the current connection. "Running" (Green) indicates that the collector is operating. "Stopped" (Red) indicates that it is in pause mode and not collecting data. "Unknown" indicates that status information about the collector is unavailable at present, perhaps as a result of a lost connection between collector and server.
Name	The name of the computer the collector is running on.
Overruns Since Yesterday	The overruns in relation to the total events collected for the past 24 hours. This value is calculated by using the following equation: $OVERRUN_PCT = \frac{OVER-$

Field	Description
	$\text{RUNS} / (\text{OVERRUNS} + \text{TOTAL_EVENTS_COLLECTED})$ <p>Overruns are a count of the total number of data events not collected on their scheduled polling cycle. In normal operation, this value should be zero. You may be able to reduce the number of overruns on the collector by increasing the tag collection intervals (per tag).</p>
Out of Order Since Yesterday	<p>The number of samples within a series of timestamped data values normally transmitted in sequence have been received out of sequence for the past 24 hours. This field applies to all collectors. Even though events are still stored, a steadily increasing number of out of order events indicates a problem with data transmission that you should investigate. For instance, a steadily increasing number of out of order events when you are using the OPC Collector means that there is an out of order between OPC Server and the OPC Collector. This may also cause an out of order between the OPC Collector and the Data Archiver, but that is not what this statistic indicates.</p>
Reconnects/Day	Displays the number of reconnections that happened in the last 24 hours.
Last Samples Received	Displays the delayed data sample duration.
Comments	Displays the comments if any.
Details	Select this button to view the Collector Detail Diagnostics

Selecting the Details option for a particular collector pops up a display that shows the current statistics on the operation of that selected data collector.



To view or modify the configuration details of the collector, select the **Configure** button. The statistics displayed on this page are computed independently on various time scales and schedules. As a result, they may update at different times. You can choose the time scales by selecting on the time options provided on the top right area of the page.

The collector detail diagnostics page has the following types of fields.

- Trendable Fields
 - These fields can be trended.
 - These fields can be distinguished by the trend icon next to the field name.
 - To graphically view a particular trendable field based on the timestamp, select on the field name.
- Non-Trendable Fields
 - These fields cannot be trended.
 - These fields have no trend icon next to the field name.

Table 409. Trendable Fields

Field	Description
Report Rate	This display is a trend chart that displays the average rate at which data is coming into the server from the selected collector. This is a general indicator of load on the Historian collector. Since this chart displays a slow trend of compressed data, it may not always match the instantaneous value of Report Rate displayed in the Collector panel of the System Statistics page.
Compression	This display is a trend chart that displays the effectiveness of collector compression. If the chart displays a low current value, you can widen the compression deadbands to pass fewer values and increase the effect of compression.
Overruns Percent	This trend chart displays the value at which data overruns are occurring. This value is calculated by the following equation: $\text{OVERRUN_PCT} = \frac{\text{OVERRUNS}}{(\text{OVERRUNS} + \text{TOTAL_EVENTS_COLLECTED})}$ Overruns are a count of the total number of data events not collected. Under normal conditions, the current value should always be zero. If the current value is not zero, which indicates that data is being lost, you should take steps to reduce peak load on the system, by increasing the collection interval.
Total Events Collected	Counts the total number of events collected from the data source by the collector.
Total Events Reported	Counts the total number of events reported to the Historian archive from the collector. This number may not match the Total Events Collected field due to collector compression.
Out of Order	The number of samples within a series of timestamped data values normally transmitted in sequence have been received out of sequence since collector startup. This field applies to all collectors. Even though events are still stored, a steadily increasing number of out of order events indicates a problem with data transmission that you should investigate. For instance, a steadily increasing number of out of order events when you are using the OPC Collector means that there is an out of order between the OPC Server and the OPC Collector. This may also cause an out of order between the OPC Collector and the data archiver but that is not what this statistic indicates.
Minimum Event Rate	Specifies the minimum number of data samples per minute sent to the archiver from all sources.

Table 409. Trendable Fields (continued)

Field	Description
Maximum Event Rate	Specifies the maximum number of data samples per minute sent to the archiver from all sources.
Status	The current status of collection. "Running" indicates that the collector is operating. "Stopped" indicates that it is in pause mode and not collecting data. "Unknown" indicates that status information about the collector is unavailable at present, perhaps as a result of a lost connection between collector and server

Table 410. Non-Trendable Fields

Field	Description
Last Sample Timestamp	Displays when the last data sample was written.
Redundancy	Indicates whether collector redundancy is enabled or disabled.
Machine Name	Displays the machine name where the collector is running.
Tag#	Displays the number of tags added to the collector.

Data Node Panel

The Data Node panel displays the basic information of the Historian Data Archivers (Primary Node plus Mirrors) currently available.

Name	IP	Reason	Details
DataArchiver_G51BGG...	G51BGG72E		

The Data Node panel displays data as described in the following table:

Field	Description
Connection	Indicates the status of the current connection. "Running" (Green) indicates that the Data Archiver is active. "Stopped" (Red) indicates that the Data Archiver is inactive. "Pause" indicates that the user has manually paused it.

Field	Description
Name	The logical name of the service.
IP	The IP address or the host name of the service.
Reason	Displays why the Data Node is not performing as expected. The reason is a warning message for the disk running out of space or memory. To view the details of the problem, move the mouse over the reason.
Details	Select this button to view the Data Node Detail Diagnostics.


Data Node Detail Diagnostics

The Data Node Detail diagnostics displays the data described in the following table. For each field, you can see the graphical representation of the values based on the time scales selected.



Note:

The statistics displayed on this page are computed independently on various time scales and schedules. As a result, they may update at different times.



You can choose the time scales by selecting on the time options provided on the top right area of the page. To graphically view a particular parameter based on the timestamp, select the chart icon of the parameter. Select the data store available with the selected data node to view its disk free space and its statistics.

Table 411. Utilization Stats

Field	Description
Memory Utilization	Indicates how much server memory is being consumed.
Write Cache Hit Ratio	The hit ratio of the write cache in percent of total writes. It is a measure of how efficiently the system is collecting data and should typically range from 95 to 99.99%. If the data is changing rapidly over a wide range, however, the hit percentage drops significantly because current values differ from recently cached values. More regular sampling may increase the hit percentage. Out of order data also reduces the hit ratio.
Archive Compression	The current effect of archive data compression. If the value is zero, it indicates that archive compression is either ineffective or turned off. To increase the effect of data compression, increase the value of archive compression deadbands on individual tags in the Tag Maintenance page to activate compression. In computing the effect of archive compression, Historian counts internal system tags as well as data source tags. Therefore, when working with a very small number of tags and with compression disabled on data source tags, this field may indicate a value other than zero. If you use a realistic number of tags, however, system tags will constitute a very small percentage of total tags and will therefore not cause a significant error in computing the effect of archive compression on the total system.
Failed Writes	The number of samples that failed to be written. Since failed writes are a measure of system malfunctions or an indication of offline archive problems, the value shown in the display should be zero. If you observe a non-zero value, investigate the cause of the problem and take corrective action. The Historian also generates a message if a write fails. Note that the message only appears once per tag, for a succession of failed writes associated with that tag. For example, if the number displayed in this field is 20, but they all pertain to one Historian tag, you will only receive one message until the Historian tag is healthy again.
Out of Order	The number of samples within a series of timestamped data values normally transmitted in sequence have been received out of sequence since collector startup. This field applies to all collectors. Even though events are still stored, a steadily increasing number of out of order events indicates a problem with data transmission that you should investigate. For example, a steadily increasing number of out of order events when you are using the OPC Collector

Table 411. Utilization Stats (continued)

Field	Description
	means that there is an out of order between the OPC Server and the OPC Collector. This may also cause an out of order between the OPC Collector and the data archiver but that is not what this statistic indicates.

Table 412. Process Rate

Field	Description
Read Queue Rate	Specifies the number of read requests processed per minute, that came into the archiver from all clients. A read request can return multiple data samples.
Write Queue Rate	Specifies the number of write requests processed per minute, that came into the archiver from all clients. A write request can contain multiple data samples.
Message Queue Rate	Specifies the number of messages processed per minute.

Table 413. Queue Size

Field	Description
Read Queue Size	Displays the total number of messages present in the Read queue.
Write Queue Size	Displays the total number of messages present in the Write queue.
Message Queue Size	Displays the total number of messages present in the Message queue.

Table 414. Disk Usage

Field	Description
Disk Free Space	The amount of disk space (in MB) left in the current archive.
Est. Days to Fill	<p>The amount of time left before the archive is full, based on the current consumption rate. At that point, a new archive must be opened (could be automatic). To increase the days to full, you must reduce the Consumption Rate as noted above.</p> <p>To ensure that collection is not interrupted, you should make sure that the Automatically Create Archives option is enabled in the Data Store Maintenance page (the Global Options section).</p>

Table 414. Disk Usage (continued)

Field	Description
	<p>You may also want to enable Overwrite Old Archives if you have limited disk capacity. Enabling overwrite, however, means that some old data will be lost when new data overwrites the data in the oldest online archive. Use this feature only when necessary.</p> <p>The Estimated Days Until Full field is dynamically calculated by the server and becomes more accurate as an archive gets closer to completion. This number is only an estimate and will vary based on a number of factors, including the current compression effectiveness. The System sends messages notifying you at 5, 3, and 1 days until full.</p>
Consumption Rate	<p>The speed at which you are using up archive disk space. If the value is too high, you can reduce it by slowing the poll rate on selected tags or data points or by increasing the filtering on the data (widening the compression dead-band to increase compression).</p>

Configuration Panel

The Configuration page displays the current system status and performance statistics of [Collectors \(on page 2822\)](#) and [Clients \(on page 2820\)](#), and allows configuration of the various components of the Historian system. This page displays the data described in the following table.

The screenshot shows the 'Collectors' and 'Clients' sections of the Historian configuration panel. The 'Collectors' table has 11 columns: Name, Rate, Overruns, Out of Order, Events Collected, Events Reported, Last Change, Redundancy, Details, and View/Edit. It lists several collectors with zero values for Rate, Overruns, and Out of Order. The 'Clients' table has 10 columns: IP, Name, Connected On, Last Activity On, Queries/Min, Avg Query Exec Time, Last Query Exec Time, Retrieved Samp/Min, and write Samp/Min. It shows one client connected on 12/16/2014 at 04:15:11 PM.

Collectors (7)										
Name	Rate	Overruns	Out of Order	Events Collected	Events Reported	Last Change	Redundancy	Details	View/Edit	
WIN-1J2J6EM33NA_JFXI	0	0	0	0	0	-		(i)	>	
WIN-6E57QURPAEC_Calculation	0	0	0	0	0	-		(i)	>	
WIN-6E57QURPAEC_OPC_KEPware_KEPSe...	0	0	0	0	0	-		(i)	>	
WIN-6E57QURPAEC_OPC_Matikon_OPC_S...	0	0	0	0	0	-		(i)	>	
WIN-6E57QURPAEC_OPCAE_Matikon_OPC...	0	0	0	0	0	-		(i)	>	
WIN-6E57QURPAEC_Simulation	0	0	0	0	0	-		(i)	>	
WIN-6E57QURPAEC_WindowsPerfMon	0	0	0	0	0	-		(i)	>	

Clients (12)									
IP	Name	Connected On	Last Activity On	Queries/Min	Avg Query Exec Time	Last Query Exec Time	Retrieved Samp/Min	write Samp/Min	
[::ffff:3.234.223.55]	NT AUTHL...	12/16/2014 04:15:11 PM		-	0	0	0	0	

Table 415. Configuration Page Fields

Field	Description
Services	Displays the number of services running. For more information, refer to the Configure Services (on page 2834) section.
Data Stores	Displays the number of data stores configured in the system. For more information, refer to the Data Stores (on page 2833) section.
Tags	The number of tags available with the data archiver. For more information, refer to the Tags (on page 2835) section.
Active Jobs	Displays the number of current active jobs in the system. For more information, refer to the Jobs Page (on page 2834) section.
Collectors	Displays the details of all the collectors available. For configuration of Collectors (on page 2822) , refer to the Configure Collectors section.
Clients	Displays the details of all the clients present in the system. For more information, refer to the Clients (on page 2820) section.

Configure Collectors

The Collectors panel in the Configuration page displays a mix of similar and additional data as the Dashboard, as described in the following table.

Field	Description
Connection	Indicates the status of the current connection. "Running" indicates that the collector is operating. "Stopped" indicates that it is in pause mode and not collecting data. "Unknown" indicates that status information about the collector is unavailable at present, perhaps as a result of a lost connection between the collector and server.
Name	The collector ID, which is used to identify the collector in an Historian system.
Rate	The current rate in number of samples/minute at which the server is receiving data from the collector. It is a measure of the collection rate and also of data compression activity. A value equal to the data acquisition rate, when Collector Compression Percent is zero, indicates that every data value received from the data source is being reported to the server. This means that the collector is not performing any data compression. You can lower the report rate, and make the system more efficient, by increasing the data compression at

Field	Description
	the collector. To do this, widen the collection compression deadbands for selected tags.
Overruns	<p>The overruns in relation to the total events collected since startup. This value is calculated by using the following equation: $OVERRUN_PCT = \frac{OVERRUNS}{(OVERRUNS + TOTAL_EVENTS_COLLECTED)}$ Overruns are a count of the total number of data events not collected on their scheduled polling cycle. In a normal operation, this value should be zero. You may be able to reduce the number of overruns on the collector by increasing the tag collection intervals (per tag).</p>
Out of Order	<p>The number of samples within a series of timestamped data values normally transmitted in sequence that have been received out of sequence since collector startup. This field applies to all collectors. Even though events are still stored, a steadily increasing number of out of order events indicates a problem with data transmission that you should investigate. For example, a steadily increasing number of out of order events when you are using the OPC Collector means that there is an out of order between the OPC Server and the OPC Collector. This may also cause an out of order between the OPC Collector and the data archiver but that is not what this statistic indicates.</p>
Events Collected	Counts the total number of events collected from the data source by the collector.
Events Reported	Counts the total number of events reported to the Historian archive from the collector. This number may not match the Total Events Collected field due to collector compression.
Last Change	The timestamp when the last collection happened.
Redundancy	<p>Displays the current redundancy status of the collector. "Active" state indicates that the collector is currently collecting data and "Standby" indicates that the collector is the standby for the primary collector.</p> <div data-bbox="511 1612 1421 1789" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: This status will be displayed only when the Redundant Collector property of the collector is Enabled.</p> </div>
Details	Select this button to view the Collector Detail Diagnostics. .

Field	Description
View/Edit	Select this button to examine or modify configuration parameters for any collector in your system. For more information, refer Collector Details Page.

Configure Clients

This page shows all clients in the system. For more information on the fields, refer to the field and description table in the [Client Statistics \(on page 2820\)](#) topic.

IP	Name	Connected On	Last Activity On	Queries/Min	Avg Query Exec Time	Last Query Exec Time	Retrieved Samp/Min	Write Samp/Min
[::ffff:3.234.223.55]	NT AUTHL	12/16/2014 04:15:11 PM	-	0	0	0	0	0
[::ffff:3.234.223.55]	NT AUTHL	12/16/2014 04:15:11 PM	-	0	0	0	0	0
[::ffff:3.234.221.92]	isa	12/16/2014 04:15:13 PM	-	0	0	0	0	0
[::ffff:3.234.221.92]	isa	12/16/2014 04:15:13 PM	-	0	0	0	0	0
[::ffff:3.234.223.232]	NT AUTHL	12/16/2014 04:15:30 PM	-	0	0	0	0	0
[::ffff:3.234.223.232]	NT AUTHL	12/16/2014 04:15:30 PM	-	0	0	0	0	0
[::ffff:60.1.1.10]	isa	12/16/2014 04:15:36 PM	12/16/2014 07:49:01 PM	5	0	0	17	0
[::ffff:60.1.1.10]	DHS\WINL	12/16/2014 04:18:09 PM	-	0	0	0	0	0
[::ffff:60.1.1.10]	WIN-685-	12/16/2014 07:49:10 PM	12/16/2014 07:49:14 PM	7	0	0	75	0
[::ffff:60.1.1.10]	WIN-685-	12/16/2014 07:49:10 PM	12/16/2014 07:49:14 PM	30	0	0	0	0

Data Stores Page

The data store Information page lets you read, add, rename, and delete the data stores. To view the data stores, select the Configuration link, and then select **Data Stores**. The **Data Stores** page appears and displays the list of available data stores and their details. For more information, refer to the **Configure Data Stores** section.

The following table describes the fields available in the **Data Stores** page:

Field	Description
Data Store Name	Displays the name of the data store.
Type	Indicates whether the storage type is Historical or SCADA buffer.
Description	Displays the description of the data store.
Is Default	Indicates whether the data store is the default store. Select Yes if you want to set the data store as the default data store.
Number of Tags	Displays the number of tags the data store contains.

Field	Description
State	The state that the data store is in. The data store state is always running until you delete the data store.
Edit	Select this button to edit the data store configuration.
Delete	Select this button to delete the data store.
Details	Select this button to view the archive details of the data store.

Jobs Page

When you add a mirror node, replicate a node, re-synch an archive file, back up an archive file or restore an archive file then a job is initiated with a Job ID, which will be seen on the user interface of the Historian Web Admin console.

To view the jobs, you can select the Active Jobs link in any of the Collector, Client, or Configuration pages. You can view the number of jobs that are currently running on the system from this page and can also search a job based on its Job ID by entering the Job ID and selecting the search button in the search field.

Field	Description
Status	Displays the current status of the job (Succeeded, Failed and In Progress) in different color codes. If you see a Failed job, you can expand it to see the description of the failure.
Job ID	The unique ID given to a particular job.
Type	The type of job.
Description	The description of the job.
Percentage	The percentage of completion of the job.
Start Time	The time at which the job started.
Complete Time	The time at which the job was completed.

Services Page

The Services page displays all the services running in the system. You can also add a mirror node from the Services page. To refresh the services page, select the  Refresh icon.

By default, a node will have four services installed during creation:

- Client Manager
- Configuration Manager
- Data Archiver
- Diagnostic Manager

Table 416. Service Configuration

Field	Description
Computer Name	The name of the computer the service is currently running.
Service Name	The name of the service and its current status.
Port	The port number. After you change the port number of a service, ensure that it is updated in the following registry key: <code>HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services</code> , and restart the service.
Type	The type of the node service.

Editing a Service

1. Select the **Edit** icon.
The Edit Service Configuration window appears.
2. Modify the configuration details.
3. Select **Save**.

Tags Page

To display the Tags page, select the Tags link in any of the Collectors, Clients, or Configuration page. The Tags page lets you read and modify all tag parameters of the Historian system. To access information on a specific tag or group of tags, however, you must first search for the tags.

You can search for tags in the Historian Tag Database by selecting the Search button or the Advanced Search button. You can also add tags manually or from the collector by selecting the appropriate icons on the Tags page.

The Tags page has two sections: Tag Viewer and Tag Editor.

Tag Viewer

Displays all the tags available in the system. You can choose to display the total number of tags you want to view by selecting the Show entries. To view all the tags, select the page numbers available at the bottom right of the section.

From this section, you can perform the following operations on the tags:

- Add Tag
- Delete Tag
- Rename Tag
- Search for Tags
- Filtering Tags
- Copy Tag
- Display a Tag

To select a tag, select on the tag name on the page. You can select multiple tags at a time. To clear your selection, select the Clear Selections button. To edit the tag parameters, select the tag and select the Edit button. The tag details are displayed in the Tag Editor. If you select multiple tags and select the Edit button, then the details of the first tag are displayed and when you update, **all** of the common parameters of the selected tags are updated.

Tag Editor

In this section, you can view and edit specific tag parameters and options. To view all the tags, select the page numbers available at the bottom right of the section.

The Tag Editor allows you to edit specific tag parameters and options for one or more selected tags. To modify the values, enter new values in the appropriate fields and then select the Update button at the bottom of the page to apply the changes. The Update button, when selected, applies all parameter changes you have made on any tabs in this page. If you want to cancel changes and return to the original values or settings, open a different page and then return to the Tag Details page without selecting the Update button. For more information, refer to the following sections.

The Advanced Section

To display or edit advanced parameters, select **Advanced**. To modify the values, enter new values in the appropriate fields and then select the Update button at the bottom of the page to apply the changes. Until you select the Update button, entering a new value changes the display of the field name to blue. The fields in the **Advanced** section contain the following information:

Table 417. Data Collection Options

Field	Description
Time Assigned By	<p>The source of the timestamp for a data value is either the collector or the data source. All tags, by default, have their time assigned by the collector. When you configure a tag for a polled collection rate, the tag is updated based on the collection interval. For example, if you set the collection interval to 5 seconds with no compression, the archive is updated with a new data point and timestamp every 5 seconds, even if the value is not changing. However, if you change the Time Assigned By field to Source for the same tag, the archive updates only when the device timestamp changes. For example, if the poll time is still 5 seconds, but the timestamp on the device does not change for 10 minutes, no new data is added to the archive for 10 minutes.</p> <div data-bbox="513 806 1414 938" style="border: 1px solid #0070c0; border-radius: 10px; padding: 10px; background-color: #e6f2ff;">  Note: This field is disabled for Calculation and Server-to-Server tags. </div>
Time Zone Bias	<p>The number of minutes from GMT that should be used to translate timestamps when retrieving data from this tag. For example, the time zone bias for Eastern Standard time is -300 minutes (GMT-5). This property is not used during collection. Use this option if a particular tag requires a time zone adjustment during retrieval other than the client or server time zone. For example, you can retrieve data for two tags with different time zones by using the tag time zone selection in the iFIX chart.</p>
Time Adjustment	<p>If the Server-to-Server collector is not running on the source computer, select the Adjust for Source Time Difference option if you want to compensate for the time difference between the source archiver computer and the collector computer. The Time Adjustment field applies only to Server-to-Server tags that use a polled collection type.</p>
Data Store	<p>The data store to which the tag belongs.</p>

The Collection Section

To display or edit collection parameters, select **Collection**. To modify the values, enter new values in the appropriate fields and then select the Update button at the bottom of the page to apply the changes. Until you select the Update button, entering a new value changes the display of the field name to blue. The fields in the **Collection** section contain the following information:

Table 418. Data Source

Field	Description
Collector	The name of the collector for the selected tag. Select the drop-down arrow to display a list of all collectors.
Source Address	<p>The address for the selected tag in the data source. Select the Browse button (...) to display a browse window. Leave the Source Address field blank for Calculation and Server-to-Server tags.</p> <div data-bbox="511 598 1412 819" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px;"> <p> Note: When exporting or importing tags using the EXCEL Add-In, the Calculation column, not the SourceAddress column, holds the formulas for the Calculation or Server-to-Server tags.</p> </div>
Data Type	<p>A list of data types.</p> <div data-bbox="511 913 1412 1134" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px;"> <p> Note: If you change the data type of an existing tag between a numeric and a string or binary data type (and vice versa), the tag's compression and scaling settings will be lost.</p> </div>
Data Length	The number of bytes for a fixed string data type. This field is active only for fixed string data types. This field is adjacent to the Data Type field.
Enumerated Set Name	The name of the Enumerated Set that can be assigned to the tags. Select the Browse button (...) to display the Define Enumerated Set window.
Is Array Tag	Indicates the tag is an array tag.
Calc Type	Indicates the type of tag. Analytic Tag, Raw tag or Expression Tag.

Choosing a Data Type

The main use of the scaled data type is to save space. Instead of using 4 bytes of data, it uses only 2 bytes. The scaled data type accomplishes this by storing the data as a percentage of the EGU limit. This saving of space results in a loss of precision. Because of the way that the scaled data type stores data, changing of the EGU limits will result in a change in the values that are displayed. For example, if the original EGU values were 0 to 100 and a value of 20 was stored using the scaled data type and if the EGUs are changed to 0 to 200 at a later date, that value of 20 will be represented as 40.

Table 419. Collection Options

Field	Description
Collection	Select the appropriate option to enable or disable collection for this tag. The default setting is Enabled. If you disable collection for the tag, Historian stops collecting data for the tag, but does not delete the tag or any data.
Collection Type	Select the type of data collection used for this tag, which can be polled or unsolicited. Polled means that the data collector requests data from the data source at the collection interval specified in the polling schedule. Unsolicited means that the data source sends data to the collector whenever necessary (independent of the data collector polling schedule).
Collection Interval	Enter the time interval between readings of data from this tag. With Unsolicited Collection Type, this field defines the minimum interval at which unsolicited data will be sent by the data source.
Collection Offset	<p>Used with the collection interval to schedule collection of data from a tag.</p> <div data-bbox="516 951 1414 1438" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note:</p> <p>The minimum value you can enter in this field is 1000 ms. If you enter a value in milliseconds, note that the value must be in intervals of 1000 ms. For example, 1000, 2000, and 3000 ms are valid values, but 500 and 1500 ms are invalid values. For example, if you want to collect a value for a tag every hour at thirty minutes past the hour (12:30, 1:30, 2:30, and so on), you would enter a collection interval of 1 hour and an offset of 30 minutes. As another example, if you want to collect a value each day at 8am, you would enter a collection interval of 1 day and an offset of 8 hours.</p> </div>
Time Resolution	Select the precision for timestamps, which can be either seconds, milliseconds or microseconds.

Condition-Based Collection

Condition-based collection is a method to control the storage of data for data tags by assigning a condition. Data is always collected but it is written to the Data Archiver only if the condition is true; otherwise, the collected data is discarded. This condition is driven by a trigger tag; a tag collected by the collector evaluating the condition. Ideally, condition-based collection should be used only with tags that are updating faster than the trigger tag.

**Note:**

Condition-based collection is supported only by the archiver and collectors of Historian version 4.5 and above.

Condition-based collection can be used to archive only the specific data that is required for analysis, rather than archiving data at all times, as the collector is running. For example, if a collector has tags for multiple pieces of equipment, you can stop collection of tags for one piece of equipment during its maintenance.

It is typically used on tags that use fast polled collection but you don't want to use collector compression. While the equipment is running, you want all the data but when the equipment is stopped, you don't want any data stored. The trigger tag will also typically use polled collection. But, either tag could use unsolicited collection.

The condition is evaluated every time data is collected for the data tag. When a data sample is collected, the condition is evaluated and data is either queued for sending to the archiver, or discarded. If the condition cannot be evaluated as true or false (for example, if the trigger tag contains a bad data quality or the collector is not collecting the trigger tag), the condition is considered true and the data is queued for sending.

No specific processing occurs when the condition becomes true or false. If the condition becomes true, no sample is stored to the data tag using that condition, but the data tag will store a sample the next time it collects. When the condition becomes false, no end of the collection marker is stored until the data tag is collected. For example, if the condition becomes false at 1:15 and the data tag gets collected at 1:20, the end of collection marker is created at 1:20 and has a timestamp of 1:20, not 1:15.

This condition-based collection is applicable only to the following collectors:

- Simulation Collector
- OPC Collector
- iFIX collector
- PI Collector

Condition-based collection does not apply to alarm collectors.

Field	Description
Condition Based	Select the appropriate option to enable or disable condition-based collection for a tag. The default setting is Disabled.

Field	Description												
Trigger Tag	The name of the tag used in the condition. Use the browse button to select a trigger tag from the list of tags associated with the collector.												
Comparison	<p>Select the appropriate comparison operator from the drop-down list. The following is a list of comparison operator parameters:</p> <table border="1" data-bbox="509 495 1419 1144"> <tbody> <tr> <td data-bbox="509 495 691 604">< =</td> <td data-bbox="691 495 1419 604">Setting condition as Trigger Tag value less than or equal to the Compare Value.</td> </tr> <tr> <td data-bbox="509 604 691 714">> =</td> <td data-bbox="691 604 1419 714">Setting condition as Trigger Tag value greater than or equal to the Compare Value.</td> </tr> <tr> <td data-bbox="509 714 691 823"><</td> <td data-bbox="691 714 1419 823">Setting condition as Trigger Tag value less than the Compare Value.</td> </tr> <tr> <td data-bbox="509 823 691 932">></td> <td data-bbox="691 823 1419 932">Setting condition as Trigger Tag value greater than the Compare Value</td> </tr> <tr> <td data-bbox="509 932 691 1041">=</td> <td data-bbox="691 932 1419 1041">Setting condition as Trigger Tag value equals the Compare Value.</td> </tr> <tr> <td data-bbox="509 1041 691 1150">!=</td> <td data-bbox="691 1041 1419 1150">Setting condition as Trigger Tag value not the same as the Compare Value.</td> </tr> </tbody> </table> <p>Collection will resume only when the value of the triggered Undefined tag changes. This is considered as an incomplete configuration, so condition-based collection is turned off and all of the collected data is sent to the archiver.</p>	< =	Setting condition as Trigger Tag value less than or equal to the Compare Value.	> =	Setting condition as Trigger Tag value greater than or equal to the Compare Value.	<	Setting condition as Trigger Tag value less than the Compare Value.	>	Setting condition as Trigger Tag value greater than the Compare Value	=	Setting condition as Trigger Tag value equals the Compare Value.	!=	Setting condition as Trigger Tag value not the same as the Compare Value.
< =	Setting condition as Trigger Tag value less than or equal to the Compare Value.												
> =	Setting condition as Trigger Tag value greater than or equal to the Compare Value.												
<	Setting condition as Trigger Tag value less than the Compare Value.												
>	Setting condition as Trigger Tag value greater than the Compare Value												
=	Setting condition as Trigger Tag value equals the Compare Value.												
!=	Setting condition as Trigger Tag value not the same as the Compare Value.												
Compare Value	Enter an appropriate target value which is compared against the value of the triggered tag. Make sure while using '=' and '!=' comparison parameters, that the format of the compared value and triggered tag are similar. For example, for a float type trigger tag, the compare value must be a float value; otherwise, the condition result is an invalid configuration, condition-based collection is disabled, and all the data is sent to the archiver.												
End of Collection Markers	Select the appropriate option to enable or disable end of collection markers. The default setting is enabled. When the condition becomes false, all the tag's values are marked as "Bad", and subquality as "ConditionCollection-Halted." Trending and reporting applications can use this information to indicate that the real-world value is unknown after this time until the condition												

Field	Description
	becomes true and a new sample is collected. If disabled, a bad data marker is not inserted when the condition becomes false.

Compression Tab

To display or edit compression parameters, select **Compression**. To modify the values, enter new values in the appropriate fields and then select the Update button at the bottom of the page to apply the changes. Until you select the Update button, entering a new value changes the display of the field name to blue.



Note:

The **Compression** section is disabled for Array Tags.

The fields in the **Compression** section contain the following information:

Table 420. Collector Compression

Field	Description
Collector Compression (Enabled, Disabled)	Select the appropriate option to enable or disable compression at the collector level. Collector compression applies a smoothing filter to incoming data by ignoring incremental changes in values that fall within a deadband centered on the last reported value. The collector reports any new value that falls outside the deadband to the Historian archive and then centers the deadband on the new value.
Collector Deadband	<p>The current value of the compression deadband. This value can be computed as a percentage of the span, centered on the data value or given as an absolute range around the data value.</p> <div data-bbox="521 1501 574 1554" data-label="Image"> </div> <p>Note: With some OPC Servers, the whole deadband value is added to and subtracted from the last data value. This effectively doubles the magnitude of the deadband compared to other OPC Servers.</p>
Engineering Unit	Converts the deadband percentage into engineering units and displays the result. This value establishes the deadband range that is centered around the new value. When enabling Archive Compression or Collector Compres-

Table 420. Collector Compression (continued)

Field	Description
	<p>sion, the Engineering Units field represents a calculated number created to give an idea of how large a deadband you are creating in Engineering Units. The deadband is entered in percent (%) and Historian multiplies that percent by the range (Hi Engineering Units-Lo Engineering Units) to calculate the percentage in Engineering Units.</p>
Collector Compression Timeout	<p>Indicates the maximum length of time the collector will wait between sending samples for a tag to the archiver. This time is kept per tag, as different tags report to the archiver at different times. For polled tags, the Collector Compression Timeout value should be in multiples of your collection interval. After the timeout value is exceeded, the tag stores a value at the next scheduled collection interval, and not when the timeout occurred. For example, if you have a 10 second collection interval, a 1 minute compression timeout, and a collection that started at 2:14:00, then if the value has not changed, the value is logged at 2:15:10 and not at 2:15:00. For unsolicited tags, a value is guaranteed in, at most, twice the compression timeout interval. A non-changing value is logged on each compression timeout. For example, an unsolicited tag with a 1 second collection interval and a 30 second compression timeout is stored every 30 seconds. A changing value for the same tag may have up to 60 seconds between raw samples. In this case, if the value changes after 10 seconds, then that value is stored, but the value at 30 seconds (if unchanged) will not be stored. The value at 60 seconds will be stored. This leaves a gap of 50 seconds between raw samples which is less than 60 seconds. Compression timeout is supported in all collectors except the PI collector.</p>
Archive Compression (Enabled, Disabled)	<p>Select the appropriate option to enable or disable compression at the Historian archive level. If enabled, Historian applies the archive deadband settings against all reported data from the collector.</p>
Archive Deadband	<p>The current value of the archive deadband expressed as a percent of span or an absolute number. Each time the system reports a new value, it computes a line between this data point and the last archived value. The deadband is calculated as a tolerance centered about the slope of this line. When the next data point is reported, the line between the new point and the last archived point is tested to see if it falls within the deadband tolerance calcu-</p>

Table 420. Collector Compression (continued)

Field	Description
	lated for the previous point. If the new point passes the test, it is reported and is not archived. This process repeats with subsequent points. When a value fails the tolerance test, the last reported point is archived and the system computes a line between the new value and the newly archived point, and the process continues.
Engineering Unit	Converts the deadband percentage into engineering units and displays the result. This value establishes the deadband range that is centered on the new value. When enabling Archive Compression or Collector Compression, the Engineering Units field represents a calculated number created to give an idea of how large a deadband you are creating in Engineering Units. The deadband is entered in percent (%) and Historian multiplies that percentage by the range (Hi Engineering Units-Lo Engineering Units) to calculate the percentage in Engineering Units.
Archive Compression Timeout	Indicates the maximum length of time from the last stored point before another point is stored, if the value does not exceed the archive compression deadband. The data archiver treats the incoming sample after the timeout occurs as if it exceeded compression. It then stores the pending sample. For more information on Collector and Archive Corruption, refer to the Notes on Collector and Archive Compression topic.

To determine how your specific server handles deadband, refer to the documentation of your OPC Server. Example: The engineering units are 0 to 200. The deadband value is 10%, which equals 20 units. If the deadband value is 10% and the last reported value is 50, the value will be reported when the current value exceeds $50 + 10 = 60$ or is less than $50 - 10 = 40$. Note that the deadband (20 units) is split around the last data value (10 on either side.) Alternatively, you could specify an absolute deadband of 5. In this instance, if the last value was 50, a new data sample will be reported when the current value exceeds 55 or drops below 45. If compression is enabled and the deadband is set to zero, the collector ignores data values that do not change and records any that do change. If you set the deadband to a non-zero value, the collector records any value that lies outside the deadband. If the value changes drastically, a pre-spike point may be inserted. See the Spike Logic section for more details.

Understand Collector and Archive Compression

This section describes the behavior of collector and archive compression. Understanding these two Historian features will help you apply them appropriately to reduce the storage of unnecessary data. Smaller archives are easier to maintain and allow you to keep a greater time span of historical data online.

Collector compression applies a smoothing filter, inside the collector, to data retrieved from the data source. By ignoring small changes in values that fall within a deadband centered on the last reported value, only significant changes are reported to the archiver. Fewer samples reported, yields less work for the archiver and less archive storage space used. The definition of significant changes is determined by the user by setting the collector compression deadband value.

For convenience, the Historian Web Admin console calculates and shows the deadband in engineering units if you enter a deadband percentage. If you later change the high and low EGU limits, the deadband is still a percentage, but of the new limits. A 20% deadband on 0 to 500 EGU span is 100 engineering units. If you change the limits to 100 and 200, then the 20% is now 20 engineering units.

The deadband is centered on the last reported sample, not simply added to it or subtracted. If your intent is to have a deadband of 1 unit between reported samples, you need a compression deadband of 2, so that it is one to each side of the last reported sample. In an example of 0 to 500 EGU range, with a deadband of 20%, the deadband is 100 units, and the value has to change by more than 50 units from the last reported value.

Changes in data quality from good to bad, or bad to good, automatically exceed collector compression and are reported to the archiver. Any data to that comes to the collector out of time order will also automatically exceed collector compression.

It is possible for collected tags with no compression to appear in Historian as if the collector or archive compression options are enabled. If collector compression occurs, you will notice an increase in the percentage of the Compression value from 0% in the Collectors panel of the System Statistics page in Historian Administrator. When archive compression occurs, you will notice the Archive Compression value and status bar change on the System Statistics page.

For all collectors, except the File collector, you may observe collector compression occurring for your collected data (even though it is not enabled) if bad quality data samples appear in succession. When a succession of bad data quality samples appears, Historian collects only the first sample in the series. No new samples are collected until the data quality changes. Historian does not collect the redundant bad data quality samples, and this is reflected in the Collector Compression percentage statistic.

For a Calculation or Server-to-Server Collector, you may possibly observe collector compression (even though it is not enabled) when calculations fail, producing no results or bad quality data.

The effect of Collector Compression Timeout is to behave, for one poll cycle, as if the collector compression feature is not being used. The sample collected from the data source is sent to the archiver. Then the compression is turned back on, as configured, for the next poll cycle with new samples being compared to the value sent to the archiver.

Archive Compression

Archive compression can be used to reduce the number of samples stored when data values for a tag form a straight line in any direction. For a horizontal line (non-changing value), the behavior is similar to collector compression. But, in archive compression, it is not the values that are being compared to a deadband, but the slope of line those values produce when plotted against time.

Archive compression logic is executed in the data archiver and, therefore, can be applied to tags populated by methods other than collectors. Archive compression can be used on tags where data is being added to a tag by migration, or by the File collector, or by an SDK program for example.

Each time the archiver receives a new value for a tag, the archiver calculates a line between this incoming data point and the last archived value. The deadband is calculated as a tolerance centered about the slope of this line. The slope is tested to see if it falls within the deadband tolerance calculated for the previous point. If the new point does not exceed the tolerance, it is held by the archiver rather than being archived to disk. This process repeats with subsequent points. When an incoming value exceeds the tolerance, the value held by the archiver is written to disk and the incoming sample becomes held.

The effect of the archive compression timeout is that the incoming sample is automatically considered to have exceeded compression. The held sample is archived to disk and the incoming sample becomes the new held sample. If the Archive Compression value on the System Statistics page indicates that archive compression is occurring, and you did not enable archive compression for the tags, the reason could be because of internal statistics tags with archive compression enabled.



Note:

Array tags do not support Archive and Collector Compression. If the tag is an array tag, then the **Compression** tab is disabled.

General Tab

To display or edit the general parameters listed below, select **General**. To modify the values, enter new values in the appropriate fields, and then select the Update button at the bottom of the page to apply the changes. Until you select the Update button, entering a new value changes the display of the field name to blue.

Table 421. Description Panel

Field	Description
Description	The tag description of the selected tag.
EGU Description	The engineering units, if any, assigned to the selected tag. Often referred to as Unit of Measure, or UoM.
Comment	Comments, if any, that apply to the selected tag.
StepValue	This tag property is used to indicate that the actual measured value changes in a sharp step instead of a smooth linear interpolation. This option should be selected only for numeric data. Enabling this option affects only data retrieval; it has no effect on data collection or storage
Spare Configuration	The Spare 1 through Spare 5 fields list any configuration information stored in these fields.

**Note:**

Do not add or update the following spare configurations as the data may get corrupted or overwritten:

- The **Spare 5** field for Server to Server Collector and Server to Server Distributor.
- The **Spare 1** field for OSI PI Distributor.

The **Scaling** Section

Scaling converts a data value from a raw value expressed in an arbitrary range of units, such as a number of counts, to one in engineering units, such as gallons per minute or pounds per square inch. The scaled data type can serve as a third form of data compression, in addition to collector compression and archive compression, if it converts a data value from a data type that uses a large number of bytes to one that uses fewer bytes. To display or edit scaling parameters, select **Scaling**. To modify the values, enter new values in the appropriate fields and then select the Update button at the bottom of the page to apply the changes. Until you select the Update button, entering a new value changes the display of the field name to blue. The fields in the **Scaling** section contain the following information:

Table 422. Input Scaling

Field	Description
Input Scaling	Select the appropriate option to enable or disable input scaling, which converts an input data point to an engineering units value.
Hi Scale Value	The upper limit of the span of the input value. Lo Scale Value The lower limit of the span of the input value.

For example, to rescale and save a 0-4096 input value to a scaled range of 0-100, enter 0 and 4096 as the low and high input scale values and 0 and 100 as the low and high engineering units values, respectively. If a data point exceeds the high or low end of the input scaling range, then Historian logs a bad data quality point with a ScaledOutOfRange subquality. In the previous example, if your input data is less than 0, or greater than 4096, then Historian records a bad data quality for the data point. For example, a value of 4097, in this case, yields a bad data quality.

OPC Servers and TRUE Values

Some OPC Servers return a TRUE value as -1. If your OPC Server is returning TRUE values as -1, modify the following scaling settings in the **Tag Maintenance** page of Historian Administrator:

```
Hi Engineering Units = 0
Lo Engineering Units = 1
Hi Scale Value = 0
Lo Scale Value = -1
Input Scaling = Enabled
```

Configure General Collector Options

Configure General Collector Options

You can modify collector configurations from the following sections of the Collector Configuration Screen.

- Action Buttons
- Configuration Tab
- Defaults Tab
- Performance Tab
- Redundancy Tab

Table 423. Action Buttons

Button	Action
	Resumes collection of the collector.
	Pauses the collection of the collector
	Refreshes the page
Update	Updates the changes made.

Table 424. The Performance Section

Field	Description
Report Rate	This display is a trend chart that displays the average rate at which data is coming into the server from the selected collector. This is a general indicator of load on the Historian collector. Since this chart displays a slow trend of compressed data, it may not always match the instantaneous value of Report Rate displayed in the Collector panel of the System Statistics page.
Out of Order	The number of samples within a series of timestamped data values normally transmitted in sequence that have been received out of sequence since collector startup. This field applies to all collectors.
Compression	This display is a trend chart that displays the effectiveness of collector compression. If the chart displays a low current value, you can widen the compression deadbands to pass fewer values and increase the effect of compression.
Total Events Collected	Displays the number of events collected from the data source.
Total Events Reported	Displays the total number of events reported to the Historian archive from the collector.
Overruns	This trend chart displays the value at which data overruns are occurring. This value is calculated by following equation: $\text{OVERRUN_PCT} = \frac{\text{OVERRUNS}}{(\text{OVERRUNS} + \text{TOTAL_EVENTS_COLLECTED})}$ Overruns are a count of the total number of data events not collected. Under normal conditions, the current value should always be zero. If the current value is not zero, which indicates that data is

Table 424. The Performance Section (continued)

Field	Description
	being lost, you should take steps to reduce peak load on the system by increasing the collection interval.

Table 425. The Defaults Section

Field	Description
Prefix for Tag Names	Displays a prefix, if any, that is automatically added to all tag names when you browse and pick the specified collector. To change the prefix, enter a new text string and select the Update button at the bottom of the page. This field applies to all collectors except the File and Calculation collectors
Collection Type	Indicates whether this collector is configured for polled data collection or unsolicited collection.
Collection Interval	The time in milliseconds, seconds, minutes, or hours required to complete a poll of a given tag on the selected collector. It is also used in unsolicited collection. In effect, it specifies how frequently data can be read from a tag. The collection interval can be individually configured for each tag. To change it, enter a new value. NOTE: To avoid collecting repeat values with the OPC Collector when using device timestamps, specify a collection interval that is greater than the OPC Server update rate.
Time Assigned By	Indicates whether the timestamp for the data value is supplied by the collector or the data source. To change it, select a different type.
	Compression Indicates whether or not collector compression is enabled as a default setting. To change it, select the other option. This option is overridden by Tag settings.
Deadband	The default setting of the collector compression deadband in absolute or percentage range values.
Timeout	The default setting for the collector compression time-out for tags added through the Add Multiple Tags From Collector window. You must enable the Collector Compression option to use this field.
Spike Logic Control	Spike logic monitors incoming data samples for spikes in a tag's values. If spike logic is enabled, a sample of equal value to the previously archived sample is inserted into the archive in front of the spike value.

Table 425. The Defaults Section (continued)

Field	Description
Multiplier	The Multiplier option specifies how much larger a spike value must be than the deadband range before spike logic is invoked. For example, if a value of 3 is entered in the Multiplier field and the deadband percentage is set to 5%, spike logic will not be invoked until the difference between the spike value and the previously archived data point is 15% of the EGU range.
Interval	The Interval option specifies how many samples must have been compressed before spike logic is invoked. For example, if the Interval field is set to 4, and 6 values have been compressed since the last archived data sample, spike logic will be invoked.
On-Line Tag Config Changes	Enabling this feature allows you to make on the fly changes to tags without having to restart the collector. If you disable this option, any changes you make to tags do not affect collection until you restart the collector executable.
Sync Timestamp for Server	Enabling this feature automatically adjusts all outgoing data timestamps to match the server clock. This feature is not active when you configure timestamps to be supplied by the data source. Note, that this does not change collector times to match the server time, it adds or subtracts an increment of time to compensate for the relative difference between the clocks of the server and collector, independent of time zone or day light saving time (DST) differences. If the collector system clock is greater than 15 minutes ahead of the archiver system clock, and the Synchronize Timestamps to Server option is disabled, data will not be written to the archive.
Delay Collection @ Start-up (Sec)	Permits you to enter the number of seconds to delay collection on startup (after loading its tag configuration). The default is 2 seconds.

**Note:**

Not all options in this section are available to all collectors. If an option is disabled, it doesn't apply to the current type of collector.

Table 426. Configuration Tab

Field	Description
Description	The name of the selected collector.
Number of Tags	Displays the number of tags currently added to the Simulation Collector. Edit this field to modify the number of Simulation tags available for addition to the Historian System.
Function Period (Seconds)	The period, in seconds, of the SIN, STEP, and RAMP functions implemented in the Simulation collector. The default is 60 seconds.
Computer Name	The machine name of the computer that the collector is installed on.
Memory Buffer Size	The size of the memory buffer currently assigned to the store and forward function. The memory buffer stores data during short-term or momentary interruptions of the server connection; the disk buffer handles long duration outages. To estimate the size you need for this buffer, you need to know how fast the collector is trying to send data to the server and how long the server connection is likely to be down. With those values and a safety margin, you can calculate the required size of the buffer. NOTE: If you enter a new value for this parameter, the change is effective the next time you restart the collector.
Minimum Free Space	The minimum free disk space that must be available on the computer. If the minimum space required is not available when the collector starts, the collector will shut down.
Heartbeat Output Address	The address in the source database into which the collector writes the heartbeat signal output. This address should be connected to a writable analog field. For an iFIX data collector, use an iFIX tag for the output address. Enter the address as NODE.TAG.FIELD (for example, MyNode.MyCollector_AO.F_CV). For an OPC Collector, use the OPC address in the server. Refer to your OPC documentation for more information. The data collector writes the value of 1 to this location every 60 seconds while it is running. You could program the iFIX database to generate an alarm if the Heartbeat Output Address is not written to once every 60 seconds, notifying you that the data collector has stopped.
Status Output Address	Address in the source database into which the collector writes the current value of the collector status (running, stopping, stopped, unknown, or start-

Table 426. Configuration Tab (continued)

Field	Description
	<p>ing) output, letting an operator or the HMI/SCADA application know the current status of the collector.</p> <p>This address should be connected to a writable text field of at least 8 characters. This value is updated only upon a change in status of the collector. For an iFIX data collector, use a TX tag for the output address. Enter the address as NODE.TAG.FIELD (for example, MyNode.MyCollector_TX.A_CV).</p> <p>For an OPC Collector, use an OPC address in the server. Refer to your OPC documentation for more information. The text string usually displays Running, Stopped, or Unknown, matching the Status column value displayed in the collector pane in the System Statistics page of Historian Administrator.</p>
Rate Output Address	<p>The address in the source database into which the collector writes the current value of the events/minute output, letting an operator or the HMI/SCADA application know the performance of the collector. This should be connected to a writable analog field. The value is written once per minute.</p> <p>For an iFIX data collector, use an iFIX tag for the output address. Enter the address as NODE.TAG.FIELD (for example, MyNode.MySIM_AO.F_CV).</p> <p>For an OPC Collector, use a writable OPC address in the server. Refer to your OPC documentation for more information. This value displays the same value as the Report Rate field in the collector pane in the System Statistics page of Historian Administrator.</p>

Redundancy Tab

Historian includes support for collector redundancy, which decreases the likelihood of lost data due to software or hardware failures. Implementing collector redundancy ensures that collection of your data remains uninterrupted. Collector redundancy makes use of two or more collectors, gathering data from a single source. Two or more collectors may be configured in a redundant group. All collectors in the group actively gather the same tags from a data source but only the "active" collector forwards its samples to the Historian server. The non-active collectors buffer their data against failover of the active collector. The Historian server actively monitors the health of the redundant collectors and will automatically switch to a backup if certain user-configurable trigger conditions are met.

The **Redundancy** section displays the following information:

Field	Description
Backup Collector	If enabled, specifies that this is a redundant collector.
Backup For	Specifies the primary collector. <div style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; background-color: #e6f2ff;">  Note: This configuration will be preserved if you disable collector redundancy. This allows you to temporarily take a redundant collector offline without losing its configuration. </div>
Backup Collector Status	The current status of this collector.
Backed Up By	The name of the collector providing redundancy for the selected collector.
Watchdog Tag	Specifies a tag to use to determine the status of the collector. If the watchdog tag meets any of the conditions specified below, the secondary collector will be brought on line to replace it.
Failover on Bad Quality	If enabled, the secondary collector is promoted when a data sample from the watchdog tag is received with bad quality. Failover happens on every write of a bad data sample to the watchdog, not just on the transition from good to bad quality
Failover When Value Transitions from Zero	If selected, the secondary collector is promoted when a data sample from the watchdog tag with a non-zero value is received from the primary collector. Failure happens every time a non-zero value is received, not just when the value promotes from zero to a non-zero value
Failover When No Value Changes for __ Seconds	If selected, the secondary collector is promoted when no data value changes have been received within the time period specified. This could be tied into a heartbeat status indicator where the value is checked every 5 seconds. To prevent failure, there must be a value change.

Maintain, Operate, and Monitor Historian

Plan For Data Recovery

Planning for data recovery means always having up-to-date backup files for important information to call up and restore quickly when the need arises.

Key Files

- The .IHC file contains all configuration information.
- The *.IHA file is the current online archive files.

The .IHC file is automatically backed up when, and only when, you back up the **current** archive .IHA file.

The .IHC uses the following naming convention: `ComputerName_Config-Backup.ihc`

By default, the .IHC backup path is the same as the archives path. If the default backup path is different than the archives path, the .IHC file is copied to the backup folder with the standard .IHC naming convention `ComputerName_Config.ihc`

Restoring the IHC file restores the system configuration (tag, archive, and collector configuration) to the state it was in before the event occurred. If you restore the archive file (IHA) along with the configuration file (IHC), you can quickly pick up where you left off when the event occurred with minimum loss of data.

Develop a Maintenance Plan

The primary goal of a maintenance plan is to maintain integrity of the data collected. If you are successful in this regard, you will always be able to recover from a service interruption and continue operations with minimal or no loss of data. Since you can never ensure 100% system uptime, you must frequently and regularly back up current data and configuration files, and maintain non-current archive files in a read-only state. It is recommended that you use the following guidelines for backup and routine maintenance.

Daily Maintenance

On a daily schedule, perform the following backup operations unless you use `ihArchiveBackup.exe` to back up archives automatically.

1. Use the Historian Web Admin console to back up the current archive and most recent .IHA archived data file. This preserves data collected up to this moment in time. You do not need to back up any read-only archive files after they have been backed up once.
2. Use Windows Explorer to back up the .IHC file if it has been modified by anyone (unless it is backed up automatically). This file contains all current configuration information (tag configuration, archive configuration, and collector configuration). Using this file, you can restore the system configuration after an unplanned shutdown.

Monitor Historian Performance

Historian provides a variety of performance counters and performance tags that can be used to monitor how well the Historian components are performing. These performance tags or counters can also be used to determine the resource usage on the computer that runs the Historian application.

Use performance tags to view information in an Excel report or SDK program, possibly along with other Historian tags. Use performance counters to view information in Windows Performance monitor, possibly along with non-Historian counter information.

Performance counters are useful when the Historian Web Admin console is not installed or cannot connect. Like any Windows performance counter, you must add the counters for collection to view history. Performance tags are always being collected and you can view past data any time.

Performance counters are updated in real time. Performance tags are updated once per minute with the activity over the last minute.

Performance counters contain more information than tags. Any counter can be collected to a tag using the Historian Windows Performance Collector. Those tags will count against your licensed tag count.

Historian Performance Tags

The following table provides information about the various Historian Server Performance tags.

Table 427. Server Performance Tags

Tag Name	Description
PerfTag_CompressionRatio	Specifies the current effect of archive data compression.
PerfTag_MinimumCompression-Ratio	Specifies the minimum compression ratio.
PerfTag_MaximumCompression-Ratio	Specifies the maximum compression ratio.
PerfTag_TotalEvents	Specifies the total number of data samples reported to the Historian archive from all sources. .
PerfTag_TotalOutOfOrder	Specifies the total out of order data samples.
PerfTag_AverageEventRate	Specifies the average number of data samples per minute sent to archiver from all sources
PerfTag_MinimumEventRate	Specifies the minimum number of data samples per minute sent to archiver from all sources.
PerfTag_MaximumEventRate	Specifies the maximum number of data samples per minute sent to archiver from all sources.

Table 427. Server Performance Tags (continued)

Tag Name	Description
PerfTag_WriteCacheHitRatio	Specifies the hit ratio of the write cache in percent of the total writes.
PerfTag_TotalFailedWrites	Specifies the total number of samples since startup that failed to be written.
PerfTag_TotalMessages	Specifies the total messages (for example, connection or audit messages) received by the archiver since startup
PerfTag_TotalAlerts	Specifies the total number of alerts received by the data archiver since startup.
PerfTag_FreeSpace	Indicates the free disk space left in the current archive.
PerfTag_SpaceConsumptionRate	Specifies an archive disk space consumption rate in megabytes per day.
PerfTag_PredictedDaysToFull	Indicates the approximate number of days required for an archive to fill.
PerfTag_MemoryUsage	Specifies the amount of RAM used by the Data Archiver.
PerfTag_MemoryVMSize	Specifies the amount of virtual memory used by the Data Archiver.
PerfTag_TotalAlarms	Specifies the total number of alarms received by the Data Archiver since starting up.
PerfTag_AverageAlarmRate	Specifies the average alarm rate in alarms per minute received by Data Archiver.
PerfTag_TotalFailedAlarms	Specifies the total number of alarms since startup that failed to be written.
Perftag_ReadQueueSize	Specifies the total number of messages present in the Read queue.
Perftag_AverageReadRate	Specifies the total number of data samples per minute returned from the Data Archiver for all read requests.
Perftag_ReadQueuePushRate	Specifies the number of read requests per minute that came into the archiver from all clients. A read request can return multiple data samples.

Table 427. Server Performance Tags (continued)

Tag Name	Description
Perftag_WriteQueuePushRate	Specifies the number of write requests per minute that came into the archiver from all clients. A write request can contain multiple data samples.

The following table provides information about the various Historian Collector Performance Tags.

**Note:**

Replace the placeholder `%CollectorName%` with the name of a Collector.

Table 428. Collector Performance Tags

Tag Name	Description
PerfTag_ <code>%CollectorName%</code> _InterfaceStatus	Specifies the status of an interface.
PerfTag_ <code>%CollectorName%</code> _InterfaceTotalEventsCollected	Specifies the total number of events collected by an interface.
PerfTag_ <code>%CollectorName%</code> _InterfaceTotalEventsReported	Specifies the total number of events reported by an interface.
PerfTag_ <code>%CollectorName%</code> _InterfaceOutOfOrderEvents	Specifies the total out of order events.
PerfTag_ <code>%CollectorName%</code> _InterfaceAverageEventRate	Specifies the average event rate of an interface.
PerfTag_ <code>%CollectorName%</code> _InterfaceMinimumEventRate	Specifies the minimum event rate of an interface.
PerfTag_ <code>%CollectorName%</code> _InterfaceMaximumEventRate	Specifies the maximum event rate of an interface.
PerfTag_ <code>%CollectorName%</code> _InterfaceOverruns	Specifies the interface overruns.
PerfTag_ <code>%CollectorName%</code> _InterfaceCompression	Specifies the compression of an interface.
PerfTag_ <code>%CollectorName%</code> _InterfaceOverrunsPercent	Specifies the number of overruns in relation to the total events collected since startup.

Historian Server Performance Counters

The Windows performance counters are exposed as objects with counters. In the table below, you can see each counter and the object to which it belongs. Each object has one or more instances as shown in the Windows Performance Monitor.

Table 429. Historian Archive Object Counters

Archive Counter	Description
Cache Priority	Relative priority of items from the archive stored to the Windows Cache. A higher priority means the item is more likely to stay in cache.
Disk Read Time (usec)	Duration of last disk read in microseconds.
Disk Read Time Max (usec)	Maximum duration across all disk reads from the archive in microseconds.
Disk Reads	Number of disk reads from archive.
Disk Write Time (usec)	Time of last disk write in microseconds.
Disk Write Time Max (usec)	Maximum duration of all disk writes to the archive in microseconds.
Disk Writes	Number of disk writes to archive.
File Size (MB)	Size of the archive file in MB.
Read Calls	Number of read calls to the archive since startup.
Read Rate (Calls/min)	Number of read calls to the archive per minute.
Write Count	Number of data samples written to archive since startup.
Write Count Rate	Number of data samples written to archive per minute.
Writes Compressed	Number of data samples since startup that were compressed writes to the archive.
Writes Expensive	Number of data samples since startup that were expensive or slow.
Writes Failed	Number of data samples that were failed writes to the archive.
Writes OutofOrder	Number of data samples that were out of time order writes to the archive.

Table 430. Historian Cache Object Counters

Cache Counter	Description
Hit Percentage	Hit rate percentage (0-100) for successful data retrieval calls to the cache. Higher numbers represent more efficiency.
Hits	Number of hits in the cache since startup. To reset the count, restart the Archiver.
Misses	Number of misses in the cache.
Num Adds	Total number objects added to cache.
Num Deletes	Total number of objects deleted from cache.
Num High Prio Objs	Number of high priority objects available for deletion.
Num Low Prio Objs	Number of low priority objects available for deletion.
Num Med Prio Objs	Number of medium priority objects available for deletion.
Obj Count	Number of objects in the cache.
Size (KB)	Size of cache in KB.

Table 431. Historian DataStores Object Counters

DataStores Counter	Description
Compression Ratio (Average)	Archive compression ratio for this data store.
Compression Ratio (Max)	Maximum archive compression ratio for the data store.
Compression Ratio (Min)	Minimum archive compression ratio for the data store.
Messages (Total Alerts)	Total alerts since startup
Messages (Total)	Total messages since startup.
Read Calls	Number of read calls to the data store.
Read Rate (Calls/min)	Average read rate across all archives in the data store. (Read Calls/Minute)
Read Samp Rate (Samp/min)	Average read rate across all archives in the data store. (Samples/Minute)

Table 431. Historian DataStores Object Counters (continued)

DataStores Counter	Description
Space (Consumption MB/day)	Disk space consumption rate. (MB/day)
Space (Days To Full)	Number of days until current archive is full.
Space (Free in MB)	Free disk space in the current archive.
Write Rate (Average)	Average event rate across all archives. (Samples/Minute)
Write Rate (Max)	Minimum event rate across all archives. (Samples/Minute)
Write Rate (Min)	Minimum event rate across all archives. (Samples/Minute)
Writes (Cache Hit Ratio)	Write Cache hit ratio.
Writes (Compressed)	Total number of compressed data samples since startup.
Writes (Total Failed)	Total failed data sample writes since startup.
Writes (Total OutOf-Order)	Total out of order data samples since startup.
Writes (Total)	Total data samples across all archives since startup.

Table 432. Historian Overview Object Counters

Overview Counter	Description
Compression Ratio (Average)	Average archive compression ratio of all data stores.
Compression Ratio (Max)	Average maximum compression ratio of all data stores.
Compression Ratio (Min)	Average minimum compression ratio of all data stores.
Memory Usage (KB)	Private bytes memory usage for Data Archiver.
Memory VM Size (KB)	Virtual Bytes memory usage for Data Archiver.
Messages (Total Alerts)	Sum of total alerts of all data stores since startup.
Messages (Total)	Sum of total messages of all data stores since startup.
Read Rate (Calls/min)	Sum of all average read rates of all data stores. (Samples/Minute)
Read Samp Rate (Samp/min)	Average read rate across all archives. (Samples/Minute)
Space (Consumption MB/day)	Sum of space consumption rate (MB/day) of all data stores.

Table 432. Historian Overview Object Counters (continued)

Overview Counter	Description
Space (Days To Full)	Minimum number of days until current archive is full for all data stores.
Space (Free in MB)	Sum of all free space in the current archive of all data stores.
Write Rate (Average)	Sum of all average event rates of all data stores. (Samples/Minute)
Write Rate (Max)	Sum of all maximum event rates of all data stores.
Write Rate (Min)	Sum of all minimum event rates of all data stores.
Writes (Cache Hit Ratio)	Average write Cache hit ratio of all data stores.
Writes (Compressed)	Sum of total number of compressed data samples of all data stores.
Writes (Expensive)	Sum of total number of expensive writes data samples of all data stores. One of the reasons for expensive writes is out-of-order data.
Writes (Total Failed)	Sum of total failed data sample writes of all data stores.
Writes (Total OutOfOrder)	Sum of total out of order data samples of all data stores.
Writes (Total)	Sum of total data samples across all archives of all data stores.

Table 433. Historian Queue Object Counters

Queue Counters	Description
ClientQueues with Msgs	The number of client queues with messages current on them. A lower number means all clients are up to date. A higher number means that the archiver is not up to date with incoming network traffic
Count (Max)	Maximum number of messages on the queue. (memory and disk)
Count (Total)	Number of messages on the queue. (memory and disk)
Disk Buf Msg Reads	Number of messages read from the disk buffer file.
Disk Buf Msg Writes	Number of messages written to the disk buffer file.
Processed Count	Number of messages processed from the queue since startup.
Processed Rate (msg/min)	Recent rate at which messages have been processed for the queue.
Processing Time (Ave)	Average time in milliseconds to process a message.

Table 433. Historian Queue Object Counters (continued)

Queue Counters	Description
Processing Time (Last)	Time in milliseconds to process the last message.
Processing Time (Max)	Maximum time in milliseconds to process a message.
Recv Count (msgs)	Number of messages received into the queue.
Recv Rate (msgs/min)	Recent rate at which messages have been received for the queue.
Size Kb (Mem&Disk Max)	Max size of messages in Kb on the queue. (memory and disk).
Size Kb (Mem&Disk)	Size of messages in Kb on the queue. (memory and disk)
Size Kb (Mem)	Size of messages in Kb on the queue. (memory only)
Threads	Number of worker threads allocated to process this queue. This is the number of created threads but they may be idle.
Threads Working	Number of queue processing worker threads currently processing messages.
Time in Queue (Ave)	Average time in milliseconds that a message was in the queue, waiting to be processed.
Time in Queue (Last)	Time in milliseconds that the last message was in the queue, waiting to be processed.
Time in Queue (Max)	Maximum time in milliseconds that a message was in the queue, waiting to be processed.

Table 434. Historian Config Counters

Config Counters	Description
File Size	The size of the Configuration File in MB
Hist Tags(Actual)	Number of the Historical tags in the system
Hist Tags (Licensed)	Total licensed Historian tags.
Hist Tags(Used)	Effective number of Historical Licensed Tags in the system. Can be greater than the number of tags because some tags count as more than one Licensed Tag.
Hist Tags (UsedBy-Arrays)	Effective number of Historical Licensed Array Tags in the system (Not the raw tag count, the effective licensed count).

Table 434. Historian Config Counters (continued)

Config Counters	Description
Hist Tags (UsedByUser-Def)	Effective number of Historical Licensed User Defined Tags in the system (Not the raw tag count, the effective licensed count).
Number of Collectors	Number of collectors defined on the system.
Number of EnumSets	Number of enumerated sets defined on the system.
Number of UserDefTypes	Number of user defined types defined on the system.
SCADA Tags (Actual)	Number of SCADA Tags in the system.
SCADA Tags (Licensed)	Total Licensed SCADA tags.
SCADA Tags (Used)	Effective number of SCADA Licensed Tags in the system. Can be greater than the number of tags because some tags count as more than one Licensed Tag.
SCADA Tags (UsedBy-Arrays)	Effective number of SCADA Licensed Array Tags in the system (Not the raw tag count, the effective licensed count).
SCADA Tags (UsedBy-UserDef)	Effective number of SCADA Licensed User Defined Tags in the system (Not the raw tag count, the effective licensed count).

Adding a Performance Tag

1. In the **Tag Maintenance** page, select the **Tags** link on the toolbar.
The Tag Maintenance page appears.
2. Select the **Add Tag Manually** link on the toolbar.
The Add Tag window appears.
3. Enter a name for the Performance Tag.
4. Select **OK**.
The Tag Maintenance page displays with the specified tag properties.

Viewing Tag or Counter Trend Data

How to display a trend of data for a selected tag or performance counter

1. On the **Tag Maintenance** page, select a tag.
2. Right-select the tag and select **Trend**. The trend for the selected tag displays.

Evaluate Data Compression Performance

You can determine how effectively data compression is functioning at any given time by examining the Collector Detail Diagnostics on the Collectors section of the Dashboard, as shown in the Understanding the Interface topic.

The compression field at the top of the page shows the current effect of archive compression. If the value is zero, it indicates that compression is either ineffective or turned off. If it shows a value other than zero, it indicates that archive compression is operating and effective. The value itself indicates how well it is functioning. To increase the effect of data compression, increase the value of the archive compression deadband so that compression becomes more active. Values for this parameter should typically range from 0 to 9%.

Handling Value Step Changes with Collector Data Compression



Note:

Individual tags can be configured to retrieve step value changes. Refer to the **General** section for more information.

If you enable collector compression, the collector does not send any new input values to the archiver if the value remains within its compression deadband. Occasionally, after several sample intervals inside the deadband, an input makes a rapid step change in value during a single sample interval. Since there have been no new data points recorded for several intervals, an additional sample is stored one interval before the step change with the last reported value to prevent this step change from being viewed as a slow ramp in value. This value marks the end of the steady-state, non-changing value period, and provides a data point from which to begin the step change in value. The collector uses an algorithm that views the size of the step change and the number of intervals since the last reported value to determine if a marker value is needed. The following is an example of the algorithm:

```
BigDiff=abs(HI_EGU-LO_EGU)*(CompressionDeadbandPercent/(100.0*2.0))*4.0
If ( Collector Compression is Enabled )
If ( Elapsed time since LastReportedValue>=( SampleInterval * 5 ) )
If ( abs(CurrentValue-LastReportedValue) > BigDiff )
Write LastReportedValue,TimeStamp=(CurrentTime-SampleInterval)
```

In the example above, if a new value was not reported for at least the last 4 sample intervals, and the new input value is at least 4 deltas away from the old value (where a single delta is equal to half of the compression deadband), then a marker value is written.

**Note:**


These settings are also adjustable from the Registry. Please contact [technical support](#) for more information.

Example: Value Spike with Collector Compression

A collector reads a value of X once per second, with a compression deadband of 1.0. If the value of X is 10.0 for a number of seconds starting at 0:00:00 and jumps to 20.0 at 0:00:10, the data samples read would be:

Time	X
0:00:00	10.0 (steady state value)
0:00:10	20.0 (new value after step change)


However, without the marker value, if this data were to be put into a chart, it would look like the data value **ramped** over 10 seconds from a value of 10.0 to 20.0, as shown in the following chart.



The addition of the marker value to the data being stored results in the following data values:

Time	X
0:00:00	10.0 (steady state value)
0:00:09	10.0 (inserted Marker value)
0:00:10	20.0 (new value after step change)

If you chart this data, the resulting trend accurately reflects the raw data and likely real world values during the time period as shown in the following chart.



Historian Data Types

Historian uses the following data types.

Table 435. Data Types

Data Type	Size	Description
Single Float	4 bytes	The single float data type stores decimal values up to 6 places. Valid ranges for the single float data type are 1.175494351e-38F to 3.402823466e+38F

Table 435. Data Types (continued)

Data Type	Size	Description
Double Float	8 bytes	The double float data type stores decimal values up to 15 places. Valid values for the double float data type are 2.2250738585072014e-308 to 1.7976931348623158e+308
Single Integer	2 bytes	The single integer data type stores whole numbers, without decimal places. Valid values for the single integer data type are -32767 to +32767.
Double Integer	4 bytes	The double integer data type stores whole numbers, without decimal places. Valid values for the double integer data type are - 2147483648 to +2147483648.
Quad Integer	8 bytes	The quad integer data type stores whole numbers without decimal places. Valid values for the quad integer data type are -9,223,372,036,854,775,808 (negative 9 quintillion) to +9,223,372,036,854,775,807 (positive 9 quintillion).
Unsigned Single Integer	2 bytes	The unsigned single integer data type stores whole numbers without decimal places. Valid values for the unsigned single integer data type are 0 to 65535.
Unsigned Double Integer	4 bytes	The unsigned double integer data type stores whole numbers without decimal places. Valid values for the unsigned double integer data type are 0 to 4,294,967, 295 (4.2 billion).
Unsigned Quad Integer	8 bytes	The unsigned quad integer data type stores whole numbers without decimal places. Valid values for the unsigned quad integer data type are 0 to 18,446,744,073,709,551,615 (19 quintillion).
Byte	1 byte	The Byte data type stores integer values. Valid values for the byte data type are -128 to +127.
Boolean	1 byte	The Boolean data type stores boolean values. Valid values for the boolean data type are 0=FALSE and 1=TRUE. If the user sends zero, the value is taken as zero. Anything other than zero is treated as one.
Fixed String	Configured by user	The fixed string data type stores string data of a fixed size. Valid values are between 0 and 255 bytes.

Table 435. Data Types (continued)

Data Type	Size	Description
Variable String	No fixed size	The variable string data type stores string values of undetermined size. This data type is useful if you cannot rely on a constant string length from your data source.
Binary Object	No fixed size	The binary object data type stores binary data. This is useful for capturing data that can not be classified by any other data type.
Scaled	2 bytes	The scaled data type lets you store a 4-byte float as a 2-byte integer in the Historian archive. The scaled data type saves disk space but sacrifices data precision as a result.

Additional Notes on Data Types

Quad Integer

If a tag is associated with Quad Integer, Unsigned Double Integer, or Unsigned Quad Integer data types and if you are retrieving data using Non-Web Admin, Excel Add-in, Calculation, ihSQL, and ihSDK, then there may be a loss of precision value due to a Visual Basic limitation.

Calculation collector supports only the calculations performed using the current value calculation. It does not support other calculations due to a Visual Basic script limitation.

The high and low EGU limits for Quad Integer, Unsigned Single Integer, Unsigned Double Integer, and Unsigned Quad Integer are between $2.2250738585072014e-308$ to $1.7976931348623158e+308$.

Fixed String Data Types

The fixed string data type lets you store string data of a fixed size. This is useful when you know exactly what data will be received by Historian. If a value is larger than the size specified in the Data Length field, it will be truncated.

Scaled Data Types

Historian uses the high and low EGU values to both store and retrieve archived values for the scaled data type. This allows you to store 4 byte floats as 2 byte integers in the Historian archive. Though this saves disk space, it also sacrifices data precision as a result. The smaller the span is between the high and low EGU limits, the more precise the retrieved value will be.

When calculating the value of a scaled data type, use this formula:

```
ArchivedValue = (((RealWorldValue - EngUnits->Low) / (EngUnits->High - EngUnits->Low) * (float) HR_SCALED_MAX_VALUE) + .5);
```

For example: A value of 12.345 was stored in a scaled tag whose high EGU was 200 and low EGU was 0. When later retrieved from the Historian archive, a value of 12.34473 would be returned.



Note:

Values that are outside of the EGU range of a scaled data type tag get stored as "bad" or "scaledoutofrange" in Historian. You **cannot** correct values for scaled data types that were inserted while EGUs were incorrect. Changing either the High or Low EGU tags does not affect existing data, but only affects the new data with new timestamps. If necessary, contact technical support for additional information.

Setting a Value For the Fixed String Data Type

1. In the Admin App, select **Tags**.
2. Select the tag you want to configure.
3. Select **Collection**.
4. In the **Data Type** drop-down list, select **Fixed String**.
5. Enter a value in bytes in the adjacent field. This field is enabled only when the data type selected is Fixed String.

Managing Tags

Access a Tag

1. [Access the Web Admin console \(on page 2818\)](#).
2. Select **Configuration** or **Show All Collectors** or **Show All Clients**.
3. Select **Tags**.
The **Tags** page appears.
- 4.

Add a Tag to a Data Source

To display the Tags page, select the Tags link in any of the Historian Web Admin console pages. The Tags page lets you read and modify all tag parameters for the Historian system. To access information on a specific tag or group of tags, however, you must first search for the tags. You can search for the tags using the Search for Tags button.

You can add tags manually through the tags page or choose the tags from the listed collectors. Typically, you add tags to Historian by browsing the data source. You can also add tags manually or add tags from the collector by selecting the appropriate link in the second line of the display.

If you add a tag with a tag name greater than 25 characters in length, the characters beyond 25 are not visible in the Tags list on the Tags page. To see the entire tag name, place the mouse cursor over the tag to see a ToolTip that displays the complete tag name.

**Note:**

Do not add or update the following spare configurations as the data may get corrupted or overwritten:

- The **Spare 1** field for OSI PI Distributor. OSI PI distributor reads data from the Historian tag displayed in the Tag Source Address field and sends it to the OSI PI tag name displayed in the **Spare 1** field.
- The **Spare 5** field for Server to Server Collector and Server to Server Distributor as it is only used for internal purposes.

Add a Tag Manually

**Note:**

If you manually add a Server-to-Server tag that uses the polled collection type, make sure that you set the **Time Adjustment** field for the tag to the **Adjust for Source Time Difference** option after you add the tag. The **Time Adjustment** field is located in the **Advanced** section in the **Tag Maintenance** page.

1. Select the icon link in the **Tag Details** page and select **Add Tags Manually**.
The Add Tag window appears.
2. Select a collector from the drop-down list in the **Collector Name** field. This associates the new tag with a specific collector.
3. Enter the **Source Address** and **Tag Name** in the appropriate fields.
4. Select the data store in the **Data Store** field.
5. Select a **Data Type** from the drop-down list.
6. For fixed string data types only, enter a value in the field adjacent to the Data Type field.
7. Select Seconds, Milliseconds, or Microseconds in the **Time Resolution** field.

8. If the tag is an Array Tag, select the **Is Array Tag** option.
9. Select **Add** to add the tag.

Add a Source Address to a Tag

1. Select a collector from the drop-down list in the **Collector Name** field.
This associates the new tag with a specific collector.
2. Enter the **Source Address** or select **Browse**.
The Add Tags from Collectors window appears.
3. Select the tag you want to associate with the source address.
You can select only one tag.
4. Select **OK**.
The source address of the tag is added.

Adding OPC Tags from a Collector

1. Select the link in the **Tag Details** page.
2. Select **Add Tags from Collector**.
The Add Tags from Collector window appears.
3. Select the collector from the **Collector** name list.
4. Enter the **Source Tag Name** or select **Browse**.
The list of folders available with the collector is displayed.
5. Expand the folder to select the desired tags.
The > symbol indicates that you need to navigate further within the folder. You can select a single tag or multiple tags. If you want a series of tags, press and hold the Shift key and select the series.
6. Select **Add** or **Add All** to add tags.
The selected tags appear in the right hand section.
7. To preview the selected tag details, select **Preview**.
8. To add the selected tags from the collectors, select **Add Selected Tags**.

Adding Simulation Tags from a Collector

1. Select the link in the Tag page and then select **Add Tags** from Collector.
The Add Tags from Collector window appears.
2. Select the collector from the **Collector** name list.
3. Enter the **Source Tag Name** or select **Browse**.
The list of available tags is displayed.
4. Select the desired tags and select **Add** or select **Add All** to add tags.

You can select a single tag or multiple tags. If you want a series of tags, press and hold the Shift key and select the series.

The selected tags appear in the right hand section.

5. To preview the selected tag details, select **Preview**.
6. To add the selected tags from the collectors, select the **Add Selected Tags**.

Filter and Search Tags

Using the **Search** window you can:

- Add multiple search criteria based on the tag criteria and the criteria value.
- Modify the existing criteria value.
- Delete unwanted search criteria from the list.
- Automatically load the most recently used criteria for re-use.
- Search the Historian database based on search criteria.
- View the details of a tag.

Filtering Tags

By default, the Tags page displays all available tags. To filter the tags based on a set of criteria, use the Filter option.

1. On the **Tags** page, select the **Filter** button.
The section expands to show the filter criteria.



2. Select the criteria and enter a value to filter by.
3. Select **Add Criteria**.
4. Select **Apply** to filter the tags based on the criteria.

Select **Remove** to remove the criteria selected or select **Reset** to reset your input.

Searching for Tags: Simple Search

1. Select the **Search** button in the Tags page.
The Search box appears.

2. Enter a tag mask in the **Search** field using either the full/partial tagname or standard Windows wildcard characters.

This will help you to filter the search query more precisely. If wildcard characters are not used, then the search will result in all the tags containing the given search string.

**Note:**

Supported wildcard characters in simple search are * and ?.

Example for using wildcard characters in search strings:

Search String	Result
W*	All tags starting with letter W
*e	All tags ending with letter e
W*e	All tags starting and ending with W and e respectively
Tag?	All four letter named tags, where the last letter can be anything
W*0000?	All tag names starting with W and ending with 0000 followed by any single letter

3. Select **Enter**.

The relevant tag(s) are listed.

Searching for Tags: Advanced Search

The Advanced Tag Search window allows you to search for a set of tags that match the search criteria and then perform actions on one or more tags that you select from the list.

It saves the most recently used search criteria to a file named **DefaultSearchCriteria.xml** in the Excel App Data path, which is: `c:\users\\AppData`, and this criteria is automatically loaded into the window the next time it is opened. This allows you to re-use or modify the criteria rather than entering them each time. To reset your criteria, delete the XML file.

1. Select the **Advanced Search** button.
The Advanced Search window appears.
2. In the **Step 1** section, select the tag criteria from the list.
3. Enter or select the **Tag Criteria Value**.

If you leave the field blank, the search returns all of the available tags.

- (optional) Select the **Add Criteria** button to add more criteria to narrow your search.
- Select the **Find Tags** button.

All the tags that satisfy the query criteria are displayed in the Step 2 section.

- Select tags from the list by selecting **Add**  .

To select all of the tags, select the **Add All** button. To remove a selected tag, select Remove  .

- Select **Apply** to return the list of tags on the parent window.

Select **Reset** to clear your search criteria. Select **Cancel** to close the window.

Access the Trend Chart of Tag Values

This topic describes how to access the values of a tag in a trend chart. The difference in the timestamp of consecutive values depends on the time resolution of the tag. For example, if the time resolution is seconds, the timestamp of consecutive values of the tag will be one second apart.

You can plot the values of multiple tags in a single trend chart.

- [Access the Web Admin console \(on page 2818\)](#).
- Select one or more tags on the **Tag Details** page.

- Select the  button at the bottom of the page and select the **Trend** option.

The Trend page displays the trend of the last 10 minutes with an interval of 1 minute and interpolated sampling mode. By default, all selected tag trends are shown.

- To zoom in on the trend, select and drag to select the region to zoom in on.
- To zoom out on the trend, select the Reset Zoom button.
- To see the tag name, date/time, quality, and value at an instance, hover your mouse over the trend.
- You can change the type of trend you want to view: Line, Column, or Area.
- Selected tag names are shown as legends; select to see a particular tag's trend and select again to hide the trend.
- Select the Refresh button to refresh the page.
- Select the Close button to cancel the operation.

Displaying Raw Data Samples

You can view the most recent ten raw samples for one or more selected tags.

1. Select one or more tags on the **Tag Details** page.



Note:

If you choose **Select All**, only the data for the first 10 tags selected will be displayed.

2. Select the button at the bottom of the page and select the **Last 10 Raw Values** option.
The Last 10 Raw Values for selected Tag(s) window appears, displaying the tag name, timestamp, value, and quality for each selected tag.
 - For each selected tag, values are sorted by timestamp in descending order.
 - Where necessary, tag names are truncated and indicated with an ellipsis "..."
 - To view the full name, hover over the tag name. A tooltip displays the full tag name.
 - Panes can be collapsed and expanded to see the last 10 raw values for more selected tags.
 - Select **Refresh** button to refresh the page.
 - Select **Close** button to cancel the operation.

Dynamic Collector Updates

The dynamic collector update feature ensures that any modifications done to the tag configuration do not affect all the tags in a collector. Only the tags that stop data collection will record zero data and bad quality without restarting the collector. In other words, the tags that do not stop data collection do not record bad data samples to the collection.

Whenever you add tags, delete tags, or modify certain tag properties, the following collectors reload only the modified tag(s) without restarting the collectors.

- OPC Collector
- iFIX collector
- Calculation collector
- Simulation Collector
- Server to Server Collector
- PI Collector
- PI Distributor

If you disable On-line Tag Configuration Changes option, any changes you make to the tags do not affect collection until after you restart the collector and the data archiver. You can restart the data archiver from Windows services. To restart the collector, stop and start the collector service or executable (or [use Configuration Hub \(on page 639\)](#)). Restarting the collector stops and restarts the tag(s) collection and records bad data samples to the collection. If the modified tags get zero bad markers and available

runtime values at the same time, then precedence is given to available runtime values instead of zero bad markers.

All the collector configuration changes done within a 30 second time frame are batched together. When possible, update/modify a small set of tags at a time to collect the modified data faster. However, when updating large sets of tags at the same time, best practice is to disable On-line Tag Configuration Changes and restart the collector after you are finished.

Starting or Stopping Data Collection For a Tag

For a tag to stop and restart collection without restarting the collector, the On-line Tag Configuration Changes option must be enabled. By default, the On-line Tag Configuration Changes option is enabled. If necessary, enable the On-line Tag Configuration Changes option on the **Advanced** section of the **Collector Maintenance** page.

1. In the **Tag Viewer** section of the **Tags** page, select the tag from the list.
2. In the **Tag Editor** section, select **Collection**.
3. Scroll down to the **Collection** field and either:
 - **Disable** the collection option.
 - **Enable** the collection option.
4. Select **Update**.

Reload Tag Parameters

Whenever you modify certain tag parameters, the following collectors reload only the modified tags without restarting the collectors.

- OPC Collector
- iFIX collector
- Calculation collector
- Simulation Collector
- Server to Server Collector
- PI Collector
- PI Distributor

For a tag to stop and restart the collection without restarting the collector, you must select the **On-line Tag Configuration Changes** option on the **Advanced** section of the **Collector Maintenance** page. By default, the On-line Tag Configuration Changes option is enabled.

If you disable the On-line Tag Configuration Changes option, any changes you make to the tags do not affect collection until after you restart the collector. To restart the collector you must stop and start the collector service or executable. Restarting the collector stops and restarts the tag(s) collection and records bad data samples to the collection. All the collector configuration changes done within a 30 second time frame are batched together and applied to the collector. If the modified tags get zero bad markers and available runtime values at the same time, then precedence is given to available runtime values instead of zero bad markers.

It is recommended that you update/modify a small set of tags at a time to collect the modified data faster. It is recommended to you disable the On-line Tag Configuration Changes option while updating large sets of tags at the same time, and restart the collector after modification.

Tag Properties that Cause the Tag Collection to Stop and Restart

Changes to the following tag properties cause an updated/modified tag to stop and restart the collection, when the On-Line Tag Configuration Changes option is enabled:

- Collector Name
- Collector Type
- SourceAddress
- Spare 1 – 5
- Data Type
- Collection Interval
- Collection Offset
- Collection Disabled/Enabled (CollectionDisabled in SDK)
- Collection Type
- TimeStampType
- Calculation Dependencies (in SDK) or Calculation Triggers (in Historian Administrator) – applies to Server-to-Server and Calculation collectors only

Tag Properties that Do Not Cause the Tag Collection to Stop and Restart

The following tag properties do not cause the tag collection to stop and restart, but the collectors use these new values immediately (when the On-Line Tag Configuration Changes option is enabled):

- High Engineering Units
- Low Engineering Units
- Input Scaling
- High Scale
- Low Scale

- Collector Compression
- Collector Deadband Percent Range
- Collector Compression Timeout

Rename Tags



Note:

To rename tags, you must be a member of the administrator's group with tag level security.

New tag names are called **active** tag names and old tag names are called **aliases**.

You can also rename or permanently rename tags using the Non-Web Historian Administrator, the Excel Add-in, or the Application Program Interfaces (ihSDK, ihUAPI, or ihAPI).

If you modify the properties of a renamed tag, the properties of all of its aliases will also be updated.

Whenever you rename a tag, only the active (newest) tag name will be visible in the Tags list on Historian Administrator Tag page. You can rename tags multiple times, but only the latest, active tag name will be visible in the Tags list.

You can also retrieve the data using any alias (that is, the new or old tag names). However, the Tag page will display only an active tag name (that is, the new tag name). Whenever you change or copy a tag name, the information about the old tag name, new tag name, and time stamps are all recorded in the audit trail.

Be aware of the following when you are using the Tag Rename feature:

- If you modify a renamed tag property, then all of the alias' tag properties will also be updated.
- If you delete a renamed tag, then all the aliases will also be deleted.
- You can rename tags multiple times, but only the latest active tag name (renamed tag name) will be visible in the Tags list.
- If you rename a tag, the tag count does not increase.
- If you copy a tag, then the tag count increases.
- An alias can be queried, but cannot be modified or deleted.

Permanently Rename a Tag

You can permanently rename a tag if you no longer want to read from and write to a tag by its previous name. Permanently renaming makes the previous tag name available for new usage. For example, if you had permanently renamed Tag A to Tag B, you can create a new tag with the tag name Tag A with no linkage to the previous tag.

Things you need to know when you are using the Permanent Rename feature:

- If you permanently rename a tag, the tag name will be updated with the new tag name and the old tag name will be lost.
- You can permanently rename tags multiple times, but only the latest tag name (new tag name) will be visible in the Tags list.
- If you permanently rename a tag, the tag count does not increase.
- Store and forward data will be lost if you do a permanent rename and the data is sent using the old tag name.
- There will be loss of data during the process of permanently renaming a tag. If you are going to perform permanent rename, it is recommended to stop the collector and then permanently rename the tag.
- If a tag is permanently renamed and is a trigger tag to other tags, then you need to re-assign the new trigger name to the tags.

Copying a Tag

If you copy a tag, then the tag count increases.

1. Select the **Copy** button in the **Tags** page.
The **Copy Tag** window appears.
2. Enter a tag name for the new tag.
3. Select **OK**.

Renaming a Tag

Renaming a tag creates an alias for the tag. Only the name changes; none of the tag's properties are changed. The tag data can be referred to using any alias for that tag, including the current name.

Renaming a tag does not increase the tag count.

1. Double-click the **Tag** link in the **Tag Details** page.
The tag name becomes editable.
2. Enter a new tag name and press the Enter key.

If you are connecting to Historian 3.5 collectors, then you must restart the respective collectors before browsing the tags.

Renaming a Tag Permanently

Tag renaming only changes the tag's name without changing any of the tag's properties.

1. In the **Tag** page, select the tag you want to rename.
2. Select the arrow button in the right-hand section and select **Rename**.
The Rename Tag window appears.
3. Enter a new tag name.
4. Select **OK**.
A message box appears confirming that you want to permanently rename the tag.
5. Select **Yes** to permanently rename the tag.

If you are connecting to Historian 3.5 collectors, then you must restart the respective collectors before browsing the tags.

Stale Tag Management

Stale tags are tags that have no new data samples within a specified period of time. These tags add to system overhead and slow down user queries. The **Data Store Configuration** option allows system administrators to configure the time period after which tags are considered stale and how often the system should check for stale tags.

Under the default configuration, tags are never considered stale. This effectively disables stale tag management.

To see the names and descriptions of all currently stale tags, use the **IsStale** criteria in a tag search.

To improve performance, [permanently delete \(on page 2882\)](#) unused tags. Perform a tag search using the **IsStale** criteria and select **Permanently Delete Tag**.

Delete Tags

There are key differences between deleting and permanently deleting a tag.

Delete	Permanently Delete
The tag is removed from the tag database but any data for that tag is retained in the archive	All data associated with the tag is completely lost and the tag name is available for reuse.
Tag data is still available from the archive, so you can still reference that tag, for example, from within a calculation formula or by using the Excel Add-In.	Tag data is no longer available from the archives and you will not be able to query the existing data for that tag.

Deleting a Tag

1. In the **Tag** page, select a tag from the list.
2. Select the button at the bottom right of the page. The Delete Tag window appears.
3. Select the **Remove Tag(s) from System** option and select **OK**. This removes the tag from the Tag Database but retains any data for that tag in the archive.
4. A message box appears asking you to confirm the deletion. Select **Yes** to delete the tag.

Deleting a Tag Permanently

1. In the **Tag** page, select a tag from the list.
2. Select the **Delete** button. The Delete Tag window appears.
3. Select the **Permanently Remove Tag(s) from System** option and select **OK**. This permanently removes the tag from the Tag Database.
4. A message box appears asking you to confirm the deletion. Select **Yes** to delete the tag.

Managing Data Stores

About Data Stores

A data store is a logical collection of tags. It is used to store, organize, and manage tags according to the data source and storage requirements. A data store can have multiple archive files (*.IHA), and includes both logical and physical storage definitions.

Tags can be segregated into separate archives through the use of data stores. The primary use of data stores is to segregate tags by data collection intervals. For example, you can put a name plate or static tags where the value rarely changes into one data store, and your process tags into another data store. This can improve query performance.

Historian data stores are stored as archive files that contain data gathered from all data sources during a specific period of time. You can write and read data from the archive files.

You can define two types of data stores:

- **Historical Data Store:** Tags stored under historical data store will store data as long as the disk space is available. Depending on your license, you may be able to create multiple historical data stores. The maximum number of historical data stores supported depends on the license.
- **SCADA Buffer Data Store:** Tags stored under the SCADA buffer data store will store data for a specific duration of time based on license.

When you install the Historian server, two historical data stores are installed by default.

- **System:** Stores Historian messages and performance tags. This is only for internal usage within Historian, and you cannot add tags to this data store. You cannot rename or delete the system data store.
- **User:** Stores tag data. This is a default data store. You can rename and delete a user data store as long as there is another default data store set for tag addition.

Based on your license, a SCADA Buffer data store may also be installed. It stores short-term tags and data.

Moving Tags Between Data Stores

You can move tags from one data store to another. After a tag is moved, the incoming data is stored in the new data store.

When you move a tag, only the tag itself is moved; the data already associated with that tag does not automatically move with it. Moving the old data is optional, but if the old data is not moved to the new data store, it cannot be retrieved.

1. In the **Tags** page, select a single tag or multiple tags.
2. In the **Tag Editor** section, select **Advanced**.
3. Select **Data Store** to select the tag's new data store.
A message appears asking you to confirm the change.
4. Select **Yes**.
5. Select **Update**.

A message appears confirming that the tag's data store has changed and reminding you that the data has to be manually moved using MigratelHA.exe.

(optional) Move the data associated with the tags you just moved with the migration utility tool (MigratelHA.exe). If you moved multiple tags, you can move the data for all, some, or none of the tags.

Before moving any data, best practice is to back up the archive file(s) that contain the old data.



Note:

When migrating tags using MigratelHA.exe, ensure that you select the **Migrate using the tag mask** option and specify the tag name or wildcard mask to migrate the tag you want to include. Refer to the How to use the IHA Migration Tool section in *Important Product Information*.

Adding a Data Store

The number of data stores you can create depends on your license.

1. [Access the Web Admin console \(on page 2818\)](#).
2. Select **Data Stores**.
A list of data stores appears.
3. Enter values as described in the following table.

Field	Description
Data Store Name	Enter a unique name for the data store. A value is required. You can use all alphanumeric characters and special characters except / \ * ? < >
Description	Enter a description for the data store.
Is Default	Switch the toggle on if you want to set this data store as the default one. A default data store is the one that is considered if you do not specify a data store while adding a tag. You can set only one data store as default.

4. Select .

The data store is created.

When you add tags to the data store, it will have its own set of .IHA (iHistorian Archive) files. Ensure that you back up the new data store archives periodically.

When you add the tags to the new data store, it will have its own set of .IHA (iHistorian Archive) files. Ensure that you [back up \(on page 2896\)](#) the new data store archives periodically.

Deleting a Data Store

You can delete a data store if it is no longer needed. You cannot delete the System data store. You cannot delete the last User store; at least one User store must exist.

1. If there are tags assigned to the data store, reassign them to other data stores or delete them.
2. In the **Data Stores** page, select the unwanted data store and then select **Delete**.
A message appears asking you to confirm deletion
3. Select **OK** to delete the data store.

Editing a Data Store

The following special characters cannot be used in data store file names: `/ \ * ? < > |`

1. Select the **Edit** button.
The **Edit Data Store Configuration** window appears.
2. Make the desired change(s):
 - a. To rename the data store, enter the new name in the **Data Store New Name** field.
 - b. Enter or modify the **Description**.
 - c. Toggle the **Is Default** option.
3. Select **Save** to save the changes.

Managing Data Archives

Configure Data Archives

About Data Archives

Historian archives are stored data files, each of which contains data gathered from all data sources during a specific period of time. There are two types of archive files in an Historian archives directory:

`Machinename_Config.ihc` – the single .IHC file contains information about the archiver, tag configuration, and collector configuration.

`Machinename_ArchiveXXX.iha` – archive data files where x is a number indicating the place of the file in a time-based sequence.

Since archived data files can be quite large, adjust system parameters carefully so that you limit data collection to meaningful data only and so that you minimize the required size of system storage. This chapter describes techniques you can use in your application to accomplish these goals.



Note:

You must have a minimum of 10 GB free space available for the Data Archiver to start.

Historian now supports a maximum archive size of 256 GB per archive. When you start Historian, it may take a longer time to start an archiver depending on the number of archives online, number of tags, and number of connections.



Note:

The limit for the number of LUNs is 100.

Archive Creation

Archive files are created to store data as the Historian server receives it until they reach their duration limit. When the limit is reached, a new archive is created and the data is loaded into that archive. These archives can be created based on number of days or hours. You can observe the archives on the left side of the **Data Store** page, under **Archives**, with the name of the archive and start time for each archive



Note:

As of Historian 7.0, Historian archives are time-based only. Historian will asynchronously create a new empty archive when data starts loading into an existing archive. If the option to automatically create archives is not enabled, however, you must open a new archive manually.

To create archives based on **days**:

1. Open the **Data Stores** page and then select **Edit**. The Archive Configuration page appears.
2. Select **Configuration**.
3. In the **Archive Duration** field, select the **Days** option from the drop-down list.
4. Enter the number of days for which you want to create archives.
5. Select **Update**.

Setting **Days** to 1 means that a new archive will be created every day starting from the time your first archive is created. The next archive is created after one day (24 hours) from the time the first archive was created.

To create archives based on **hours**:

1. Open the **Data Stores** page, and then select **Edit**. The **Archive Configuration** page appears.
2. Select **Configuration**.
3. In the **Archive Duration** field, select the **Hours** option from the drop-down list.
4. Enter the number of hours for which you want to create archives.
5. Select **Update**.

Setting **Hours** to 1 means that a new archive will be created after every hour starting from the time your first archive has been created.

The Archive Configuration Screen

To access the **Archive Configuration** page, select **Edit** on the **Data Stores** page.

The Archive Configuration page lets you read and modify the parameters of archives and data stores. In this page, you can see the list of all archives of the selected data store.

To examine a particular archive, select the archive and then select **Edit**. The details of the archive are displayed in the Archive Details section.

- Action Buttons
- Statistics Section
- Archives Section
- Archive Details Section

Points To Remember

- You may need to add an archive when the current archive is almost full and you have not enabled automatic creation of archives.
- You may need to restore an archive when you start up after an unplanned shutdown or when you need to retrieve data from an old, inactive archive.
- You may need to back up an archive before a planned Historian software product upgrade.
- You may need to manually resynchronize archives when the archives in the mirrored environment are not synchronized.

Action Buttons

Select a button to perform the action indicated by the name. The following table describes these buttons.

Button	Action
Add Archive 	Select this button to add a new archive to the data store.
Remove Archive 	Remove an archive. First select an archive name to select it, and then select Remove. Selecting OK removes the archive file from the list of archives for the system, and places it in the \Archives\Offline directory. This does not delete the archive file from the system. An archive must be closed before it can be removed.
Close Archive 	Manually close the current archive. An archive must be closed before it can be removed.
Backup Archive 	Back up a selected archive. Verify the file name and path and then select OK to save the file.

Button	Action
Restore Archive 	Restores an archive from backup.
Update	Apply all parameter changes that you have made in this page. If you want to cancel changes and return to the original values or settings, open a different page and then return to the Archive Configuration page.
Edit	Select this to edit the Archive configuration details.

Statistics Section

Indicates the current status of the collector.

- **Running** indicates that the collector is operating.
- **Stopped** indicates that it is in pause mode and not collecting data.
- **Unknown** indicates that status information about the collector is unavailable at present, perhaps as a result of a lost connection between collector and server.

Table 436. Configuration Tab

Field	Description
Default Archive Path	<p>The path name that will be used for any newly created archives. If you change the path, the change takes effect the next time a new archive is created.</p> <div data-bbox="617 1230 1416 1453" style="border: 1px solid #00a0e3; border-radius: 10px; padding: 10px; background-color: #e6f2ff;"> <p> Note: Do not use a period in the default archive path field. If a period is present in the default archive path, you will not be able to specify a default archive name.</p> </div>
Default Backup Path	The location to which the backup file will be saved.
Archive Duration (Days/Hours)	Specifies the duration of a newly created archive in days or hours. A new archive will be created after the selected number of days or hours.

Table 436. Configuration Tab (continued)

Field	Description
	<div data-bbox="630 331 1421 541" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px;">  Note: When the Archive Duration property is changed in a mirrored environment, the changes will take effect only after a time gap of 15 minutes. </div>
Data is Read-only After (Hours)	<p data-bbox="613 569 1417 737">The number of hours, prior to now, for which data can be stored in a read/write archive. After the time expires, that portion of the archive file is automatically made read-only. Incoming data values with time-stamps prior to this time are rejected.</p> <p data-bbox="613 779 1417 898">A single archive file, therefore, may contain a read-only section, another read-write section containing recently written data, and unused free space.</p> <div data-bbox="630 934 1421 1234" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px;">  Note: A read-only archive file cannot be moved using Windows Explorer. To move a read-only archive file, select the file and select the Remove button on the Details section of the Archive Maintenance page. The Archiver then releases its locks, which permits you to move the file at will. </div>
Base Archive Name	<p data-bbox="613 1268 1417 1388">A prefix that is automatically added to the file name of all created archives. To change the prefix, enter a new text string and select Update.</p>
Free Space Required (MB)	<p data-bbox="613 1419 1417 1539">Indicates the remaining disk space required after a new archive is created. If the available space is less than the requirement, a new archive is not created. The default is 5000 MB.</p> <p data-bbox="613 1581 1417 1835">The Free Space Required field does not apply to alarms and events archives. The alarms and events archiver will continue writing to the alarms and events archive until the drive is full. If this occurs, the alarms and events archiver will buffer incoming alarms and events data until the drive has free space. An error will also be written to the Historian message log.</p>

Table 436. Configuration Tab (continued)

Field	Description
Automatically Create Archives (Enable/Disable)	<p>Select the appropriate button to enable or disable this function. When enabled, the server automatically starts a new archive in the default path directory whenever the current archive fills up. If disabled, no new data will be written to the archives once the default size has been reached.</p> <div data-bbox="613 579 1417 758" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: To create multiple archives at the same time, Automatically Create Archives must be <i>Disabled</i>.</p> </div>
Overwrite Old Archives (Enable/Disable)	<p>Select the appropriate button to enable or disable this function. When enabled, the system replaces the oldest archived data with new data when the default size has been reached.</p> <ul style="list-style-type: none"> • To create multiple archives at the same time, Overwrite Old Archives must be <i>Disabled</i>. • If you enable both Automatically Create Archives and Overwrite Old Archives, then you must set <code>ihArchiveFreeSpaceHardLimit</code> to TRUE using APIs. <div data-bbox="613 1209 1417 1430" style="border: 1px solid #FFD700; border-radius: 10px; padding: 10px; background-color: #FFF2CC;"> <p> CAUTION: Since this action deletes historical data, exercise caution in using this feature. Be sure that you have a backup of the archive so that you can restore it later.</p> </div>
SCADA Buffer Duration (Days)	<p>Indicates the maximum number of days the trend data can be stored. The maximum number of days is 200 days.</p> <p>This field applies only to SCADA buffer data stores.</p>
Use Caching (Enabled/Disabled)	<p>When reading data from the archiver, some data is saved in the system memory and retrieved using caching. This results in faster retrieval as the data is already stored in the buffer. Enable the Use Caching option to retrieve data faster.</p> <p>This option is not available for SCADA buffer data stores.</p>

Table 436. Configuration Tab (continued)

Field	Description
Generate Message on Data Update (Enabled/Disabled)	<p>If this option is enabled, an audit log entry will be made any time the value of a previously archived data point in the Historian archive is overwritten. This log entry will contain both the original and new values.</p> <p>To create multiple archives at the same time, Generate Message on Data Update must be <i>Disabled</i>.</p> <p>This option is not available for SCADA buffer data stores.</p>
Store OPC Quality (Enabled/Disabled)	<p>Stores the OPC data quality.</p> <p>To create multiple archives at the same time, Store OPC Quality must be <i>Disabled</i>.</p>
Stale Period	<p>Specifies the time period after which tags are considered stale for this data store. The value is defined in days. Valid values are:</p> <ul style="list-style-type: none"> • 0 (zero): This default value means that tags are never considered stale. This effectively disables stale tag management. • 7 days (1 week) to 36500 days (100 years)
Stale Period Check	<p>Specifies the frequency with which the staleness of the tag is checked. The value is defined in days. Valid values are 1 day (the default) to 30 days.</p>

Archives Section

The Archives section displays the list of archives available with the selected data store. To edit an archive, select the archive and select the **Edit** button. The details of the archive are displayed in the Archive Details section.

Field	Description
Name	The name of the archive.
Start Time	The time of the oldest sample in the archive.
End Time	The time the archive is automatically or manually closed.

Archive Details Section

Archive Details section of the page lets you read and modify all archiving parameters for the Historian system.

Table 437. Archiving Parameters

Field	Description
Status	<p>The current operating state of the archive: Active, Current, Empty.</p> <ul style="list-style-type: none"> • Current: Archive is actively accepting data. • Active: Archive contains data but is not currently accepting data. • Empty: Archive was created but has never accepted data.
Start Time	The time of the oldest sample in the archive.
End Time	The time the archive is automatically or manually closed.
Last Backup On	The date and time the last backup was performed on this archive.
Backup By	User name (at time of login to Historian Administrator) of the person who performed the last backup of the archive.
File Location	The path and name of the archive file.
File Size (MB)	<p>The size (in MB) of the archive file.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: Historian now supports a maximum Archive Size of 256 GB per archive.</p> </div>
File Attribute	<p>The attribute to set a closed archive to Read-only or Read/Write.</p> <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: If you plan to create multiple archives at the same time, then you must set File Attribute to Read/Write.</p> </div>

Calculate Required Archive Size

Historian will asynchronously create a new empty archive when data starts loading into an existing archive. Whenever the current archive becomes full, Historian will immediately serve data to a newly created archive. This significantly reduces archive creation and transition time. If the option to

automatically create archives is not enabled, however, you must open a new archive manually. As of Historian 7.0, Historian archives are time-based only.

**CAUTION:**

When the default size limit is reached, if automatic archive creation is disabled and you do not manually create a new archive, new data will not be written to the archives .

**CAUTION:**

If the available disk space is less than the configured amount of free disk space, Historian cannot automatically create new archives.

If you enable the Overwrite Old Archives option, the system replaces the oldest archived data with new data. Since this action deletes historical data, exercise caution in using this feature. Be sure that you have a backup of the archive so that you can restore it later.

If you enable the Overwrite Old Archives option and if you want to retrieve time-based information, create an additional archive to overcome the early loss of data due to archive preparedness. For example, if you want to save 12 months of data into 12 archives, create 13 archives.

During archiver startup and every 60 seconds while the server is running, Historian checks to make sure that you have configured enough free disk space to save the archives, buffer files, and log files. If there is insufficient disk space, the Data Archiver shuts down and a message is logged into the log file. For each archive, you need approximately 1MB of archive space for every 1000 tags, for tag information.

By default, you can view the Historian archiver log file in `Historian Data\LogFiles`

```
[03/03/10 15:28:41.398] Insufficient space available in [d:\Historian\Archives\]
[03/03/10 15:28:41.399] The server requires a minimum of [5000 MB] to continue
[03/03/10 15:28:41.679] USER: DataArchiver TOPIC: ServiceControl MSG: DataArchiver(DataArchiver) Archiver s
[03/03/10 15:28:41.807] DataArchiver Service Stopped.
[03/03/10 15:28:41.809] [d:\Historian\LogFiles\DataArchiver-34.log] Closed.
```

Archive size is a function of the rate at which you archive data and the time period that you want the archive to cover. You may want the archive to cover a time period of perhaps, 30 days.

Factors that affect the rate at which you archive data are:

- Number of tags – a large number of tags increases the data rate.
- Polling frequency of each tag – a high polling frequency increases the data rate.

- Compression settings – disabling compression or setting narrow deadband parameters increases the data rate.
- Data types – choosing data types that increase the number of bytes per value increases the data rate.

The following is an example of a manual calculation of required archive size, using typical parameter values.

Table 438. Assumptions

Number of tags	5000
Polling rate	1 value/5 seconds
% Pass Compression	5% (Pass Compression is the number of data values archived relative to the number of values read, expressed as percent.)
Bytes/value:	4
Duration:	1 month (30 days)

Calculation

$$\#Tags \times \frac{Values}{Tag} \times \frac{Tags}{Second} \times \%PassComp \times \frac{Bytes}{Value} \times \frac{Seconds}{Hour} \times \frac{Hours}{Day} \times \frac{MB}{Bytes} = \frac{MB}{Day}$$

$$5000 \times \frac{1}{1} \times \frac{1}{5} \times \frac{5}{100} \times \frac{4}{1} \times \frac{3600}{1} \times \frac{24}{1} \times \frac{1}{1024 \times 1024} \times 30 = 494 \frac{MB}{Month}$$

The calculation shows that a file size of 500 MB is adequate for archiving one month of data for this application.

If you believe the calculated size is too large for your application, you can modify parameters as follows:

- Decrease the polling frequency.
- Increase compression deadband, reducing the pass percentage.
- Reduce the number of tags.
- Add more disk capacity to your computer.

Archive Size Calculator

An Archive Size Calculator tool is available to estimate archive size based on your input and estimates the archive size and collector compression based upon a tag that has already been configured. Log on to <http://support.ge-ip.com/devsupport/> to download this and other GE Intelligent Platforms freeware product solutions.

Prepare for Multiple Archive Creation

If you plan to create multiple archives at the same time, set the following parameters. These parameters apply **only** when creating multiple archives at the same time.

- In the **Archive Details** section, set **File Attribute** to **Read/Write**.
- In the **Configuration** Tab:
 - set **Automatically Create Archives** to **Disabled**.
 - set **Overwrite Old archives** to **Enabled**.
 - set **Store OPC Quality** to **Disabled**.
 - set **Data is Readonly After (Hours)** to **1 month**.
 - set **Generate Message on Data Update** to **Disabled**.

Before you begin creating multiple archives on a remote machine, ensure that you have enough hard disk space on that machine. The Allocate Space slider does **not** display a remote machine's hard disk space; the `r:percentage of available disk space will be used` message displayed by the Allocate Space slider will be inaccurate if it appears at all.

If you receive the error message `Runtime error 330 Invalid Property Value` while creating multiple archives on a remote machine, it is probably because you did not have enough hard disk space on that machine. When you select **OK** on the error message, Historian Administrator may disappear. You must now clean up the remote machine's hard disk space and restart Historian Administrator.

Adding One or More Archives


You may need to add an archive when the current archive is almost full and you have not enabled automatic creation of archives.



Note:

Historian now supports a maximum archive size of 256 GB per archive. When the current archive is full, the system will write to the next archive in the sequence in which it was created. As of Historian 7.0, Historian archives are time-based only.

1. In the **Archives** section, select the icon.
The Add New Archive(s) window appears.



The screenshot shows a dialog box titled "Add New Archive(s)". It has three input fields: "Archive Name" (empty), "File Location" (containing "C:\Proficy Historian Data\Archives\iha"), and "Archive Size(MB)" (containing "1"). At the bottom right, there are "Cancel" and "Ok" buttons.

2. In the **Archive Name** field, enter the name of the archive. The archive name must be the same as the filename.
3. In the **File Location** field, enter the path of the archive from a local drive or specify a UNC path.
4. In the **Archive Size (MB)** field, enter the size of the file in MB that you want to create.
5. Select **OK**.
6. Select **Cancel** to stop the operation.

If you cancel the operation, any archives already created during this operation will be deleted.

Back up Historian Archive Files

Back up your Historian archive files periodically to ensure your data is protected. Historian bundles alarms and events data with tag data in its backup files, and stores them as ZIP files. After an archive has been backed up, it can be stored to a shared network location, stored off-site, or written to physical media.



Note:

- Use Microsoft® [Volume Shadow Copy Service to back up archives more than 2 GB in size.](#) ([on page 2898](#)).
- Ensure that you have enough hard drive space on your default backup location before backing up your archives.
- For Historian 6.0 or later clients, you can only back up time-based archives.

The .IHC file is automatically backed up when, and only when, you back up the "current" archive .IHA file. By default, the .IHC backup path is the same as the archives path. The .IHC uses the following naming convention: `ComputerName_Config-Backup.ihc` If the default backup path is different than the

archives path, the .IHC file is copied to the backup folder with the standard .IHC naming convention `ComputerName_Config.ihc`.

If you back up an archive more than once, the backup tool will (by default) attempt to use the same name for the backup file and will detect that an archive with the same name already exists. Rename the backup archive file or move the original backup archive file from the target backup directory.

Backing up Archives using Historian

Best practice is to store archive **backups** in a different location than the archive **files**.

1. Open the **Archive Configuration** page.
2. In the **Archives** section, select an existing archive.
3. Select the **Backup** button.
4. Enter the **Archive Name**.
5. Save the backup file to the archive backup file location.

The Backing up Archive window appears.

A new Job Id is created and the details of the status are displayed in the Jobs Page.

Including Alarm Data in Archive Backups

When backing up your Historian archives, any alarms that have a life cycle that overlaps the data archive being backed up will be included. This means that an alarm with a long life cycle can be included up in multiple backups. For example, say the following alarm and archive dates were the following:

Alarm/Data Archive	Start Time	End Time
Alarm1	09/02/2004	09/06/2004
Archive1	09/01/2004	09/03/2004
Archive2	09/03/2004	09/04/2004
Archive3	09/04/2004	09/06/2004

If any or all of these archives are backed up, Alarm1 will go into the backup for each one. When the archives are restored, Historian will analyze the included alarm data and, if the data is already in the Historian archive, is intelligent enough to know it already has the alarm.

Use the following procedure to change alarm timestamp checking.

1. From the **Start** menu, select **Run** and enter `Regedit`.
2. Open the following key folder `HKEY_LOCAL_MACHINE\SOFTWARE\Intellution, Inc.\iHistorian\Services\DataArchiver\`
3. Create a new DWORD called **AlarmTimestampCheck** and set its value to 1.
Set **AlarmTimestampCheck** to 2 for slower timestamp checking. Set **AlarmTimestampCheck** to 0 to disable timestamp checking entirely.
4. Select **OK**.
5. Close the Registry Editor
6. Open Historian Administrator.
7. Restart the Data Archiver for the changes to take effect.

Backing up Archives Using Volume Shadow Copy Service

Historian can use the Microsoft® Volume Shadow Copy Service to back up and restore large archive files reliably and in a short period of time without affecting the data collection. The Historian Data Archiver uses `ihArchiverBackup.exe` as the default backup system. If you want to back up your archiver files regularly, you can set the scheduler to back up your files automatically.

VSS provides fast volume capture of the state of a disk which is called a snapshot or shadow copy. When the snapshot is taken, disk writes are suspended for a brief period of time, typically on the order of milliseconds. After the snapshot, disk writes can resume, but the original state of the files are maintained by a difference file. The difference file allows the state of the original file at the time of the snapshot to be reconstructed. This behavior allows files to be backed up while new data is being written to files.

If you are using `ihArchiveBackup.exe` before the upgrade, your backup will continue to work in the same or similar manner as it did before the upgrade. There is no change in the backup procedure and the Auto Recovery Backup Files option remains unchanged.



Note:

You can use both `ihArchiveBackup.exe` or VSS for backup, however, VSS is a better choice for larger archives to reduce the load on the Data Archiver service.

The Volume Shadow Copy feature is provided by Windows Operating System, and the instructions to use backup and restore vary depending on the backup application that is used in the Windows operating system.

Historian supports using the Volume Shadow Copy Service in the following operating systems.

- Microsoft® Windows® Server 2019 (64-bit)
- Microsoft® Windows® Server 2016 (64-bit)
- Microsoft® Windows® Server 2012 R2 (64-bit)
- Microsoft® Windows® 10 IoT (32-bit or 64-bit)
- Microsoft® Windows® 10 (32-bit or 64-bit)
- Microsoft® Windows® 8.1 Professional (32-bit or 64-bit)

Microsoft uses a backup format called Virtual Hard Disk (VHD) to back up files. If you create an archive backup using Microsoft® Volume Shadow Copy Service, you must first restore the archives files (that is, convert **.bkf** or **.vhd** into **.iha**) using the Windows Restore wizard, and then restore the archives (.iha) into Historian. For more information on restoring an archive (.iha) into Historian, refer to the [Restoring an Archive \(on page 2899\)](#) topic.

In addition to using the Backup and Restore wizard, you can also use the command line utilities:

- Refer to How to use command line parameters with the Ntbackup command: <http://support.microsoft.com/kb/814583>
- Refer to How to use command line parameters with the Wbadmin command: [http://technet.microsoft.com/en-us/library/cc754015\(WS.10\).aspx](http://technet.microsoft.com/en-us/library/cc754015(WS.10).aspx)
- If you need additional assistance about using Windows Server Backup Wizard, refer to Microsoft's website at: <http://technet.microsoft.com/en-us/library/cc753528.aspx>

Restore Historian Archive Files

Under certain circumstances, you may want to restore tag and alarms and events data to Historian. This may be after an unplanned shutdown, or you may need to retrieve data from an old, inactive archive. You can restore only time-based archives.

**Warning:**

Never restore an archive to a production Historian server without a current archive already online.

**CAUTION:**

Restoring an archive is a resource-intensive operation and should be scheduled for non-peak usage times.

Restoring Archives from Historian Backup Files

If it is not already present, **copy** the archive file to the default archive path. Leave the original backup file where it is. Archives that have been previously removed from Historian can be found in the `\Archives` `\Offline` directory. Archives on removable media must also be copied into the default archive path.

1. Open the **Archive Configuration** page.
2. Select the **Restore Archive** icon.
The Restore Archive window appears.
3. In the **Archive Name** field, enter the name of the archive you want to restore.
4. In the **File Location** field, enter the path name of the archive from a local drive or specify a UNC path.
5. Verify that the file name and path are correct.
6. In the **Data Store** field, select the name of the data store to load the archive file into.
If Historian is unable to find the specified data store, the file will be loaded to the default data store.
7. Select **OK**.
The restored archive is moved to the `\Archive` directory and is made available for querying.

Chapter 43. Extract, Transform, and Load (ETL)

Overview of the Historian ETL Tools

Transferring data from one Historian server to another is typically performed by Proficy Historian collectors. These collectors provide a connected streaming data transfer mechanism (except the Calculation and File collectors). In a system where a steady network connection is not possible or not cost-effective, a periodic file-oriented data transfer is preferred. The Historian Extract, Transform, and Load (ETL) tools consist of a comprehensive set of file-oriented data extraction, transfer, and loading tools.

Potential ways of using ETL tools:

- Data transfer from any of the following sources:
 - An eDNA server
 - An ODBC data source
 - Proficy Historian
 - PI Historian
- Data transfer via radio or low bandwidth cellular connection
- Data transfer where there is no connectivity (read and write using portable media)
- Data transfer for periodic connectivity applications (for example, ships can transfer data when they arrive at a port)
- Data migration from OSI PI Server to Proficy Historian
- Data extraction to import into other applications
- Data import from other applications

Components of Historian ETL:

- **Extract:** Using this tool, you can extract time series data from an eDNA server, an ODBC data source, Proficy Historian or PI Server. For Proficy Historian, you can also extract alarms and events data, perform scaling and absolute deadband compression.
- **Transform:** Using this tool, you can transfer data from an onsite Historian server or an ODBC data source to the destination Historian server using a file-sharing application such as FTP, BITS, and so on.
- **Load:** Using this tool, you can load data into Proficy Historian. This tool monitors a file directory, unzips the files, and processes them.

Depending on the use case, you can use these tools independently or together.

Limitations:

- The ETL tools do not support array data.

Workflow for Transferring Data from eDNA

To transfer data from an eDNA server, you must perform the following steps.

Step Number	Description	Notes
1	Install Historian ETL (on page 202) .	This step is required. You must install ETL on both the source and destination machines of the data transfer. <div data-bbox="902 783 1419 1255" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;">  Note: If you want to upgrade ETL: <ol style="list-style-type: none"> 1. Uninstall the existing version of ETL. 2. Backup the configuration files, and delete them. 3. Install the latest version of ETL. </div>
2	Specify the tags whose data you want to extract. You can do so using the utility (on page 2911) , creating the configuration file manually (on page 2912) , using a template (on page 2913) , or using a blank spreadsheet (on page 2914) .	This step is required. It involves providing a list of tags whose data you want to extract.
3	Configure the extract settings (on page 2933) .	This step is required. It involves providing the .xml files that contain the tags list and the tables list, along with other parameters.
4	Start the data extraction (on page 2937) .	This step is required. It involves extracting tag data and compressing it so that it can

Step Number	Description	Notes
		be transferred to the destination Historian server.
5	Transfer the data using BITS (on page 2957) , FTP (on page 2959) , or any other file-sharing application.	This step is required. It involves setting up the file-sharing application that you want to use and then transferring the data to the machine on which the destination Historian server is installed.
6	Load the data (on page 2961) into the destination Historian server.	This step is optional. It involves extracting the .zip files transferred by the file-sharing application and then loading the data into the destination Historian server.

**Note:**

Depending on the use case, you can use these tools independently or together.

Workflow for Transferring Data from an ODBC Data Source

To transfer data from an ODBC data source, you must perform the following steps.

Step Number	Description	Notes
1	Install Historian ETL (on page 202) .	<p>This step is required. You must install ETL on both the source and destination machines of the data transfer.</p> <div data-bbox="912 1482 964 1533" data-label="Image"> </div> <div data-bbox="971 1493 1049 1524" data-label="Section-Header">Note:</div> <div data-bbox="971 1535 1308 1570" data-label="Text"> <p>If you want to upgrade ETL:</p> </div>

Step Number	Description	Notes
		 <ol style="list-style-type: none"> 1. Uninstall the existing version of ETL. 2. Backup the configuration files, and delete them. 3. Install the latest version of ETL.
2	Specify the tags and tables whose data you want to extract. You can do so manually (on page 2924) , using a template (on page 2926) , or using a blank spreadsheet (on page 2928) .	This step is required. It involves providing a list of tags whose data you want to extract and the tables from which you want to extract data.
3	Configure the extract settings (on page 2933) .	This step is required. It involves providing the .xml files that contain the tags list and the tables list, along with other parameters.
4	Start the data extraction (on page 2937) .	This step is required. It involves extracting tag data and compressing it so that it can be transferred to the destination Historian server.
5	Transfer the data using BITS (on page 2957) , FTP (on page 2959) , or any other file-sharing application.	This step is required. It involves setting up the file-sharing application that you want to use and then transferring the data to the machine on which the destination Historian server is installed.
6	Load the data (on page 2961) into the destination Historian server.	This step is optional. It involves extracting the .zip files transferred by the file-sharing application and then loading the data into the destination Historian server.



Note:

Depending on the use case, you can use these tools independently or together.

Workflow for Transferring Data from Proficy Historian

To transfer data from Proficy Historian, you must perform the following steps.

Step Number	Description	Notes
1	<p>Install Historian ETL (on page 202).</p>	<p>This step is required. You must install ETL on both the source and destination machines of the data transfer.</p> <div data-bbox="1024 621 1419 1182" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; background-color: #E6F2FF;"> <p> Note: If you want to upgrade ETL:</p> <ol style="list-style-type: none"> 1. Uninstall the existing version of ETL. 2. Backup the configuration files, and delete them. 3. Install the latest version of ETL. </div>
2	<p>Specify the tags and tables whose data you want to extract. You can do so manually (on page 2938), using a template (on page 2939), or using a blank spreadsheet (on page 2940).</p>	<p>This step is required. It involves providing a list of tags whose data you want to extract and the tables from which you want to extract data.</p>
3	<p>Configure the extract settings (on page 2942).</p>	<p>This step is required. It involves providing the .xml files that contain the tags list and the tables list, along with other parameters. You can also extract alarms and events data.</p>
4	<p>Start the data extraction (on page 2947).</p>	<p>This step is required. It involves extracting tag data and com-</p>

Step Number	Description	Notes
		pressing it so that it can be transferred to the destination Historian server.
5	Transfer the data using BITS (on page 2957) , FTP (on page 2959) , or any other file-sharing application.	This step is required. It involves setting up the file-sharing application that you want to use and then transferring the data to the machine on which the destination Historian server is installed.
6	Load the data (on page 2961) into the destination Historian server.	This step is optional. It involves extracting the .zip files transferred by the file-sharing application and then loading the data into the destination Historian server.



Note:

Depending on the use case, you can use these tools independently or together.

Workflow for Transferring Data from PI Historian

To transfer data from PI Historian, you must perform the following steps.

Step Number	Description	Notes
1	Install Historian ETL (on page 202) .	<p>This step is required. You must install ETL on both the source and destination machines of the data transfer.</p> <div data-bbox="1036 1602 1421 1753" style="border: 1px solid #0070C0; border-radius: 10px; padding: 5px; margin-top: 10px;">  <p>Note: If you want to upgrade ETL:</p> </div>

Step Number	Description	Notes
		 <ol style="list-style-type: none"> 1. Uninstall the existing version of ETL. 2. Backup the configuration files, and delete them. 3. Install the latest version of ETL.
2	Specify the tags and tables whose data you want to extract. You can do so manually (on page 2948) , using a template (on page 2949) , or using a blank spreadsheet (on page 2950) .	This step is required. It involves providing a list of tags whose data you want to extract and the tables from which you want to extract data.
3	Configure the extract settings (on page 2952) .	This step is required. It involves providing the .xml files that contain the tags list and the tables list, along with other parameters.
4	Start the data extraction (on page 2957) .	This step is required. It involves extracting tag data and compressing it so that it can be transferred to the destination Historian server.
5	Transfer the data using BITS (on page 2957) , FTP (on page 2959) , or any other file-sharing application.	This step is required. It involves setting up the file-sharing application that you want to use and then transferring the data to the machine on which the destination Historian server is installed.
6	Load the data (on page 2961) into the destination Historian server.	This step is optional. It involves extracting the .zip files transferred by the file-sharing application and then loading the data in-

Step Number	Description	Notes
		to the destination Historian server.

**Note:**

Depending on the use case, you can use these tools independently or together.

Install the Historian ETL Tools

- If you want to use the Historian Extract, Transform, and Load (ETL) tools to transfer data from a PI Historian server, install the PI SDK package.
- If you want to use the ETL tools to transfer data from an eDNA server, copy the following eDNA binaries to the `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract` folder:
 - `EzDnaApi.dll`
 - `EzDNAApiNet.dll`


By default, these files are available in the following folder on the machine on which the eDNA server is installed: `C:\Program Files(x86)\eDNA`

Installing ETL installs the following tools:

- The Extract tool
- The Transform tool
- The Load tool

This topic describes how to install ETL to extract, transform, and load data from an onsite Historian machine to the destination Historian server. You must install Historian ETL on both the onsite Historian machine and the destination Historian server (that is, the source and destination machines for data transfer).

1. Run the `InstallLauncher.exe` file.
2. Select **Install Historian ETL Tools**.
The welcome page appears.
3. Select **Next**.
The license agreement appears.
4. Select the **Accept** check box, and then select **Next**.
The default installation drive appears.



5. If required, modify the installation drive for Historian ETL, and then select **Next**.

A message appears, stating that you are ready to install ETL.

6. Select **Install**.

The Historian ETL tools are installed on your machine.

- The following folders are created in the `<installation drive>/Program Files/GE Digital` folder:
 - Historian ETL eDNA Extract
 - Historian ETL Extract
 - Historian ETL Load
 - Historian ETL ODBC Extract
 - Historian ETL PI Extract
 - Historian ETL Transform
- The following services are installed:
 - Historian ETL eDNA Extract
 - Historian ETL Extract
 - Historian ETL ODBC Extract_x64

- Historian ETL ODBC Extract_x86
- Historian ETL Load
- Historian ETL PI Extract
- The following registry paths are created:
 - HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\GE Digital\Historian ETL eDNA Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\GE Digital\Historian ETL ODBC Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\Historian ETL Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\Historian ETL ODBC Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\Historian ETL PI Extract
 - HKEY_LOCAL_MACHINE\SOFTWARE\GE Digital\Historian ETL Load

1. If you want to extract data from an eDNA server, copy the `Customdna.ini` file in the eDNA server into the `C:\Windows` folder on the machine on which you have installed ETL.
2. Extract data from [an eDNA server \(on page 2910\)](#), [ODBC data source \(on page 2924\)](#), [Proficy Historian \(on page 2938\)](#), or [PI Historian \(on page 2948\)](#).

Upgrade the ETL Tools

1. Uninstall the existing version of Historian ETL.
2. Backup the configuration files, and delete them.
3. [Install the latest version of Historian ETL \(on page 202\)](#).

About Extracting Data from an eDNA Server

The Historian ETL eDNA Extract tool extracts data as follows:

1. Extracts data related to tags into text files, which are named in the following format: `YYYYDDMMHRR_<OSM name>.txt`. These files are stored in the following folder: `<installation drive>\Historian ETL eDNA Extract\Hist Files`.

You can only extract tag data; you cannot extract alarms and events data.

2. After a specified number of files are extracted (by default, 6), the files are compressed into a .zip file, which is named in the following format: `YYYYDDMMHRR_<OSM name>.zip`. These files are stored in the following folder: `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\Zip Files`.
3. Deletes the text files in the `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\Hist Files` folder after they are compressed.

Specify Tags for the eDNA Data Extraction Using a Utility

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags by generating the tag configuration file automatically using the Historian ETL eDNA Extract utility. Alternatively, you can specify the tags by [creating a configuration file manually \(on page 2912\)](#), [using a template spreadsheet \(on page 2913\)](#), or [using a blank spreadsheet \(on page 2914\)](#).

1. Run the `HistorianETLeDNAExtractConfigTool` file located in the `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract` folder.



Tip:

You can also enter ETL eDNA Extract in Windows Run.

The **Historian ETL eDNA Extract Settings** window appears, displaying the **Basic Configuration** section.

2. Select **Files**, and then provide values as specified in the following table.

Field	Description
Service Name	Enter the service name used by the Historian ETL eDNA Extract tool to connect to the eDNA server. You can enter multiple values separated by commas.
Tag Name	Specify whether you want to use the extended ID or the long ID in the tag name. If you select ExtendedID , the name of the tag created in Historian will contain the extended ID (and the spare field of the tag will contain the long ID). Similarly, if you select LongID , the name of the tag created in Historian will contain the long ID (and the spare field of the tag will contain the extended ID).
OSM Name	Enter a name to identify the Original Equipment/Sales Manufacturer (OSM). This name is included in the .zip files that are extracted on this machine.
Zip TagConfig	Select True if you want to create a .zip file of the metadata of eDNA tags. It is a good practise to create a .zip file of the metadata.

3. Select **Tag Config File**.

A file named `TagConfig.xml` is generated in the `<installation drive>:\Program Files\GE Digital\Historian ETL eDNA Extract` folder. This file contains the list of tags and their properties.

[Configure the eDNA Data Extraction settings \(on page 2916\)](#).

Specify Tags for eDNA Data Extraction Manually

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags by creating a configuration file manually. Alternatively, you can specify the tags using [the utility \(on page 2911\)](#), [a template spreadsheet \(on page 2913\)](#), or [a blank spreadsheet \(on page 2914\)](#).

1. Run the `HistorianETLeDNAExtractConfigTool` file located in the `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract` folder.



Tip:

You can also enter ETL eDNA Extract in Windows Run.

The **Historian ETL eDNA Extract Settings** window appears, displaying the **Basic Configuration** section.

2. Select **Files**, and then select **Sample Tag Config**.

A sample tag configuration .xml file is created.

3. Include the [tag properties \(on page 2916\)](#) for all the tags whose data you want to extract.

Tag properties for a tag named voltage used in an eDNA server:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<Taglist>
  <Tag Name="SUBSTN.TATANAGR.BUS.6B1.MES1.KV">
    <LocalName>A0000001</LocalName>
    <RemoteName>SUBSTN.TATANAGR.BUS.6B1.MES1.KV</RemoteName>
    <ServiceName>JHARMP.SCADA1</ServiceName>
    <DataType>Float</DataType>
    <RemoteNameDesc>SUBSTN.TATANAGR.BUS</RemoteNameDesc>
    <RemoteNameSpare4>SUBSTN.TATANAGR.BUS</RemoteNameSpare4>
    <RemoteNameSpare5>SUBSTN.TATANAGR.BUS</RemoteNameSpare5>
    <RemoteNameEnggUnits>MW</RemoteNameEnggUnits>
```

```
<TagName>ExtendedID</TagName>

</Tag>

</Taglist>
```

4. In the `HistorianETLeDNAExtractConfigTool` file located at `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract`, select **Files**, and then in the **Tag Configuration File** field, provide the path to the configuration file that you have created, and then select **Save**.

The tag configuration file is specified.

[Configure the eDNA Data Extraction settings \(on page 2916\)](#).

Specify Tags for eDNA Data Extraction Using a Template

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags using a template spreadsheet, which is provided with the Historian ETL package. Alternatively, you can specify the tags [using the utility \(on page 2911\)](#), [using a blank spreadsheet \(on page 2914\)](#), or [by creating a configuration file manually \(on page 2912\)](#).

1. Access the `eDNAHistTagConfigGenerateExcel.xlsx` file located in the `Historian eDNA ETL Extract` folder.
2. **Optional:** If you want to modify an existing tag configuration file, you can import the data from that .xml file by selecting **Developer > Import**.



Tip:

If the **Developer** tab is not available, right-click the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

Data from the .xml file is imported into the spreadsheet.



Note:

If an error occurs, stating that the data is not valid according to the schema, verify that:

- You have provided values in all the red-colored columns.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to [Tag Properties \(on page 2916\)](#).

3. For each tag, enter or modify values in the columns for the [tag properties \(on page 2916\)](#). A value is required in the red-colored columns.
4. Save the file.
5. Select **Developer > Export**.



Tip:

If the **Developer** tab is not available, right-click the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

6. Enter a name and location for the .xml file.
The tag configuration file is created with the list of tags and their properties to be extracted.
If an error occurs, stating that the data is not valid according to the schema, verify that:
 - You have provided values in all the red-colored columns.
 - Values in the Name column are unique.
 - There are no blank rows.
 - The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to [Tag Properties \(on page 2916\)](#).

7. In the `HistorianETLeDNAExtractConfigTool` file located at `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract`, select **Files**, and then in the **Tag Configuration File** field, provide the path to the configuration file that you have created, and then select **Save**.

The tag configuration file is specified.

[Configure the eDNA Data Extraction settings \(on page 2916\)](#).

Specify Tags for eDNA Data Extraction Using a Blank Spreadsheet

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags manually by creating a configuration file. Alternatively, you can specify the tags using [the utility \(on page 2911\)](#), [a template spreadsheet \(on page 2913\)](#) or [a blank spreadsheet \(on page 2914\)](#).

1. Create a Microsoft Excel file.
2. Enter column names matching the names of the [tag properties \(on page 2916\)](#).
3. **Optional:** If you want to modify an existing tag configuration file, you can import the data from that .xml file by selecting **Developer > Import**.

**Tip:**

If the **Developer** tab is not available, right-click the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

**Note:**

If a message appears, stating that the .xml file is not linked to schema, ignore the message.

4. Select **Developer > Source > XML Maps > Add**.
5. Select the `eDNAHistTagConfigSchema.xsd` file located in the `<installation drive>:\Program Files\GE Digital\Historian ETL eDNA Extract` folder.
6. Map each column name with each entry under **Taglist** in the **XML Source** section. To do so, select each column name, and then double-click the corresponding property under **Taglist**. Each property under **Taglist** changes to bold formatting, indicating that it is mapped to the corresponding column.
7. For each tag, enter or modify values in the columns.
8. Select **Design > Properties**, select the **Validate data against schema for import and export** check box, and then select **OK**.
9. Save the file.
10. Select **Developer > Export**.
11. Enter a name and location for the .xml file.
The tag configuration file is created with the list of tags and their properties to be extracted.
If an error occurs, stating that the data is not valid according to the schema, verify that:
 - You have provided values in all the red-colored columns.
 - Values in the Name column are unique.
 - There are no blank rows.
 - The values that you have entered are valid and of the same data type as defined for each property.
 For details, refer to [Tag Properties \(on page 2916\)](#).
12. In the `HistorianETLeDNAExtractConfigTool` file located at `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract`, select **Files**, and then in the **Tag Configuration File** field, provide the path to the configuration file that you have created, and then select **Save**.
The tag configuration file is specified.

[Configure the eDNA Data Extraction settings \(on page 2916\)](#).

Tag Properties for eDNA Data Extraction

This topic provides a list of tag properties that you can define for each tag that you want to extract from an eDNA server.

Column Name	Data Type	Description
Name	String	Enter the name of the tag. A value is required and must be unique.
LocalName	String	Enter a unique identifier for the tag. A value is required and must be unique.
RemoteName	String	Enter the name of the tag that you want to use after it is imported to Historian. A value is required.
ServiceName	String	Enter the service name used to connect to the eDNA server. You can enter multiple values separated by commas. A value is required.
DataType	String	Enter the data type of the tag. A value is required.
RemoteNameDesc	String	Enter the description of the remote name. A value is required.
RemoteNameSpare4	String	Enter the longID or extendedID of the tag. A value is required.
RemoteNameSpare5	String	Enter a description for the value in the RemoteNameSpare4 parameter. A value is required.
RemoteNameEngg-Units	String	Enter the engineering units of the tag values. A value is required.
TagName	String	Specify whether you want to use the extended ID or the long ID in the tag name.

Configure the eDNA Data Extraction Settings

Specify the tags whose data you want to extract from an eDNA server. You can do so by [using the utility \(on page 2911\)](#), [creating a configuration file manually \(on page 2912\)](#), [using a template \(on page 2913\)](#), or [using a blank spreadsheet \(on page 2914\)](#).

This topic describes how to configure the settings for eDNA data extraction. These settings are saved in the `eDNAHistorianETLExtract.exe.config` file.

1. Run the `HistorianETLeDNAExtractConfigTool` file located in the `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract` folder.

**Tip:**

You can also enter ETL eDNA Extract in Windows Run.

The **Historian ETL eDNA Extract Settings** window appears, displaying the **Basic Configuration** section.

2. If the configuration details are stored in a file, select **Import Config** to import the settings, and skip to step 6.
3. Provide values as specified in the following table.

Field	Description	Default Value
Service Name	Enter the service name used by the Historian ETL eDNA Extract tool to connect to the eDNA server. You can enter multiple values separated by commas.	
Tag Name	Specify whether you want to use the extended ID or the long ID in the tag name. If you select ExtendedID , the name of the tag created in Historian will contain the extended ID (and the spare field of the tag will contain the long ID). Similarly, if you select LongID , the name of the tag created in Historian will contain the long ID (and the spare field of the tag will contain the extended ID).	
Run Interval (Seconds)	Enter the interval, in seconds, at which the Historian ETL eDNA Extract tool will extract data. You must enter a value greater than or equal to 60.	150 (that is, a text file is created for data that is extracted in 150 seconds)
Min # of Files to Compress	Enter the number of files that must be compressed into a single .zip file.	6 (that is, a .zip file is created for every six text files)
Extract Type	Specifies whether you want to extract only the current data or historical data or both.	Both (Historical and Current)

Field	Description	Default Value
OSM Name	Enter a name to identify the Original Equipment/Sales Manufacturer (OSM). This name is included in the .zip files that are extracted on this machine.	Host name of the local machine
Zip TagConfig	Select True if you want to create a .zip file of the metadata of eDNA tags.	

4. Select **Files**, and then provide values as specified in the following table.

Field	Description	Default Value
Historian Export Path	Enter the path to the folder in which the text files containing the extracted data must be stored.	<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\Hist Files
Tag Configuration File	Enter the path to the tag configuration that you have created. You can create it automatically (on page 2911) , manually (on page 2912) , a template spreadsheet (on page 2913) , or using a blank spreadsheet (on page 2914) .	<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\TagConfiguration.xml
Zip Export Path	Enter the path to the folder in which the compressed files must be stored.	<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\Zip Files
State File	Enter the path to the file that the Historian ETL eDNA Extract tool will create to store the timestamp of the last successful export. This timestamp is used to identify the start time for the next iteration of extraction. This ensures that there is no loss of data during extraction.	<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\State.xml

Field	Description	Default Value
	<p>For example, suppose the current time is 11am, and data has been extracted only till 9am. The state file contains the timestamp for 9am. Therefore, when data extraction is resumed, it is extracted from 9am.</p> <p>The state file is created after you apply the Historian ETL eDNA Extract settings. It is updated each time .zip files are transferred to the destination Historian server or when the Historian ETL eDNA Extract tool is stopped. For a sample state file, refer to Example of a State File (on page 2968).</p>	
Regen File	<p>Enter the path to the regeneration file. You can use this field to extract data.</p> <p>If the Gen Sample Regen File field is set to True, a sample regeneration file will be created after you apply the settings. You can modify this file as needed, and specify the path of the same file in the Regen File field. For a sample regeneration file, refer to Example of a Regeneration File (on page 2966).</p>	<code><installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\Regen.xml</code>
Gen Sample Regen File	<p>Specify whether you want to generate the sample regeneration file. You can then modify this file as needed.</p>	False
Sample Regen File	<p>Enter the path to the sample regeneration file that will be created if the Gen Sample Regen File field is set to True. You can modify this file as needed.</p>	<code><installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\Sample_Regen.xml</code>

Field	Description	Default Value
Tag Config File	Select this button to generate a file with the list of tags from which you want to extract data. For instructions, refer to Specify Tags for the eDNA Data Extraction Using a Utility (on page 2911) .	
Sample Tag Config	Select this button to generate a sample tag configuration file. You can then include the list of tags from which you want to extract data. For instructions, refer to Specify Tags for eDNA Data Extraction Manually (on page 2912) .	

5. Select **Advanced Configuration**, and then provide values as specified in the following table.

Field	Description	Default Value
Log Level	Select the log level to indicate the amount of information to be logged. The following options are available: <ul style="list-style-type: none"> ◦ Info ◦ Error ◦ Debug 	Info
Delay Interval	The duration, in seconds, by which the data retrieval time will be reduced. For example, if data will be retrieved for 10 minutes, and if you enter 60 in this field, data for the last 60 seconds will not be retrieved in that batch; it will be retrieved in the next batch. This will ensure the retrieval of any dynamic records that were updated in that duration.	60
Catch Up Interval (Minutes)	Enter the catchup interval, in minutes, used to size files when catching up to the current time.	10

Field	Description	Default Value
Save Limit	Enter the number of files to be exported after which the <code>State.xml</code> file must be updated.	20
Catch Up Time Limit (Hours)	Enter the maximum time, in hours, to go back when catching up after a restart. If you want to extract historical data as well, enter the duration for which you want to extract the data. For example, if you want to extract data for the past one day, enter 24.	168
Quality Conversion Good	<p>Enter the mapping details for good quality between eDNA hexadecimal codes and SCADA binary codes.</p> <p>For example, if the hexadecimal code for good quality is 8203, and if the binary codes in a SCADA system for good quality are 1, 27, and 30, enter 8203=1,27,30.</p> <p>Use a semicolon to separate multiple entries (for example, 8203=27,30,1;8003=30;203=34).</p> <p>If this field is blank, all the values are considered as bad quality, without storing any binary digits.</p>	
Quality Conversion Bad	<p>Enter the mapping details for bad quality between eDNA hexadecimal codes and SCADA binary codes.</p> <p>For example, if the hexadecimal code for bad quality is C003, and if the binary codes in a SCADA system for good quality are 2, 4, and 6, enter C003=2,4,6.</p> <p>Use a semicolon to separate multiple entries (for example, C003=2,4,6;C406=8,9).</p>	

Field	Description	Default Value
	If this field is blank, all the values are considered as bad quality, without storing any binary digits.	

6. Select **Save**.

The changes to the settings are applied and saved in the `HistorianETLeDNAExtract.exe.config` file.

Start the data extraction ([on page 2923](#)).

Extract Historical eDNA Data

By default, the ETL tools extracts both current and historical data. This topic describes how to configure the settings to extract historical data using the ETL tools.

1. Create a regeneration file, specifying the start time, end time, and interval for which you want to capture the historical data. For a sample regeneration file, refer to [Example of a Regeneration File \(on page 2966\)](#).
2. Run the `HistorianETLeDNAExtractConfigTool` file located in the `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract` folder.



Tip:

You can also enter ETL Historian eDNA Extract in the Windows Start menu.

The **Historian ETL Extract Configuration** window appears, displaying the **Basic Configuration** section.

3. Select **Advanced Configuration**, and then provide values as specified in the following table.

Field	Description	Default Value
Regen File	Enter the path to the regeneration file that you have created.	<code><installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\Regen.xml</code>
Catch Up Time Limit	Enter the duration, in hours, for which you want to extract historical data.	168

Field	Description	Default Value
	For example, if you want to extract data for the past one day, enter 24.	
Temp Regen File	Enter the path to the temporary regeneration file.	<code><installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract\Temp_Regen.xml</code>
Generate Temp Regen File	Select True .	False

- As needed, [provide values in the remaining fields \(on page 2942\)](#).

[Start the data extraction \(on page 2923\)](#).

Start the eDNA Data Extraction

- [Configure the Historian ETL eDNA Extract settings \(on page 2916\)](#).
- If the machine on which you want to extract the data is different from the eDNA sever, access the `hosts` file located in `C:\Windows\System32\drivers\etc`, and add the host name and IP address of the eDNA server in the following format:

```
<IP address> <eDNA service directory name>
```

For example: 100.300.50.7 dna_svcdir_01

- Run the `HistorianETLeDNAExtractConfigTool` file located in the `<installation drive>\Program Files\GE Digital\Historian ETL eDNA Extract` folder.



Tip:

You can also enter ETL Historian eDNA Extract in the Windows Start menu.

The **Historian ETL eDNA Extract Configuration** window appears.

- Select **Start Service**.

Data extraction from the eDNA server begins.



Tip:

If the tool does not start as expected, access the logs using Windows Event Viewer.

Transfer data using [BITS \(on page 2957\)](#), [FTP \(on page 2959\)](#), or any other file-sharing application.

About Extracting Data from an ODBC Data Source

The Historian ETL ODBC Extract tool extracts data as follows:

1. Extracts data related to tags into text files, which are named in the following format:

`YYYYDDMMHHRR_<onsite Historian computer name>.txt`. These files are stored in the following folder: `<installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\Hist Files`.

You can only extract tag data; you cannot extract alarms and events data.

2. After a specified number of files are extracted (by default, 6), the files are compressed into a .zip file, which is named in the following format: `YYYYDDMMHHRR_<DSN>.zip`. These files are stored in the following folder: `<installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\Zip Files`.
3. Deletes the text files in the `<installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\Hist Files` folder after they are compressed.

Specify Tags and Tables for ODBC Data Extraction Manually

Before you extract data, you must specify the tags and tables whose data you want to extract.

This topic describes how to specify the tags and tables manually by creating a configuration file. Alternatively, you can specify them using a [template spreadsheet \(on page 2926\)](#) or a [new spreadsheet \(on page 2928\)](#).

1. Create an .xml file to include the [tag properties \(on page 2931\)](#) for all the tags whose data you want to extract.

Tag properties for a tag named Pressure used in an ODBC data source:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<Taglist>
  <Tag Name="Pressure">
    <LocalName>ValvePressure</LocalName>
    <RemoteName>ValvePressure</RemoteName>
    <DataType>int</DataType>
    <TableName>Valve_Pressure_Table</TableName>
  </Tag>
</Taglist>
```

2. Create another .xml file to include the column names of the table for each tag whose data you want to extract. This file is used to identify the column names in the database table whose data you want to extract. For a list of table properties that you can specify, refer to [Table Properties for an ODBC Data Source \(on page 2932\)](#).

Suppose you want to extract values of a tag named Pressure from a table named Valve_Pressure_Table. Suppose this table contains the following columns in the database:

- TagName
- TagQuality
- TagTimestamp
- TagValue

In this case, provide these column names as follows:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<TableList>
  <Table>
    <TableName>Valve_Pressure_Table</TableName>
    <TagName>TagName</TagName>
    <Timestamp>TagTimestamp</Timestamp>
    <Value>TagValue</Value>
    <Quality>TagQuality</Quality>
    <Condition></Condition>
  </Table>
</TableList>
```

In addition, you can specify other properties to determine the quality of each value. For example, suppose you want to define the quality values as follows:

Tag Value	Quality
0-50	Good
51-100	Bad
101 and 102	Uncertain
103, 104, and 105	Not applicable

In that case, provide these values as follows:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<TableList>
  <Table>
```

```

<TableName>PressureTable</TableName>
<TagName>TagName</TagName>
<Timestamp>TagTimestamp</Timestamp>
<Value>TagValue</Value>
<Quality>TagQuality</Quality>
<QualityStatus>
  <ihOPCBad>0-50</ihOPCBad>
  <ihOPCGood>51-100</ihOPCGood>
  <ihOPCUncertain>101,102</ihOPCUncertain>
  <ihOPCNA>103,104,105</ihOPCNA>
</QualityStatus>
<Condition></Condition>
</Table>
</TableList>

```

When you do so, if the tag value is, say, 56, the quality of the value is stored as Good in Historian. However, if this value does not match the value in the Quality column, the value is stored as Bad in Historian.

3. Verify that all the tags and tables that you specify in the first file contain the corresponding entries in the second file.

[Configure the Historian ETL ODBC Extract settings \(on page 2933\).](#)

Specify Tags and Tables ODBC Data Extraction Using a Template

Before you extract data, you must specify the tags and tables whose data you want to extract.

This topic describes how to specify the tags using a template spreadsheet, which is provided with the Historian ETL package. Alternatively, you can specify the tags using a [new spreadsheet \(on page 2928\)](#) or by [creating a configuration file manually \(on page 2924\)](#).

1. Access the `ETLODBCConfigXMLGenerate.xlsx` file located in the Historian ETL ODBC Extract folder.
2. **Optional:** If you want to modify an existing tag configuration file, you can import the data from that .xml file by selecting **Developer > Import**. Similarly, if you want to modify an existing table configuration file, import the data into a separate worksheet.

**Tip:**

If the **Developer** tab is not available, right-click the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

Data from the .xml file is imported.

**Note:**


If an error occurs, stating that the data is not valid according to the schema, verify that:

- You have provided values in all the red-colored columns.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to the [Tag Properties \(on page 2931\)](#) and [Table Properties \(on page 2932\)](#) topics.

3. For each tag, enter or modify values in the columns in the **ETLODBCTagConfig** worksheet. A value is required in the red-colored columns. For a list of tag properties that you can provide, refer to [Tag Properties for ODBC Data Extraction \(on page 2931\)](#).
4. Select the **ETLODBCTableConfig** worksheet.
5. For each tag that you specified in the **ETLODBCTagConfig** worksheet, specify the [table properties \(on page 2932\)](#). A value is required in the red-colored columns.
6. Save the file.
7. To create a tag configuration file:
 - a. Select the **ETLODBCTagConfig** worksheet.
 - b. Select **Developer > Export**.

The **Export XML** window appears, asking you to choose whether you want to export the tag configuration or the table configuration.




- c. Select **Taglist_Map**, and then select **OK**.
- d. Provide a file name and location.

The tag configuration file is created with the list of tags whose data you want to extract.

8. To create a table configuration file:

- a. Select the **ETLODBCTableConfig** worksheet.
- b. Select **Developer > Export**.

The **Export XML** window appears, asking you to choose whether you want to export the tag configuration or the table configuration.



- c. Select **TableList_Map**, and then select **OK**.
- d. Provide a file name and location.

The table configuration file is created with the list of tables from which you want to extract data.

[Configure the Historian ETL ODBC Extract settings \(on page 2933\)](#), providing the paths to the two .xml files you have created.

Specify Tags and Tables for ODBC Data Extraction Using a Blank Spreadsheet

Before you extract data, you must specify the tags and tables whose data you want to extract.


This topic describes how to specify the tags using a new spreadsheet. Alternatively, you can specify the tags [using a template spreadsheet \(on page 2926\)](#) or by [creating a configuration file manually \(on page 2924\)](#).

1. Create a Microsoft Excel file, and create the following worksheets:
 - **ETLODBCTagConfig**
 - **ETLODBCTableConfig**
2. In the **ETLODBCTagConfig** worksheet, enter column names matching the names of the [tag properties \(on page 2931\)](#). Similarly, in the **ETLODBCTableConfig** worksheet, enter column names matching the names of the [table properties \(on page 2932\)](#).
3. Import the tag configuration schema:
 - a. In the **ETLODBCTagConfig** worksheet, select **Developer > Source > XML Maps > Add**.
 - b. Select the `ETLODBCTagConfigSchema` file located in the `Historian ETL ODBC Extract` folder.
 - c. Map each column name with each entry under **Taglist** in the **XML Source** section. To do so, select each column name, and then double-click the corresponding property under **Taglist**. Each property under **Taglist** changes to bold formatting, indicating that it is mapped to the corresponding column.
4. For each tag, enter or modify values in the columns.
5. Import the table configuration schema:
 - a. In the **ETLODBCTableConfig** worksheet, select **Developer > Source > XML Maps > Add**.
 - b. Select the `ETLODBCTableConfigSchema` file located in the `Historian ETL ODBC Extract` folder.
 - c. Map each column name with each entry under **TableList** in the **XML Source** section. To do so, select each column name, and then double-click the corresponding property under **TableList**. Each property under **TableList** changes to bold formatting, indicating that it is mapped to the corresponding column.
6. For each table, enter or modify values in the columns.
7. In both the worksheets, select **Design > Properties**, select the **Validate data against schema for import and export** check box, and then select **OK**.
8. Save the file.
9. Select **Developer > Export**.
10. Create a tag configuration file:

a. Select the **ETLODBCTagConfig** worksheet.

b. Select **Developer > Export**.

The **Export XML** window appears, asking you to choose whether you want to export the tag configuration or the table configuration.



c. Select **Taglist_Map**, and then select **OK**.

d. Provide a file name and location.

The tag configuration file is created with the list of tags whose data you want to extract.

If an error occurs, stating that the data is not valid according to the schema, verify that:

- You have provided values in all the red-colored columns.
- Values in the Name column in the **ETLODBCTagConfig** worksheet are unique.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.


For information, refer to [Tag Properties \(on page 2931\)](#).

11. Create a table configuration file:

a. Select the **ETLODBCTableConfig** worksheet.

b. Select **Developer > Export**.

The **Export XML** window appears, asking you to choose whether you want to export the tag configuration or the table configuration.



- c. Select **TableList_Map**, and then select **OK**.
- d. Provide a file name and location.

The table configuration file is created with the list of tables from which you want to extract data.

If an error occurs, stating that the data is not valid according to the schema, verify that:

- You have provided values in all the red-colored columns.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For information, refer to [Table Properties \(on page 2932\)](#).

[Configure the Historian ETL ODBC Extract settings \(on page 2933\)](#), providing the paths to the two .xml files you have created.

Tag Properties for ODBC Data Extraction

This topic provides a list of tag properties that you can define for each tag that you want to extract from an ODBC data source.

Column Name	Data Type	Description
Name	String	Enter the name of the tag. A value is required and must be unique.
LocalName	String	Enter the local name of the tag. A value is required.
RemoteName	String	Enter the remote name of the tag. This will be used to name the tag after it is imported into Historian. A value is required.
DataType	String	Select the data type of the tag. A value is required.

Column Name	Data Type	Description
TableName	String	Enter the table that contains the tag data you want to import. A value is required and must match the name of a table in the list of table names you provide. Otherwise, an error occurs.

Table Properties for an ODBC Data Source

This topic provides a list of table properties that you can define for each tag that you want to extract from an ODBC data source.

Column Name	Data Type	Description
TableName	String	Enter the name of the table. A value is required and must match the name of a table you specify in the list of tags.
TagNameColumn	String	Enter the name of the tag whose data you want to extract from the table. A value is required and must match the name of a tag you specify in the list of tags.
TimestampColumn	String	Enter the name of the column in the database table from which you want to extract the timestamp values.
ValueColumn	String	Enter the name of the column in the database table from which you want to extract the tag values.
QualityColumn	String	Enter the name of the column in the database table from which you want to extract the quality values.
ihOPCBad	String	Enter the values or range of values whose quality must be considered bad. For example, if a tag value is considered bad when the value is between 0 and 50, enter <code><ihOPCBad>0-50</ihOPCBad></code> . You can also enter words and values separated by commas (for example, <code><ihOPCBad>bad, uneven</ihOPCBad></code>). A value is required.
ihOPCGood	String	Enter the values or range of values whose quality must be considered good. For example, if a tag value is considered good when the value is between 51 and 100, enter <code><ihOPCGood>51-100</ihOPCGood></code> . You can also enter words and val-

Column Name	Data Type	Description
		ues separated by commas (for example, <code><ihOPCGood>good, better, excellent</ihOPCGood></code>). A value is required.
ihOPCUncertain	String	Enter the values or range of values whose quality must be considered uncertain. For example, if a tag value is considered uncertain when the value is 101 or 102, enter <code><ihOPCUncertain>101,102</ihOPCUncertain></code> . You can also enter a range of values.
ihOPCNA	String	Enter the values or range of values whose quality must be considered not applicable. For example, if a tag value is considered not applicable when the value is 103, 104, or 105, enter <code><ihOPCNA>103,104,105</ihOPCNA></code> . You can also enter a range of values.
Condition	String	Enter the condition that you want to use to filter data. For example, if you enter <code>Historian = 1</code> , you can use this condition in a WHERE clause when querying data.

Configure the ODBC Data Extraction Settings

Specify the tags whose data you want to extract from an ODBC data source. You can do so by [creating a configuration file manually \(on page 2924\)](#), [using a template \(on page 2926\)](#), or [using a blank spreadsheet \(on page 2928\)](#).

1. Run the `HistorianETLODBCEExtractConfigTool_x64` file (for Windows 32 bit) or the `HistorianETLODBCEExtractConfigTool_x86` file (for Windows 64 bit) located in the `<installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract` folder.



Tip:

You can also enter ETL ODBC Extract in Windows Run.

The **Historian ETL ODBC Extract Settings** window appears, displaying the **Basic Configuration** section.

2. If the configuration details are stored in a file, select **Import Config** to import the settings, and skip to step 6.

3. Provide values as specified in the following table.

Field	Description	Default Value
Data Source Name (DSN)	<p>Enter the name of the data source from which you want to extract data. It is the saved collection of settings required to connect to the ODBC data source.</p> <p>You can use only a 32-bit or a 64-bit DSN depending on whether your application is 32-bit or 64-bit.</p> <p>If you do not have a DSN, select ODBC DataSource, and create a system DSN.</p>	
Username	Enter the username of the user to connect to ODBC data source. A value is required only if using SQL authentication.	
Password	Enter the password of the user to connect to ODBC data source. A value is required only if using SQL authentication.	
Unit ID	Enter the unit ID of the machine from which you want to transfer data.	
Min # of Files to Compress	Enter the number of files that must be compressed into a single .zip file.	6 (that is, a .zip file is created for every six text files)
Run Interval (Seconds)	Enter the interval, in seconds, at which the Historian ODBC ETL Extract tool will extract data. You must enter a value greater than or equal to 60.	150 (that is, a text file is created for data that is extracted in 150 seconds)
Delay Interval	The duration, in seconds, by which the data retrieval time will be reduced. For example, if data will be retrieved for 10 minutes, and if you enter 60 in this field, data for the last 60 seconds will not be retrieved in that batch; it will be retrieved in the next batch. This will ensure the re-	

Field	Description	Default Value
	trieval of any dynamic records that were updated in that duration.	

4. Select **File Configuration**, and then provide values as specified in the following table.

Field	Description	Default Value
Data Extract Path	Enter the path to the folder in which the text files containing the extracted data must be stored.	<installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\Hist Files
Zip Extract Path	Enter the path to the folder in which the compressed files must be stored.	<installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\Zip Files
Tag Configuration File	Enter the path to the tag configuration file (on page 2924) that you have created.	<installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\OSM_OSMName.xml
Table Configuration File	Enter the path to the table configuration file (on page 2924) that you have created.	<installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\TableConfig.xml
State File	<p>Enter the path to the file that the Historian ODBC ETL Extract tool will create to store the timestamp of the last successful export. This timestamp is used to identify the start time for next iteration of extraction. This ensures that there is no loss of data during extraction.</p> <p>For example, suppose the current time is 11am, and data has been extracted only till 9am. The state file contains the timestamp for 9am.</p>	<installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\State.xml

Field	Description	Default Value
	<p>Therefore, when data extraction is resumed, it is extracted from 9am.</p> <p>The state file is created after you apply the Historian ODBC ETL Extract settings. It is updated each time .zip files are transferred to the destination Historian server or when the Historian ODBC ETL Extract tool is stopped. For a sample state file, refer to Example of a State File (on page 2968).</p>	
Regen File	<p>Enter the path to the regeneration file. You can use this field to extract data.</p> <p>If the Generate Sample Regen File field is set to True, a sample regeneration file will be created after you apply the settings. You can modify this file as needed, and specify the path of the same file in the Regen File field. For a sample regeneration file, refer to Example of a Regeneration File (on page 2966).</p>	<p><installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\Regen.xml</p>
Sample Regen File	<p>Enter the path to the sample regeneration file that will be created if the Generate Sample Regen File field is set to True. You can modify this file as needed.</p>	<p><installation drive>\Program Files\GE Digital\Historian ETL ODBC Extract\Sample_Regen.xml</p>

5. Select **Advanced Configuration**, and then provide values as specified in the following table.

Field	Description	Default Value
Log Level	<p>Select the log level to indicate the amount of information to be logged. The following options are available:</p>	Info

Field	Description	Default Value
	<ul style="list-style-type: none"> ◦ Info ◦ Error ◦ Debug 	
Extract Type	Specifies whether you want to extract only the current data or historical data or both. However, we recommend that you extract only current data.	Current Data
Generate Sample Regen File	Select True if you want to generate the sample regeneration file. You can then modify this file as needed.	False
Query Timeout	The time, in seconds, after which a query to the database times out.	30
Save Limit	Enter the number of files to be exported after which the <code>State.xml</code> file must be updated.	20
Catch Up Interval (Seconds)	Enter the catch up interval, in seconds, used to size files when catching up to the current time.	10
Catch Up Time Limit (Hours)	Enter the maximum time, in hours, to go back when catching up after a restart. You can use this field to extract data.	168

6. Select **Save**.

The changes to the settings are applied and saved in the `HistorianETLODBCExtract.exe.config` file.

[Start the data extraction \(on page 2947\).](#)

Start the ODBC Data Extraction

[Configure the Historian ETL ODBC Extract settings \(on page 2933\).](#)

1. Run the `Historian ETL ODBC Extract Configuration` file located in the `Historian ETL ODBC Extract` folder.
The **Historian ETL ODBC Extract Configuration** window appears.
2. Select **Start Service**.

Data extraction from the ODBC data source begins.



Tip:

If the tool does not start as expected, access the logs using Windows Event Viewer.

Transfer data using [BITS \(on page 2957\)](#), [FTP \(on page 2959\)](#), or any other file-sharing application.

About Extracting Data from Proficy Historian

The Historian ETL Extract tool extracts data as follows:

1. Extracts data related to tags into text files, which are named in the following format:

YYYYDDMMHHRR_<onsite Historian computer name>.txt. These files are stored in the following folder: <Historian ETL installation location>/Historian ETL Extract/HistFiles.



Note:

Data related to alarms and events is stored in .lax files. You can choose not to extract data related to alarms and events.

2. After a specified number of files are extracted (by default, 6), the files are compressed into a .zip file, which is named in the following format: YYYYDDMMHHRR_<onsite Historian computer name>.zip. These files are stored in the following folder: <Historian ETL installation location>/Historian ETL Extract/ZipFiles.
3. Deletes the text files in the <Historian ETL installation location>/Historian ETL Extract/HistFiles folder after they are compressed.

Specify Tags for Proficy Historian Data Extraction Manually

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags manually by creating a configuration file. Alternatively, you can specify the tags using a [template spreadsheet \(on page 2939\)](#) or a [blank spreadsheet \(on page 2940\)](#).

Create an .xml file to include the [tag properties \(on page 2942\)](#) for all the tags whose data you want to extract.

Tag properties for a tag named Pressure used in Proficy Historian:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<Taglist>
  <Tag Name="Pressure">
    <LocalName>ValvePressure</LocalName>
    <RemoteName>ValvePressure</RemoteName>
    <Compression>1</Compression>
    <DeadbandRange>2.5</DeadbandRange>
    <DeadbandTimeout>2</DeadbandTimeout>
    <RequireRescale>1</RequireRescale>
    <HiEng>10</HiEng>
    <LowEng>8</LowEng>
    <HiScale>10</HiScale>
    <LowScale>8</LowScale>
  </Tag>
</Taglist>
```

[Configure the Historian ETL Extract settings \(on page 2942\)](#).

Specify Tags for Proficiency Historian Data Extraction Using a Template

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags using a template spreadsheet, which is provided with the Historian ETL package. Alternatively, you can specify the tags using a [new spreadsheet \(on page 2940\)](#) or by [creating a configuration file manually \(on page 2938\)](#).

1. Access the ProficiencyHistTagConfigGenerateExcel.xlsx file located in the Historian ETL Extract folder.
2. **Optional:** If you want to modify an existing tag configuration file, you can import the data from that .xml file by selecting **Developer > Import**.



Tip:

If the **Developer** tab is not available, right-click the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

Data from the .xml file is imported into the spreadsheet.



Note:

If an error occurs, stating that the data is not valid according to the schema, verify that:



- You have provided values in all the red-colored columns.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to the [Tag Properties \(on page 2942\)](#) topic.

3. For each tag, enter or modify values in the columns for the [tag properties \(on page 2942\)](#). A value is required in the red-colored columns.
4. Save the file.
5. Select **Developer > Export**.



Tip:

If the **Developer** tab is not available, right-select the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

6. Enter a name and location for the .xml file.

The tag configuration file is created with the list of tags and their properties to be extracted.



Note:

If an error occurs, stating that the data is not valid according to the schema, verify that:

- You have provided values in all the red-colored columns.
- Values in the Name column are unique.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to the [Tag Properties \(on page 2942\)](#) topic.

[Configure the Historian ETL Extract settings \(on page 2942\)](#).

Specify Tags for Proficiency Historian Data Extraction Using a Blank Spreadsheet

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags using a new spreadsheet. Alternatively, you can specify the tags [using a template spreadsheet \(on page 2939\)](#) or by [creating a configuration file manually \(on page 2938\)](#).

1. Create a Microsoft Excel file.
2. Enter column names matching the names of the [tag properties \(on page 2942\)](#).
3. **Optional:** If you want to modify an existing tag configuration file, you can import the data from that .xml file by selecting **Developer > Import**.

**Tip:**

If the **Developer** tab is not available, right-select the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

**Note:**

If a message appears, stating that the .xml file is not linked to schema, ignore the message.

4. Select **Developer > Source > XML Maps > Add**.
5. Select the `ProficiencyHistTagConfigSchema` file located in the `Historian ETL Extract` folder.
6. Map each column name with each entry under **Taglist** in the **XML Source** section. To do so, select each column name, and then double-click the corresponding property under **Taglist**. Each property under **Taglist** changes to bold formatting, indicating that it is mapped to the corresponding column.
7. For each tag, enter or modify values in the columns.
8. Select **Design > Properties**, select the **Validate data against schema for import and export** check box, and then select **OK**.
9. Save the file.
10. Select **Developer > Export**.
11. Enter a name and location for the .xml file.

The tag configuration file is created with the list of tags and their properties to be extracted.

**Note:**

If an error occurs, stating that the data is not valid according to the schema, verify that:

- You have provided values in all the red-colored columns.
- Values in the Name column are unique.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to the [Tag Properties \(on page 2942\)](#) topic.

[Configure the Historian ETL Extract settings \(on page 2942\)](#).

Tag Properties for Proficy Historian Data Extraction

This topic provides a list of tag properties that you can define for each tag that you want to extract from Proficy Historian.

Column Name	Data Type	Description
Name	String	Enter the name of the tag. A value is required and must be unique.
LocalName	String	Enter the local name of the tag. A value is required.
RemoteName	String	Enter the remote name of the tag. This will be used to name the tag after it is imported into Historian. A value is required.
Compression	Boolean	<ul style="list-style-type: none"> • Enter 1 if you want to enable collector compression. • Enter 0 if you do not want to enable collector compression.
DeadbandRange	Numeric	Enter the collector deadband range (only absolute values, not in percentage).
DeadbandTimeout	Numeric	Enter the collector compression timeout for the tag.
RequireRescale	Boolean	<ul style="list-style-type: none"> • Enter 1 if you want to enable scaling, which converts an input data point to an engineering units value. • Enter 0 if you do not want to enable scaling.
HiEng	Numeric	Enter the upper limit in engineering units for the tag.
LowEng	Numeric	Enter the lower limit in engineering units for the tag.
HiScale	Numeric	Enter the upper limit for the tag value if scaling is enabled.
LowScale	Numeric	Enter the lower limit for the tag value if scaling is enabled.

Configure the Proficy Historian Data Extraction Settings

Specify the tags whose data you want to extract from Proficy Historian. You can do so by [creating a configuration file manually \(on page 2938\)](#), [using a template \(on page 2939\)](#), or [using a blank spreadsheet \(on page 2940\)](#).

This topic describes how to configure the Historian ETL Extract tool to modify the default folders to store the extracted data, to specify whether data related to alarms and events must be extracted, and so on.

**Note:**

These settings are saved in the `HistorianETLExtract.exe.config` file.

1. Run the `Historian ETL Extract Configuration` file located in the `Historian ETL Extract` folder.

**Tip:**

You can also enter ETL Historian Extract in Windows Run.

The **Historian ETL Extract Configuration** window appears, displaying the **Basic Configuration** section.

2. If the configuration details are stored in a file, select **Import Config** to import the settings. Otherwise, skip to the next step.
3. Provide values as specified in the following table.

Field	Description	Default Value
Historian Server	Enter the host name or IP address of the onsite Historian machine. If you leave it blank, the local host name is considered.	
Historian User	Enter the ID of the user to connect to the Historian server on the onsite Historian machine. A value is required only if security is enabled for the Historian server.	
Historian Password	Enter the password of the user to connect to the Historian server on the onsite Historian machine. A value is required only if security is enabled for the Historian server.	
Unit ID	Enter the unit ID of the machine from which you want to transfer data.	OSMName
Run Interval	Enter the interval, in seconds, at which the Historian ETL Extract tool will extract data. You must enter a value greater than or equal to 60.	300 (that is, a text file is created for data that is extracted in 300 seconds)

Field	Description	Default Value
Min # of Files to Compress	Enter the number of files that must be compressed into a single .zip file.	6 (that is, a .zip file is created for every six text files)
Alarms & Events	Select False if you do not want to extract data related to alarms and events.	True

4. Select **Files**, and then provide values as specified in the following table.

Field	Description	Default Value
Historian Export Path	Enter the path to the folder in which the text files containing the extracted data must be stored.	<Installation folder of Historian ETL>/Historian ETL Extract/HistFiles
Tag Configuration File	Enter the path to the tag configuration file that you have created.	<Installation folder of Historian ETL>/Historian ETL Extract/OSM_OSMName.xml
Zip Export Path	Enter the path to the folder in which the compressed files must be stored.	<Installation folder of Historian ETL>/Historian ETL Extract/ZipFiles
State File	<p>Enter the path to the file that the Historian ETL Extract tool will create to store the timestamp of the last successful export. This timestamp is used to identify the start time for next iteration of extraction. This ensures that there is no loss of data during extraction.</p> <p>For example, suppose the current time is 11am, and data has been extracted only till 9am. The state file contains the timestamp for 9am. Therefore, when data extraction is resumed, it is extracted from 9am.</p>	<Installation folder of Historian ETL>/Historian ETL Extract/State.xml

Field	Description	Default Value
	The state file is created after you apply the Historian ETL Extract settings. It is updated each time .zip files are transferred to the destination Historian server or when the Historian ETL Extract tool is stopped. For a sample state file, refer to Example of a State File (on page 2968) .	
Regen File	<p>Enter the path to the regeneration file. You can use this field to extract historical data (on page 2946).</p> <p>If the Generate Sample Regen File field is set to True, a sample regeneration file will be created after you apply the settings. You can modify this file as needed, and specify the path of the same file in the Regen File field. For a sample regeneration file, refer to Example of a Regeneration File (on page 2966).</p>	<installation folder of Historian ETL>\Regen.xml

5. Select **Advanced Configuration**, and then provide values as specified in the following table.

Field	Description	Default Value
Log Level	<p>Select the log level to indicate the amount of information to be logged. The following options are available:</p> <ul style="list-style-type: none"> ◦ Info ◦ Error ◦ Debug 	Info
Catch Up Interval	Enter the catch up interval, in seconds, used to size files when catching up to the current time.	10

Field	Description	Default Value
Save Limit	Enter the number of files to be exported after which the <code>State.xml</code> file must be updated.	20
Catch Up Time Limit	Enter the maximum time, in hours, to go back when catching up after a restart. You can use this field to extract historical data (on page 2946) .	168
Delay Interval	The duration, in seconds, by which the data retrieval time will be reduced. For example, if data will be retrieved for 10 minutes, and if you enter 60 in this field, data for the last 60 seconds will not be retrieved in that batch; it will be retrieved in the next batch. This will ensure the retrieval of any dynamic records that were updated in that duration.	60
Sample Regen File	Enter the path to the sample regeneration file that will be created if the Generate Sample Regen File field is set to True . You can modify this file as needed.	<installation folder of Historian ETL>\Sample_Regen.xml
Generate Sample Regen File	Select True if you want to generate the sample regeneration file. You can then modify this file as needed.	False

6. Select **Save**.

The changes to the settings are applied and saved in the `HistorianETLExtract.exe.config` file.

[Start the data extraction \(on page 2947\)](#).

Extract Historical Data from Proficy Historian

By default, the ETL tools extract current data, starting from the time you have configured the tags for data extraction. This topic describes how to extract historical data using the ETL tools.

1. Create a regeneration file, specifying the start time, end time, and interval for which you want to capture the historical data. For a sample regeneration file, refer to [Example of a Regeneration File \(on page 2966\)](#).
2. Run the `Historian ETL Extract Configuration` file located in the `Historian ETL Extract` folder.

**Tip:**

You can also enter ETL Historian Extract in the Windows Start menu.

The **Historian ETL Extract Configuration** window appears, displaying the **Basic Configuration** section.

3. Select **Advanced Configuration**, and then provide values as specified in the following table.

Field	Description	Default Value
Regen File	Enter the path to the regeneration file that you have created.	<installation drive>\Program Files\GE Digital\Historian ETL Extract\Regen.xml
Catch Up Time Limit	Enter the duration, in hours, for which you want to extract historical data. For example, if you want to extract data for the past one day, enter 24.	168
Temp Regen File	Enter the path to the temporary regeneration file.	<installation drive>\Program Files\GE Digital\Historian ETL Extract\Temp_Regen.xml
Generate Temp Regen File	Select True .	False

4. As needed, [provide values in the remaining fields \(on page 2942\)](#)

[Start the data extraction \(on page 2947\)](#).

Start the Proficy Historian Data Extraction

[Configure the Historian ETL Extract settings \(on page 2942\)](#).

1. Run the Historian ETL Extract Configuration file located in the Historian ETL Extract folder.

The **Historian ETL Extract Configuration** window appears.

2. Select **Start Service**.

Data extraction from the Proficy Historian server begins.



Tip:

If the tool does not start as expected, access the logs using Windows Event Viewer.

Transfer data using [BITS \(on page 2957\)](#), [FTP \(on page 2959\)](#), or any other file-sharing application.

Extracting Data from PI Historian

The Historian ETL PI Extract tool extracts data as follows:

1. Extracts data related to tags into text files, which are named in the following format: YYYYDDMMHRR_<onsite Historian computer name>.txt. These files are stored in the following folder: <Historian ETL installation location>/Historian ETL PI Extract/HistFiles.
2. After a specified number of files are extracted (by default, 6), the files are compressed into a .zip file, which is named in the following format: YYYYDDMMHRR_<onsite Historian computer name>.zip. These files are stored in the following folder: <Historian ETL installation location>/Historian ETL PI Extract/ZipFiles.

Specify Tags for PI Historian Data Extraction Manually

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags manually by creating a configuration file. Alternatively, you can specify the tags using a [template spreadsheet \(on page 2949\)](#) or a [blank spreadsheet \(on page 2950\)](#).

Create an .xml file to include the [tag properties \(on page 2951\)](#) for all the tags whose data you want to extract.

Tag properties for a tag named Pressure used in an ODBC data source:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<Taglist>
  <Tag Name="Pressure">
    <LocalName>ValvePressure</LocalName>
```

```

    <RemoteName>ValvePressure</RemoteName>

  </Tag>

</Taglist>

```

Configure the Historian ETL PI Extract settings ([on page 2952](#)).

Specify Tags for PI Historian Data Extraction Using a Template

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags using a template spreadsheet, which is provided with the Historian ETL package. Alternatively, you can specify the tags using a [new spreadsheet \(on page 2950\)](#) or by [creating a configuration file manually \(on page 2948\)](#).

1. Access the `PIHistTagConfigGenerateExcel.xlsx` file located in the `Historian PI ETL Extract` folder.
2. **Optional:** If you want to modify an existing tag configuration file, you can import the data from that `.xml` file by selecting **Developer > Import**.



Tip:

If the **Developer** tab is not available, right-click the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

Data from the `.xml` file is imported into the spreadsheet.



Note:

If an error occurs, stating that the data is not valid according to the schema, verify that:

- You have provided values in all the red-colored columns.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to the [Tag Properties \(on page 2951\)](#) topic.

3. For each tag, enter or modify values in the columns for the [tag properties \(on page 2951\)](#). A value is required in the red-colored columns.
4. Save the file.
5. Select **Developer > Export**.



Tip:

If the **Developer** tab is not available, right-select the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

6. Enter a name and location for the .xml file.

The tag configuration file is created with the list of tags and their properties to be extracted.



Note:

If an error occurs, stating that the data is not valid according to the schema, verify that:

- You have provided values in all the red-colored columns.
- Values in the Name column are unique.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to the [Tag Properties \(on page 2951\)](#) topic.

[Configure the Historian ETL PI Extract settings \(on page 2952\).](#)

Specify Tags for PI Historian Data Extraction Using a Blank Spreadsheet

Before you extract data, you must specify the tags whose data you want to extract.

This topic describes how to specify the tags using a new spreadsheet. Alternatively, you can specify the tags [using a template spreadsheet \(on page 2949\)](#) or by [creating a configuration file manually \(on page 2948\)](#).

1. Create a Microsoft Excel file.
2. Enter column names matching the names of the [tag properties \(on page 2951\)](#).
3. **Optional:** If you want to modify an existing tag configuration file, you can import the data from that .xml file by selecting **Developer > Import**.



Tip:

If the **Developer** tab is not available, right-select the menu bar of the spreadsheet, select **Customize the Ribbon**, and then select the **Developer** check box.

**Note:**

If a message appears, stating that the .xml file is not linked to schema, ignore the message.

4. Select **Developer > Source > XML Maps > Add**.
5. Select the `PIHistTagConfigSchema` file located in the `Historian ETL PI Extract` folder.
6. Map each column name with each entry under **Taglist** in the **XML Source** section. To do so, select each column name, and then double-click the corresponding property under **Taglist**.
Each property under **Taglist** changes to bold formatting, indicating that it is mapped to the corresponding column.
7. For each tag, enter or modify values in the columns.
8. Select **Design > Properties**, select the **Validate data against schema for import and export** check box, and then select **OK**.
9. Save the file.
10. Select **Developer > Export**.
11. Enter a name and location for the .xml file.

The tag configuration file is created with the list of tags and their properties to be extracted.

**Note:**

If an error occurs, stating that the data is not valid according to the schema, verify that:

- You have provided values in all the red-colored columns.
- Values in the Name column are unique.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to the [Tag Properties \(on page 2951\)](#) topic.

[Configure the Historian ETL PI Extract settings \(on page 2952\)](#).

Tag Properties for PI Historian Data Extraction

This topic provides a list of tag properties that you can define for each tag that you want to extract from PI Historian.

Column Name	Data Type	Description
Name	String	Enter the name of the tag. A value is required and must be unique.
LocalName	String	Enter the local name of the tag. A value is required.
RemoteName	String	Enter the remote name of the tag. This will be used to name the tag after it is imported into Historian. A value is required.

Configure the PI Historian Data Extraction Settings

Specify the tags whose data you want to extract from PI Historian. You can do so by creating a configuration file manually, using a template, or using a blank spreadsheet.

This topic describes how to configure the Historian ETL PI Extract tool to modify the default folders to store the extracted data.



Note:

These settings are saved in the `PIHistorianETLExtract.exe.config` file.

1. Run the `Historian ETL PI Extract Configuration` file located in the `Historian ETL PI Extract` folder.



Tip:

You can also enter ETL PI Extract in Windows Run.

The **Historian ETL PI Extract Configuration** window appears, displaying the **Basic Configuration** section.

2. If the configuration details are stored in a file, select **Import Config** to import the settings. Otherwise, skip to the next step.
3. Provide values as specified in the following table.

Field	Description	Default Value
Historian Server	Enter the host name or IP address of the PI Server machine.	

Field	Description	Default Value
Historian User	Enter the ID of the user to connect to the PI Server machine. A value is required only if security is enabled for the Historian server.	
Historian Password	Enter the password of the user to connect to the PI Server machine. A value is required only if security is enabled for the Historian server.	
Unit ID	Enter the unit ID of the machine from which you want to transfer data.	OSMName
Run Interval	Enter the interval, in seconds, at which the Historian ETL PI Extract tool will extract data. You must enter a value greater than or equal to 60.	150 (that is, a text file is created for data that is extracted in 150 seconds)
Min # of Files to Compress	Enter the number of files that must be compressed into a single .zip file.	6 (that is, a .zip file is created for every six text files)

4. Select **Files**, and then provide values as specified in the following table.

Field	Description	Default Value
Historian Export Path	Enter the path to the folder in which the text files containing the extracted data must be stored.	<Installation folder of Historian ETL>/Historian ETL PI Extract/HistFiles
Tag Configuration File	Enter the path to the tag configuration file that you have created.	<Installation folder of Historian ETL>/Historian ETL PI Extract/OSM_OSM-Name.xml
Zip Export Path	Enter the path to the folder in which the compressed files must be stored.	<Installation folder of Historian ETL>/Historian ETL PI Extract/ZipFiles
State File	Enter the path to the file that the Historian ETL PI Extract tool will create to store the timestamp of the last successful export. This timestamp is	<Installation folder of Historian ETL>/Historian ETL PI Extract/State.xml

Field	Description	Default Value
	<p>used to identify the start time for next iteration of extraction. This ensures that there is no loss of data during extraction.</p> <p>For example, suppose the current time is 11 am, and data has been extracted only till 9am. The state file contains the timestamp for 9am. Therefore, when data extraction is resumed, it is extracted from 9am.</p> <p>The state file is created after you apply the settings. It is updated each time .zip files are transferred to the destination Historian server or when the Historian PI ETL Extract tool is stopped. For a sample state file, refer to Example of a State File (on page 2968).</p>	

5. Select **Advanced Configuration**, and then provide values as specified in the following table.

Field	Description	Default Value
Log Level	<p>Select the log level to indicate the amount of information to be logged. The following options are available:</p> <ul style="list-style-type: none"> ◦ Info ◦ Error ◦ Debug 	Info
Catch Up Interval	Enter the catch up interval, in seconds, used to size files when catching up to the current time.	10
Regen File	Enter the path to the regeneration file. You can use this field to extract historical data (on page 2946) .	<installation folder of Historian ETL>\Regen.xml

Field	Description	Default Value
	If the Generate Sample Regen File field is set to True , a sample regeneration file will be created after you apply the settings. You can modify this file as needed, and specify the path of the same file in the Regen File field. For a sample regeneration file, refer to Example of a Regeneration File (on page 2966) .	
Save Limit	Enter the number of files to be exported after which the <code>State.xml</code> file must be updated.	20
Catch Up Time Limit	Enter the maximum time, in hours, to go back when catching up after a restart. You can use this field to extract historical data (on page 2946) .	168
Delay Interval	The duration, in seconds, by which the data retrieval time will be reduced. For example, if data will be retrieved for 10 minutes, and if you enter 60 in this field, data for the last 60 seconds will not be retrieved in that batch; it will be retrieved in the next batch. This will ensure the retrieval of any dynamic records that were updated in that duration.	60
Sample Regen File	Enter the path to the sample regeneration file that will be created if the Generate Sample Regen File field is set to True . You can modify this file as needed.	<installation folder of Historian ETL>\Sample_Regen.xml
Generate Sample Regen File	Select True if you want to generate the sample regeneration file. You can then modify this file as needed.	False

6. Select **Save**.

The changes to the settings are applied and saved in the `PIHistorianETLExtract.exe.config` file.

[Start the data extraction \(on page 2947\)](#).

Extract Historical Data from PI Historian

By default, the ETL tools extract current data, starting from the time you have configured the tags for data extraction. This topic describes how to extract historical data using the ETL tools.

1. Create a regeneration file, specifying the start time, end time, and interval for which you want to capture the historical data. For a sample regeneration file, refer to [Example of a Regeneration File \(on page 2966\)](#).
2. Run the `Historian ETL PI Extract Configuration` file located in the `Historian ETL PI Extract` folder.



Tip:

You can also enter ETL PI Extract in the Windows Start menu.

The **Historian ETL PI Extract Configuration** window appears, displaying the **Basic Configuration** section.

3. Select **Advanced Configuration**, and then provide values as specified in the following table.

Field	Description	Default Value
Regen File	Enter the path to the regeneration file that you have created.	<code><installation drive>\Program Files\GE Digital\Historian ETL Extract\Regen.xml</code>
Catch Up Time Limit	Enter the duration, in hours, for which you want to extract historical data. For example, if you want to extract data for the past one day, enter 24.	168
Temp Regen File	Enter the path to the temporary regeneration file.	<code><installation drive>\Program Files\GE Digital\Historian ETL PI Extract\Temp_Regen.xml</code>
Generate Temp Regen File	Select True .	False

4. As needed, [provide values in the remaining fields \(on page 2952\)](#).

[Start the data extraction \(on page 2957\).](#)

Start the PI Historian Data Extraction

[Configure the Historian ETL PI Extract settings \(on page 2952\).](#)

1. Run the `Historian ETL PI Extract Configuration` file located in the `Historian ETL PI Extract` folder.

The **Historian ETL PI Extract Configuration** window appears.

2. Select **Start Service**.

Data extraction from PI Server begins.

**Tip:**

If the tool does not start as expected, access the logs using Windows Event Viewer.

About Transferring Data Using Background Intelligent Transfer Service (BITS)

After you extract data, you must transfer it to the destination machine. To do so, you can use BITS, FTP, or any other file-sharing application.

To transfer data using BITS, perform the following steps:

1. Install the BITS IIS server extension.
2. [Configure the BITS settings \(on page 2957\).](#)
3. [Transfer data to the destination machine \(on page 2958\).](#)

Configure BITS

Install the BITS IIS server extension.

1. Using IIS Management Console, navigate to the default website node, select **Add Virtual Directory**, and create a virtual directory named `MD_BITS`.
2. In the `MD_BITS` folder, create a folder named `OSMUploads`.
3. Enable the BITS IIS server extension:
 - a. Navigate to the virtual directory in IIS Manager.
 - b. From the list of features in the virtual directory, double-click **BITS Uploads**.
 - c. Select the **Allow clients to upload files** check box, and then select **Apply**.
4. Change the port number of the default website in IIS. By default, the port number is 80.

- a. In IIS Manager, in the **Connections** section, under the computer name > **Sites**, select **Default Web Site**.
- b. In the **Actions** pane, under **Edit Site**, select **Bindings**.
- c. In the **Site Bindings** window, select **http > Edit**.
- d. In the **Edit Site Bindings** window, in the **Port** field, enter the new port number (for example, 6150), and then select **OK**.
- e. In the **Site Bindings** window, select **Close**.
- f. In the **Actions** section, under **Manage Web Site**, select **Stop**, and then select **Start**.

[Verify the data transfer settings \(on page 2958\)](#).

Verify the Data Transfer Settings

This topic provides a list of tasks that you can perform to verify that the data transfer settings are correct.

- From your onsite Historian machine, using Internet Explorer, verify that you can access a web page created on the destination machine.
- Verify that the Historian ETL Load tool running on the destination machine is configured to watch the virtual folder in IIS for the incoming .zip files.

Transfer Data using BITS

[Configure BITS \(on page 2957\)](#).

You can transfer data using BITS by performing one of the following steps:

1. If you want to use the `OSM_LBW_Transfer.vbs` file to transfer files, perform the following steps:
 - a. Verify that the `OSM_LBW_Transfer.vbs` file is configured to watch the folder in the destination machine in which the .zip files will be placed.
 - b. Run the `OSM_LBW_Transfer.vbs` script by running the `OSM_LBW_Transfer.cmd` file. The script transfers files in the `<Historian ETL installation location>/Historian ETL Extract/ZipFiles` folder to the destination machine.
2. If you want to use the `OSMbitsDownload.vbs` file to download files, perform the following steps:
 - a. Access the `OSMbitsDownload.vbs` file, and verify that the path to the files and folders specified in the file is correct.
 - b. Run the `OSMbitsDownload.vbs` script by running the following command: `cscript OSMbitsDownload.vbs`.

The script uses the `DownloadFilesToOSM.txt` file to fetch the names of the files that must be transferred.

**Important:**

- Ensure that the `DownloadFilesToOSM.txt` file exists in the same location as the `OSMbitsDownload.vbs` file.
- In the `DownloadFilesToOSM.txt` file, enter the file names that you want to download using the `OSMbitsDownload.vbs` script. If you want to transfer all zip files, enter `*.zip`.

**Tip:**

To access the jobs created by BITS while transferring data, access the `BITSADMIN/LIST/ALLUSERS` folder. If the tool does not start as expected, access the logs using Windows Event Viewer.

Load the data into the destination Historian server ([on page 2961](#)).

About Transferring Data Using File Transfer Protocol (FTP)

After you extract data, you must transfer it to the destination Historian server. To do so, you can use BITS, FTP, or any other file-sharing application.

**Note:**

The minimum bandwidth required to transfer data using FTP is 2 KBps.

To transfer data using FTP, perform the following steps:

1. Install an FTP server on the destination Historian server.
2. [Configure the FTP settings \(on page 2959\)](#).
3. [Transfer data to the destination Historian server \(on page 2960\)](#).

Configure FTP

Install FTP on the destination Historian server.

1. Access the `FTPFileTransfer` file located in the `<Installation folder of Historian ETL>/Historian ETL Transform` folder.
The **FTP File Transfer Tool** window appears.
2. If the FTP configuration details are saved in a file, select **File > Load**, and then select the configuration file that contains the details. Otherwise, skip to the next step.
3. Provide values as specified in the following table.



Tip:

You can select **File > New** to create a new instance of the settings.

Field	Description	Default Value
FTP Server Address	Enter the address of the FTP server.	ftp://127.0.0.1/ftpserver
FTP UserID	Enter the user ID to log in to the FTP server.	Blank
FTP Password	Enter the password to log in to the FTP server.	Blank
Directory to Monitor	Provide the folder from which files must be transferred.	C:\
File Mask	Enter the file mask for the FTP server.	*.zip

4. **Optional:** Select **Test Connection** to test the FTP server connection.
5. Select **File > Save** to save the configuration details, which you can reuse.
6. Select **File > Detail Log** if you want a detailed logging, which will help you in troubleshooting.

The FTP server settings are configured.

[Transfer data using FTP \(on page 2960\).](#)

Transfer Data Using FTP

[Configure FTP \(on page 2959\).](#)

1. Access the `FTPFileTransfer` file located in the `<Installation folder of Historian ETL>/Historian ETL Transform` folder.
The **FTP File Transfer Tool** window appears.

2. Select **Start**.

Data is transferred from the `ZipFiles` folder to the machine on which the destination Historian is installed.

[Load the data into the destination Historian server \(on page 2961\).](#)

About Loading Data

After the data is transferred to the machine on which the destination Historian is installed, you must load it into the destination Historian server using the Historian ETL Load tool. This tool loads data as follows:

1. Extracts the `.zip` files in the `<Historian ETL installation location>/Historian ETL Load/ZipImportFiles` folder and stores the text files in the `<Historian ETL installation location>/Historian ETL Load/ImportFiles` folder in the destination Historian server.
2. Loads the data into the destination Historian server.
3. Deletes the `.zip` files in the `<Historian ETL installation location>/Historian ETL Load/ZipImportFiles` folder, and imports the text files to the destination Historian server.
4. Deletes the text files in the `<Historian ETL installation location>/Historian ETL Load/ImportFiles` folder after importing them to the destination Historian server.

Configure the Historian ETL Load tool

This topic describes how to configure the Historian ETL Load service to modify the default folders to store the extracted data, to specify whether data related to alarms and events must be transferred, and so on.



Note:

These settings are saved in the `HistorianETLLoad.exe.config` file.

1. Run the `Historian ETL Load Configuration` file located in the `Historian ETL Load` folder.



Tip:

You can also enter `ETL Historian Load` in Windows Run.

The **Historian ETL Load Configuration** window appears, displaying the **Basic Configuration** section.

2. If the configuration details are stored in a file, select **Import Config** to import the settings. Otherwise, skip to the next step.

3. Provide values as specified in the following table.

Field	Description	Default Value
Historian Server	Enter the host name or IP address of the destination Historian server. If you leave this field blank, the local host name is considered.	Blank
Historian User	Enter the ID of the user to connect to the destination Historian server. A value is required only if security is enabled for the destination Historian server.	Blank
Historian Password	Enter the password of the user to connect to the destination Historian server. A value is required only if security is enabled for the destination Historian server.	Blank
IH Status Tagname	Enter the name of the tag that is used to check the state of the destination Historian server. This tag must exist in Historian.	IHStatusTag
Alarms & Events	Select False if you do not want to load data related to alarms and events.	True
Add Tag Automatically	Select True to create a tag automatically in the destination Proficy Historian server if the tag name that you entered does not exist in the server.	False

4. Select **Files**, and then provide values as specified in the following table.

Field	Description	Default Value
Historian File Path	Enter the path to the folder in which the text files containing the extracted data are stored.	<Installation folder of Historian ETL>/Historian ETL Load/ImportFiles
Zip File Path	Enter the path to the folder in which the compressed files are available.	<Installation folder of Historian ETL>/Historian ETL Load/ZipImportFiles
Error File Path	Enter the path to the folder in which file that could not be loaded or deleted must be stored.	<Installation folder of Historian ETL>/Historian ETL Load/ErrorFiles
Error File Life Time (days)	Enter the amount of time, in days, error files must be stored before deletion.	3.5

5. Select **Advanced Configuration**, and then provide values as specified in the following table.

Field	Description	Default Value
Log Level	Select the log level to indicate the amount of information to be logged. The following options are available: <ul style="list-style-type: none"> ◦ INFO ◦ ERROR ◦ DEBUG 	INFO
Write Batch Size	Enter the number of records to write to the Historian server at one time. <div style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px; margin-top: 10px;"> <p> Tip: A large batch size can produce faster tag value writes, but can lead to poor performance</p> </div>	1000

Field	Description	Default Value
	 if multiple collectors share the same Historian server. A 1000 to 2000 batch size is ideal for a shared Historian server.	
Wait Interval (seconds)	Enter the amount to time, in seconds, to wait to check for new files.	90
Wait For Reply	Select False if you do not want the Historian ETL Load tool to wait for the acknowledgement from Historian that files are transferred.	True
Error On Replace	Select True if you want an error to be logged if duplicate data is transferred.	False
Max Retries	Enter the maximum number of times the Historian ETL Load tool must try to resend data in case of an error or failure.	2
Retry Timeout (seconds)	Enter the amount of time, in seconds, to wait before trying to resend data.	5

6. Select **Save**.

The changes to the settings are applied and saved in the `HistorianETLLoad.exe.config` file.

[Load data into the destination Historian server \(on page 2965\).](#)

Load Data into the Destination Historian Server

1. [Configure the ETL Load tool \(on page 2961\)](#).
2. Verify that the Historian ETL Load tool running on the destination Historian server is configured to watch the IIS Virtual folder for the incoming .zip files.

1. Run the `Historian ETL Load Configuration` file located in the `Historian ETL Load` folder.

The **Historian ETL Load Configuration** window appears.

2. Select **Start Service**.



Tip:

If the tool does not start as expected, access the logs using Windows Event Viewer.

The data is loaded in the destination Historian server.

Data File Format

This topic provides the format of the content in a text file that contains tag data extracted by the Historian ETL Extract tool. Each line in the text file contains the following parameters, separated by commas:

Parameter	Description	Valid Values
Time	<p>The time at which the data is captured. It is displayed in the following format: <epoch format>:<nanoseconds, human-readable></p> <p>For example, if the value is 1601890328:76000000, then:</p> <ul style="list-style-type: none"> • 1601890328 indicates the time in the epoch format. • 76000000 indicates the time in nanoseconds, human-readable. <p>The value after the colon is greater than 0 only if the time</p>	N/A

Parameter	Description	Valid Values
	resolution of the tag is milliseconds or microseconds.	
Tag name	The name of the tag for which the data is captured.	Any tag that exists in the destination Historian server <div data-bbox="1024 485 1419 846" style="border: 1px solid #0070C0; border-radius: 10px; padding: 10px;">  Note: If the AddTagAutomatically parameter is set to True, when you add a tag that does not exist in the Historian server, it will be created. </div>
Data value	The value of the data that is captured.	N/A
Data type	The data type for the value that is captured.	<ul style="list-style-type: none"> • short • int • float • Double • Single Byte String
Quality	The quality of the data that is captured.	<ul style="list-style-type: none"> • GOOD • BAD

**Note:**

- The BLOB data type is not supported.
- Comments are not captured.
- Data quality other than GOOD and BAD is not supported.

Example of a Regeneration File

The following lines of code represent the content of a regeneration file, which provides the start time, end time, and interval to export data. After all the requests are processed, the regeneration file is deleted.

**Note:**

The regeneration file has three sections for setting the start time, end time, and interval. These multiple sections act as a backup. That is, if the values provided in the first section are not valid (for example, the start time is later than the end time, interval has a negative value), the values from the next section are considered.

```
<?xml version="1.0"?>
<SOAP-ENV:Envelope xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:xsd="http://www.w3.org/2001/XMLSchema"
  xmlns:SOAP-ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
  xmlns:clr="http://schemas.microsoft.com/soap/encoding/clr/1.0"
  SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/">
<SOAP-ENV:Body>
<a1:ArrayList id="ref-1" xmlns:al="http://schemas.microsoft.com/clr/ns/System.Collections">
  <_items href="#ref-2"/>
  <_size>3</_size>
  <_version>3</_version>
</a1:ArrayList>
<SOAP-ENC:Array id="ref-2" SOAP-ENC:arrayType="xsd:anyType[4]">
  <item href="#ref-3"/>
  <item href="#ref-4"/>
  <item href="#ref-5"/>
</SOAP-ENC:Array>
<a3:RegenRequest id="ref-3"
  xmlns:a3="http://schemas.microsoft.com/clr/nsassem/ETLExtract/HistorianETLExtract%2C%20Version%3D1.9.0.0%2C%20Culture%3Dneutral%2C%20PublicKeyToken%3Dnull">
  <startTime>2020-07-02T09:39:37.3384336+05:30</startTime>
  <endTime>2020-07-02T10:39:37.3384336+05:30</endTime>
  <interval>3</interval>
</a3:RegenRequest>
<a3:RegenRequest id="ref-4"
  xmlns:a3="http://schemas.microsoft.com/clr/nsassem/ETLExtract/HistorianETLExtract%2C%20Version%3D1.9.0.0%2C%20Culture%3Dneutral%2C%20PublicKeyToken%3Dnull">
  <startTime>2020-07-02T09:39:37.3384336+05:30</startTime>
  <endTime>2020-07-02T10:39:37.3384336+05:30</endTime>
```

```

<interval>4.5</interval>

</a3:RegenRequest>

<a3:RegenRequest id="ref-5"

  xmlns:a3="http://schemas.microsoft.com/clr/nsassem/ETLExtract/HistorianETLExtract%2C%20Version%3D1.9.0.0%2C%20Culture%3Dneutral%2C%20PublicKeyToken%3Dnull">

  <startTime>2020-07-02T09:39:37.3384336+05:30</startTime>

  <endTime>2020-07-02T10:39:37.3384336+05:30</endTime>

  <interval>14.5</interval>

</a3:RegenRequest>

</SOAP-ENV:Body>

</SOAP-ENV:Envelope>

```

Example of a State File

The following lines of code represent the content of a state file indicating that the last successful export occurred on June 6, 2010 at 5:00:04 PM in the UTC-4 time zone:

```

<SOAP-ENV:Envelope xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:xsd="http://www.w3.org/2001/XMLSchema"

  xmlns:SOAP-ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"

  xmlns:clr="http://schemas.microsoft.com/soap/encoding clr/1.0"

  SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/">

  <SOAP-ENV:Body>

  <a1:Persist id="ref-1"

    xmlns:a1="http://schemas.microsoft.com/clr/nsassem/LBExport/LBExport%2C%20Version%3D1.0.1.0%2C%20Culture%3Dneutral%2C%20PublicKeyToken%3Dnull">

    <lastExport>2010-06-07T17:00:04.2017462-04:00</lastExport>

  </a1:Persist>

</SOAP-ENV:Body>

</SOAP-ENV:Envelope>

```

Troubleshooting ETL Issues

Recommendations

Some overall recommendations when working with ETL to minimize issues:

- Extract Historian data for 30000 tags with 18MM samples per day.
- Set the Regen Interval to be less than 10 minutes.

Unable to Start the ETL Tools

Issue: When you try to start the Historian ETL Extract, Historian ETL PI Extract, or the Historian ETL Load service, an error occurs.

Diagnostics: If there is a limited bandwidth of the internet, the certificate publisher service times out after 30 seconds. To avoid this issue, disable the publisher service:

1. Access the configuration file for the service that you want to start. For example, for the Historian ETL Extract service, access the `HistorianETLExtract.exe.config` file.
2. Set the element **generatePublisherEvidence** to disabled.

An Error Occurs When Importing Tag Data into an Excel Spreadsheet

Issue: To specify tags using a template spreadsheet, when you import the tags stored in an .xml file, an error occurs, stating that the data is not valid according to the schema.

Diagnostics: Verify that:

- You have provided values in all the red-colored columns.
- Values in the Name column are unique.
- There are no blank rows.
- The values that you have entered are valid and of the same data type as defined for each property.

For details, refer to the [Tag Properties \(on page 2942\)](#) topic.

Issue: When you attempt to import tag data to an Excel spreadsheet from an .xml file, an error occurs, stating that the .xml file is not linked to schema.

Workaround: Ignore the message.