



iFIX 6.1

Mastering iFIX



Proprietary Notice

The information contained in this publication is believed to be accurate and reliable. However, General Electric Company assumes no responsibilities for any errors, omissions or inaccuracies. Information contained in the publication is subject to change without notice.

No part of this publication may be reproduced in any form, or stored in a database or retrieval system, or transmitted or distributed in any form by any means, electronic, mechanical photocopying, recording or otherwise, without the prior written permission of General Electric Company. Information contained herein is subject to change without notice.

© 2020, General Electric Company. All rights reserved.

Trademark Notices

GE, the GE Monogram, and Predix are either registered trademarks or trademarks of General Electric Company.

Microsoft® is a registered trademark of Microsoft Corporation, in the United States and/or other countries.

All other trademarks are the property of their respective owners.

We want to hear from you. If you have any comments, questions, or suggestions about our documentation, send them to the following email address:

doc@ge.com

Table of Contents

Mastering iFIX	1
Reference Documents	1
Scheduler	2
Overview	2
Using the Scheduler with iFIX	4
Getting Started with the Scheduler	5
Using the Scheduler	6
Securing Schedules	6
Resolving Schedules	6
Running Foreground and Background Schedules	6
Opening Pictures From Background Schedules	7
Debugging VBA Scripts	8
Starting the FixBackgroundServer Task	8
Adding Schedules to the Background Task Startup List	8
Foreground Schedule Checklist	8
Background Schedule Checklist	9
Designing Schedules	9
Event-Based Entries	9
Time-Based Entries	10
Adjusting for Daylight Saving Time	10
Multiple Command Script Wizard and Scheduling	11
Writing VBA Scripts that Access the iFIX WorkSpace	11
Creating and Editing Schedules and Entries	11
Sorting the Spreadsheet	12
Viewing and Controlling Entry Diagnostics	12
Writing Custom Scripts for the Scheduler	13
Form Script Sample Code	13
Button Script Sample Code	14
Generated Script Sample Code	14

Scheduler Dialog Boxes	14
Add Event Entry Dialog Box	15
Schedule Info	15
Event Data Source	15
Event Properties Tab	15
Event Type	15
Interval	16
Historical Properties Tab	16
Start Date	16
Start Time	16
Time Zone	16
Historical Mode	17
Duration	17
Update Rate	18
Action Info	18
Add Timer Entry Dialog Box	18
Name	18
Description	19
Trigger Info	19
Operation	20
Run Wizard	21
VB Editor	21
Scheduler Properties Dialog Box	21
Run Time State	21
Window Properties	21
Stats Refresh	22
Background Files	22
Script Authoring Wizard Dialog Box	22
Operation	22
Run Wizard	22
VB Editor	22

How Do I...	22
Working with the Scheduler	22
Overview: Creating and Running a Scheduled Event	23
To create and run a schedule:	23
Creating New Schedules	23
To create a new schedule:	23
Running Schedules as Background Tasks	23
To run a schedule as a background task:	24
Starting FixBackgroundServer	24
To start FixBackgroundServer:	24
Starting FixBackgroundServer as a Windows Service	24
To start FixBackgroundServer as a Windows Service:	24
Resolving Schedules	25
To resolve a schedule:	25
Assigning Schedules to a Security Area	25
To assign a schedule to a security area:	25
Working with Entries	26
Creating Event-Based Entries	26
To create an event-based entry:	26
Creating Time-Based Entries	26
Creating One Shot Time-Based Entries	27
To create a one shot time-based entry:	27
Creating Continuous Time-Based Entries	27
To create a continuous time-based entry:	27
Creating Daily Time-Based Entries	27
To create a daily time-based entry:	28
Creating Monthly Time-Based Entries	28
To create a monthly time-based entry:	28
Editing, Copying, and Sorting Entries	29
Modifying Existing Entries	29
To modify an existing entry:	29

Copying Entries to Other Schedules	29
To copy an entry to another schedule:	29
Moving Entries To Other Schedules	29
To move an entry to another schedule:	30
Sorting Entries in the Scheduler's Spreadsheet	30
To sort entries in the Scheduler's spreadsheet:	30
Working with the Scheduler at Run-time	30
Viewing the Status of Entries in the Run-time Environment	30
To view an entry's status in the run-time environment:	30
Starting and Stopping Entries from Executing	31
To start or stop an entry from executing:	31
Resetting the Statistics of Entries	31
To reset the statistics of an entry:	31
Firing Entries Manually	31
To fire an entry manually:	31
Using Advanced Features	31
Viewing or Editing Scheduler Properties	32
To view or edit Scheduler properties:	32
Using the Multiple Command Script Wizard in Scheduler	32
To use the Multiple Command Script Wizard in Scheduler:	32
Creating Entries Using Custom Scripts	32
To create an entry using a custom script:	33
Troubleshooting Scripts That Are Not Firing Properly	33
To troubleshoot scripts that are not firing properly in a schedule:	33
Local Node Alias	34
Enabling Local Node Alias	34
Using Local Node Alias	34
Local Node Alias Examples	34
Picture Example	34
Recipe Example	35
Historical Collection Group Example	35

Reporting	37
The Cross Reference Tool	38
Understanding the Cross Reference Tool	38
Searching for All Tags	39
Searching for One Tag	39
Searching for Text	39
Searching for Dynamo Objects in Pictures	40
Searching for Pictures Containing Dynamo Objects	41
Using the Report Wizard or the Quick Report	41
Quick Report Features	42
Cross Reference Report Wizard Features	42
Exploring the Cross Reference Tool Interface	42
Using the Cross Reference Tool Toolbar	43
Creating Quick Reports	43
Search Options	44
Report Option	44
View Options	44
To create a report using the Quick Report dialog box:	44
Creating Reports Using the Cross Reference Report Wizard	44
To create a report using the Cross Reference Report Wizard:	44
Specifying Search Settings	45
Specifying Picture Files for the Report	45
Specifying Schedule Files for the Report	45
Specifying Dynamo Sets for the Report	45
Specifying Report Settings Options	46
Reviewing the Report Settings	46
Viewing the Report Results	46
Viewing the Status Trail	47
Viewing a Search that Resolves Tags Using All Tag Group Files	48
Viewing a Search that Includes VBA Scripts	48
Selecting Print Options and Printing a Report	49

To select print options and print a report:	49
Selecting Page Options for Printing	49
Customizing Header or Footer Text	50
Creating a Cross Reference Tool Report from the Command-Line	50
Cross Reference Tool Dialog Boxes	51
Change Header or Footer Attributes Dialog Box	51
Header Text	51
Footer Text	51
Text Reset Button	51
Cross Reference Report Wizard Dialog Box	51
Search Settings Tab	51
Picture Files Tab	53
Schedule Files Tab	53
Dynamo Sets Tab	53
Report Settings Tab	54
Apply and Go Tab	55
Left/Right Buttons	55
Back/Next Buttons	55
OK	55
Page Setup Dialog Box	55
Portrait	55
Landscape	55
Page Margins	55
Change Header and Footer Attributes	56
Range	56
Print Dialog Box	56
Print Range	56
Print Options	56
Print Preview Screen	57
Next	57
Previous	57

Zoom	57
Print	57
Setup	57
Close	57
Quick Report Dialog Box	57
All Tags	57
One Tag (Button)	58
Tag (Edit Box)	58
Text (Button)	58
Text (Edit Box)	58
Dynamos	58
Search	58
Options	58
Quick Report Options Dialog Box	58
Resolve Tags Using All Tag Groups	58
Include VBA Scripts in Search	59
Include Summary	59
Automatically Resize Report Columns	59
Append to Status Trail	59
How Do I...	59
Generating a Cross Reference Report Using the Quick Report Dialog Box	59
To generate a Cross Reference Report using the Quick Report dialog box:	59
Generating a Cross Reference Report Using the Report Wizard	60
To generate a Cross Reference Report using the Report Wizard:	60
Resolving Tags During a Search Using All Tag Group Files	61
To resolve tags during a search using all Tag Group Files:	61
Searching Through VBA Scripts	62
To search through VBA scripts:	62
Configuring Report Output Settings	62
To configure report output settings:	62
Report Output Settings	62

Report Option	63
View Option	63
Modifying Print Options	63
Selecting Print Options and Printing a Report	63
To select print options and print a report:	63
Selecting Page Options for Printing	64
To select page options for printing:	64
Customizing Header or Footer Text	65
To customize header or footer text:	65
Creating Picture-specific Help Files	66
Why Create Picture-specific Help Files?	66
What's This? Help	66
Example	67
What's This? Help Design	68
Adding Help to an iFIX Picture	69
To specify the Help file name:	69
To assign a Help context ID:	69
To make the object selectable so that the operator can view the help:	69
Creating the Help File	69
Requirements	70
HTML Help	70
Creating a Topic File	70
To create a simple Winhelp topic file (.rtf) in Microsoft Word:	70
To create a simple HTML Help topic file (.htm) in a text editor:	71
Creating a Map and Alias File	71
To create a header file with the context IDs (for both Winhelp & HTML Help):	71
To create an alias file with additional ID mapping (for HTML Help only):	72
Creating and Compiling a Project File	72
Creating and Compiling a Simple Help Project	72
To create and compile the project file in Winhelp:	72
To create and compile the project file in HTML Help:	73

How to Compile from a Command Line	74
To build and compile Winhelp from the command line:	74
To build and compile HTML Help from the command line:	74
Testing Your Help File	74
To test your Help file:	74
Example: Creating a Picture-specific Help File	75
HTML Help Example	75
To create the HTML content in a text editor:	75
To assign the HTML Help file, context ID, and set the IsSelectable property:	75
To create a map file and alias file for HTML Help:	76
To create and build the HTML Help project file:	76
To test the HTML Help file:	77
Customizing the System Tree	77
Adding Folders to the System Tree	78
To add a folder to the system tree:	79
Adding Files to the System Tree	80
To add a file to the system tree:	80
Deleting Folders and Files from the System Tree	81
To delete a folder or file from the system tree:	82
Validating an Application	82
Application Validator Basics	82
Running the Application Validator	82
Running With or Without iFIX	83
Running in Demo Mode	83
General Configuration for the Application Validator	84
Working with Default Settings	84
Using the Application Validator Toolbar and Quick Keys	84
Types of Reports from the Application Validator	85
Summary Report	85
Comparison Detail Report	86
Viewing Only the Files that Changed	87

Saving the Comparison Detail Report	87
General Overview of Steps for Using the Application Validator	87
To use the Application Validator:	87
Command Line Options for the Application Validator	88
Notes on the Syntax	88
Descriptions of Optional Arguments	88
Command Line Options You Can Define in the GUI	89
Command Line Errors	89
Understanding Auditing for the Application Validator	89
To enable audited actions in the Application Validator:	89
Understanding the AppValConfig.ini File and Auditing	89
To configure the AppValConfig.ini file for auditing purposes:	90
Viewing the Audited Messages	90
Sample Audit Message from the Application Validator	90
List of Audit Messages from the Application Validator	90
Activity Log in the Main Window	91
Best Practices	92
Application Validator Dialog Boxes	92
Application Validator Options Dialog Box	93
Exclusion List Tab	93
Application Execution Tab	93
Auto Report Naming Tab	93
How Do I...	94
Working with iFIX	94
Troubleshooting	94
Customizing the iFIX Installation	95
Types of Users Who Create Custom Install Programs	95
The Administrator	95
The System Integrator	96
The Original Equipment Manufacturer	96
Creating a Custom iFIX Install for a DVD or Network	97

To create a customized install program:	97
To create a customized product DVD:	98
To create a customized network install in preparation for deployment:	98
Running a Quiet Install	98
To launch the iFIX install so it runs quietly (without making any configuration changes):	98
To customize the iFIX install so that it always runs quietly:	99
Modifying the Default Behavior of the iFIX Install	99
To modify the default behavior of the install program:	99
Including Additional iFIX Project Files in the Install	100
The Runtask.bat File	100
To create a Runtask.bat file which copies additional files:	101
Installing Software Improvement Modules (SIMs) with iFIX	101
To add SIMs to your customized iFIX install:	101
Including Additional Third-Party Software in the Install	102
To add other software programs to your customized iFIX install:	102
Customizing the Install Splash Screen	103
To replace the install splash screen for a customized install:	104
To customize the text that appears on this splash screen:	104
Rebranding Install Graphics	104
To replace the install graphics that appear after the splash screen:	104
Rebranding Install Text	105
To translate the strings for the main install:	105
To update additional text strings:	106
To update the install program with the rebranded string table files:	106
Rebranding the License Agreement	106
To replace the install splash screen for a customized install:	106
Recompressing the iFIX Install with Rebranded Material	106
To recompress the install with the InstallShield SAB:	107
Rebranding the iFIX DVD Booklet and Tray Card	107
Rebranding Other Parts of the iFIX Product	107
Deploying the iFIX Install Setup.exe Command Line Options	107

Example 1	108
Example 2	108
Example 3	108
INI Files Used by the iFIX Install	108
Installation.ini	108
InstallConfig.ini	111
Subinstall.ini	112
Setup.ini	114
Language Codes Used by the iFIX Install Program	115
Index	117

Mastering iFIX

The Mastering iFIX manual is intended for system integrators, OEMs, and process control engineers responsible for implementing a software automation solution using iFIX®. This manual assumes that you are familiar with Microsoft Windows, Microsoft Visual Basic, the iFIX WorkSpace, and your plant's network.

Reference Documents

For related information about iFIX, refer to the following manuals:

- [Understanding iFIX](#)
- [Writing Scripts](#)
- [Creating Pictures](#)
- [Setting Up the Environment](#)
- [Implementing Alarms and Messages](#)


Scheduler

There are certain tasks that you may want to perform at a specified time or interval, or when a change occurs in a database value or in any OPC data server value. For example, you may want to run a Visual Basic® for Applications (VBA) script that generates a report at the end of every shift or replaces the currently-displayed picture when a database point exceeds a certain value. The Scheduler allows you to create, edit, monitor, and run both types of actions as scheduled entries. In the Scheduler, you define the time or event that triggers a scheduled entry, and the action, referred to as an *operation*, that you want to occur.

iFIX® supplies Experts for common tasks such as replacing a picture. These Experts generate scripts based on the information that you supply. The Multiple Command Script Wizard enables you to use one or more Experts to assemble a scripted sequence of commands. You can also write custom scripts for tasks that do not have Experts. Refer to the [Writing Scripts](#) manual for detailed information on writing VBA scripts.

Overview

In the configuration environment, iFIX displays schedules in the iFIX WorkSpace, allowing you to easily create, edit, and start monitoring entries while you work on your project.



Scheduler in the Configuration Environment

In the run-time environment, you can view the status and statistics of the entries in your schedule. You can also control your entries using the Start/Stop, Reset, and Fire Now buttons.

Scheduled Entries

Indicates if the schedule runs in the foreground (F) or background (B)

Schedule

Entry Tabs

Entry Status, Name, Statistics, Description, and Controls

F	Status	Name	Number of Times Fired	Last Fired At	Next time to fire	Description	Start/Stop	Reset	Fire Now
1	Active	Line_Prod1	0	Undefined	11:40:00 AM	Shift Report	Stop	Reset	Fire Now
2	Active	Line_Prod2	0	Undefined	11:40:00 AM	Weekly Report	Stop	Reset	Fire Now
3									
4									
5									
6									
7									
8									
9									
10									
11									
12									
13									
14									
15									
16									
17									
18									
19									
20									
21									
22									
23									
24									
25									
26									
27									
28									
29									
30									
31									

For Help, press F1

Run

CAP NUM ...

Scheduler in the Run-time Environment

The Scheduler provides the following features:

- Spreadsheet design that allows you to easily view and edit entries.
- Ability to schedule as many entries as necessary and to trigger them as often as necessary.
- Ability to run as a service under Microsoft Windows.
- Experts, via the Multiple Command Script Wizard, for common events.
- Ability to easily monitor entries and view diagnostic statistics.
- Ability to trigger scheduled scripts on demand.
- Ability to run schedules as a foreground or background task.

Using the Scheduler with iFIX

Individual schedules can be run as a foreground or the background task. When you run a schedule in the foreground, you can easily test and debug scripts in the run-time environment. When an error occurs, VBA launches the Visual Basic Editor (VBE) debugger, where you can edit and save changes to a script. You cannot run scripts in the configuration environment.

When you run schedules as background tasks, they run regardless of whether the iFIX WorkSpace is in the run-time or configuration environment, and regardless of whether the iFIX WorkSpace is running. If you modify a scheduled entry, it automatically restarts. When the iFIX WorkSpace is in the run-time environment, you can view Scheduler statistics and diagnostic information about each entry in the schedule, including the number of times each entry has been fired and the last time it was fired.

You can also run the Scheduler in the background as a service under Windows. Because the Scheduler runs as a service, operators can log in and out of an Windows node without affecting scheduled entries, and entries are triggered regardless of whether or not the iFIX WorkSpace is running.

You can create multiple schedules, which allows you to organize and easily maintain entries. Each schedule can be configured individually to run as a background or foreground task. Also, as you add events to a schedule, you can choose whether or not to start monitoring them immediately, or to wait until the next time the iFIX WorkSpace starts.

The Scheduler supports a powerful Find and Replace feature that allows you to quickly and easily modify information in a schedule. For additional information on using the Find and Replace feature, refer to the [Finding and Replacing Data](#) section of the Understanding iFIX manual.

Getting Started with the Scheduler

Before you start scheduling entries, you should understand how the Scheduler executes scripts. The Scheduler can run as a foreground or background task. When you run a schedule in the foreground, it runs on the same thread as the scripts in the iFIX WorkSpace, allowing you to quickly test and debug scripts in the run-time environment. When you run a schedule in the background, it runs on a separate thread from the scripts in the iFIX WorkSpace, monitoring the system and triggering scheduled events.

The Scheduler does not loop; it waits for events to occur. When a selected event occurs, the script is triggered from a schedule running in the background, it is added to the queue, and it executes after the scripts in front of it have finished executing. For this reason, when a schedule is run as a background task it is ideal for monitoring tasks. This is exactly the same as scripts triggered from schedules running as foreground tasks in the iFIX WorkSpace.

Generally, schedules created to run in the foreground are used for testing and debugging. Once a schedule created to run in the foreground has been tested and debugged, we suggest that you set it to run in the background.

This section includes the following topics on how to get started with the Scheduler:

- [Using the Scheduler](#)
- [Securing Schedules](#)
- [Resolving Schedules](#)
- [Running Foreground and Background Schedules](#)
- [Opening Pictures From Background Schedules](#)

- [Debugging VBA Scripts](#)
- [Starting the FixBackgroundServer Task](#)
- [Adding Schedules to the Background Task Startup List](#)
- [Foreground Schedule Checklist](#)
- [Background Schedule Checklist](#)

Refer to the [Writing Scripts](#) manual for an explanation of how scripts are implemented in the iFIX WorkSpace.

Using the Scheduler

Schedules are spreadsheets with separate tabs for event-based entries and time-based entries. Double-clicking an empty row in a schedule displays a dialog box for adding an entry. Once you have created an entry, you can edit individual cells in the spreadsheet without using the dialog box.

Time-based entries create a timer object while event-based entries create an event object. These iFIX objects have associated properties, methods, and events that you can use in VBA scripts. They are displayed in the system tree and are the objects to which scheduled scripts are tied.

Securing Schedules

iFIX's schedule protection prevents unauthorized users from accessing or modifying schedules. To configure security for your schedules, enter a security area in the Properties window. For more information on configuring security, refer to the [Configuring Security Features](#) manual.

Resolving Schedules

Database information for each data source in a schedule is saved as part of the file on disk. When a schedule executes in the run-time environment, and the database information is not up-to-date, iFIX queries the database and *resolves* the tag definitions. This can be a time-consuming process which slows the execution of the schedule.

Resolving schedules removes the need for iFIX to query the database. Therefore, resolved schedules execute faster in the run-time environment. We recommend resolving your schedules as a final step in the configuration process. The Resolve feature is available for both schedules and pictures.

If the process database is modified after you resolve a schedule, you need to run Resolve again. These modifications include:

- Loading a different database.
- Deleting database tags.

Running Foreground and Background Schedules

You can select whether you want your schedules to run as foreground or background tasks. When you create a new schedule, the default is for it to run in the foreground. To run a schedule in the foreground, the iFIX WorkSpace must be running in the run-time environment. Running a schedule in the foreground is useful for testing and debugging VBA scripts.

To run a schedule in the background, the FixBackgroundServer task must be running. If the FixBackgroundServer task is not running, it is automatically started when a schedule is added to the background task. To create a schedule that runs in the background you must change the default setting in the Scheduler Properties dialog box, which is available by right-clicking a schedule and selecting Scheduler Properties from the pop-up menu. You can use this dialog box to change the default setting for a new schedule or for an existing schedule that is set to run in the foreground. Also, you can select whether you want a schedule to run in the foreground or the background, set the window properties, and set the statistics refresh rates.

NOTE: An unsigned write occurs when a database tag is configured for electronic signature, but you write a value directly to that tag without capturing a signature. If you are working in a secure environment with the Electronic Signature option enabled, you must be aware of the impact of unsigned writes to the process database. Unsigned writes can originate from schedules. Refer to the [Implications of Database Writes With Electronic Signature](#) section of the Using Electronic Signatures manual for detailed information.

To avoid the possibility of these messages occurring, append the intErrorMode parameter, set to "2", to the schedule's script command. This will send an error message without a prompt to configured iFIX alarm destinations, and the schedule will continue without the need for user intervention.

For example, if the schedule script is as follows:

```
WriteValue "33", "Fix32.ROXIE.AI_TAG.F_CV"
```

modify it to:

```
WriteValue "33", "Fix32.ROXIE.AI_TAG.F_CV", 2
```

Opening Pictures From Background Schedules

If a schedule running as a background task opens a picture while you are editing another picture or schedule in configure mode, you may experience unexpected behavior. In some instances, the picture may open over a modal dialog box and you will not be able to return to the original dialog box.

To avoid this problem, it is recommended that when adding an entry to a background schedule that references a picture, you write a custom script that configures the schedule to check whether the object is in the run mode or configure mode before opening a picture.

NOTE: It is recommended that schedules configured to run in the background do not reference pictures. If you do not check whether the WorkSpace is in run mode before opening the picture, and the WorkSpace is in configure mode when the open attempt occurs, the attempt fails since FixBackgroundServer cannot open pictures in configure mode.

The following VBA code shows an example on how a timer object checks whether the Workspace is in run mode before opening a picture named MyPicture.grf. If the WorkSpace is in configure mode, the picture does not open and a program called Task.exe runs instead. The timer object in this example runs from a background schedule:

```
Private Sub FixTimer3_OnTimeOut(ByVal lTimerId As Long)
    Dim WrkSpcApp As Object
    Set WrkSpcApp = GetObject("", "Workspace.Application")

    'If the object is in run mode open the picture
    If WrkSpcApp.Mode = 4 Then
```

```

    OpenPicture "MyPicture"

'Otherwise, just run this program called Task.exe
    Else
        Task.exe
    End If

Set WrkSpcApp = Nothing
End Sub

```

For more information on creating new schedules and using the Scheduler Properties dialog box, refer to the [Creating and Editing Schedules and Entries](#) section.

Debugging VBA Scripts

If a scripting error occurs while a schedule is running, the VBE debugger automatically launches to allow you to quickly edit and save the changes made to the script. If the schedule is running in the foreground when the VBE launches, any changes made to the script are automatically saved in the schedule. If the schedule is running in the background when the VBE launches, close the VBE editor, re-open it in iFIX WorkSpace, and make the necessary changes to the script. Any changes made to the script are automatically saved in the schedule.

NOTE: In order for scripting changes to be saved in a schedule, the VBE must be started in the iFIX WorkSpace. Any scripting changes made in the VBE launched from the FixBackgroundServer task will not be saved in a schedule.

Starting the FixBackgroundServer Task

The FixBackgroundServer task can run on its own, or as a Windows service. If you configure iFIX to start as a service, the FixBackgroundServer task runs as a service, provided you have added it to the task list.

To start iFIX as a service, shut down iFIX and in the SCU's Local Startup Definition dialog box enable the Continue Running After Log Off option. If iFIX is running, this option is unavailable. In the Task Configuration dialog box, add the FixBackgroundServer task to the task list.

Refer to the [Configuring Startup Tasks](#) section in the Setting Up the Environment manual for more information on configuring startup tasks.

Adding Schedules to the Background Task Startup List

Normally, you want your schedules to start automatically when iFIX is started. To do this, you must add the schedules to the background task startup list. If you are adding entries to a schedule that is already running in the background, you can choose whether or not to start monitoring the entry immediately.

Foreground Schedule Checklist

The following is an overview of the steps necessary to successfully implement a foreground schedule:

1. Create a foreground schedule in the configuration environment of the iFIX WorkSpace.
2. Monitor entries as necessary from the run-time environment of the iFIX WorkSpace.

Background Schedule Checklist

When creating a schedule that runs in the background, you can create it directly as a background schedule or create a foreground schedule and convert it to a background schedule. The following is an overview of the steps necessary to successfully implement a background schedule:

1. Create a background schedule in the configuration environment of the iFIX WorkSpace.
2. Add the schedule to the background task startup list, using the Background Startup tab in the User Preferences dialog box.
3. Monitor entries as necessary from the run-time environment in the iFIX WorkSpace.

Designing Schedules

This chapter explains the issues you need to consider while you are designing schedules. When creating schedules, there are two types of entries that you can select: event-based entries and time-based entries. This section describes both types of entries and the triggers that can be used by each. Refer to the following sections for more information on:

- [Event-Based Entries](#)
- [Time-Based Entries](#)
- [Script Authoring Experts](#)
- [Writing VBA Scripts that Access the iFIX WorkSpace](#)

Event-Based Entries

Event-based entries are created using the Add Event Entry dialog box. Event-based entries can use any data source available to the system to trigger an action. To select a data source, you can either enter the data source in the Data Source field or click the Browse button to access the Expression Builder.

Five event types are available to trigger an action based on the value of a data source. For example, you may want to have a certain action occur when an alarm equals HIHI. By tying the value of the alarm field to the OnTrue event type, you can trigger an action when the value of this field becomes equal to HIHI.

The following table lists the event types that are available and when they trigger:

The event type...	Triggers...
-------------------	-------------

OnChange	When the expression changes.
OnTrue	When the expression resolves to a non-zero value.
OnFalse	When the expression resolves to zero.
WhileTrue	At the specified interval as long as the expression evaluates to a non-zero value.
WhileFalse	At the specified interval as long as the expression evaluates to zero.

Time-Based Entries

Time-based entries are created using the Add Timer Entry dialog box. Time-based entries trigger at a scheduled time and are not tied to a data source. The following table lists the time triggers that are available and when they trigger:

The time type...	Triggers...
One Shot	Once at the specified date and time. For example, you can schedule an entry to trigger at 5:00 p.m. on 7/4/98.
Continuous	Continuously at the specified interval, starting at the specified time. For example, you can schedule an entry to trigger every eight hours. NOTE: You may notice in the log file that the timers occasionally fire +/- 1 or 2 milliseconds off. This may happen on the first fire and will return to the specified interval in a subsequent firing.
Daily	On the scheduled days of the week at a particular time. Optionally, you can specify an end time and interval. For example, you can schedule an entry to trigger Monday through Friday, at noon, or every hour from noon until 6:00 p.m.
Monthly	On the scheduled days of the month at a particular time. Optionally, you can specify an end time and interval. For example, you can schedule an event for the 15 th of the month, at 9:00 a.m., or every hour from 9:00 a.m. until 5:00 p.m. You can also schedule an event for the end of the month at a particular time. This setting determines the last day of the month for you.

NOTE: If you have Daylight Saving Time enabled and you create a timed-based entry to have a 2:30 AM Start Time, be aware that during the transition from Standard Time to Daylight Saving Time, the schedule will actually fire at 1:30 AM. All other days of the year, it will fire at 2:30 AM.

All time-based entries run the script tied to the OnTimeout event procedure.

Adjusting for Daylight Saving Time

The Scheduler supports daylight saving time for time-based events. Before allowing automatic Daylight Saving Time to be used in a production environment, you should test your application under each of the following scenarios for proper behavior:

- While in Standard Time.
- While in Daylight Time.
- During the transition from Standard Time to Daylight Time.
- During the transition from Daylight Time to Standard Time.

Multiple Command Script Wizard and Scheduling

When selecting an action in the Operation field of either the Add Timer Entry or Add Event Entry dialog box, you can click the Run Wizard button to open the Multiple Command Script Wizard. You can also open the Multiple Command Script Wizard by double-clicking the Operation field of an existing timer or event entry and then clicking the Run Wizard button in the dialog box that appears.

The wizard enables you to select one or more commands for the desired operation, each of which is configured using an Expert. After you have provided each Expert with its required information, a VBA script tied to the appropriate event is generated. You can later edit the script by rearranging or deleting commands in the wizard, or you can customize the script in the VB Editor.

NOTES:

- Although the Multiple Command Script Wizard's purpose is to fully automate the VBA command scripting process, you can manually edit scripts generated by the wizard with the VB Editor. You may add or edit VBA scripts anywhere before the Scripts Authoring Tool header line (***** Scripts Authoring Tool *****), or directly between a "WizardEnd" and a "Wizard[x]=" statement. Do not edit any of the commented areas in the wizard-generated script. If the Multiple Command Script Wizard detects an improperly customized VBA script, you may encounter an error.
- The Multiple Command Script Wizard does not check the command sequence to make sure commands occur in a logical order.

If you do not want to use the Multiple Command Script Wizard, you can also use the VB Editor to write your own custom scripts for frequently performed tasks. Refer to the [Writing Custom Scripts for the Scheduler](#) section for information on how to create your own custom scripts for the Scheduler.

Writing VBA Scripts that Access the iFIX WorkSpace

When you write a scheduled script that opens, closes, replaces, or accesses a property of an object in a picture, you must ensure that the iFIX WorkSpace is running and that the picture you need to access is open and active. This differs from writing scripts that run from pictures.

Before you can access any information about the active picture in the iFIX WorkSpace, you must activate the iFIX WorkSpace using the GetObject method as shown in the following example.

```
Dim AppObj As Object
Set AppObj = GetObject("", "Workspace.Application")
```

You can now check to see if the picture is open:

```
If UCase(AppObj.ActiveDocument.Name) = UCase("MyPicture") Then
<perform a task or open the picture>
```

You can then check to see which document or picture is open, and replace it if it is not the one you need. Once the proper picture is open, you can access its objects.

Refer to the [Writing Scripts](#) manual for more information on using VBA with iFIX.

Creating and Editing Schedules and Entries

The Scheduler allows you to create multiple schedules which help you to easily organize and maintain events. When you create a new schedule, you can control its properties from the Scheduler Properties dialog box.

The following table lists the tabs on the Scheduler Properties dialog box and the properties that can be controlled from each:

Tabs	Properties
Run Time State	Run in Foreground Run in Background
Window Properties	Window Height Window Width Window Styles
Stats Refresh	Timer Statistics Refresh Rate (in seconds) Event Statistics Refresh Rate (in seconds)
Background Files	Lists all schedules running in the background. No changes can be made from this tab.

You can create new schedules when the iFIX WorkSpace is in the configuration environment.

NOTE: iFIX does not support schedules that use the same name as the local node. Therefore, do not use your local node's name for any schedules you create.

Once you have created a schedule, the schedule and all its entries appear in the Schedules folder of the system tree. You can open a schedule and view or edit its properties at any time by double-clicking the schedule name in the system tree.

Once you have created a schedule, you can add new entries to it using the Multiple Command Script Wizard or by writing your own custom scripts in the VB Editor. You can edit an existing entry by selecting the entire entry or a specific cell within the entry. Once created, entries can be easily copied or moved from one schedule to another.

Sorting the Spreadsheet

You can sort Scheduler entries in ascending or descending order by clicking the heading of the column you want to sort. For example, if you want to sort entries alphabetically by name, click the Name column's heading. The entries will appear in ascending order. To sort them in descending order, click the Name column's heading again.

NOTE: Sorting is only available in the configuration environment. In the run-time environment, entries appear in the order they were added to the schedule.

Viewing and Controlling Entry Diagnostics

The Scheduler allows you to view and control entry diagnostics in the run-time environment. If you open a schedule in the run-time environment, you can view the status of entries, the number of times they have been fired, and the time when they were last fired. You can also:

- Start or stop an entry from executing.
- Reset the statistics (number of times it has been fired and time when it was last fired) of the entry.
- Trigger an entry to fire on demand.

If you have loaded a schedule, but the scripts are not firing, you need to determine whether the problem is caused by the firing mechanism or by the script itself.

Writing Custom Scripts for the Scheduler

The Scheduler provides Experts that generate a script that is executed when an entry triggers. These Experts, which are available for common tasks such as toggling a digital point or generating a report, are accessed using the Multiple Command Script Wizard.

You can also create custom scripts for tasks that you need to perform using the Visual Basic Editor. This section shows sample code that may be helpful when writing custom scripts for use with the Scheduler. It includes the following sections:

- [Form Script Sample Code](#)
- [Button Script Sample Code](#)
- [Generated Script Sample Code](#)

For additional examples, use the VBE to view the code for the Experts, buttons, and forms supplied with iFIX. Refer to the [Writing Scripts](#) manual for detailed information on writing VBA scripts.

Form Script Sample Code

The following example shows code that collects the name of the picture the user wants to display when the event is triggered, generates the script, and creates the event. The Procedures object is a collection of scripts. Before you generate the script, you need to get the index number for the next script using the `GetEventHandlerIndex` method. Once you generate the string that will become the script, use the `AddEventHandler` method to add the event.

```
Private CurrentObject As Object
Private EventName As String

Public Sub GetCurrentObjectValues(obj, Str)
    Set CurrentObject = obj
    EventName = Str
End Sub

Private Sub CommandButton1_Click()

    'get file name entered by user
    Dim FileName As String
    FileName = TextBox1.Value

    Dim WorkingObj As Object
    Set WorkingObj = CurrentObject.Procedures

    'Get the index for the procedure
    Dim Index As Long
    Dim Found As Long
```

```

WorkingObj.GetEventHandlerIndex EventName, Index, Found

'Generate code
Dim StringCode As String
StringCode = "Dim doc As Object" & Chr(13) _
            & "Dim PicturePath As String" & Chr(13) _
            & "PicturePath = ""c:\fix32\pic\" & FileName" & _
            Chr(13) & "Set doc = _
            Application.Documents.Open(PicturePath)" & Chr(13)

'Add the event
WorkingObj.AddEventHandler EventName, StringCode, Index

'Close the form
End

End Sub

```

Button Script Sample Code

The following example shows code for a button object called MyExpert that gets the timer or event object, the event trigger name, and picture name, if any, from the Add Event dialog box. It passes this information in to the form using the GetCurrentObjectValues procedure, and then displays the form.

```

Private Sub MyExpert_Click()

    Dim CurrentObj As Object
    Dim EventName As String

    'Set procedure object, event name, and file name
    Set CurrentObj = MyExpert.ProcedureObject
    EventName = MyExpert.EventProcedure
    MyExpert.Property1 = frmOpenPicture.TextBox1.Value

    'Pass the object and event name into the form
    Call frmOpenPicture.GetCurrentObjectValues(CurrentObj, _
    EventName)
    frmOpenPicture.Show
    frmOpenPicture.Hide
End Sub

```

Generated Script Sample Code

The following example shows the script that would be generated if you ran this Expert on the Timer7 object, using the OnTimeOut event.

```

Private Sub Timer7_OnTimeOut(ByVal lTimerId As Long)
Dim doc As Object
Dim PicturePath As String
PicturePath = "c:\fix32\pic\" & FileName
Set doc = Application.Documents.Open(PicturePath)
End Sub

```

Scheduler Dialog Boxes

The Scheduler includes the following dialog boxes (listed in alphabetical order):

- [Add Event Entry Dialog Box](#)
- [Add Timer Entry Dialog Box](#)
- [Scheduler Properties Dialog Box](#)
- [Script Authoring Wizard Dialog Box](#)

Add Event Entry Dialog Box

NOTE: If you are modifying an existing Scheduler event-based entry, the title of this dialog box changes to "Modify Event Entry."

The Add Event Entry dialog box displays the following items:

Schedule Info

Item	Description
Name	Allows you to specify a name for an event-based Scheduler entry. The name can be any alphanumeric name up to 64 characters and must begin with a letter. Do not use names that contain VBA reserved words. See the Microsoft VBA help system for more information on VBA reserved words.
Description	Allows you to provide a description of up to 80 characters for an event-based Scheduler entry.

Event Data Source

Allows you to enter a data source or expression for this Data link. The term data source refers to a reference to a source of information, such as iFIX tagnames and historical files, or other OPC-compliant data servers. A data source may also consist of iFIX objects (such as shapes, charts, and variables) or 3rd party OLE controls. The term expression refers to constants, data sources, or a combination of constants and data sources that are connected with one or more operators. Use the Browse (...) button to open the Expression Builder dialog box. Use the Quick Modify button to modify a database block directly without launching the Database Manager.

Event Properties Tab

Event Type

Allows you to select the condition that must be met for the event-based script to fire. The options are:

Option	Description
On True	Evaluates a Boolean expression in the Data Source field and fires the entry if the expression evaluates to a non-zero value.
On False	Evaluates a Boolean expression in the Data Source field and fires the

	entry if the expression evaluates to zero.
On Data Change	Fires the entry every time the value in the Data Source field changes.
While True	Evaluates a Boolean expression in the Data Source field and fires the entry at the specified interval for as long as the expression evaluates to a non-zero value.
While False	Evaluates a Boolean expression in the Data Source field and fires the entry at the specified interval for as long as the expression evaluates to zero.

Interval

Allows you to specify the duration of time between each triggering of a While True or While False event-based entry. The entry will fire for as long as the expression in the Data Source field evaluates to one or zero, respectively.

Historical Properties Tab

The Historical Properties tab allows you to set the parameters for a query that fetches historical data from GE Historian. The tab contains the following items:

NOTE: The following fields, with the exception of the Update Rate fields, are only available if you select a Historical Mode other than Current Value.

Start Date

Item	Description
Fixed Date	Specifies whether to enter a specific start date for the query of the data source.
Days Before Now	Specifies whether to enter the number of days prior to today to fetch data from GE Historian. For example, if you want to display data collected for the data source two days ago, enter 2.

Start Time

Item	Description
Fixed Time	Specifies whether to designate a specific time to start, based on a 24-hour clock.
Lock Time	Locks the fixed time, even if you change the time zone in the Date and Time Properties dialog box in the Control Panel. This field is available only when you designate a specific time to start using the Fixed Time field.
Duration Before Now	Specifies whether to enter the duration prior to the current time to start. The minimum duration is 0 seconds; the maximum is 23 hours, 59 minutes, and 59 seconds.

Time Zone

Item	Description
------	-------------

Time Zone	Allows you to select the time zone to associate with the start time. You can select the client time (time zone for your computer), the server time (time zone used by the Historian server), or the tag time (uses the time zone bias of the tag, which is set in Historian). The default time zone is that of the client machine. This field is available only when Historian is used.
Adjust for Daylight Savings Time	Adjusts the time if the zone you selected is experiencing daylight saving. This field works only if you selected the Automatically adjust clock for daylight saving changes check box located on the Time Zone tab of the Date/Time Properties dialog box in the Control Panel.

Historical Mode

Allows you to determine how iFIX selects and fetches data from a historical data source and, determines what each displayed value represents. The options are:

- Sample - The last valid value found, up to and including the start of the specified interval.
- Avg - The average of all valid data found during the specified interval.
- High - The highest valid data point value found during the specified interval.
- Low - The lowest valid data point value found during the specified interval.
- Interpolated - The data is interpreted by assuming that the line between two values is a straight line. All points along that line are estimated except the starting point and the ending point.
- Current Value - The current value of the data point.

IMPORTANT: The Current Value may update at a rate different from the rate set in the Update Rate field. The update rate is not set solely by the rate entered in the Update Rate field. It also depends on the collection rate, the rate for querying Historian, and the time required to request an update from the Historian server and send it back to the client. As a result, the time it takes to display the updates may be longer than anticipated. Additionally, please be aware that the timestamp for this mode represents the timestamp from the Historian server, not the client.

- Standard Deviation - The standard deviation of all valid data found during the specified interval.
- Total - The total of all valid data found during the specified interval.

Duration

The duration determines the time range for the historical data source. The minimum duration for a fetch is one second; the maximum is 999 days, 23 hours, 59 minutes, and 59 seconds.

Item	Description
Days	Allows you to enter the number of days. This field can be used in conjunction with the other fields in this area.
Hours	Allows you to enter the number of hours for the duration for the data fetch query. This field can be used in conjunction with the other fields in this area.
Mins	Allows you to enter the number of minutes for the duration for the data fetch query. This field can be used in conjunction with the other fields in this area.
Secs	Allows you to enter the number of seconds for the duration for the data fetch query. This field can be used in conjunction with the

other fields in this area.

Update Rate

Allows you to specify the rate at which the data is updated. The default rate is five seconds. Zero is permitted for a one-time fetch. The fastest update rate is five seconds, the slowest, 1:59:59.

Item	Description
Hours	Allows you to enter the number of hours for the rate of data update. This field can be used in conjunction with the other fields in this area.
Mins	Allows you to enter the number of minutes for the rate of data update. This field can be used in conjunction with the other fields in this area.
Secs	Allows you to enter the number of seconds for the rate of data update. This field can be used in conjunction with the other fields in this area.

Action Info

Item	Description
Operation	Displays the command(s) currently scheduled to trigger when the defined event occurs. If the field is blank, you can specify one or more commands by clicking the Run Wizard button to open the Multiple Command Script Wizard, or the VB Editor button to open the VB Editor. If more than one command is specified, the Operation field will display "Multiple Commands". If you specify a command using the VB Editor, the Operation field will display "Custom Script".
Run Wizard	Opens the Multiple Command Script Wizard to automatically create a VBA script for the current event-based entry.
VB Editor	Launches the Visual Basic Editor to display the script, if any exists, for the current event-based entry. If no script exists, you can use the VB Editor to create one.

Add Timer Entry Dialog Box

NOTE: If you are modifying an existing Scheduler time-based entry, the title of this dialog box changes to "Modify Timer Entry."

The Add Timer Entry dialog box displays the following items:

Name

Allows you to specify a name for the time-based Scheduler entry. The name can be any alphanumeric name up to 64 characters and must begin with a letter. Do not use names that contain VBA reserved words. See the Microsoft VBA help system for more information on VBA reserved words.

Description

Allows you to provide a description of up to 80 characters for the time-based Scheduler entry.

Trigger Info

One Shot

Allows you to schedule a time-based entry to trigger once on a specific date and time.

Item	Description
Date	Allows you to specify the date on which a one shot time-based entry will trigger.
Time	Allows you to specify the time at which a one shot time-based entry will trigger.

Continuous

Allows you to schedule a time-based entry to trigger continuously at a specific interval.

Item	Description
Start Time	Allows you to specify the time at which a continuous time-based entry will begin triggering. Once triggered, the entry will trigger at a regular period of time specified by the Interval field.
Interval	Allows you to specify the duration of time between each triggering of a continuous time-based entry. The entry will begin running at the time specified in the Start Time field.

Daily

Allows you to schedule a time-based entry to trigger at a particular time on the days of the week you specify.

Item	Description
Day of the Week	Allows you to select this day as one of the days of the week that you want a daily time-based entry to trigger.
Start Time	Allows you to specify the time at which a time-based entry will begin triggering.
Enable End Time/Interval	Allows you to configure a time-based entry to trigger continuously from the time specified in the Start Time field to the time specified in the End Time field. The entry will continuously trigger between these times at the regular time intervals specified by the Interval field.

End Time	Allows you to specify the time at which a time-based entry stops triggering. This field is only available if the Enable End Time/Interval check box is selected.
Interval	Allows you to specify the duration of time between each triggering of a time-based entry. The entry will begin triggering on the selected days at the time specified in the Start Time field and end at the time specified in the End Time field. This field is only available if the Enable End Time/Interval check box is selected.

Monthly

Allows you to schedule a time-based entry to trigger at a particular time on the days of the month you specify.

Item	Description
Day of the Month	Allows you to select this day as one of the days of the month that you want a monthly time-based entry to trigger.
End of Month	Allows you to automatically schedule a monthly time-based entry to trigger on the last day of each month.
Start Time	Allows you to specify the time at which a time-based entry will begin triggering.
Enable End Time/Interval	Allows you to configure a time-based entry to trigger continuously from the time specified in the Start Time field to the time specified in the End Time field. The entry will continuously trigger between these times at the regular time intervals specified by the Interval field.
End Time	Allows you to specify the time at which a time-based entry stops triggering. This field is only available if the Enable End Time/Interval check box is selected.
Interval	Allows you to specify the duration of time between each triggering of a time-based entry. The entry will begin triggering on the selected days at the time specified in the Start Time field and end at the time specified in the End Time field. This field is only available if the Enable End Time/Interval check box is selected.

Operation

Displays the command(s) currently scheduled to trigger at the specified date and time. If the field is blank, you can specify one or more commands by clicking the Run Wizard button to open the Multiple Command Script Wizard, or the VB Editor button to open the VB Editor. If more than one command is specified, the Operation field will display "Multiple Commands". If you specify a command using the VB Editor, the Operation field will display "Custom Script".

Run Wizard

Opens the Multiple Command Script Wizard to automatically create a VBA script for the current time-based entry.

VB Editor

Launches the Visual Basic Editor to display the script, if any exists, for the current time-based entry. If no script exists, you can use the VB Editor to create one.

Scheduler Properties Dialog Box

The Scheduler Properties dialog box displays the following items:

Run Time State

Item	Description
Run in Fore-ground	Allows a schedule to run as a foreground task in the run-time environment of the iFIX WorkSpace.
Run in Back-ground	Allows a schedule to run as a background task, separately from the iFIX WorkSpace. Time-based and event-based scripts will still run as scheduled, even if the iFIX WorkSpace is not running - provided that the scripts have been added to the FixBackgroundServer task and the FixBackgroundServer task is running.

Window Properties

Item	Description
Window Height	Allows you to configure the height of the iFIX schedule that is currently open. Window height is specified as a percentage.
Window Width	Allows you to configure the width of the iFIX schedule that is currently open. Window width is specified as a percentage. .
Title Bar	Enables or disables the Scheduler's title bar at run-time.
System Menu	Enables or disables the Scheduler's system menu.
Resizable	Specifies whether or not the Scheduler window is resizable at run-time.
Always On Top	Specifies whether or not the Scheduler window stays in front of other windows within the iFIX WorkSpace at run-time.

Stats Refresh

Item	Description
Timer Statistics Refresh Rate	Allows you to set the rate, in seconds, at which time-based entry statistics are refreshed at run-time. Setting the refresh rate to a higher value will improve CPU time.
Event Statistics Refresh Rate	Allows you to set the rate, in seconds, at which event-based entry statistics are refreshed at run-time. Setting the refresh rate to a higher value will improve CPU time.

Background Files

Displays all the schedules that are currently loaded in the FixBackgroundServer task.

Script Authoring Wizard Dialog Box

The Script Authoring Wizard dialog box displays the following items:

Operation

Displays the command(s) currently scheduled to trigger for the specified event or date and time. If the field is blank, you can specify one or more commands by clicking the Run Wizard button to open the Multiple Command Script Wizard, or the VB Editor button to open the VB Editor. If more than one command is specified, the Operation field will display "Multiple Commands". If you specify a command using the VB Editor, the Operation field will display "Custom Script".

Run Wizard

Opens the Multiple Command Script Wizard to automatically create a VBA script for the current time-based or event-based entry.

VB Editor

Launches the Visual Basic Editor to display the script, if any exists, for the current time-based or event-based entry. If no script exists, you can use the VB Editor to create one.

How Do I...

Click on any of the following links for more information on working with the Scheduler application:

- [Working with Scheduler](#)
- [Working with Entries](#)
- [Working with Scheduler at Run-time](#)
- [Advanced Topics](#)

Working with the Scheduler

You can perform the following tasks when working with the Scheduler:

- [Creating and Running a Scheduled Event](#)
- [Creating New Schedules](#)
- [Running Schedules as Background Tasks](#)
- [Starting FixBackgroundServer](#)
- [Starting FixBackgroundServer as a Windows Service](#)
- [Resolving Schedules](#)
- [Assigning Schedules to a Security Area](#)

Overview: Creating and Running a Scheduled Event

► To create and run a schedule:

1. In the iFIX WorkSpace's configuration environment, create the schedule.
2. Add a new time-based or event-based entry to the schedule.
3. Configure the schedule to run as a foreground or background task.
4. View or edit the properties of the schedule as necessary.

Creating New Schedules

► To create a new schedule:

1. In Classic view, in WorkSpace, click the New Schedule button on the Standard Toolbar.
-Or-
In Ribbon view, click the WorkSpace button, select New, and then click Schedule.
2. Right-click anywhere in the schedule window and choose Add New Timer Entry.
-Or-
Right-click anywhere in the schedule window and choose Add New Event Entry.
3. Select the desired timer or event options.
4. In Classic view, on the WorkSpace menu, click Save As.
-Or-
In Ribbon view, click the WorkSpace button, and then Save As.
5. In the File Name field, enter a name for the schedule. iFIX schedules are saved to the Database (PDB) path with an .EVS file extension.
6. Click Save.

Running Schedules as Background Tasks

► **To run a schedule as a background task:**

1. In Classic view, on the WorkSpace menu, click User Preferences.
-Or-
In Ribbon view, on the Home tab, in the WorkSpace group, click Settings, and then click User Preferences.
2. Select the Background StartUp tab.
3. Select the first empty row and click the Browse (...) button.
4. Select the schedule that you want to add to the Background Task Startup list and click Open.
5. Click OK to save the changes that you have made and close the User Preferences dialog box.

Starting FixBackgroundServer

► **To start FixBackgroundServer:**

1. Click the Start button, and point to Run.
2. Enter the path and file name of the FixBackgroundServer application. By default:
`C:\Program Files (x86)\GE\iFIX\FIXBACKGROUNDSERVER.EXE`
3. Click OK.

Starting FixBackgroundServer as a Windows Service

► **To start FixBackgroundServer as a Windows Service:**

1. Shut down iFIX.
2. Ensure that you are logged in as an Administrator.
3. On the Start menu, point to Programs, iFIX, and then System Configuration. The System Configuration Utility (SCU) window appears.
4. From the Configure menu, click Local Startup. The SCU's Local Startup Definition dialog box appears.
5. Select the Continue Running After Log Off check box, and click OK. This configures iFIX to run as a service.
6. Click the Task Configuration button on the SCU toolbox. The SCU's Task Configuration dialog box appears.
7. In the Filename field, enter the path and file name of the FixBackgroundServer application. By default:

`C:\Program Files (x86)\GE\iFIX\FIXBACKGROUNDSERVER.EXE`

8. Select the Background Option button.
9. Click Add to add FixBackgroundServer to the Configured Tasks list.
10. Click OK.
11. On the File menu, click Save to save the SCU file.
12. Exit the SCU.
13. Restart iFIX.

Resolving Schedules

► To resolve a schedule:

1. In Classic view, from the WorkSpace toolbar, click the Resolve Files Tool button.
-Or-
In Ribbon view, on the Applications tab, in the Utilities group, click Utilities, and then click Resolve Files.
2. In the File Types area, select the Schedule check box.
3. In the Directories area, verify that your schedule directory is correct. If it is not, enter the correct path in the Schedules field.
4. In the Resolve Files area, select the schedule file you want to resolve. To select every file in the list, click Select All.
5. Click the Update Schedule Files button and then click OK.

Assigning Schedules to a Security Area

► To assign a schedule to a security area:

1. Open the schedule that you want to assign by:
Double-clicking it in the Schedules folder of the iFIX WorkSpace system tree,
-Or-
Creating a new schedule:
In Classic view, click the New Schedule button on the Standard Toolbar.
-Or-
In Ribbon view, click the WorkSpace button, select New, and then click Schedule.
2. In Classic view, on the View menu, click Property Window.
-Or-
In Ribbon view, on the View tab, in the Window group, click Property Window.
3. In the Security Area field, enter the security area you want to use.

Working with Entries

You can perform the following tasks when working with the Scheduler entries:

- [Creating Event-Based Entries](#)
- [Creating Time-Based Entries](#)
- [Editing, Copying, and Sorting Entries](#)

Creating Event-Based Entries

► To create an event-based entry:

1. Open the schedule that you want to add the event-based entry to by double-clicking it in the Schedules folder of the iFIX WorkSpace system tree, or create a new schedule by clicking the New Schedule button on the Standard Toolbar.
2. Right-click a row in the schedule. From the pop-up menu, select Add New Event Entry. The Add Event Entry dialog box appears.
3. Enter the data source that will trigger the event-based script for the entry, or click Browse to launch the Expression Builder dialog box. If you are using a tagname expression as a data source, click Quick Modify to modify the properties of a block directly without launching the Database Manager.

NOTE: The data source can be a process value, object property, VBA script, or mathematical expression.

4. From the Event Type menu, select the condition for triggering action.
5. If you selected While True or While False for the Event Type, enter an interval in the Interval field.
6. If you selected a historical data source, complete the Historical Properties tab. To do so:
 - a. From the Historical Mode list, select a mode.
 - b. In the Update Rate area, select the hours, minutes, and seconds for the update rate. If you chose a historical mode other than Current Value, go to Step C. Otherwise, go to Step 7.
 - c. In the Start Date area, choose whether to use a fixed date or a relative date, (Days Before Now). Depending on your selection, select either the date or the Days Before Now.
 - d. In the Start Time area, choose whether to use a fixed time or a relative time, (Duration Before Now). Depending on your selection, select either the time, and optionally, Lock Time, or the hours, minutes, and seconds for the Duration Before Now.
 - e. From the Time Zone list, choose a time zone.
 - f. In the Duration Area, select the days, hours, minutes, and seconds for the duration.
7. Click either Run Wizard or VB Editor to create a script for the event. Complete the actions as necessary.
8. Click OK.

Creating Time-Based Entries

You can perform the following tasks when working with time-based entries:

- [Creating One Shot Time-Based Entries](#)
- [Creating Continuous Time-Based Entries](#)
- [Creating Daily Time-Based Entries](#)
- [Creating Monthly Time-Based Entries](#)

Creating One Shot Time-Based Entries

► To create a one shot time-based entry:

1. Open the schedule that you want to add the one shot time-based entry to by double-clicking it in the Schedules folder of the iFIX WorkSpace system tree, or create a new schedule by clicking the New Schedule button on the Standard Toolbar.
2. Right-click a row in the schedule. From the pop-up menu, select Add New Timer Entry. The Add Timer Entry dialog box appears.
3. Select the One Shot option button and enter the date and time at which you want the entry to occur.
4. Enter the necessary information in the Schedule and Action areas. For help on individual fields within the Add Timer Entry dialog box, click the What's This? (question mark) help button and select the field for which you want more information.
5. Click OK. To save your changes, click the Save button on the Standard Toolbar.

Creating Continuous Time-Based Entries

► To create a continuous time-based entry:

1. Open the schedule that you want to add the continuous time-based entry to by double-clicking it in the Schedules folder of the iFIX WorkSpace system tree, or create a new schedule by clicking the New Schedule button on the Standard Toolbar.
2. Right-click a row in the schedule. From the pop-up menu, select Add New Timer Entry. The Add Timer Entry dialog box appears.
3. Select the Continuous option button and enter the date and time at which you want the entry to occur.
4. Enter the necessary information in the Schedule and Action areas. For help on individual fields within the Add Timer Entry dialog box, click the What's This? (question mark) help button and select the field for which you want more information.
5. Click OK. To save your changes, click the Save button on the Standard Toolbar.

Creating Daily Time-Based Entries

► **To create a daily time-based entry:**

1. Open the schedule that you want to add the daily time-based entry to by double-clicking it in the Schedules folder of the iFIX WorkSpace system tree, or create a new schedule by clicking the New Schedule button on the Standard Toolbar.
2. Right-click a row in the schedule. From the pop-up menu, select Add New Timer Entry. The Add Timer Entry dialog box appears.
3. Select the Daily option button.
4. Select the check box for all of the days of the week that you want the entry to trigger.
5. In the Start Time field, enter the time that you want the event to trigger.
6. Optionally, select the Enable End Time/Interval check box to configure the entry to trigger repeatedly at a specific rate and for a specific duration of time. Enter the time that you want to stop the entry from firing in the End Time field. Enter the duration of time between occurrences of the entry in the Interval field.
7. Enter the necessary information in the Schedule and Action areas. For help on individual fields within the Add Timer Entry dialog box, click the What's This? (question mark) help button and select the field for which you want more information.
8. Click OK. To save your changes, click the Save button on the Standard Toolbar.

Creating Monthly Time-Based Entries

► **To create a monthly time-based entry:**

1. Open the schedule that you want to add the monthly time-based entry to by double-clicking it in the Schedules folder of the iFIX WorkSpace system tree, or create a new schedule by clicking the New Schedule button on the Standard Toolbar.
2. Right-click a row in the schedule. From the pop-up menu, select Add New Timer Entry. The Add Timer Entry dialog box appears.
3. Select the Monthly option button.
4. Select the buttons for all of the days of the month that you want the entry to trigger. Select the End of Month check box to have iFIX automatically trigger the entry on the last day of the month.
5. In the Start Time field, enter the time that you want the event to trigger.
6. Optionally, select the Enable End Time/Interval check box to configure the entry to trigger repeatedly at a specific rate and for a specific duration of time. Enter the time that you want to stop the entry from firing in the End Time field. Enter the duration of time between occurrences of the entry in the Interval field.
7. Enter the necessary information in the Schedule and Action areas. For help on individual fields within the Add Timer Entry dialog box, click the What's This? (question mark) help button and select the field for which you want more information.
8. Click OK. To save your changes, click the Save button on the Standard Toolbar.

Editing, Copying, and Sorting Entries

The following sections provide information on editing, copying, and sorting entries in the Scheduler:

- [Modifying Existing Entries](#)
- [Copying Entries to Other Schedules](#)
- [Moving Entries to Other Schedules](#)
- [Sorting Entries in the Scheduler's Spreadsheet](#)

Modifying Existing Entries

► To modify an existing entry:

1. Open the schedule that contains the entry you want to modify by double-clicking it in the Schedules folder of the iFIX WorkSpace system tree.
2. Double-click the row number of the entry to display the Modify Timer Entry or Modify Event Entry dialog box.
3. Modify the fields in the Schedule, Trigger, and Action areas as desired. For help on individual fields, click the What's This? (question mark) help button and select the field for which you want more information.
4. Click OK. To save your changes, click the Save button on the Standard Toolbar.

TIP: You can also select an individual cell in the schedule's spreadsheet and change its value directly rather than accessing the Modify Timer Entry or Modify Event Entry dialog boxes. Your modifications are automatically put into effect when you exit the cell.

Copying Entries to Other Schedules

► To copy an entry to another schedule:

1. Right-click the entry you want to copy from the Schedules folder of the iFIX WorkSpace system tree and select Copy from the pop-up menu.
2. From the Schedules folder of the iFIX WorkSpace system tree, right-click the schedule to which you want to copy the entry and select Paste from the pop-up menu. The entry is added to the schedule.
3. Open the schedule to which you copied the entry and click the Save button on the Standard Toolbar.

Moving Entries To Other Schedules

► **To move an entry to another schedule:**

1. Drag and drop the entry from the one schedule to another in the Schedules folder of the iFIX WorkSpace system tree. The entry is deleted from the schedule from which it was moved and is added to the schedule to which it was moved.
2. Open each schedule and click Save on the Standard Toolbar.

Sorting Entries in the Scheduler's Spreadsheet

► **To sort entries in the Scheduler's spreadsheet:**

Click the heading of a spreadsheet column to toggle between sorting entries by ascending or descending order according to the information in that column.

NOTE: Sorting is only available in the configuration environment. In the run-time environment, entries display in the order that they were added to the schedule.

Working with the Scheduler at Run-time

You can perform the following tasks when working with the Scheduler at run-time:

- [Viewing the Status of Entries in the Run-Time Environment](#)
- [Starting and Stopping Entries from Executing](#)
- [Resetting the Statistics of Entries](#)
- [Firing Entries Manually](#)

Viewing the Status of Entries in the Run-time Environment

► **To view an entry's status in the run-time environment:**

1. From the run-time environment, open the schedule you want to view.
2. Observe the following fields:
 - **Status** - displays the current status of the entry. Based on the current condition of the entry, this cell may display Active or Stopped.
 - **Name** - displays the name that you provided for the entry.
 - **Number of Times Fired** - displays the number of times that the entry has fired since it was created, or since it was last reset.
 - **Last Fired At** - displays the most recent time that the event has fired.
 - **Next Time to Fire** - displays the next time that the entry is scheduled to fire.

NOTE: The Next Time to Fire field only appears in time-based entries.

- **Description** - displays the description you provided for the entry.

Starting and Stopping Entries from Executing

► To start or stop an entry from executing:

1. From the run-time environment, on the File menu, click Open.
2. Select the schedule with the entry you want to control and click Open.
3. Click the Start/Stop button in the row of the entry. The Status cell changes to indicate whether the entry is Active or Stopped.

Resetting the Statistics of Entries

► To reset the statistics of an entry:

1. From the run-time environment, on the File menu, click Open.
2. Select the schedule with the entry you want to control and click Open.
3. Click the Reset button in the row of the entry. The Number of Times Fired cell resets to zero and the Last Fired At cell resets to Undefined.

Firing Entries Manually

► To fire an entry manually:

1. From the run-time environment, on the File menu, click Open.
2. Select the schedule with the entry you want to control and click Open.
3. Click the Fire Now button in the entry's row. The entry fires and the Number of Times Fired and Last Fired At cells update to show the new information.

Using Advanced Features

Advanced features of the Scheduler include the following:

- [Viewing or Editing Scheduler Properties](#)
- [Using Script Authoring Experts](#)

- [Creating Entries Using Custom Scripts](#)
- [Troubleshooting Scripts That are not Firing Properly](#)

Viewing or Editing Scheduler Properties

► To view or edit Scheduler properties:

1. Open a schedule by double-clicking it in the Schedules folder of the iFIX WorkSpace system tree, or create a new schedule by clicking the New Schedule button on the Standard Toolbar.
2. Right-click any row in the schedule and select Scheduler Properties from the pop-up menu. The Scheduler Properties dialog box appears.
3. Click the Run Time State, Window Properties, Statistics Refresh, and Background Files tabs to view the current settings and make changes as necessary. Use the What's This? (question mark) help button to get field-specific help for each tab.
4. Click OK.

Using the Multiple Command Script Wizard in Scheduler

► To use the Multiple Command Script Wizard in Scheduler:

1. In the Add Timer Entry, Add Event Entry, or Script Authoring Wizard dialog box, click the Run Wizard button. The Multiple Command Script Wizard appears.

NOTE: If you do not want to create a script automatically using the wizard, you can click the VB Editor button to launch the Visual Basic Editor, which allows you to enter your own custom script to fire at a specific date and time, or based on a particular event. Refer to the *Writing Scripts* manual for more information.

2. Choose a command from the Select Action to Append list. The Expert associated with the command you chose appears.
3. Complete the Expert with your desired settings and information.
4. Optionally, repeat steps 2 and 3 if you want to add additional commands to your scripted command sequence.
5. When you have finished choosing your command sequence, click OK.

Creating Entries Using Custom Scripts

► **To create an entry using a custom script:**

1. Double-click the schedule you want to add the entry to in the system tree. The schedule appears in the iFIX WorkSpace.
2. Right-click a row in the schedule and select Add New Event Entry from the pop-up menu. The Add Event Entry dialog box appears.
- Or -
Right-click a row in the schedule and select Add New Timer Entry from the pop-up menu. The Add Timer Entry dialog box appears.
3. Enter the Schedule and Trigger information and click the VB Editor button. The Visual Basic Editor (VBE) appears.
4. Write your custom script in the VBE and click the Save Project button on the toolbar.
5. Exit the VBE and click OK.

NOTES:

- Although the Multiple Command Script Wizard's purpose is to fully automate the VBA command scripting process, you can manually edit scripts generated by the wizard with the VB Editor. You may add or edit VBA scripts anywhere before the Scripts Authoring Tool header line (**** Scripts Authoring Tool ****), or directly between a "WizardEnd" and a "Wizard[x]=" statement. Do not edit any of the commented areas in the wizard-generated script. If the Multiple Command Script Wizard detects an improperly customized VBA script, you may encounter an error.
- The Multiple Command Script Wizard does not check the command sequence to make sure commands occur in a logical order.

Troubleshooting Scripts That Are Not Firing Properly

► **To troubleshoot scripts that are not firing properly in a schedule:**

- In the run-time environment, click the Fire Now button for the entry that is not working properly. This button executes the script independently from when the script is scheduled to fire. Ensure that the script fires and runs properly.
- Check the entry's configuration by returning to the configuration environment and double-clicking the entry number to display the Modify Event Entry or Modify Timer Entry dialog box. Ensure that the parameters are set correctly.
- Check the SCU and ensure that SAC is running. Refer to the [Setting Up the Environment](#) e-book.
- Check the Database Manager and ensure that the block is on scan. Refer to the [Building a SCADA System](#) e-book.
- Use the Visual Basic Editor to debug the script.

Local Node Alias

The local node alias feature allows iFIX local SCADA nodes to share pictures, recipes, and historical collection groups across nodes without changing the node name. When you use this feature, you can create generic pictures and recipes and save development and maintenance time.

For more information, refer to the following sections:

- [Enabling Local Node Alias](#)
- [Using Local Node Alias](#)
- [Local Node Alias Examples](#)

Enabling Local Node Alias

Before you can use the local node alias features you must enable the local node alias feature in the SCU.

Using Local Node Alias

Once you have enabled the local node alias feature, you can use the THISNODE placeholder in the node portion of the tagname (NODE.TAG.FIELD). iFIX substitutes the local physical node name for the THISNODE placeholder, increasing the portability of pictures and recipes and eliminating the need to change tagname references for different nodes. The system tree in the iFIX WorkSpace always shows the actual node represented by the THISNODE placeholder.

If, for example, you have ten production lines that produce similar products, you can create one generic display that can access real-time data from any of the ten lines. By using the THISNODE placeholder, if you need to change the display, you only need to make the change once. Refer to the [Setting Up the Environment](#) manual for more information.

Local Node Alias Examples

The local node alias feature can be used for pictures, recipes, and historical collection groups, as illustrated in the following examples:

- [Picture Example](#)
- [Recipe Example](#)
- [Historical Collection Group Example](#)

Picture Example

Assume that you have a Data link in a picture that is configured with the tagname FIX32.THISNODE.AI-1.F_CV, and your local SCADA node name is CANLINE1. When you open the picture, the Data link behaves as if it were configured as FIX32.CANLINE1.AI-1.F_CV.

If you open the same picture on a different computer whose local SCADA node name is CANLINE2, the Data link's tagname resolves to FIX32.CANLINE2.AI-1.F_CV.

Recipe Example

Assume that you have two SCADA nodes: FERMENTER1 and FERMENTER2. The recipes Beer1 and Beer2 are used to make beer and download to FERMENTER1 and FERMENTER2, respectively. The Beer1 recipe defines the following items:

Identifier	Formula
FERMENTER1:ILK1.F_CV	0
FERMENTER1:XCV1F1.F_CV	0
FERMENTER1:W16S1.F_CV	150
FERMENTER1:T16F.F_CV	55
FERMENTER1:K16F1.F_CV	132

The Beer2 recipe is identical except for the node name:

Identifier	Formula
FERMENTER2:ILK1.F_CV	0
FERMENTER2:XCV1F1.F_CV	0
FERMENTER2:W16S1.F_CV	150
FERMENTER2:T16F.F_CV	55
FERMENTER2:K16F1.F_CV	132

In this implementation, both recipes are required because each recipe has hard-coded node name references. The local node alias feature eliminates the need for two recipes. Instead, you can create one recipe for both SCADA nodes, as shown in the following example:

Identifier	Formula
THISNODE:ILK1.F_CV	0
THISNODE:XCV1F1.F_CV	0
THISNODE:W16S1.F_CV	150
THISNODE:T16F.F_CV	55
THISNODE:K16F1.F_CV	132

After you create this recipe, share the directory that it resides in and map the recipe paths of both SCADA servers to the shared directory. For information on changing the recipe paths, refer to the [Creating Recipes](#) manual.

Historical Collection Group Example

Assume that you want to create a chart using the tank level and tank temperature from the two SCADA nodes in the Recipe example. On FERMENTER1 these tagnames are:

Identifier	Formula
Tank Level	FIX32.FERMENTER1.AI_LEVEL.F_CV
Tank Temperature	FIX32.FERMENTER1.AI_TEMP.F_CV

On FERMENTER2 these tagnames are:

Identifier	Formula
Tank Level	FIX32.FERMENTER2.AI_LEVEL.F_CV
Tank Temperature	FIX32.FERMENTER2.AI_TEMP.F_CV

When you define the pens for the chart, use the following data sources: FIX32.THISNODE.AI_LEVEL.F_CV and FIX32.THISNODE.AI_TEMP.F_CV.

If you open the chart on FERMENTER1, the tagnames resolve to FIX32.FERMENTER1.AI_LEVEL.F_CV and FIX32.FERMENTER1.AI_TEMP.F_CV.

If you open it on FERMENTER2, the tagnames resolve to FIX32.FERMENTER2.AI_LEVEL.F_CV and FIX32.FERMENTER2.AI_TEMP.F_CV.

Reporting

Detailed reports are important tools for reviewing the performance of a process. They allow you to quickly grasp the relationships between specific pieces of manufacturing process data so that you can make effective decisions. Using any third-party reporting application that supports ODBC queries, you can create customized reports based on iFIX real-time and historical data. When you use iFIX real-time data, you generate the report with current data extracted from an iFIX database. When you create a report using iFIX historical data, you generate the report based on data gathered over a period of time.

Once generated, reports can be printed or displayed in the iFIX WorkSpace. The ability to display reports directly in the iFIX WorkSpace allows you to quickly view a report from any number of nodes in your system, greatly reducing the time it takes for you to make informed decisions about your process.

The Cross Reference Tool

The Cross Reference Tool is an iFIX utility that allows you to create a report identifying every data source or occurrence of a data source in pictures, scripts, schedules, or a User Global. Using the Cross Reference Tool, you can also locate a text string in object names, property names, and property values. The Cross Reference Tool also enables you to find pictures containing selected Dynamo objects, or Dynamo objects that are in selected pictures.

By default, the report results display in the Cross Reference Tool interface. Additionally, the Cross Reference Tool provides options that allow you to configure the report to automatically print or save upon report completion.

This chapter describes the Cross Reference Tool interface and its functionality including:

- [Understanding the Cross Reference Tool](#)
- [Using the Report Wizard or the Quick Report](#)
- [Exploring the Cross Reference Tool Interface](#)
- [Creating Quick Reports](#)
- [Creating Reports Using the Cross Reference Report Wizard](#)
- [Viewing the Report Results](#)
- [Selecting Print Options and Printing a Report](#)
- [Creating a Cross Reference Tool Report from the Command-Line](#)

Understanding the Cross Reference Tool

The Cross Reference Tool allows you to identify where tags are used within iFIX pictures, scripts, schedules, and tag groups. Additionally, you can also perform a search to find a text string, or search for Dynamo objects. Once you select which type of search you would like to perform and define additional search options, the Cross Reference Tool creates a report that details the objects, properties, and property values that are related to that tag or text string.

You can create five types of searches using the Cross Reference Tool:

- [All Tags](#)
- [One Tag](#)
- [Text](#)
- [Dynamo Objects in Pictures](#)
- [Pictures Containing Dynamo Objects](#)

For detailed information regarding the report results of each search, refer to [Viewing the Report Results](#).

For information on displaying the results of a search that includes VBA scripts or that resolves tag substitutions with Tag Group files, refer to the [Viewing a Search that Includes VBA Scripts](#) and [Viewing a Search that Resolves Tags Using All Tag Group Files](#) sections.

Searching for All Tags

The *All Tags* search type returns a list of all the tags in the selected object, picture, schedule, or User Global. This search returns a list that displays the name of the object that references the tag (Object column), the property of that tag (Property column), and the tag itself (Current Value column), as shown in the following figure.

	Object	Property	Current Value
1	OneOfEachObject.DataLink1.Format1	Source	Fix32.THISNODE.AA1.F_CV
2	OneOfEachObject.Text2	Caption	System.CurrentTime
3	OneOfEachObject.Text3	Caption	System.CurrentDate
4	OneOfEachObject.TestEvent	Source	Fix32.THISNODE.AA1.F_CV = 1
5	OneOfEachObject.Chart1.Pen1	Source	FIX32.NODE.TAG.F_CV

Report Results of a Search for All Tags

Searching for One Tag

The *One Tag* search type searches for a specific tag in the selected object, picture, schedule, or User Global, and all tag group files. You can enter a string in the Tag field or click the Browse (...) button to open the Expression Editor.

TIP: You can also search using a partial tag name. For example, entering AI would find AI1 and TANKAI.

The One Tag search also allows you to perform a find on an object in an object to object connection. Using the Cross Reference Tool report results, you could then determine which object required modification and make the change manually.

This search returns the name of the object that references the tag (Object column), the property type (Property column), and the tag name (Current Value column). For example, the following figure displays a One Tag search on the partial tag name ACTIVESTATUS.

	Object	Property	Current Value
1	NetworkStatusDisplay.Group1.AnimatedForegroundColor	Source	Fix32.THISNODE.NSD.F_ACTIVESTATUS_1
2	NetworkStatusDisplay.Group2.AnimatedForegroundColor1	Source	Fix32.THISNODE.NSD.F_ACTIVESTATUS_2
3	NetworkStatusDisplay.Group3.AnimatedForegroundColor2	Source	Fix32.THISNODE.NSD.F_ACTIVESTATUS_3
4	NetworkStatusDisplay.Group4.AnimatedForegroundColor3	Source	Fix32.THISNODE.NSD.F_ACTIVESTATUS_4
5	NetworkStatusDisplay.Group5.AnimatedForegroundColor4	Source	Fix32.THISNODE.NSD.F_ACTIVESTATUS_5
6	NetworkStatusDisplay.Group6.AnimatedForegroundColor5	Source	Fix32.THISNODE.NSD.F_ACTIVESTATUS_5
7	NetworkStatusDisplay.Group7.AnimatedForegroundColor6	Source	Fix32.THISNODE.NSD.F_ACTIVESTATUS_7
8	NetworkStatusDisplay.Group8.AnimatedForegroundColor7	Source	Fix32.THISNODE.NSD.F_ACTIVESTATUS_8

Report Results for a One Tag Search

Searching for Text

The *Text* search type searches for a text string in the object names, property names, and property values of selected object, picture, schedule, or User Global.

Leave <ALL> in the Text field to display all object names, property names, and property values. To search for a specific text string, enter text that would appear in the either the object name, property, or property value.

NOTE: Do not use a * wildcard in this field. Entering a wildcard returns a Search completed with no output error.

The Text search returns the object name, property, and property value in the Report Results section. If the Cross Reference Tool finds the text string in the object name, all of the object properties are listed in the Property column. For example, the following figure displays a Text search on the Text string FOREGROUNDColor:

	Object	Property	Property Value
18	NetworkStatusDisplay.Group1.AnimatedForegroundColor	Name	AnimatedForegroundColor
19	NetworkStatusDisplay.Group1.AnimatedForegroundColor	Parent	NetworkStatusDisplay
20	NetworkStatusDisplay.Group1.AnimatedForegroundColor	IsSelectable	False
21	NetworkStatusDisplay.Group1.AnimatedForegroundColor	Description	
22	NetworkStatusDisplay.Group1.AnimatedForegroundColor	IsDirty	False
23	NetworkStatusDisplay.Group1.AnimatedForegroundColor	IsSelected	False
24	NetworkStatusDisplay.Group1.AnimatedForegroundColor	NumberOfTargets	1
25	NetworkStatusDisplay.Group1.AnimatedForegroundColor	ContainedObjects	
26	NetworkStatusDisplay.Group1.AnimatedForegroundColor	ContextID	-1
27	NetworkStatusDisplay.Group1.AnimatedForegroundColor	ClassName	Lookup
28	NetworkStatusDisplay.Group1.AnimatedForegroundColor	Category	Animation
29	NetworkStatusDisplay.Group1.AnimatedForegroundColor	Version	257
30	NetworkStatusDisplay.Group1.AnimatedForegroundColor	ContainedSelections	
31	NetworkStatusDisplay.Group1.AnimatedForegroundColor	FullyQualifiedName	NetworkStatusDisplay.Group1.AnimatedFor

Report Results of a Text Search

Searching for Dynamo Objects in Pictures

The *Dynamics in Pictures* search type searches for Dynamo objects in selected pictures.

To search for all Dynamo objects in a single picture, you can use either the Quick Report or the Report Wizard. To search for all Dynamics in more than one picture, use the Report Wizard to select multiple pictures from the Picture Files tab.

NOTE: At least one picture must be selected in the Picture Files tab, and at least one Dynamo Set must be selected in the Dynamo Sets tab, before you can conduct a search.

The Dynamics in Pictures search returns the name, revision number, and description of Master Dynamics and Dynamo Instances in the selected picture(s), as well as the Dynamo Sets to which the Dynamo objects belong.

If the Cross Reference Tool finds a Dynamo Instance and Master Dynamo whose revision numbers are different, the search result is listed in red, as shown below:

Search For: Dynamics in C:\Program Files\Proficy\Proficy iFIX\PIC\test.grf							
	Dynamo Sets	Master Dynamo	Revision of Master	Description of Master	Dynamo Instance	Revision of Instance	Dynamo Description of Instance
1	Pipes.fds	Pipes.Dynamo3	3		test.Dynamo1	1	
2	Pipes.fds	Pipes.Dynamo3	3		test.Dynamo3	3	
3	Pipes.fds	Pipes.Dynamo5	2		test.Dynamo4	1	

Report Results of a Dynamics in Pictures Search

You can use the Dynamo Updater, available via a button on the toolbar, to update mismatched Dynamos. When you launch the Dynamo Updater, it pre-selects the Dynamos that were identified in the Cross Reference Tool's search results and displays them in its Select Dynamos tab.

NOTE: The Dynamo Updater is only available when a search reveals at least one revision mismatch between a Dynamo Instance and a Master Dynamo.

For more information on updating Dynamos, refer to [Updating Dynamos in Pictures](#).

Searching for Pictures Containing Dynamo Objects

The *Pictures Containing Dynamos* search type searches for pictures that contain the selected Dynamo objects.

To search for all pictures that contain a single Dynamo object, you can use either the Quick Report or the Report Wizard. To search for all pictures that contain more than one Dynamo object, use the Report Wizard to select multiple Dynamos from the Dynamo Sets tab.

NOTE: At least one picture must be selected in the Picture Files tab, and at least one Dynamo Set must be selected in the Dynamo Sets tab, before you can conduct a search.

The Pictures Containing Dynamos search returns the names of the pictures in which the selected Dynamo objects exist, along with each Master Dynamo or Dynamo Instance's name, revision number, and description.

If the Cross Reference Tool does not find the selected Dynamo object(s) in any pictures, the search result is listed in red, as shown below:

Search For: Pictures containing Dynamos in C:\Program Files\Proficy\Proficy iFIX\PIC\Pipes.fds							
	Picture Name	Dynamo Instance	Revision of Instance	Dynamo Description of Instance	Master Dynamo	Revision of Master	Description of Master
1	No Picture referenced				Pipes.Dynamo3	3	
2	No Picture referenced				Pipes.Dynamo5	2	
3							

Report Results of a Pictures Containing Dynamos Search

You can use the Dynamo Updater, available via a button on the toolbar, to update mismatched Dynamos. When you launch the Dynamo Updater, it pre-selects the Dynamos that were identified in the Cross Reference Tool's search results and displays them in its Select Dynamos tab.

NOTE: The Dynamo Updater is only available when a search reveals at least one revision mismatch between a Dynamo Instance and a Master Dynamo.

For more information on updating Dynamos, refer to [Updating Dynamos in Pictures](#).

Using the Report Wizard or the Quick Report

The Cross Reference Tool offers two utilities to create a report: the Quick Report dialog box and the Cross Reference Report Wizard. The Quick Report dialog box allows you to select from the most common Cross Reference Tool search features on one picture, schedule, User Global, or object listed in the Object Tree.

The Cross Reference Report Wizard allows you to search on multiple files and configure automatic saving and printing options. Use the following feature lists to help you determine when to use each tool.

Quick Report Features

The Quick Report dialog box allows you to do the following:

- Search for all tags, one tag, or a text string in the selected picture, schedule, user global page, or object.
- Search for all pictures that contain a single Dynamo object, or all Dynamo objects in a single picture.
- Display the search results in the Report Results screen. Once the search completes, you can manually print out the results or choose to save the search results to a .CSV, .HTM, .XLS, or .TB2 file.
- Resolve tags during a search using all tag group files.
- Search through VBA scripts.
- Include a summary of the report at the end of the report.
- Automatically resize report columns.
- Append results to the Status Trail.

For more information, refer to [Creating Quick Reports](#).

Cross Reference Report Wizard Features

The Cross Reference Report Wizard allows you to do the following:

- Search for all tags, one tag, or a text string in the selected picture, schedule, user global page, or object.
- Search for Dynamo objects in multiple pictures, or multiple pictures that contain several Dynamo objects.
- Select multiple files to search through and arrange them in a specific order.
- Resolve tags during a search using all tag group files.
- Search through VBA scripts.
- Configure report settings options, including:
 - Automatically save report to file.
 - Automatically save a status trail as a file.
 - Automatically print the report upon generation.
- Include a summary of the report at the end of the report.
- Automatically resize report columns.

For more information, refer to [Creating Reports Using the Cross Reference Report Wizard](#).

Exploring the Cross Reference Tool Interface

To open the Cross Reference Tool, double-click the Cross Reference Tool icon in the system tree.

The Cross Reference Tool interface includes the following sections:

Object Tree: Displays pictures, schedules, and User Globals that are currently opened in the Proficy iFIX WorkSpace. You can select a file or select an object within that file.

NOTE: If you have opened new files in the WorkSpace since opening the Cross Reference Tool, you will need to refresh the tree in order to see them displayed. To do this, click the Refresh button in the Cross Reference Tool Toolbar.

Report Results Area: Displays the results of the search. Refer to [Viewing the Report Results](#) for more information.

Status Trail : Displays the detailed status of the report, including error messages. Refer to [Viewing the Status Trail](#) for more information.

Using the Cross Reference Tool Toolbar

You can quickly access many of the Cross Reference Tool features in the Cross Reference Tool toolbar. The following table describes the functions of the Cross Reference Tool toolbar buttons.

Cross Reference Tool Toolbar Buttons

Use this button...	To...
	Open the Quick Report dialog box. For more information, refer to the Creating Quick Reports section.
	Save the currently displayed report. Available files types include *.CSV, *.HTM, *.XLS, or *.TB2. NOTE: Microsoft Excel enforces a maximum row limit of 65536. If you try to save a report that exceeds this row limitation in Excel, you will be prompted to continue or cancel. Please be aware that rows exceeding that limitation may be lost if you select either option.
	Open the Print dialog box to configure print settings and print the currently displayed report. For more information, refer to the Selecting Print Options and Printing a Report section.
	Refresh the Object Tree. If you have opened new files in the WorkSpace since opening the Cross Reference tool, you will need to refresh the tree in order to see them.
	Open the Font dialog box. This dialog box allows you to specify font type, size, and style.
	Open the Report Wizard dialog box. For more information, refer to the Creating Reports Using the Cross Reference Report Wizard section.
	Opens the Dynamo Updater. For more information, refer to the Working with Dynamo Objects section.
	Open the Cross Reference Tool Help.

Creating Quick Reports

[The Quick Report Dialog Box](#) appears when you open the Cross Reference Tool. In addition to allowing you to select a search type, the Quick Report dialog box also allows you to select the following search, report, and view options when you click the Options button:

Search Options

Resolve Tags using All Tag Group Files - If the selected file or object contains Tag Group symbols, this option resolves those symbols by attempting to match symbols with all Tag Group Definition files and finds all substitutions. This option is available for all search types.

Include VBA Scripts in Search - Allows the Cross Reference Tool to search through scripts within the selected file for the tag(s) or text.

Report Option

Include Summary - Adds a summary report to the end of the Cross Reference Report detailing the number of objects and tags searched.

View Options

Automatically Resize Report Columns - Automatically resizes the columns in the Report results to accommodate the text.

Append to Status Trail - If enabled, the status trail adds any new tracking information to the existing status trail. If disabled, each time the Report runs, all previous tracking information is overwritten by the new status trail.

► To create a report using the Quick Report dialog box:

1. Select a file or object in the Object Tree.

NOTE: If you want to run a [Dynamos Quick Report](#) to search for all pictures that contain [Dynamo objects from a Dynamo Set](#), select the [Dynamo Set](#) in the Object Tree. If you want to run a [Dynamos report that searches for all Dynamo objects in a picture](#), select the picture.

2. From the File menu, select Quick Report. The Quick Report dialog box appears.
3. Select the desired search settings in the Quick Report dialog box.
4. Click the Search button.

NOTE: You cannot access the [iFIX WorkSpace](#) while the Cross Reference Tool generates a report. Once the report completes, you will be able to access the [iFIX WorkSpace](#) again.

You can also double-click an object or file in the Object Tree to run a Quick Report. This runs the Quick Report using the default settings or the settings of your last report.

The results of the Quick Report display in the Report Results section of the Cross Reference Tool. You can save or print the report manually using the appropriate toolbar buttons.

Creating Reports Using the Cross Reference Report Wizard

The Cross Reference Report Wizard walks you through the process of creating a Cross Reference Report. The Cross Reference Report Wizard allows you to search through multiple files, and then configure the report to automatically print or save upon report completion.

► To create a report using the Cross Reference Report Wizard:

1. Select what you want to search for and specify search options.
2. Choose which files the Cross Reference Tool searches and modify the search order.

3. Select whether the report results are automatically saved or printed and modify additional output options.
4. Review the wizard settings and run the report.

Specifying Search Settings

The Search Settings tab of the Cross Reference Report Wizard allows you to select the type of search that the report runs and specify the following search options:

Resolve Tags using All Tag Group Files - If the selected file or object contains Tag Group symbols, this option resolves those symbols by attempting to match symbols with all Tag Group Definition files and finding all substitutions. This option is available for all search types.

Include VBA Scripts in Search - Allows the Cross Reference Tool to search through scripts within the selected files for the tag(s).

Specifying Picture Files for the Report

The Picture Files tab of the Cross Reference Report Wizard allows you to select one or more pictures to search, and allows you to arrange them in a specific search order.

By default, the Select Files list displays all pictures in the C:\Program Files (x86)\GE\FIX\PIC folder. If any of the selected pictures are not opened in the WorkSpace, the Cross Reference Tool opens them during report generation. Once the report finishes, these pictures are closed.

The Cross Reference Tool processes pictures from top to bottom in the list. You can re-arrange the order in which the pictures are processed by selecting a picture and clicking the up or down arrow button to move the selected picture up or down in the list.

Specifying Schedule Files for the Report

The Schedule Files tab of the Cross Reference Report Wizard allows you to select one or more schedules to search, and allows you to arrange them in a specific search order.

By default, the Select Files list displays all schedules in the C:\Program Files (x86)\GE\FIX\PDB folder. If any of the selected schedules are not opened in the WorkSpace, the Cross Reference Tool opens them during report generation. Once the report finishes, these schedules are closed.

The Cross Reference Tool processes schedules from top to bottom in the list. You can re-arrange the order in which the schedules are processed by selecting a schedule and clicking the up or down arrow button to move it up or down in the list.

Specifying Dynamo Sets for the Report

The Dynamo Sets tab of the Cross Reference Report Wizard allows you to select one or more Dynamo Sets to search, and allows you to arrange them in a specific search order.

By default, the Select Files list displays all Dynamo Sets in the C:\Program Files (x86)\GE\iFIX\PIC folder. If any of the selected Dynamo Sets are not opened in the WorkSpace, the Cross Reference Tool opens them during report generation. Once the report finishes, these Dynamo Sets are closed.

The Cross Reference Tool processes Dynamo Sets from top to bottom in the list. You can re-arrange the order in which the Dynamo Sets are processed by selecting a Dynamo Set and clicking the up or down arrow button to move it up or down in the list.

Specifying Report Settings Options

By default, the Cross Reference Tool displays the results of a search in the Report Results section of the Cross Reference Tool. The Report Settings tab of the Cross Reference Report Wizard allows you to specify the following output options in addition to the default display:

Save Report to File - Automatically saves the report when the report generation completes. You can save the report to the default file and location listed, enter one directly into the Save Report to File field, or click the Browse (...) button to locate a file or path.

Available file types include *.CSV, *.HTM, *.XLS, or *.TB2.

NOTE: Microsoft Excel enforces a maximum row limit of 65536. If you try to save a report that exceeds this row limitation in Excel, you will be prompted to continue or cancel. Please be aware that rows exceeding that limitation may be lost if you select either option.

Save Status Trail - Saves the status trail information when the report completes. You can save the report to the default file and location listed, enter one directly into the Save Status Trail field, or click the Browse (...) button to locate a file or path.

The available file type is *.TXT.

Print Report - Automatically prints the report when complete. Click the Advanced button to modify the Print settings. Refer to [Selecting Print Options and Printing a Report](#) for more information.

Additionally, the Report Settings tab also allows you to set the following report and view options:

Include Summary - Adds a summary report to the end of the report that details the number of objects and tags searched.

Automatically Resize Report Columns - Automatically resizes the columns in the Report Results section to accommodate the text.

Reviewing the Report Settings

The Apply and Go tab displays all of the settings you have selected in the Wizard.

Review your choices and if they are correct, click the OK button. If you need to modify any of the options, click the Back button to return to the appropriate tab.

NOTE: You cannot access the iFIX WorkSpace while the Cross Reference Tool generates a report. Once the report completes, you will be able to access the iFIX WorkSpace again.

Viewing the Report Results

Once you create a report using either the Quick Report or Cross Reference Report Wizard, the results display in the Report Results section of the Cross Reference Tool interface.

The information that appears in the Report Results columns depends upon which type of search you selected. The following table describes the search type and display results.

Search Results	
Type of Search	Displays
All Tags	Returns a list that displays the name of the object that references the tag (Object column), the property of that tag (Property column), and the tag itself (Current Value column), as shown in the Report Results of a Search for All Tags figure.
One Tag	Returns the name of the object that references the tag (Object column), the property type (Property column), and the tag name (Current Value column). For example, the Report Results for a One Tag Search figure shows a One Tag search on the partial tag name ACTIVESTATUS.
Text	Returns the object name, property, and property values. If the Cross Reference Tool finds the text string in the object name, all of the object properties are listed in the Property Column. For example, the Report Results of a Text Search figure shows a Text search on the string FOREGROUNDCOLOR.

Additionally, if you selected the Save Report to File or Print Report options in the Cross Reference Report Wizard, those are automatically completed when the results display. Once the Report Results display, you can also save or print the report manually using the appropriate toolbar buttons.

Viewing the Status Trail

The Status Trail, shown in the following figure, tracks the processing status of the report. This allows you to monitor the report progress and messages, and track errors encountered in the report.

Date	Time	Status
5/25/2002	2:12:26 PM	**** Search started on [HasTagGroupsKeyMacrosScripts]...
5/25/2002	2:12:29 PM	Source @tag1@ - [HasTagGroupsKeyMacrosScripts.Chart1.Pen1] was unresolved because there is no TGD file...
5/25/2002	2:12:29 PM	@tag1@ - [HasTagGroupsKeyMacrosScripts.Chart1.Pen1.Source] was assumed as a DataSource, but it may not exist...
5/25/2002	2:12:42 PM	Source @tag2@ - [HasTagGroupsKeyMacrosScripts.Chart1.Pen2] was unresolved because there is no TGD file...
5/25/2002	2:12:42 PM	@tag2@ - [HasTagGroupsKeyMacrosScripts.Chart1.Pen2.Source] was assumed as a DataSource, but it may not exist...
5/25/2002	2:12:55 PM	Source @tag3@ - [HasTagGroupsKeyMacrosScripts.Chart1.Pen3] was unresolved because there is no TGD file...
5/25/2002	2:12:55 PM	@tag3@ - [HasTagGroupsKeyMacrosScripts.Chart1.Pen3.Source] was assumed as a DataSource, but it may not exist...
5/25/2002	2:13:09 PM	Source @tag4@ - [HasTagGroupsKeyMacrosScripts.Chart1.Pen4] was unresolved because there is no TGD file...
5/25/2002	2:13:09 PM	@tag4@ - [HasTagGroupsKeyMacrosScripts.Chart1.Pen4.Source] was assumed as a DataSource, but it may not exist...
5/25/2002	2:13:27 PM	Searching scripts...
5/25/2002	2:13:30 PM	**** Search completed on [HasTagGroupsKeyMacrosScripts]...

Status Trail

To automatically save the Status Trail to a .TXT file when the report generates, select the Save Status Trail option in the Report Settings tab of the Cross Reference Report Wizard. You can also modify the name and default location of the Status Trail file in the Report Settings tab.

Viewing a Search that Resolves Tags Using All Tag Group Files

If you select the Resolve Tags Using All Tag Group Files option in either the Quick Report dialog box or the Cross Reference Report Wizard, the Cross Reference Tool attempts to resolve any tag substitutions found in the selected files with all Tag Group Files that you have on your computer during the All Tags, One Tag, or Text search.

The following figure displays the results of an All Tags search with the Resolve Tags using All Tag Group Files option.

	Object	Property	Current Value	Resolved	Tag Group File
1	**** Search For: All Tags in Charts/Wit				
2	ChartsWithTagGroups.Chart1.Pen1	Source	@tag1@	[Possible DataSource found: Fix32.THISNODE.d11.F_C FILEFORCHARTWITHTAGGROUPS	
3				[Possible DataSource found: Fix32.DARKSIDE.d11.F_C FILEFORCHARTWITHTAGGROUPS	
4				Fix32.NODE.ablast1.F_CV	TAGABLASTONETOTEN.TGD
5				[Possible DataSource found: Fix32.THISNODE.ablast1	TAGABLASTONETOTENFQN.TGD
6				[Unresolved: A11]	TAGAIONETOTEN.TGD
7	ChartsWithTagGroups.Chart1.Pen2	Source	@tag2@	[Possible DataSource found: Fix32.THISNODE.aa1.F_ FILEFORCHARTWITHTAGGROUPS	
8				[Possible DataSource found: Fix32.DARKSIDE.HOLD11 FILEFORCHARTWITHTAGGROUPS	
9				Fix32.NODE.ablast2.F_CV	TAGABLASTONETOTEN.TGD
10				[Possible DataSource found: Fix32.THISNODE.ablast2	TAGABLASTONETOTENFQN.TGD
11				[Unresolved: A12]	TAGAIONETOTEN.TGD
12	ChartsWithTagGroups.Chart1.Pen3	Source	@tag3@	[Possible DataSource found: Fix32.THISNODE.ablast9	FILEFORCHARTWITHTAGGROUPS
13				[Possible DataSource found: Fix32.DARKSIDE.ablast9	FILEFORCHARTWITHTAGGROUPS
14				Fix32.NODE.ablast3.F_CV	TAGABLASTONETOTEN.TGD
15				[Possible DataSource found: Fix32.THISNODE.ablast3	TAGABLASTONETOTENFQN.TGD
16				[Unresolved: A13]	TAGAIONETOTEN.TGD
17	ChartsWithTagGroups.Chart1.Pen4	Source	@tag4@	Hist.THISNODE.ABLAST2.F_CV	FILEFORCHARTWITHTAGGROUPS
18				Hist.Darkside.ABLAST2.F_CV	FILEFORCHARTWITHTAGGROUPS
19				Fix32.NODE.ablast4.F_CV	TAGABLASTONETOTEN.TGD
20				[Possible DataSource found: Fix32.THISNODE.ablast4	TAGABLASTONETOTENFQN.TGD
21				[Unresolved: A14]	TAGAIONETOTEN.TGD

Search Results of Resolving Tags using All Tag Group Files

The Report Results section displays the object that references the tag, the property type of that tag, the tag substitution in the Current Value column, the resolved data source in the Resolved column, and the Tag Group File name that the substitution was found in.

The Cross Reference Tool attempts to resolve the substitution in all Tag Group files. Therefore, if the substitution does not exist in a Tag Group file, the Resolved column displays Unresolved, as shown in the previous figure.

Viewing a Search that Includes VBA Scripts

If you select the Include VBA Scripts in Search option in either the Quick Report or Cross Reference Report Wizard, the Cross Reference Tool searches through all scripts that are contained within the selected file(s) during an All tags, One Tag, or Text search.

The following figure displays the results of an All Tags search with the Include VBA Scripts in Search option.

	Object	Property	Current Value
6	HasTagGroupsKeyMacrosScripts.DataLink1.Format1	Source	Fix32.THISNODE.aa1.F_CV
7	HasTagGroupsKeyMacrosScripts.HasTagGroupsKeyMacrosScripts	ScriptSource	Line: 8 ToggleDigitalPoint "Fix32.THISNODE.D11.F_CV"
8	HasTagGroupsKeyMacrosScripts.HasTagGroupsKeyMacrosScripts	ScriptSource	Line: 12 MsgBox "The value of Fix32.THISNODE.ABLAST2.F_CV is "
9	HasTagGroupsKeyMacrosScripts.HasTagGroupsKeyMacrosScripts	ScriptSource	Line: 17 writevalue "33", "Fix32.THISNODE.AA1.F_CV"
10			

Search Results of Including VBA Scripts in Search

If the Cross Reference Tool finds a tag in a script (or the tag or text string that you searched for), the Object column displays the object associated with that script, the Property column displays ScriptSource, and the Current Value column displays the line number and line text of the script that the tag appears in.

NOTE: If the scripts contained in the files that you are searching include variables and those variable names are either custom alarm areas or tag names, the Cross Reference Tool displays the variable as a source.

Selecting Print Options and Printing a Report

The Print dialog box allows you to specify the print settings for a report. When a report completes and displays in the Report Results section of the Cross Reference Tool, you can access this dialog box on the File menu by clicking the Print button. This prints the report as it appears. You can also access this dialog box in the Cross Reference Report Wizard, on the Report Settings tab, by clicking the Advanced button.

The Print option in the Report Settings tab allows you to set these options for automatic printing once the report generates.

► To select print options and print a report:

1. Select a Print Range.
2. Click the Page Setup button to configure page settings. Refer to the [Selecting Page Options for Printing](#) section for more information.
3. Select any of the following Print Options:
 - Column Headers** - Prints column headers at the top of each page.
 - Row Headers** - Prints row headers on the left side of each page.
 - Grid Lines** - Prints spreadsheet grid lines.
 - Border** - Prints the spreadsheet border.
 - Data Cells Only** - Does not print empty cells beyond the last column and row containing data.
 - Color** - Prints colors in the spreadsheet as they appear on the screen.
 - Shadows** - Prints the shadow effect in the column and row headers.
4. Click the Printer Setup button to modify the current printer and printer options.
5. Optionally, click the Print Preview button to view how the Report will appear when printed. Select Close from the Print Preview screen to return to the Print dialog box.
6. Click OK.

If you accessed the Print dialog box from the print toolbar button, clicking OK prints the report. If you accessed the Print dialog box from the Cross Reference Report Wizard, clicking OK returns you to the wizard.

Selecting Page Options for Printing

The Page Setup dialog box allows you to:

- Select page orientation
- Enter or modify page margins
- Create or modify headers and footers
- Specify the Preview zoom setting

Enter any desired changes to the Page Setup dialog box and click OK to return to the Print dialog box.

Customizing Header or Footer Text

The Change Header and Footer Attributes dialog box, shown in the following figure, allows you to create and modify headers and footers for your printed report. To access the Change Header and Footer Attributes dialog box, click the Change Header and Footer Attributes button on the Page Setup dialog box.

To add a header or footer to your printed report, select either the Header Text or Footer text option from the Apply to section and enter your text in the appropriate column. For example, if you want your text to be centered, enter the text in the Center column.

The Cross Reference Tool also provides some pre-configured common header and footer options, including:

<Default Header> - Inserts the Report Title including the file name, date, and time.

<Time> - Inserts a time stamp (date and time).

<Page Number> - Inserts the current page number.

To select from these pre-configured strings, select a cell in the table and right-click it. The display toggles through the options.

Creating a Cross Reference Tool Report from the Command-Line

The Cross Reference Tool also allows you create reports or access the Cross Reference Tool Help while the Cross Reference Tool is closed. You can run the command-line options outlined in the following table from the Windows Run prompt.

Option Syntax	Description
/r	Creates a report with the CrossReference.ini settings. This runs the CrossReference.ini settings which were automatically saved when you last closed the Cross Reference Tool. If no CrossReference.ini is found, the report runs with the defaults.
/r	

NOTE: You must use the Cross Reference Report Wizard once before using the /r command. The Cross Reference Tool writes to the CrossReference.ini file when you create reports using the Cross Reference Report Wizard. Reports created using the Quick Report do not get written to the CrossReference.ini file.

The /r parameter allows you to set up an entire search in the

Cross Reference Report Wizard, navigate to the Apply and Go tab, and then click the Cancel button to cancel the search. After exiting the Cross Reference Tool, you could then run the cross-reference.exe /r command at any point to generate the report with the settings you had entered.

/? crossreference.exe Displays Cross Reference Tool Help.
/?

Cross Reference Tool Dialog Boxes

The Cross Reference Tool includes the following dialog boxes (listed in alphabetical order):

- [Change Header or Footer Attributes Dialog Box](#)
- [Cross Reference Report Wizard Dialog Box](#)
- [Page Setup Dialog Box](#)
- [Print Dialog Box](#)
- [Print Preview Screen](#)
- [Quick Report Dialog Box](#)
- [Quick Report Options Dialog Box](#)

Change Header or Footer Attributes Dialog Box

The Change Header or Footer Attributes dialog box displays the following items:

Header Text

Select this option to insert or modify text in the header.

Footer Text

Select this option to insert or modify text in the footer.

Text Reset Button

Resets all header or footer information.

Cross Reference Report Wizard Dialog Box

The Cross Reference Report Wizard dialog box displays the following items:

Search Settings Tab

Item	Description
------	-------------

All Tags	Select this option to search for all tags contained in the selected picture, schedule, User Global, or object.
One Tag	Select this option to search for a specific tag, tag substitution, or symbol in the selected picture, schedule, User Global, or object and all Tag Group Definition files. Enter a specific tag, tag substitution, or symbol in the Tag field or click Browse to open the Expression Editor.
Tag (edit box)	Enter a specific tag, tag substitution, or symbol in the Tag field or click Browse to open the Expression Builder. NOTE: Do not use a * wildcard in this field. Entering a wildcard returns a Search completed with no output error.
Text (button)	Select this option to search for text in object names, property names, and property values in the selected object. Enter a text string that would appear in the Object, Property, Property Value, Resolved, or Tag Group File name columns in the Text field. To return a list of all objects, leave <ALL> in the Text field.
Text (edit box)	Leave <ALL> or clear the field to return a list of all objects. To search for specific objects, enter a text string that would appear in the Object, Property, Property Value, Resolved, or Tag Group File name columns. NOTE: Do not use a * wildcard in this field. Entering a wildcard returns a Search completed with no output error.
Dynamos in Pictures	Select this option to search for Dynamo objects in selected pictures.
Pictures Containing Dynamos	Select this option to search for pictures that contain the selected Dynamo objects.
Resolve Tags using All Tag Group Files	If the selected picture or object contains Tag Group symbols, this option resolves those symbols by attempting to match the symbols with all tag group files and find all substitutions. This option is available for all search types.
Include VBA Scripts in Search	Select this option to allow the Cross Reference Tool to search for the tag(s) through scripts within the selected file. Both the All Tag and One Tag searches return the tag, if found. The Text search returns all lines of script.

Picture Files Tab

Item	Description
File Location Field	Click Browse to select another location to search for picture files. The iFIX PIC path is chosen by default: C:\Program Files (x86)\GE\iFIX\PIC.
Select All Button	Click this button to select all files listed in the Picture Files tab. During report generation, the Cross Reference Tool opens any of the selected files that were closed. When the Report finishes, those files are closed again.
Clear All Button	Click this button to clear any currently selected files.
Up Arrow Button	Select this option to move the selected file up in the arranged search order.
Down Arrow Button	Select this option to move the selected file down in the arranged search order.

Schedule Files Tab

Item	Description
File Location Field	Click Browse to select another location to search for schedule files. The iFIX PDB path is chosen by default: C:\Program Files (x86)\GE\iFIX\PDB.
Select All Button	Click this button to select all files listed in the Schedule Files tab. During report generation, the Cross Reference Tool opens any of the selected files that were closed. When the Report finishes, those files are closed again.
Clear All Button	Click this button to clear any currently selected files.
Up Arrow Button	Select this option to move the selected file up in the arranged search order.
Down Arrow Button	Select this option to move the selected file down in the arranged search order.

Dynamo Sets Tab

Item	Description
------	-------------

File Location Field	Click Browse to select another location to search for Dynamo files. The iFIX PIC path is chosen by default: C:\Program Files (x86)\GE\iFIX\PIC.
Select All Button	Click this button to select all files listed in the Dynamo Sets tab. During report generation, the Cross Reference Tool opens any of the selected files that were closed. When the Report finishes, those files are closed again.
Clear All Button	Click this button to clear any currently selected files.
Up Arrow Button	Select this option to move the selected file up in the arranged search order.
Down Arrow Button	Select this option to move the selected file down in the arranged search order.

Report Settings Tab

Item	Description
Save Report to File... (check box)	Select this option to automatically save the report when the report generation completes. Save the report to the default file and location listed, enter one directly into the Save Report to File field, or click Browse to locate a file or path. Available file types include *.csv, *.htm, *.xls, or *.tb2. NOTE: Microsoft Excel enforces a maximum row limit of 65536. If you try to save a report that exceeds this row limitation in Excel, Excel prompts you to continue or cancel. Be aware that rows exceeding that limitation may be lost if you select either option.
Save Report to File... (edit box)	Displays the location of the saved report file. To modify the default settings, enter a new location or file name directly into this field, or click the Browse (...) button to locate one. Available file types include *.csv, *.htm, *.xls, or *.tb2.
Save Status Trail... (check box)	Select this option to save the status trail information when the report completes. Save the report to the default file and location listed, enter one directly into the Save Status Trail field, or click Browse to locate a file or path. You can only save this file as a *.txt file.
Save Status Trail... (edit box)	Displays the location of the status trail file. To modify the default settings, enter a new location or file name directly into this field or click

box)	Browse to locate one. You can only save this file as a *.txt file.
Print Report	Select this option to automatically print the report when complete. Click Advanced to modify the Print settings.
Advanced Button	Click this button to open the Print dialog box and modify the settings for your print report.
Include Summary	Select this option to add a summary report to the end of the Cross Reference Report detailing the number of objects and tags searched. This option is not available for a One Tag search.
Automatically Resize Report Columns	Select this option to automatically resize the Report Results columns to accommodate the text.

Apply and Go Tab

Review your settings prior to generating a report.

Left/Right Buttons

Click the Left or Right button to scroll the row of tabs left or right.

Back/Next Buttons

Click the Back or Next button to navigate between tabs.

OK

Click the OK button to run the Cross Reference Report.

Page Setup Dialog Box

The Page Setup dialog box displays the following items:

Portrait

Prints a page that is taller than it is wide.

Landscape

Prints a page that is wider than it is tall.

Page Margins

Item	Description
Left	Enter the desired space between the left line of the page and the left line of the report.

Right	Enter the desired space between the right line of the page and the right line of the report with no indent.
Top	Enter the desired space between the top of the page and the first line of the report.
Bottom	Enter the desired space between the bottom line of the report and the bottom edge of the page.

Change Header and Footer Attributes

Click to open the Change Header and Footer dialog box, and configure headers and footers for your report. You can configure up to 9 lines of text for both the header and footer.

Range

Select the percent or number of pages that you would like to display in the Print Preview screen.

Print Dialog Box

The Print dialog box displays the following items:

Print Range

Item	Description
All	Prints the entire report. This is the only option available in Report Wizard configurations.
Selected Cells	Prints only the cells that you highlighted in the Cross Reference Tool screen.
Current Page	Prints only the current page of your report.
Pages	Prints a specific page range. Enter the desired start and end page ranges in the Pages fields.

Print Options

Item	Description
Column Headers	Prints the column headers at the top of each page.
Row Headers	Prints the row headers on the left side of each page.
Grid Lines	Prints the spreadsheet grid lines.

Border	Prints the spreadsheet border.
Data Cells Only	Select this option to ensure that the printer does not print empty cells beyond the last column and row containing data.
Screen Image Color	Prints the colors in the spreadsheet as they appear on the screen.
Shadows	Prints the shadow effect within the column and row headers.

Print Preview Screen

The Print Preview screen displays the following items:

Next

Allows you to browse through multiple report pages in the Print Preview dialog box.

Previous

Allows you to browse through multiple report pages in the Print Preview dialog box.

Zoom

Click to zoom in and out on the displayed report. You configure the zoom percentage in the Page Setup dialog box.

Print

Click to print the previewed report directly from the Print Preview dialog box.

Setup

Click to open the Page Setup dialog box and modify any Page Orientation, Page Margins, Header and Footer Display, or Preview Zoom options.

Close

Closes the Print Preview screen and returns you to the Print dialog box.

Quick Report Dialog Box

The Quick Report dialog box displays the following items:

All Tags

Select this option to search for all tags contained in the selected picture, schedule, User Global, or object.

One Tag (Button)

Select this option to search for a specific tag, tag substitution, or symbol in the selected picture, schedule, User Global, or object and all Tag Group Definition files.

Enter a specific tag, tag substitution, or symbol in the Tag field or click the Browse (...) button to open the Expression Editor.

Tag (Edit Box)

Enter a specific tag, tag substitution, or symbol in the Tag field or click the Browse (...) button to open the Expression Builder.

NOTE: Do not use a * wildcard in this field. Entering a wildcard returns a Search completed with no output error.

Text (Button)

Select this option to search for text in object names, property names, and property values in the selected object.

Enter a text string that would appear in the Object, Property, Property Value, Resolved, or Tag Group File name columns in the Text field. To return a list of all objects, leave <ALL> in the Text field.

Text (Edit Box)

Leave <ALL> or clear the field to return a list of all objects. To search for specific objects, enter a text string that would appear in the Object, Property, Property Value, Resolved, or Tag Group File name columns.

NOTE: Do not use a * wildcard in this field. Entering a wildcard returns a Search completed with no output error.

Dynamos

Select this option to search for Dynamo objects in a selected picture, or pictures containing Dynamo objects from a selected Dynamo Set. The type of object you select in the Object Tree determines which search is conducted.

Search

Generates the Quick Report based on the settings and selections you have chosen.

NOTE: You can also generate the Quick Report by double-clicking an object in the Object Tree.

Options

Opens the Quick Report Options dialog box.

Quick Report Options Dialog Box

The Quick Report Options dialog box displays the following items:

Resolve Tags Using All Tag Groups

If the selected picture or object contains Tag Group symbols, this option resolves those symbols by attempting to match the symbols with all tag group files and find all substitutions. This option is

available for all search types.

Include VBA Scripts in Search

Select this option to allow the Cross Reference Tool to search for the tag(s) through scripts within the selected file. Both the All Tag and One Tag searches return the tag, if found. The Text search returns all lines of script.

Include Summary

Select this option to add a summary report to the end of the Cross Reference Report detailing the number of objects and tags searched. This option is not available for a One Tag search.

Automatically Resize Report Columns

Select this option to automatically resize the Report Results columns to accommodate the text.

Append to Status Trail

Select this option to add any new tracking information to the existing status trail, if enabled. If disabled, each time a search runs, all previous tracking information is overwritten by the new status trail.

How Do I...

Click the appropriate link below for information about Cross Reference Tool's step-by-step procedures:

- [Generating a Report Using the Quick Report Dialog Box](#)
- [Generating a Report Using the Report Wizard](#)
- [Resolving Tags During a Search using Tag Group Files](#)
- [Searching through VBA Scripts](#)
- [Configuring Report Output Settings](#)

Generating a Cross Reference Report Using the Quick Report Dialog Box

► **To generate a Cross Reference Report using the Quick Report dialog box:**

1. In Classic view, from the WorkSpace toolbar, click the Cross Reference Tool button.
-Or-
In Ribbon view, on the Applications tab, in the Utilities group, click Utilities, and then click Cross Reference Tool.
2. On the File menu, click Quick Report.
By default, the Quick Report dialog box also appears when you open the Cross Reference Tool.
3. From the Object Tree, select a picture or object. To search through multiple pictures or objects, use the Report Wizard.

4. Choose to search for All Tags, One Tag, Text, or Dynamos in the selected object.
5. Click the Options button and select from the following search options from the Quick Report Options dialog box, if applicable:
 - **Resolve Tags using All Tag Group Files** - If the selected picture or object contains Tag Group symbols, this option resolves those symbols by attempting to match symbols with the Tag Group Definition file and find all substitutions. This option is available for all Search types.
 - **Include VBA Scripts in Search** - Allows the Cross Reference Tool to search through scripts within the selected file for the tag(s).
 - **Summary Report** - Includes a Summary Report at the end of the Cross Reference Report.
 - **Automatically Resize Report Columns** - Automatically resizes the columns in the Report Results section to accommodate the text.
 - **Append to Status Trail** - If enabled, the status trail adds any new tracking information to the existing status trail. If disabled, each time the report runs, all previous tracking information is overwritten by the new status trail.
6. Click OK to close the Quick Report Options dialog box.
7. Click Search to generate the report.

NOTE: You cannot access the iFIX WorkSpace while the Cross Reference Tool generates a report. Once the report completes, you will be able to access the iFIX WorkSpace again.

Generating a Cross Reference Report Using the Report Wizard

► To generate a Cross Reference Report using the Report Wizard:

1. In Classic view, from the WorkSpace toolbar, click the Cross Reference Tool button.
-Or-
In Ribbon view, on the Applications tab, in the Utilities group, click Utilities, and then click Cross Reference Tool.
2. On the Tool menu, click Report Wizard.
3. On the Search Settings tab, select what you would like to search for: All Tags, One Tag, Text, Dynamos in Pictures, or Pictures Containing Dynamos.
4. Select any of the Search Options, if appropriate.
5. Click Next to proceed to the Pictures Files Tab. This tab allows you to select multiple picture files to search through when the report generates. You can change the order of the search hierarchy by selecting the appropriate file and clicking the up and down arrow buttons.

NOTE: The Cross Reference Tool opens any closed files that are selected for report generation. When the report finishes, these files are closed again.

6. Click Next to proceed to the Schedule Files Tab. This tab allows you to select multiple schedule files to search through when the report generates. You can change the order of the search hierarchy by selecting the appropriate file and clicking the up and down arrow buttons.
7. Click Next to proceed to the Dynamo Sets Tab. This tab allows you to select multiple Dynamo files to search through when the report generates. You can change the order of the search hierarchy by selecting the appropriate file and clicking the up and down arrow buttons.
8. Click Next to proceed to the Report Settings tab. This tab allows you to select any appropriate Report Output options.
9. Optionally, select the Include Summary option. This option adds a summary report to the end of the report that details the number of objects and tags searched.
10. Optionally, select the Automatically Resize Report Columns option. Enabling this option automatically resizes the columns in the Report Results display and printed report to accommodate the text.
11. Click Next to proceed to the Apply and Go tab. This tab allows you to review all the settings you have configured throughout the wizard.

TIP: If you need to make any changes, click the Back button to return to the appropriate tab.

12. Click OK to generate the Report. You cannot access the iFIX WorkSpace while the Cross Reference Tool generates a report. Once the report completes, you will be able to access the iFIX WorkSpace again.

TIP: If the progress bar stops during report generation, an error message may have appeared in the background. Click in the Cross Reference Tool to move the Cross Reference Tool error dialog box to the foreground and acknowledge the error.

The output from the report displays in the Cross Reference Tool screen. If you configured Save Report to File or Print Report, those automatically occur. Once the results from the Report appear, you can also save or print the report manually from the toolbar buttons in the Cross Reference screen.

Resolving Tags During a Search Using All Tag Group Files

► To resolve tags during a search using all Tag Group Files:

1. In Classic view, from the WorkSpace toolbar, click the Cross Reference Tool button.
-Or-
In Ribbon view, on the Applications tab, in the Utilities group, click Utilities, and then click Cross Reference Tool.
2. From the File menu, select Quick Report.
-Or-
From the Tool menu, select Report Wizard.
3. In the Quick Report Options dialog or Search Options section, select the Resolve Tags using All Tag Group Files option.

If the selected picture or object contains Tag Group symbols, this option resolves those symbols by attempting to match symbols with the Tag Group Definition file and find all substitutions. The Resolve Tags using All Tag Group Files option is available for all Search types.

Searching Through VBA Scripts

► To search through VBA scripts:

1. In Classic view, from the WorkSpace toolbar, click the Cross Reference Tool button.
-Or-
In Ribbon view, on the Applications tab, in the Utilities group, click Utilities, and then click Cross Reference Tool.
2. From the File menu, select Quick Report.
-Or-
From the Tool menu, select Report Wizard.
3. In the Quick Report Options dialog or Search Options section, select the Include VBA Scripts in Search option. This option allows the Cross Reference Tool to search through scripts within the selected picture for the tag(s).

Configuring Report Output Settings

► To configure report output settings:

1. In Classic view, from the WorkSpace toolbar, click the Cross Reference Tool button.
-Or-
In Ribbon view, on the Applications tab, in the Utilities group, click Utilities, and then click Cross Reference Tool.
2. From the Tool menu, select the Report Wizard.
3. The Report Settings tab of the Cross Reference Report Wizard allows you to configure the following settings:

Report Output Settings

Option	Description
Save Report to File	Automatically saves the report when the report generation completes. Save the report to the default file and location listed, enter one directly into the Save Report to File field, or click the Browse (...) button to locate a file or path. Available file types are *.csv, *.htm, *.xls, or *.tb2.
Save Status Trail	Saves the status trail information when the report completes. Save the report to the default file and location listed, enter one directly into the Save Status Trail field, or click the Browse (...) button to

Print Report	locate a file or path. The available file type for this file is *.txt. Automatically prints the report when complete. Click the Advanced button to modify Print settings.
--------------	--

Report Option

Option	Description
Include Summary	Adds a summary report to the end of the report that details the number of objects, number of tags, and VBA project reference information.

View Option

Option	Description
Automatically Resize Report Column	Automatically resizes the columns in the Report results to accommodate the text.

Modifying Print Options

Click the appropriate link below for information on modifying print options:

- [Selecting Print Options and Printing a Report](#)
- [Selecting Page Options for Printing](#)
- [Customizing Your Header or Footer Text](#)

Selecting Print Options and Printing a Report

► To select print options and print a report:

1. In Classic view, from the WorkSpace toolbar, click the Cross Reference Tool button.
-Or-
In Ribbon view, on the Applications tab, in the Utilities group, click Utilities, and then click Cross Reference Tool.
2. Perform one of the following sets of steps:
 - In the Object Tree pane, select an object with a report that you want to print.
 - On the File menu, click Print.
 - Or -

- From the Tool menu, select Report Wizard.
 - From the Report Settings tab, select the Print Report option, and click the Advanced button.
2. Select a Print Range.
 3. Click Page Setup.
 4. Configure the page settings and click OK to return to the Print dialog box.
 5. Optionally, select any of the following Print Options:
 - **Column Headers** - Prints column headers at the top of each page.
 - **Row Headers** - Prints row headers on the left side of each page.
 - **Grid Lines** - Prints spreadsheet grid lines.
 - **Border** - Prints the spreadsheet border.
 - **Data Cells Only** - Does not print empty cells beyond the last column and row containing data.
 - **Screen Image Color** - Prints colors in the spreadsheet as they appear on the screen.
 - **Shadows** - Prints the shadow effect in the column and row headers.
 5. Optionally, click the Printer Setup button to modify the current printer and printer options.
 6. Click the Print Preview button to view how the Report will appear when printed.
 7. Click the Close button to return to the Print dialog box.
 8. Click OK.

If you accessed the Print dialog box from the Cross Reference Report Wizard, clicking OK returns you to the wizard. If you accessed the Print dialog box on File menu by clicking the Print option, clicking OK prints the report.

Selecting Page Options for Printing

► To select page options for printing:

1. In Classic view, from the Workspace toolbar, click the Cross Reference Tool button.
-Or-
In Ribbon view, on the Applications tab, in the Utilities group, click Utilities, and then click Cross Reference Tool.
2. Perform one of the following sets of steps:
 - In the Object Tree pane, select an object with a report that you want to print.
 - On the File menu, click Print.
 - Or-
 - From the Tool menu, select Report Wizard.
 - From the Report Settings tab, select the Print Report option, and click the Advanced button.

3. Click the Page Setup button.
TIP: You can also access the Page Setup dialog box by clicking the Setup button in the Print Preview screen.
4. Select either Portrait or Landscape for the Page Orientation.
5. Modify the Page Margins, if necessary.
6. Optionally, you can modify the Header and Footer text and display. To do this:
 - Click the Change Header and Footer Attributes button. .
 - Modify the Header and Footer text and display attributes you would like to change.
 - Click OK to save the changes and return to the Page Setup dialog box.
7. From the Preview Display Range drop-down menu, select a display setting. This setting determines the percentage of or number of pages displayed in the Print Preview screen.
8. Click OK to save changes and exit the Page Setup dialog box.

Customizing Header or Footer Text

► To customize header or footer text:

1. In Classic view, from the WorkSpace toolbar, click the Cross Reference Tool button.
 -Or-
 In Ribbon view, on the Applications tab, in the Utilities group, click Utilities, and then click Cross Reference Tool.
2. Perform one of the following sets of steps:
 - In the Object Tree pane, select an object with a report that you want to print.
 - On the File menu, click Print.
 - Or-
 - From the Tool menu, select Report Wizard.
 - From the Report Settings tab, select the Print Report option, and click the Advanced button.
3. Click the Page Setup button.
TIP: You can also access the Page Setup dialog box by clicking the Setup button in the Print Preview screen.
4. Click the Change Header and Footer Attributes button.
5. In the Apply to area, select the Header Text or Footer Text option.
6. Enter text in the appropriate column. For example, if you want text to be centered in the header, enter that text in the Center column.
 To select from some pre-configured common Header or Footer options, select a cell in the table and right-click it. The display toggles through a list of options including:
 - **<Default Header>** - Inserts the Report Title including the picture name, date, and time.
 - **<Time>** - Inserts a time stamp (date and time).

- **<Page Number>** - Inserts the current page number.
4. Optionally, click the Browse (...) button to modify the Font characteristics.
 5. Click OK to save your changes.

Creating Picture-specific Help Files

Picture-specific Help files are an efficient means of bringing more information to operators electronically without taking up valuable display space. This section describes how to add your own context-sensitive Help files to iFIX pictures. It includes the following sections:

- [Why Create Picture-specific Help Files?](#)
- [What's This? Help](#)
- [Adding Help to an iFIX Picture](#)
- [Creating the Help File](#)
- [Example: Creating a Picture-specific Help File](#)

Why Create Picture-specific Help Files?

There are several reasons why you might want to create a picture-specific Help file. For example, you may want to provide operators with concise answers to the following questions:

- What piece of equipment does this object represent?
- Where is this equipment located?
- What does this equipment control?
- Who is the manufacturer of this equipment?
- What are the Standard Operating Procedures (SOPs) for this picture?

In general, if you develop pictures that need to provide operators with equipment-specific information or sets of instructions, you should consider creating picture-specific Help files. For example, you are developing a picture that contains a pump. You can design the picture so that when operators click the pump and press SHIFT+F1, they receive a pop-up with information about the pump's manufacturer, voltage, amp rating, and horsepower.

Similarly, you can use picture-specific Help to develop training screens for new operators. If you were developing a training screen for the pump picture in the previous example, you could display Help pop-up windows containing such basic information as how to know when the pump is on or off, and when it is operating properly.


What's This? Help

Context-sensitive Help within a picture is in the form of What's This? Help. What's This? Help is a simple but highly useful form of Help that is designed to allow operators to quickly access Help inform-


ation and return to their work. To get What's This Help on an object within an iFIX picture in run mode, an operator presses SHIFT+F1, points and clicks on the object, and a brief explanation appears.

Example

In the following example, an operator has pressed SHIFT+F1 in a picture while in run mode. The mouse cursor changes to the What's This? Help pointer.



While in What's This? Help mode, operators can click any object in the picture (or even the picture itself) for a Help pop-up window on that object.



What's This? Help Design

The iFIX WorkSpace supports What's This? Help in two different types of compiled formats: Winhelp (*.hlp) and HTML Help (*.chm). A Winhelp .hlp file consists of the following source files: a project file, a topic file, and a map file. An HTML Help .chm file consists of the following source files: a project file, a topic file, a map file, and, an alias file.

The Help project file contains the Help file's project options, such as the source files to include and compile, the name of the Help file, and so forth. The topic file contains the content that you want to display in the pop-up window when you invoke What's This? Help. The map file is a header file that creates an association between the object that you want to provide Help for and the topic within the Help file. In HTML Help, the alias file works in tandem with the map file to associate the object name with a specific HTML file name (you can map one or more objects to the same file name). In Winhelp, the alias file is an optional tool to help you map the same topic content to multiple objects.

What's This? Help files are not difficult to create, since you only have to specify a couple of Help project options in order to build a useful context-sensitive Help file. The following table provides an overview of the minimum file types you need to create a What's This? Help project for use with iFIX.

Help Component	Winhelp	HTML Help
Project File	*.hpj	*.hnp
Content File	*.rtf	*.htm
Map File	*.h	*.h
Alias File (optional for Winhelp)	*.h	*.h

Adding Help to an iFIX Picture

First, specify the Help file name in the HelpFile property of your picture.

► To specify the Help file name:

1. Right-click a blank space within the *picture* and select Properties from the pop-up menu. The Properties dialog box appears with the name of the CFixPicture object as the active object.
2. In the HelpFile property cell, specify the name of the Help file that contains your context-sensitive topics. If you copied this file to a path other than the default path (for example: C:\Program Files (x86)\GE\iFIX, or C:\Program Files (x86)\GE\iFIX\PIC), you need to include the path to the help file as well.

Refer to the [Creating Picture-specific Help Files](#) section for examples on how to create the Help file.

3. Save the picture.

Next, assign a unique number, called a Help *context ID*, to each object in your picture that you want the operator to be able to get Help on.

► To assign a Help context ID:

1. Right-click each object in your picture (including the picture itself) for which you want to write a Help topic and select the Property Window command. The Properties window appears with the name of the selected object as the active object.
2. Set the ContextID property to the desired number. Remember that all context IDs within the same Help file *must* be unique. These values are used by the Help (Winhelp or HTML Help) application to correctly display the Help topic that is associated with the control. If two controls have the same context ID, the Help compiler displays an error message.

Finally, you need to make any object that you want an operator to be able to get Help on selectable.

► To make the object selectable so that the operator can view the help:

1. Right-click each object in your picture (including the picture itself) for which you want to write a Help topic and select the Property Window command. The Properties window appears with the name of the selected object as the active object.
2. Set the IsSelectable property to True.

Creating the Help File

This chapter discusses how to create the source files that comprise a picture-specific Help file, and also provides all of the steps required to successfully implement What's This? Help into iFIX pictures. It includes the following sections:

- [Requirements](#)
- [Creating a Topic File](#)
- [Creating a Map and Alias File](#)
- [Creating and Compiling a Project File](#)
- [Testing Your Help File](#)

Requirements

The requirements for creating a picture-specific What's This? Help files in iFIX are different for Winhelp and HTML Help. The sections below describe what each type of Help project requires.

HTML Help

- A text editor such as Notepad (to create or modify .htm and .h files).
- Microsoft® HTML Help Workshop, version 1.31 or higher . If you do not have Microsoft HTML Help Workshop, you can obtain the latest version from Microsoft at this location: <http://msdn.microsoft.com/library/default.asp?url=/library/en-us/htmlhelp/html/hwmicrosofthtmlhelpdownloads.asp>.

Creating a Topic File

When creating What's This? Help topic files, keep in mind that each topic **must** contain a unique *topic ID number*. The Help application needs a unique ID to display topics correctly. The steps below describe how to create a new topic whether you are using Winhelp or HTML Help.

► To create a simple Winhelp topic file (.rtf) in Microsoft Word:

1. Open Microsoft® Word.
2. Create a new document.
3. From the Insert menu, click Footnote. The Footnotes and End Note dialog box appears.
4. Select the Custom Mark option button, enter a pound sign (#) in the adjacent field, and click OK. The document window displays a footnote area.
5. In the footnote area, enter a unique context string to the right of the pound sign. Do not include spaces in the context string. One common method is to use underscores for more descriptive context strings, such as:
`water_pump_onoff_btn`
6. Click the Close button on the footnote pane to close the footnote area and return to a full-screen document window. (To view the footnote text again, double-click the footnote symbol at the top of the topic.)
7. To the right of the footnote symbol, on the main page, enter the information that you want to appear in the Help pop-up window.

NOTE: If you want to create more topics, repeat steps 2-5 for each topic. Additionally, add a manual page break between the topics. Each topic must appear on a separate page in the .RTF file. (In Microsoft Word, select Ctrl+Enter to create a manual page break between Help topics.)

8. Save the document as an .RTF file.

► **To create a simple HTML Help topic file (.htm) in a text editor:**

1. Open a text editor, such as Notepad.

NOTE: Optionally, you can use an HTML Editor such as Macromedia® HomeSite® or Microsoft® FrontPage®. This allows you to add more formatting to your HTML page, without requiring a lot of knowledge of how to use HTML tags.

2. Copy (CTRL+C) the following text to the Windows clipboard, and paste (CTRL+V) it into your text editor:

```
<HTML>
<HEAD>
<TITLE>Title 1</TITLE>
</HEAD>
<body>

<H1><font face="Arial">Title 1 </font> </H1>
<P><font face="Arial">Paragraph 1 </font> </P>
</BODY>
</HTML>
```

3. Enter a title (heading) in the two "Title 1" sections, shown bolded above.
4. Replace "Paragraph 1" (shown bolded above) with the rest of the information that you want to appear in the Help pop-up window.
5. Save the file.

Creating a Map and Alias File

In order for the Help application to display the correct Help pop-up window when you select SHIFT+F1 on a particular object, you must associate each unique topic ID name with its corresponding Help context ID number (defined in the property page of an object). This association, or *mapping*, is done in the MAP section of a Help project file. The easiest way to map these values is to create a header file (.h) in a text editor and include that header in the MAP section.

Additionally, in HTML Help only, the next step is to create an alias (.h) file to map the ID number to an .htm file name. This file name is included in the ALIAS section of the Help project.

NOTE: The alias file is optional in Winhelp. It's not an integral component for the context-sensitive Winhelp, like it is for HTML Help. If you use Robohelp to create your HTML Help files, your aliases are stored in a .ali file instead of the default .h file that Microsoft Help WorkShop uses.

► **To create a header file with the context IDs (for both Winhelp & HTML Help):**

1. Create a new text file in a text editor, such as Notepad.
2. In the text file, associate each topic ID name with an object's context ID number using the following format:

```
#define <topic ID name> <context ID number>
```

For example, in the iFIX WorkSpace, if you defined the HelpContextID property of the pump in the previous example as 1000, it would appear in the header file as:

```
#define water_pump_onoff_btn 1000
```

3. Continue to add these define statements, one per line, until all of your Context IDs have been added to the header file.
4. Save the file as a text-only file and provide it with an .h file name extension.

► **To create an alias file with additional ID mapping (for HTML Help only):**

1. Create a new text file in a text editor, such as Notepad.
2. In the text file, associate each topic ID name with an object's HTML file name using the following format:

```
<topic ID name>=<HTML File Name>
```

For example, if the HTML file name of the pump in the previous example is water_pump_onoff_btn.htm, it would appear in the alias file as:

```
water_pump_onoff_btn = water_pump_onoff_btn.htm
```

3. Continue to add these statements, one per line, until all of your topics IDs have an associated HTML file name.
4. Save the file as a text-only file and provide it with a .h file name extension.

Creating and Compiling a Project File

The final step is to create a Help project file that allows you to compile the map file(s) and topic files into one binary Help file. At a minimum, the steps you need to perform include:

- For **HTML Help**, you need to create a .hhp project file, add your .htm files with the content, add the .h file with the ID numbers, add your .h file with the aliases, define a default window type, and then save and compile the help project.

Creating and Compiling a Simple Help Project

► **To create and compile the project file in Winhelp:**

1. In Microsoft Help Workshop, from the File menu, click New. The New dialog box appears.
2. Select Help Project and click OK. The Project Name dialog box appears.
3. Type or browse for a path location, and enter a file name. Remember to use the same Help file name that you specified in the picture's Properties dialog box.
4. Click Save.
5. Click the Options button. The Options dialog box appears.
6. Select the General tab, and then, in the Help Title field, enter the name you want to appear in the title bar of your Help system.
7. Select the Files tab and click Change. The Topic Files dialog box appears.

8. Click the Add button and browse for the .rtf file that includes your Help topics. Click OK when you are complete.
9. From the Options dialog box, click OK.
10. Click the Map button. The Map dialog box appears.
11. Click Include. The Include File dialog box appears.
12. Browse and select the header file that includes all of your map statements. Click OK to exit the Include File dialog box, and click OK again to save your changes to the Map dialog box.
13. When you are ready to compile, click the Save and Compile button.

► **To create and compile the project file in HTML Help:**

1. In the Microsoft HTML Help Workshop, from the File menu, click New. The New dialog box appears.
2. In the list box, select Project and click OK. The New Project wizard appears.
3. Leave the Convert Winhelp Project check box cleared, and click Next. The New Project - Destination screen appears in the wizard.
4. In the edit box, enter the location and name that you want your Help project to use. Remember to use the same Help file name that you specified in the picture's Properties dialog box.
5. Click Next. The New Project - Existing Files screen appears in the wizard.
6. Select the HTML Files (.htm) check box, and click Next. The New Project - HTML Files screen appears in the wizard.
7. Click Add. The Open dialog box appears.
8. Browse to and select the HTML file(s) that you want to add to your project and click Open to return to the New Project - HTML Files screen.
9. Click Next. The New Project - Finish screen appears in the wizard.
10. Click Finish.
11. Click the HTML Help API Information button (the fourth button down, on the Project tab). The HTML Help API Information dialog box appears.
12. From the Map tab, click the Header File button. The Include File dialog box appears.
13. Enter or browse to select the path and file name of your .h file.
14. Click OK.
15. Click the Alias tab, and then click the Include button. The Include File dialog box appears.
16. Enter or browse to select the path and file name of your .ali file.
17. Click OK, and then click OK again to close and save the information in the HTML Help API Information dialog box. After you do that, you will notice two new sections in your help project: [ALIAS] and [MAP].
18. Click the Add/Modify Window Definitions button (the third button down, on the Project tab). The Add a New Window Type dialog box appears.
19. Enter a name for your default window. For example, you may want to create a window named *main*. After you do that, click OK. The Window Types dialog box appears.

20. Click the Position tab, and then click the Autosizer button. The Autosizer dialog box appears.
21. Drag the dialog box and its corners until the box appears where you want topics to display on your screen, by default, and click OK.
22. On the Window Types dialog box, click OK.
23. Click the Save All Files and Compile button (the bottom button on the Project tab).

How to Compile from a Command Line

As an alternative, you can also build and compile a Help system from the command line. If you are building more complex help systems, you may find the command line options helpful.

Use these steps if you already created a .hpj or .hhp file and just want to build and compile an updated version. From the DOS prompt or from within a batch file, use the following commands to build and compile your help:

► To build and compile Winhelp from the command line:

Type this command to build and compile a help file:

```
hcrtf -xn "C:\MyFolder\ProjectName.hpj"
```

In this example, replace **C:\Myfolder** with the path of your Help project and replace **ProjectName.hpj** with the name of your help project. The -xn option, in this example, builds the help file without displaying the Help Workshop window. Refer to the Microsoft Help Workshop online Help for detailed information on command-lines and options.

► To build and compile HTML Help from the command line:

Type this command to build and compile a help file:

```
hhc "C:\MyFolder\ProjectName.hhp"
```

In this example, replace **C:\Myfolder** with the path of your Help project and replace **ProjectName.hhp** with the name of your help project. Refer to the Microsoft HTML Help Workshop online Help for detailed information on command-lines and options.

Testing Your Help File

After you create the Help file, you should test it within your application.

► To test your Help file:

1. Copy your compiled Help file to the iFIX base path or PIC path. By default, this path is: C:\Program Files (x86)\GE\iFIX\PIC.
2. Follow the steps in the [Adding Help to an iFIX Picture](#) section to create a picture with context-sensitive help information, if you have not already created one.
3. In the iFIX WorkSpace run-time environment, open your Help-enabled picture.
4. Press SHIFT+F1. The cursor changes to a question mark pointer, indicating that it is in What's This? Help mode.

5. Click an object to which you assigned a Help context ID. The Help topic that you assigned to the object displays in a pop-up window. To dismiss the Help pop-up window, click anywhere on the screen.

Example: Creating a Picture-specific Help File

This section serves as a mini-tutorial that walks you through the complete process of creating a sample Help file and assigning it to a picture. For clarity, this example assumes that iFIX is installed to the C:\Program Files (x86)\GE\iFIX path and that you are developing your Help file in a working directory entitled C:\Program Files (x86)\GE\iFIX\HELP TEST.

HTML Help Example

► To create the HTML content in a text editor:

1. Open a text editor, such as Notepad.
2. Copy (CTRL+C) the following text to the Windows clipboard, and paste (CTRL+V) it into your text editor:

```
<HTML>
<HEAD>
<TITLE>Title 1</TITLE>
</HEAD>
<body>

<H1><font face="Arial">Title 1 </font> </H1>
<P><font face="Arial">Paragraph 1 </font> </P>
</BODY>
</HTML>
```

3. For the two "Title 1" sections, shown bolded above, enter "My Square."
4. Replace "Paragraph 1" (shown bolded above) with the following:
This is the Help topic for my square.
5. Save the file as SQUARE.htm in the C:\Program Files (x86)\GE\iFIX\HELP TEST folder.

► To assign the HTML Help file, context ID, and set the IsSelectable property:

1. In the iFIX WorkSpace configure mode, open a new iFIX picture.
2. Right-click the picture and select the Property Window command.
3. In the HelpFile property field, enter the following text:
square.chm
4. Click the Rectangle button on the Toolbox and draw a rectangle.
5. Right-click the rectangle and select the Property Window command.
6. In the ContextID property field, enter the following number:
1000
7. Set the IsSelectable property field to True.
8. Save the picture with the name HELPTEST. By default, iFIX saves the picture to this folder:
C:\Program Files (x86)\GE\iFIX\PIC.

► **To create a map file and alias file for HTML Help:**

1. Create a new text file in a text editor, such as Notepad.
2. In the text file, enter the following information:

```
#define square 1000
```

3. Save the file as SQUARE.h in the C:\Program Files (x86)\GE\iFIX\HELP TEST folder.
4. Create another new text file in a text editor, such as Notepad.
5. In the text file, enter the following information:

```
square = SQUARE.htm
```

6. Save the file as MYALIASES.h in the C:\Program Files (x86)\GE\iFIX\HELP TEST folder.

► **To create and build the HTML Help project file:**

1. In the Microsoft HTML Help Workshop, from the File menu, click New. The New dialog box appears.
2. In the list box, select Project and click OK. The New Project wizard appears.
3. Leave the Convert Winhelp Project check box cleared, and click Next. The New Project - Destination screen appears in the wizard.
4. In the edit box, enter the location and name that you want your Help project to use: C:\Program Files (x86)\GE\iFIX\HELP TEST\SQAURE.HHP
5. Click Next. The New Project - Existing Files screen appears in the wizard.
6. Select the HTML Files (.htm) check box, and click Next. The New Project - HTML Files screen appears in the wizard.
7. Click Add. The Open dialog box appears.
8. Browse to and select the following file: C:\Program Files (x86)\GE\iFIX\HELP TEST\SQAURE.htm. Click Open to return to the New Project - HTML Files screen.
9. Click Next. The New Project - Finish screen appears in the wizard.
10. Click Finish.
11. Click the HTML Help API Information button (the fourth button down, on the Project tab). The HTML Help API Information dialog box appears.
12. From the Map tab, click the Header File button. The Include File dialog box appears.
13. Click Browse to select the SQUARE.h file in your C:\Program Files (x86)\GE\iFIX\HELP TEST folder.
14. Click OK.
15. Click the Alias tab, and then click the Include button. The Include File dialog box appears.
16. Click Browse to select the MYALIASES.h file in the C:\Program Files (x86)\GE\iFIX\HELP TEST folder.
17. Click OK, and then click OK again to close and save the information in the HTML Help API Information dialog box. After you do that, you will notice two new sections in your help project: [ALIAS] and [MAP].

18. Click the Add/Modify Window Definitions button (the third button down, on the Project tab). The Add a New Window Type dialog box appears.
19. Enter a name for your default window. For example, you may want to create a window named *main*. After you do that, click OK. The Window Types dialog box appears.
20. Click the Position tab, and then click the Autosizer button. The Autosizer dialog box appears.
21. Drag the dialog box and its corners until the box appears where you want topics to display on your screen, by default, and click OK.
22. From the Window Types dialog box, click OK.
23. Click the Save All Files and Compile button (the bottom button on the Project tab).

► **To test the HTML Help file:**

1. Copy the SQUARE.CHM Help file to the C:\Program Files (x86)\GE\iFIX\PIC directory.
2. In the iFIX WorkSpace, open the HELPTEST picture.
3. If you are not already in run mode, on the WorkSpace menu, select Switch to Run (Classic view) or on the Home tab, in the WorkSpace group, click Switch to Run (Ribbon view).
4. Press SHIFT+F1. The cursor changes to a question mark pointer, indicating that it is in What's This? Help mode.
5. Click the rectangle. A Help pop-up window with the following text appears:

```
My Square
This is the Help topic for my square.
```

Customizing the System Tree

CAUTION: The instructions in this section are *strictly* intended for users who are creating their own custom installation DVD. We *strongly discourage* customizing your system tree under any other circumstances. This information is meant for advanced users only.

The iFIX WorkSpace system tree is the main tool for locating files and launching applications. It also provides access to your files and applications during the development of your pictures and schedules.

Depending on your needs, you may want to remove certain applications or folders or add new ones. For example, you may want to add a custom application to the system tree. On the other hand, if you did not purchase FIX SCADA support, you may want to delete the Database Manager application and I/O Drivers folder.

You can customize the system tree by modifying the text file SystemTree.CSV. This file defines the folders, applications, and files that appear when you start the iFIX WorkSpace. The file resides in the Local path.

CAUTION: Any changes made to the SystemTree.CSV file are done so at your own risk. All changes made to the system tree are permanent. We recommend making a backup copy of the SystemTree.CSV file that, if necessary, can be used to reset the system tree to its default settings.


NOTE: We recommend using Microsoft Excel when editing the SystemTree.CSV file. When saving the file in Excel, be sure to save it with a .CSV extension. If prompted to save the file in Microsoft Excel Workbook format, select No. If the SystemTree.CSV file is saved incorrectly, the system may not be usable. When editing the file, you must use a comma (,) as the list separator. Other characters, such as the international list

separator (;) cannot be used as the list separator in the SystemTree.CSV file. To view or modify the list separator setting on your system, double-click the Regional Settings icon in the Control Panel and click the Number tab.

The SystemTree.CSV file is divided into two sections. The top section defines the folders in the system tree and the bottom section defines the files. Within each of these sections are attributes that determine how a folder or file appears in the system tree. For example, the Key field contains the name of the file or folder as it appears in the system tree, and the Key Type field defines whether it is a folder or file. The remaining attributes have Entry and Value fields. The Entry field holds the name of the attribute and the Value field defines the corresponding attribute value. The attributes for folders and files are defined in the [Folder Attributes](#) and [File Attributes](#) tables.

NOTE: Although not all of the attributes in this file need to be defined, it is important to note that if the Entry field is completed for an attribute, the corresponding Value field must also be completed.

When you are ready to customize the SystemTree.CSV file, refer to the following figure for an overview of the required steps.



System Tree Customization Overview

Adding Folders to the System Tree

You can add folders to the system tree by editing the top section of the SystemTree.CSV file. Use the [Folder Attributes](#) table as a guide to editing the file.

► **To add a folder to the system tree:**

1. Open the SystemTree.CSV file located in the Local path.
2. Insert a row within the Define GE Folder section.
3. Enter the information for the folder in the attribute fields. For example, to add a folder named Events that contains event files enter the following (leave unused fields blank):

For the attribute...	Enter...
Description	Events
Folders	Folder
Extension Entry	Extension
Extension of the files for this folder	Evt
AutoFind Entry	AutoFind
Used to find, create, and populate this folder on startup	TRUE
Fix Path Entry	Fix Path
Default path for files in this folder	ALM_PATH

4. Save the file in the Local path with a .CSV extension.
5. Close the iFIX WorkSpace.
6. Click the Start button, and then click Run. In the Open field, type Regedit. Find HKEY_CLASSES_ROOT\FIX32\BrowseTree\LocalNode. Delete the LocalNode branch.
7. Click the Start button, and then click Run. In the Open field, type WorkSpace /regserver.
8. Click OK.
9. Restart the iFIX WorkSpace.

Folder definitions include the attributes in the following table.

Folder Attributes

The attribute...	Defines...
Description	The names of the folders in the system tree. By adding a new name, you add a new folder to the system tree. If you want the folder to appear inside another folder enter the complete path. For example, to add a folder called Drawings to the Pictures folder you would enter: Pictures\Drawings
Folders	Each entry as a folder and always has the value FOLDER.
AppKey	An entry that is reserved for future use and should be left blank.
Vendor of Folder	A company name. When you add a folder, enter the name of your company. Completing this attribute is optional.
ProgID of files in this folder	The program identification from the registry of the ActiveX documents residing in the folder. If the folder does not contain ActiveX documents, leave the ProgID blank.
Extension of the files for this folder	The file extension you want to associate with the folder. Completing this attribute is optional. If Used to find create and populate this folder on startup is set to TRUE, this attribute must be completed.
Used to find create and populate this folder	Whether the iFIX WorkSpace automatically displays the files with the specified extension. Setting Used to find create and populate this folder on startup to TRUE displays the files; entering FALSE or leaving the extension undefined creates an empty folder.

on startup	Typically, this attribute is set to TRUE. If set to TRUE, the Extension attribute must be completed.
Fix Path Entry	The path to each folder. When you add a folder, enter the complete path to it. This must be a FIX path.
Disable New Entry	Whether the New command on the folder's right mouse menu is grayed out or enabled. Entering TRUE grays out the command; setting the attribute to FALSE or leaving it undefined enables the command. Typically, this attribute is set to FALSE.
OpenExclusive	How the documents in the folder are opened. Entering TRUE opens the files exclusively for use in the iFIX WorkSpace; no other applications can read or write to these files. Setting the attribute to FALSE opens documents in a non-exclusive manner so that other applications can read or write the file. Typically, this attribute is set to FALSE.

Adding Files to the System Tree

You can add files to the system tree by editing the bottom section of the SystemTree.CSV file. Use the [File Attributes](#) table as a guide to editing the file.

► To add a file to the system tree:

1. Open the SystemTree.CSV file located in the Local path.
2. Add a folder named Event as described in the [Adding Folders to the System Tree](#) section.
3. Insert a row within the Define GE Files section of the file.
4. Enter the information for the file in the attribute fields. For example, to add a text file called Text File within the Events folder enter the following (leave unused fields blank):

For the attribute...	Enter...
Description	Events\Text File
Files	File
Fix Path Entry	Fix Path
Path of this file	ALM_ PATH\Test.txt
AutoLoad Entry	AutoLoad
Used to determine if this file should be opened on startup by the WorkSpace	FALSE

5. Save the file in the Local path with a .CSV extension.
6. Using Notepad, create a text file named Test.txt and save it in your C:\Program Files (x86)\GE\iFIX\Alm folder.
7. Close the iFIX WorkSpace.
8. Click the Start button, and then click Run. In the Open field, type Regedit. Find HKEY_CLASSES_ROOT\FIX32\BrowseTree\LocalNode. Delete the LocalNode branch.
9. Click the Start button, and then click Run. In the Open field, type WorkSpace /regserver.
10. Click OK.
11. Restart the iFIX WorkSpace.

Folder definitions include the attributes in the following table.

File Attributes

The attribute...	Defines...
Description	The names of the files that appear directly off the system tree root. By adding a new name, you add a new file to the system tree. If you want the file to appear inside a folder, enter the complete path. For example, to add a globals file called OEMGlobals to the Globals folder you would enter: Globals\OEMGlobals
Files	Each entry as a file and always has the value FILE.
AppKey	An entry that is reserved for future use and can be left blank.
Vendor of File	A company name. When you add a file, enter the name of your company. Completing this attribute is optional.
Path of this File	The complete path to each file. This must be a FIX path and the file name. If the file resides in an iFIX path, you can specify the path with a predefined alias, such as PDB_PATH or BASE_PATH. For example, if you are adding a globals file, enter PIC_PATH since all global files reside in the iFIX Picture path.
Used to determine if this file should be opened on startup by the Workspace	Whether the iFIX Workspace automatically opens the file on start-up. This attribute is set to TRUE for globals files only. Typically, this attribute is set to FALSE.
Hidden In Tree Entry	Whether the file is visible or hidden in the system tree. In general, you only want to set this attribute to TRUE for any non-modifiable globals file you add to the system tree. Typically, this attribute is set to FALSE.
Not In Collection Entry	Whether the file should be included in a collection. A <i>collection</i> is one or more open ActiveX documents. Typically, you want to include all files except non-modifiable (system) globals files in collections. Consequently, you enter TRUE for system globals files and FALSE for any other file. Typically, this attribute is set to FALSE.
Disable Close Entry	Whether the Close command on the file's right mouse menu is grayed out or enabled. Entering TRUE grays out the command; entering FALSE or leaving it undefined enables the command. Typically, this attribute is set to FALSE.
Disable Show Entry	Whether the Show command on the file's right mouse menu is grayed out or enabled. Entering TRUE grays out the command; entering FALSE or leaving it undefined enables the command. Typically, this attribute is set to FALSE.
Disable Save Entry	Whether the Save command on the file's right mouse menu is grayed out or enabled. Entering TRUE grays out the command; entering FALSE or leaving it undefined enables the command. Typically, this attribute is set to FALSE.
Type of file we are creating	Whether the file is a globals file. If it is not a globals file, enter DEFAULT. If it is, enter USER for user-defined globals files or SYSTEM for non-modifiable globals files. Typically, you supply system globals to prevent these value from being changed.
ProgID of this file	The program identification for your system and user globals files. This attribute is left blank or set to FIXGLOBALSSERVER.FIXGLOBALSSERVER.1
Determines if this file can be renamed and deleted	Whether the Rename and Delete commands on the file's right mouse menu is grayed out or enabled. Entering TRUE grays out the command; entering FALSE or leaving it undefined enables the command. This attribute is set according to user preference.

Deleting Folders and Files from the System Tree

You can delete folders and files from the system tree by editing the SystemTree.CSV file.

► **To delete a folder or file from the system tree:**

1. Open the SystemTree.CSV file located in the Local path.
2. Delete the row with the file or folder information you want to remove from the system tree.
3. Save the file in the Local path with a .CSV extension.
4. Close the iFIX WorkSpace.
5. Click the Start button, and then click Run. In the Open field, type Regedit. Find HKEY_CLASSES_ROOT\FIX32\BrowseTree\LocalNode. Delete the LocalNode branch.
6. Click the Start button, and then click Run. In the Open field, type WorkSpace /regserver.
7. Click OK.
8. Restart the iFIX WorkSpace.

Validating an Application

The Application Validator is a utility you use to verify the versions of an application's files, and to ensure that the files associated with the application have not changed. You can run the Application Validator with or without iFIX running.

To use the Application Validator, you first specify the Windows folders that you want to work with. After you specify the folders, you take an initial "snapshot" of the content. This "snapshot" is called a baseline. You can later compare this baseline snapshot to the same folder(s) at another date, or on a regular basis, to see if the contents of each folder have changed.

You will find the Application Validator utility most helpful, for instance, when you finish configuring your iFIX system. Once you configure iFIX, you can create a baseline of the iFIX folders and other ones associated with your process. You can monitor which files were changed since you created the baseline. So, if you ever run into problems, or want to go back to an original configuration, you can determine which files were changed or added, and you can manually rollback to that configuration. You can view these changes, as a summary or detailed report, in online or printed format.

Application Validator Basics

There is certain basic information you should know before using the Application Validator. This section contains information on the following:

- [Running the Application Validator](#)
- [Running With or Without iFIX](#)
- [Running in Demo Mode](#)
- [General Configuration for the Application Validator](#)
- [Working with Default Settings](#)
- [Using the Application Validator Toolbar and Quick Keys](#)

Running the Application Validator

You can run the Application Validator from the iFIX WorkSpace, the Windows Explorer, or the command line. Refer to the following table for more information.

Running the Application Validator

If you want to start the Application Validator from the...	Do this...
iFIX WorkSpace	Double-click the Application Validator icon in the system tree.
Windows Explorer	Double-click the AppValidator.exe file in the folder where you installed iFIX.
Command Line	From the DOS prompt type the AppValidator command with the desired command line options.

Refer to the [Command Line Options for the Application Validator](#) section for a full description of these options.

Running With or Without iFIX

You can use the Application Validator with or without iFIX. If you require that iFIX be running, open the AppValConfig.ini file in the folder where you installed iFIX and specify Yes for the RunningIFixIsRequired key in this file. If you require that iFIX is running, you can also specify whether iFIX Security is required by setting the EnabledSecurityIsRequired key to Yes in the AppValConfig.ini file.

For example, an AppValConfig.ini file with both options enabled appears as follows:

```
[Security]
RunningIFixIsRequired=Yes
EnabledSecurityIsRequired=Yes
```

If you use iFIX Security, you can modify your iFIX groups to allow the users in the designated groups to create baselines and/or have runtime access to the Application Validator. The iFIX application features name for these privileges are as follows:

- Application Validator - Creation of Baselines
- Application Validator - Run-time Access

For more information on iFIX security setup, refer to the [Defining and Assigning Security Privileges](#) in the Configuring Security Features manual.

Running in Demo Mode

Demo mode in the Application Validator restricts how you:

- Select directories
- Load application settings

- Save application settings
- Save Detail Reports

If you do not have an iFIX software license, you can only use the Application Validator when iFIX runs in Demo mode. The command line mode for the Application Validator is not available while iFIX is in Demo mode.

General Configuration for the Application Validator

To change the default options for the Application Validator, select Options from the Tools menu to open the Options dialog box. From this dialog box you can:

- Identify specific files or file types to exclude from the comparison.
- Define an application to run if differences are found when running the Application Validator from the command line.
- Specify an automatic report naming convention when running the Application Validator from the command line.

Working with Default Settings

Every time you shutdown the Application Validator, it updates the Default.avs file. The .AVS (Application Validator Settings) file contains the settings that you define in the Application Validator Options dialog box and includes a list of the folders to display in the main window. Each time you restart the Application Validator, it displays the settings from when you last used the Application Validator.

You later can define your own settings, save them in another file, and load them when you want to run specific reports. You could also use these custom .AVS files when running the Application Validator from the command line.

Using the Application Validator Toolbar and Quick Keys

All of the commands found on the menu bar have corresponding toolbar buttons. For each action that you can perform from the toolbar and menu bar, there are also quick keys that you can enter from the keyboard. The following table summarizes the functions of the toolbar buttons and key combinations that you can use.

Application Validator Toolbar Buttons

Use this...	To...
	Select directories for use in the Application Validator.
	Load predefined settings.
	Open the Save As dialog box to save settings.
	Open the Print Preview dialog box.

-  Open the Print dialog box to print the current screen.
-  Select all folders displayed in the main window.
-  Clear the check boxes for all folders selected in the main window.
-  Create a baseline file for each folder selected in the main window.
-  Create a baseline for a single folder.
-  Generate summary information indicating which folders contain changes. This information appears in the third column of the main window.
-  Generate a detailed summary report. This information appears in another window.
-  Open the Application Validator Options dialog box.
-  Show or hide the activity log window in the bottom half of the main window.
-  View information about the Application Validator version.

Ctrl+A Select all folders displayed in the main window.

Ctrl+B Create baseline files for each folder selected in the main window.

Ctrl+D Open the Select Directories dialog box from the main window, or if you are in the Comparison Detail Report window, this key combination allows you to display differences only.

Ctrl+G Create a baseline for a single folder. To create a baseline for one folder, only select the check box for that folder.

Ctrl+L Open the Open dialog box to load predefined settings.

Ctrl+M Generate summary information indicating which folders contain changes. This information appears in the third column of the main window.

Ctrl+O Open the Application Validator Options dialog box.

Ctrl+P Open the Print dialog box to print the current screen.

Ctrl+S Open the Save As dialog box to save the application settings or detailed report.

Ctrl+T Generate a detailed summary report. This information appears in another window.

Ctrl+U Clear the check boxes for all folders selected in the main window.

Types of Reports from the Application Validator

There are two types of reports that you can run from the Application Validator:

- [Summary Report](#)
- [Comparison Detail Report](#)

You can view both these reports in online or printed format.

Summary Report

When you run a Summary Report, it displays in the main window of the Application Validator. A status for each folder appears in the third column of the main window, indicating if differences were found or if

the files in the folder were identical to the original baseline. For instance, the Compare Status field for the folder could be identified as Identical, Differences Found, or Missing a Baseline.

The following figure shows an example of a Summary Report as it appears in the main window of the Application Validator. Notice the Compare Status column of the far right of the window that includes the Summary Report information.

Directory	Baseline Status	Compare Status
✓ C:\Program Files\Proficy\Proficy iFIX	Baseline Exists	Differences Found
✓ C:\Program Files\Proficy\Proficy iFIX\ALM	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\APP	Baseline Exists	Differences Found
✓ C:\Program Files\Proficy\Proficy iFIX\APP\CustomUserDir	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\Config Files Backup	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\HTR	Baseline Exists	Differences Found
✓ C:\Program Files\Proficy\Proficy iFIX\HTRDATA	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\HTRDATA\FIX	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\HTRDATA\SCADA01	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\LOCAL	Baseline Exists	Differences Found
✓ C:\Program Files\Proficy\Proficy iFIX\NLS	Baseline Exists	Differences Found
✓ C:\Program Files\Proficy\Proficy iFIX\NDB	Baseline Exists	Differences Found
✓ C:\Program Files\Proficy\Proficy iFIX\NIC	Baseline Exists	Differences Found
✓ C:\Program Files\Proficy\Proficy iFIX\NIC\Backup	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\NIC\TagStatus	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\ProjectBackup	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\RCC	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\RDM	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\Resources	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\SampleSystem	Baseline Exists	Identical
✓ C:\Program Files\Proficy\Proficy iFIX\SampleSystem\Application	Baseline Exists	Differences Found

For Help, press F1 Row Count: 34

Example of the Summary Report from the Main Window

Comparison Detail Report

When you run a Comparison Detail Report, it displays in a new window. A Comparison Detail Report describes whether a file in any folder was modified, added, removed, or unchanged. Unlike the Summary Report that details the changes in complete folders, the Comparison Detail Report describes the changes for individual files.

The following figure shows an example of a Comparison Detail Report. Notice the Status column (the second column from the left) that displays whether the file is Identical, Different, Added to Current (New), or Deleted from the Current folder.

File	Status	Baseline Size	Current Size	Baseline Modified Date	Current Modified Date
C:\Program Files\Proficy\Proficy\FDK					
APPVALIDATOR.log	Added To Current	N/A	1017	N/A	9/23/2005 7:57:18 PM
C:\Program Files\Proficy\Proficy\FDK\ALM					
C:\Program Files\Proficy\Proficy\FDK\APP					
C:\Program Files\Proficy\Proficy\FDK\APP\CustomUserDir					
C:\Program Files\Proficy\Proficy\FDK\Config Files Backup					
C:\Program Files\Proficy\Proficy\FDK\HTR					
C:\Program Files\Proficy\Proficy\FDK\HTRDATA					
C:\Program Files\Proficy\Proficy\FDK\HTRDATA\FDK					
C:\Program Files\Proficy\Proficy\FDK\HTRDATA\SCADA01					
C:\Program Files\Proficy\Proficy\FDK\LOCAL					
CAD Toolbar.tbx	Different	33792	33792	9/23/2005 5:17:15 PM	9/23/2005 8:15:01 PM
FdUserPreferences.ini	Different	5005	5190	9/23/2005 7:52:33 PM	9/23/2005 8:15:02 PM
Toolbox.tbx	Different	142848	142336	9/23/2005 5:17:15 PM	9/23/2005 8:15:01 PM
Utilities.tbx	Different	88064	88064	9/23/2005 5:17:15 PM	9/23/2005 8:15:01 PM
WORKSPACE.ini	Different	677	665	9/23/2005 7:32:42 PM	9/23/2005 8:15:02 PM
C:\Program Files\Proficy\Proficy\FDK\NLS					
C:\Program Files\Proficy\Proficy\FDK\FDB					
ShellReport.evs	Different	9728	8704	9/23/2005 7:18:30 PM	9/23/2005 8:15:00 PM
C:\Program Files\Proficy\Proficy\FDK\TRAC					

Example of Comparison Detail Report Window

Viewing Only the Files that Changed

In the Comparison Detail Report, you can reduce the number of files included in the list by ignoring identical files. If you want to view only the files that changed, select the Differences Only option from the View menu in the Comparison Detail Report window.

Saving the Comparison Detail Report

In addition, you can save the Comparison Detail Report to a .CSV or .TXT file. Select Save from the File menu in the main window to open the Save dialog box, from which you can select a comma-delimited format (.CSV) or text format (.TXT) from the drop-down list.

General Overview of Steps for Using the Application Validator

Once you understand and configure the [Application Validator Basics](#), you can begin to use Application Validator with your application. The steps are generally the same for each application.

► To use the Application Validator:

1. Select the folders you want to work with.
2. Generate a baseline for the selected directory or directories.

NOTE: The Application Validator cannot create a baseline for files that are open with exclusive rights. For instance, if you attempt to create a baseline of the root drive C:/, where the Pagefile.sys is open with exclusive rights from the operating system, the baseline will fail. The operating system has full

control over that file, and no one else, not even the administrator nor the user creating the baseline, has rights to open it.

3. At a later time when you want to validate the files, run a report:
 - Summary Report.
 - Comparison Detail Report.

Command Line Options for the Application Validator

The syntax for the Application Validator command line is as follows:

```
AppValidator /ConfigFile:"C:\FullPath\Settings.avs"  
            | /Directory:"single directory name"  
[/CreateBaseline | /CB]  
[/OverWrite]  
[/PrintSingleBaseline | /PSB]  
[/PrintComparisonSummary | /PCS]  
[/PrintComparisonDetail | /PCD]  
[/SaveComparisonDetail:"Full path of output file"  
            | /SCD:"Full path of output file"]  
[/CSV]  
[/DifferencesOnly | /DO]  
[/? | /Help]
```

Notes on the Syntax

- The brackets ([]) indicate that a parameter is optional. The brackets are not part of a command; if a bracketed option is desired, only type the text that is inside the brackets, and not the brackets themselves.
- The pipe bar (|) indicates separate items in a group that you can choose from. For instance you can use the /CreateBaseline or the /CB argument with the AppValidator command, and, in this case, both perform the same task.
- Italics are used to represent the information that the user must supply to run the command. The information in italics is not typed exactly as it appears. Instead, the user enters the information specific to the italicized expression.

Descriptions of Optional Arguments

The following table outlines the optional arguments. If an abbreviation is available, that is listed instead of the full argument name. For instance, the /CB argument is listed instead of the /CreateBaseline argument, but either could be used.

Application Validator Command Line Options(Sheet 1 of 2)	
Argument	Description
/CB	Creates baseline files for the specified directories and folders.
/OverWrite	Overwrites any existing baseline files. (Used with the /CB argument only.)
/PSB	Prints the existing baseline for the specified folder.
/PCS	Prints the Summary Report for the specified folders.
/PCD	Prints the Comparison Detail Report for the specified folders.
/SCD:"Full Path	Saves a copy of the Comparison Detail Report for the specified folders. If you do not

<i>Output File"</i>	use the /CSV argument, the file is saved as a .TXT file.
/CSV	Specifies that the Comparison Detail Report be saved in Comma Separated Value (CSV) format. (Used with the /SCD option only.)
/DO	Specifies that you only want to display the files with changes in the Comparison Detail Report. (Used with the /SCD option only.)
/?	Displays the Help for the command line options.

Command Line Options You Can Define in the GUI

In addition to the options that you can specify on the command line, some options must be set from within the Application Validator user interface (non-command line version). These options include:

- Using an automatic report naming convention when running the Application Validator from the command line.
- Define an application to run if differences are found when running the Application Validator from the command line.

Command Line Errors

You may encounter errors caused when an invalid command line parameter is passed to the Application Validator. Errors are logged to the AppValidator.log file in the iFIX folder.

Understanding Auditing for the Application Validator

You can configure the Application Validator to audit all user actions. Once configured, each time you perform an action, such as create a baseline, run a baseline summary report, or run a comparison report, an audit message is sent to the iFIX alarm system. This message is then recorded as part of the standard iFIX audit trail.

► To enable audited actions in the Application Validator:

1. Open the AppValConfig.ini file and enable both options in this .ini file by entering Yes for both settings:

```
RunningIFixIsRequired=Yes
EnabledSecurityIsRequired=Yes
```

2. Enable the Alarm ODBC Service and configure your relational database to store the audit messages in the ODBC alarm table.

For more information on the AppValConfig.ini, refer to the [Understanding the AppValConfig.ini File and Auditing](#) section in this chapter. For more information on enabling and configuring the Alarm ODBC Service, refer to [Configuring the Alarm ODBC Service](#) section in the Implementing Alarms and Messages manual.

Understanding the AppValConfig.ini File and Auditing

The AppValConfig.ini file specifies whether iFIX must be running in order to start the Application Validator and if iFIX security applies. This file is located in the iFIX folder (the folder where you installed iFIX). Both options must be enabled if you want to audit user actions in the Application Validator. With both options enabled, the Application Validator user and node can be tracked in the standard iFIX audit trail.

► To configure the AppValConfig.ini file for auditing purposes:

1. Open the AppValConfig.ini in Notepad or another text editor.
2. Make that both settings in this file are set to Yes:

```
[Security]
RunningIFixIsRequired=Yes
EnabledSecurityIsRequired=Yes
```

NOTE: If you set EnabledSecurityIsRequired to Yes, then the Application Validator only runs when Security is Enabled within iFIX. If you set EnabledSecurityIsRequired to No, then iFIX Security does not have to be enabled in order to run the Application Validator.

3. Save the file into the iFIX folder (the same location where you installed iFIX).
4. Restart the Application Validator.

Viewing the Audited Messages


Use your database tools or VisiconX to view the iFIX audit trail. For information on Microsoft SQL Server or Oracle database tools, refer to your manufacturer's documentation. For more information on VisiconX, refer to the [Using VisiconX](#) manual.

iFIX alarm destinations such as the Alarm File and Alarm Printer also get these audit messages. For information on configuring these alarm locations, refer to the [Configuring Alarms](#) chapter in the Implementing Alarms and Messages manual.

NOTE: The Alarm History window only displays the most recent 500 messages; it is not a complete list of messages, and therefore, not an audit trail.

Sample Audit Message from the Application Validator

The following figure displays a sample of the audit message sent to the iFIX alarm system. Notice that the timestamp, iFIX node name, node name where the user was logged in, plus the name of iFIX operator who performed the action are all included with the audit message.



Format of Audit Message Sent to iFIX Alarm System

List of Audit Messages from the Application Validator

The following list describes the audit messages associated with the Application Validator. These messages describe the events that can occur (to the operator) when running the Application Validator:

- Application Validator - Baseline File has been tampered with!
- Application Validator - Command-line: Create Baseline
- Application Validator - Command-line: Print Comparison Detail
- Application Validator - Command-line: Print Comparison Summary
- Application Validator - Command-line: Print Single Baseline
- Application Validator - Command-line: Save Comparison Detail
- Application Validator - Create Baseline
- Application Validator - Error retrieving security user
- Application Validator - Error with Compare Directory: %s
- Application Validator - Error with Fill Baseline Detail: Checksum difference for baseline file: [%s]. %s
- Application Validator - Error with Fill Baseline Detail: Failed to read encrypted baseline file: [%s]. %s
- Application Validator - Failed to start Application: %s
- Application Validator - iFIX isn't running
- Application Validator - Insufficient Security Rights
- Application Validator - Invalid Security Feature
- Application Validator - Print Baseline Status/Comparison Summary
- Application Validator - Report Comparison Detail
- Application Validator - Report Comparison Summary
- Application Validator - Report Printed
- Application Validator - Report Saved
- Application Validator - Report Single Baseline
- Application Validator - Security not enabled
- Application Validator - User not logged in

NOTE: The %s in these messages is replaced with the actual the directory name when the message appears.


Activity Log in the Main Window

The activity log displays informational messages on the actions performed in the Application Validator since you enabled logging. This log displays the most recent actions first in the list, at the top of the window. By scrolling down, you can review previous actions.

The activity log may be helpful when trying to diagnose problems using the Application Validator.

NOTE: The activity log is not saved when you stop the Application Validator or shut it down.

The following figure shows an example of the Application Validator main window with the Log window displayed.



Application Validator with Log Window Displayed

Best Practices

Some best practices to keep in mind when using the Application Validator include the following:

- Specify that iFIX be running in order to start the Application Validator and that iFIX security be enabled in the AppValConfig.ini file, if you want to use auditing.
- If using iFIX security, limit the creation of baselines to a specified set of users. For each designated user in the Security Configuration tool, select the Application Validator - Creation of Baselines feature from the Application Feature Selection dialog box.

NOTE: Depending upon your security requirements, you probably can allow run-time access to the Application Validator (Application Validator - Run-time Access feature) more liberally.

For more information on iFIX security setup, refer to the [Defining and Assigning Security Privileges](#) in the Configuring Security Features manual.

Application Validator Dialog Boxes

The Application Validator includes the following dialog boxes:

- [Application Validator Options Dialog Box](#)
- [Select Directories Dialog Box](#)

Application Validator Options Dialog Box

The Application Validator Options Dialog Box consists of three tabs:

Exclusion List Tab

Item	Description
Exclusion List	Displays the files excluded when you compare the folders with the baseline.
Excluded File Filter	Enter the file or file name mask that you want to exclude from the folder comparison. Click Add to add it to the file exclusion list. For file name masks, you can use standard Windows wildcard characters. For instance, use the * symbol to represent multiple unknown characters in a file name. Use the ? symbol for a single unknown character in a file name.
Exclusion List Text Box	Enter the file or file name mask that you want to exclude from the folder comparison. Click Add to add it to the file exclusion list. For file name masks, you can use standard Windows wildcard characters. For instance, use the * symbol to represent multiple unknown characters in a file name. Use the ? symbol for a single unknown character in a file name.
Add	Click to add the file or file name mask, entered in the field above, to the file exclusion list.
Remove	Click to delete the selected file or file mask from the file exclusion list.

Application Execution Tab

Field Name	Description
Enable Application Execution	Select this check box if you want to run an executable file when differences are found between the baseline and the current folder versions, when running the Application Validator from the command line.
Application	Enter the name and location of the file that you want to run (when the Application Validator runs from the command line) and finds differences.
Browse	Click to browse for a file.

Auto Report Naming Tab

Field Name	Description
------------	-------------

Enable Auto Report Naming	Select this check box if you want to use a predefined name for all reports generated from the command line with the Application Validator.
Report Name	Enter the name for the auto-generated report file. If you select the Auto Increment option, a number is added to the end of this name each time a new report is run from the command line.
Directory	Enter the name and location of the folder to which you want to save the detailed summary reports generated when you run the Application Validator from the command line.
Browse (...)	Click to browse for a folder to which you want to save the report.
Prefix	Enter the name for the auto-generated report file. If you select the Auto Increment option, a number is added to the end of this name each time a new report is run from the command line.
Auto Increment	Select this check box if you want to individually number each report file, instead of overwriting the original file each time you run a new report.

How Do I...

Refer to one of the following sections for steps on how to use the Application Validator:

- [Configuring Settings](#)
- [Creating Baselines](#)
- [Working with Reports](#)
- [Working with the Command Line](#)
- [Working with iFIX](#)

Working with iFIX

To use the Application Validator with iFIX, you should be aware of the following operations:

- [Auditing the Actions Performed in the Application Validator](#)
- [Requiring that iFIX to be Running in Order to Start the Application Validator](#)

Troubleshooting

You can troubleshoot the Application Validator by:

- [Viewing the Error Log](#)
- [Displaying Informational Log Messages for the Current Session](#)

Customizing the iFIX Installation

The following sections provide information for users who want to create a custom iFIX installation for use on either a DVD or over a network:

- [Types of Users Who Create Custom Install Programs](#)
- [Creating a Custom iFIX Install for a DVD or Network](#)
- [Running a Quiet Install](#)
- [Modifying the Default Behavior of the iFIX Install](#)
- [Including Additional iFIX Project Files in the Install](#)
- [Installing Software Improvement Modules \(SIMs\) with iFIX](#)
- [Including Additional Third-Party Software in the Install](#)
- [Customizing the Install Splash Screen](#)
- [Rebranding Install Graphics](#)
- [Rebranding Install Text](#)
- [Rebranding the iFIX DVD Booklet and Tray Card](#)
- [Rebranding Other Parts of the iFIX Product](#)
- [Deploying the iFIX Install Setup.exe Command Line Options](#)
- [INI Files Used by the iFIX Install](#)
- [Language Codes Used by the iFIX Install Program](#)

IMPORTANT: If you want to create and/or produce rebranded iFIX DVDs for use other than internal to your company, you must have license agreement and permission from GE to do so. Contact GE for more information.

Types of Users Who Create Custom Install Programs

With a customized iFIX install program, you can change the default install settings, modify the components included with the install, or change the appearance of the install. The following types of users may be interested in custom iFIX install programs:

- [The Administrator](#) (Admin)
- [The System Integrator](#) (SI)
- [The Original Equipment Manufacturer](#) (OEM)

Depending on the type of user you are, your requirements for creating a custom iFIX install program will differ. The following sections describe the types of actions each type of user may want to do with their custom iFIX install program.

The Administrator

As an Administrator, you may want to create a custom iFIX install that includes:

- A quiet install of the iFIX product. For more information, refer to the [Running a Quiet Install](#) section.
- Modification of the default behavior of the install, such as a different install path for the iFIX product, or a different name for the PIC or PDB folders. For more information, refer to the [Modifying the Default Behavior of the iFIX Install](#) section.

IMPORTANT: If you want to create and/or produce custom iFIX DVDs for use other than internal to your company, you must have license agreement and permission from GE to do so. Contact GE for more information.

The System Integrator

As a system integrator, you may want to can create a custom iFIX install that includes:

- A quiet install of the iFIX product. For more information, refer to the [Running a Quiet Install](#) section.
- Modification of the default behavior of the install, such as a different install path for the iFIX product, or a different name for the PIC or PDB folders. For more information, refer to the [Modifying the Default Behavior of the iFIX Install](#) section.
- Additional files, such as customized project, database, or alarming files. For more information, refer to the [Including Additional iFIX Project Files in the Install](#) section.
- Software Improvement Modules (SIMs) that have been released after the initial release of the iFIX product. You can also choose to install these SIMs quietly. For more information, refer to the [Installing Software Improvement Modules \(SIMs\) with iFIX](#) section.
- Additional third-party software, specific to your organization or site. For more information, refer to the [Including Additional Third-Party Software in the Install](#) section.
- A different initial graphic (splash screen) that displays when you first load the iFIX product install DVD. For more information, refer to the [Customizing the Install Splash Screen](#) section.

IMPORTANT: If you want to create and/or produce custom iFIX DVDs for use other than internal to your company, you must have license agreement and permission from GE to do so. Contact GE for more information.

The Original Equipment Manufacturer

As an Original Equipment Manufacturer (OEM), you may want to can create a custom iFIX install that includes:

- A quiet install of the iFIX product. For more information, refer to the [Running a Quiet Install](#) section.
- Modification of the default behavior of the install, such as a different install path for the iFIX product, or a different name for the PIC or PDB folders. For more information, refer to the [Modifying the Default Behavior of the iFIX Install](#) section.

- Additional files, such as customized project, database, or alarming files. For more information, refer to the [Including Additional iFIX Project Files in the Install](#) section.
- Software Improvement Modules (SIMs) that have been released after the initial release of the iFIX product. You can also choose to install these SIMs quietly. For more information, refer to the [Installing Software Improvement Modules \(SIMs\) with iFIX](#) section.
- Additional third-party software, specific to your organization or site. For more information, refer to the [Including Additional Third-Party Software in the Install](#) section.
- A different initial graphic (splash screen) that displays when you first load the iFIX product install DVD. For more information, refer to the [Customizing the Install Splash Screen](#) section.
- Rebranded graphics that appear when the install program runs, after the splash screen. For more information, refer to the [Rebranding Install Graphics](#) section.
- Rebranded text that appears in the install. For more information, refer to the [Rebranding Install Text](#) section.
- Rebranded license agreement. For more information, refer to the [Rebranding the License Agreement](#) section.
- Rebranded DVD booklet and tray card. For more information, refer to the [Rebranding the iFIX DVD Booklet and Tray Card](#) section.
- Rebranded product items. For more information, refer to the [Rebranding Other Parts of the iFIX Product](#) section.

IMPORTANT: As an OEM, you must have license agreement and permission from GE to create rebranded installations. Additionally, you will need a copy of the iFIX NLS Toolkit for the InstallShield Stand-Alone builder, which you need to recompress the install program if you choose to modify the graphics, text, or license in the actual installer. With the NLS Toolkit, you can also rebrand other parts of the iFIX application. Contact GE for more information.

Creating a Custom iFIX Install for a DVD or Network

You can create a customized iFIX install (for use on a DVD or a network) for use at your site, assuming that a license is available for each individual install. The steps that follow describe how to produce a custom iFIX install program.

IMPORTANT: If you want to create and/or produce rebranded iFIX DVDs for use other than internal to your company, you must have license agreement and permission from GE to do so. Contact GE for more information.

► To create a customized install program:

1. In Windows Explorer, create a folder on your local drive named *dvdimage*. For example: C:\dvdimage. You must have at least 400 MB of free space available.
2. Obtain an iFIX product DVD, for the version you want to install or upgrade.
3. Copy all of the files and folders from the iFIX DVD, and paste them to your *dvdimage* folder.
4. Perform the steps for the options you want to customize.

► **To create a customized product DVD:**

1. After you finish your customizations, copy all of the files and folders from your *dvdimage* folder to a new DVD using your DVD writing software.
2. Test the new DVD. Make sure that iFIX installs properly, and that all your customizations appear correctly.

After all of your tests pass, you can use this DVD internally on other computers, or supply it to customers who use your rebranded, customized software (if you have a license from GE to do so).

► **To create a customized network install in preparation for deployment:**

1. After you finish your customizations, copy all of the files and folders from your *dvdimage* folder to a network drive that you want to run the install from.
2. Test the network install. Make sure that iFIX installs properly, and that all your customizations appear correctly.

After all of your network install tests pass, you can use this network installation on other computers, or supply it to customers who use your rebranded, customized software (if you have a license from GE to do so).

Running a Quiet Install

A quiet install is useful if you want to create an iFIX install that is non-interactive and uses a set of pre-defined installation options. With a non-interactive install, you can ensure that iFIX installs or upgrades to the latest release the same way on each computer you run the install on. If you are installing or upgrading iFIX on many systems and you want every system to install the same way, a quiet install program helps you save time.

A quiet install is similar to a silent install, except that with a quiet install the user knows when the product is installing. A silent install program installs the product without any online cues, so the user may not even be aware when the product is in the process of installing. A quiet install does display dialogs and messages on the user's computer during the install, but no user input is required.

When you use the quiet install capability, you can modify the installation defaults, such as the local paths and additional program features. For instance, you can customize the quiet install with iFIX. To customize a quiet install, modify the default answers to all of the desired install questions and options beforehand by editing the `InstallConfig.ini` file on the iFIX product DVD. The `InstallConfig.ini` supplies the setup program with all of the information that a user is prompted to enter during the install, as well as pre-configured information about items such as the install paths. For more information on modifying this file, refer to the [Modifying the Default Behavior of the iFIX Install](#) section.

IMPORTANT: GE Historian does not support a quiet or silent install.

► **To launch the iFIX install so it runs quietly (without making any configuration changes):**

Launch the install with the "/Quiet" install command line option:

```
setup.exe /quiet /nomsg
```

► **To customize the iFIX install so that it always runs quietly:**

1. Create a customized iFIX install program. For steps, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.
2. Locate the InstallConfig.ini file in the dvdimage folder, and open it in a text editor such as Notepad.
3. In the [config] section, set Quiet=TRUE.
4. Save the file.

Modifying the Default Behavior of the iFIX Install

To modify the default behavior of the iFIX install program, edit the InstallConfig.ini file for the iFIX product install. The InstallConfig.ini supplies the setup program with all the information that a user is prompted to enter during the install, as well as pre-configured information. The information you can edit in the InstallConfig.ini file includes:

- Pre-configured path locations for the iFIX product during install.
- Enabled features such as the e-books.
- Behavior such as whether iFIX creates shortcuts for Launch.exe or the e-books.
- Default answers to prompted install questions, such as the node name, whether networking is enabled, or whether SCADA support is enabled.
- The option to run the iFIX install quietly (without user input).

For example, as a system administrator, system integrator, or an OEM, you may want to change the default paths that iFIX uses for pictures, alarm history files, recipes, and so on, so that the paths are specific to your environment. Be aware that if you change these paths, you may not be able to use iFIX with the Change Management product. Contact GE for more information.

► **To modify the default behavior of the install program:**

1. Create a customized iFIX install program. For steps, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.
2. Locate the InstallConfig.ini in the dvdimage folder, and open it in a text editor such as Notepad.
3. If you want to change the default paths to which iFIX installs in your Program Files folder, you can do so by editing the bold text in the following snippet. Be aware that if you change these paths, you may affect iFIX's capability to work with other GE products, such as Change Management.

```
[PATHS]
ROOT=
BasePath=GE\iFIX
PDBPath=PDB
NLSPath=NLS
PICPath=PIC
APPPath=APP
HTRPath=HTR
HTRDATAPath=HTRDATA
LOCALPath=LOCAL
ALMPath=ALM
```

```
RCMPath=RCM
RCCPath=RCC
AADPath=PDB
```

4. To specify the node name, enable or disable networking or SCADA support, or indicate whether to run a quiet install, edit the bold text in the following snippet. Quiet must be set to TRUE for the install to run quietly.

```
[config]
NODENAME=FIX
NETWORK=TRUE
SCADA=FALSE
quiet=FALSE
```

5. To specify whether features such as the e-books are to be installed, or to specify whether iFIX should show these features in the Custom Install option, edit the bold text in the following snippet. TRUE indicates that the feature installs, and FALSE means that it does not.

```
[features]
PAV=TRUE
EBOOKS=TRUE
MYTSOFT=TRUE
SHOWEBOOKS=TRUE
SHOWMYTSOFT=TRUE
```

6. Create a customized DVD or a customized network install in preparation for deployment. For more information, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.

Including Additional iFIX Project Files in the Install

Along with the iFIX product itself, you can install customized iFIX project files specific to your company or site. If you are a system integrator or OEM, this feature can significantly decrease your deployment time by allowing you to install your iFIX project files to all your computers without having to copy these files manually afterward.

To include additional iFIX project files, you create a custom batch or executable file that runs during the iFIX install (named Runtask.bat). The instructions you provide in this file will indicate a designated location to copy from and to.

The Runtask.bat File

The Runtask.bat file is a batch command file that you can run at the end of the iFIX product installation program. The iFIX product install is configured to automatically run this file if it exists.

This batch file copies picture files and customized help files from the MyProjects\pic folder you created in your dvdimage folder, to your local product install folder. It also copies Alarm Area Databases (.AAD files) and Process Databases (.PDB files) from the MyProjects\pdb folder in your dvdimage folder, to your local product install folder. The default install paths of C:\Program Files (x86)\GE\iFIX\PIC and C:\Program Files\Proficy\Proficy iFIX\PDB are used, as illustrated below in a sample Runtask.bat file:

```
REM Copy Picture Files
copy %2\MyProjects\pic\*.grf "%1\Program Files\Proficy\Proficy iFIX\PIC"

REM Fl Help Files for Picture
copy %2\MyProjects\pic\*.chm "%1\Program Files\Proficy\Proficy iFIX\PIC"
```

```

REM Copy Alarm Area Database Files
copy %2\MyProjects\pdb\AlarmAreas.AAD "%1\Program Files\Proficy\Proficy iFIX\PDB"

REM Copy Process Database Files
copy %2\MyProjects\pdb\MyDatabase.PDB "%1\Program Files\Proficy\Proficy iFIX\PDB"

```

As you can see in this example, there are two variable parameters: %1 and %2. To specify the directories that you want to work with, you need to modify these two parameters as follows:

- %1 is the target directory where iFIX installs.
- %2 is the iFIX install image folder (on a DVD or network).

► **To create a Runtask.bat file which copies additional files:**

1. Open Notepad or another text editor.
2. Enter the instructions that you want to include.
3. Copy this file to the dvdimage folder that you created when you created a custom iFIX install program. For more information, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.

Installing Software Improvement Modules (SIMs) with iFIX

If you want to install additional GE product SIMs along with iFIX, you can easily do so by adding them to the iFIX installation. Use this feature to save time if you need to install iFIX upgrades and multiple SIMs on several computers. You can customize the SIM install options so that they install quietly as well.

► **To add SIMs to your customized iFIX install:**

1. Create a customized iFIX install program. For steps, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.
2. Locate the Subinstall.ini file in the dvdimage folder, and open it in a text editor such as Notepad.
3. In the [post_install] section, add another sequential line that includes the name of your SIM. For instance, in this example we add install6 with the SIM name of iFIX_MySIM:

```

[post_install]
install0=WindowsInstaller-KB893803-v2-x86
install1=dotnet11
install2=dotnet20
install3=vc redistrib_x86
install4=plicense
install5=ilicense
install6=iFIX_MySIM

```

NOTE: The numbers that follow after the "install" text must be in sequential order. For instance: install0, install1, install2, install3, install4, and so on. If the numbers skip, or appear out of order, the install tasks may not run.

4. Scroll to the end of the Subinstall.ini file. Copy this entire snippet and paste it at the very end of your file:

```

[iFIX_MySIM]
display1031=Installing SIM iFIX_MySIM
display1033=Installing SIM iFIX_MySIM
display1036=Installing SIM iFIX_MySIM
display1041=Installing SIM iFIX_MySIM

```

```
display1042=Installing SIM iFIX_MySIM
display1045=Installing SIM iFIX_MySIM
display1049=Installing SIM iFIX_MySIM
display2052=Installing SIM iFIX_MySIM
required=1
execute=iFIX45SIMs\iFIX45_1135599586.exe
cmdline=/quiet /nomsg
```

NOTES:

- The /quiet /nomsg command line options allow the SIM to install quietly, without any messages prompting the user. These command line options are the preferred way to install SIMs along with the iFIX product install.
 - If you want to run the SIM install command from the dvdimage folder, instead from a DVD, you need to include the dvdimage path. For example: execute=dvdimage\iFIX45SIMs\iFIX45_1135599586.exe
5. In the first line replace the bracketed text with the SIM name you entered in step 3. In the previous example, the SIM was named iFIX_MySIM, and the bracketed item is similarly named [iFIX_MySIM].
 6. For the display lines 1031-2052, enter the text that you want to appear in localized product installs. The display code at the beginning of these lines represents the languages that iFIX installs on. If you are creating an English install, these text strings can be left at their default values, as shown in the previous example. If you are installing different language versions of iFIX, you can modify the bold text to display an informational message in the language corresponding to the language code at the beginning of each line. For a list of language codes, refer to the [Language Codes Used by the iFIX Install Program](#) section.
 7. For the execute line, enter the file location and name of the SIM that you want to install.
 8. Make sure that the cmdline contains the /quiet /nomsg options. This ensures that your SIM installs quietly.
 9. Save the file.
 10. Create a customized DVD or a customized network install in preparation for deployment. For more information, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.

Including Additional Third-Party Software in the Install

Along with iFIX, you can install other software specific your company or site. For instance, you might want to include tools you created to work with iFIX, or patches for other required software. Your custom install can include these as part of the standard iFIX install.

NOTE: If you install additional documentation, it currently cannot be accessed from the main iFIX e-book. You can only access it outside of the iFIX master e-book, or directly from iFIX picture files.

► To add other software programs to your customized iFIX install:

1. Create a customized iFIX install program. For steps, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.
2. Locate the Subinstall.ini file in the dvdimage folder, and open it in a text editor such as Notepad.

3. In the [post_install] section of the Subinstall.ini file, add another sequential line that includes the name of your software's executable installation file. For instance, in this example we add install6 with the name of MySpecialInstall:

```
[post_install]
install0=WindowsInstaller-KB893803-v2-x86
install1=dotnet11
install2=dotnet20
install3=vcredist_x86
install4=plicense
install5=ilicense
install6=MySpecialInstall
```

NOTE: The numbers that follow after the "install" text must be in sequential order. For instance: install0, install1, install2, install3, install4, and so on. If the numbers skip, or appear out of order, the install tasks may not run.

4. Scroll to the end of the Subinstall.ini file. Copy this entire snippet and paste it to the very end of your file:

```
[MySpecialInstall]
display1031=Installing MySpecialInstall
display1033=Installing MySpecialInstall
display1036=Installing MySpecialInstall
display1041=Installing MySpecialInstall
display1042=Installing MySpecialInstall
display1045=Installing MySpecialInstall
display1049=Installing MySpecialInstall
display2052=Installing MySpecialInstall
required=1
execute=Myfolder\MySpecialInstall.exe
cmdline=/MyCommand
```

NOTE: If you want to run the executable command from the dvdimage folder, instead from a DVD, you need to include the dvdimage path. For example: execute=dvdimage\Myfolder\MySpecialInstall.exe.

5. In the first line, replace the bracketed text with the name you entered in step 3. In the previous example, the executable installation file was named MySpecialInstall, and the bracketed item has the exact same name [MySpecialInstall].
6. For the display lines 1031-2052, enter the text that you want to appear in localized product installs. The display code at the beginning of these lines represents the languages that iFIX installs on. If you are creating an English install, these text strings can be left at their defaults as shown in the previous example. If you are installing different language versions of iFIX, you can modify the bold text to display an informational message in the language corresponding to the language code at the beginning of each line. For a list of language codes, refer to the [Language Codes Used by the iFIX Install Program](#) section.
7. For the execute line, enter the folder and executable installation file that you want to run. In this example, it's Myfolder\MySpecialInstall.exe.
8. If there are command lines that you want to include with your custom install add-on, add them to the cmdline section.
9. Save the file.
10. Repeat steps 3-9 for each additional software program that you want to add to the install.
11. Create a customized DVD or a customized network install in preparation for deployment. For more information, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.

If you are an OEM that resells the iFIX product with your own customizations, or a system integrator that wants to brand your customized install program, you can modify the first screen that a user encounters when installing the product. This screen is called the install splash screen.

When you insert the rebranded iFIX DVD into the DVD drive, the install splash screen appears. You can rebrand the install splash screen so that it includes your company name or logo, for instance. Be aware that GE requires special licensing to distribute rebranded DVDs. Contact GE for more information.

IMPORTANT: If you want to create and/or produce rebranded iFIX DVDs for use other than internal to your company, you must have license agreement and permission from GE to do so. Contact GE for more information.

► **To replace the install splash screen for a customized install:**

1. Create a customized iFIX install program. For steps, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.
2. Locate the InstallFrontEnd.bmp in your dvdimage folder.
3. In an image editing software program (Microsoft Paint or Paint Shop Pro, for instance), modify the InstallFrontEnd.bmp. Be careful not to change the dimensions of the graphic.
4. Save the file over the existing image.

► **To customize the text that appears on this splash screen:**

1. Locate the Installation.ini file in your dvdimage folder.
2. In Notepad or another text editor, modify the Installation.ini file. Use the comments in the file to guide you with your changes.
3. Save the file over the existing file.
4. Create a customized DVD or a customized network install in preparation for deployment. For more information, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.

Rebranding Install Graphics

To include rebranded graphics that appear *during* the install (not just the initial graphic in the splash screen), you must also have a special agreement with GE. Contact GE for details.

The artwork includes a number of graphic files named: bbrd1.bmp, bbrd2.bmp, bbrd3.bmp, and so on. These graphics are also known as the billboard graphics that appear in the middle of the screen during the install. To rebrand these files, edit each .bmp file in an image editing program. Make sure that you do not change the dimensions or resolution of the graphics. If you want to add additional billboard graphic files, you can do so. However, you must make sure that their file name and numbering sequence fits with the existing files, and you must make sure that they are the same dimensions and resolution as the other billboard graphics.

► **To replace the install graphics that appear after the splash screen:**

1. Obtain the bbrd*.bmp files from GE.
2. Create a customized iFIX install program. For steps, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.

3. In the dvdimage folder, create a folder named OEM\ 1033 folder, where 1033 represents the English language code. For a list of language codes, refer to the [Language Codes Used by the iFIX Install Program](#) section. Copy the bbrd*.bmp files to this folder.

NOTE: Other language codes are supported as well. Contact GE for more a list of language codes and information on licensing localized products.

4. Use any graphics editor to edit the bbrd*.bmp graphics, or create new bbrd*.bmp graphics.

IMPORTANT: Be sure that you do not change the height and width (dimensions or resolution) of the graphic. If you do, the graphic may not appear correctly in the install.

5. Save changed or new files with the same naming convention.

Rebranding Install Text

To provide rebranded text that appears *during* the install, you must also have a special agreement with GE. Contact GE for details. After an agreement is signed, GE will provide the string table files that you need to modify the product's install program.

The string table files have an .ips file extension, such as StringTable-0009-English.ips, and an associated .ini file, such as stringtable_English.ini. String table files are included for the main install program. To rebrand a string table file, use a text editor such as Notepad and enter changes for each row you want to rebrand. You may need additional help from GE with this process. Contact GE for details and availability.

If you modify the text in an .ips file, you must recompress the install program using the InstallShield Stand-Alone Builder (SAB), version 11.5, that is available with the iFIX NLS Toolkit. For more information on the InstallShield SAB, refer to the [Recompressing the iFIX Install with Rebranded Material](#) section.

► To translate the strings for the main install:

1. Obtain the *.ips and corresponding *.ini files for the main install from GE.
2. Create a customized iFIX install program. For steps, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.
3. In your dvdimage folder, create a new folder named Translate_iFix_Installer_Strings. Copy the *.ips and *.ini files obtained for this installer from GE to this folder.
4. Open the .ips file corresponding to your language in a text editor such as Notepad. For example, for English that file is named StringTable-0009-English.ips.
5. Provide edits for each string you want to rebrand. The text that you can rebrand appears to the right of the equals (=) sign. For example, if you wanted to modify the text that appears when a user who is not an Administrator attempts to install iFIX, you would edit the bold portion shown here:

```
ERROR_NO_ADMIN_RIGHTS=Setup requires an user account with Administrator privileges.
```

6. Save the file.

► **To update additional text strings:**

1. Locate the Setup.ini file in the dvdimage folder, and open it in a text editor such as Notepad.
2. In the [Startup] section of the Setup.ini file, provide updated information for the AppName, CompanyName, or CompanyURL fields:

```
[Startup]
AppName=iFIX
ProductGUID=8E2D0FDB-EF39-4AE0-A9E8-619E7575A17E
CompanyName=GE
CompanyURL=https://digitalsupport.ge.com
...
```

3. Save the file.

► **To update the install program with the rebranded string table files:**

1. Recompress the install program using the InstallShield Stand-Alone Builder.
2. Create a customized DVD or a customized network install in preparation for deployment. For more information, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.

Rebranding the License Agreement

To include a rebranded end-user license agreement (EULA) in your install program, you must also have a special agreement with GE. Contact GE for details. After an agreement is signed, GE will provide the license file that you need to modify the product's install program. The license file is named license.rtf, and can be edited in Microsoft® Word.

► **To replace the install splash screen for a customized install:**

1. Obtain the license.rtf file from GE.
2. Create a customized iFIX install program. For steps, refer to the [Creating a Custom iFIX Install for a DVD or Network](#) section.
3. In the dvdimage folder, create a folder named OEM\1033 folder, where 1033 represents the English language code. For a list of language codes, refer to the [Language Codes Used by the iFIX Install Program](#) section. Copy the license.rtf file to this folder.

NOTE: Other language codes are supported as well. Contact GE for more a list of language codes and information on licensing localized products.

4. In Microsoft® Word, open the license.rtf file and make the rebranding edits.
5. Save the file (with the original license.rtf file name).
6. Copy the file to the dvdimage folder.
7. Validate the rebranded End User License Agreement with the appropriate legal counsels at your company and GE before you ship the license.rtf with the product. If changes need to be made to the license.rtf file at any future date, copy the edited version to the OEM\1033 folder and overwrite the existing file. For a list of language codes, refer to the [Language Codes Used by the iFIX Install Program](#) section.

Recompressing the iFIX Install with Rebranded Material

To recompress an iFIX install program with your rebranded text, you need to use the InstallShield Stand-Alone Builder (SAB), version 2012 Spring Edition. A copy of this program is included as part of the iFIX NLS Toolkit. You must have a special agreement with GE to obtain a copy of the NLS Toolkit CD with the InstallShield SAB installer. Steps on how to install the InstallShield SAB are described in the "Installing the InstallShield Standalone Builder" topic in the Translating iFIX with the NLS Toolkit e-book (NLSToolkit.chm).

To recompress the install, run the InstallShield SAB (ISCab.exe) from the command-line, with the required command line options (described in the steps below). This allows you to add files into the data1.cab cabinet file for the install program, and rebuild the installer.

► **To recompress the install with the InstallShield SAB:**

1. For the main installer (if you modified an .IPS file for it), copy the updated .IPS string table file from the Translate_iFIX_Installer_Strings and the stringtable_<language>.ini file into the dvdimage folder.
2. Using a Command Prompt, from the dvdimage directory, run the following command:

```
iscab.exe data1.cab -a -i"stringtable_<language>.ini"
```
3. In the dvdimage folder, remove the files you copied over in step 1.

Rebranding the iFIX DVD Booklet and Tray Card

Optionally, other artwork, such as the DVD Booklet and tray card, can also be rebranded. You must have a special agreement with GE, to do so. Contact GE for details. After an agreement is signed, GE will provide the artwork for these items.

The artwork source is in QuarkXpress format, so that you can replicate these graphics as accurately as possible. You must have QuarkXpress to edit these files.

Rebranding Other Parts of the iFIX Product

As an OEM, you must have license agreement and permission from GE to rebrand any parts of the iFIX product. To do this, you will need a copy of iFIX NLS Toolkit product. The NLS Toolkit allows you to rebrand parts of the iFIX user interface, as well as the install program. Contact GE for more information.

Deploying the iFIX Install Setup.exe Command Line Options

You can run the iFIX Setup.exe program from the command line using the options described in the following table. These command line options are particularly helpful if you want to deploy the iFIX install over a network using system management software, such as Microsoft Systems Management Server (SMS).

IMPORTANT: For Microsoft Windows 7 and up, when running iFIX Setup.exe directly, the installation user must either be the build Administrator or use the same account that was used to set up the machine.

Option	Description
--------	-------------

<code>/targetdir=c:\Path</code>	Sets the install folder, where <code>c:\Path</code> represents the path where you want iFIX to install to.
<code>/inifile=c:\Path\installconfig.ini</code>	Redirects the install program to use the <code>installconfig.ini</code> in the specified folder, where <code>c:\Path</code> represents the path of the <code>installconfig.ini</code> file that you want to use.
<code>/quiet</code>	Installs iFIX in unattended mode. For more information, refer to the Running a Quiet Install section.
<code>/nomsg</code>	Installs iFIX without prompts (even for critical message boxes), when used with the <code>/quiet</code> command.

Example 1

In this example, we install iFIX quietly using a custom installation file in the user's `c:\myfolder` directory:

```
Setup.exe /inifile=c:\myfolder\installconfig.ini /quiet /nomsg
```

Example 2

In this example, we install iFIX from the DVD without prompts:

```
Setup.exe /quiet /nomsg
```

Example 3

In this example, we change the default the iFIX install to the `c:\Program Files\MyFolder` directory:

```
Setup.exe /targetdir=c:\Program Files\MyFolder
```

NOTE: Instead of using the command line in Example 3, you can also modify the `BasePath=` option in the `InstallConfig.ini` file.

INI Files Used by the iFIX Install

The following initialization (`.ini`) files are associated with the iFIX install program. You can modify these `.ini` files to create a custom iFIX install:

- [Installation.ini](#)
- [InstallConfig.ini](#)
- [Subinstall.ini](#)
- [Setup.ini](#)

Installation.ini

The following is an example of the iFIX `Installation.ini` file. Use the `Installation.ini` file to modify the items displayed on the install splash screen graphic.

```
; The Settings section configures general properties as follows
;
; Key Name Description
; -----
; ShowTitle: If true, a caption bar displays at the top. Otherwise, it doesn't
; Title: The caption that shows up at the top of the installation screen.
; SplashScreen: The splash screen used if the color resolution is > 256 colors
```

```

; OnColor: The color value used to display the active option (RGB) - Format of BBGRR (COLORREF)
; OffColor: The color value used to display inactive options (RGB) - Format of BBGRR (COLORREF)
; ShadowColor: The color value used to provide a 3d effect to the text - Format of BBGRR (COLORREF)
; FontName: Use to override the default font name used by the software.
; FontSize: Use to override the default font size used.
; FontBold: 1 for bold, 0 for no bold.
; FontItalic: 1 for italic, 0 for no italic
; Icon Specify the icon file (.ico) to use for an icon. The icon should have a 16x16 and 32x32 version.
;
;
; IMPORTANT
; =====
; The splash screen will get sized to match the size of the splash bitmap.
; the default label-button sizes and positions work well for a 640x480 bitmap.
; if you use a different size, you should use the XCoord and YCoord parameters (see
; below) to adjust the position of each label on the screen.
;
; if you remove the caption bar (ShowTitle=0) make sure one of your buttons
; includes the ExitButton=1 field . This command is used to exit the program. Otherwise
; users won't be able to exit the program at all.
;
; NOTE: All values except for FontSize, FontBold, FontItalic, and Icon are required.
[Settings]
ShowTitle=1
Title=iFIX installation program
SplashScreen=InstallFrontEnd.bmp
OnColor=0xFF0000
OffColor=0xF0F0F0
ShadowColor=0x000000
FontSize=0x00000D
FontItalic=0
FontBold=1
FontName=Arial
Icon=Fix.ico
Status=Installing Proficy iFIX
;
; Key Name Description
; -----
; ButtonX where X is a number (Button1).
; NOTE: Button names MUST be sequential!
; The values will be the section names of the buttons to be created.
; This allows for many buttons to be defined while only showing a subset of them.
[Buttons]
Button1=InstalliFIX
Button2=6XDriver
Button3=SupportWebsite
Button4=ReleaseNotes
Button5=Browse
Button6=Exit
Button7=Hist45
Button8=DataProvider
Button9=ServiceProvider
Button10=WorkflowTrigger11
;-----
; Buttons
; This is made up of one or more sections. Each section describes 1 button.
; ButtonText, XCoord and YCoord are required or the button will not be created.
; Also either ExitButton Or Executable are required.
; All other fields are optional.
;
; Key Name Description
; -----
; ButtonText: The text to be shown
; Hint: The tool tip that shows up when that button is highlight.
; ConfirmationRequired:0 for no confirmation, 1 for confirmation (default is 0)
; ConfirmationPrompt: The string you want to use as a confirmation prompt.

```



```

YCoord = 105
[ReleaseNotes]
ButtonText=View iFIX release notes
Hint=View the iFIX release notes
Executable=hh.exe
CmdLineParam=releasenotes/ipiifix.chm
XCoord = 355
YCoord = 140
[Browse]
ButtonText=Browse the DVD
Hint=Explore the DVD
XCoord = 355
YCoord = 175
Executable=explorer.exe
CmdLineParam=.
[DataProvider]
ButtonText=Install Proficy iFIX DataProvider
Hint=Install iFIX58 Data Provider Service components.
XCoord = 355
YCoord = 210
Executable="Setup\Proficy\iFIXDataProvider\iFIX58_DataProvider_001.exe"
[ServiceProvider]
ButtonText=Install Proficy iFIX ServiceProvider
Hint=Install Proficy iFIX Service Provider components.
XCoord = 355
YCoord = 245
Executable="Setup\Proficy\iFIXServiceProvider\ProficyiFIXServiceProvider.exe"
[WorkflowTrigger11]
ButtonText=Install Workflow Trigger 1.1
Hint=Install Workflow Trigger 1.1 and related components
XCoord = 355
YCoord = 280
Executable="Setup\Proficy\WorkflowTrigger\Workflow Trigger.exe"
[Exit]
ButtonText=Exit
Hint=Exit
XCoord=575
YCoord =330
FontScale=10
ExitButton=1
;FontName=MS Sans Serif

```

InstallConfig.ini

The following is an example of the iFIX InstallConfig.ini file. Use the InstallConfig.ini to modify the default install settings, or to indicate whether iFIX installs quietly.

```

[PATHS]
ROOT=
BasePath=GE\iFIX
PDBPath=PDB
NLSPath=NLS
PICPath=PIC
APPPPath=APP
HTRPath=HTR
HTRDATAPath=HTRDATA
LOCALPath=LOCAL
ALMPath=ALM
RCMPPath=RCM
RCCPath=RCC
AADPath=PDB

```

```

[config]
NODENAME=FIX
NETWORK=TRUE
SCADA=FALSE
quiet=FALSE
[features]
PAV=TRUE
EBOOKS=TRUE
MYTSOFT=TRUE
SHOWEBOOKS=TRUE
SHOWMYTSOFT=TRUE
[upgrade]
USESCU=TRUE
WarnBTKUpgrade=TRUE
[nlsToolkit]
NLSTOOLKITFOLDER=FIX
[EBOOKS]
DOCPATH=Proficy\ProficyDoc
DEFAULTLANGUAGECODE=1033
PRODUCTNAME=IFIX

```

Subinstall.ini

The following is an example of the iFIX SubInstall.ini file. Use the Subinstall.ini to include additional third-party software, or Software Improvement Modules (SIMs) with your iFIX install.

```

[requisite]
install0=WindowsInstaller-KB893803-v2-x86
install1=vcredist_x86
install2=vcredist_x64
[pre_install]
install0=dotnetfx40
install1=plicense
[post_install]
install0=ChangeManagementClient
install1=opcclient
install2=discovery
install3=ikbf
[post_workspace_register]
[UNINSTALL]
[WindowsInstaller-KB893803-v2-x86]
display1031=Installing Microsoft Windows Installer 3.1
display1033=Installing Microsoft Windows Installer 3.1
display1036=Installing Microsoft Windows Installer 3.1
display1041=Installing Microsoft Windows Installer 3.1
display1042=Installing Microsoft Windows Installer 3.1
display1045=Installing Microsoft Windows Installer 3.1
display1049=Installing Microsoft Windows Installer 3.1
display2052=Installing Microsoft Windows Installer 3.1
required=1
execute=Microsoft\WindowsInstaller3_1\WindowsInstaller-KB893803-v2-x86.exe
cmdline=/quiet /norestart
checkregistry=SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\KB893803v2
[dotnetfx40]
display1031=Installing Microsoft .NET framework v4
display1033=Installing Microsoft .NET framework v4
display1036=Installing Microsoft .NET framework v4
display1041=Installing Microsoft .NET framework v4
display1042=Installing Microsoft .NET framework v4
display1045=Installing Microsoft .NET framework v4
display1049=Installing Microsoft .NET framework v4
display2052=Installing Microsoft .NET framework v4

```

```

required=1
execute=Microsoft\DotNetFx40\dotNetFx40_Full_x86_x64.exe
cmdline=/q /norestart
checkregistry=SOFTWARE\Microsoft\NET Framework Setup\NDP\v4
[vcredist_x86]
display1031=Installing Microsoft Visual C++ Runtime Libraries (x86)
display1033=Installing Microsoft Visual C++ Runtime Libraries (x86)
display1036=Installing Microsoft Visual C++ Runtime Libraries (x86)
display1041=Installing Microsoft Visual C++ Runtime Libraries (x86)
display1042=Installing Microsoft Visual C++ Runtime Libraries (x86)
display1045=Installing Microsoft Visual C++ Runtime Libraries (x86)
display1049=Installing Microsoft Visual C++ Runtime Libraries (x86)
display2052=Installing Microsoft Visual C++ Runtime Libraries (x86)
required=1
execute=Microsoft\vcpp2010\vcredist_x86.exe
cmdline=/q /r:n /norestart
checkregistry=SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\{196BB40D-1578-3D01-B289-BEFC77A11A1E}
[vcredist_x64]
display1031=Installing Microsoft Visual C++ Runtime Libraries (x64)
display1033=Installing Microsoft Visual C++ Runtime Libraries (x64)
display1036=Installing Microsoft Visual C++ Runtime Libraries (x64)
display1041=Installing Microsoft Visual C++ Runtime Libraries (x64)
display1042=Installing Microsoft Visual C++ Runtime Libraries (x64)
display1045=Installing Microsoft Visual C++ Runtime Libraries (x64)
display1049=Installing Microsoft Visual C++ Runtime Libraries (x64)
display2052=Installing Microsoft Visual C++ Runtime Libraries (x64)
required=1
execute64=Microsoft\vcpp2010x64\vcredist_x64.exe
cmdline64=/q /r:n /norestart
[ikbf]
display1031=Installing Keyboard Driver
display1033=Installing Keyboard Driver
display1036=Installing Keyboard Driver
display1041=Installing Keyboard Driver
display1042=Installing Keyboard Driver
display1045=Installing Keyboard Driver
display1049=Installing Keyboard Driver
display2052=Installing Keyboard Driver
required=1
execute=Proficy\ikbf5\setupikbf5.exe
cmdline=/SILENT
[plicense]
display1031=Installing Proficy Common Licensing
display1033=Installing Proficy Common Licensing
display1036=Installing Proficy Common Licensing
display1041=Installing Proficy Common Licensing
display1042=Installing Proficy Common Licensing
display1045=Installing Proficy Common Licensing
display1049=Installing Proficy Common Licensing
display2052=Installing Proficy Common Licensing
required=0
execute=Proficy\license\ProficyClientInstaller.exe
cmdline=/quiet /nomsg
[opclient]
display1031=Installing OPC Client Driver
display1033=Installing OPC Client Driver
display1036=Installing OPC Client Driver
display1041=Installing OPC Client Driver
display1042=Installing OPC Client Driver
display1045=Installing OPC Client Driver
display1049=Installing OPC Client Driver
display2052=Installing OPC Client Driver
required=0
execute=Proficy\OPCClientSetup\setup.exe
cmdline=1
[discovery]

```

```

display1031=Installing Discover And Auto Configure
display1033=Installing Discover And Auto Configure
display1036=Installing Discover And Auto Configure
display1041=Installing Discover And Auto Configure
display1042=Installing Discover And Auto Configure
display1045=Installing Discover And Auto Configure
display1049=Installing Discover And Auto Configure
display2052=Installing Discover And Auto Configure
required=0
execute=Proficy\discovery\discovery.exe
cmdline=/quiet /nomsg
[ChangeManagementClient]
display1031=Installing Change Management Client
display1033=Installing Change Management Client
display1036=Installing Change Management Client
display1041=Installing Change Management Client
display1042=Installing Change Management Client
display1045=Installing Change Management Client
display1049=Installing Change Management Client
display2052=Installing Change Management Client
required=1
execute=Proficy\ChangeManagementAPI\setup.exe
cmdline=/s /v"/qn"

```

Setup.ini

The following is an example of the iFIX Setup.ini file. Use the Setup.ini to modify text that appears in the actual install program. It is recommended that you do not modify this file, unless you obtain permission from GE. Do not attempt to modify the ProductGUID item, or you may experience unexpected errors.

```

[Startup]
Product=iFIX
ProductGUID=8E2D0FDB-EF39-4AE0-A9E8-619E7575A17E
CompanyName=GE
CompanyURL=https://digitalsupport.ge.com
ErrorReportURL=http://www.installshield.com/isetup/ProErrorCentral.asp?ErrorCode=%d : 0x%x&ErrorInfo=%s
MediaFormat=1
LogMode=1
SmallProgress=N
SplashTime=
CheckMD5=Y
CmdLine=
ShowPasswordDialog=N
ScriptDriven=4
[Languages]
Default=0x0409
Supported=0x0409,0x0804,0x0404,0x040c,0x0407,0x0410,0x0411,0x0412,0x0415,0x0416,0x0816,0x0419,0x040a,0x041d,0x0406,0x0
RequireExactLangMatch=0x0404,0x0804
RTLLangs=0x0401,0x040d
[0x0409]
0x0409=English (United States)
0x0411=Japanese
0x0401=Arabic (Saudi Arabia)
0x042d=Basque
0x0402=Bulgarian
0x0403=Catalan
0x0804=Chinese (PRC)
0x0404=Chinese (Taiwan)
0x041a=Croatian
0x0405=Czech

```

0x0406=Danish
 0x0413=Dutch (Netherlands)
 0x040b=Finnish
 0x0c0c=French (Canada)
 0x040c=French (France)
 0x0407=German (Germany)
 0x0408=Greek
 0x040d=Hebrew
 0x040e=Hungarian
 0x0421=Indonesian
 0x0410=Italian (Italy)
 0x0412=Korean
 0x0414=Norwegian (Bokmal)
 0x0415=Polish
 0x0416=Portuguese (Brazil)
 0x0816=Portuguese (Portugal)
 0x0418=Romanian
 0x0419=Russian
 0x0c1a=Serbian (Cyrillic)
 0x041b=Slovak
 0x0424=Slovenian
 0x040a=Spanish (Traditional Sort)
 0x041d=Swedish
 0x041e=Thai
 0x041f=Turkish

Language Codes Used by the iFIX Install Program

The following table displays a list of language codes you can use when creating a customized iFIX install.

Language	Code
Catalan	1027
Czech	1029
Danish	1030
English	1033
German	1031
Greek	1032
Japanese	1041
Swedish	1053
Basque	1069
Brazilian Portuguese	1046
Chinese - Taiwan	1028
Chinese PRC	2052
Croatian	1050
Cyrillic	3098
Dutch	1043
Finnish	1035
French	1036
French Canadian	3084
Hungarian	1038
Indonesian	1057
Italian	1040

Korean	1042
Norwegian	1044
Polish	1045
Portuguese	2070
Russian	1049
Slovak	1051
Slovenian	1060
Spanish	1034
Thai	1054
Turkish	1055

Index

.ips 105

A

Activity Log 91

 main window 91

Administrator 95

All Tags 39

 search in the Cross Reference Tool 38

Application Validator 82

 audit messages 90

 auditing 89

 basics 82

 command line options 88

 general configuration 84

 overview steps 87

 report types 85

 running 82

 toolbar 84

Apply and Go tab 46

AppValConfig.ini file 89

arguments, Application Validator command
 line 88

assigning schedules to a security area 25

attributes 65

 header and footer 65

audit messages 90

 list 90

 sample format 90

 viewing 90

auditing 89

 AppValConfig.ini file 89

 understanding 89

Automatically Resize Report Columns 46

B

background 23

background schedules 4

background task startup list 8

basics, Application Validator 82

best practices 92

 Application Validator 92

billboard graphics 104

buttons 43

 toolbar buttons for the Application
 Validator 84

 toolbar buttons for the Cross Reference
 Tool 43

C

changes only in Compare Detail Report 86

command-line (Cross Reference Tool) 50

command line (Application Validator) 88

 from GUI 88

 options 88

command line options 107

Comparison Detail Report

 overview 86

compiling a project file 72

configuration for the Application Validator 84

continuous 27

continuous entry 10

- creating 23, 60
 - a map file 71
 - a project file 72
 - a report 61
 - picture-specific help files 66
 - reports 44, 59
 - the help file 69
 - topic file 70
- creating entries 32
- Creating Reports Using the Cross Reference Report Wizard 41
- Cross Reference Report 59
- Cross Reference Report Wizard 44, 60
- Cross Reference Tool 38
 - All Tags search 38
 - Apply and Go tab 46
 - automatically saving the report file 46
 - creating Quick Reports 43
 - customizing header and footers 50
 - including the summary report 43
 - introduction 38
 - introduction to 37
 - One Tag search 39
 - Page Setup dialog box 50
 - printing a report 49
 - printing report automatically 46
 - Quick Report and Report Wizard 41
 - refreshing 43
 - Report Settings tab 46
 - Report Wizard 41
 - resizing columns 43
 - resolving tags 43

- running from command-line 50
- search settings 45
- search types 38
- searching for text 39
- searching through scripts 43
- selecting multiple files 45
- selecting print options 49
- toolbars 43
- types of searches 38
- viewing results 46
- viewing searches through scripts 48
- viewing status trail 47
- Crystal Reports 36
 - using with iFIX 36
- custom iFIX installation 95
- custom scripts 13, 32
 - writing for Scheduler 13
- customized iFIX install 97
- customizing the system tree 77

D

- daily 27
- daily entry 10
- debugging VBA scripts in a schedule 8
- defining Application Validator command line options (GUI) 88
- Demo Mode, Application Validator 83
- deployment 107
- descriptions
 - optional arguments in Application Validator command line 88
- Detail Report, Comparison 86

drag and drop 29

DVD Booklet and tray card 107

E

editing 32

end-user license agreement 106

entering text into the header or footer 65

entries 10

- continuous 10

- creating 11

- daily 10

- diagnostics 12

- editing 11

- event-based 9

- monthly 10

- one-shot 10

- time-based 10

entry 29

errors, command line (Application Validator) 88

EULA 106

event 26

event-based 26

event-based entries 9

event types 9

executing 31

Experts 11, 32

- Script Authoring 11

F

file attributes 81

- SystemTree.CSV file 80

files 45

- adding to the system tree 80

- deleting from the system tree 81

- selecting multiple 45

Files tab 45

files that changed 87

finding 41

- tags in files 41

finding tags 43

- in the Cross Reference Tool 43

firing 31

FixBackgroundServer task 8

- as a Windows service 8

folder attributes 79

- SystemTree.CSV file 78

folders 81

- adding to the system tree 78

- deleting from the system tree 81

footers 65

foreground 24

foreground schedules 4

G

general configuration for the Application Validator 84

generating a report 59

GUI, Application Validator command line options 88

H

headers 65

Headers and Footers 50

- customizing 50

help

- adding to an iFIX picture 69
- creating the file 69
- designing What's This ? 68
- understanding What's This ? 66

I

- iFIX, running with or without (Application Validator) 83
- Include Summary 46
- Include VBA Scripts in Search 43
- Installation.ini 108
- InstallConfig.ini 98-99, 111
- InstallFrontEnd.bmp 104
- InstallShield 107
- InstallShield Standalone Builder 107
- ips 105

L

- language codes 115
- license agreement 107
- list 90
 - audit messages from the Application Validator 90
- load a predefined profile 84
- local node alias
 - enabling 34
 - examples 34
 - overview 33
 - THISNODE 34
 - using 34
- Log window from the Application Validator 91

M

- main window, Activity Log 91
- map file 71
- margins 65
- messages from the Application Validator 90
- Microsoft Systems Management Server 107
- mode, Demo 83
- modifying 29
- monthly 28
- monthly entry 10
- move 30
- multiple files 45, 60
 - searching through 45

N

- network install 98
- new 23
- notes on the syntax (Application Validator) 88

O

- Object Tree 43
 - refreshing 43
- OEM 96
- one-shot entry 10
- one shot 27
- One Tag 39
 - searching for in Cross Reference Tool 39
- optional arguments, Application Validator command line 88
- Original Equipment Manufacturer 96
- overview 23, 87
 - Application Validator steps for using 87

P

- page 64
 - ranges 63
 - setup 64
 - setup options 65
- page margins 65
- page options 64
- page setup 65
 - header and footers 65
- paste 29
- picture-specific help files 66
 - creating 66
- predefined profile, loading 84
- printing 46, 64
 - reports 49
 - reports automatically 46
- printing a report 62
 - automatically 62
- profile 84
 - loading 84
 - saving 84
- project file 72
 - creating and compiling 72
- properties 32

Q

- Quick Report 43, 59
 - All Tags 39
 - differences between Report Wizard and 41
 - feature list 41
 - One Tag 39

Quick Reports 43

- creating 43
- quiet install 98

R

- rebranded install graphics 104
- rebranded install text 105
- recompress an iFIX install 107
- refresh 43
 - Object Tree 43
- report 59
 - creating one with multiple files 60
 - including a summary 43
 - printing and saving automatically 62
 - reviewing settings 46
 - saving to a file 46
 - specifying output options 46
 - viewing report results 46
 - viewing search results that resolve tags 47
- report output options 62
- Report Results 46
- Report Settings tab 46
 - automatically print report 46
- Report Settings Tab 46, 62
 - Save Status Trail 46
- Report Wizard 60
 - All Tags 39
 - automatically saving status trail 46
 - creating reports 44
 - differences between Quick Report and 41
 - feature list 41
 - One Tag 39

- output options 46
- resolving tags 45
- search settings 45
- searching through scripts 45
- selecting multiple files 45
- reports 48, 59
 - automatically printing 46
 - Comparison Detail 86
 - creating 43
 - printing 49
 - quick reports 59
 - resizing columns 43
 - searching through VBA scripts 62
 - selecting page options 49
 - viewing search through script results 48
- Reports
 - overview 85
 - Summary 85
- resetting 31
- resizing columns 43
- resolve 25
- Resolve Tags 44
 - using All Tag Group Files 43
- Resolve Tags using All Tag Group Files 48
 - viewing results 47
- resolving schedules 6
- resolving tags 45, 61
 - using all Tag Group Files 61
 - using the Cross Reference Tool 43
 - using the Report Wizard 45

- results 46
 - of tag search 46
 - of text search 46
- running 23, 83
 - Demo Mode 83
 - with or without iFIX 83

S

- SAB 107
- sample 90
 - audit message from the Application Validator 90
- Save Status Trail 46
- saving 62, 84
 - automatically 62
 - Comparison Detail Report 86
 - profile 84
- Scheduler
 - introduction 1
 - overview 2
 - running as a background task 5
 - running as a foreground task 5
 - script execution 5
 - using the VBE 4
 - using with iFIX 4
- schedules 12, 25
 - adding to background task startup list 8
 - debugging VBA scripts 8
 - designing 9
 - resolving 6
 - running in the background 6
 - running in the foreground 6

- securing 6
- sorting 12
- Script Authoring Experts 11
- scripts 33, 48
 - searching through 43
 - viewing reports 48
- Search Settings tab 45
- searching 38, 61
 - for tags 37
 - for text 38
 - for text strings 39
 - resolving tags while 61
 - through scripts 45
 - through VBA scripts 62
 - types of searches for tags 38
 - using the Quick Report 59
- searching for 39
 - one tag 39
- searching for tags 45
 - resolving tags 45
- securing schedules 6
- security areas 25
- selecting print options 49, 63
- settings 84
 - working with 84
- Setup.exe 107
- Setup.ini 106, 114
- SIMs 101
- SMS 107
- Software Improvement Modules 101
- sorting a schedule 12

- splash screen 103
- starting 31
- statistics 31
- Status Trail 47
 - automatically saving 46
- steps 87
 - using the Application Validator 87
- stopping 31
- Subinstall.ini 101-102, 112
- summary report 44
- Summary Report 85
- syntax, Application Validator command line 88
- system integrator 96
- system tree 77
 - adding files 80
 - adding folders 78
 - customizing 77
 - deleting folders and files 81
 - SystemTree.CSV file 77
- Systems Management Server 107
- SystemTree.CSV file 77

T

- tag name 39
 - searching for a partial name 39
- tags 38
 - searching for all tags 38
 - searching for one tag 38
- Text 39
 - finding in files 39
- Text search 40
- THISNODE 34

time-based entries 10
toolbar, Application Validator 84
toolbars 43
topic file 70
troubleshooting 33
types of reports (Application Validator) 85

U

understanding 89
 auditing for the Application Validator 89
using 84
 Application Validator 87
 Application Validator toolbar 84

V

validating an application 82
VBA scripts 13, 62
 searching through 62
 to access the iFIX WorkSpace 11
 writing custom scripts for Scheduler 13
VBE 5
 using with Scheduler 4

viewing 32
 audited messages (Application Validator) 90
 changed files 86

W

What's This ? help 66
 designing 68
 overview 66
Wizard 60

wizards 41
 feature list for Cross Reference Tool 41
 Report Wizard 41
working 84
 with settings 84

Z

zoom rate 64