

APM Connect

Data Loaders V2.0.0, EAM MAX V2.0.0, EAM SAP V2.0.0, EAM SAP PI V2.0.0



APM Connect

© 2017 General Electric Company.

GE, the GE Monogram, and Predix are either registered trademarks or trademarks of General Electric Company. All other trademarks are the property of their respective owners.

This document may contain Confidential/Proprietary information of General Electric Company and/or its suppliers or vendors. Distribution or reproduction is prohibited without permission.

THIS DOCUMENT AND ITS CONTENTS ARE PROVIDED "AS IS," WITH NO REPRESENTATION OR WARRANTIES OF ANY KIND, WHETHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO WARRANTIES OF DESIGN, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. ALL OTHER LIABILITY ARISING FROM RELIANCE UPON ANY INFORMATION CONTAINED HEREIN IS EXPRESSLY DISCLAIMED.

Access to and use of the software described in this document is conditioned on acceptance of the End User License Agreement and compliance with its terms.

About This Document

This file is provided so that you can easily print this section of the GE Digital APM Help system.

You should, however, use the Help system instead of a printed document. This is because the Help system provides hyperlinks that will assist you in easily locating the related instructions that you need. Such links are not available in a print document format.

The GE Digital APM Help system can be accessed within GE Digital APM itself or via the GE Digital APM Documentation Website (https://www.me-ridium.com/secure/documentation/WebHelp/Home.htm).

Note: If you do not have access to the GE Digital APM Documentation Website, contact GE Global Support (https://www.ge.com/digital/asset-performance-management).

Table of Contents

APM Connect	1
Copyright and Legal	2
About This Document	3
Table of Contents	4
APM Connect System Requirements	10
Deploy APM Connect	15
Deploy the APM Connect Base	16
Deploy the APM Connect Base for the First Time	17
Upgrade the APM Connect Base to V2.0.0	19
Run the Third-Party Software Batch File	20
Run the APM Connect Installer	22
Install the Meridium Web Service	39
Enable Internet Explorer for APM Connect	41
Update PostgreSQL Networking Configuration	42
Access the APM Connect Administration Center	43
Change the APM Connect Administration Center User Password	47
Validate the APM Connect Administration Center License	48
Configure the APM Connect Administration Center	51
Set User Permissions	54
Authorize Users for Projects	57
Create a Service Account User	59
Configure the APM Connect Administration Center for the Studio	63
Install the Studio	66
Uninstall APM Connect	69
Set Java Environment Variables	70
Deploy the Data Loaders	72
Deploy the Data Loaders for the First Time	73
Upgrade APM Connect Data Loaders to DL V2.0.0	74

Configure SSL	75
Set Permissions for APM Connect Directory	78
Deploy and Configure Data Loader Files	85
Create the Intermediate Repository Database	88
Enable Test Connection	90
Change H2 Console Password	91
Create APM Service User	93
Deploy the Maximo Adapters	94
Deploy Maximo Adapters for the First Time	95
Upgrade Maximo to EAM MAX V2.0.0	96
Configure the Maximo Context File	97
Encrypt Passwords	106
Import Notification Management File	107
Configure Context Parameters	108
Create the Intermediate Repository Database	110
Create Object Structures in Maximo	112
Create Web Services in Maximo	118
Configure the Default Password	119
Set System Properties Settings for Web Service Response	120
Create EAM System Records	121
Maximo Interfaces Security Groups	122
About Site Filtering in the EAM Adapters	124
Deploy the SAP Adapters	126
Deploy the SAP Adapters for the First Time	127
Upgrade SAP Adapters to EAM SAP V2.0.0	131
Upgrade SAP Cloud Adapters to EAM SAP Cloud V2.0.0	132
Configure the Context File Directory	133
Configure the Context File Directory for Multiple SAP Systems	134
Install SAP Java Connector	135
Configure SSL	136

Configure the Context File	137
Encrypt Passwords	178
Configure Context Parameters	179
Configure the Context Parameters for APM Now	182
Create the Intermediate Repository Database	184
About Site Filtering	186
Mount a File Share	188
About File Shares and APM Connect	197
Load Bulk IDs	199
Establish SFTP Transfer in SAP	201
Create File Share Folder Structure	202
Install the ABAP Base Service Pack Add-on	203
Verify ABAP Installation	207
Create APM Connect User Profile in SAP	209
SAP Interfaces Security Groups	211
Identify Trigger Values for Creating Task Records	213
Configure GE Digital APM to Create Notifications from Recommendation Records	214
Deploy and Configure the RFC Connector Files	215
Configure Notification Priority	218
Create an EAM System Record	219
Test the Connection Defined in an EAM System Record	222
Configure SAP Task and Confirmation Creation	223
Configure the Query Get Tasks for Work Order Generation	225
Schedule Work Orders	226
Create CMMS Classification Type Records	228
ldentify Classifications to Extract	229
Identify Characteristics to Extract	230
Refresh GE Digital APM to Reflect Current SAP Classifications and Characteristics	231

A	About Classification Hierarchies	. 232
A	About Extracting Characteristics	. 236
A	About Site Filtering in the EAM Adapters	. 237
I	mport Notification Management File	.239
De	ploy the SAP PI Adapters	. 240
[Deploy the SAP PI Adapters for the First Time	.241
ι	Jpgrade the SAP PI Adapters to EAM SAP PI V2.0.0	. 242
I	mport Notification Management File	.243
I	mport the Design Objects	244
I	mport the Configuration Object	.246
ľ	Modify the Baseline Communication Channels	. 248
A	Activate the RFCReceiver_SAP Object	. 250
[Define the Command Name in SAP	.252
I	nstall the SAPCAR File on the APM Connect Server	. 253
(Create SAP PI Directory Structure	254
Ove	rview of APM Connect	255
Ov	erview of the EAM Adapters	. 256
EA	M Adapter Workflow	.257
Ov	rerview of the SAP Adapters	. 258
E	Employ the Notification Management Adapter	.259
	Create an SAP Notification from a Recommendation Record	260
	Update an SAP Notification from a Recommendation Record	. 262
E	Employ the Work Management Adapter	263
	Work Management Workflow	.264
	Create a Task Record	. 266
	Create an Event Record or Inspection Record	. 268
	Close a Work Order	. 269
	Update an SAP Confirmation by Updating the Actual Work Time in a Confirmation Record	271
	Validate SAP Confirmations Against GE Digital APM Confirmation Records	.272

M	lanage Filter Parameters in the Context File	274
	Apply Common Filter Parameters	. 275
	Apply Equipment Filter Parameters	. 279
	Apply Functional Location Filter Parameters	. 282
	Apply Work History Filter Parameters	. 285
	Apply Technical Characteristics Filters	.289
	Apply Work Management Filters	. 292
Α	bout the SAP Adapters	. 295
	About the Equipment and Functional Location Adapters	.296
	About the Work History Adapter	. 298
	About the Technical Characteristics Adapter	309
	About the Work Management Adapter	.316
	About Filter Parameters	. 322
R	eference Information: SAP Adapters	.325
	SAP Adapter Data Model	326
	About Site Filtering in the EAM Adapters	328
	Family Field Descriptions	330
	CMMS Characteristic	. 331
	CMMS Classification	.333
	CMMS Classification Type	335
	EAM System	337
	Technical Characteristic	. 340
	SAP Transactions-Quick Reference	. 341
	SAP Adapter Mappings	.342
	SAP Equipment Mappings	. 343
	SAP Functional Location Mappings	. 349
	SAP Work History Mappings	. 353
	SAP Work History Detail Mappings	. 374
	SAP Technical Characteristics Mappings	377
	SAP Work Management Mappings	379

	SAP Recommendation Mappings	.381
	SAP Task Value Mappings	.384
0	verview of the Maximo Adapters	. 388
	Create Maximo Work Orders or Service Requests	.389
	About Extracting Data From Maximo	.390
	Reference Information: Maximo Adapters	.393
	Maximo Data Model	. 394
	About Site Filtering in the EAM Adapters	.396
	Maximo Values Mapped to GE Digital APM Records	. 398
	Maximo Equipment Records Mappings	. 399
	Maximo Functional Location Mappings	. 402
	Maximo Work History Mappings	. 404
	Maximo Work History Detail Mappings	413
	Maximo Recommendation Mappings	.416
M	lanage Jobs in the Administration Center	418
	Schedule a Job	.419
	Execute a Run-Now Job	.421
	View the Execution Log	.422
	Update Existing Jobs	.423
API	M Connect Administrative Help	425
Α	PM Connect EAM Jobs	.426
	Access APM Connect EAM Jobs	.427
	Access the Details of an EAM Job	428
Α	PM Connect	. 430
	Access the APM Connect Page	.431
	Establish Connection from GE Digital APM	. 432
	Determine Logging Level	.433
	Schedule Work Orders	.434
	APM Connect Connection Records	.436

APM Connect System Requirements

License Requirements

APM Connect has a three-tier license system which enables the APM Connect Framework. One of the following license types is required to take advantage of APM Connect functionality:

- APM Connect Basic
- APM Connect Plus
- APM Connect Studio

Additional Licensing

The following additional licenses may also be required to take advantage of the SAP Adapters:

- **SAP Integration Interfaces**: Enables the SAP Equipment, Functional Location, Work History, and Notification Creation Adapters.
- SAP Technical Characteristics: Enables the SAP Technical Characteristics Adapter.
- SAP Work Management: Enables the SAP Work Management Adapter

The following additional licenses may also be required to take advantage of the SAP PI Adapters:

• SAP Process Integration: Enables the SAP PI Adapters.

The following additional license may also be required to take advantage of the Maximo Adapters:

• Maximo Interfaces: Enables the Maximo Equipment, Functional Location, Work History, Service Reguest, and Work Order Generation Adapters.

Note: There is no additional license required to take advantage of the Data Loader functionality.

Additional Components Required

In addition to the basic GE Digital APM system architecture, your system must also contain the following components:

Minimum Software Requirements

- Windows Server 2008 R2
- Windows Server 2012
- Java SE 8 Update 131 or higher
- The third-party components listed in the following grid.

Note: For assistance with accessing these file, contact the GE Digital Professional Services department.

Third-Party File Name	Version	Where You Can Obtain It	
edtftpj.jar	Version: 2.0.5	http://enterprisedt.com/products/edtftpj/	
ftp4j-1.5.1.jar	Version: 1.5.1	http://www.sauronsoftware.it/projects/ftp4j/	
jboss-seri- alization.jar	Version: 1.0.3.GA	http://serialization.jboss.org/downloads	
trove.jar	Version: 1.0.2	http://trove4j.sourceforge.net/	
xom-1.2.7.jar	Version: 1.2.7	http://www.xom.nu/	

Recommended Software

• Windows Server 2012 R2

• Windows 7 64-bit OS

Note: Windows 8 operating system is not supported.

Browser Requirements

Web Browser	Recommended or Supported
Microsoft Internet Explorer 11	Recommended
Mozilla Firefox 13 to 28	Recommended
Microsoft Internet Explorer 10	Supported
Apple Safari 5 to 7	Supported
Google Chrome 22 to 34	Supported

Minimum Hardware Requirements

- Four Processor Core, 2.0 GHz
- 8 GB RAM
- 100 GB Free Disk
- 100 MB Network Interface
- 10,000 RPM SATA NAS/SAN fabric 1G interfaces

Recommended Hardware

- 15 Processor, 2.0 + GHz
- 32 GB RAM
- 300 GB Free Disk
- 1 GB Network Interface
- 10,000 RPM SAS NAS/SAN fabric 10G interfaces

(i) Hint: APM Connect is input and output intensive, and requires a lot of storage space. Faster storage is the best way to improve performance.

Depending upon how your system is configured, these requirements may not be sufficient. Parameters that affect the hardware requirements include the number of users, modules purchased, database size, and other factors that can vary from one customer to another. For help refining your specific system requirements, contact GE Digital.

SAP System Requirements

- **SAP Backend System**: An SAP server machine with an ECC system. The following versions are supported:
 - SAP ECC 6.0 (Enhancement Packs [EhP] 1 and above)
- SAP Database: A database that contains the SAP data model and data.
- SAP Internet Transaction Server (ITS): Version 6.20 or higher.
- SAP Java Connector Files (SAP JCO) download from the SAP marketplace.
 - sapjco.dll
 - sapjco3.dll
 - sapjco3.jar

SAP PI System Requirements

- SAP Backend System: An SAP server machine with an ECC system. The following versions are supported:
 - SAP ECC 6.0 (Enhancement Packs [EhP] 1 and above)
- SAP PI: An SAP PI system 7.00 and above, up to SAP PI 7.40.

Maximo System Requirements

APM Connect supports Maximo versions above 7.1.1.6.


- Maximo Application Server: A Maximo Application Server machine that houses the Maximo Web Services and is running version 7.1, 7.5, or 7.6.
- Maximo Database Server: A database that houses the Maximo data model and data and is running a version that is supported by the Maximo Application Server.
 For details on requirements of the Maximo Database Server, see the Maximo documentation.

- Maximo Client Workstation: A computer that is used to access the Maximo application. For details on the requirements of the Maximo Client workstation, see the Maximo documentation.
- Maximo Administrative Workstation: A computer that contains the Maximo application. For details on the requirements of the Maximo Administrative workstation, see the Maximo documentation.

System Architecture for EAM Adapters

Single Server Configuration (Recommended)


The single server configuration is the simplest way to configure APM Connect. However, it does include an embedded database. The following image depicts this configuration:



External Database Configuration

Many organizations choose to separate their databases. It is possible to install the intermediate repository database on an external server, and keep APM Connect Systems database on a different server. The following image depicts this configuration:

Note: The external configuration will affect performance. The single server configuration results in faster performance.



Deploying APM Connect

After you have installed and configured the basic GE Digital APM system architecture, you will need to perform some configuration steps specifically for APM Connect.

Supported Features in APM Now

In the APM Now environment, the following features are unavailable:

- · ASI for SAP
- SAP PI
- SAP Technical Characteristics Adapter
- SAP Work Management Adapter
- Maximo Integration

All other APM Connect features are available.

Deploy APM Connect

The checklists in this section of the documentation contain all the steps necessary for deploying and configuring this module whether you are deploying the module for the first time or upgrading from a previous module.

Deploy the APM Connect Base

The checklists in this section of the documentation contain all the steps necessary for deploying and configuring this module whether you are deploying the module for the first time or upgrading from a previous module.

Deploy the APM Connect Base for the First Time

The following table outlines the steps that you must complete to deploy and configure this module for the first time. These instructions assume that you have completed the steps for deploying the basic GE Digital APM system architecture.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.

Note: If you are deploying this module in APM Now, before you begin completing these tasks, review the system requirements for this module to identify the supported features for this module in APM Now. Unless noted, all deployment tasks in the following table are applicable for the deployment of this module in APM Now.

Step	Task	Notes
1	Ensure that you meet the software and hardware system requirements for APM Connect.	This step is required.
2	On you APM Connect server, <u>run the</u> <u>third-party software batch file</u> .	This step is required
3	On your APM Connect Server, <u>run the</u> <u>APM Connect installer</u> .	This step is required.
4	On the APM Connect server, install the Meridium web services.	This step is required only if you are completing an on-premises deployment.
5	On your APM Connect server, enable Internet Explorer for APM Connect.	This step is required only if you are using Internet Explorer to access the APM Connect Administration Center.
6	On your APM Connect server, <u>update</u> <u>PostgreSQL networking configuration</u> .	This step is required.
7	On you APM Connect sever, <u>access the APM Connect Administration Center</u> web application.	This step is required.
8	On you APM Connect sever, change the APM Connect Administration Center user password.	This step is required.
9	On your APM Connect Server, <u>validate</u> <u>the APM Connect Administration</u> <u>Center license</u> .	This step is required only if your APM Connect Administration Center license it not automatically validated.

Step	Task	Notes	
10	In the APM Connect Administration Center, configure the APM Connect Administration Center web application.	This step is required.	
11	In the APM Connect Administration Center, set user permissions.	This step is required.	
12	In the APM Connect Administration Center, authorize users for projects.	This step is required.	
13	In GE Digital APM, establish the connection from GE Digital APM to APM Connect.	This step is required only if you are completing an on-premises deployment.	
14	On the APM Connect Server, <u>create a service user.</u>	This step is required.	
license	⚠ IMPORTANT: Each of the following tasks may be required depending on the license that you have purchased and the APM Connect component that you are deploying.		
15	Configure the APM Connect Administration Center for the Studio.	This step is required only if you have the APM Connect <i>Studio</i> license.	
16	On the APM Connect server, <u>install the Studio</u> .	This step is required only if you have the APM Connect <i>Studio</i> license.	
17	Deploy the Data Loaders.	This step is required only if you are deploying the Data Loaders.	
18	Deploy the Maximo Adapters.	This step is required only if you are deploying the Maximo Adapters.	
19	Deploy the SAP Adapters.	This step is required only if you are deploying the SAP Adapters.	

Upgrade the APM Connect Base to V2.0.0

The following table outlines the steps that you must complete to upgrade this module to V2.0.0.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.

Upgrade from V1.0.0 through V1.0.3

Step	Task	Notes
1	Uninstall APM Connect.	This step is required.
2	Complete the steps to deploy the APM Connect Base for the first time.	This step is required.

Run the Third-Party Software Batch File

APM Connect requires third party software files for FTP capabilities and improved Java performance. This topic describes how to incorporate these components into the jobs.

Steps

- 1. On your APM Connect server, access your APM Connect installation package, and then navigate to the **Jobs** folder.
- Right-click on the folder ApplyThirdPartySoftware_0.1.zip, and then select Extract All.

The **Extract Compressed (Zipped) Folders** window appears.

3. Select Extract.

The files are extracted, and the folder **ApplyThirdPartySoftware_0.1** appears in the same directory.


- 4. Download the <u>third party software files</u>, and then create a directory on the APM Connect server containing those files.
- 5. Open a command prompt, and navigate, to <root>ApplyThirdPartySoftware_0.1\ApplyThirdPartySoftware.
- 6. Enter the command following command: ApplyThirdPartySoftware_run.bat --context_param JOBS_DIR=<JOB PACKAGE DIR> --context_param THIRD_PARTY_SOFTWARE_DIR>.
 - <JOB PACKAGE DIR>: Replace with the filepath to the directory that contains the job zip files (e.g., C:/APMConnect/Jobs).
 - <YOUR THIRD_PARTY_SOFTWARE_DIR>: Replace with the filepath for the directory that you created in step 4 (e.g., C:/APMConnect/ThirdPartySoftware).

(i) **Hint**: When entering a directory in a command prompt window, the file path must use the forward slashes.

7. Execute the command by pressing Enter.

The adapter jobs are updated with the third-party software component, and a message appears on the command prompt window, indicating that the update is complete. Additionally, a new folder is created: **updated_jobs**.

Note: The jobs contained in the updated_jobs folder are the jobs that will be used to facilitate the data transfer from the source to GE Digital APM.



What's Next?

• Refer back to the first-time deployment workflow.

Run the APM Connect Installer

The APM Connect installer completes many tasks, including installing Java, installing APM Connect Windows services, and installing the intermediate repository (PostgreSQL).

<u>MPORTANT:</u> Each of the following steps may be required depending on the license that you have purchased and the APM Connect component that you are deploying.

Before You Begin

Before you can run the APM Connect Installer, you must:

- Access the APM Connect installation package.
- Ensure that your system meets the APM Connect system requirements.
- For SAP integrations, download the <u>SAP Java Connector Files (SAP JCO)</u> from the SAP marketplace.


Steps

- 1. On your APM Connect server, access the APM Connect installation package, navigate the *Installer* folder, and then open it.
- 2. Double-click the file APMConnect-Base.exe.

A message appears, asking if you want to allow the installer to make changes to your machine.


3. Select **Yes**.

The **Setup - APM Connect** window appears.



4. Select **Next**.

The **Select Destination Location** screen appears.




5. By default, the APM Connect software will be saved to the following folder: C:\APMConnect. If you are satisfied with the default location where the software will be installed, select Next.

-or-

If you want to change the location where the software will be installed, select **Browse...**, and then navigate to the location where you want to install the APM Connect software. The folder path that you select will be displayed in place of the default folder path. When you are satisfied with the installation location, select **OK**, and then select **Next**.

The **Select Components** screen appears.



6. If you want to install all components, select **Next**.


-or-

As needed, clear the check boxes based on your APM Connect license and the APM Connect component(s) you are deploying:

- Install Oracle Java JDK 1.8 (uncheck if java already installed): If Java JDK 1.8 is already installed on your machine, clear the check box.
- Install PostgreSQL (required unless using external database): If you are using an external database configuration, clear the check box.
- Install APM Connect Container (required unless already installed): If you
 have previously installed the APM Connect Container, clear the check box.

7. Select **Next**.

The **Select Start Menu Folder** screen appears.




8. By default, the Start Menu folder will be saved to the following folder: **APMConnect**. If you are satisfied with the default location where the software will be installed, select **Next**.

-or-

If you want to change the location where the folder will be saved, select **Browse...**, and then navigate to the location where you want to install the APM Connect software. The folder path that you select will be displayed in place of the default folder path. When you are satisfied with the installation location, select **OK**, and then select **Next**.

The **Select Additional Tasks** screen appears.



9. If you want to perform all additional tasks, select **Next**.


-or-

As needed, clear the check boxes based on your APM Connect license and the APM Connect component(s) you are deploying:

- Create a desktop shortcut: If you do not want to create a shortcut on your desktop, clear the box.
- Set JAVA_HOME environment variable: If Java is already installed, and an environment variable does not need to be created, clear the check box.
- **APMConnect Services**: If the APM Connect Services do not need to be installed, clear the check box.
- **Tomcat Windows service**: If the Tomcat Windows service does not need to be created, clear the check box.
- APMConnect Container service: If you don't want to install the APM Connect Container service, clear the check box.
- Configure APMConnect Container service: If you don't want to configure the APM Connect Container service, clear the check box.
- Install APM Connect Container service SAP JCO driver software: If your source system is SAP, select this check box.


10. Select Next.

The **Ready to Install** screen appears.



11. Review the items to be installed, and then select **Install**.


If you selected **Install APM Connect Container service SAP JCO driver software** on the previous screen, the **Select the SAP JCO Driver Location** screen appears.



Note: If you did not select Install APM Connect Container service SAP JCO driver software, the Select the Job Location screen appears, and you can proceed to Step 13.

12. In the **SAP Bundle** box, specify the location of the file **sapjco3.jar**, which is part of the SAP Java Connector Files (SAP JCO) that you downloaded from the SAP marketplace, and then select **Next**.

The **Select the Job Location** screen appears.




13. By default, the folder containing the job files is specified as **C:\APMConnect\Downloaded Jobs Package**. If this location is correct, select **Next**.

-or-

If this location is incorrect, select **Browse...**, navigate to the location where the jobs package is located, select **OK**, and then select **Next**.

Note: The jobs package is not part of the APM Connect Installation package. Instead, you will receive it as a separate artifact (e.g., download from a designated ftp site).

The **Select the APMConnect License file** screen appears.




14. By default, the folder specified is **C:\APMConnect\license**. If this location is correct, select **Next**.

-or-


If this location is incorrect, select **Browse...**, navigate to the location where the license file is located, select **OK**, and then select **Next**.

The **APMConnect Server Information** screen appears.




15. In the **Hostname** box, enter the name of you APM Connect server, and then select **Next**.

The **Installing** screen appears, displaying an installation progress bar.



Once the progress bar indicates that the APM Connect installer is *Finishing installation...*, **Java SE Development Kit <JAVA_VERSION_NUMBER> - Setup** window appears.



16. Select Next.

The **Select optional features to install** screen appears.

17. Select **Next**.

The Java installation progress bar appears. Once the progress bar indicates that the process is complete, the **Destination Folder** screen appears.

18. Select **Next** to install Java in the default location.

<u>MPORTANT</u>: These instructions assume that Java is installed in the default location.

The progress bar reappears. After the progress bar indicates that the installation is complete, the Successfully Installed Java SE Development Kit <JAVA_VERSION_NUMBER> screen appears.

19. Select Close.

Java is installed.


A command prompt appears, prompting you to press any key to continue.

(i) Hint: If an error appears on the command prompt window, refer to creating

Java environment variables.


20. Press any key.

The command prompt window closes, then the **Installing** screen reappears briefly, and then the **Setup** dialog box appears, displaying the JavaHome path.



21. Select OK.

The **Setup - PostgreSQL** screen appears.



22. Select Next.

The **Installation Directory** screen appears, prompting you to select the location where PostgreSQL for APM Connect will be installed.

23. By default, PostgreSQL will be saved to the following folder: C:\Program Files\PostgreSQL\9.6. If you are satisfied with the default location, select Next.

-or-

If you want to change the location where the software will be installed, select the button, then navigate to the location where you want to install PostgreSQL for APM Connect, and then select **Next**.

The **Data Directory** screen appears.

24. Select Next.

The **Password** screen appears.

25. In the **Password** box, and in the **Retype password** box, enter a password.

(i) **Hint:** This password will be used as a service account for PostgreSQL, and is needed in later configuration. Be sure to record it. Additionally, this documentation assumes *admin* as the password, and uses it in subsequent default configurations.

26. Select Next.

The **Port** screen appears.

27. If you are satisfied with the default port, select **Next**.

(i) **Hint:** The port number is needed in later configuration. Be sure to record it. Additionally, these instructions and all subsequent instructions assume that the default port 5432 is used.

-or-

In the **Port** box, enter the port on which you prefer the server to listen, and then select **Next**.

The **Advanced Options** screen appears.


28. Select Next.

The **Ready to Install** screen appears.

29. Select Next.

The **Installing** screen appears, displaying an installation progress bar. After the installation bar indicates that the installation is complete, the **Completing the Post-greSQL Setup Wizard** screen appears.

30. Clear the Stack Builder may be used to download and install additional tools, drivers and applications to complement your PostgreSQL installation check box.




31. Select Finish.

PostgreSQL server is installed, then the **Installing** screen reappears briefly, and then **Completing the APM Connect Setup Wizard** appears.

Note: If you have selected the installation of APM Connect Container service or the SAPJCO driver software, the Administrator: Windows Power Shell and Administrator: Karaf windows appear. Installation progress may not be visible on the screen for 2-3 minutes. During this time, do not press any key or close the windows.

The **Yes, restart the computer now** check box should be selected.



32. Select Finish.

The APM Connect installer has completed its operations, and the machine should restart automatically.

33. If it does not do so automatically, restart your machine.

What's Next?

Install the Meridium Web Service

<u>MPORTANT</u>: This step is required only if you are deploying APM Connect onpremises. If you are deploying in APM Now, you can skip this procedure, and proceed to the next step in the APM Connect Base First-Time Deployment Workflow.

Steps

- 1. On the APM Connect server, access the GE Digital APM distribution package, and then navigate to the folder \\Setup\Meridium APM Server and Add-ons.
- 2. Double-click the file **Setup.exe**.

The **Welcome** screen appears.

3. Select **Next**.

The **License Agreement** screen appears.

4. Read the License Agreement and, if you agree, select the I accept the terms of the license agreement check box. Then, select Next.


The **Select Installation Location** screen appears.

5. Select **Next** to accept the default location.

The **Select the features you want to install** screen appears.

6. Select the **Meridium Integration Services** option.

Note: While additional options are available for selection, these options are not meant to be installed on with the APM Connect server. These instructions assume that you want to install only Meridium Integration Services.



7. Select **Next**.

The **Websites** screen appears.

8. Select Next.

The Complete the Installation screen appears.

9. Select Install.

The **Setup Status** screen appears, displaying a progress bar. Once the installation is complete, the **Installation is complete screen** appears.

10. Select Finish.

The Meridium Integration Services installation is complete

What's Next?

Enable Internet Explorer for APM Connect

<u>MPORTANT</u>: This step is required only if you are using Internet Explorer to access the APM Connect Administration Center. If you are not using Internet Explorer, you can skip this procedure, and proceed to the next step, in the <u>APM Connect Base First-Time Deployment Workflow</u>.

Steps

1. On the APM Connect server, access **Control Panel\Network and Internet**, and then select **Internet Options**.

The Internet Properties screen appears

2. Select the **Security** tab, then, in the **Select a zone to view or change security settings** section, select **Local intranet**, and then select **Custom level...**.

The **Security Settings -Intranet Zone** screen appears.

- 3. In the **Settings** section, access the **Include local directory path when uploading files to a server**, and select **Disable**.
- 4. Select OK.

The **Security Settings -Intranet Zone** screen closes.

On the Internet Properties screen, select Apply.
 Internet Explorer is configured accommodate APM Connect.

What's Next?

Update PostgreSQL Networking Configuration

To allow connections from the APM server to APM Connect, you must update the Post-greSQL networking configuration. This topic describes how to perform the configuration update.

Steps

- On the machine on which you installed APM Connect, navigate to your PostgreSQL installation files. The default location is <root:>\Program Files\PostgreSQL\9.3\data.
- 2. Locate the configuration file *pg_hba.conf*, right-click the file, and then open it with a text editor.

The file *pg_hba.conf* opens in the text editing application.

3. Scroll down to the end of the document and locate the following line of text: *host all all 127.0.0.1/32 md5*

```
# TYPE DATABASE USER ADDRESS METHOD

# IPv4 local connections:

host all all 127.0.0.1/32 md5

# IPv6 local connections:

host all all ::1/128 md5

# Allow replication connections from localhost, by a user with the

# replication privilege.

# host replication postgres 127.0.0.1/32 md5

# host replication postgres ::1/128 md5
```

4. Save the file, and then close the text editor.

PostgreSQL is now configured to open the connection from the GE Digital APM Server.

What's Next?


Access the APM Connect Administration Center

The APM Connect Administration Center is allows you to execute extraction and load jobs. Before you can begin executing jobs, you must set up the APM Connect Administration Center. This topic explains how to access and deploy the APM Connect Administration Center for the first time.

Steps

1. Open a web browser, and then enter the following URL into your web browser: http://localhost:8080/apmconnect/.


The **Login** window appears.



- 2. In the **Password** box, enter *admin*.
- 3. Select OK.

The **Login** window disappears, the **Database parameter** section is fully visible, and a check is performed by the APM Connect Administration Center.


<u>MPORTANT</u>: If your license does not validate, you can <u>validate your license</u> <u>manually</u>.



4. Select Go to login page.


The **Login** page appears.

- 5. In the **Login** box, enter the default username: *admin@company.com*.
- 6. In the **Password** box, enter the default password: *admin*.



7. Select Login.

The APM Connect Administration Center is successfully deployed, and the APM Connect Administration Center **Welcome** page appears.




What's Next?



Change the APM Connect Administration Center User Password

Steps

- 1. Access the APM Connect Administration Center.
- In the Menu pane, in the Settings section, select the Users tab.
 The Users workspace appears.
- 3. In the **Users** workspace, select the user whose password you want to change.
- 4. In the **Data** pane, select **change password**.



The **User Password** window appears.

- 5. Enter the new password, and enter it again to confirm.
- 6. Select Validate.

The password has been changed.


Validate the APM Connect Administration Center License


<u>MPORTANT</u>: This step is required only if you license was *not* validated automatically when you <u>accessed APM Connect Administration Center</u>. If you did not receive the *No token set* error when accessing the APM Connect Administration Center, you can skip this procedure, and proceed to the next step, <u>Configure the APM Connect Administration Center</u>, in the <u>APM Connect Base deployment workflow</u>.

To use the APM Connect Administration Center, you must validate your Administration Center license. Typically, validation is done automatically. However, user specific environment configuration, such as firewalls, may require manual validation. This topic describes how to manually validate your APM Connect Administration Center license.

Steps

If you receive the *No token set* error when accessing the APM Connect Administration Center, as shown in the following image, select Validate your license manually.





The Validation request screen appears.

- 2. In the Validation message (put this message on the form of the next Link) box, copy the text.
- 3. In the Validation link (put the generated validation token to the next text Area) section, select link.

If a browser opens, displaying the **Enter your validation request** page, skip to step 6.

-or-

If a browser does not open, proceed to the next step.

- 4. Right-click **link**, and then select **copy link text**.
- 5. Via email or chat, send the link to a machine with internet access that is not behind the firewall, and then, on that machine, paste the link into a browser.
 - The **Enter your validation request page** appears in your browser.
- 6. Paste or enter the text from the Validation message (put this message on the form of the next Link) box into the box in the browser.



7. Select **Get your validation token**.

The **Copy your validation token** screen appears.

- 8. Copy the text in the box.
- 9. Return to the APM Connect Administration Center.
- 10. Paste the token text into the Validate box.
- 11. Select Validate.

The license is validated manually.

What's Next?

Configure the APM Connect Administration Center

Depending on whether you are using the EAM Adapters (SAP Adapters and Maximo Adapters) or the Data Loaders, configuring the APM Connect Administration Center requires defining parameters for some or all of the following components: SVN, Commandline, Job conductor, Monitoring, and Log4j. This topic describes how to configure these parameters in the APM Connect Administration Center.


Steps

- 1. If you not already in the APM Connect Administration Center, access the it via http://localhost:8080/apmconnect/.
- 2. If prompted, log in to the APM Connect Administration Center.
- 3. In the **Menu** pane, in the **Settings** section, select the **Configuration** tab. The **Configuration** pane appears.
- 4. Select the **Job conductor** (**7 Parameters**) group to expand the workspace.
- 5. According the following table, enter the recommended parameters.

Note: You can accept the default values of parameters not listed in the table.

Parameter	Description	Recommended or Default Value
Generated jobs folder	The path to the folder with the Job execution archives.	C:\APMConnect\Utilities\jobserver\generated_ jobs
Tasks logs folder	The path to the folder with the Job execution logs.	C:\APMConnect\Utilities\jobserver\execution_ logs


The default parameters are configured as shown in the following image.



- 6. Select the **Monitoring (2 Parameters)** group to expand the workspace.
 - Note: Configuring this parameter is optional.
- 7. Select the **Log4j (4 Parameters)** group to expand the workspace.
- 8. According following table, enter the necessary parameters.

Parameter	Description	Recommended or Default Value
Technical file appender	The path to the technical log file of the APM Connect Administration Center.	C:/APMConnect/Utilities/Tomcat/logs/technical.log
Technical log threshold	The level of logs you want to append.	WARN
Business log file path	The path to the business log file of the APM Connect Administration Center.	C:/APMConnect/Utilities/Tomcat/logs/business.log
Technical logstash appender	The host and port cor- responding to the Logstash instance.	localhost:8050

The default parameters are configured as shown in the following image.



The APM Connect Administration Center parameters are configured.

What's Next?


Set User Permissions

To begin using the APM Connect Administration Center to run data extractions, or Jobs, you must first give the admin user all of the user roles.

Steps


- 1. In the **Menu** pane, in the **Settings** section, select the **Users** tab.
- 2. Select the user that you want to be the admin user.

The **Data** pane is activated.



3. On the Data pane, on the **Role:** box row, select */*.

The Role Selection window appears.



4. Select each check box to assign the user all roles, or select the box of the role(s) you want to assign the user, according to the following table:

<u>MPORTANT:</u> You must designate at least one user the role of Operation Manager in order to access the Job Conductor.

Note: No matter their assigned roles or rights, <u>a user must be authorized for a project</u> before they can view or change sections associated with a project.

Role	Read Permissions by Module	Write Permissions by Module
Administrator	None.	License, Configuration, Users, Projects, Rights Management, Backup, Notifications, Software Updates
Operations Manager	Projects, EBS Publisher, Service Activity Monitoring, Authorization, Service Registry, Studio, Repository Browser	Configuration, Lock, Notifications, Servers, Job Conductor, ESB Conductor, Execution Plan, Monitoring Audit BRMS (Drools), Service Locator
Designer	Configuration, Projects, Servers, Job Conductor, EBS Conductor, EBS Publisher, Execution Plan, Monitoring	Execution Plan, Audit, BRMS (Drools), Service Locator
Viewer	Servers, Job Conductor, Execution Plan, Audit, Studio, Repository	None.

- 5. Select **Validate**.
- 6. Select **Save**.

The user permissions are set.

What's Next?


Authorize Users for Projects

Before a user can begin work on a specific project, that user must be authorized to work on that project. Each project can have multiple users with differing roles. Users can also be authorized for multiple projects. This topic explains how to authorize a user for a project.

Steps

1. In the **Menu** pane, in the **Settings** section, select **Project authorizations**.

The **Project Authorizations** workspace appears displaying the **Project** section which lists all the projects to which you can add users and the **User Authorizations for the Project: <name>** section which lists all users that can be added to the project.



- 2. From the **Project** list, select the project to which you want to add a user.
- 3. To give a user *read* permissions only, in the **Right** column in the row for that user, select the button.
- 4. To give a user *read and write* permissions, in the **Right** column in the row for that user, select the button.

(i) **Hint:** The icons in the **Right** column will be appear in a lighter color if the user is not authorized for a specific action, and be colored if the user has the required permissions.

The user is now authorized for the project.


What's Next?

Create a Service Account User

For security reasons, it is important to limit the number of users that can access the file shares between the SAP server and the APM Connect server. The best way to do this is to create one service account user to run the Jobserver and to access the SAP file shares on the SAP server. This topic describes how to create a service account user that has access to the SAP server and runs the Jobserver.

Steps

- 1. In the same domain as the SAP server, create an active directory user.
- 2. On the SAP server, create a new folder that will be shared with the new user you just created.
- 3. Right-click the new folder.
- 4. Select Properties.
 - The **<Folder Name> Properties** window appears.
- 5. Select the **Sharing** tab.



6. Select Share...

The **File Sharing** window appears.

- 7. In the text box, enter the user name of the service account.
- 8. Select Add.

The new user appears in the list of users.

- 9. In the **Permission Level** column, select \checkmark , and then select **Read/Write**.
- 10. Select Share.
- 11. Close the windows.
- 12. On the APM Connect server, select the Windows Start button to open the Windows Start menu.
- 13. In the **Search programs and files** box, enter *services*.

Services appears in the Programs list.


14. Open Services.

The **Services** window appears.

- 15. Right-click the *APM-CONTAINER* service.
- 16. Select Properties.

The **APM-CONTAINER Properties (Local Computer)** window appears.

17. Select the Log On tab.



- 18. Select This account:.
- 19. Enter the service account user.
- 20. Select OK.

The service account user has been created, authorized to run the Jobserver, and given access to the file shares on the SAP server.

What's Next?

Configure the APM Connect Administration Center for the Studio

<u>MPORTANT</u>: This step is required only if you have the APM Connect Studio license. If you are deploying APM Connect Base with a Basic or Plus License, skip this procedure and proceed to the next step in the APM Connect Base deployment workflow.

Steps

1. Open a web browser.


(i) Hint: APM Connect is most compatible with Google Chrome or Mozilla Firefox web browsers. It is not recommend using Internet Explorer to access the APM Connect Administration Center.

- 2. Enter the following URL into your web browser: http://localhost:8080/apmconnect/.
- 3. If prompted, log in to the APM Connect Administration Center.
- 4. In the **Menu** pane, in the **Settings** section, select the **Configuration** tab. The **Configuration** pane appears.
- 5. Select the **Svn (7 Parameters)** group to expand the workspace.
- 6. According to the following table, enter the necessary parameters.

Parameter	Description	Recommended or Default Value
Server loc- ation URL	URL location of the SVN server.	http://localhost/svn/MIAPMINT
Username	SVN user name created to use in the APM Connect Administration Center when installing the SVN server.	APM
Password	SVN password created to use in the APM Connect Administration Center when installing the SVN server.	Connect

Commit Log Pattern	SVN commit log according to your log format convention.	{0}
Library loc- ation URL	URL location of the SVN external libraries directory downloaded with the Studio.	Not Required
Library user- name	User name of the SVN user that has access to the libraries directory.	Not Required
Library pass- word	Password of the SVN user that has access to the libraries directory.	Not Required

The default parameters are configured as shown in the following image.




- 7. Select the **CommandLine/primary (5 Parameters)** group to expand the workspace.
- 8. According to the information in the following table, enter the necessary parameters.

Para- meter	Description	Recommend or Default Value
Host	The IP address of the CommandLine.	localhost

Port	The port number on which the CommandLine is queried.	8002
Job gen- eration folder	The path to the folder where Jobs are gen- erated.	<root:>\APMCon- nect\Utilities\cmdline\generationCache</root:>
User com- ponent path	The path to the folder where user components are stored.	<root:>\APMConnect\Utilities\cmdline\custom_com- ponents</root:>

The default parameters are configured as shown in the following image.



What's Next?


Install the Studio

<u>MPORTANT</u>: This step is required only if you have the APM Connect Studio license. If you are deploying APM Connect Base with a Basic or Plus License, skip this procedure and proceed to the next step in the APM Connect Base deployment workflow.

Steps

- 1. On the machine on which you installed APM Connect, access the Talend Studio installation package.
- 2. Open the file **TalendStudioInstall.exe**.

The **Setup-Talend Studio** window opens.



3. Select **Next**.

The **License Agreement** screen appears.

- 4. Read the entire license agreement, and then select one of the following options:
 - I accept the agreement: If you agree to the terms of the license agreement and want to continue. These instructions assume that you want to continue.

• I do not accept the agreement: This option is selected by default. If you do not agree to the terms of the license agreement and do not want to continue, select Cancel to exit the installer.

Next is enabled.


5. Select **Next**.

The **Select Destination Location** screen appears.

6. Select **Next**.

The **Select Components** screen appears.

7. Select the **Add Start Menu Entry** box, and then select the **Add Desktop Icon** box.



8. Select Next.

The **Select Start Menu Folder** screen appears.

9. Select **Next**.

The **Ready to Install** screen appears.

10. Select Install.

The **Installing** screen appears, displaying an installation progress bar. Once the installation is complete, the **Completing the Talend Studio Setup Wizard** screen appears.

11. Select Finish.

The installation is complete, and Talend Studio desktop icon is available.

What's Next?

Uninstall APM Connect

Before you can <u>upgrade the APM Connect Base</u>, you must uninstall your current version of APM Connect.

Steps

- 1. On the APM Connect server, access the **Uninstall or Change a Program** section of the Control Panel.
- 2. Select *APMConnect 1.0.3*, right-click, and then select **Uninstall**.
- 3. Access the **Services** section of the Control Panel (in the **Administrative Tools** section of **System and Security**) and stop the following services:
 - APM-CONTAINER
 - 7.0.57 APMConnect_Tomcat
- 4. Access the **Uninstall or Change a Program** section of the Control Panel again, select the Java programs (e.g., *Java 1.7.71* and *Java SE Development Kit 1.7.71*), right-click, and then select **Uninstall**.
- 5. On the APM Connect server, locate the folder *C:\APMConnect*, and then delete it.
 - (i) **Tip**: If files are locked and prevent you from deleting this folder, you may need to restart the APM Connect server machine.
- 6. Access the DOS Command Prompt window, and run the following commands:
 - SC DELETE APM-CONTAINER
 - SC DELETE APMConnect_Tomcat
- 7. Restart the APM Connect server machine.

APM Connect is uninstalled.

Set Java Environment Variables

Note: The Java Environment variables are set automatically when you <u>run the APM Connect installer</u>. However, if you need to update or reinstall Java without reinstalling APM Connect, complete these steps to configure Java on your APM Connect server.

Steps

1. On the APM Connect server, navigate to **Control Panel\System and Security\System** to open Window's system properties for the machine.

The **View basic information about your computer** screen appears.


- 2. In the **Control Panel Home** pane, select **Advanced systems setting**. The **System Properties** window appears, displaying the **Advanced** tab.
- 3. Select **Environment Variables**.

The **Environment Variables** window appears.

4. In the **Systems variables** section, select **New...**.

The **New System Variable** window appears.

- 5. In the **Variable name** box, enter JAVA HOME.
- 6. In the Variable value box, enter the path to the root jdk installation directory. If you installed Java in the default location, the path you should enter is C:\Program Files\Java\jdk<JAVA_VERSION_NUMBER>. For example, the default path for Java 8 is C:\Program Files\Java\jdk1.8.0 131




- 7. Select **OK**.
- 8. In the **Systems variables** section, select **New...**.

The **New System Variable** window appears.

9. In the Variable name box, enter JRE HOME.

10. In the Variable value box, enter the path to the root *jre* installation directory. If you installed Java in the default location, the path you should enter is C:\Program Files\Java\jdk<JAVA_VERSION_NUMBER>\jre. For example, the default path for Java 8 is C:\Program Files\Java\jdk1.8.0 131\jre



11. Select **OK**, and then close the properties screens.

The Java environment variables are created.

Deploy the Data Loaders

The checklists in this section of the documentation contain all the steps necessary for deploying and configuring this module whether you are deploying the module for the first time or upgrading from a previous module.

Deploy the Data Loaders for the First Time

The following table outlines the steps that you must complete to deploy and configure this module for the first time. These instructions assume that you have completed the steps for deploying the basic GE Digital APM system architecture.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.

Note: If you are deploying this module in APM Now, before you begin completing these tasks, review the system requirements for this module to identify the supported features for this module in APM Now. Unless noted, all deployment tasks in the following table are applicable for the deployment of this module in APM Now.

Step	Task	Notes
1	Deploy the APM Connect Base.	This step is required.
2	In the GE Digital APM web browser, configure SSL.	This step is required only if you are completing an on-premises deployment and if your GE Digital APM system is configured to use SSL.
3	On your APM Connect server and on your GE Digital APM Application Sever, set permissions for the APM Connect Directory.	This step is required.
4	On your APM Connect server, <u>deploy and configure data loaders files</u> .	This step is required.
5	In the APM Connect Administration Center, <u>create the Intermediate Repository database</u> .	This step is required.

Upgrade APM Connect Data Loaders to DL V2.0.0

The following table outlines the steps that you must complete to upgrade this module to DL V2.0.0.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.

Upgrade from DL V1.6.3

Step	Task	Notes
1	Upgrade the APM Connect Base.	This step is required.
2	Complete the steps to <u>deploy the data loaders</u> <u>for the first time</u> .	This step is required.

Upgrade from any Version DL V1.0.0 through DL V1.5.5

These instructions assume that you have completed the steps for upgrading the basic GE Digital APM system architecture.

Step	Task	Notes
1	Upgrade the APM Connect Base.	This step is required.
2	Complete the steps to <u>deploy the data loaders</u> <u>for the first time</u> .	This step is required.

Configure SSL

If your GE Digital APM Web Server is configured to use SSL, this step is required to use the Data Loader functionality.

Steps

1. Log in to your GE Digital APM web application, and then access your browsers certificate information.

Note: Typically you can access certificate information by selecting the lock icon in the address bar.

The **Certificate** window appears.

2. Select **Details**, and select **Copy to File...**.

The **Certificate Export Wizard** window appears.



3. Select Next.

- 4. In the **Export File Format** window, select the **DER encoded binary X.509 (.cer)** button, and then select **Next**.
- 5. On the **File to Export** window, select **Browse...**.
 - The **Save As** window appears.
- 6. Save the file to your Desktop under the name *certificate.cer*.
- 7. Select **Next**.



8. Select Finish.

The Certificate Export Wizard window appears.

- 9. Select OK.
- 10. Copy the certificate.cer file, and then paste it into the location of your machine's Java files.

For example, if your Java files are located at C:\Program Files\Java\jre7\bin, you will want to copy the certificate.cer file to that bin folder.

- 11. On the machine on which you are running GE Digital APM or APM Now, run the Command Prompt as an Administrator, and navigate to the location of your machine's Java files.
- 12. Enter keytool.


Commands for the **Key and Certificate Management Tool** appear in the Command Prompt.

- 13. In the last line line, C:\Program Files\Java\jre7\bin>, enter keytool –import –alias test –file certificate.cer –keystore publickey.store.
- 14. Enter a password, and confirm the password by re-entering it.In the Command Prompt, you are asked if you want to trust the certificate.
- 15. For yes, enter y.

The keystore file is created.

- 16. Log into an instance of the APM Connect Administration Center.
- 17. In the **Job Conductor** workspace, select the Job for which you would like to set parameters.
- 18. At the bottom of the **Job Conductor** workspace, select **Context parameters**.

The **Context parameters** section appears.



- 19. Enter the following values for the corresponding parameters:
 - TRUSTSTORE_FILE: The location of the certificate file
 - TRUSTSTORE_PASSWORD: The password you entered into the Command Prompt when you installed the certificate.
 - USE_SSL: true.

SSL is now enabled.

What's Next?

Refer back to the first-time deployment workflow.

Set Permissions for APM Connect Directory

Before you begin importing data into GE Digital APM using the Excel source files, you must set up a network folder share. The data is passed from the APM Server to the APM Connect server through a file share, a situation in which a folder on the network is shared and accessible to both servers. This topic describes the steps for setting up the permissions required to enable the file share.

Steps:

To create a domain user for the APM Container:


- 1. On the machine on which you installed APM Connect, from your desktop, select the Windows Start button to open the Windows Start Menu.
- 2. In the **Search programs and files** box, search for *Run*.

Run appears in the Programs list.

3. Open Run.

The **Run** window appears.

4. In the Open box, enter: services.msc.




5. Select **OK**.

The **Services** window appears.

6. Right-click **APM-CONTAINER**, and then select **Properties**.

The **APM-CONTAINER Properties** window appears.

- 7. Select the **Log On** tab, and then select **This account**.
- 8. Enter the credentials for a user within your network, designated to run APM Connect services.



Example: user1@meridium.com


- 9. Select **Apply**, and then select **OK**.
- Repeat Steps 6-8 for the service Apache Tomcat 7.0 APMConnect_Tomcat.
 A domain user has been assigned to run the APM Container service and the Tomcat service.

To create a Data Loaders file share:

<u>MPORTANT:</u> If you are employing a load-balancing setup using multiple servers, before you proceed, you must first configure the APM Server file share. If you are employing a standalone server, you may proceed with the following steps.

- 2. In the directory window, select **New folder**, and then name the folder with the


recommended name: DataLoaderFiles.




The Data Loader files folder is created.

- 3. Right-click the folder **DataLoaderFiles**.
- 4. Point to **Share with**, and then select **Specific people...**.

The File Sharing window appears.



- 5. Select the domain user that you indicated in **Step 8** of the **To create a domain user for the APM Container** section of this topic.
- 6. In the **Permission Level** column for that user, select the drop-down arrow, and then select **Read/Write**.



Note: Users running the APM-CONTAINER service and the APM Server must have Read/Write access to this folder.

7. Select **Share**.

Permission for the folder is granted to the user that you selected.

Grant Read/Write Access to the APMConnect folder:

1. Navigate to the **APMConnect** folder.


If you installed APM Connect in the default location the folder is *C:/APMConnect*.

2. Right-click on the folder **APMConnect**, and then select **Properties**.

The **APMConnet Properties** window appears.

3. Select the **Security** tab, and then select **Edit**.

The **Permissions for APMConnect** window appears.



4. Select Add....

The Select Users, Computers, Service Accounts, or Groups window appears.

- 5. In the Enter the object names to select(examples): box, enter the name of the APM Connect user that you indicated in Step 8 of the To create a domain user for the APM Container section of this topic.
- 6. Select Check Names.

The APMConnect user's name is validated.

7. Select OK.

The **Select Users, Computers, Service Accounts, or Groups** window closes, and the APM Connect user is populated in the **Group or user names** box.

8. Select the APM Connect user.

- 9. In the **Permissions for <Username>** box, on the **Full Control** row, select **Allow**.
- 10. Select OK.

The **Permissions for APM Connect** window closes.

11. On the **APMConnect Properties** window, select **OK**.

The APM Connect service user has access to the APM Connect folder.

What's Next?

• Refer back to the first-time deployment workflow.

Deploy and Configure Data Loader Files

Note: The APM Connect installer automatically deletes the file *Run-DataLoaderRoute.cfg* from the following location *C:\APMCon-nect\Utilities\runtime\deploy*, if it exists there. You must complete the remaining steps in this topic manually.

Steps

- 1. Access the APM Connect installation package, and then copy the file **Run-DataLoaderRoute.cfg**.
- 2. Navigate to <**root**>\APMConnect\Utilities\runtime\etc, and then paste the copied file in that location.
- 3. Open the file to edit, and then configure the following parameters:

Parameter	Description	Default or Recommended Value
context	Defines what Talend context environment is used.	Default.
TRUSTSTORE_FILE	The directory path to the dinoloader SSL configuration file.	Value is unique to the user.
TRUSTSTORE_PASSWORD	The password for the keystore files.	Value is unique to the user.
USE_SSL	Determines if SSL is used.	true: will use SSL.false: will not use SSL.
IR_HOST	Intermediary Repository host name.	Value is unique to the user.
IR_DATABASE	Database for the dinoloader job.	Value is unique to the user.

IR_USERID	Intermediary Repository user- name.	Value is unique to the user.
IR_PASSWORD	Intermediary Repository pass- word.	Value is unique to the user.
IR_PORT	Intermediate Repository port.	Default value is <i>5432</i> .
LOG4J_CONFIG_FILE	Log4j directory path.	C:/APMCon- nect/Config/log4j.properties
IS_LINUX	Indicates if the machine on which the Data Loaders are deployed is a POSIX-compliant operating system (e.g., Linux, UNIX, AIX, HPUX etc.) or another operating system.	 true: Enter true if you are deploying the Data Loaders on a POSIX-compliant operating system. false: Enter false if you are not deploying the Data Loaders on a POSIX-compliant operating system.
LINUX_BASE_PATH	The directory path where the data loader file share is mounted.	This parameter is required only if you are deploying the Data Loaders on a Linux machine. This path is defined by system administrator for the Linux machine, and the value is unique to the user.
org.a- pache.karaf.fea- tures.configKey	Karaf web console configuration tie-in is used to associate this configuration file with the RunDataLoaderRoute class.	Run- DataLoad- erRoute.talendcontext.Default MIMPORTANT: Do not modify this parameter.

- 4. Save the file.
- 5. In the installation package, copy the file **RunDataloadersRoute_0.2.kar**.

6. On your APM Connect server, navigate to <**root**>\APMCon-nect\Utilities\runtime\deploy, and then paste the copied file in that location.

Note: If new configuration is not automatically applied, restart the APM_CONTAINER service. This will force the changes to be applied.

What's Next?

• Refer back to the first-time deployment workflow.

Create the Intermediate Repository Database

Before you can run an extraction job, you must prepare the intermediate repository and enable the static data pull. This topic describes how to set up a repository and static data pull in preparation to run your first job.

<u>MPORTANT</u>: If you are using the Data Loaders and the SAP Adapters, you must deploy and run the *CreateIntermediateRepository* job for each set of adapters.

Before You Begin

Before you can prepare and deploy the repository, you must import the Create Intermediate Repository Job

Steps

1. Open and log in to the APM Connect Administration Center web application.

Note: The user logging in <u>must have access to the Job Conductor</u> by being designated the Operations Manager role. By default, users designated admin do not have Job Conductor permissions.

- 2. In the **Job Conductor** workspace, in the appropriate project, select the *CreateIntermediateRepository* Job.
- 3. At the bottom of the **Job Conductor** workspace, select **Context parameters**. The **Context parameters** section appears.
- 4. Configure the following parameters:

Context Parameter	Description
CONFIG_FILE_DIRECTORY	The file path to context files for the jobs.
PG_ADMIN_USERNAME	The user name for the PostGresSQL IR.
PG_ADMIN_PASSWORD	The password for the PostGresSQL IR.
apmconnect_Database	Enter your APM Connect database name.
	The default value is DINODB.

apmconnect_Login	Enter your APM Connect database username.
apmconnect_Password	Enter your APM Connect database password.
apmconnect_Server	Enter your APM connect server name

5. Select **Run**.

The intermediate repository is created for the project.

- 6. In the **Job Conductor** workspace, in the appropriate project, select the *CreateStaticData* Job.
- 7. Select Run.

The static data pull is enabled.

You are now able to execute the jobs.

What's Next?

- Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.
 -or-
- Return to the <u>Maximo Adapter workflow</u> for the next steps in the deployment process.
 - -or-
- Return to the <u>Data Loader workflow</u> for the next step in the deployment process.

Enable Test Connection

Note: This step is completed automatically when you <u>run the APM Connect installer</u>. These steps are included here for your reference if necessary.

Steps

- 1. Access your APM Connect Installation package, navigate to the Jobs folder, and then copy the file CheckConnections.jar.
- 2. On your APM Connect server, navigate to C:\APMConnect\Utilities\runtime\deploy.
- 3. In the deploy directory, paste the file CheckConnections.jar.

Results

• You can now test the connections required to complete a data load.


Change H2 Console Password

Note: This step is completed automatically when you <u>run the APM Connect installer</u>. These steps are included here for your reference if necessary.


This topic describes how to change the H2 Console password associated with the APM Connect Administration Center.

Steps

- 1. Access the APM Connect Administration Center.
- 2. In the **Menu** pane, in the **Settings** section, select the **Configuration** tab. The **Configuration** section appears.
- 3. Select the **Database (4 Parameters)** group to expand the workspace.
- 4. Highlight and copy the URL in the **URL** row.



- 5. Select the link in the **Web Console** row.
 - In a new browser tab, the **H2 Console Login** screen appears.
- 6. In the H2 Console, in the JDBC URL field, paste the copied URL.
- 7. In the **User Name** field, enter the user name. The default user name is *tisadmin*.
- 8. In the **Password** field, enter the password. The default password is *tisadmin*.



- 9. Select Connect.
- 10. In the H2 Console, in the **SQL statement** pane, enter the following command: SET PASSWORD '<password>'.

Note: The password must be in single quotes. Example: SET PASSWORD 'abcstrng!5'.

11. Select Run (Ctrl+Enter).

The H2 Console password is changed.

Create APM Service User

Note: This step is completed automatically when you <u>run the APM Connect installer</u>. These steps are included here for your reference if necessary.

Running jobs in the APM Connect Administration Center is perpetrated by users. The *apmService* user is required in order to facilitate communication between APM Connect and GE Digital APM.

Steps

- 1. In the APM Connect Administration Center, from the **Menu** pane, in the **Settings** section, select the **Users** tab.
- 2. Select Add.

The **Users** pane appears.

3. Enter the user information into the empty fields as necessary according to the following table:

Field	Description	Value
Login	Email login for user	apmService@meridium.com
First name	User first name	apm
Last name	User last name	service
Password	User password	apmConnect (default pass- word)
Туре	Type of data migration	Data Integration/ESB
Role	User role	Operation manager
Active	Select check box to signify active user	Must select check box

4. Select Save.

The apmService user is created, and it appears in the list of users.

Deploy the Maximo Adapters

The checklists in this section of the documentation contain all the steps necessary for deploying and configuring this module whether you are deploying the module for the first time or upgrading from a previous module.

Deploy Maximo Adapters for the First Time

The following table outlines the steps that you must complete to deploy and configure this module for the first time. These instructions assume that you have completed the steps for deploying the basic GE Digital APM system architecture.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.

1 Note: This GE Digital APM module is not available in the APM Now environment.

Step	Task	Notes
1	Deploy the APM Connect Base.	This step is required.
2	In GE Digital APM, assign security users to one or more of the APM Connect <u>Security Groups</u> .	This step is required.
3	On the APM Connect sever, configure the context <u>file</u> .	This step is required.
4	On the APM Connect server, <u>encrypt passwords</u> in the context file.	None
5	On the APM Connect sever, import notification management file.	This step is required.
6	In the APM Connect Administration Center, <u>configure the context parameters</u> .	This step is required.
7	In the APM Connect Administration Center, <u>create</u> the intermediate repository database.	None
8	In Maximo, <u>create object structures</u> .	This step is required.
9	In Maximo, <u>create web services</u> .	This step is required if you are <i>not</i> using the REST web services.
10	In Maximo, configure Default password.	This step is required.
11	In GE Digital APM, <u>create EAM System records</u> to identify your Maximo systems.	This step is required.

Upgrade Maximo to EAM MAX V2.0.0

The following table outlines the steps that you must complete to upgrade this module to EAM MAX V2.0.0 These instructions assume that you have completed the steps for upgrading the basic GE Digital APM system architecture.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.

Upgrade from any version EAM MAX V1.0.0 through EAM MAX V1.1.2

Step	Task	Notes
1	Upgrade the APM Connect Base.	This step is required.
2	Complete the steps to <u>deploy the Maximo</u> <u>adapters for the first time</u> .	This step is required.

Configure the Maximo Context File

Steps

- 1. On the APM Connect server, navigate to the <root:>/APMConnect/Config folder.
- 2. Rename the RENAME_TO_SYSTEM_NAME folder to the name of the system you will be using.
- 3. Open the folder, and then open the context file to edit.

<u>MPORTANT</u>: Changes made to the context file will override changes made in the APM Connect Administration Center Context parameters section.

Note: Multiple values can be entered into the filter parameters using comma separated values or standard wild cards values.

Intermediate Repos- itory (IR) Connection Parameters	Description	Default or Recommend Value
IR_HOST	IP address of the IR.	Value is unique to the user.
IR_PORT	Port number of the IR.	5432 (PostgreSQL default)
IR_DATABASE	Database in which the IR data is stored.	APMconnectIR_ <release number(x_x_x)="">.</release>
IR_SCHEMA	Schema associated with the IR.	Public
IR_USER_ID	IR user name.	Value is unique to the user.
IR_PASSWORD	IR system password.	Value is unique to the user.
IR_TALEND_OUTPUT	File share folder to which the Maximo Adapter will write files.	Value is unique to the user.
PG_ADMIN_USER	Administrator user name for the PostgresSQL IR.	Value is unique to the user, and is used when creating the IR database. It can be removed after the database is created.

PG_ADMIN_ PASSWORD	Administrator pass- word for the Post- gresSQL IR.	Value is unique to the user, and is used when creating the IR database. It can be removed after the database is created.	
APM Connection Parameters	Description	Default or Recommend Value	
APM_APP_SERVER	GE Digital APM Server name.	Value is unique to the user.	
APM_DATASOURCE	GE Digital APM data source to which the data will be exported.	Value is unique to the user.	
APM_USERID	The GE Digital APM APM Framework User ID.	Value is unique to the user.	
APM_PASSWORD	The GE Digital APM APM Framework password.	Value is unique to the user.	
SITE_REFERENCE_ EQUIP	Used to map the site reference value to a Maximo field. This dictates which Maximo field will be used as the site reference for GE Digital APM Equipment records.	You can enter a value defined in GE Digital APM. Note: The value that is entered will be applied to all records. -or- You can use the character # at the beginning and end of a GE Digital APM Field Name to indicate the field that is used to set to set the site reference.	

SITE_REFERENCE_FLOC	Used to map the site reference value to a Maximo field. This dictates which SAP field will be used as the site reference for GE Digital APM Functional Location records.	You can enter a value defined in GE Digital APM. Note: The value that is entered will be applied to all records. -or- You can use the character # at
		the beginning and end of a GE Digital APM Field Name to indicate the field that is used to set to set the site reference.
APM_WEBSERVICE	URL for the APM integration web services.	/MeridiumIntegrationServices
APM_CONNECTION_ TIMEOUT	How long, in seconds, GE Digital APM will wait for the connection to the Adapters before timing out.	300
APM_RECEIVE_ TIMEOUT	How long, in seconds, GE Digital APM will wait for the response from the Adapters before timing out.	600
Maximo Connection Parameters for Extraction Interfaces	Description	Default or Recommended Value
MAXIMO_USERID	Maximo system user ID.	Value is unique to the user.
MAXIMO_PASSWORD	Maximo system pass- word.	Value is unique to the user.

LANGUAGE	The Maximo letter code that represents the language of the description to transfer into GE Digital APM.	Value is unique to the user.
MAXIMO_REST_URL	The REST URL for the Maximo end point, and is used if you want to use the REST service component.	http:// <host>:<port>/maxrest/rest/os This value is not required if using the MAXIMO_ WEBSERVICE_URL parameter. Note: REST services are not fully supported in 7.1 and 7.5.</port></host>
MAXIMO_ WEBSERVICE_URL	The web service URL when SOAP web ser- vices are used to call Maximo	http://maximo <host>:<port>/meaweb/services. This value is not required if using the MAXIMO_REST_URL parameter.</port></host>
MAXIMO_WEBSERVICE	Determines which type of web service to use: REST services or SOAP web services.	 true: Uses the web services false: Uses the REST web services and is the default value.
MAXIMO_SYSTEM	The EAM system named defined on the EAM System Record in GE Digital APM.	Value is unique to the user, and should match the value in GE Digital APM exactly.
MAXIMO_ CONNECTION_ TIMEOUT	How long, in seconds, the Maximo Adapters will wait for the connection to Maximo before timing out.	Recommended value is 30.

MAXIMO_RECEIVE_ TIMEOUT	How long, in seconds, the Maximo Adapters will wait for the response from Maximo before timing out.	Recommended value is 60.
MAXIMO_REST_ ASSETNAME	<u>Created equipment</u> <u>object structure</u> .	MIASSET
MAXIMO_REST_ FLOCNAME	Created functional location object structure.	MIOPERLOC
MAXIMO_REST_ SRNAME	<u>Created service</u> <u>request object struc</u> - <u>ture</u> .	MISR
MAXIMO_REST_ WONAME	<u>Created work order</u> <u>object structure</u> .	MIWO
Common Filters	Description	Default or Recommend Value
CHANGE_DATE_START	Date value that limits the data extracted to records changed on or after the specified date.	Dates must be entered in the following format: YYYYMMDD. Optional.
	Date value that limits the data extracted to	
CHANGE_DATE_END	records changed on or before the specified date.	Dates must be entered in the following format: YYYYMMDD. Optional.
CHANGE_DATE_END CHANGE_TIME_START	records changed on or before the spe-	following format: YYYYMMDD.

SITE_ID	Site ID as identified in GE Digital APM	Value is unique to the user. Optional.
Functional Location Specific Filters	Description	Default or Recommend Value
LOCATION	Number that identifies the Functional Location record you want to extract.	Value is unique to the use. Optional.
LOCATION_TYPE	ID of the Functional Location Type that will limit the Func- tional Locations extracted.	Value is unique to the user. Optional.
LOCATION_STATUS	Status of the Functional Location that will limit the Functional Locations extracted.	Value is unique to the user. Optional.
Asset Specific Filters	Description	Default or Recommend Value
Asset Specific Filters ASSETNUM	Asset number for the asset(s) that you want to extract.	Value is unique to the user. Optional.
	Asset number for the asset(s) that you want	Value is unique to the user.
ASSETNUM	Asset number for the asset(s) that you want to extract. ID of the Asset Type that will limit the	Value is unique to the user. Optional. Value is unique to the user.
ASSETNUM ASSET_TYPE	Asset number for the asset(s) that you want to extract. ID of the Asset Type that will limit the assets extracted. Status of the Asset that will limit the Functional Locations	Value is unique to the user. Optional. Value is unique to the user. Optional. Value is unique to the user.

SERVICE_REQUEST_ STATUS	Service Request status that will limit the data extracted.	Value is unique to the user. Optional.
WORK_ORDER_NO	Work Order number (s) that will limit the Work Order(s) extracted.	Value is unique to the user. Optional.
WORK_ORDER_TYPE	Type of Maximo Work Order that will limit the work orders extracted.	Value is unique to the user. Optional.
WORK_ORDER_ SYSTEM_STATUS	Work Order system status that will limit the work orders extracted.	Value is unique to the user. Optional.
WORKORDER_OR_ SERVICEREQUEST_ FILTER	Determines if Maximo services Requests or Work Orders will be transferred to and from GE Digital APM.	 SERVICEREQUEST: Loads only service requests. WORKORDER: Loads only work orders. null: Will load service requests.
Maximo Miscellaneous Parameters	Description	Default or Recommenced Value
EXTRACT_ONLY	Determines if records will be loaded only into the staging tables or into the IR and then to APM.	 true: Will only load records into the IR. false: Will load records from EAM to APM.

MANUAL_RUN	Determines how the date parameters will be treated.	 true: The dates specified in the context file will be used. Additionally, the dates of the last successful run stored in the database will not be updated. false: The date range used during the extraction will be the date of the last successful record, as stored in the database. Each time a Job is run successfully, the database is updated with those dates, and all subsequent runs will use the dates from the last successful record.
RESTART	Determines if the Maximo Adapters will pull records from the failure log or from the failure logs and other records.	 true: Looks to the failure table in the IR and loads the records from there. false: Will look to the failure records and then continue to process other records.
LOG_REQUEST	Logs the GE Digital APM Web service requests.	 true: Enables logging false: Disables logging Note: False is recommended.
LOG_RESPONSE	Logs the GE Digital APM Web service responses.	 true: Enables logging false: Disables logging Note: False is recommended.
ROWS_TO_PROCESS	GE Digital APM web services batch count.	Default value is 100.

REST_FILTER_LIMIT	Limits the amount of records in the failure table that are extracted in one load.	Default value is 100.
MAXIMO_RS_COUNT	Limits the amount of Maximo records extracted in one load.	Default value is 1,000.
Maximo Notification Management Para- meters	Description	Default or Recommended Value
Adapters. All other parar extraction filters and cor MIMPORTANT: You mumeters that correspond	neters are configured us nnection parameters. ust configure the Maxim to your version of Maxi	o Notification Management sing the same guidelines as the oparameters for the paramo. For example, if you are the Maximo 76 section.
MAXIMO_CREATE_ WO_SR	Determines if the Maximo Adapter will transfer Maximo Work Orders or Ser- vice Request.	 WO: Will transfer only work orders SR: Will transfer only service request null: Will transfer service requests only.
MAXIMO_DEFAULT_ SITE_ID	Maximo Site ID.	Value is unique to the user, but can match the value of the Site Reference record that is linked to the EAM System

What's Next?

• Return to the <u>Maximo Adapter workflow</u> for the next step in the deployment process.

Encrypt Passwords

Passwords in the APM Connect context file are not encrypted by default. However, you can encrypt any password manually. This topic describes how to manually encrypt passwords.

Steps

- 1. On the machine on which you installed APM Connect, access the APM Connect installation package, locate the *Encrypt String_0.1.zip*, and then unzip the file.
- Open the EncryptString folder, and then select EncryptString_run.bat.
 Command prompt opens, and then the Talend Open Studio window appears.
- 3. Enter the password that you want to encrypt in the **Enter the text to be encrypted:** box.
- 4. Select OK.
- 5. In the command prompt, between the banners, copy the text that was generated.
- 6. Open the context file.
- 7. In the parameter that you want to encrypt, paste the generated text.
- 8. Append the highlighted parameter the with _AES, as shown in the following image.

```
<!-- Intermediate Repository connection parameters-->
<IR_HOST>APMCONNECTVM</IR_HOST>
<IR_PORT>5432</IR_PORT>
<IR_DATABASE>APMconnectFTP</IR_DATABASE>
<IR_PASSWORD_AES>FyoGBWa6ftigcB2nAWZ56w==</IR_PASSWORD_AES>
```

- 9. Save the context file.
- 10. For each password that you want to encrypt, repeat steps 2 through 9. The passwords are encrypted.

What's Next?

- Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.
 -or-
- Return the <u>Maximo Adapter workflow</u> for the next steps in the deployment process.

Import Notification Management File

Steps

1. On your APM Connect Server, in the <root:>\APMConnect\Utilities\runtime\etc directory create a context file name:Maximo_NotificationManagement.cfg.

<u>MPORTANT:</u> The file name must match *Maximo_NotificationManagement.cfg* exactly.

- 2. Paste the following into the context file:
 - context = Default
 - CONFIG_FILE_PATH = <The directory path to your <u>Maximo Context File</u>. >
 - 1) Note: The path must use forward slashes (/).
- 3. Save the file.
- 4. Access the APM Connect installation package, and then copy the file *Maximo_Noti-ficationManagement.jar*.
- 5. Navigate to <root:>\APMConnect\Utilities\runtime\deploy.
- 6. Paste the copied file *Maximo_NotificationManagement.jar* in the directory. The Notification Management File is imported.

What's Next?

Return to the <u>Maximo Adapter workflow</u> for the next step in the deployment process.

Configure Context Parameters

Steps

- 1. In the APM Connect Administration Center, in the **Job Conductor** workspace, select the MAXIMO_MASTER_INTERFACE Job.
- 2. At the bottom of the **Job Conductor** workspace, select **Context parameters**.

The **Context parameters** section appears, displaying the following parameters:

Context Parameter	Description
CONFIG_FILE_DIRECTORY	The file path to context files for the jobs.
SYSTEM_TO_RUN	Name of the folder in which the context file is stored, and is the <system name=""> folder.</system>
LOG4J_CONFIG_FILE	The file path for Log4j.
RUN_WORKHISTORY	The Work History Job.
RUN_EQUIPMENT	The Equipment Job.
RUN_FLOC	The Functional Location Job.

- 3. Select the **Active** check box for each parameter whose custom value you want to edit.
- 4. To save the custom value, press Enter.
- 5. In the **CONFIG_FILE_DIRECTORYCustom value** box, enter the directory where the context files are stored. If the default configuration was followed, the path will be the following: <root:>\APMConnect\Config.
- 6. Press Enter.
- 7. In the **SYSTEM_TO_RUNCustom value** box enter:
 - The name of the system directory from which you want to extract data.
 - -or-
 - * to extract from all systems.
- 8. Press Enter.

The master job is configured.

What's Next?

cess.			

Create the Intermediate Repository Database

Before you can run an extraction job, you must prepare the intermediate repository and enable the static data pull. This topic describes how to set up a repository and static data pull in preparation to run your first job.

<u>MPORTANT</u>: If you are using the Data Loaders and the SAP Adapters, you must deploy and run the *CreateIntermediateRepository* job for each set of adapters.

Before You Begin

Before you can prepare and deploy the repository, you must import the Create Intermediate Repository Job

Steps

1. Open and log in to the APM Connect Administration Center web application.

Note: The user logging in must have access to the Job Conductor by being designated the Operations Manager role. By default, users designated admin do not have Job Conductor permissions.

- 2. In the **Job Conductor** workspace, in the appropriate project, select the *CreateIntermediateRepository* Job.
- 3. At the bottom of the **Job Conductor** workspace, select **Context parameters**. The **Context parameters** section appears.
- 4. Configure the following parameters:

Context Parameter	Description
CONFIG_FILE_DIRECTORY	The file path to context files for the jobs.
PG_ADMIN_USERNAME	The user name for the PostGresSQL IR.
PG_ADMIN_PASSWORD	The password for the PostGresSQL IR.
apmconnect_Database	Enter your APM Connect database name.
	The default value is DINODB.

apmconnect_Login	Enter your APM Connect database username.	
apmconnect_Password	Enter your APM Connect database password.	
apmconnect_Server	Enter your APM connect server name	

5. Select **Run**.

The intermediate repository is created for the project.

- 6. In the **Job Conductor** workspace, in the appropriate project, select the *CreateStaticData* Job.
- 7. Select Run.

The static data pull is enabled.

You are now able to execute the jobs.

What's Next?

- Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.
 -or-
- Return to the <u>Maximo Adapter workflow</u> for the next steps in the deployment process.
 - -or-
- Return to the <u>Data Loader workflow</u> for the next step in the deployment process.

Create Object Structures in Maximo

To connect your Maximo system and your GE Digital APM system, you will need to create object structures in Maximo for the following:

- Asset
- Location
- Work Order
- Service Request

Steps: Create Object Structure - Asset

- In the Go To Application column, select Integration, and select Object Structures.
 The Object Structure page appears.
- 2. In the **Object Structure** box, enter *MXASSET*, and then open the object structure.
- 3. In the **Go To Application** column, in the **More Actions** section, select **Duplicate Object Structure**.
- 4. Enter the Object Structure name MIASSET.
- 5. In the **Source Object for MIASSET** section, remove all objects *except* the ASSET object.
- 6. In the **Go To Application** column, in the **More Actions** section, select **Exclude/ Include Fields**.
 - The **Exclude/Include Fields** window appears.
- 7. On the **Persistent Fields** tab, clear the **Exclude?** check boxes on the rows corresponding to the following fields:
 - ASSETID
 - ASSETNUM
 - ASSETTYPE
 - CHANGEDATE
 - DESCRIPTION
 - INSTALLDATE
 - ITEMNUM
 - LOCATION

- MANUFACTURER
- PRIORITY
- SERIALNUM
- SITEID
- STATUS
- VENDOR
- WARRANTYEXPDATE
- 8. On the **Non-Persistent Fields** tab, select the **Include?** check box on the row corresponding to the following field:
 - DESCRIPTION_LONGDESCRIPTION
- 9. Select **OK**.

Steps: Create Object Structure - Location

- In the Go To Application column, select Integration, and select Object Structures.
 The Object Structure page appears.
- 2. In the **Object Structure** box, enter *MXOPERLOC*, and then open the object structure.
- 3. In the **Go To Application** column, in the **More Actions** section, select **Duplicate Object Structure**.
- 4. Enter the Object Structure name MIOPERLOC.
- 5. In the **Source Object for MIOPERLOC** section, remove all objects *except* the LOCATION object.
- 6. Add the ASSET object with LOCATION as parent and ASSET as relationship.
- 7. In the **Go To Application** column, in the **More Actions** section, select **Exclude/ Include Fields**.
 - The **Exclude/Include Fields** window appears.
- 8. On the **Persistent Fields** tab, clear the **Exclude?** check boxes on the rows corresponding to the following Fields:
 - CHANGEDATE
 - DESCRIPTION

- LOCATION
- LOCATIONSID
- SITEID
- STATUS
- TYPE
- 9. On the **Non-Persistent Fields** tab, select the **Include** ? check box on the row corresponding to the following fields:
 - FAILURECODE
 - PARENT
 - LOCPRIORITY
 - DESCRIPTION_LONGDESCRIPTION
- 10. Select OK.

Steps: Create Object Structure - Work Order

- In the Go To Application column, select Integration, and select Object Structures.
 The Object Structure page appears.
- 2. In the **Object Structure** box, enter *MXWO*, and then open the object structure.
- 3. In the **Go To Application** column, in the **More Actions** section, select **Duplicate Object Structure**.
- 4. Enter the Object Structure name MIWO.
- 5. In the **Source Object for MIWO** section, remove all objects *except* the WORK ORDER object.
- 6. In the **Go To Application** column, in the **More Actions** section, select **Exclude/ Include Fields**.
 - The **Exclude/Include Fields** window appears.
- 7. On the **Persistent Fields** tab, clear the **Exclude?** check boxes on the rows corresponding to the following Fields:
 - ACTFINISH
 - ACTLABCOST
 - ACTLABHRS

- ACTMATCOST
- ACTSERVCOST
- ACTSTART
- ACTTOOLCOST
- ACTTOTALCOST
- ASSETLOCPRIORITY
- ASSETNUM
- CALCPRIORITY
- CHANGEBY
- CHANGEDATE
- CREWID
- DESCRIPTION
- ESTLABCOST
- ESTLABHRS
- ESTMATCOST
- ESTSERVCOST
- ESTTOOLCOST
- JPNUM
- JUSTIFYPRIORITY
- LEAD
- LOCATION
- OUTLABCOST
- OUTMATCOST
- OUTTOOLCOST
- PMNUM
- REPORTDATE
- SCHEDFINISH
- SCHEDSTART
- SITEID

- STATUS
- TARGCOMPDATE
- TARGSTARTDATE
- WONUM
- WOPRIORITY
- WORKTYPE
- 8. On the **Non-Persistent Fields** tab, select the **Include** ? box on the row corresponding to the following **Fields**:
 - DESCRIPTION_LONGDESCRIPTION
- 9. Select OK.

Steps: Create Object Structure - Service Request

- In the Go To Application column, select Integration, and select Object Structures.
 The Object Structure page appears.
- 2. In the **Object Structure** box, enter *MXSR*, and then open the object structure.
- 3. In the **Go To Application** column, in the **More Actions** section, select **Duplicate Object Structure**.
- 4. Enter the Object Structure name MISR.
- 5. In the **Source Object for MIWO** section, remove all objects *except* the service request object.
- 6. In the **Go To Application** column, in the **More Actions** section, select **Exclude/ Include Fields**.
 - The **Exclude/Include Fields** window appears.
- 7. On the **Persistent Fields** tab, clear the **Exclude?** check boxes on the rows corresponding to the following Fields:
 - ASSETNUM
 - DESCRIPTION
 - LOCATION
 - SITEID
 - TICKETID

- 8. On the **Non-Persistent Fields** tab, select the **Include?** box on the row corresponding to the following **Fields**:
 - DESCRIPTION_LONGDESCRIPTION
- 9. Select **OK**.

What's Next?

• Return to the <u>Maximo Adapter workflow</u> for the next step in the deployment process.

Create Web Services in Maximo

Note: You must only complete this step if you are not using the REST services. REST services are not fully supported in Maximo versions 7.1 and 7.5.

To complete the connection between your Maximo and your GE Digital APM System, you need to deploy each of the following web services in your Maximo system:

- MIASSET
- MIOPERLOC
- MIWO
- MISR

Steps

1. On the **Go To Applications** menu, select **Integration**, and then select **Web Service Library**.

The **Web Services Library** page appears.

2. In the More Actions section, select Create Web Service, and then select Create Web Service from Object Structure.

The Create Web Service from an Object Structure Service Definition window appears.

3. In the **Source Name** column, select the check box next to the web service name you want to create, and then select **Create**.

The web service name appears in the **Web Services Library** list.

- 4. In the More Actions tab, select Deploy to Product Web Service Container, and then select Deploy Web Service.
- 5. Repeat Steps 1-4 to create the remaining web services.

What's Next?

Return to the <u>Maximo Adapter workflow</u> for the next step in the deployment process.

Configure the Default Password

If you have enabled web service authentication in your Maximo system, then you must configure a default user name and password in Maximo.

Steps

- 1. In Maximo, select **System configuration**, and then select **Platform configuration**, and then select **System properties**.
- 2. Search for the following property: *mxe.int.dfltuser*.
- 3. For the mxe.int.dfluser property set the default user as *mxintadm*.
- 4. Refresh your Maximo system, and then search for the following property *mxe.in-t.dfltuserpassword*.
- 5. For the mxe.int.dfltuserpassword property, enter your default password, and then refresh your Maximo system.

The default user name and password are configured.

Results

After configuring the default user name and password, you can run the web service, and authentication will be accomplished through the default user and password.

What's Next?

Return to the <u>Maximo Adapter workflow</u> for the next step in the deployment process.

Set System Properties Settings for Web Service Response

Steps

- 1. In the **Go To Application** column, select **System Configuration**, select **Platform configuration**, and then select **System Properties**.
 - The **System Properties** page appears displaying the **Global Properties** and **Instance Properties**.
- 2. In the **Global Properties** section, navigate the property *mxe.int.keyresponse*.
- 3. On the mxe.int.keyresponse row, select ...
 - The row is expanded, and the **Global Properties Details** appear.
- 4. In the **Global Value** box, enter 1.
 - The **Global Value** is equal to 1.

Results

• Setting the **Global Value** to one enables Service Request numbers or Work Order numbers on GE Digital APMRecommendation to be updated and the Request Number field will be populated. It allows the response returned during the update to contain key elements and will prevent the value from being null.

What's Next?

• Return to the <u>Maximo Adapter workflow</u> for the next step in the deployment process.

Create EAM System Records

Steps

- 1. Create a new record, using the EAM System family.
- 2. In the **Name** box, enter the name of the Maximo system.
- 3. To populate the System ID: box, you must run the following query: UPDATE [MI_SAPSYSTM] SET [MI_SAPSYSTM].[MI_SAPSYSTM_ID_C] = '<NAME>' WHERE [MI_SAPSYSTM].[MI_SAPSYSTM_NAME_C]_LIKE '%<NAME>%'

<u>MPORTANT</u>: In the query, you must replace *<NAME>* with the value you entered into the **Name** box. By doing so, when you test the connection to the Maximo system, the value in the Name field will match the value that will be populated automatically in the System ID field.

4. If this Maximo system is the system to and from which you want to send data by default, select the **Default EAM System?** check box.

Results

- An EAM system record is created for the EAM system to and from which you want to establish a connection with GE Digital APM. This record should now be used to link Site Reference.
- Linking an EAM system to an EAM System record enables the APM Connect Adapters to create Notifications against that EAM System.

What's Next?

• Return to the Maximo workflow for the next step in the deployment process.

Maximo Interfaces Security Groups

The following table lists the baseline Security Groups available for users within this module, as well as the baseline Roles to which those Security Groups are assigned.

<u>MPORTANT</u>: Assigning a Security User to a Role grants that user the privileges associated with *all* of the Security Groups that are assigned to that Role. To avoid granting a Security User unintended privileges, before assigning a Security User to a Role, be sure to review all of the privileges associated with the Security Groups assigned to that Role. Also be aware that additional Roles, as well as Security Groups assigned to existing Roles, can be added via Security Manager.

Security Group	Roles	
MI CMMS Interface Administrator	MI Data Loader Admin	
MI CMMS Interface User	MI Data Loader User	

The baseline family-level privileges that exist for these Security Groups are summarized in the following table.

Family	MI CMMS Interface Administrator	MI CMMS Inter- face User
Entity Families		
CMMS Interface	View, Update, Insert, Delete	View
CMMS Mapping	View, Update, Insert, Delete	View
CMMS System	View, Update, Insert, Delete	View
Equipment	View, Update, Insert, Delete	View
Functional Location	View, Update, Insert, Delete	View
Interface Log	View, Update, Insert, Delete	View
SAP System1	View, Update, Insert, Delete	View
Site Reference	View	View

Work History	View, Update, Insert, Delete	View, Update, Insert
Work History Detail	View, Update, Insert, Delete	View, Update, Insert
Relationship Families		
Equipment Has Equipment	View, Update, Insert, Delete	View, Update, Insert
Functional Location Has Equipment	View, Update, Insert, Delete	View, Update, Insert
Functional Location Has Functional Location(s)	View, Update, Insert, Delete	View, Update, Insert
Has CMMS Interface	View, Update, Insert, Delete	View
Has CMMS Mapping	View, Update, Insert, Delete	View
Has CMMS System	View, Update, Insert, Delete	View
Has Event Detail	View, Update, Insert, Delete	View, Update, Insert
Has SAP System	View, Update, Insert, Delete	View

About Site Filtering in the EAM Adapters

<u>MPORTANT</u>: Site Reference records must preexist in your GE Digital APM system, before you can use the EAM Adapters to populate the Site Reference Key. Additionally, the site entered into the context file must match the exact value in the corresponding Site Reference record.

MPORTANT: The user who is running the EAM Adapters jobs must be assigned, in GE Digital APM, to the site to which the records being loaded will be assigned. Additionally, the credentials for that user must be entered into the context file. If the user is not a member of the appropriate site, then the data load will fail, and an error message will appear.

The EAM Adapters are used to populate the Site Reference on Equipment, Functional Location, and Work History records in GE Digital APM. The adapters populate the MI_SITE_KEY system field with the ENTY_KEY system field associated with the Site Reference value to be populated. On asset records, the Site Reference is stored in the MI_SITE_KEY field, a system field in GE Digital APM. The EAM Adapters use the Site Name (MI_SITE_NAME) to translate the value to the corresponding Site Reference Key and populate the MI_SITE_KEY field; therefore, you do not need to know the key to be able to populate the site reference. This functionality is important because this value can change from one database to another.

When records are loaded using the Equipment, Function Location, and Work History Adapters, the system will assign the Site Reference Key (MI_SITE_KEY) to the assets using the value designated in the context file context file. The following parameters are used to designate the Site Reference Key value:

- SITE_REFERENCE_EQUIP: Used to populate the Site Reference Key on Equipment records being loaded into GE Digital APM. The Site Reference Key determines the Site to which the Equipment record(s) will be assigned.
- SITE_REFERENCE_FLOC: Used to populate the Site Reference Key on Functional Location records loaded into GE Digital APM. The Site Reference Key determines Site to which the Functional Location record(s) will be assigned.

Note: The values entered into these parameters should match, because Equipment records are linked to Functional Location records. Therefore, they should have the same site.

These parameters accept three types of values to determine the site reference value.

- a. **Site Name:** You can enter the site name directly as defined on the preexisting Site Reference record (i.e., Site 100).
- b. **Column Name:** You can enter a column value between two pound symbols (#) to set the site reference. The following columns can be used:

- · SAP columns:
 - MI_EQUIP000_SAP_SYSTEM_C
 - MI_EQUIP000_MAINT_PLANT_C
 - MI_FNCLOC00_MAINT_PLNT_C
 - MI_FNCLOC00_SAP_SYSTEM_C
- Maximo columns:
 - MI_FNCLOC00_SITE_C
 - MI_EQUIP000_SITE_C

For example, if you wanted to use your SAP maintenance plant field as your GE Digital APM site reference, you would enter #MI_EQUIP000_MAINT_PLANT_C#.

c. **Null:** You can leave the value as null. The record will be a global record if a Site Reference value is not mapped in between the tags.

If the assets being loaded into GE Digital APM are global records, meaning they will not be filtered according to site, then the Site Reference parameters can be left blank. When records are loaded with a null values in their Site Reference parameters, those created asset records will be designated as Global.

After the adapters are run, records designated to be transferred into GE Digital APM will be assigned to the site defined in the Site Reference parameters.

In addition to Equipment and Functional Location records loaded by the EAM adapters, Work History records and shell records are impacted by site reference functionality as detailed in the following table.

Action	Result
If the Work History Adapter is run after the Equipment or Functional Location Adapter	The Work History records will inherit the Site Reference Key of their parent Functional Loca- tion or Equipment records.
If the Work History Adapter is run before the Equipment or Functional Location Adapter	The Site Reference Key will inherited from the shell record that will be created for Equipment and Functional Location.
If a shell record is created while loading data	The Site Reference Key will be the value set in the context parameters.

Note: If you are using multiple SAP Systems, you must set up a context file for each system, and then designate the appropriate site(s) for each EAM Systems.

Deploy the SAP Adapters

The checklists in this section of the documentation contain all the steps necessary for deploying and configuring this module whether you are deploying the module for the first time or upgrading from a previous module.

Deploy the SAP Adapters for the First Time

The following table outlines the steps that you must complete to deploy and configure this module for the first time. These instructions assume that you have completed the steps for deploying the basic GE Digital APM system architecture.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.

Note: If you are deploying this module in APM Now, before you begin completing these tasks, review the system requirements for this module to identify the supported features for this module in APM Now. Unless noted, all deployment tasks in the following table are applicable for the deployment of this module in APM Now.

Step	Task	Notes
1	Deploy the APM Connect Base.	This step is required.
2	On the APM Connect Server, <u>configure the context file directory</u> .	This step is required.
3	On the APM Connect Server, configure the directory for multiple SAP systems.	This step is required only if you are using multiple SAP systems.
4	On the APM Connect Server, install the SAP Java connector.	This step is required.
5	On the APM Connect Server, configure SSL.	This step is required only if you are completing an APM Now deployment.
6	On the APM Connect Server, configure the context file.	This step is required.
7	On the APM Connect Server, encrypt passwords.	This step is required.
8	In the APM Connect Administration Center, configure the context parameters.	This step is required.
9	In the APM Connect Administration Center, create the intermediate repository.	This step is required.
10	Configure site filtering.	This step is required only in the APM Now environment.

11	On the APM Connect Server and the SAP server, mount a file share.	This step is required.
12	On the SAP Server and in SAP, <u>estab</u> - <u>lish SFTP Transfer in SAP</u> .	This step is required only if you are using SFTP to transfer files between SAP and GE Digital APM and you are not using the SAP PI Adapters.
13	On your SAP server, <u>create file share</u> <u>folder structure</u> .	This step is required.
14	In SAP, install the SAP Adapters ABAP base service pack add-on.	This step is required.
15	In SAP, <u>verify the SAP ABAP add-on</u> .	This step is required.

<u>∧ IMPORTANT:</u> Each of the following tasks may be required depending on the license that you have purchased and the APM Connect component that you are deploying. The Work Management Adapter and Technical Characteristic Adapter are unavailable for the APM Now environment.

16	In SAP, identify the Operation values that will be used to trigger the management of Inspection Task and Calibration Task records.	This step is required only if you are using the Work Management Adapter.
17	In GE Digital APM, assign the desired Security Users to the SAP Adapters Security Groups.	This step is required.
18	In GE Digital APM, configure the GE Digital APM system to create Notifications from Recommendation records belonging to customerdefined Recommendation families.	This step is required if you are using the Notification Management Adapter.
19	Deploy the RFC Connector files.	The step required.
20	In GE Digital APM, <u>configure the Priority values</u> .	This step is required if you are using the Notification Management Adapter.

21	In GE Digital APM, <u>create EAM System records</u> to identify your SAP system (s).	This step is required only if you are using the: • Work Management Adapter • Technical Characteristic Adapters • Notification Management Adapter
22	In GE Digital APM, <u>test the SAP connection information</u> that you specified in your EAM System records.	This step is required only if you are using the on-premises: • Work Management Adapter • Technical Characteristic Adapters • Notification Management Adapter Note: This step is not required if you are using the SAP Cloud Adapters.
23	In GE Digital APM, <u>configure SAP task</u> and confirmation creation.	This step is required only if you are using the Work Management Adapter.
24	In GE Digital APM, <u>configure the Get</u> <u>Tasks for Work Order Generation</u> <u>query</u> .	This step is required only if you are using the Work Management Adapter.
25	In GE Digital APM, <u>create a scheduled</u> item to create Work Orders in SAP.	This step is required only if you are using the Work Management Adapter.
26	In GE Digital APM, <u>create CMMS Clas</u> - <u>sification Type records</u> .	This step is required only if you are using the Technical Characteristic Adapters.
27	In GE Digital APM, <u>identify Clas</u> - <u>sifications whose Characteristics you</u> <u>want to extract</u> .	This step is required only if you are using the Technical Characteristic Adapters.
28	In GE Digital APM, identify Characteristics that you want to extract.	This step is required only if you are using the Technical Characteristic Adapters.
29	In GE Digital APM, <u>refresh GE Digital</u> <u>APM to reflect current SAP Clas</u> <u>sifications and Characteristics</u> .	This step is required only if you are using the Technical Characteristic Adapters.

Deploy the SAP PI Adapters for the first time.	This step is required only if you are deploying SAP PI on-premises.
--	---

Upgrade SAP Adapters to EAM SAP V2.0.0

The following tables outline the steps that you must complete to upgrade this module to EAM SAP V2.0.0. These instructions assume that you have completed the steps for upgrading the basic GE Digital APM system architecture.

The steps that you must complete may vary depending on the version from which you are upgrading. Follow the workflow provided in the appropriate section.

Upgrade from EAM SAP V1.5.0 through EAM SAP V1.6.3

Step	Task	Notes
1	Upgrade the APM Connect Base.	This step is required.
2	Complete the steps to <u>deploy the SAP adapters</u> <u>for the first time</u> .	This step is required.

Upgrade from APM Connect V1.0.0 through V1.3.0

Step	Task	Notes
1	Upgrade the APM Connect Base.	This step is required.
2	Complete the steps to <u>deploy the SAP adapters</u> <u>for the first time</u> .	This step is required.

Upgrade SAP Cloud Adapters to EAM SAP Cloud V2.0.0

The following table outlines the steps that you must complete to upgrade this module to EAM SAP Cloud V2.0.0.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.


Upgrade from V1.0.0 through V1.0.1

Step	Task	Notes
1	Upgrade the APM Connect Base.	This step is required.
2	Complete the steps to <u>deploy the SAP adapters for the first time</u> .	This step is required.

Configure the Context File Directory

Steps

- 1. On the APM Connect server, access your APM Connect installation package, and then navigate to the Jobs folder.
- 2. Access the context file, and then copy the file.
- 3. Navigate to the directory C:\APMConnect\Config.



- 4. Rename the folder **RENAME_TO_SYSTEM_NAME** to represent the name of your SAP System. This folder will define the Systems Context Directory.
- 5. Paste the context file, in the C:\APMConnect\Config\<System_Name> directory you renamed in step 4.
- 6. Delete the file *place context file here and delete this file.deleteme*. The Context File Directory is configured.

What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Configure the Context File Directory for Multiple SAP Systems

<u>MPORTANT</u>: This step is required only if you are using multiple SAP Systems from which you plan on extracting data. If you are not using multiple SAP systems, you can skip this procedure and proceed to the next step, <u>install the SAP Java connector</u>, in the APM Connect Base First-Time Deployment Workflow.

APM Connect allows you to extract data from multiple SAP Systems using the Master Job to extract from multiple systems. You must set up the appropriate directory structures. Additionally, jobs are automatically configured to run a full extraction or load per context file for each job cycle, allowing different configurations per SAP System.

Steps

- 1. On the machine on which you installed APM Connect, navigate to the following location: C:\APMConnect\Config\.
- 2. Create a new folder for each SAP System using the following folder structure: C:\APMConnect\Config\<SAP System Name>.
- 3. In each SAP system folder, place a copy of the context file.
- 4. Label each copy of the context file using the following format: *SAP_<system* name>_Contextfile.xml.

<u>MPORTANT</u>: You must label the context file with *SAP*_ at the beginning of the file name, or APM Connect will be unable to read the context file during the extraction.

The directory structure is in place with the complete file path: *C:APMConnect\Config\<SAP system name>\SAP_<SAP system name>_Contextfile.xml.*

For example, a configured directory will resemble the following: C:\APMConnect\Config\Q-66\SAP_Q66_Contextfile.xml.

What's Next?

• Return to the SAP Adapter workflow for the next step in the deployment process.

Install SAP Java Connector

To facilitate the data transfer, there must be a java connector between SAP and the APM Connect server. This topic describes how to establish the connection via the SAP Java Connector (SAP JCO).

Note: The <u>APM Connect installer</u> automatically places the files *sapjco3.dll* and *sapjco.jar* into the location *C:\APMConnect\Utilities\runtime\lib*. You must complete the remaining steps in this topic manually.

Steps

- 1. Navigate to the location where you downloaded the SAP Java Connector package from the SAP marketplace, and copy the following files:
 - sapjco3.dll
 - sapjco3.jar

Note: If you are using a 64-bit machine, per the APM Connect system requirements, you must select the 64-bit installer.

- 2. Navigate to *C:\APMConnect\Utilities\runtime\lib\wrapper*, and then paste the copied files in that location.
- 3. Copy the file *sapjco3.dll* again.
- 4. Navigate *C:\windows\system32*, and then paste the copied file in that location. The Java Connecter is installed.

What's Next?

Return to the SAP Adapter workflow for the next step in the deployment process.

Configure SSL

The SAP Adapters in APM Now require an SSL certificate to transfer files. As a part of implementation, GE Digital will supply you with an SSL certificate.

Steps

- 1. Access the SSL truststore file, provided at installation.
- 2. Copy the truststore file.
- 3. On your APM Connect Server, paste the truststore file in a secure file system location that is accessible by the <u>APM Container service user</u>.
- 4. In the context file, ensure you have configured the SSL Connection parameters, USE_SSL, TRUSTSTORE_FILE, and TRUSTSTORE_PASSWORD.

The SAP Adapters are configured to use SSL.

What's Next?

• Return to the SAP Adapter workflow for the next step in the deployment process.

Configure the Context File

Before you can run a job in the APM Connect Administration Center, you must specify a set of connection parameters and corresponding values to establish a connection between APM Connect components, GE Digital APM, and your EAM system. Each of these connections is used when executing a job, and they are *required*. The connections are established via context files. This topic describes how to access and configure parameters in these context files.

(i) Hint: The SAP Adapters support <u>connections between multiple SAP systems</u> and multiple GE Digital APM databases by using one context file for each SAP system or GE Digital APM system.

Steps

- 1. On the APM Connect server, access your context file. If you installed in the default location, navigate to the folder *C:/APMConnect/Config*.
- 2. Open the context file to edit.

<u>MPORTANT</u>: Changes made to the context file will override changes made in the APM Connect Administration Center Context parameters section.

3. Based you your type of deployment (i.e., SAP Adapters on premises, SAP Adapters in APM Now, or SAP PI Adapters), configure the appropriate context file.

-or-

Configure the Context File for SAP Adapters On Premises

a. If you are deploying the SAP Adapters on premises, enter the appropriate values for each parameter into the context file according to the following table.

Intermediate Repository

(IR) Connection

Parameters

Description

Default or Recommend Value

IR_HOST	IP address of the IR.	Enter the host name of the PostgresSQL server. If you installed APM Connect using the default settings, then the value is <i>localhost</i> .
IR_PORT	Port number of the IR.	Enter your PostgreSQL port. The default value is <i>5432</i> .
IR_DATABASE	Database in which the IR data is stored.	Enter a name for the IR database. This value will be used to create the IR database.
IR_SCHEMA	The schema in which the IR database will be created.	The default value is <i>Public</i> .
IR_USER_ID	The IR user name.	Enter the user name for the PostgresSQL database. The default user name is <i>postgres</i> .
IR_PASSWORD	The IR system password.	Enter the password for the PostgresSQL data- base that was created during installation.
APM Connect Para- meter	Description	Default or Recom- mend Value
APM_CONNECT_ HOST	The host name of the machine where APM Connect Administration Center is installed.	Value is unique to the user.

APM_CONNECT_ PORT	The port name of the machine where APM Connect Administration Center is installed.	Value is unique to the user.
APM Connection Parameters	Description	Default or Recom- mend Value
APM_APP_SERVER	APM Application Server name.	Enter the name of your GE Digital APM Server.
APM_DATASOURCE	APM data source to which the data will be exported.	Enter the name of your GE Digital APM datasource.
APM_USERID	The GE Digital APM APM Framework User ID.	Value is unique to the user.
APM_PASSWORD	The GE Digital APM APM Framework password.	Value is unique to the user.

You can enter a value defined in GE Digital APM. Note: The value that is entered will be applied to all records. -or-You can use the char-Used to map the site acter # at the beginreference value to an ning and end of a SAP field. This dic-GE Digital APM Field SITE_REFERENCE_ tates which SAP field Name to indicate the **EQUIP** will be used as the field that is used to set site reference for the site reference. GE Digital APM Equip-For example, if you ment records. wanted to use your SAP maintenance plant field as your GE Digital APM site reference, you would enter the following: <SITE_ REFERENCE_ EQUIP>#MI_EQUIP000_ MAINT_PLANT_ C#</SITE_REFERENCE_ EQUIP>

	Used to map the site reference value to an SAP field. This dictates which SAP field will be used as the site reference for GE Digital APM Equipment records.	You can enter a value defined in GE Digital APM.
		Note: The value that is entered will be applied to all records.
SITE_REFERENCE_ FLOC		-or- You can use the character # at the beginning and end of a GE Digital APM Field Name to indicate the field that is used to set the site reference. For example, if you wanted to use your SAP maintenance plant field as your GE Digital APM site reference, you would enter the following: <site_ floc="" reference_="">#MI_FNCLOC00_ MAINT_PLANT_ C#</site_>
SAP Connection Parameters	Description	Default or Recom- mend Value
SAP_CLIENT	SAP client from where data is imported.	Value is unique to the user.

SAP_HOST	IP address of the SAP Application Server.	Value is unique to the user.
SAP_LANGUAGE	The letter code that represents the language of the description to transfer into GE Digital APM.	Value is unique to the user.
SAP_SYSTEM_ NUMBER	Service port of the SAP Application Server.	Value is unique to the user.
SAP_USERID	SAP system user ID.	Value is unique to the user.
SAP_PASSWORD	SAP system pass- word.	Value is unique to the user.
EQUIP_MULTI_ OBJECTS_ENABLED	Enables records with Equipment Class (002) configured for Multiple Objects Allowed in SAP to be transferred to GE Digital APM.	true: Enter true if you Equipment Class (002) is configured for Mul- tiple Objects Allowed in SAP.
FLOC_MULTI_ OBJECTS_ENABLED	Enables records with Functional Location (003) configured for Multiple Objects Allowed in SAP to be transferred to GE Digital APM.	true: Enter true if your Functional Location (003) is configured for Multiple Objects Allowed in SAP.
File System Para- meters	Description	Default or Recom- mend Value
IR_TALEND_ OUTPUT	Temporary work- space.	Value is unique to the user.

PLSAP_INPUT	Path of the directory you created in which APM Connect searches for the generated files from SAP.	Value is unique to the user.
PLSAP_OUTPUT	Path of the directory where the data is stored on the SAP server prior to sending it to the APMConnect server. This Directory should be shared with either the SAP server.	Value is unique to the user.
Miscellaneous Para- meters	Description	Default or Recom- mended Value

true false Note: If the MANUAL_RUN parameter is set to true, the dates specified in the context file will be used. Additionally, the dates of the last successful run stored in the database will not be updated. If set to Determines how the false, the date range MANUAL_RUN dates parameters will used during the be treated. extraction will be the date of the last successful record, as stored in the database. Each time a Job is run successfully, the database is updated with those dates, and all subsequent runs will use the dates from the last successful record.

LOG_REQUEST	Logs the APM Web service requests.	 true: enables logging false: disables logging Note: False is recommended.
LOG_RESPONSE	Logs the APM Web service responses.	true: enables loggingfalse: disables logging
		Note: False is recommended.
Parallel Job Control Parameters		
EXTRACT_NUM_ PARALLEL_JOBS	The maximum number of parallel SAP jobs that APM Connect will open in a single extraction.	Choose a value that corresponds to the number of background processors that you have available to APM Connect.
IR_LOAD_NUM_ PARALLEL_JOBS	The maximum number of IR load jobs in a single extraction.	30
APM_LOAD_ THREAD_COUNT	The maximum number of APM web service calls that will be made in parallel.	50
FTP Parameters	Description	Default or Recom- mend Value

Using an FTP Connection is only supported for the SAP and SAP PI Adapters, and configuration is only required if you are using FTP to transfer information between your systems.

MPORTANT: If you are using an SAP System with the SAPFTP_ SERVERS table, you must configure that table to activate FTP servers according to the SAP Help System. You can refer to SAP OSS 1605054 for more details. Typically, this will apply to any SAP version later than ECC6 EHP5.

PLSAP_FTP_HOST	The FTP server host name.	Value is unique to the user.
PLSAP_FTP_USERID	The FTP server user name.	Value is unique to the user.
PLSAP_FTP_ PASSWORD	The FTP server password.	Value is unique to the user.
PLSAP_FTP_PORT	The FTP server port.	If the default configuration was followed, enter one of the following:
		• 21: for FTP connection.
		• 22: for SFTP connection.
PLSAP_FTP_MODE	The mode by which files are copied.	Enter one of the following values:
		• SERVER: to use file shares.
		• FTP: to use stand- ard FTP.
		• SFTP: to use standard Secure FTP.

PLSAP_FTP_SCAN_ DIR	The remote FTP directory used to scan for files.	Value is unique to the user.
PLSAP_FTP_NUM_ OF_RETRY	The number of times to scan the FTP server for files.	10
PLSAP_FTP_SLEEP_ TIME	The time in seconds between scans.	10

-or-

Configure the Context File for SAP Adapters in APM Now

a. If you are deploying the SAP Adapters in APM Now, enter the appropriate values for each parameter into the context file according to the following table.

Intermediate Repository (IR) Connection Parameters	Description	Default or Recom- mended Value
IR_HOST	IP address of the IR.	Enter the host name of the PostgreSQL server. If you installed APM Connect using the default settings, then the value is <i>localhost</i> .
IR_PORT	Port number of the IR.	The default value is 5432.
IR_DATABASE	Database in which the IR data is stored.	Enter a name for the IR database. This value will be used to create the IR database.

IR_SCHEMA	The schema in which the IR database will be created.	The default value is <i>Public</i> .
IR_USER_ID	The IR user name.	Enter the user name for the PostgreSQL database. The default user name is postgres.
IR_PASSWORD	The IR system pass- word.	Enter the password for the PostgreSQL database that was created during installation.
PG_ADMIN_USER	The IR user name, and is used exclusively when creating the database.	Enter the user name for the PostgreSQL database. The default user name is postgres.
PG_ADMIN_ PASSWORD	The IR system password and is used exclusively when creating the database.	Enter the password for the PostgresSQL database that was created during installation.
SAP System Para- meters	Description	Default or Recom- mended Value
SAP_CLIENT	SAP client from which data will be extracted.	Value is unique to the user.
SAP_HOST	IP address of the SAP Application Server.	Value is unique to the user.
SAP_LANGUAGE	The letter code that represents the language used during extraction into GE Digital APM.	Value is unique to the user.

SAP_SYSTEM_ NUMBER	Service port of the SAP Application Server.	Value is unique to the user.
SAP_USERID	SAP system user ID.	Value is unique to the user.
SAP_PASSWORD	SAP system password.	Value is unique to the user.

SAP_FILE_ ENCODING	Determines the encoding of the source data.	The default value is UTF8. The following encodes are supported, and can be entered as a valid value. • Cp858: Variant of Cp850 with Euro character • Cp437: MS-DOS United States, Australia, New Zealand, South Africa • Cp775: PC Baltic • Cp850: MS-DOS Latin-1 • Cp852: MS-DOS Latin-1 • Cp855: IBM Cyrillic • Cp857: IBM Turkish • Cp862: PC Hebrew • Cp866: MS-DOS Russian • ISO8859_1: Latin alphabet No. 1 • ISO8859_2: Latin Alphabet No. 2
-----------------------	---	---

• ISO8859_4: Latin Alphabet No. 4 • ISO8859_5: Latin/Cyrillic Alphabet • ISO8859_7: Latin/Greek Alphabet (ISO-8859-7:2003) • ISO8859_9: Latin Alphabet No. 5 • ISO8859_13: Latin Alphabet No. 7 • ISO8859_15: Latin Alphabet No. 9 • KOI8_R:KOI8-R, Russian • KOI8_U: KOI8-U, Ukrainian • **ASCII**: American Standard Code for Information Interchange • UTF8: Eight-bit

> Unicode (or UCS) Transformation Format

• Cp1250: Windows Eastern

		 European Cp1251: Windows Cyrillic Cp1252: Windows Latin-1 Cp1253: Windows Greek Cp1254: Windows Turkish Cp1257: Windows Baltic Cp737: PC Greek Cp874: IBM Thai
EXTRACT_NUM_ PARALLEL_JOBS	The maximum number of parallel SAP jobs that APM Connect will open in a single extraction.	Choose a value that corresponds to the number of background processors that you have available to APM Connect.
File System Para- meters	Description	Default or Recom- mended Value
PLSAP_INPUT	Path of the directory you created in which SAP writes files.	Value is unique to the user.
PLSAP_OUTPUT	Path of the directory where APM Connect will access the files written by SAP.	Value is unique to the user.

IR_TALEND_ OUTPUT	The root directory for all internal file processing. This is the directory where files will be transformed.	Enter a file system location to which files will be written. You can create a directory in the following location: C:\IR\TalendOutput.
LOG_BASE_DIR	Directory path to the log file.	None.
SFTP_STAGING_ DIR	Temporary storage location for files that are waiting to be loaded.	Value is unique to the user, and provided at installation.
USE_SSL	Determines whether an SSL certificate will be used when transferring file.	Enter the value <i>true</i> . SSL certificate are required, and <i>true</i> is the only valid value.
TRUSTSTORE_FILE	The directory path were the SSL certificate is stored.	Enter the directory path where the SSL truststore is stored on the APM Connect Server.
TRUSTSTORE_ PASSWORD	The password to the SSL certificate file.	Value is unique to the user, and will be provided at installation.
Filter Parameters	Description	Recommended or Default Value
CREATE_DATE_ START	Date value that limits the data extracted to records created on or after the specified date.	Dates must be entered in the following format: YYYYMMDD.

CREATE_DATE_ END	Date value that limits the data extracted to records created on or before the specified date.	Dates must be entered in the following format:
CHANGE_DATE_ START	Date value that limits the data extracted to records changed on or after the specified date.	Dates must be entered in the following format: YYYYMMDD.
CHANGE_DATE_ END	Date value that limits the data extracted to records changed on or before the specified date.	Dates must be entered in the following format:
CREATE_TIME_ START	Time value that limits the data extracted to records created on or after the specified date.	Time must be in the following format: HHMMSS.
CREATE_TIME_ END	Time value that limits the data extracted to records created on or before the specified date.	Time must be in the following format: HHMMSS.
CHANGE_TIME_ START	Time value that limits the data extracted to records changed on or after the specified date.	Time must be in the following format: HHMMSS.
CHANGE_TIME_ END	Time value that limits the data extracted to records changed on or before the specified date.	Time must be in the following format: HHMMSS.

Equipment Filter Criteria	Description	Recommended or Default Value
EQUIPMENT_NO	Equipment that you want to extract.	The Equipment number should not exceed 18 characters. You cannot exceed 500 Equipment numbers.
EQUIPMENT_ CATEGORY	ID of the Equipment Category that will limit the Equipment extrac- ted.	Must be a single character.
EQUIPMENT_TYPE	ID of the Equipment Type that will limit the Equipment extracted.	The Equipment Type should not exceed 10 characters.
EQUIPMENT_ CLASS	ID of the Equipment Classification that will limit the Equipment extracted.	The Equipment Classification should not exceed 18 characters. If an Equipment has multiple Classifications, as long as you specify one of those Classifications, the Equipment record will be extracted.
LANGUAGE	The SAP code that represents the language.	Must be a single character.
Functional Loca- tion Filter Criteria	Description	Recommended or Default Value

FLOC_NO	ID of the Functional Location that will limit the Functional Loca- tions extracted.	The Functional Location ID should not exceed 40 characters. You cannot exceed 500 Functional Location numbers.
FLOC_TYPE	ID of the Functional Location Type that will limit the Functional Locations extracted.	Functional Location Type ID should not exceed 10 characters.
FLOC_CLASS	ID of the Functional Location Classification that will limit the Func- tional Locations extrac- ted.	Functional Location Classification ID should not exceed 18 characters.
FLOC_CATEGORY	ID of the Functional Location Category that will limit the Functional Locations extracted.	Must be a single character.
Work History Fil- ter Criteria	Description	Recommended or Default Value
NOTIFICATION_NO	Number that identifies the Notification record.	Notification number should not exceed 12 characters.
WORK_ORDER_NO	Number that identifies the Work Order record.	Work Order number should not exceed 12 characters.
NOTIFICATION_ TYPE	Order Type that limits the orders that you want to extract.	Notification Type should not exceed two characters.

WORK_ORDER_ TYPE	ID of the Work Order Type that limits the orders that you want to extract.	Work Order Type should not exceed four characters.
WORK_ORDER_ SYSTEM_STATUS	Work Order Systems Status that limits the Work Orders you want to extract.	Work Order System Status should not exceed four characters.
WORK_ORDER_ USER_STATUS	Work Order User Status that limits the Work Orders that you want to extract.	Work Order User Status should not exceed four char- acters.
NOTIFICATION_ SYSTEM_STATUS	Notification System Status that limits the notifications that you want to extract.	Notification System Status should not exceed four characters.
NOTIFICATION_ USER_STATUS	Notification User Status that limits the notifications that you want to extract.	User Status should not exceed four characters.
MAINT_PLANT	ID(s) of the Main- tenance Plant whose data you want to extract.	Plant values cannot exceed four characters.
Miscellaneous Parameters	Description	Recommended or Default Value

MANUAL_RUN	Determines how the date parameters will be treated.	• True: The dates specified in the context file will be used, and the dates of the last successful run stored in the database will not be updated. • False: The date range used during the extraction will be the date of the last successful record, as stored in the database. Each time a Job is run successfully, the database is updated with those dates, and all subsequent runs will use the dates from the last successful record.
Queue	Description	Recommended or Default Value
QUEUE_HOST	The APM Now queue host name.	Value is unique to the user, and provided at installation.

QUEUE_HOST_1	Additional APM Now queue host name.	Value is unique to the user, and provided at installation.
QUEUE_HOST_2	Additional APM Now queue host name.	Value is unique to the user, and provided at installation.
QUEUE_ PASSWORD	The APM Now queue password.	Value is unique to the user, and provided at installation.
QUEUE_PORT	The APM Now queue port.	Value is unique to the user, and provided at installation.
QUEUE_PORT_1	Additional APM Now queue port.	Value is unique to the user, and provided at installation.
QUEUE_PORT_2	Additional APM Now queue port.	Value is unique to the user, and provided at installation.
QUEUE_USER	The APM Now queue user name.	Value is unique to the user, and provided at installation.
CUSTOMER_NAME	The coded customer name.	Value is unique to the user, and provided at installation.
SFTP Parameter	Description	Recommended or Default Value
SFTP_HOST	The SFTP server host name.	Value is unique to the user, and provided at installation.

SFTP_USERID	The SFTP server user name.	Value is unique to the user, and provided at installation.
SFTP_PASSWORD	The SFTP server password.	Value is unique to the user, and provided at installation.
SFTP_PORT	The SFTP server port.	Value is unique to the user, and provided at installation.
SFTP_LANDING_ DIR	The directory path where the shared files are stored.	Value is unique to the user, and provided at installation.
USE_SSH_KEY	Determines if SSH security configuration will be used by the adapters.	True: SSH configuration will be used. False: SSH configuration will not be used.
SSH_PRIVATE_KEY	The directory where the SSH key is stored.	Value is unique to the user. The SSH key is provided at installation, and can be stored in any directory on the APM Connect server, but it is recommended to store it in the following folder: C:/APMConnect/Config
Email Notification Parameters	Description	Recommenced or Default Value

EMAIL_TO	The email address(es) to which the notification email will be sent.	Value is unique to the user.
EMAIL_FROM	The email address from which the notification email will be sent.	Value is unique to the user.
REPORT_TARGET_ DIR	The directory path were the report file will be delivered.	Value is unique to the user.
FAILURE_DETAIL_ REPORT_JRXML_ FILE_PATH	The directory path were the failure deport file will be delivered.	Value is unique to the user.
LOAD_SUMMARY_ REPORT_JRXML_ FILE_PATH	The directory path were the load complete report file will be delivered.	Value is unique to the user.
SMTP_HOST	The host for SMTP installation the APM Connect server.	Value is unique to the user.
SMTP_PORT	The port for SMTP.	Default value is 25.
LOAD_SUMMARY_ REPORT_ENABLED	Indicates whether or not to load the complete report with every extraction.	True: The Load Complete report will be sent detailing the number of records that were extracted and successfully loaded into GE Digital APM. False: The Load Complete report will not be sent.

FAILURE_DETAIL_ REPORT_ENABLED	Indicates whether or not the failure detail report will be sent when a record fails to load.	True: The Failure Detail report will be sent detailing the records that failed to load and the reason why. False: The Failure Detail report will not be sent.
CMMS_ID	The CMMS ID is used as the identifier for your SAP System, and is <sap id="" system="">-<sap client="" id="">. For example, if your SAP System ID is D03 and your SAP Client ID is 001, then your CMMS ID would be DO3-001.</sap></sap>	Value is unique to the user.
PLASP FTP and STFP Parameters	Description	Recommenced or Default Value

PLSAP_FTP_MODE	The mode by which files are copied.	 SERVER: Enter this option to use file shares. FTP: Enter this option to use standard FTP. If this option is selected, then the subsequent parameters in this table are required. SFTP: Enter this option to use standard Secure FTP. If this option is selected, then the subsequent parameters in this table are required.
PLSAP_FTP_HOST	The FTP server host name.	Value is unique to the user, and only required if you are using SFTP file transfer method.
PLSAP_FTP_ USERID	The FTP server user name.	Value is unique to the user.
PLSAP_FTP_ PASSWORD	The FTP server password.	Value is unique to the user.
PLSAP_SFTP_SCP_ COMMAND	The FTP Command Name in SAP.	The default value is <i>ZSCP</i> .

PLSAP_FTP_PORT	The FTP server port.	If the default configuration was followed, enter one of the following:
		 21: Is the port number for FTP connections.
		 22: Is the port number for SFTP con- nections.
PLSAP_FTP_NUM_ OF_RETRY	The number of times to scan the FTP server for files.	Value is unique to the user.
PLSAP_FTP_SCAN_ DIR	The remote FTP directory used to scan for files.	10
PLSAP_FTP_ SLEEP_TIME	The time in seconds between scans.	10

-or-

Configure the Context File for the SAP PI Adapters On Premises

a. If you are deploying the SAP PI Adapters, the SAP Adapters for Process integration, enter the appropriate values for each parameter into the context file according to the following table.

SAP PI Parameter	Description	Default or Recom- mend Value
Intermediate Repos- itory connection para- meters	Description	Default or Recom- mended Value
IR_HOST	IP address of the IR.	Value is unique to the user.

Port number of the IR.	5432 (PostgreSQL default)
Database in which the IR data is stored.	APMconnectIR_ <release number=""></release>
Database in which the IR data is stored.	APMconnectIR_ <release number=""></release>
The schema in which the IR database will be created.	The default value is Public
The IR user name.	Enter the user name for the PostgresSQL database. The default user name is <i>postgres</i> .
The IR system pass-word.	Enter the password for the Post-gresSQL database that was created during installation.
Description	Default or Recom- mended Value
The name of the GE Digital APM server to which data will be loaded.	Value is unique to the user.
The GE Digital APM data source to which data will be loaded.	Value is unique to the user.
The GE Digital APM user name of the user loading data with the adapters.	Value is unique to the user.
	Database in which the IR data is stored. Database in which the IR data is stored. The schema in which the IR database will be created. The IR user name. The IR system password. Description The name of the GE Digital APM server to which data will be loaded. The GE Digital APM data source to which data will be loaded. The GE Digital APM user name of the user loading data with the

APM_PASSWORD	The GE Digital APM password of the user loading data with the adapters.	Value is unique to the user.
--------------	---	------------------------------

You can enter a value defined in GE Digital APM. Note: The value that is entered will be applied to all records. -or-You can use the character # at the Used to map the site beginning and end reference value to an of a GE Digital APM SAP field. This dictates Field Name to indic-SITE_REFERENCE_ which SAP field will be ate the field that is **EQUIP** used as the site refused to set the site erence for GE Digital reference. **APM Equipment** For example, if you records. wanted to use your SAP maintenance plant field as your GE Digital APM site reference, you would enter the following: <SITE_ REFERENCE EQUIP>#MI_ EQUIP000_MAINT_ PLANT_C#</SITE_ REFERENCE_ EQUIP>

		You can enter a value defined in GE Digital APM.
		Note: The value that is entered will be applied to all records.
SITE_REFERENCE_FLOC	Used to map the site reference value to an SAP field. This dictates which SAP field will be used as the site reference for GE Digital APM Equipment records.	-or- You can use the character # at the beginning and end of a GE Digital APM Field Name to indicate the field that is used to set the site reference. For example, if you wanted to use your SAP maintenance plant field as your GE Digital APM site reference, you would enter the following: <site_ floc="" reference_="">#MI_ FNCLOC00_MAINT_ PLANT_C#</site_>
Filter Parameters	Description	Default or Recom- mended Value

CREATE_DATE_END	Date value that limits the data extracted to records created on or before the specified date.	Dates must be entered in the following format: YYYYMMDD. Optional.
CHANGE_DATE_START	Date value that limits the data extracted to records changed on or after the specified date.	Dates must be entered in the following format: YYYYMMDD. Optional.
CHANGE_DATE_END	Date value that limits the data extracted to records changed on or before the spe- cified date.	Dates must be entered in the following format: YYYYMMDD. Optional.
CREATE_TIME_START	Time value that limits the data extracted to records created on or after the specified date.	Time must be in the following format: HHMMSS. Optional.
CREATE_TIME_END	Time value that limits the data extracted to records created on or before the specified date.	Time must be in the following format: HHMMSS. Optional.
CHANGE_TIME_START	Time value that limits the data extracted to records changed on or after the specified date.	Time must be in the following format: HHMMSS. Optional.

CHANGE_TIME_END	Time value that limits the data extracted to records changed on or before the spe- cified date.	Time must be in the following format: HHMMSS. Optional.
EQUIPMENT_NO	Equipment that you want to extract.	The Equipment number should not exceed 18 char- acters. You cannot exceed 500 Equip- ment numbers.
FLOC_NO	ID of the Functional Location that will limit the Functional Loca- tions extracted.	The Functional Location ID should not exceed 40 char- acters. You cannot exceed 500 Func- tional Location numbers.
NOTIFICATION_NO	Number that identifies the Notification record.	Notification Number should not exceed 12 characters.
WORK_ORDER_NO	Number that identifies the Work Order record.	Work Order Number should not exceed 12 characters.
MAINT_PLANT	ID(s) of the Main- tenance Plant whose data you want to extract.	Plant values cannot exceed four characters.
EQUIPMENT_ CATEGORY	ID of the Equipment Category that will limit the Equipment extrac- ted.	Must be a single character.

EQUIPMENT_TYPE	ID of the Equipment Type that will limit the Equipment extracted.	The Equipment Type should not exceed 10 characters.
		The Equipment Classification should not exceed 18 characters.
EQUIPMENT_CLASS	ID of the Equipment Classification that will limit the Equipment extracted.	If an Equipment has multiple Classifications, as long as you specify one of those Classifications, the Equipment record will be extracted.
LANGUAGE	The SAP code that represents the language.	Must be a single character.
NOTIFICATION_TYPE	Order type that limits the orders you want to extract.	Notification type should not exceed two characters.
WORK_ORDER_TYPE	ID of the Work Order that limits the orders you want to extract.	Work Order Type should not exceed four characters.
FLOC_CATEGORY	ID of the Functional Location Category that will limit the Func- tional Locations extracted.	Must be a single character.
FLOC_TYPE	ID of the Functional Location Type that will limit the Functional Locations extracted.	Functional Location Type should not exceed 10 characters.

FLOC_CLASS	ID of the Functional Location Classification that will limit the Func- tional Locations extracted.	Functional Location Classification should not exceed 18 characters.
WORK_ORDER_ SYSTEM_STATUS	Work Order Systems Status that limits the work orders you want to extract.	Work Order System Status should not exceed four characters.
WORK_ORDER_USER_ STATUS	Work Order User Status that limits the work orders you want to extract.	Work Order User Status should not exceed four char- acters.
NOTIFICATION_ SYSTEM_STATUS	Notification System Status that limits the notifications you want to extract.	Notification System Status should not exceed four characters.
NOTIFICATION_USER_ STATUS	Notification User Status that limits the notifications you want to extract.	User Status should not exceed four characters.

true false Note: If the MANUAL_RUN parameter is set to *true*, the dates specified in the context file will be used. Additionally, the dates of the last successful run stored in the database will not be updated. If set to Determines how the false, the date MANUAL_RUN dates parameters will range used durbe treated. ing the extraction will be the date of the last successful record, as stored in the database. Each time a lob is run successfully, the database is updated with those dates, and all subsequent runs will use the dates from the last successful record.

MAX_FILE_WAIT_SEC	How long the PI Adapters will wait for the extract to com- plete before the Job times out.	Recommended value is 1000 seconds.
EXTRACT_NUM_ PARALLEL_JOBS	The maximum number of parallel SAP jobs that APM Connect will open in a single extraction.	Choose a value that corresponds to the number of background processors that you have available to APM Connect.
IR_LOAD_NUM_ PARALLEL_JOBS	The maximum number of IR load jobs in a single extraction.	The recommended value is <i>30</i> .
LOG_REQUEST	Logs the APM Web service requests.	 true: enables logging false: disables logging Note: False is recommended.
LOG_RESPONSE	Logs the APM Web service responses.	 true: enables logging false: disables logging Note: False is recommended.

COMPRESS_TYPE	Determines if the files will be compressed and which method of compression is being used.	None: files will are not compressed SAPCAR: files are compressed by SAP. ZIP-files are compressed through a standard zip method.
COMPRESS_SAP_ COMMAND_NAME	The value of the <u>com</u> - <u>mand name created</u> .	ZSAPCAR
SAP PI Parameters		
SAP_SYSTEM_ID	Systems ID of the SAP systems you would like to extract from.	Value is unique to the user.
SAP_PI_HOST	The SAP PI server host.	Value is unique to the user.
SAP_PI_PORT	The SAP PI server port.	Value is unique to the user.
SAP_PI_RECEIVER_ PARTY	Receiver determined in the communication channel section in SAP.	This is optional and unique to the user.
SAP_PI_RECEIVER_ SERVICE	Receiver service determined in the communication channel section in SAP.	This is optional and unique to the user.

SAP_PI_SENDER_ PARTY	Receiver sender determined in the communication channel section in SAP.	This is optional and unique to the user.
SAP_PI_SENDER_ SERVICE	Sender service that must match what is in the Communication Channel in SAP.	Meridium_APMCon- nect
SAP_PI_USERID	The SAP User ID.	Value is unique to the user.
SAP_PI_PASSWORD	The SAP PI password.	Value is unique to the user.
FILE_MOVE_USE_PI	Determines if APM Connect should use the SAP-PI to extract and load data.	true -the file move- ment will use the PI between SAP and APM Connect. false- the file move- ment will not use PI and it will go dir- ectly.
PLSAP_INPUT	Base path of the directory you created in which APM Connect searches for the generated files from SAP.	Value is unique to the user.

PLASAP_OUTPUT	Path of the directory where the data is stored on the SAP server prior to sending it to the APMConnect server. This Directory should be shared with either the SAP PI server or the APMConnect Server depending on the value of FILE_MOVE_USE_PI.	Value is unique to the user.
SAP_PI_AAE	If you are using SAP 7.3 or above you many use the Advanced Adapter Engine (AAE). This parameter allows this functionality to be used during extraction.	 false: If you are not using AAE. This is the default. true: If you are using AAE.

What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Encrypt Passwords

Passwords in the APM Connect context file are not encrypted by default. However, you can encrypt any password manually. This topic describes how to manually encrypt passwords.

Steps

- 1. On the machine on which you installed APM Connect, access the APM Connect installation package, locate the *Encrypt String_0.1.zip*, and then unzip the file.
- Open the EncryptString folder, and then select EncryptString_run.bat.
 Command prompt opens, and then the Talend Open Studio window appears.
- 3. Enter the password that you want to encrypt in the **Enter the text to be encrypted:** box.
- 4. Select OK.
- 5. In the command prompt, between the banners, copy the text that was generated.
- 6. Open the context file.
- 7. In the parameter that you want to encrypt, paste the generated text.
- 8. Append the highlighted parameter the with _AES, as shown in the following image.

```
<!-- Intermediate Repository connection parameters-->
<IR_HOST>APMCONNECTVM</IR_HOST>
<IR_PORT>5432</IR_PORT>
<IR_DATABASE>APMconnectFTP</IR_DATABASE>
<IR_PASSWORD_AES>FyoGBWa6ftigcB2nAWZ56w==</IR_PASSWORD_AES>
```

- 9. Save the context file.
- 10. For each password that you want to encrypt, repeat steps 2 through 9. The passwords are encrypted.

What's Next?

- Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.
 -or-
- Return the <u>Maximo Adapter workflow</u> for the next steps in the deployment process.


Configure Context Parameters

For every job that is imported, certain context parameters in the APM Connect Administration Center must be configured. This topic describes how to configure the required context parameters, so that you can run the job.

Steps

- 1. In the APM Connect Administration Center, in the **Job Conductor** workspace, select the Job for which you would like to set parameters.
- 2. At the bottom of the **Job Conductor** workspace, select **Context parameters**.

The **Context parameters** section appears.



- 3. In the **Context parameter** column, scroll down to the context parameter you would like to configure.
- 4. In the **Custom value** box, configure context parameters, and select the **Active** check boxes for the following:
 - APM User_ID: Enter your GE Digital APM user name
 - APM_PASSWORD: Enter your GE Digital APM password.
 - **IR_USERID**:Enter the your intermediate repository user name.
 - **IR_PASSWORD**: Enter your intermediate repository password.
 - SAP_USERID: Enter you SAP System user name.
 - SAP_PASSWORD: Enter your SAP system password.
 - **CONFIG_FILE_PATH**: Enter the file path to the location where the context file is stored.
 - LOG4j_FILE_PATH: Enter the filed path to the location where the Log4j file is stored. If you installed APM Connect in the defualt location, then enter \APMConnect\Config\log4jproperties
 - MANUAL_RUN: Enter true or false to determine whether or not the dates

recorded in the context file will be used during extraction.

Note: If the MANUAL_RUN parameter is set to *true*, the dates specified in the context file will be used. Additionally, the dates of the last successful run stored in the database will not be updated. If set to *false*, the date range used during the extraction will be the date of the last successful run, as stored in the database. Each time a Job is run successfully, the database is updated with those dates, and all subsequent runs will use the dates from the last successful run.

The context parameters are configured.

- 5. Repeat steps 1-3 for every imported Job you will run.
- 6. To configure the Master job to run, select the SAP_MASTER_INTERFACE Job.
- 7. At the bottom of the **Job Conductor** workspace, select **Context parameters**.

The **Context parameters** section appears, displaying the following parameters:

- RUN_STATIC_DATA: The Static Data Job
- RUN_EQUIPMENT: The Equipment Job
- RUN_FLOC: The Functional Location Job
- RUN_WORKHISTORY: The Work History Job
- RUN_WORKMANAGEMENT: The Work Management Job
- MASTER_CONFIG_FILE_DIR: The file path to context files for the jobs
- SYSTEM_TO_RUN: The source system from which you want to extract data
- RUN_TC_EQUIPMENT: The Equipment Technical Characteristic Job
- RUN_TC_FLOC: The Functional Location Technical Characteristics Job
- 8. For each extraction jobs you want to run, in the **Custom value** column enter *true*, and then select the **Active** check box.
- 9. In the MASTER_CONFIG_FILE_DIRCustom value box, enter the directory where the context file(s) is stored.
- 10. In the **SYSTEM_TO_RUNCustom value** box enter:
 - The name of the system directory from which you want to extract data.
 -or-
 - * to extract from all systems.
- 11. Press Enter.

The Jobs are configured to run.

What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Configure the Context Parameters for APM Now

<u>MPORTANT:</u> The Extraction Wrapper job is required only for APM Now deployment of the SAP Adapters.

The extraction wrapper job is a container job for the following APM Now SAP Adapters extraction jobs:


- RUN_STATIC_DATA
- RUN_EQUIPMENT
- RUN_FLOC
- RUN_WORKHISTORY

In addition to the extractions jobs, the Extraction Wrapper contains additional context parameters are required to configure the jobs to run.

Steps

1. In the APM Connect Administration Center, in the **Job Conductor** workspace, select the Extraction Wrapper job, and then select **Context parameters**.


The **Context parameters** section appears.



- 2. Configure the **Custom value** for the following connection parameters:
 - CONFIG_FILE_DIR: Enter the directory path where your context file is stored.
 - SYSTEM_TO_RUN: Enter the <u>name of the directory</u> containing the context file from which you want to extract data, or, to extract from all context directories, enter *.
 - LOG_BASE_DIR: Enter the directory path into which the log files will be written.

- LOG4J_CONFIG_FILE: Enter the directory path where your log4j properties file is stored.
- 3. Select the **Active** check box corresponding to each of the connection parameters.
- 4. For each extraction jobs you want to run, in the **Custom value** column enter *true*, and then select the **Active** check box.

For example, if you want run only the Equipment Adapter, in the RUN_ EQUIPMENT row, in the Custom value box enter true. Then, select the Active check box.



The Extraction Wrapper job is configured to run. Once the job is executed, the data designated to be extracted in the **Connect parameters** will be transferred from your SAP System to your GE Digital APM system.

- 5. For each of the remaining jobs imported into the APM Connect Administration center, select the job, and then **Context parameters**.
- 6. Configure the following parameters:
 - CONFIG_FILE_PATH: Enter the directory path where your context file is stored including the name of the context file, e.g.C:\APMConnect\Config\SYS-001\SAP_ContextFile.xml
 - LOG4J_CONFIG_FILE: Enter the directory path where your log4j properties file is stored. including the file name e.g. C:\APMConnect\Config\log4j.properties
- 7. Repeat steps 5-7 for each imported job that you plan to run.

The jobs are configured to run.

What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Create the Intermediate Repository Database

Before you can run an extraction job, you must prepare the intermediate repository and enable the static data pull. This topic describes how to set up a repository and static data pull in preparation to run your first job.

<u>MPORTANT</u>: If you are using the Data Loaders and the SAP Adapters, you must deploy and run the *CreateIntermediateRepository* job for each set of adapters.

Before You Begin

Before you can prepare and deploy the repository, you must import the Create Intermediate Repository Job

Steps

1. Open and log in to the APM Connect Administration Center web application.

Note: The user logging in must have access to the Job Conductor by being designated the Operations Manager role. By default, users designated admin do not have Job Conductor permissions.

- 2. In the **Job Conductor** workspace, in the appropriate project, select the *CreateIntermediateRepository* Job.
- 3. At the bottom of the **Job Conductor** workspace, select **Context parameters**. The **Context parameters** section appears.
- 4. Configure the following parameters:

Context Parameter	Description
CONFIG_FILE_DIRECTORY	The file path to context files for the jobs.
PG_ADMIN_USERNAME	The user name for the PostGresSQL IR.
PG_ADMIN_PASSWORD	The password for the PostGresSQL IR.
apmconnect_Database	Enter your APM Connect database name.
	The default value is DINODB.

apmconnect_Login	Enter your APM Connect database username.
apmconnect_Password	Enter your APM Connect database password.
apmconnect_Server	Enter your APM connect server name

5. Select **Run**.

The intermediate repository is created for the project.

- 6. In the **Job Conductor** workspace, in the appropriate project, select the *CreateStaticData* Job.
- 7. Select Run.

The static data pull is enabled.

You are now able to execute the jobs.

What's Next?

- Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.
 -or-
- Return to the <u>Maximo Adapter workflow</u> for the next steps in the deployment process.
 - -or-
- Return to the <u>Data Loader workflow</u> for the next step in the deployment process.

About Site Filtering

Note: This site filtering configuration applies only to the APM Now environment. If you are deploying the SAP Adapters on-premises, site filtering is handled by <u>parameters</u> in the context file.

Site Reference values are managed in the Intermediate Repository specifically in the autojoin_control table.

			default_site_reference character varying
MI_SITE_NAME	MI_FNCLOC00	0	*Global*
MI_SITE_NAME	<pred_family_id></pred_family_id>	1	*Global*
MI_SITE_NAME	MI_EQUIPO00	1	*Global*
	character varying MI_SITE_NAME MI_SITE_NAME	character varying character varying MI_SITE_NAME MI_FNCLOCOO MI_SITE_NAME <pred_family_id></pred_family_id>	MI_SITE_NAME MI_FNCLOCOO 0 MI_SITE_NAME <pred_family_id> 1</pred_family_id>

There are many columns in the autojoin_control table. The follow apply directly to site reference:

- **site_reference**: the Site Reference to be used. This can be the name of a specific site, or it can contain an indirect site reference.
 - Note: The baseline value is #MI_FNCLOCOO_SAP_SYSTEM_C# for Functional Location Records and #MI_EQUIPOO_SAP_SYSTEM_C# for equipment records. This means the SAP System will determine to which site records are assigned.
- apm_site_reference_column: The GE Digital APM column used to store Site Reference values.
- apm_site_reference_family: The GE Digital APM family to which the site reference will be applied. When the relationship is being built within the records of the same entity. The value is <PRED_FAMILY_ID>.
- **use_relationship_lookup**: signifies if the sheet is the for the entity or the relationship
- **default_site_reference**: The default site reference used when the specified site reference value is blank a record being imported.
 - Enter *Global* to assign the site as global
 - Enter the name of a site to assign records to that site.

About the Baseline Site Reference Configuration

The baseline configuration of the SAP Adapters uses the SAP System to determine to which site a record should be assign. This is driven by the value <code>,#MI_EQUIP00_SAP_SYSTEM_C#</code> and <code>MFUNCL00_SAP_SYSTEM_C#</code>, in the site_reference column in the auto-join_control table.

Additionally, if SAP System value is null or empty on a record is SAP, once transferred into GE Digital APM, it will be assign the site reference defined in the defaut_site_reference column in the autojoin_control table. The default value is Global.

If you want to use your SAP System as the site for all records transferred from SAP to APM then no additional configuration is needed.

Note: A Site Reference record corresponding to your SAP System(s) must exist in GE Digital APM before you can transfer records.

Mount a File Share

To enable writing files between the servers within your APM Connect architecture, file shares need to be mounted. This topic details the basic process for setting up a file share based on your operating systems. Generally, this process involves, creating a file share to be mounted, then mounting the file share, and then making the file share permanent.

<u>MPORTANT</u>: The process can vary greatly between organizations based on network configurations. Additionally, this procedure should be completed by an administrator with the expertise to manage network configurations.

Before You Begin


- Be sure that you understand the recommended configurations to enable <u>file</u> shares within the APM Connect architecture.
- You will need access to the Linux console and root privileges on your Linux server.
- You will need the APM Connect server service account user name and password.
- You should be a network administrator with working knowledge of your network configurations.

Steps: Create a File Share on a Windows Server, and then Mount the Share to a Linux Server


Create the File Share

- 1. On your APM Connect server (i.e., the Windows server on which you want to create the share), create a new folder for file sharing.
 - Note: This share can be anywhere on your APM Connect server and can have any name.
- 2. Right-click on the new folder, and then select **Properties**.

The **<Folder Name> Properties** window appears.



Select the Sharing tab, and then select Advanced Sharing.
 The Advanced Sharing window appears.




4. Select the **Share this folder** check box.

The other fields on the window are enabled.


- 5. Optionally, edit the name in the **Share name:** box. If you do not edit this name, the name will default to the folder name.
- 6. Select **Permissions**.

The **Permissions for <Folder Name>** window appears.



7. Select Add....

The Select, Users, Computers, Service Accounts, or Groups window appears.



8. In the **Enter the object names to select (examples)** box, enter the name of your APM Connect service account user.

Note: The user must have permission to read and write to the shared folder.

9. Select **OK**.

The Select, Users, Computers, Service Accounts, or Groups window closes.

- 10. On the Permissions for <Folder Name> window, in the Permissions for <Service User Name> box, in the Allow column select the Full Control check box, the Change check box, and the Read check box.
- 11. Select **OK**.

The **Permissions for <Folder Name>** window closes.

12. On the Advanced Sharing window, select OK.

The **Advanced Sharing** window closes. Then, on the **Folder Name Properties** window, in the **Network File and Folder Sharing** section, the **Network Path:** subsection is populated.

13. Record the network path.

Mount the File Share

- 14. Access your SAP PI Server or your SAP server (i.e., the Linux server to which you want to mount the share) via a Linux Command Line Editor tool (e.g., Vim or Nano).
- 15. Determine an existing directory that will be used as the share, or create a new directory.
- 16. In that directory, to initiate the connection between your source and target share, execute a mount command. The command will likely require the APM Connect service account user, source of the file share folder you created on the APM Connect server, and target for the share on your Linux server.

(i) **Tip:** The exact mount command will vary based on the system that you are using. An example of a mount command is *mount -t smbfs -o user-name=Administrator //recurring/c\$ /mnt/recurring*

17. To verify that the new mount is configured correctly, enter the command *mount*.

The mount appears in the list of mounted shares.

Tip: At this point, you should be able to write files from one share to another. To test, place a file in the source folder on the Windows machine, and then the file should appear in the target directory on the Linux machine.

Make the Share Permanent

18. On the Linux machine, navigate to the file /etc/fstab.

Tip: Mounting the share into the /etc/fstab file makes the file share permanent meaning that upon reboot the file share is still be mounted. If you do not execute the mount in this location, once the machine is rebooted the mount will be disconnected.

- 19. Open the file to be edited using a data base editor (e.g. Vim or Nano).
- 20. Add a new line to the file defining the share, mount point, file system driver, and options.

Tip: The following is an example of the file syntax: //<Source Folder Name> /<Target Folder Name <Systems Type or Driver> username=username password=<password> 02.

Additionally, the following is the same entry with sample values: //APMConnectServer1/WindowsSharedFolder /opt/LinuxSharedFolder cifs –o username=APMConnectSeriveAccount1 password=APMConnect 0 2

- 21. Close the file, and then return to the root directory.
- 22. To unmount the share created, execute the command *umount* (i.e., if the original mount directory was */opt/LinuxFileShare*, then execute the command *unmount /opt/LinuxFileShare*).

Tip: You must unmount the share from the original location for it to be mounted from the /etc/fstab file.

23. Execute the command *mount*.

The original mount directory does not appear in the list of mounted shares, and the new share in the /etc/fstab folder can be mounted.

- 24. Execute the command *mount –a*.
 - **Tip:** Executing the command will read the configuration from the /etc/fstab file, and then preform the mount operation based on the parameters in the file.
- 25. To verify that the share has been mounted, execute the command *mount*.

The new mount point added to the /etc/fstab file appears in the list.

At this point, you can place a file on the APM Connect server in the shared folder, and it will be transferred to the shared Linux folder.

Steps: Create a File Share on a Linux Server, and then Mount the Share to a Linux Server

Create the File Share

- 1. Access your SAP Server (i.e., the Linux server to which you want to mount the share) via a Linux Command Line Editor tool (e.g., Vim or Nano).
- 2. Ensure that the *nfs-kernel-server* service is installed and running.

<u>MIMPORTANT</u>: The name of this service can vary based on the Linux system.

- 3. Create the directory that will be mounted to you SAP PI server.
- 4. To grant the remote server permission to mount a local directory, locate the file /etc/exports.
- 5. In that file, enter the directory you created in Step 3, and then identify the server that can mount the directory.

For example, if you wanted to create the directory /opt/PI_FileShare and grant all users permissions to mount that directory, then you would enter the following: /opt/PI_FileShare *(rw, sync, no_root_squash, not_subtree_check).

- **Tip:** You can find all of the export options and access control lists in the manual file accessed by executing the command *man exports*.
- 6. Restart the service /etc/init.d/nfs-kernel-server.

Mount the File Share

- 7. Access your SAP PI server (i.e., the Linux machine to which you want to mount the share).
- 8. Create a directory to which files will be written from the share.

9. Execute the mount command to mount the exported directory on to the SAP PI server.

Tip: The exact mount command will vary based on the system that you are using. An example of a mount command is *mount example.host-name.com:/ubuntu/local/ubuntu.*

For example, if your SAP PI server hostname is SAPPIServer1, your source directory is /opt/PI_FileShare, and your target directory is /opt/SAP_FileShare, you would enter the following: mount SAPPIServer1: /opt/PI_File_Share /opt/SAP_FileShare

10. The directory created in step 8 appears in the list of mounted directories.

① **Tip:** At this point, you should be able to write files from one share to another. To test, place a file in the source folder on the Windows machine, and then the file should appear in the target directory on the Linux machine

Make the File Share Permanent

11. On the Linux machine on which the share will be mounted, navigate to the file /etc/fstab.

(i) **Tip:** Mounting the share into the /etc/fstab file makes the file share permanent, meaning that upon reboot the file share will still be mounted. If you do not execute the mount in this location, once the machine is rebooted the mount will be disconnected.

- 12. Open the file to be edited using a database editor (e.g., Vim or Nano).
- 13. Add a new line to the file defining the share, mount point, file system driver, and options.

(i) **Tip:** The following is an example of the file syntax: <exporting server host-name>:<exported Folder Name> <Target Folder Name> <Systems Type or Driver> 0 2.

Additionally, the following is the same entry with sample values: *APMConnectServer1.company.com:/exportedFolder /opt/mountpointFolder nfs 0 2*

- 14. Close the file, and then return to the root directory.
- 15. To unmount the share in the directory created in step 8, execute the command

umount.

For example if the original mount directory was /opt/LinuxFileShare, then execute the command *unmount /opt/LinuxFileShare*.

①Tip: You must unmount the share from the original location for it to be mounted from the /etc/fstab file.

16. Execute the command *mount -a*.

Tip: Executing the command will read the configuration from the /etc/fstab file, and then preform the mount operation based on the parameters in the file.

17. To verify that the share has been mounted, execute the command *mount*.

The new mount point added to the /etc/fstab file appears in the list.

At this point, you can place a file on the APM Connect server in the shared folder, and it will be transferred to the shared Linux folder.

What's Next?

• Return to the SAP Adapter workflow for the next step in the deployment process.

About File Shares and APM Connect


File shares mounted in the APM Connect architecture allow you to read and write files between servers within your architecture configuration.

File Mount Configurations

If you are using SAP PI, create a file share on your APM Connect server, and then mount it to your SAP PI server. Then, create a share on your SAP server, and then mount to your SAP PI Server. Similarly, if you are not using SAP PI, or you are bypassing your SAP PI server, you must create a file share on your APM Connect server, and then mount it to your SAP Server.

Note: The SAP PI Adapters determine if SAP PI server will be used via the FILE_MOVE_USE_PI parameter in the context file. If the parameter is true, then SAP PI will be used to copy files from your SAP server to your APM Connect server. If it is false, SAP PI will not be used to copy files from your SAP server to your APM Connect sever. In both configurations however, the SAP PI server will be used to proxy RFC calls.

Additionally, in the most common architecture, the APM Connect server is hosted on a Windows Sever with the SAP server and the SAP PI server hosed on a Linux server. The following diagrams details the recommended configurations.



User's Permissions for File Shares

When using a shared file system to facilitate data extraction from SAP to APM Connect,

you will need to grant the <u>service account user(s)</u> the appropriate permissions to access both systems.

Note: Using active directory to manage the service account is recommended.

The volume to be mounted can be in three configurations: NAS/SAN, Windows, or Unix. Additionally, access control could be different for each configuration, as shown in the following table:

(i) **Tip:** When the shares are created and permissions configured correctly, <u>run the equipment job</u> for a single equipment ID. This is a quick and easy way to check that permissions are set up correctly. After you run the job, a file will be created using the SAP service account, then opened and read by the APM Connect

Volume (Disk, Share, LUN)	Access Control
NAS/SAN	Vendor specific user mapping (i.e. NetApp), or active directory integrations.
Windows	Users/Groups permissions are defined in Active Directory.
Unix	Active Directory integration, or user maps (i.e. Samba or Config).

Load Bulk IDs

To load more than 5,000 IDs in GE Digital APM, you must <u>use the Load_ID_List job</u> and the corresponding Excel template. You will need to create a directory structure on your APM Connect server that will allow many IDs to be loaded into GE Digital APM and configure the BASE_DIRECTORY parameter in the context file.

Steps

- 1. On the machine on which you installed APM Connect, determine a <u>base file path</u> where you would like to place the input Excel file and archive the bulk ID loads.
- 2. Create the following subdirectories to load IDs for each type of IDs you plan to load:

ID Type	Directory Structure	If ZERO_ PAD_ID is enabled, then
Equipment IDs:	<pre><base directory=""/>/EQUIPMENT/input/ archive</pre>	IDs will be padded up to 18 characters.
Functional Loca- tion IDs	<base directory=""/> /FLOC/input/archive	N/A: Func- tional Loca- tion IDs are not padded.
Work History Noti- fication IDs	<pre><base dir-="" ectory=""/>/WH/NOTIFICATION/input/archive</pre>	IDs will be padded up to 12 characters.
Work Order IDs	<pre><base dir-="" ectory=""/>/WH/WORKORDER/input/archive</pre>	IDs will be padded up to 12 characters.
Work Management Equipment IDs:	<base directory=""/> /WMI/EQUI/input/archive	IDs will be padded up to 12 characters.
Work Management Functional Loca- tion IDs:	<base directory=""/> /WMI/FLOC/input/archive	N/A: Func- tional Loca- tion IDs are not padded.

Technical Char- acteristic Equip- ment IDs:	<base directory=""/> /EQUIPMENT_TC/input/ archive	IDs will be padded up to 18 characters.
Technical Characteristic Functional Location IDs:	<base directory=""/> /FLOC_TC/input/archive	N/A: Func- tional Loca- tion IDs are not padded.

Note: You cannot load Locations with the Load_ID_List job. You can only load internal IDs for Functional Locations. Additionally, you cannot load class information for Technical Characteristics. You can only load Equipment and Functional Location IDs.

- 3. Into each corresponding directory, place the Excel file(s) listing the IDs that you would like to load into GE Digital APM.
- 4. Run the Load_ID_List job in the APM Connect Administration Center.

Results

• The IDs in the Excel file are loaded into GE Digital APM, The Excel file is removed for the input directory, and then the Excel file is relocated to the archive directory.

What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Establish SFTP Transfer in SAP

l Note: If you using SAP PI, then you can skip this procedure.

If you use (S)FTP to transfer files between SAP, APM Connect, and GE Digital APM, you must complete additional configuration in SAP. You must download a puTTY file and set up command names in SAP to use the puTTY file.

Steps

- 1. On your SAP system, in a browser, navigate to the PuTTY website.
- 2. Download the following puTTy file: pscp.exe.
- 3. Copy it into the PATH on your SAP system. The recommended directory is *%WINDIR%/System32*.
- 4. In SAP, run the transaction code SM69.

The External Operation System Commands screen appears.

5. Select 🛅.

The **Create an External Command** screen appears.

- 6. In the **Command Section**, in the **Command Name** box, enter a name for your command.
- 7. In the **Definition** section, in the **Operating system command** box, enter following systems commands: *pscp*.
- 8. Select Save.

The puTTY file is on the SAP system, and the corresponding command names are set up.

What's Next?

Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Create File Share Folder Structure

The Note: If you using SAP PI, then you can skip this procedure.

When SAP writes a data file, it is placed in a specific directory defined by the context parameter PLSAP_INPUT. This topic describes how to create the appropriate directory structure.


Steps

1. Navigate to the folder on which your SAP system writes files.

Note: This folder will be different for each customer, but will likely be labeled PLSAP_INPUT.

- 2. Create a new folder for each of the following:
 - EQUIPMENT
 - FLOC
 - TC
 - WMI
 - WORKHISTORY

The file structure will look like the following image:



The directory is created, and SAP will be able to write files to the necessary location.

What's Next?

• Return to the SAP Adapter workflow for the next step in the deployment process.

Install the ABAP Base Service Pack Add-on

Note: To complete the following instructions successfully, you must use SAP client 000.

Before You Begin

Determine the release and level of your current ABAP installation by completing the steps to verify the ABAP installation.

Steps

- 1. On a machine from which you can access the SAP Server, insert the SAP Interfaces installation DVD.
- 2. If your currently installed ABAP release is 400_600 and level is 0000, proceed to Step 18 (i.e., you do not need to complete Steps 3 through 17).

-or-

If your currently installed ABAP release is any other version, or if you are installing the ABAP Add-on for the first time, continue to the next step.


- 3. Navigate to the folder \\SAP Interfaces ABAP Add-On\Service Pack Files, and then select one of the following folders:
 - Exchange Upgrade: To upgrade the ABAP package when upgrading to a new SAP version.
 - Install: To install the ABAP Package for the first time.
 - **Upgrade**: To upgrade the ABAP package.
- 4. Navigate to the subfolder ECC6, and copy the .PAT file(s).
- 5. On the SAP Server, paste the copied file into the folder \\usr\sap\trans\eps\in.
- 6. Log in to the SAP system as a user with:
 - SCTSIMPSGL and S_CTS_ADMIN authorizations.

-or-

- SAP_ALL authorization.
- 7. Run the following transaction: **SAINT**.

The **Add-On Installation Tool** screen appears.

8. On the **Installation Package** menu, point to **Load packages**, and then select **From Application Server**.




A message appears, asking if you want to upload OCS packages from the ECS inbox.

9. Select Yes.

The SAINT: Uploading Packages from the File System screen appears.

SAINT: Uploading Packages from the File System



- 10. Select the .PAT file that you copied in step 3 of these instructions. The message column should read **Uploaded successfully**.
- 11. Select 🚷.

The **Add-On Installation Tool** screen appears again.

12. Select Start.

A new grid appears. MIAPMINT appears in the list of add-on packages that can be installed.

13. Select the row containing the value MIAPMINT in the first column, and then select **Continue**.

The **Support Package selection** tab appears.

- 14. Select Continue.
- 15. Select **Continue** again.

Note: During the installation, the Add Modification Adjustment Transports to the Queue dialog box might appear. If it does, select No.

An indicator appears at the bottom of the screen to indicate the installation progress.

When the progress indicator disappears, a message appears, indicating that the add-on package will be installed.

16. Select **✓**.

The status is updated to indicate that the add-on package will now be imported, and the installation process continues.

When the installation process is complete, the status is updated to indicate that the add-on package was imported successfully.

17. Select Finish.

The MIAPMINT add-on package appears in the list of installed add-on packages on the Add-On Installation Tool screen.

- 18. On the SAP Interfaces installation DVD, navigate to the folder \\SAP Interfaces ABAP Add-On/Support Package.
- 19. Navigate to the folder **ECC6**, and copy the .PAT file(s).
- 20. On the SAP Server, paste the copied file(s) into the folder \\usr\sap\trans\eps\in.
- 21. Log in to the SAP system.
- 22. Run the following transaction: **SPAM**.

The **Support Package Manager** screen appears.

23. On the **Support Package** menu, point to **Load Packages**, and then select **From Application Server**.

A message appears, asking if you want to upload the package.

24. Select Yes.

A summary screen appears, indicating that the package was uploaded successfully.

- 25. Select Back.
- 26. Select **Display/define**.

The **Component Selection** dialog box appears.

- 27. Select the **MIAPMINT** component.
- 28. When prompted, confirm that the patch will be imported into the queue, and then select \checkmark .
- 29. On the **Support Package** menu, select 🔒.
- 30. On the **SPAM: Import: Queue** dialogue box, select ✓.

The import process begins. When it is complete, a message appears, indicating that the import process was successful.

31. Select **Continue**.

Another message appears, indicating that the import process was successful.

- 32. Select ✓.
- 33. On the **Support Package** menu, select **%**.

The installation is complete.

What's Next?


• Return to the SAP Adapter workflow for the next step in the deployment process.

Verify ABAP Installation

Steps


1. In SAP, on the **System** menu, select **Status**.

The **System: Status** window appears.



2. In the SAP System data section, select 📵.

The **Support Package Level for Installed Software Components** window appears.



3. If you deployed the SAP Adapter's ABAP Add-On package, scroll down until you see the Software Component *MIAPMINT*. If you see the following values in the following columns, the Add-On was applied successfully:

• Release: 400_600, where <SAP version> indicates the version of SAP that you have installed.

Level: 0030


What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Create APM Connect User Profile in SAP

1. In SAP, run the transaction *PFCG*.

The role maintenance screen appears.



2. In the **Role** box enter the role name *ZRM_APMConnect_auth_profile*, and then select **Single Role**.

The **Display Roles** screen appears.

- 3. Select the **Authorizations** tab.
- 4. In the Maintain Authorization Data and Generate Profiles section, on the Change Authorization Data row, select .

The **Choose Template** window appears.

5. Select do not select templates.

The **Change Role: Authorizations** window appears.

6. Select **Manually**.

The **Manual selection of authorizations** pane appears.

- 7. In the **Authorization Object** box enter the following:
 - S_RFC
 - S_BTCH_JOB
 - S_DATASET
 - S_TABU_NAM
 - S_LOG_COM
 - I_QMEL
 - I_AUART
 - I_BETRVORG
 - C_TCLA_BKA
- 8. Select ✓.
- 9. On the **Cross-application Authorization Objects** row to expand the workspace, select . To a selec

- 10. On the **Activity** row, select .The Define Values window appears.
- 11. Select the **Execute** box.

Select 📙 .

What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

SAP Interfaces Security Groups

The following table lists the baseline Security Groups available for users within this module, as well as the baseline Roles to which those Security Groups are assigned.

<u>MPORTANT</u>: Assigning a Security User to a Role grants that user the privileges associated with *all* of the Security Groups that are assigned to that Role. To avoid granting a Security User unintended privileges, before assigning a Security User to a Role, be sure to review all of the privileges associated with the Security Groups assigned to that Role. Also, be aware that additional Roles, as well as Security Groups assigned to existing Roles, can be added via Security Manager.

Security Group	Roles
MI SAP Interface Administrator	None
MI SAP Interface User	None

The baseline family-level privileges that exist for these Security Groups are summarized in the following table.

Family	MI SAP Interface Administrator	MI SAP Interface User
Entity Family		
Confirmation	View, Update, Insert, Delete	View, Update, Insert
Equipment	View, Update, Insert, Delete	View, Update, Insert
Functional Location	View, Update, Insert, Delete	View, Update, Insert
SAP System	View, Update, Insert, Delete	View
Site Reference	View	View
Work History	View, Update, Insert, Delete	View, Update, Insert
Work History Detail	View, Update, Insert, Delete	View, Update, Insert
Relationship Families		
Equipment Has Equipment	View, Update, Insert, Delete	View, Update, Insert, Delete
Functional Location Has Equipment	View, Update, Insert, Delete	View, Update, Insert, Delete
Functional Location Has Functional Location(s)	View, Update, Insert, Delete	View, Update, Insert, Delete

Has Confirmation	View, Update, Insert, Delete	View, Update, Insert, Delete
Has Event Detail	View, Update, Insert, Delete	View, Update, Insert, Delete
Has SAP System	View, Update, Insert, Delete	View, Update, Insert, Delete
Has Work History	View, Update, Insert, Delete	View, Update, Insert, Delete
User Assignment	View, Update, Insert, Delete	View, Update, Insert, Delete

Identify Trigger Values for Creating Task Records

The Work Management Adapter allows you to create Inspection Task and Calibration Task records from SAP Maintenance Plans using Operations and Object Lists. This topic describes how to identify which values in an Operation or Object list will trigger the creation of which Task records in GE Digital APM.

The baseline product is configured such that:

- Operations with the control key ZMI2 will be used to create Calibration Task records.
- Operations with the control key ZMI1 will be used to create Inspection Task records.

Note: You are not required to use the default configuration. If you want to use values in different Operation fields (not control keys) to trigger the creation of GE Digital APM Task records, you can do so.

Steps

- If you want to accept the baseline configuration complete the following:
 - a. Create the control keys ZMI1 and ZMI2.
 - b. In the <u>context file</u>, configure the following <u>Work Management parameters</u> to enable trigger values.

What's Next?

Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Configure GE Digital APM to Create Notifications from Recommendation Records

The SAP Interfaces feature allows you to create Recommendation records in GE Digital APM that will be used to create SAP Notifications automatically. For a Recommendation record to generate an SAP Notification automatically, the Create Work Request field must exist on the Recommendation datasheet. This field is available on the baseline datasheets for the baseline Recommendation families from which you are allowed to create SAP Notifications.

If you want to generate SAP Notifications from Recommendation records that belong to customer-defined subfamilies of the root Recommendation family, in addition to implementing the correct rules (for an example of the rules that you will need to implement, you can look at any active baseline Recommendation family), you will need to add the Create Work Request field to the desired datasheets for that family.

(i) Hint: You can create multiple types of SAP Notifications (e.g., M1) from Recommendation records. By default, GE Digital APM creates M1 Notifications.

Steps

- 1. If you want to create different Notification types, you will need to:
 - a. Add the Notification Type field to the datasheet.
 - b. Configure the Notification Type field to accept values other than M1.

Note: In the baseline SAP Interfaces product, this field is disabled. If desired, you could configure it to be enabled so that users can type a value directly in the Notification Type cell on the datasheet. You might also consider creating a Valid Values rule that provides a list of acceptable values so that users can select the desired value from the list.

What's Next?

Return to the workflow for the next step in the deployment process.

Deploy and Configure the RFC Connector Files

As recommended and by default, a RestFUL SAP web service call is used as an intermediary between SAP and GE Digital APM, thereby avoiding RFC calls directly between GE Digital APM and your SAP sever. Complete these steps to deploy and configure the files necessary to enable this connection.

Steps

- 1. Access the APM Connect installation package, and then copy the file *SAP_RFC_Connector.jar*.
- 2. On your APM Connect server, navigate to <root:>\APMConnect\Utilities\runtime\deploy.
- 3. Paste the copied file SAP_RFC_Connector.jar into the directory.
- 4. Access the APM Connect installation package again, and then copy the file *SAP_RFC_CONNECTOR.xml*.
- 5. On your APM Connect server, navigate to <*root:*>\APMConnect\Utilities\runtime\etc.
- 6. Paste the copied file SAP_RFC_CONNECTOR.xml in the directory.
- 7. If you are *not* using SAP PI, the required parameters are configured by default, so no further steps are required.

-or-

If you are using SAP PI, open the file and configure the following parameters as necessary.

Parameter	Description	Default or Recommended Value
LOG_ REQUEST	Specified whether or not APM Web service requests are logged.	This setting is optional. The default value is <i>false</i> , which means that logging is not enabled.
LOG_ RESPONSE	Specified whether or not APM Web service responses are logged.	This setting is optional. The default value is <i>false</i> , which means that logging is not enabled.
SAP_USE_PI	Specifies whether or not you want to use an SAP PI connection.	The default value is <i>false</i> . Specify <i>true</i> to use SAP PI.

SAP_PI_AAE	If you are using SAP 7.3 or above you may use the Advanced Adapter Engine (AAE). This parameter enables this functionality.	The default value is <i>false</i> . Specify <i>true</i> if you want to use AAE.
SAP System ID tags	Replace the default value in both the closing and opening tags with the value in the name field (SAP_SYSTEM_NAME) of the corresponding EAM System record. For example, if the system name defined in the EAM record is PRF-800, the opening tag would be <prf-800> and the closing tag would be </prf-800> .	The default placeholder value is <i>D07-001</i> . Within these tags, you must specify the relevant SAP PI details using the parameters described in the remainder of this table.
SAP_PI_ HOST	The SAP PI server host.	This value is unique to the user. Required only if you are using SAP PI.
SAP_PI_ PORT	The SAP PI server port.	This value is unique to the user. Required only if you are using SAP PI.
SAP_PI_ USERID	A user ID associated with the SAP PI system.	This value is unique to the user. Required only if you are using SAP PI.
		This value is unique to the user.
SAP_PI_ PASSWORD_ AES	The password associated with the specified user.	The password must be encrypted before you enter it into this parameter. See the Encrypt Passwords topic for details.
		Required only if you are using SAP PI.
SAP_PI_ SENDER_ SERVICE	The sender service that matches what is in the Communication Channel in SAP.	The default value is Meridium_APMConnect. Required only if you are using SAP PI.

SAP_PI_ RECEIVER_ PARTY	Receiver determined in the communication channel section in SAP.	This value is optional and unique to the user. Required only if you are using SAP PI.
SAP_PI_ RECEIVER_ SERVICE	Receiver service determined in the communication channel section in SAP.	This value is optional and unique to the user. Required only if you are using SAP PI.
SAP_PI_ SENDER_ PARTY	Receiver sender determined in the communication channel section in SAP.	This value is optional and unique to the user. Required only if you are using SAP PI.
SAP_PI_URL	Custom URL defining the sender service and receiver service. If this is used, the SAP PI Configuration parameters above, other than Other than SAP_PI_USERID, SAP_PI_PASSWORD_AES, are ignored.	This value is optional. Required only if you are using SAP PI.

8. Save and close the file.

The RFC Connector files are deployed and configured.

What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Configure Notification Priority

You can configure the priority value in GE Digital APM to match the priority value in SAP by editing the MI_PRIORITY system code table.

Steps

- 1. Determine the values in your EAM system that determine priority.
- 2. For each priority that exist in you EAM System, modify the MI_PRIORITY system table to match the values in your EAM system.

Results

 When priority values are transferred from a GE Digital APM recommendation to an SAP Notification, the priority values will match.

What's Next?

• Return to the workflow for the next step in the deployment process.

Create an EAM System Record

You must configure an EAM System Record to establish a connection between any EAM system and GE Digital APM.

Steps

- 1. Create a new record, using the EAM System family.
- 2. In the Name box, enter the name of your SAP system
- 3. If this SAP system is the system to and from which you want to send data by default, select the **Default EAM System?** check box.
- 4. In the **User ID** box, enter a valid SAP User ID.
- 5. In the **Password** box, select

The **Enter SAP System Password** window appears.


- 6. In the **Enter Password** box, enter the password that is associated with the specified user ID.
- 7. In the **Confirm Password** box, reenter the password.
- 8. Select OK.
- 9. In the Connection String box:
 - a. Replace the text SAP_SERVER_IP with the IP address of the SAP Server.
 - b. Replace the text SAP_SYSTEM_NUMBER with the SAP System number.
 - c. Replace the text SAP_CLIENT_NUMBER with the SAP Client number.
 - d. Delete all angle brackets.

10. In the ITS URL box:

- a. Replace the text *its_or_integrated_its_server_url* with the ITS Server information. To locate the ITS Server information:
 - i. In SAP, run the following transaction: SE80.
 - Note: If you do not have access to this transaction, contact your SAP BASIS team for assistance.
 - ii. On the toolbar, select **Utilities**, and then select **Settings**.
 - iii. In the upper-right corner of the screen, select **Internet Transaction Server** tab appears.

iv. Select the Internet Transaction Server tab.

The ITS Server information that you must enter in the **ITS URL** box in GE Digital APM is <Log><Path>, where <Log> is the text in the **Log** section and <Path> is the text in the **Path** section.



- b. Delete the angle brackets.
- c. At the end of the URL, enter: webgui/!.

For example, the ITS URL that corresponds with the values in the image above is http://DOCROAECC6.me-ridium.com:8000/sap/bc/gui/sap/its/webgui/!.

11. Select 🖺.

The EAM System record is saved.

12. Select 🖹, and then select **Test Connection**.

The connection parameters are verified, and the **System ID** box is populated with you EAM System ID.

Results

 An EAM system record is created for the EAM system to and from which you want to establish a connection with GE Digital APM. This record should now be used to link Site Reference.

• Linking an EAM system to an EAM System record enables the APM Connect Adapters to create Notifications against that EAM System.

What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Test the Connection Defined in an EAM System Record

Steps

- 1. In the GE Digital APM application, open the <u>EAM System record</u> whose connection information you want to test.
- 2. To access the **Associated Pages** menu, select , and then select **Test Connection**. The connection is tested.

Results

 The connection information that you provided is tested, and a message appears, indicating whether or not the test was successful. In addition, the System ID field is populated automatically with the name of the SAP system, using the format <SYSID>-<CLIENT>, where <SYSID> is the System ID of the SAP system, and <CLIENT> is the Client number.

What's Next?

• Return to the <u>SAP Adapter workflow</u> for the next step in the deployment process.

Configure SAP Task and Confirmation Creation

In order to transfer data between SAP items and GE Digital APM Task records and Event records for Inspection and Calibration, you will need to configure the datasheets used as the default datasheet.

Steps: Configure GE Digital APM to Transfer Data Between SAP Items and Task Records

- 1. Set the following baseline datasheets as the default datasheets on the Inspection and Calibration Task families:
 - Inspection Task for SAP Integration: Defined on the Inspection Task family.
 - Calibration Task for SAP Integration: Defined on the Calibration Task family.

Steps: Configure GE Digital APM to Create Confirmations from Calibration Event Records

- 1. Set the following baseline datasheets as the default datasheets on the Calibration Event families:
 - Calibration, Analog: Defined on the Calibration, Analog family.
 - Calibration, Analyzer Multi-Component: Defined on the Calibration, Analyzer Multi-Component family.
 - Calibration, Analyzer Single Component: Defined on the Calibration, Analyzer Single Component family.
 - Calibration, Discrete: Defined on the Calibration, Discrete family.
 - Calibration, Functional Test: Defined on the Calibration, Functional Test family.
 - Calibration, Weight Scale: Defined on the Calibration, Weight Scale family.

Steps: Configure GE Digital APM to Create Confirmations from Inspection Event Records

- 1. Set the following baseline datasheets as the default datasheets on the Inspection Event families:
 - **Bundle Inspection SAP Integration**: Defined on the Bundle Inspection family.
 - **Bundle Sub-Inspection SAP Integration**: Defined on the Bundle Sub-Inspection family.
 - Visual Inspection SAP Integration: Defined on the Full Inspection family.

- **General Inspection SAP Integration**: Defined on the General Inspection family.
- **Pressure Test Inspection SAP Integration**: Defined on the Pressure Test Inspection family.
- **Pressure Test Sub-Inspection SAP Integration**: Defined on the Pressure Test Sub-Inspection family.

What's Next?

• Return to the workflow for the next step in the deployment process.

Configure the Query Get Tasks for Work Order Generation

The query Get Tasks for Work Order Generation is used to determine which Task records to use to create Orders in SAP.

The query contains the Task query source. For each record that is returned by the query, GE Digital APM will create an Order in SAP. The baseline query is configured to transfer Task records that meet specific criteria. If desired, you can modify the query to further limit the Task records that you want to transfer.

Steps

- 1. Create a query that meets at least the following requirements:
 - Contains the following column:
 - Field: ([Task].[Next Date]-[Task].[Call Horizon])
 - Alias: Expr
 - Criteria (>=(?:d:caption='Last Successful Execution Date': id=LAST_ DATE) AND < Now())
 - Includes at least one field from the source family record.

What's Next?

• Return to the workflow for the next step in the deployment process.

Schedule Work Orders

Steps

1. Access the **APM Connect** page.

The **APM Connect Configuration** page appears.

2. Select **EAM Settings**.

The **EAM Settings** page appears.

3. In the **Scheduling Properties** section, select **Edit Schedule**.

Note: If there is a previously schedule item, a schedule summary will be displayed next to Edit Schedule. If there is no scheduled item, Not scheduled appears next to the Edit Schedule button.

- 4. On the **Edit Schedule** window, select the **Recurrence** check box.
- 5. In the **Time Zone** box, select the appropriate time zone.
- 6. In the **Start** box, select $\stackrel{\square}{=}$ to schedule the start date and time.
 - a. Select one of the following as appropriate:
 - The current date: Select this option to use the current time and date as the starting point.
 - **Clear**: Select this option to clear the current selection.
 - **<Date>**: Select this option to use the selected date as the start date.
 - b. Select (1), and then select the appropriate time.
 - c. Select Close.
- 7. In the **Every** section, in the interval box, enter the numeric value for how often you want the generation to occur.
- 8. In the **Every** section, in the units box, select the interval unit (i.e., minutes, hours, years, etc).
- 9. In the **Every** section, in the begin box, select one of the following:
 - **From start time**: Select this option to start the recurrence from the previously selected start time.
 - After last occurrence: Select this option to begin the generation after the last time the job ran.
- 10. In the **End** box, based on when you want the recurrence to end, use the drop-down to select one of the following:

- Never: If you select this option, then the recurrence will not end.
- After: If you select this option, then you will enter a number of occurrences after which the generation will end.
- **Time & Date**: Select this option to use the calendar to select a time and date when the generation will end.

11. Select **OK**.

The schedule summary appears next to the **Edit Schedule**. Additionally, the scheduled item can be viewed in **Operations Manager** in **Scheduling**.

What's Next?

• Return to the SAP Adapter workflow for the next step in the deployment process.

Create CMMS Classification Type Records

Note: If you using SAP PI, Classification and Characteristic synchronization are not supported.

Steps

- 1. Create a new record , using the **CMMS Classification Type** family.
- 2. In the **CMMS System** list, select the SAP system from which you want to extract characteristics.

The **SAP System** list is populated automatically with the value that appears in the Name field in the EAM System record whose **Default EAM System?** check box is selected.

- 3. In the **Classification Type** list, select the item whose characteristics you want to extract: Equipment or Functional Location.
- 4. To access the **Associated Pages** menu, select **⊙**, and then select **Synchronize Classifications**.
- 5. Select .

What's Next?

• Return to the workflow for the next step in the deployment process.

Identify Classifications to Extract

Steps

- 1. Open the <u>CMMS Classification Type record</u> representing the item whose classifications you want to extract (i.e., Equipment or Functional Location).
- 2. Select the **Details** tab.
- 3. In the Classification for Class Type grid, in the rows representing the Classifications whose characteristics you want to extract, select the Extract From CMMS System boxes.

-or-

If you want to stop extracting all Characteristic for a Classification, clear the **Extract From CMMS System** check box.

4. Select .

The CMMS Classification records are saved.

Results

If you chose to stop extracting a classification:

- The Extract From CMMS System check box is cleared automatically in all CMMS Characteristic records that are linked to the CMMS Classification record.
- When you run the corresponding characteristic extraction adapter, the characteristics whose Extract From CMMS System check boxes were cleared automatically will not be extracted.

What's Next?

Return to the workflow for the next step in the deployment process.

Identify Characteristics to Extract

Steps

- 1. Open the <u>CMMS Classification</u> record representing the classification whose characteristics you want to extract.
 - Open the specific record in the Record Manager.
 - -or-
 - Open the master <u>CMMS Classification Type</u> record to which it is linked, and view the CMMS Classification record in the grid in the datasheet.
- 2. Select \emptyset .
- 3. In the grid on the CMMS Classification datasheet, in the rows representing the Characteristics that you want to extract, select the Extract From CMMS System check boxes.

-or-

If you want to stop extracting a characteristic, clear the **Extract From CMMS System** check box.

4. Select .

The CMMS Characteristic records are saved.

What's Next?

• Return to the workflow for the next step in the deployment process.

Refresh GE Digital APM to Reflect Current SAP Classifications and Characteristics

In some cases, after CMMS Classification and CMMS Characteristic records have been created in the GE Digital APM system, classifications and characteristics may get added or deleted in SAP. If this happens, you can refresh your GE Digital APM system so that it accurately reflects the most current data in SAP.

Steps

- 1. In the Record Manager, open the CMMS Classification Type record whose CMMS Classification records you want to update.
- 2. To access the **Associated Pages** menu, select •, and then select **Synchronize Classifications**.

The Classifications are refreshed.

Results

- The GE Digital APM system checks the SAP system for any new or deleted classifications that are associated with the specified classification type (i.e., Equipment or Functional Location).
- If any classifications have been deleted in SAP, the corresponding CMMS Classification record is deleted.
- Likewise, if any classifications have been added, a new CMMS Classification record is created.
- If any classification descriptions have changed in SAP, the corresponding CMMS Classification record is updated with the new description.

What's Next?


Return to the workflow for the next step in the deployment process.

About Classification Hierarchies


In SAP, for any given class, multiple characteristics can be inherited from another class. For example, consider the following SAP classes:

- EQ_CLASS_0001
- Fasteners
- Bolts
- Hexagonal Bolt


As shown in the following image, EQ_CLASS_0001 has four unique characteristics:




As shown in the following image, Fasteners also has four sets of unique characteristics:




Bolts, however, inherits all of the characteristics from EQ_CLASS_0001 and FASTENERS. In addition, Bolts has two unique characteristics of its own: HEAD_SHAPE and BOLT_TYPE:



Finally, Hexagonal Bolt also inherits all of the characteristics from EQ_CLASS_0001, FASTENERS, and BOLTS. It also has one unique characteristic of its own: TOLERANCE:



Using these SAP classes, in the GE Digital APM system, if you were to select the **Extract From CMMS System** check box for the HEXAGONALBOLT class, after selecting the **Synchronize Characteristics** link while viewing the HEXAGONALBOLT CMMS Classification record, the following CMMS Characteristic records would be created automatically:



As you can see from the Classification column, some of the characteristics are inherited from other classes:

Specifically, you can see that:

- The following characteristics are inherited from the class EQ_CLASS_0001:
 - COLOR
 - LOCAL_REG_NUM
 - OPH
 - SAP_EHS_1017_003_TEST_TYPE
- The following characteristics are inherited from the class FASTENERS:
 - FASTENER_DIAMETER
 - LENGTH
 - NUMBEROFTHREADS
 - THREAD_TYPE
- The following characteristics are inherited from the class BOLTS:
 - HEAD_SHAPE
 - BOLT_TYPE
- The characteristic TOLERANCE is assigned directly to the class HEXAGONALBOLT (no highlighting).

If you selected the **Extract From CMMS System** check boxes for *all* of these characteristics, if you were to run the Equipment Characteristics Extraction Interface without filters, *all* of these characteristics would be extracted.

If, however, you were to filter the report to extract only characteristics belonging to the HEXAGONALBOLT class, only characteristics that are assigned directly at the HEXAGONALBOLT level would be extracted. In other words, because only TOLERANCE is assigned directly to HEXAGONALBOLT, only the TOLERANCE characteristic would be extracted.

About Extracting Characteristics

Note: If you using SAP PI, Classification and Characteristic synchronization are not supported.

When you create CMMS Classification Type records using the CMMS System list, you must select the SAP system from which you want to extract characteristics belonging to that classification type. The **CMMS System** list displays the values in the Name field in all existing EAM System records. When you save the CMMS Classification Type record, the GE Digital APM system finds the EAM System record whose Name field contains the selected value, and the value in the System ID field in that EAM System record is copied to the CMMS System ID field in the CMMS Classification Type record.

Then, when you create CMMS Classification or CMMS Characteristic records that are associated with that CMMS Classification Type record, the value in the CMMS System ID field in the CMMS Classification Type record is copied automatically to the CMMS System ID field in those records.

CMMS Characteristic records are created automatically and linked to the CMMS Classification record. Each CMMS Characteristic record is created from a characteristic that currently exists in the specified SAP system (using the CMMS System field in the CMMS Classification record). The CMMS Characteristic records are displayed in a grid on the CMMS Classification datasheet, as shown in the following image:

Note: The System ID field is available on the baseline EAM System datasheet, but the CMMS System ID field is not available on the baseline CMMS Classification Type, CMMS Classification, or CMMS Characteristic datasheets.

When you run the Equipment Characteristic Extraction Interface or the Functional Location Characteristic Extraction Interface, the GE Digital APM code needs to determine which specific characteristics to extract from that system. To do so, it evaluates the CMMS Characteristic records that exist in your GE Digital APM database. If it finds any CMMS Characteristic records whose CMMS System ID field value identifies the SAP system from which you are running the interface, it will extract only those characteristics from that SAP system (assuming that the **Extract from CMMS System** check box is selected in the CMMS Characteristic record).

About Site Filtering in the EAM Adapters

<u>MPORTANT</u>: Site Reference records must preexist in your GE Digital APM system, before you can use the EAM Adapters to populate the Site Reference Key. Additionally, the site entered into the context file must match the exact value in the corresponding Site Reference record.

<u>MPORTANT</u>: The user who is running the EAM Adapters jobs must be assigned, in GE Digital APM, to the site to which the records being loaded will be assigned. Additionally, the credentials for that user must be entered into the context file. If the user is not a member of the appropriate site, then the data load will fail, and an error message will appear.

The EAM Adapters are used to populate the Site Reference on Equipment, Functional Location, and Work History records in GE Digital APM. The adapters populate the MI_SITE_KEY system field with the ENTY_KEY system field associated with the Site Reference value to be populated. On asset records, the Site Reference is stored in the MI_SITE_KEY field, a system field in GE Digital APM. The EAM Adapters use the Site Name (MI_SITE_NAME) to translate the value to the corresponding Site Reference Key and populate the MI_SITE_KEY field; therefore, you do not need to know the key to be able to populate the site reference. This functionality is important because this value can change from one database to another.

When records are loaded using the Equipment, Function Location, and Work History Adapters, the system will assign the Site Reference Key (MI_SITE_KEY) to the assets using the value designated in the context file context file. The following parameters are used to designate the Site Reference Key value:

- SITE_REFERENCE_EQUIP: Used to populate the Site Reference Key on Equipment records being loaded into GE Digital APM. The Site Reference Key determines the Site to which the Equipment record(s) will be assigned.
- SITE_REFERENCE_FLOC: Used to populate the Site Reference Key on Functional Location records loaded into GE Digital APM. The Site Reference Key determines Site to which the Functional Location record(s) will be assigned.

Note: The values entered into these parameters should match, because Equipment records are linked to Functional Location records. Therefore, they should have the same site.

These parameters accept three types of values to determine the site reference value.

- a. **Site Name:** You can enter the site name directly as defined on the preexisting Site Reference record (i.e., Site 100).
- b. **Column Name:** You can enter a column value between two pound symbols (#) to set the site reference. The following columns can be used:

- · SAP columns:
 - MI_EQUIP000_SAP_SYSTEM_C
 - MI_EQUIP000_MAINT_PLANT_C
 - MI_FNCLOC00_MAINT_PLNT_C
 - MI_FNCLOC00_SAP_SYSTEM_C
- Maximo columns:
 - MI_FNCLOC00_SITE_C
 - MI_EQUIP000_SITE_C

For example, if you wanted to use your SAP maintenance plant field as your GE Digital APM site reference, you would enter #MI_EQUIP000_MAINT_PLANT_C#.

c. **Null:** You can leave the value as null. The record will be a global record if a Site Reference value is not mapped in between the tags.

If the assets being loaded into GE Digital APM are global records, meaning they will not be filtered according to site, then the Site Reference parameters can be left blank. When records are loaded with a null values in their Site Reference parameters, those created asset records will be designated as Global.

After the adapters are run, records designated to be transferred into GE Digital APM will be assigned to the site defined in the Site Reference parameters.

In addition to Equipment and Functional Location records loaded by the EAM adapters, Work History records and shell records are impacted by site reference functionality as detailed in the following table.

Action	Result
If the Work History Adapter is run after the Equipment or Functional Location Adapter	The Work History records will inherit the Site Reference Key of their parent Functional Loca- tion or Equipment records.
If the Work History Adapter is run before the Equipment or Functional Location Adapter	The Site Reference Key will inherited from the shell record that will be created for Equipment and Functional Location.
If a shell record is created while loading data	The Site Reference Key will be the value set in the context parameters.

Note: If you are using multiple SAP Systems, you must set up a context file for each system, and then designate the appropriate site(s) for each EAM Systems.

Import Notification Management File

Note: This step is needed only if the notification management file was not imported when you <u>ran the APM Connect installer</u>.

<u>MPORTANT</u>: This step is required only for on-premises deployment of the SAP Adapters. If you are not completing an on-premesis deployment, you can skip this procedure, and proceed to the next step in the <u>SAP Adapter First-Time Deployment Workflow</u>.

Steps

- 1. Access the APM Connect installation package, and then copy the file *SAP_Noti- ficationManagement.jar.*
- 2. Navigate to <root:>\APMConnect\Utilities\runtime\deploy.
- 3. If you already have an existing SAP_NotificationManagement.jar file, delete it before copying the new file into the directory.
- 4. Paste the copied file *SAP_NotificationManagement.jar* in the directory. The Notification Management File is imported.

What's Next?

• Return to the <u>SAP Adapter First-Time Deployment Workflow</u>.

Deploy the SAP PI Adapters

This topic provides a list of all procedures related to the PI Specific setup, as well as links to the related concept and reference topics.

Deploy the SAP PI Adapters for the First Time

The following table outlines the steps that you must complete to deploy and configure this module for the first time. These instructions assume that you have completed the steps for deploying the basic GE Digital APM system architecture.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.

Note: This GE Digital APM module is not available in the APM Now environment.

Step	Task	Notes
1	Deploy the SAP Adapters.	This step is required.
2	On the APM Connect Server, import the notification management . jar file.	This step is required only if you are completing an on-premises deployment.
3	On your SAP PI sever, <u>import the design</u> <u>object.</u>	This step is required.
4	On your SAP PI sever, import the configuration object.	This step is required.
5	On your SAP PI sever, modify the baseline communication channels.	This step is required.
6	On your SAP PI server, <u>activate the RFCReceiverToECC object</u> .	This step is required.
7	In SAP, <u>define the command name</u> .	This step is required.
8	In SAP, <u>install the SAPCAR file</u> .	This step is required.
9	In SAP, <u>create SAP PI directory structure</u> .	This step is required.

Upgrade the SAP PI Adapters to EAM SAP PI V2.0.0

The following tables outlines the steps that you must complete to upgrade this module to EAM SAP PI V2.0.0. These instructions assume that you have completed the steps for upgrading the basic GE Digital APM system architecture.

These tasks may be completed by multiple people in your organization. We recommend, however, that the tasks be completed in the order in which they are listed.

To Upgrade from EAM SAP PI V1.0.0 through V1.2.0

Step	Task	Notes
1	Upgrade the APM Connect Base.	This step is required.
2	Complete the steps to <u>deploy the SAP adapters</u> <u>for the first time</u> .	This step is required.
3	Complete the steps to <u>deploy the</u> <u>SAP PI adapters for the first time</u> .	This step is required.

Import Notification Management File

Steps

1. On your APM Connect Server, in the <root:>\APMConnect\Utilities\runtime\etc directory create a context file named: SAP_PI_NotificationManagement.cfg.

<u>MIMPORTANT</u>: The file name must match *SAP_PI_NotificationManagement.cfg* exactly.

- 2. Paste the following into the context file:
 - context = Default
 - CONFIG_FILE_PATH = <The directory path to your <u>SAP PI Context File</u>. >
 - 1) Note: The path must use forward slashes (/).
- 3. Save the file.
- 4. Access the APM Connect installation package, and then copy the file *SAP_PI_Noti-ficationManagement.jar*.
- 5. Navigate to <root:>\APMConnect\Utilities\runtime\deploy.
- 6. Paste the copied file *SAP_PI_NotificationManagement.jar* in the directory. The Notification Management File is imported.

What's Next?

Return to the <u>SAP PI Adapter workflow</u> for the next step in the deployment process.

Import the Design Objects

Steps

- 1. Access the APM Connect installation package.
- 2. Navigate to the folder that corresponds to the version of SAP PI that you are using. For example if you are using SAP PI version 7.3, navigate to *SAP PI 730*.
- 3. Copy the following files:
 - APMConnect_DesignObjects_BaseV4_3.tpz
 - APMConnect_DesignObjects_SupportPackV4_3.tpz
- 4. On the SAP PI Server, paste the copied files to the folder \(\lambda s r\sap\\\ SID\\ SYS\\ global\\ xi\\ repository_ server\\ import\,\ where \(\lambda SID\) is the system ID of the SAP PI Server.

-or-

Paste the copied files anywhere on your local machine.

5. If you are using a version prior to SAP PI 7.3, select **Integration Repository**.

-or-

If you are using SAP PI 7.3 or above, select **Enterprise Services Builder**.

A login screen appears.

6. Log in as an administrator.

Depending on the SAP PI Server version you are using, the **Design: Integration Builder** window or the **Enterprise Services Builder** window appears.

7. On the **Tools** menu, select **Import design objects**.

The **Choose Import Source** window appears.

- 8. Select **Client** if the files copied in Step 3 were pasted onto your local machine, or select **Server** if the files copied in Step 3 were pasted in \us-r\sap\<SID>\SYS\global\xi\repository_server\import
- 9. Select the **Design Objects** folder.
- Select the file APMConnect_DesignObjects_BaseV4_3.tpz, and then select OK.
 A confirmation dialog box appears.
- 11. Select **Import**.

The file is imported.

12. Select the file APMConnect_DesignObjects_SupportPackV4_3.tpz, and then select

OK.


A confirmation dialog box appears.

13. Select **Import**.

The file is imported.

14. Select Close.

The design objects are imported and appear in the **Objects** section.



What's Next?

Return to the <u>SAP PI Adapter workflow</u> for the next step in the deployment process.

Import the Configuration Object

Steps

- 1. Access the APM Connect installation package.
- 2. Navigate to the folder that corresponds to the version of SAP PI that you are using. For example if you are using SAP PI version 7.3, navigate to *SAP PI 730*.
- 3. Copy the file APMConnect_ConfigurationObjectsV4_3.tpz.
- 4. On the SAP PI Server, paste the copied file into the folder *\us-r\sap\<SID>\SYS\global\xi\\directory_server\import*, where *<SID>* is the system ID of the SAP PI Server.

-or-

Paste the copied file anywhere on your local machine.

5. In a web browser, navigate to <a href="http://<SAP PI Server">http://<SAP PI Server is the name of the SAP PI Server and and and and is the port number of the specified SAP PI Server.

The **SAP Exchange Infrastructure** window appears.

6. Select Integration Directory.

A login screen appears, prompting you to log in to the **Configuration: Integration Builder**.

7. Log in as an administrator.

The **Configuration: Integration Builder** window appears.

8. On the **Tools** menu, select **Import configuration objects**.

The **Choose Import Source** window appears.

- 9. Select **Client** if the file copied in step three was pasted onto your local machine, or select **Server** if the file copied in step one was pasted to *\us-r\sap\<SID>\SYS\global\xi\directory_server\import*.
- 10. Select the **Configuration Objects** folder.
- 11. Select the file *APMConnect_ConfigurationObjectsV4_3.tpz*, and then select **OK**. A confirmation dialog box appears.
- 12. Select **Import**.

The file is imported, and a confirmation message appears.

13. Select Close.

The configuration object is imported, and the objects appear in the **Configuration Integration Builder**.

What's Next?

• Modify the baseline communication channels. To do so, you will need to remain logged in to the Configuration: Integration Builder.

Modify the Baseline Communication Channels

Note: If the FILE_MOVE_USE_PI parameter is set to false in the context file, you can skip this procedure.

The SAP PI adapters have four baseline communication channels: FileReceiver_APMConnect, SOAPSender_APMConnect, FileSender_SAP_ECC, and RFCReceiver_SAP_ECC. You will need to modify the following baseline communication channels:

- FileReceiver_APMConnect
- FileSender_Meridium_ECC

Steps

1. In a web browser, navigate to <a href="http://<SAP PI Server">http://<SAP PI Server:port number
server
is the name of the SAP PI Server
and port number
is the port number of the specified SAP PI Server.

The **SAP Exchange Infrastructure** window appears.

2. Select **Integration Directory**.

A login screen appears, prompting you to log in to the **Configuration: Integration Builder**.

3. Log in as an administrator.

The **Configuration: Integration Builder** window appears.

- 4. In the Configuration: Integration Builder, in the Scenarios section, expand the APMConnect_IDConfigurationsV4_3 row.
- 5. Expand the **Service Without Party** row.
- 6. Expand the **Business Service** row.
- 7. Expand the **Meridium_APMConnect** row.
- 8. Expand the **Communication Channel** row.

The row expands, and the following APM Connect Communication Channels appear:

- FileReceiver_APMConnect
- FileSender_Meridium_ECC
- Select FileReceiver_APMConnect.

The **Display Communication Channel** screen appears.

10. Select 🧐

11. In the **File Access Parameters** section, in the **Target Directory** box, enter the target directory file path.

<u>MPORTANT:</u> This path must match exactly the IR_TALEND_OUTPUT <u>parameter in the context file</u>.

- 12. In File Name Scheme, enter *.*.
- 13. Select 📙.
- 14. Select the FileSender_Meridium_ECC.

The **Display Communication Channel** screen appears.

- 15. Select 🧐.
- 16. In the **File Access Parameters** section, in **Source Directory** box, enter the endpoint of the share between your SAP server and your SAP PI server exactly as it is in the <u>PLSAP_INPUT</u> parameter in the context file.
- 17. In **Processing Parameters** section, the **Poll Interval** box, enter the recommended value of 100.
- 18. In the **Processing Mode** box, select **Delete**.
- 19. In the File Name Scheme, enter *.*.
- 20. In **Advanced** section, complete the following steps:
 - a. In the **Adapter-Specific Message Attributes** section, select the following options:
 - Set Adapter-Specific Message Attributes
 - File Name
 - File Type
 - b. In the **Adapter Status** section, in the **Status** box, select **Active**.
 - c. Select the **Advanced Mode** check box.
 - d. In the **Additional Parameters** section, in the **Msecs to Wait Before Modification Check** box, enter the recommended value of 1000 or more.
- 21. Select 📙.

The communication channels are modified.

What's Next?

Return to the <u>SAP PI Adapter workflow</u> for the next step in the deployment process.

Activate the RFCReceiver_SAP Object

Steps

- 1. In the Configuration: Integration Builder, select the **Change Lists** tab.
- 2. In the Change Lists section, select | Meridium_SAP | RFCReceiver_SAP.

Note: The Error Loading Adapter Metadata dialog box may appear. If it appears, select Close.

The communication channel details appear on the right side of the screen.

- 3. On the right side of the screen, select 🦅.
- 4. In the **Parameters** section, in the **Adapter Type** row, select $\Box \vdash$.

The Choose Adapter Metadata window appears.

5. Select the latest RFC Adapter from the list, and then select **Apply**.

The communication channel details return to focus.

- 6. In the **Properties** section, confirm or enter values for the following parameters:
 - RFC Server Type
 - Note: This parameter must be set to SAP System.
 - · Application Server
 - System Number
 - Authentication Mode
 - Note: This parameter must be set to Use Logon Data for SAP System.
 - Logon User
 - Logon Password
 - Logon Language
 - Logon Client
- 7. Select 📙.
- 8. In the **Change Lists** section, right-click on **PI <version number> Import**, and then select **Activate**.

A confirmation message appears.

9. Select **Activate**.

The object is activated.

What's Next?

• Return to the <u>SAP PI Adapter workflow</u> for the next step in the deployment process.

Define the Command Name in SAP

Note: If you are not using a compression method during the extraction, then you can skip this procedure.

If you are using a compression option in the context file, you need to define the command name for the compression type you are using. There are two types of compressions for APM Connect SAPCAR and ZIP. You can only use one type of compression.

lt is recommended to use SAPCAR as your compression type.

Steps

1. In SAP, run the transaction code *SM69*.

The **External Operation System Commands** screen appears.

2. Select 1.

The **Create an External Command** screen appears.

- 3. In the **Command** section, in the **Command Name** box, enter one of the following the command names:
 - **ZSAPCAR**: if you are using SAPCAR for compression.
 - -or-
 - **ZZIP**: if you are using ZIP for compression.
- 4. In the **Definition** section, in the **Operating system command** box, enter one of the following systems commands:
 - *SAPCAR -cvf*: if you are using SAPCAR for compression.
 - -or-
 - *ZIP -9 -j*: if you are using ZIP for compression.
- 5. Select **Save**.

The Command Name is defined.

What's Next?

Return to the <u>SAP PI Adapter workflow</u> for the next step in the deployment process.

Install the SAPCAR File on the APM Connect Server

Note: If you are not using SAPCAR to compress files, then skip this procedure and proceed to the next procedure in the installation workflow.

Steps

- 1. On the SAP Server, copy the SAPCAR.exe file.
- 2. Access the APM Connect Server.
- 3. In the windows system32 directory, paste the SAPCAR.exe file, as shown in the following image:



The SAPCAR file is installed.

What's Next?

Return to the <u>SAP PI Adapter workflow</u> for the next step in the deployment process.

Create SAP PI Directory Structure

You will need to set up a directory structure on your SAP server to facilitate transfers from SAP PI to APM Connect. The structure depends on the FILE_MOVE_USE_PI parameter and the COMPRESS_TYPE parameter usage in the context file. Additionally, the folder structure depends on whether you are using FTP to transfer files.

Steps

• On your SAP server, create one directory and subdirectory according to the following grid:

If FILE_MOVE_USE_PI is	and COMPRESS_ TYPE is	create the following directory structure:	
false	NONE	<root:>/<new directory<br="">Name></new></root:>	
false	ZIP or SAPCAR	<root:><new directory<br="">Name>/Compress</new></root:>	
true	NONE	<root:>/<new directory<br="">Name></new></root:>	
true	ZIP or SAPCAR	<root:>/<new directory<br="">Name>/Compress</new></root:>	
If you are running the adapters in FTP Mode			
true	NONE	<root:>/<new directory<br="">Name>/FTP</new></root:>	
true	SAPCAR or ZIP	<root:>/<new directory<br="">Name>/FTP/Compress</new></root:>	

Note: Each directory needs to be in a shared directory that APM Connect can access, and should be the base path value in PLSAP_INPUT parameter. Additionally, once the job is run, the compress directory will be programmatically added to the value PLSAP_INPUT in the context file.

The directories are created, and the SAP PI server and APM Connect server can extract files from the SAP sever.

What's Next?

Return to the <u>SAP PI Adapter workflow</u> for the next step in the deployment process.

Overview of APM Connect

GE Digital APM Connect is an integration framework designed to connect users to the valuable data that exists in data stores, systems, and applications throughout the enterprise.

The framework delivers data transformation engines to convert data to their appropriate forms, a modular integration engine to handle complex routing scenarios, and other engineered components to create a unified integration solution.

Built on the APM Connect framework are numerous adapters that can meet many integration needs by either pulling data from or pushing it into other sources in the data ecosystem. APM Connect offers new EAM connection adapters as replacement technology for some existing EAM interfaces, and will continue to add additional adapters and capabilities in subsequent releases.

Adapters

The following adapters are currently available through the most recent release of APM Connect:

- · ASI for SAP.ASI for SAP
- EAM Adapters
 - SAP Adapters
 - Equipment Adapter
 - Functional Location Adapter
 - Work History Adapter
 - Notification Management Adapter
 - Technical Characteristics Adapter
 - Work Management Adapter
 - SAP PI Adapters
 - Maximo Adapters
 - Equipment
 - Functional Location Adapters
 - Service Request Adapter
 - Work Order Adapter
- Data Loaders

Overview of the EAM Adapters

The APM Connect EAM Adapters transfer data from your existing Enterprise Asset Management (EAM) system into GE Digital APM using the APM Connect Administration Center.

APM Connect is built upon a fundamental premise that you are using an external EAM system to store information about your equipment, the locations in which the equipment exists, failures of the equipment and locations, and work that has been performed on the equipment and locations.

GE Digital APM provides tools that let you analyze and process this data. Before you can analyze the data in the GE Digital APM, however, you must transfer it from your EAM system into your GE Digital APM system. After the data exists in GE Digital APM, it can be analyzed to determine the state of your equipment and locations, and the reliability, trends, potential risks, and probability of failures associated with them.

EAM Adapter Workflow

This workflow provides the basic, high-level steps for using this module. The steps and links in this workflow do not necessarily reference every possible procedure. For more procedures, see the links in the Related Information section.

- 1. Identity the records you want to transfer from your EAM system(s) to GE Digital APM.
- 2. Apply filter parameters in the context file as necessary.
- 3. Schedule a job(s) to run in the APM Connect Administration Center.

-or-

Execute a run-now job.

4. Check that the record was transferred into GE Digital APM.

Note: This step is not necessary to complete the data transfer. However, it is a check to ensure that the transfer was executed successfully.

5. If the transfer was not successful, view the execution log for errors.

Overview of the SAP Adapters

Data extractions, also referred to as Jobs, are orchestrated through the different adapters. Depending on the type of data (i.e., Equipment, Functional Location, Work History) you want to extract, there is a corresponding job. SAP extractions are facilitated by the <u>APM Connect Administration Center</u> and a corresponding context file. The context file contains <u>filter parameters</u> that are applied to each extraction adapter Job. The filter parameters define the scope of the data extraction.

More Details

The following SAP adapters and SAP PI are available for data extractions:

- <u>Equipment Adapter</u>: Extracts records that are used to store information about physical pieces of equipment, such as pumps, motors, and compressors.
- <u>Functional Location Adapter</u>: Extracts records that are used to store information about locations in your organization, including but not limited to the locations at which the physical pieces of equipment are installed.
- Work History Adapter: Extracts records that are used to store data about work that was performed against your locations and equipment, as well as failures that occurred for those locations and equipment. Additionally, it allows you to transfer Notifications and Orders from SAP to GE Digital APM.
- <u>Notification Management Adapter</u>: Allows you to transfer Recommendation records from GE Digital APM to SAP in the form of Notifications.
- <u>Technical Characteristics Adapter</u>: Allows you to transfer Functional Location characteristics and Equipment characteristics from SAP to GE Digital APM.
- Work Management Adapter: Allows you to manage scheduled work in SAP and GE Digital APM.

Note: The SAP PI adapters do not support Work Management harmonization.

Employ the Notification Management Adapter

This topic provides a list of all procedures related to employing the Notification Management Adapter, as well as links to the related concept and reference topics.

Create an SAP Notification from a Recommendation Record

Before you Begin

- Ensure **Create Work Request** exists in the family of the necessary **Recommendation** record and that it also exists on the datasheet.
- Ensure Notification Type exists in the family of the necessary Recommendation
 record and on the datasheet as an enabled field. In the baseline database, Notification Type is already available in all baseline Recommendation families that
 exist for the purpose of using the SAP Adapters. It is not, however, included on
 any baseline datasheets or configured as an enabled field. The following instructions assume, therefore, that an administrative user has enabled the field and
 added it to the datasheet.

Steps

- 1. Create a new General Recommendation record or open an existing Recommendation record.
- 2. Link the Recommendation record to an Equipment or Functional Location record that represents an SAP Equipment or Functional Location.
 - Note: If you select an Equipment or Functional Location record that does not exist in SAP, after you save the record, a Notification will be created in SAP, but its Equipment or Functional Location field will be empty.
- 3. Select the **Create Work Request?** box.
- 4. In the **Notification Type** cell, specify the type of Notification that you want to create.
 - Note: If you do not specify the type of Notification that you want to create, the GE Digital APM system will create M1 Notifications by default.
- 5. Select 🖺.

The record is saved.

Results

After you create a new **Recommendation** record, the adapter does the following:

- Creates a Notification in SAP.
- Populates the Work Request Reference cell with the ID of the corresponding SAP Notification.

- Populates the **Work Request Equipment** cell with the value in the Equipment field in the SAP Notification.
- Populates the **Work Request Functional Location** cell with the value in the Functional Location field in the SAP Notification.

Note: If a Notification could not be created for any reason, a message appears, indicating the problem. In addition, you will be unable to save the **Recommendation** record until you clear the **Create Work Request?** box.

Update an SAP Notification from a Recommendation Record

Once an SAP Notification is created from a **Recommendation** record, the **Recommendation** record and the SAP Notification can be updated. This topic describes how to update an existing SAP Notification by updating the corresponding **Recommendation** record in the GE Digital APM.

Note: Only Recommendation records with the Create Work Request? box can be updated.

Before You Begin

• Create an SAP Notification from a Recommendation record.

Steps

- 1. Open a Recommendation record that you want to update.
- 2. Select the field you want to update.
- 3. Enter the updated information.

For example, if you would like to update the description of an existing Recommendation record, select the **Description** box, and edit the text accordingly.

4. Select ...

The Recommendation record is updated in the GE Digital APM, and the Notification is updated in your SAP system.

Employ the Work Management Adapter

This topic provides a list of all procedures related to employing the Work Management Adapter, as well as links to the related concept and reference topics.

Work Management Workflow

This workflow provides the basic, high-level steps for using this module. The steps and links in this workflow do not necessarily reference every possible procedure. For more procedures, see the links in the Related Information section.

Manage Scheduled Work in SAP Workflow

- 1. In SAP, on a Maintenance Plan, enter a value or combination of values that has been configured to trigger the creation of a GE Digital APM Task record.
- 2. In the Administration Center, run the Work Management Job.

A Task record(s) is automatically created in GE Digital APM.

Note: If the Task records are created from Maintenance Plans that are associated with Equipment or Functional Locations, corresponding Equipment and Functional Location records will be created automatically and linked to the new Task records. These Equipment and Functional Location records will contain values only in key fields as defined in the mappings (e.g., Equipment ID, Functional Location Internal ID, CMMS System). You will need to run the Equipment Extraction and Functional Location Adapters to populate the remaining fields.

- 3. In GE Digital APM, create an Inspection record or Calibration Event record.
- 4. Link the new record to the Inspection Task or Calibration Task record that you created by running the Work Management Job.
- 5. Close the Work Order.
- 6. In GE Digital APM, if needed, update the Confirmation record.

-or-

In SAP, validate the Confirmation.

Manage Scheduled Work in GE Digital APM Workflow

- 1. In GE Digital APM, create a Task record.
- 2. creation.
- 3. In GE Digital APM, create an Inspection record or Calibration Event record.
- 4. Link the new record to the Inspection Task or Calibration Task record that you created.
- 5. Close the Work Order.

6. If needed, in GE Digital APM, <u>update the Confirmation record.</u>

-or-

In SAP, validate the Confirmation.

Create a Task Record

Note: To complete the following steps, use the Task datasheet that is configured for use with the SAP Adapter. For Inspection Task records, use the Inspection Task for SAP Integration Adapter datasheet. For Calibration Task records, use the Calibration Task for SAP Integration datasheet. These datasheets are defined on the corresponding Task family in the baseline database, but they are not set as the default datasheets.

Note: To create the Task record, make sure to use the Task Builder and not the Record Manager. Otherwise, the Task record will not be linked to the Equipment or Functional Location record, and the Work Management Adapter will not work as expected.

Before You Begin

You can create an SAP Order from a Task record only if all of the following conditions are true:

- The Work Order Number field in the Task record is empty.
- The Task record was not created automatically from SAP data.

Steps

- 1. In GE Digital APM, create an Inspection Task or Calibration Task record.
- 2. In the Task record, in the Task List cell, select
 - The **Locate Task List** window appears.
- 3. In the **Search Criteria** section, enter the desired search criteria.
 - Note: If you accept the default criteria, the search results will return *all* Task Lists.
- 4. Select Search.
 - The Task Lists that meet the search criteria appear in the **Search Results** section.
- 5. In the **Search Results** section, select the row containing the desired Task List, and then select **OK**.
 - The Task List field on the Task record is updated with the Task List group number.
- 6. In the Last Date cell, enter or select the last date on which the task was executed.
- 7. In the **Desired Interval** cell, enter the desired interval.

The value in the Next Date field is updated automatically based on the Last Date and the Desired Interval.

8. In the **Call Horizon** box, enter the desired call horizon.

(i) **Hint:** For details about call horizons, see the SAP Help, which is located at http://help.sap.com/.

9. Save the Task record.

Create an Event Record or Inspection Record

Note: The following instructions work correctly only if the SAP Interfaces - Work Management license is active.

Note: When creating the Inspection record or Calibration Event record, be sure to use the process defined by the module rather than the Record Manager. Otherwise, the record will not be linked to the Equipment or Functional Location record, and the Work Management Adapter will not work as expected.

Steps

- 1. Using the process defined by the module, create an Inspection record or Calibration Event record. As you proceed through the Event Builder, on the **Task(s) Selection** screen, select the appropriate Task record(s). This could be:
 - A Task record that was generated from SAP.
 -or-
 - A Task record that you created manually to generate an SAP Order automatically.
- 2. If the Event record is an Inspection record, select values in the Commencement Date and Completion Date fields. Make sure that the Completion Date is a date after the Commencement Date.

Close a Work Order

Steps

- 1. Access the event record linked to the task record you want to mark as complete.
- 2. In the **Tasks Addressed** box, select the task ID for the record you transferred from SAP by running the Work Management Adapter.
- 3. In the **Actual Work Time** box, enter a value for the number of hours worked to complete the task.
- 4. In the Event record, in the **Actual Work Time** box, enter the time (in hours) that you spent completing the work.
- 5. If the Event record is a Calibration Event record, select the **Calibration Close** box.

-or-

If the Event record is an Inspection record, select the Inspection **Task Complete** box.

6. Save the Event record.

The event record is saved, and the work order is closed. A confirmation record is created in GE Digital APM and in SAP.

<u>MPORTANT</u>: When transferring Work Management data from SAP into GE Digital APM, the **Desired Interval** field is populated with a null value. After the Plan is called, the **Next Date** field will populate with the next execution date based on calculations made by SAP.

Results

After saving the record, the following occurs:

 A Confirmation record is created and linked to the Event record and the Task records to which the Event record is linked. The number of Confirmation records created equals the number of Task records that are linked to the Event record. In addition, a Confirmation is created in SAP for each Confirmation record that is created in GE Digital APM.

If only one Confirmation record is created, the Actual Work Time in the Confirmation record matches the Actual Work Time in the Event record. If more than one Confirmation record is created, the Actual Work Time in the Event record is split evenly between those Confirmation records.

For example, if an Event record is linked to two Task records, two Confirmation records will be created. If the Actual Work Time in the Event record is 14, the Actual Work Time in each Confirmation record will be 7 (14/2).

- The Work Order Number fields in the Task records that are linked to the Event record are cleared.
- The Confirmation that is created in SAP is marked as final.

Update an SAP Confirmation by Updating the Actual Work Time in a Confirmation Record

Steps

- 1. Open the Confirmation record that you want to modify.
- 2. Modify the **Actual Work Time** value, and then save the record.

Results

- The associated SAP Confirmation is canceled in SAP, and a new SAP Confirmation is created. The counter in the new SAP Confirmation is one digit higher than the counter in the canceled SAP Confirmation.
- The Actual Work Time field in the Inspection record or Calibration Event record to which this Confirmation record is linked is updated automatically to reflect the updated value in the Confirmation record. If this is the only Confirmation record that is linked to the Inspection or Calibration Event record, the Actual Work Time in the Inspection or Calibration Event record will match the value in the Confirmation record.
- If more than one Confirmation record is linked to the Inspection or Calibration Event record, however, the Actual Work Time in the Event record is updated to be the sum of the values in the Actual Work Time fields in all of those Confirmation records.

For example, if an Event record is linked to this Confirmation record and two other Confirmation records, and the final values in the Actual Work Time fields of those Confirmation records are 7, 6, and 5, the Event record will contain the value 18 (7 + 6 + 5) in the Actual Work Time field.


Validate SAP Confirmations Against GE Digital APM Confirmation Records

After you have created SAP Confirmations from GE Digital APM Confirmation records, you can validate the information in the SAP Confirmations against the information in the GE Digital APM Confirmation records.

Steps

1. In SAP, run the following transaction: IW43.

The window appears.



2. If you know the Confirmation number of the Confirmation that you want to validate, in the **Confirmation** text box, enter the Confirmation number, which appears in the **Confirmation Number** cell on the Confirmation datasheet in the GE Digital APM system.

-or-

If you know the Order number associated with the Confirmations that you want to validate, in the **Order** text box, enter the Order number, which appears in the

Work Order Number cell on the Confirmation datasheet in the GE Digital APM system.

3. Select 💞.

If only one Confirmation meets the specified criteria, the **Display PM Order Confirmation: Actual Data** screen appears, displaying the values that appear on the Confirmation datasheet in the GE Digital APM system.

-or-

If more than one Confirmation meets the specified criteria, the **Display PM Order Confirmation: Confirmation Overview** screen appears, displaying a list of the Confirmations that meet the specified criteria. In the list, you can see the values that appear on the Confirmation datasheet in the GE Digital APM system.

Manage Filter Parameters in the Context File

This topic provides a list of all procedures related to applying filter parameters in the context file, as well as links to the related concept and reference topics.

Apply Common Filter Parameters

There are common filter parameters in the context file that operate in the same manner, no matter which adapter you are using to extract data. This topic describes how to configure the common filter parameters.

Before You Begin

Before you can transfer data with an adapter, you must complete the following:

• Import an Adapter Job to which filters can be applied.

Steps

1. On the machine on which you installed APM Connect, navigate to <root:\\>APMConnect\Config.

Note: If you are using multiple SAP systems, there will be multiple context files to which you will need to apply the filter parameters.

2. Right-click on the *context file* file, and then select **Edit**.

The context file opens.

3. As necessary, configure the following common parameters in the table:

Common Filter Parameters	Description	Value Requirements	Required, Optional
CHANGE_DATE_ START	Date value that limits the data extracted to records changed on or after the specified date.	Dates must be entered in the following format: YYYYMMDD.	Required
CHANGE_DATE_ END	Date value that limits the data extracted to records changed on or before the specified date.	Dates must be entered in the following format: YYYYMMDD.	Required
CREATE_DATE_ START	Date value that will limits the data extracted to records created on or after the specified date.	Dates must be entered in the following format: YYYYMMDD.	Optional
CREATE_DATE_ END	Date value that limits the data extracted to records created on or before the specified date.	Dates must be entered in the following format: YYYYMMDD.	Optional
LANGUAGE	The SAP code that represents the language.	Must be a single character.	Required
MAINT_PLANT	ID(s) of the Main- tenance Plant whose data you want to extract.	Plant values cannot exceed four characters.	Required
SITE_ID	Name of the plant site whose data you want to extract.	N/A	Required

4. Save the changes to the context file.

The common filter parameters are configured and applied to all Adapter Jobs in the APM Connect Administration Center.

Results

• When Jobs are executed in the APM Connect Administration Center, APM Connect will use the common filters in the context file to determine the scope of the extrac-

tion required by that Job. Now, you can configure the filter parameters specific to the Adapter Job that you would like to run.

Example: Using the Common Filters

To extract English records created between January 1st and December 31, 2000 and changed between January 1st and December 31st, 2012 from maintenance plant 1000:

- 1. In the CREATE_DATE_START field, enter the following to reflect January 01, 2000: 20000101.
- 2. In the **CREATE_DATE_END** field, enter the following to reflect December 31, 2000: 20001231.
- 3. In the **CHANGE_DATE_START** field, enter the following to reflect January 01, 2012: 20120101.
- 4. In the **CHANGE_DATE_END** field, enter the following to reflect December 31, 2012: 20121231.
- 5. In the **LANGUAGE** field, enter the following SAP code for English: E.
- 6. In the MAINT_PLANT field, enter the following maintenance plant ID: 1000.

The necessary filter parameters are entered into the context file, as shown in the following image:

```
ContextFile.xml - Notepad
File Edit Format View Help
        <!-- Filter parameters(some more will added based on requirement) -->
   <EQUIPMENT_NO></EQUIPMENT_NO>
    <FLOC NO></FLOC NO>
    <NOTIFICATION NO></NOTIFICATION NO>
        <WORK ORDER NO></WORK ORDER NO>
        <CREATE DATE START>20000101</CREATE DATE START>
        <CREATE DATE END>20001231</CREATE DATE END>
        <CHANGE_DATE_START>20120101</CHANGE_DATE_START>
        <CHANGE DATE END>20121231</CHANGE DATE END>
        <CREATE_TIME_START></CREATE_TIME_START>
        <CREATE_TIME_END></CREATE_TIME_END>
        <CHANGE TIME START></CHANGE TIME START>
        <CHANGE TIME END></CHANGE TIME END>
       <MAINT PLANT>1000</MAINT PLANT>
        <EQUIPMENT_CATEGORY></EQUIPMENT_CATEGORY>
    <FLOC CATEGORY></FLOC CATEGORY>
        <EQUIPMENT_TYPE></EQUIPMENT_TYPE>
        <FLOC_TYPE></FLOC_TYPE>
        <NOTIFICATION TYPE></NOTIFICATION TYPE>
        <WORK ORDER TYPE></WORK ORDER TYPE>
        <SYSTEM STATUS></SYSTEM STATUS>
        <USER_STATUS></USER_STATUS>
        <EQUIPMENT CLASS></EQUIPMENT CLASS>
        <FLOC CLASS></FLOC CLASS>
        <LANGUAGE>E</LANGUAGE>
        <WORK ORDER SYSTEM STATUS></WORK ORDER SYSTEM STATUS>
        <WORK_ORDER_USER_STATUS></WORK_ORDER_USER_STATUS>
```

7. Save the context file.

Only records with English descriptions created in 2000 and changed in 2012 from maintenance plant 1000 will be extracted when an Adapter is run in the APM Connect Administration Center.

What's Next?

- Common filters can be applied to each adapter. After the necessary common filters are configured, you can apply the following adapter specific parameters:
 - <u>Equipment Adapter filter parameters</u>.
 - Functional Location Adapter filter parameters.
 - Work History Adapter filter parameters.
 - Technical Characteristic filter parameters.
 - Work Management filter parameters.

Apply Equipment Filter Parameters

In the context file, there are filter parameters that apply specifically to the Equipment Adapter Jobs. These filter parameters determine what types of Equipment data will be transferred from the EAM source system into the GE Digital APM. This topic outlines the functions of Equipment-specific filters, and how to apply them.

Before You Begin

Before you can manipulate the Equipment Adapter data, you must first complete the following:

• Import the Equipment Adapter Job into the APM Connect Administration Center.

Steps

1. On the machine on which you installed APM Connect, navigate to <root:\\>\APMConnect\Config.

Note: If you are using multiple SAP systems there will be multiple context files to which you will need to apply the filter parameters.

2. Right-click on the *context file* file, and then select **Edit**.

The context file opens.

3. As needed, configure the <u>Common Filters</u>.

4. As needed, configure the following Equipment Filter parameters in the table:

Equipment Filter Parameters	Description	Value Requirements	Required or Optional
EQUIPMENT_NO	Equipment that you want to extract.	The Equipment number should not exceed 18 characters. You cannot exceed 500 Equipment numbers.	Optional
EQUIPMENT_ CATEGORY	ID of the Equipment Category that will limit the Equipment extracted	The Equipment Category should not exceed one character.	Optional
EQUIPMENT_ TYPE	ID of the Equipment Type that will limit the Equipment extrac- ted.	The Equipment Type should not exceed 10 characters.	Optional
EQUIPMENT_ CLASS	ID of the Equipment Classification that will limit the Equipment extracted.	The Equipment Class should not exceed 18 characters. If an Equipment has multiple classifications, as long as you specify one of those classifications, the Equipment record will be extracted.	Optional

5. Save the changes to the context file.

Results

The Equipment filter parameters are configured, and the Equipment Adapter Job
can be run in the APM Connect Administration Center. When a Job is run in the
APM Connect Administration Center, the Job will look to the context files for the
parameters of the extraction. If no filters are entered to limit the records extracted, all Equipment records will be extracted.

Example: SAP Equipment Data Extraction

To extract Equipment records created between December 2009 and December 2010 with Equipment numbers 1001273-1001277:

- 1. On the machine clear the APM Connect, navigate to <root:\\>\APMConnect\Config.
- 2. Right-click on the *context file* file, and then select **Edit**.

The context file opens.

- 3. In the **CREATE_DATE_START** field, enter the following to reflect the date December 1, 2009: 20091201.
- 4. In the **CREATE_DATE_END** field, enter the following to reflect the date December 31, 2010: 20101231.
- In the EQUIPMENT_NO field enter the following Equipment identification numbers: 00000000001001273, 00000000001001274,00000000001001275,00000000001001276,0000000000100-1277.

The necessary filter parameters are entered in the context file, as shown in the following image:

6. Save the context file.

Only Equipment records with the IDs 1001273-1001277 created between December 2009 and December 2010 are extracted when the Job is run in the APM Connect Administration Center.

What's Next?

• After you have applied the filters in the context file, you can <u>run the associated job in the APM Connect Administration Center</u>.

Apply Functional Location Filter Parameters

In the context file, there are filter parameters that apply specifically to the Functional Location Adapter. These filter parameters determine what types of Functional Location data will be transferred from the EAM source system into the GE Digital APM. This topic outlines the functions of Functional Location-specific filters, and how to apply them.

Before You Begin

Before you can manipulate the Functional Location data, you must first complete the following:

• Import the Functional Location Adapter Job into the APM Connect Administration Center.

Steps

1. On the machine on which you installed APM Connect, navigate to <root:\\>\APMConnect\Config.

Note: If you are using multiple SAP systems there will be multiple context files to which you will need to apply the filter parameters.

2. Right-click on the context file file, and then select Edit.

The context file opens.

- 3. As necessary, configure the Common Filters.
- 4. As necessary, configure the following Functional Location Filter parameters in the table:

Functional Location Para- meters	Description	Value Requirements	Required or Optional
FLOC_NO	Number that identifies the Functional Location record you want to extract.	The Functional Location number should not exceed 40 characters. You cannot exceed 500 Functional Location numbers.	Optional

FLOC_ CATEGORY	ID of the Functional Location Category that will limit the Functional Locations extracted.	The Functional Location Category should not exceed one character.	Optional
FLOC_CLASS	ID of the Functional Location Clas- sification that will limit the Functional Locations extracted.	The Functional Location Class should not exceed 18 characters.	Optional
FLOC_TYPE	ID of the Functional Location Type that will limit the Func- tional Locations extracted.	The Functional Location Type should not exceed ten characters.	Optional

5. Save the changes to the context file.

Results

• The Functional Location filters parameters are configured, and the Functional Location Adapter Job can be run in the APM Connect Administration Center. When a Job is run in the APM Connect Administration Center, the Job will look to the context files for the parameters of the extraction. If no filters are entered to limit the records extracted, all Functional Location records will be extracted.

Example: SAP Functional Location Extraction

To extract Functional Location records changed between January 1 and December 31, 2013, with the Functional Location class WCM:

- 1. On the machine on which you installed APM Connect, navigate to <root:\\>\APMConnect\Config.
- 2. Right-click on the *context file* file, and then select **Edit**.

The context file will open in notepad.

- 3. In the CHANGE_DATE_START field, enter 20130101.
- 4. In the **CHANGE_DATE_END** field, enter 20131231.
- 5. In the **FLOC_CLASS** field, enter *WCM* to limit records extracted to those with the Functional Location class of WCM, as shown in the following image:

```
ContextFile.xml - Notepad
File Edit Format View Help
        <!-- Filter parameters(some more will added based on requirement) -->
    <EQUIPMENT NO></EQUIPMENT NO>
    <FLOC NO></FLOC NO>
    <NOTIFICATION_NO></NOTIFICATION_NO>
        <WORK_ORDER_NO></WORK_ORDER_NO>
        <CREATE DATE START></CREATE DATE START>
        <CREATE_DATE_END></CREATE_DATE_END>
        <CHANGE DATE START>20130101</CHANGE DATE START>
        <CHANGE DATE END>20131231</CHANGE DATE END>
        <CREATE_TIME_START></CREATE_TIME_START>
        <CREATE TIME END></CREATE TIME END>
        <CHANGE_TIME_START></CHANGE_TIME_START>
        <CHANGE_TIME_END></CHANGE_TIME_END>
        <MAINT PLANT></MAINT PLANT>
        <EQUIPMENT_CATEGORY></EQUIPMENT_CATEGORY>
    <FLOC CATEGORY></FLOC CATEGORY>
        <EQUIPMENT TYPE></EQUIPMENT TYPE>
        <FLOC_TYPE></FLOC_TYPE>
        <NOTIFICATION_TYPE></NOTIFICATION_TYPE>
        <WORK ORDER TYPE></WORK ORDER TYPE>
        <SYSTEM_STATUS></SYSTEM_STATUS>
        <USER_STATUS></USER_STATUS>
        <EQUIPMENT CLASS></EQUIPMENT CLASS>
        kFLOC CLASS>WCM</FLOC CLASS>
        <LANGUAGE>E</LANGUAGE>
        <WORK_ORDER_SYSTEM_STATUS></WORK_ORDER_SYSTEM_STATUS>
```

6. Save the context file.

Only Functional Location records with the Functional Location class WCM that were modified between January 1 and December 31, 2013, are extracted when the Job is run in the APM Connect Administration Center.

What's Next?

• After you have applied the filters in the context file, you can <u>run the associated job</u> in the APM Connect Administration Center.

Apply Work History Filter Parameters

There are filter parameters in the context file that specifically apply to the Work History Adapter. The filter parameters determine what types of Work History data will be transferred from SAP into the GE Digital APM. This topic describes the functions of Work History-specific filters, and how to apply them.

Before You Begin

Before you can manipulate the Work History data, you must complete the following:

• Import the Work History Adapter Job into the APM Connect Administration Center.

Steps

- 1. On the machine on which you installed APM Connect, navigate to <root:\\>\APMConnect\Config.
- Right-click on *context file* file, and select **Edit**.The context file opens.
- 3. As necessary, configure the Common Filters.
- 4. As necessary, configure the following Work History parameters in the context file:

Work History Para- meters	Description	Value Requirements
CHANGE_TIME_ START	Time value. Retrieves records changed on or after the specified time.	Times must be entered in the following format: HHMMSS.
CHANGE_TIME_END	Time value. Retrieves records changed on or before the specified time.	Times must be entered in the following format: HHMMSS.
CREATE_TIME_START	Time value. Retrieves records created on or after the specified time.	Times must be entered in the following format: HHMMSS.
CREATE_TIME_END	Time value. Retrieves records created on or before the specified time.	Times must be entered in the following format: HHMMSS.
WORK_ORDER_ SYSTEM_STATUS	Work Order systems status that limits the work orders you want to extract	Work Order System Status should not exceed four characters.

WORK_ORDER_ USER_STATUS	Work Order user status that limits the work orders you want to extract	Work Order User Status should not exceed four characters.
NOTIFICATION_ SYSTEM_STATUS	Notification system status that limits the notifications you want to extract.	Notification system status should not exceed four characters.
NOTIFICATION_ USER_STATUS	Notification user status that limits the notifications you want to extract.	User status should not exceed four characters.
NOTIFICATION_NO	Number that identifies the Notification record.	Notification Number should not exceed 12 characters.
WORK_ORDER_NO	Number that identifies the Work Order record.	Work Order Number should not exceed 12 characters.
NOTIFICATION_TYPE	Order type that limits the orders you want to extract.	Notification type should not exceed two characters.
WORK_ORDER_TYPE	ID of the work order that limits the orders you want to extract.	Work Order type should not exceed four characters.
EQUIPMENT_ CATEGORY	ID of the Equipment category that limits the Equipment data extracted.	Equipment category should not exceed one character.
EQUIPMENT_CLASS	ID of the Equipment class that limits the Equipment data extracted.	Equipment class should not exceed 18 characters.
EQUIPMENT_TYPE	ID of the Equipment Type that will limit the Equipment extracted.	Equipment type should not exceed 10 characters.
FLOC_CATEGORY	ID of the Functional Location Category that will limit the Functional Locations extracted.	Functional Location category should not exceed one character.
FLOC_CLASS	ID of the Functional Location Classification that will limit the Functional Locations extracted.	Functional Location class should not exceed 18 characters.

FLOC_TYPE ID of the Functional Location Type that will limit the Functional Locations extracted.	Functional Location type should not exceed 10 characters.
---	---

Results


• The context file is configured, and the Work History Adapter Job can be run in the APM Connect Administration Center. When a Job is run in the APM Connect Administration Center, the job will look to the context files for the parameters of the extraction. If no filters are entered to limit the records extracted, all Work History records for work orders and notifications will be extracted.

Example: SAP Work History Extraction

To extract Work History records created in 2014 between October 1-31st, changed between the hours of 8:00 A.M. and 5:00 P.M., with the Work Order type maintenance orders, with the Equipment Type mobile cranes:

- 1. On the machine on which you installed APM Connect, navigate to <root:\\>\APMConnect\Config.
- 2. Right-click on the *context file* file, and select **Edit**.
 - The context file opens.
- 3. In the **CREATE_DATE_START** field, enter the following to reflect October 1, 2014: 20141001.
- 4. In the **CREATE_DATE_END** field, enter the following to reflect October 31, 2014: 20141031.
- 5. In the **CHANGE_TIME_START** field, enter the following to reflect 8:00 A.M.: 080000.
- 6. In the CREATE_TIME_END field, enter the following to reflect 5:00 P.M.: 170000.
- 7. In the **WORK_ORDER_TYPE** field, enter the following SAP code for Maintenance order: PAM.
- 8. In the **EQUIPMENT_TYPE** field, enter the following SAP code for Mobile Cranes: 007.

The necessary parameters are in the context file, as shown in the following image:



9. Save the context file.

Only Work History records that are Maintenance Orders for Mobile Cranes created in October 2014, changed between the hours of 8:00 A.M. and 5:00 P.M., will be extracted when the Work History Job is run in APM Connect Administration Center.

What's Next?

 After you have applied the filters in the context file, you can <u>run the associated job</u> in the APM Connect Administration Center.

Apply Technical Characteristics Filters

In the context file, there are filter parameters that apply specifically to the Technical Characteristics Adapter Jobs. These filter parameters determine what types of Technical Characteristics data will be transferred from the EAM source system into the GE Digital APM.

Before You Begin

Before you can manipulate the Technical Characteristics Adapter data, you must import the Technical Characteristics Adapter Job into the APM Connect Administration Center.

Steps

To configure filter parameters for the Equipment Technical Characteristics Adapter:

- 1. On the machine on which you installed APM Connect, navigate to <root:\\>\APMConnect\Config.
- Right-click on the *context file* file, and then select **Edit**.The context file opens.
- 3. As needed, configure the Common Filters.
- 4. As needed, configure the following Technical Characteristics Filter parameters for *Equipment* in the table:

Equipment Fil- ter Parameters	Description	Value Requirements	Required/ Default or Optional
EQUIPMENT_ NO	Equipment number that defines the Equipment that you want to extract	The Equipment number should not exceed 18 characters.	Optional
EQUIPMENT_ CATEGORY	ID of the Equipment Category that will limit the Equipment extracted	The Equipment Category should not exceed one character.	Optional

EQUIPMENT_ CLASS	ID of the Equipment Classification that will limit the Equipment extracted. If an Equipment has multiple classifications, as long as you specify one of those classifications, the Equipment record will be extracted. Note: When Technical Characteristic classifications are updated in GE Digital APM, they will override any changes made to the classifications parameter in the context file.	The Equipment Class should not exceed 18 characters.	Optional
EQUIPMENT_ TYPE	ID of the Equipment Type that will limit the Equipment extracted	The Equipment Type should not exceed 10 characters.	Optional

5. Save the changes to the context file.

Results

 The Equipment Technical Characteristics filter parameters are configured, and the Equipment Technical Characteristics Adapter Job can be run in the APM Connect Administration Center. When a Job is run in the APM Connect Administration Center, the Job will look to the context files for the parameters of the extraction. If no filters are entered to limit the records extracted, all Equipment Technical Characteristics records will be extracted.

Steps

To configure filter parameters for the Functional Location Technical Characteristics Adapter:

- 1. On the machine on which you installed APM Connect, navigate to <root:\\>\APMConnect\Config.
- 2. Right-click on the *context file* file, and then select **Edit**.

The context file opens.

- 3. As necessary, configure the following Common Filters.
- 4. As needed, configure the following Functional Location Technical Characteristics filter parameters in the table:

Functional Location Para- meters	Description	Value Requirements	Required/ Default or Optional
FLOC_NO	Functional Location number that defines the Functional Loca- tion that you want to extract.	The Functional Location number should not exceed 40 characters.	Optional
FLOC_ CATEGORY	ID of the Functional Location Category that will limit the Functional Locations extracted.	The Functional Location Category should not exceed one character.	Optional
FLOC_CLASS	ID of the Functional Location Clas- sification that will limit the Functional Locations extracted.	The Functional Location Class should not exceed 18 characters.	Optional
FLOC_TYPE	ID of the Functional Location Type that will limit the Func- tional Locations extracted.	The Functional Location Type should not exceed 10 characters.	Optional

5. Save the changes to the context file.

Results

The Functional Location Technical Characteristics filters parameters are configured, and the Technical Characteristics Adapter Job can be run in the APM Connect Administration Center. When a Job is run in the APM Connect Administration Center, the Job will look to the context files for the parameters of the extraction. If no filters are entered to limit the records extracted, all Technical Characteristics records will be extracted.

What's Next?

• After you have applied the filters in the context file, you can <u>run the associated job</u> <u>in the APM Connect Administration Center</u>.

Apply Work Management Filters

There is a filter parameter in the context file that applies specifically to the Work Management Adapter. The filter parameter determines what Work Management data will be transferred from SAP into the GE Digital APM.

Before You Begin

Before you can apply Work Management filters, you must import the Work Management Adapter Job into the APM Connect Administration Center.

Steps

- 1. On the machine on which you installed APM Connect, navigate to <root:\\>\APMConnect\Config.
- Right-click on the *context file* file, and then select **Edit**.The context file opens.
- 3. As needed, configure the Common Filters.
- 4. As needed, configure the Work Management filter parameter in the table:

Work Man- agement Filter Parameter	Description	Value Requirements	Required/ Default or Optional
MAINTENANCE_ PLAN	Maintenance Plan ID number that defines the Work Management data that you want to extract.	The Maintenance Plan ID is 12 char- acters.	Optional
INSPECTION_ FAMILY	Determines to which family the Inspection records are associated.	To use the default association enter the value <i>MI_TASKINSP</i> .	Required

INSPECTION_ CONDITION	Determines the SAP control key used to identify trigger values for inspection records.	The parameter requires specific syntax as follows: <sap table="">-<sap field=""> EQ '<key 1="" value="">, <key 2="" value="">,<key 3="" value="">, etc' To use the default configuration, enter the following value PLPO-STEUS EQ 'ZMI1'.</key></key></key></sap></sap>	Required
CALIBRATION_ FAMILY	Determines to which family the Cal-ibration records are associated.	To use the default conflagration enter the value <i>MI_TASKCALB</i> .	Required
CALIBRATION_ CONDITION	Determines the SAP control key used to identify trigger values for calibration records.	The parameter requires specific syntax as follows: <sap table="">-<sap field=""> EQ '<key 1="" value="">, <key 2="" value="">,<key 3="" value="">, etc' To use the default configuration, enter the following value PLPO-STEUS EQ 'ZMI2'</key></key></key></sap></sap>	Required

Example 1: Configure Work Management to use Non-default Control Keys

Suppose you want to use the SAP field STEUS with the control keys PM01 and PM02 to trigger Calibration task records. Additionally, suppose you want to use the control keys QM01 and QM02. In this case, you should configure the context file as follows:

- 1. In the INSPECTION_FAMILY parameter, enter MI_TASKINSP
- 2. In the INSPECTION_CONDITION parameter, enter PLPO-STEUS EQ 'QM01,QM02'
- 3. In the CALIBRATION_FAMILY parameter, enter MI_TASKCALB.
- 4. In the CALIBRATION_CONDITION parameter enter, PLPO-STEUS EQ 'PM01,PM02'

The Work Management parameters are configured.

```
<INSPECTION_FAMILY>MI_TASKINSP</INSPECTION_FAMILY>
<INSPECTION_CONDITION>PLPO-STEUS EQ 'QM01,QM02'</INSPECTION_CONDITION>
<CALIBRATION_FAMILY>MI_TASKCALB</CALIBRATION_FAMILY>
<CALIBRATION CONDITION>PLPO-STEUS EQ 'PM01,PM02'</CALIBRATION CONDITION>
```

Example 2: Configure Work Management to use Non-default Control Keys

Suppose you want to use the SAP field USROO from the PLPO table, the control key values PM01 or PM02 for Calibration Task, and the control key QM01 or QM02 for Inspection Tasks.

- 1. In the INSPECTION_FAMILY parameter, enter MI_TASKINSP
- 2. In the INSPECTION_CONDITION parameter, enter PLPO-USR00 EQ 'QM01,QM02'
- 3. In the CALIBRATION_FAMILY parameter, enter MI_TASKCALB.
- 4. In the CALIBRATION_CONDITION parameter enter PLPO-USR00 EQ 'PM01,PM02"

The Work Management parameters are configured.

```
<INSPECTION_FAMILY>MI_TASKINSP</INSPECTION_FAMILY>
<INSPECTION_CONDITION>PLPO-USR00 EQ 'QM01,QM02'</INSPECTION_CONDITION>
<CALIBRATION_FAMILY>MI_TASKCALB</CALIBRATION_FAMILY>
<CALIBRATION_CONDITION>PLPO-USR00 EQ 'PM01,PM02'</CALIBRATION_CONDITION>
```

Results

• The context file is configured, and the Work Management Adapter Job can be run in the APM Connect Administration Center. When a Job is run in the APM Connect Administration Center, the Job will look to the context file for the parameters of the extraction. If no filters are entered to limit the records extracted, all Work Management records will be extracted.

What's Next?

 After you have applied the filters in the context file, you can <u>run the associated job</u> in the APM Connect Administration Center.

About the SAP Adapters

This topic provides a listing of all overviews and high level explanatory information to help you understand the SAP Adapters.


About the Equipment and Functional Location Adapters

The Equipment Adapter lets you extract Equipment items from your SAP system into your GE Digital APM system. When you do so, for each SAP Equipment item that meets the criteria defined in the extraction Job, a corresponding Equipment record is created in the GE Digital APM database.

Likewise, the Functional Location Adapter lets you extract Functional Locations from your SAP system into your GE Digital APM system. When you do so, for each Functional Location that meets the criteria defined in the extraction Job, a corresponding Functional Location record is created in the GE Digital APM database.

Because the SAP system allows you to define a hierarchy in which Functional Locations are related to other Functional Locations, and because Equipment items are also related to Functional Locations, when you run either the Equipment Adapter or the Functional Location Adapter, the SAP hierarchy is maintained. In some cases, to maintain the hierarchy, placeholder records are created in the GE Digital APM database to represent the SAP relationships.

For example, suppose that the SAP system contains the following Functional Locations and Equipment items, where the Functional Locations are shaded red, and the Equipment items are shaded green.



In this case, if you were to run the Functional Location Adapter, the following Functional Location records would be created automatically in the GE Digital APM database:

- FL-101
- FL-101-A
- FL-101-A-01

Then, if you were to run the Equipment Adapter, the following Equipment record would be created automatically in the GE Digital APM database:

• Equipment-1

This Equipment record would be linked automatically to the Functional Location record for *FL-101-A-01*.

Suppose, however, that using the same SAP data structure example, you decide to run the Equipment Adapter *before* running the Functional Location Adapter. In this case, when running the Equipment Adapter, the Equipment record *Equipment-1* would be created automatically to represent that SAP Equipment item. In addition, the following placeholder Functional Location record would also be automatically created to represent the SAP Functional Location that is directly associated with the Equipment:

• FL-101-A-01

The Equipment record would be automatically linked to the Functional Location record *FL-101-A-01*. This placeholder record would contain a value only in the Functional Location key fields. You would need to run the Functional Location Adapter to populate the remaining fields in the placeholder Functional Location record.

About the Work History Adapter

If Orders and Notifications are associated with a Technical Object, you can extract Orders and Notifications from SAP to create Work History records and Work History Detail records in GE Digital APM. To do so, you will need to run the Work History Adapter Job.

When you extract an Order (with or without Notifications), the following Work History records are created:

- One Work History record to represent the Order Header, which appears on the
 HeaderData tab in SAP. This Work History record will be created for the Technical
 Objects that appears on the HeaderData tab in SAP. This means that the Work History record will be populated with values representing those Technical Objects,
 and it will also be linked to the Equipment or Functional Location records representing those objects. Only this Work History record will contain cost values and
 estimated and actual confirmed hours.
- One Work History record per object that appears in the Order's object list (i.e., on the Objects tab when you are viewing the Order). These Work History records will be created for the Technical Objects that are specifically associated with those items. This means that these Work History records will be populated with values representing those Technical Objects, and they will also be linked to the Equipment or Functional Location records representing those Technical Objects.

When you extract a Notification that is not associated with an Order, one Work History record is created to represent the Notification, and this Work History record will be linked to Equipment and Functional Location records representing the Notification reference objects. Specifically:

- If the Notification has only an Equipment reference object, the Work History record for that Notification will be linked to an Equipment record.
- If the Notification has only a Functional Location reference object, the Work History record for that Notification will be linked to a Functional Location record.
- If the Notification has Equipment and Functional Location reference objects, the Work History record for that Notification will be linked to an Equipment record and a Functional Location record.

If a Notification has items, one Work History Detail record will be created to represent each item.

The following tables detail what to expect when running a Work History Job based on your SAP work order and notification combinations:

Orders Without Notifications

After you:	Run this Job:	Result:
Create an Order that is not associated with a Notification.	SAP_ WorkHistory	A Work History record is created.
Update the Order referenced above.	SAP_ WorkHistory	The corresponding Work History record is updated.

Orders With Notifications

Notifications Without Items:

After you:	Run this Job:	Result:
Create an Order that is associated with a Notification without items.	SAP_ WorkHistory	A Work History record is created to capture the data in the Order and the Notification.
Update only the Order.	SAP_ WorkHistory	The corresponding Work History record is updated.
Update only the Notification.	SAP_ WorkHistory	The corresponding Work History and Work History Detail records are updated.
Update both the Order and Notification.	SAP_ WorkHistory	The corresponding Work History and Work History Detail records are updated.

Notifications With Items:


After you:	Run this Job:	Result:
Create a Notification with items, but do not associate it with an Order.	SAP_ WorkHistory	A Work History record and a Work History Detail record are created to capture the data in the Notification.
Update the Notification referenced above.	SAP_ WorkHistory	The corresponding Work History and Work History Detail records are updated.

Notifications and Work orders transferred from SAP into GE Digital APM maintain their SAP ID in the Work History Detail and Work History record naming convention.

For example, suppose Work Order 18652 and Notification 20087 are related in SAP. Then, the Work Order and Notification are transferred into GE Digital APM. One Work History record will be created using the following syntax: WH ~ <Notification Number> ~

<Work Order Number>. In this example, the Work History record ID would be WH~20087~18652.


The following diagram exemplifies how records in SAP are mapped to Work History records in GE Digital APM.




Example: Order With Notification: Items on Object List

Suppose the following SAP Order exists, where the red outlines indicate that:

- The Order number is 4000483.
- The associated Notification number is 10001363.
- The reference Technical Objects are Functional Location *ABC-PQR/12-34-56/8* and Equipment *TURBINE*.



In addition, you can see from the Objects tab that there are items on the object list:



If you were to extract this Order, two Work History records would be created:

- One for the Order and Notification combination.
- One for the object list item EQABC123.

Work History Record for the Order and Notification Combination

Suppose there is a Work History record for the Order and Notification combination, where the associated Technical Object is *TURBINE*, and the Work History record is also linked to the Equipment record *TURBINE*.

Note: The Equipment record *TURBINE* is created during the Order extraction process as a placeholder record. You would need to run the Equipment Adapter to populate the Equipment fields.

If the Notification contained items, a Work History Detail record would also be created to capture additional information about that Notification.

Work History Record for the Object List Item *EQABC123*


Suppose the Work History record for the object list item *EQABC123*, and that the Work History record is also linked to the Equipment record *EQABC123*.

Note: The Equipment record *EQABC123* and the associated Functional Location record *ABC-XYZ-DE-VW-123456* are created during the Order extraction process as placeholder records. You would need to run the Equipment Adapter and the Functional Location Adapter to populate the Equipment record and Functional Location record fields.

Example: Order Without Notification: No Items on Object List

Suppose the following SAP Order exists, where the red outlines indicate that:

- The Order number is 4000141.
- There is no associated Notification.
- The reference Technical Object is Equipment *V100*.



In addition, you can see from the Objects tab that there are no items on the object list:



If you were to extract this Order, the following Work History record would be created, with the following:


- The referenced technical object is *V100*.
- The Work History record is linked to the Equipment record *V100*.

Note: The Equipment record *V100* is created during the Order extraction process as a placeholder record. You would need to run the Equipment Adapter to populate the Equipment fields.

Example: Notification Without Order: Without Notification Items

Suppose the following SAP Notification exists, where the red outlines indicate that:

- The Notification number is 10001364.
- The reference Technical Object is Functional Location *A1*.
- There are no items.



If you were to extract this Notification, the Work History record would be created, with the following:

- The Work History record is associated with the Notification's Technical Object A1.
- The Work History record is linked to the Functional Location record A1.

Note: The Functional Location record *A1* is created during the Notification extraction process as a placeholder record. You would need to run the Functional Location Adapter to populate the Functional Location fields.

Example: Notification Without Order: With Notification Items

Suppose the following SAP Notification exists, where the red outlines indicate that:

- The Notification number is 10001365.
- The reference Technical Object is Functional Location *F1*.
- There are two items.

Displa Displa	y PM Notification: Maintenance Request
3 4 3 6 .	
Notification Status	M1 Notification_With Items OSNO
Notification	Reference object Malfunction, breakdown Location data Scheduling overview
Reference object Functional loc. Equipment Assembly Subject Coding Description Notification	F1 Functional Location F1
Responsibilities	
Planner group	KG / 3002 Kroger
Main WorkCtr	SERVICES / 1061 services
Department resp	
Person respons.	H
Reported by	Notif.date 07/27/2012 20:54:57
Stort/End Dates	
Start/End Dates	07/27/2012 20:54:57 Priority
Required Start	07/27/2012 20:54:57 Priority 07/28/2012 00:00:00 Breakdown
Required End	0772072012 00.00.00 Dieakdowii
Item	
Object part	PM1 2 Object part 2
Damage	
Text	Text test
Cause code	PM1 1 Cause 1
Cause text	
	Entry 1 frm 2

If you were to extract this Notification, the following records would be created:

- One Work History record.
- Two Work History Detail records: one to capture additional information about the first notification item, and another to capture additional information about the second notification item.

The Work History record, would be created with the following:


- The Work History record is associated with the Notification's Technical Object *F1*.
- The Work History record is linked to the two Work History Detail records.
- The Work History record is linked to the Functional Location record *F1*.

Note: The Functional Location record F1 is created during the Notification extraction process as a placeholder record. You would need to run the Functional Location Adapter to populate the Functional Location fields.

About the Technical Characteristics Adapter

Note: You can run the Technical Characteristics Adapters successfully only if the SAP Technical Characteristics license is active.

In SAP, you can assign specific characteristics to Equipment and Functional Locations. Each characteristic belongs to a Classification, and each Classification belongs to a Class Type. For example, the Class Type Equipment Class might contain the classification Storage Tanks, which might contain the Characteristics Diameter and Wall Thickness, as illustrated in the following image:



When you extract Equipment and Functional Locations from SAP into the GE Digital APM system, their corresponding Characteristics will not be extracted into the Equipment and Functional Location records that are created during the extraction process. If you want to extract their corresponding Characteristics, you will need to run the Technical Characteristics Adapter. When you run these adapters, Technical Characteristic records are created to store the Characteristics that have been configured to be extracted, and these records are linked automatically to the appropriate Equipment and Functional Location records.

Note: When Technical Characteristic classifications are updated in GE Digital APM, they will override any changes made to the <u>classifications parameter in the context</u> file.


Numeric Value Format

The format in which numbers are displayed in GE Digital APM is determined by the SAP user that is used to extract the SAP data. For example, if the SAP user is configured to display the value one thousand one hundred and one-tenth as 1.100,1. The value in GE Digital APM will be displayed in the same format.

Multiple Objects Allowed

The Technical Characteristic Adapter can transfer Equipment and Functional Locations configured for Multiple Objects Allowed. This functionality is enable by context parameters in the context file.

Equipment and Functional Locations are configured for Multiple Object in SAP, as shown in the following image.



This indicator tells you whether several different types of object can be classified in classes of this class type. This allows you to classify objects that are logically related to each other in the same classes.

GE Digital APM Actions and Results

In GE Digital APM, you can configure which Characteristics you want to extract from SAP. When you do so, various actions that you perform in the GE Digital APM system and the SAP system cause specific results, as seen in the following table.

Action	Result	Notes
Select the Extract From CMMS System check box in a CMMS Characteristic record.	The next time the Technical Characteristics Adapter is run, the characteristic is extracted.	During the extraction process, a corresponding Technical Characteristic record is created.
Clear the Extract From CMMS System check box in a CMMS Characteristic record.	If a Technical Characteristic record has been created using this CMMS Characteristic record, it is not deleted automatically when you delete the CMMS Characteristic record. Instead, the next time that the Technical Characteristics Adapter is run, the corresponding Technical Characteristic record is deleted.	To begin extracting the characteristic again, you will need to select the Extract From CMMS System check box.

Delete a CMMS Char- acteristic record.	If a Technical Characteristic record has been created using this CMMS Characteristic record, it is not deleted automatically when you delete the CMMS Characteristic record. Instead, the next time that the Technical Characteristics Adapter is run, the corresponding Technical Characteristic record is deleted. In addition, until the CMMS Characteristic record is recreated and flagged for extraction, beginning with the next time the Technical Characteristics Adapter is run, the characteristic is no longer extracted.	To begin extracting the characteristic again, you will need to: • Refresh the GE Digital APM system to reflect the current SAP characteristics, which will cause the CMMS Characteristic record to be recreated. • Select the Extract From CMMS System check box in that CMMS Characteristic record.
---	---	--

All CMMS Characteristic records that were linked to the CMMS Classification record are deleted automatically.

If a Technical Characteristic record has been created using this CMMS Classification record, it is not deleted automatically when you delete the CMMS Classification record.

Delete a CMMS Classification record.

Instead, the next time that the Technical Characteristics Adapter is run, the corresponding Technical Characteristic records are deleted automatically.

In addition, until the CMMS Classification record is recreated and flagged for extraction, beginning with the next time the Technical Characteristics Adapter is run, characteristics belonging to that classification are no longer extracted.

To begin extracting characteristics belonging to this classification again, you will need to:

- Refresh the GE Digital APM system to reflect the current SAP classifications, which will cause the CMMS Classification record to be recreated automatically.
- Select the Extract From CMMS System check box in the CMMS Classification record.
- Refresh the GE Digital APM system to reflect the current SAP characteristics, which will cause the CMMS Characteristic records that were previously deleted to be recreated automatically.
- Select the Extract From CMMS System check box in the appropriate CMMS Characteristic records.

Delete a

sification

CMMS Clas-

Type record.

All CMMS Classification and CMMS Characteristic records that were linked (directly or indirectly) to the CMMS Classification Type record are deleted automatically.

If a Technical Characteristic record has been created using this CMMS Classification Type record, it is not deleted automatically when you delete the CMMS Classification Type record.

Instead, the next time that the Technical Characteristics Adapter is run, the Technical Characteristic record is deleted automatically.

In addition, until the CMMS Classification Type record is recreated and its CMMS Classification and CMMS Characteristic records are flagged for extraction, beginning with the next time the Technical Characteristics Adapter is run, *no* characteristics are extracted.

To begin extracting characteristics again, you will need to:

- Recreate the CMMS Classification Type record.
 Refresh the GE Digital APM system to reflect the current SAP classifications and characteristics, which will cause CMMS Classification records to be recreated.
- Select the Extract From CMMS System check box in the desired CMMS Classification records.
- Refresh the GE Digital APM system to reflect the current SAP classifications and characteristics, which will cause CMMS Classification records to be recreated.
- Select the Extract From CMMS System check box in that CMMS Characteristic record.

SAP Actions and Results

Action	Result
Specify a value for a characteristic that is configured to be extracted.	The next time the Technical Characteristics Adapter is run, a Technical Characteristic record is created and linked to the corresponding Equipment or Functional Location record.

Remove a value for a characteristic that is configured to be extracted.	The next time the Technical Characteristics Adapter is run, the corresponding Technical Characteristic record is updated by removing the value from the Value field.
Assign a new classification to an Equipment or Functional Location, and specify values for the characteristics belonging to that class.	The next time the Technical Characteristics Adapter is run, Technical Characteristic records representing the new characteristic values are created and linked to the corresponding Equipment or Functional Location record.
Remove the assignment of a classification from an Equipment or Functional Location record.	The next time the Technical Characteristics Adapter is run or you refresh the GE Digital APM system to reflect current SAP characteristics, the corresponding Technical Characteristic record is deleted.
Delete a characteristic from a classification.	The next time the Technical Characteristics Adapter is run, the corresponding Technical Characteristic record is deleted.

About the Work Management Adapter

Note: You can run the Work Management Interface only if the SAP-Work Management Interface license is active.

The Work Management Adapter facilitates integration with SAP's planning and scheduling modules for Condition Assessment activities. The adapter allows you to manage scheduled work in SAP and GE Digital APM.

About Task Records


If an SAP Maintenance Plan has a task List that has an Operations and Object Lists that meets the criteria defined in context file, when you run the Work Management Adapter in the Administration Center, task(s) record will be created in GE Digital APM. The corresponding task record will be created based on the task configuration done in the context file.

If you later modify that Maintenance Plan and then run the Work Management Adapter again, the corresponding task record will be updated automatically in GE Digital APM. Likewise, if you add an Order to the Maintenance Plan, the corresponding task record will also be updated automatically in GE Digital APM.

After executing the Work Management Adapter, it creates tasks in GE Digital APM using the following items in SAP:

- Operations
- Object list

For example, suppose you have a maintenance plan with two operations and two object lists. When you run the adapter, six tasks will be created and associated with the particular asset in GE Digital APM as show in the following image:



About Last and Next Date from SAP

When transferring Work Management data from SAP into GE Digital APM, the Desired Interval field is populated with a null value. The Next Date field will populate with the next execution date of the task (GE Digital APM) or operation (SAP) when transferred to GE Digital APM.

I Note: Last Date and Next Date values are calculated in SAP, not in GE Digital APM.

The following chart includes the possibilities for the Last Date and Next Date fields upon transferring data from SAP into GE Digital APM task records:

Workflow Step	Step Narrative	Last Date Field	Next Date Field
Plan is created, but not sched- uled, and the Work Man- agement Job is run.	The tasks of a Plan are created in GE Digital APM when the Work Man- agement Job is run.	Null	Null
Plan is scheduled, but not called, and the Work Management Job is run.	The Plan is scheduled. The task created above should be updated in GE Digital APM.	Null	If the Plan is <i>On Hold</i> , the field will contain the next execution date. Otherwise, the field is Null.
Plan is called for the first time, and the Work Man- agement Job is run.	The task previously created will be updated with information from the Work Order from SAP.	Null	Next execution date of task. Work Order started.
Task is executed in GE Digital APM.	An inspection event is linked to the task. The inspection Hours field is set, and the inspection is closed. A confirmation record is created.	Date is set to date of Confirmation.	Next execution date of task. Work Order started.

SAP Maintenance Plans Supported

The Work Management Adapter creates GE Digital APM Inspection or Calibration tasks

from SAP Operations on the Task List from the following Plan Types

SAP Plan Type	Supported by the Work Management Adapter
Single Cycle: Time-Based	Supported
Single Cycle: Performance-Based	Supported
Strategy Plan: Time-Based	Supported
Strategy Plan: Performance-Based	Supported
Multiple Counter Plan	Supported

About Discontinued Task Records

If a task record was created from SAP data and you later modify the SAP data in a way that causes that task record to become obsolete, you can run the Work Management Job to resolve the differences.

When you run the adapter, the tasks are validated against the data in SAP. SAP will search for the task records with an Equipment or Functional Location, Maintenance Plan, Maintenance Plan Item, Task List, and Operation combination to check if the task is valid. If it finds one that is not valid:

- The task ID of the invalid task record will be set to **DISCONTINUED**.
- The value in the Reason field will be pre-pended with the following:
 - <Date> <User ID> task was discontinued due to changes in SAP. The previous task ID was previous task ID.

Where <Date> is the date on which the task ID was set to **DISCONTINUED** and <User ID> is the user name of the user updating the record.

For example, suppose a Calibration task record was created from an Operation with the control key ZMI2. If you later change the control key and run the report, the Calibration task record will be discontinued.

Note: When a task ID in a task record has already been set to **DISCONTINUED**, if you run Work Management Adapter again and the task data is still not valid, the task record will be skipped. In other words, its Reason field will not contain more than one instance of the text **DISCONTINUED**.

Note: If you modify the SAP data so that it corresponds to the existing task record again, running the adapter will cause GE Digital APM to create a new records instead of updating the discontinued task record.

About Call Horizon

When the scheduled item that GE Digital APM delivers for the purpose of creating SAP Orders is executed, the GE Digital APM system performs a calculation on the Next Date and Call Horizon values in all task records. The calculated result is passed into the query Get tasks for Work Order Generation. If the result meets the criteria defined for the query column ([Task].[Next Date] - [Task].[Call Horizon]), the task record meets the remaining criteria defined in the query, and the task does not already contain a value in the Work Order Number field, an Order will be created from the task record.

Using the baseline query, an SAP Order will be created if the task record meets all query criteria (e.g., the Maintenance Plan field does not contain a value) and the calculated result meets the following criteria:

Task Next Date - Task Call Horizon = A date between the Last Executed Date and the Next Execution Date of the scheduled item.

Example

Suppose the scheduled item contains the following values:

Last Executed Date	Next Execution Date
July 1, 2008 1:00:00 A.M.	July 2, 2008 1:00:00 A.M.

Based on these values, an SAP Maintenance Order will be created automatically if the Next Date of the task record minus its Call Horizon is between July 1, 12:00:00 A.M. and July 2, 12:00:00 A.M.

Suppose a task record contains the following values:

Next Date	Call Horizon
July 11, 2008 3:00:00 A.M.	10

Using these task record values, if you subtract the Call Horizon, 10 days, from the Next Date, July 11, 2008 3:00:00 A.M., the result is July 1, 2008 3:00:00 A.M.

Because July 1, 2008 3:00:00 A.M. falls between the Last Executed Date of July 1, 2008 1:00:00 A.M. and July 2, 2008 1:00:00 A.M., the task record will be used to generate an Order (assuming that the task record meets the remaining query criteria).

In other words:

July 11, 2008 3:00:00 A.M. (Task Next Date) - 10 (Call Horizon) = July 1, 2008 3:00:00 A.M. (A date between the Last Executed Date and the Next Execution Date of the scheduled item)

Note: If the scheduled item is being executed for the first time, GE Digital APM assumes a Last Executed Date of 1/1/1900. Also, if the Call Horizon field does not contain a value, the value is treated as zero (0).

About Filter Parameters

Filter parameters determine what data will be transferred from the EAM source systems to GE Digital APM, and are applied to the extraction job in the context file. There are two types of filter parameters: configuration parameters and adapter filter parameters. Each adapter has specific filters that apply only to that adapter. Additionally, there are some filter parameters that are common to all of the SAP adapters. When an adapter job executes, it will apply all common filters and those unique to the specific adapter job. This topic provides an overview of the adapter filter parameters for the following adapters:

- Equipment
- Functional Location
- Work History
- Technical Characteristics
- Work Management

Scope of the Filter Parameters

By entering a value into the parameter, you limit the scope of the extraction to the values in the parameter. If no value is entered into a parameter, all data for that parameter will be transferred from the EAM system source into the GE Digital APM.

Additionally, changes made in the context file will change the scope of all jobs connected to that context file. For example, if you changed the FLOC_CLASS value in the context file, all Functional Location jobs in the APM Connect Administration Center, associated with that context file, will change accordingly. However, you can use more than one context file for multiple SAP systems.

How Times and Dates are Used

There are certain conditions that apply to some of the <u>common filter parameters</u>, as shown in the following table:

Condition	Expect Result	Note
If <u>start date para</u> - <u>meter</u> is empty	then the start date defaults to 1/1/1900.	None
If <u>end date parameter</u> is empty	then the end date defaults to the current date.	None

If <u>start time para</u> - <u>meter</u> is empty	then the start time defaults to 00:00:00.	This only applies to the Work History Adapter, and only if the start and end dates are the same.
If <u>end time para</u> - <u>meter</u> is empty	then the end time defaults to the current time.	This only applies to the Work History Adapter, and only if the start and end dates are the same.
If a <u>date range</u> is not entered	then the Job defaults to the date of the last successful run.	None
If it is the very first execution and no dates are specified	records for all dates will be extracted.	None

Using Multiple Values

<u>MIMPORTANT:</u> If you are using multiple values, you should not exceed 500 values.

Multiple values can be entered into the parameters using comma separated values. For example, if you wanted to extract data from Equipment Classes M, S, and A, the equipment class parameter would look like the following: **<EQUIPMENT_CLASS>** *M,S,A.* **<EQUIPMENT_CLASS>**. Comma separated values can be used with the following parameters:

- Plants
- Equipment numbers
- Equipment categories
- Equipment classes
- Equipment Types
- Functional Location Numbers
- Functional Location Categories
- Function Location Classes
- Function Location Types
- Order System Status
- Order user statuses
- Notification system statuses
- Notification user statuses

Overview of APM Connect


- Notification Numbers
- Notification type
- Work Order type
- Work Order numbers
- Maintenance Plans

Reference Information: SAP Adapters

This topic provides a listing of all detailed reference information provided for the SAP Adapters, such as command syntax, specifications, and table/field descriptions.

SAP Adapter Data Model

The following diagram shows how families used by the APM Connect SAP Adapters are related to one another:



Note: In the diagram, boxes represent entity families and arrows represent relationship families that are configured in the baseline database. You can determine the direction of the each relationship definition from the direction of the arrowhead: the box from which the arrow originates is the predecessor, and the box to which the arrow head points is the successor.

Like all GE Digital APM modules, the GE Digital APM SAP Adapters feature consists of entity families, relationship families, and business rules. When attempting to understand and make use of the SAP Adapters functionality, it can be helpful to visualize the SAP Adapters data model.

Because you should already be familiar with the concept of records and viewing records in the GE Digital APM Record Manager, as you attempt to get your bearings in the SAP Adapters feature, it may be useful to remember that the SAP Adapters feature simply lets you create, view, and manage records.

Each adapter is responsible for creating or updating one or more records that are displayed in the image. For example, when you run the Equipment Extraction Interface, Equipment records are created or updated.

Note: Although, the data model image does not show the relationship, Equipment and Functional Location records are also linked to Site Reference records.

About Site Filtering in the EAM Adapters

<u>MPORTANT</u>: Site Reference records must preexist in your GE Digital APM system, before you can use the EAM Adapters to populate the Site Reference Key. Additionally, the site entered into the context file must match the exact value in the corresponding Site Reference record.

<u>MPORTANT</u>: The user who is running the EAM Adapters jobs must be assigned, in GE Digital APM, to the site to which the records being loaded will be assigned. Additionally, the credentials for that user must be entered into the context file. If the user is not a member of the appropriate site, then the data load will fail, and an error message will appear.

The EAM Adapters are used to populate the Site Reference on Equipment, Functional Location, and Work History records in GE Digital APM. The adapters populate the MI_SITE_KEY system field with the ENTY_KEY system field associated with the Site Reference value to be populated. On asset records, the Site Reference is stored in the MI_SITE_KEY field, a system field in GE Digital APM. The EAM Adapters use the Site Name (MI_SITE_NAME) to translate the value to the corresponding Site Reference Key and populate the MI_SITE_KEY field; therefore, you do not need to know the key to be able to populate the site reference. This functionality is important because this value can change from one database to another.

When records are loaded using the Equipment, Function Location, and Work History Adapters, the system will assign the Site Reference Key (MI_SITE_KEY) to the assets using the value designated in the context file context file. The following parameters are used to designate the Site Reference Key value:

- SITE_REFERENCE_EQUIP: Used to populate the Site Reference Key on Equipment records being loaded into GE Digital APM. The Site Reference Key determines the Site to which the Equipment record(s) will be assigned.
- SITE_REFERENCE_FLOC: Used to populate the Site Reference Key on Functional Location records loaded into GE Digital APM. The Site Reference Key determines Site to which the Functional Location record(s) will be assigned.

Note: The values entered into these parameters should match, because Equipment records are linked to Functional Location records. Therefore, they should have the same site.

These parameters accept three types of values to determine the site reference value.

- a. **Site Name:** You can enter the site name directly as defined on the preexisting Site Reference record (i.e., Site 100).
- b. **Column Name:** You can enter a column value between two pound symbols (#) to set the site reference. The following columns can be used:

- · SAP columns:
 - MI_EQUIP000_SAP_SYSTEM_C
 - MI_EQUIP000_MAINT_PLANT_C
 - MI_FNCLOC00_MAINT_PLNT_C
 - MI_FNCLOC00_SAP_SYSTEM_C
- Maximo columns:
 - MI_FNCLOC00_SITE_C
 - MI_EQUIP000_SITE_C

For example, if you wanted to use your SAP maintenance plant field as your GE Digital APM site reference, you would enter #MI_EQUIP000_MAINT_PLANT_C#.

c. **Null:** You can leave the value as null. The record will be a global record if a Site Reference value is not mapped in between the tags.

If the assets being loaded into GE Digital APM are global records, meaning they will not be filtered according to site, then the Site Reference parameters can be left blank. When records are loaded with a null values in their Site Reference parameters, those created asset records will be designated as Global.

After the adapters are run, records designated to be transferred into GE Digital APM will be assigned to the site defined in the Site Reference parameters.

In addition to Equipment and Functional Location records loaded by the EAM adapters, Work History records and shell records are impacted by site reference functionality as detailed in the following table.

Action	Result
If the Work History Adapter is run after the Equipment or Functional Location Adapter	The Work History records will inherit the Site Reference Key of their parent Functional Loca- tion or Equipment records.
If the Work History Adapter is run before the Equipment or Functional Location Adapter	The Site Reference Key will inherited from the shell record that will be created for Equipment and Functional Location.
If a shell record is created while loading data	The Site Reference Key will be the value set in the context parameters.

Note: If you are using multiple SAP Systems, you must set up a context file for each system, and then designate the appropriate site(s) for each EAM Systems.

Family Field Descriptions

This topic provides a list of all detailed reference information provided for Family Field Descriptions, such as command syntax, specifications, and table/field descriptions.

CMMS Characteristic

CMMS Characteristic records are used by the SAP Adapters to facilitate data extracts and loads to and from SAP.

This topic provides an alphabetical list and description of the fields that exist for the CMMS Characteristic. The information in the table reflects the baseline state and behavior of these fields.

Field	Data Type	Description	Behavior and Usage
Characteristic Description	Character	The description of the characteristic (as it is defined in the SAP system).	This field is disabled.
Characteristic Name	Character	The ID of the characteristic (as it is defined in the SAP system).	On the datasheet, the value in this field is formatted as a hyperlink, which you can select to open the CMMS Characteristic by itself, outside of the context of its master CMMS Classification record. This field is disabled.
Class Group	Character	The SAP class group to which this characteristic belongs.	The value in this field is set automatically, and this field is disabled.
Classification	Character	The clas- sification to which this characteristic belongs.	On the datasheet, the value in this field is formatted as a hyperlink, which you can select to open the CMMS Classification record representing the classification to which this characteristic belongs. This field is disabled.

CMMS Sys- tem ID	Character	The ID of the SAP System from which this characteristic will be extracted.	This field is populated automatically and used internally by the GE Digital APM system. This field is not available on the baseline datasheets.
Extract From CMMS Sys- tem	Boolean	A value that identifies whether or not this characteristic will be extracted.	On the datasheet, you can select this check box if you want to extract this characteristic.

CMMS Classification

CMMS Classification records are available on the baseline Classification Type Classifications master-detail datasheet, the table explains how these fields behave when you are viewing CMMS Classification records in the context of this master-detail record.

This topic provides an alphabetical list and description of the fields that exist for the CMMS Classification family. The information in the table reflects the baseline state and behavior of these fields.

Field	Data Type	Description	Behavior and Usage
Class Group	Character	The SAP class group to which this classification belongs.	The value in this field is set automatically, and this field is disabled.
Classification	Character	The ID of the classification (as it is defined in the SAP system).	On the datasheet, the value in this field is formatted as a hyperlink, which you can select to see all of the characteristics that belong to this classification.
			This field is disabled.
Classification Description	Character	The description of the classification (as it is defined in the SAP system).	This field is disabled.
CMMS Sys- tem	Number	This value is used internally by the GE Digital APM system.	This field is not available on the baseline datasheets.
CMMS Sys- tem ID	Character	The value in the System ID field in the EAM System record whose Name field contains the value that is stored in the CMMS System field in this record.	This field is populated automatically and used internally by the GE Digital APM system. This field is not available on the baseline datasheets.

Extract From CMMS Sys- tem	Logical	A value that identifies whether or not characteristics for this classification will be extracted from the SAP system.	On the datasheet, you can select this check box if you want to extract characteristics belonging to this classification.
Internal Clas- sification Number	Character	This value is used internally by the GE Digital APM system.	The value in this field is set automatically, and this field is disabled.

CMMS Classification Type

CMMS Classification Type records are used by the SAP Adapters to facilitate data extracts and loads to and from SAP.

This topic provides an alphabetical list and description of the fields that exist for the CMMS Classification Type. The information in the table reflects the baseline state and behavior of these fields.

Field	Data Type	Description	Behavior and Usage
Classification Type	Character	The item whose characteristics will be extracted.	On the datasheet, this field displays a list, from which you can select one of the following values: • Equipment • Functional Location This field is required.
Classification Type Code	Character	A value that is used internally by the GE Digital APM system.	This value is set automatically. This field is not available on the baseline datasheets.
CMMS Sys- tem	Number	The SAP system from which characteristics will be extracted.	On the datasheet, the CMMS System list contains the values that are stored in the Name field in all EAM System records. The list is pop- ulated automatically with the value in the Name field in the EAM System record whose Default EAM System field contains the value True.

CMMS Sys- tem ID	Character	The value in the System ID field in the EAM System record whose Name field contains the value that you selected in CMMS System list in this CMMS Classification Type record.	This field is populated automatically and used internally by the GE Digital APM system. This field is not avail- able on the baseline datasheets.
---------------------	-----------	--	--

EAM System

EAM System records are used to store information about your SAP Systems to facilitate data extracts and loads to and from SAP.

When you transfer data from GE Digital APM to your EAM during any of the following workflows, the GE Digital APM system uses EAM System records to determine which EAM system to use:

- <u>Creating or updating SAP Notifications from GE Digital APM Recommendation</u> records.
- <u>Creating or updating SAP Confirmations from GE Digital APM Confirmation</u> records.
- Creating SAP Orders from GE Digital APM Task records.

In addition, EAM System records are used by the Equipment Characteristics Extraction Adapter and the Functional Location Characteristics Extraction Adapter in both of the following workflows:

- When you create <u>CMMS Classification Type records</u>, EAM System records are used to determine which EAM system information to use to populate the CMMS System ID field.
- When you <u>refresh the GE Digital APM system to reflect the current SAP classifications and characteristics</u>, EAM System records are used to determine the EAM system in which to look for the current classifications and characteristics.

This topic provides an alphabetical list and description of the fields that exist for the SAP System family and appear on the baseline SAP System datasheet. The information in the table reflects the baseline state and behavior of these fields.

This family is not enabled for site filtering, which means that records in this family can be accessed by any user with the appropriate license and family privileges. See the Site Filtering section of the documentation for more information.

Field	Data Type	Description	Behavior and Usage
Connection String	Character	The connection information for the SAP system.	In new EAM System records, you will need to delete all angle brackets and: Replace the text SAP_SERVER_IP with the IP address of the SAP Server. Replace the text SAP_SYSTEM_ NUMBER with the SAP System number. Replace the text SAP_CLIENT_ NUMBER with the SAP Client number.

Connection Type	Character	The type of connection that will be used to connect to the EAM system.	This field available on the SAP System for RCMO datasheet, and is not enabled by default. The default and recommended value is RFC. This connection type uses a RestFUL web service call as an intermediary between SAP and GE Digital APM, thereby avoiding RFC calls directly between GE Digital APM and your SAP server.
			the connection type to <i>RFC Direct</i> . Changing this value will bypass APM Connect and use a direct RFC connection when connecting your APM system and your SAP system.
Default EAM Sys- tem?	Logical	A value that indicates whether this EAM system should be used by default when transferring data between your GE Digital APM system and your SAP system.	On the datasheet, you can select the check box to identify this SAP system as the Default EAM System.
Encrypted Password	Character	The password to the SAP system.	On the datasheet, you can select the button to display the Enter SAP Sys- tem Password dialog box, where you can type the desired password. The password that you type will be encryp- ted and displayed as asterisks on the datasheet.
ITS URL	Character	The URL to the ITS Server.	In new EAM System records, you will need to delete the angle brackets and replace the textits_or_integrated_its_ server_url with the appropriate URL.

Name	Character	The name of the SAP system.	You can type any name, but we recommend that you use the format <sysid>-<client>, where <sysid> is the System ID of the SAP system and <client> is the Client number. By doing so, the value in the Name field will match the value that will be populated automatically in the System ID field.</client></sysid></client></sysid>
System ID	Character	The ID of the SAP system.	This field is populated automatically after you test the connection to the SAP system using the Test Connection link on the Associated Pages menu. Specifically, the System ID field is populated automatically with the name of the SAP system, using the format <sysid>-<client>, where <sysid> is the System ID of the SAP system and <client> is the Client number.</client></sysid></client></sysid>
User ID	Character	The User ID of a user that can log into the SAP system.	None.

Technical Characteristic

Technical Characteristics records are used to store information about your SAP Technical Characteristics to facilitate data extracts and loads to and from SAP.

This topic provides an alphabetical list and description of the fields that exist for the Technical Characteristic family and appear on the baseline SAP System datasheet. The information in the table reflects the baseline state and behavior of these fields.

Field	Data Type	Description	Behavior and Usage
Name	Character	The name of the characteristic.	None
Value	Character	The value assigned to the characteristic.	If multiple values are assigned to a characteristic in SAP, all of those values will be displayed in the Value field, separated by commas.

SAP Transactions-Quick Reference

The following table provides a list of SAP transactions and their functions:

This transaction:	Lets you:
/n/MIAPM/MIPRO	View a list of GE Digital APM-specific steps that can be performed in SAP.
/n/MIAPM/MANAGE_ PARAMS	Access and manage the /MIAPM/PARAMS table.
/n/MIAPM/MANAGE_ PI_CNF	Access and manage the /MIAPM/PI_PARAMS table, where you can specify your PI Server (e.g., name and port number).
/n/MIAPM/MANAGE_ TSKCNF	Access the /MIAPM/TASK_CNF table.
SM37	Check the status of a background process.
IW43	Validate SAP Confirmations against that data in GE Digital APM Confirmation records.

SAP Adapter Mappings

This topic provides a listing of all SAP Adapter Mapping Topics.

SAP Equipment Mappings

The following table explains the SAP fields that are used to populate the baseline Equipment fields when you extract SAP Equipment to create Equipment records in GE Digital APM:

GE Digital APM Fam- ily ID	GE Digital APM Field ID	GE Digital APM Field Cap- tion	SAP Table	SAP Field ID	SAP Field Cap- tion
MI_ EQUIP000	MI_ EQUIP000_ CAT_ PROF_C	Catalog Profile	EQUZ	RBNR	Catalog Profile
MI_ EQUIP000	MI_ EQUIP000_ CAT_ PROF_ DESC_C	Catalog Profile Description	T352B_T	RBNRX	Catalog Profile Description
MI_ EQUIP000	MI_ EQUIP000_ CHANGE_ DATE_D	CMMS Last Changed Date	EQUI	AEDAT	SAP Last Changed Date
MI_ EQUIP000	MI_ EQUIP000_ CONSTN_ TYP_C	Construction Type	EQUZ	SUBMT	Construction Type
MI_ EQUIP000	MI_ EQUIP000_ CONSTN_ TYP_DESC_ C	Construction Type Descrip- tion	MAKT	MAKTX	Construction Type Descrip- tion
MI_ EQUIP000	MI_ EQUIP000_ CREATE_ DATE_D	CMMS Creation Date	EQUI	ERDAT	SAP Creation Date
MI_ EQUIP000	MI_ EQUIP000_ CRITI_IND_ C	Criticality Indicator	ILOA	ABCKZ	Criticality Indic- ator

MI_ EQUIP000	MI_ EQUIP000_ CRITI_IND_ DESC_C	Criticality Indic- ator Descrip- tion	T370C_T	ABCTX	Criticality Indic- ator Descrip- tion
MI_ EQUIP000	MI_ EQUIP000_ EQUIP_ID_ C	Equipment ID	EQUI	EQUNR	Equipment ID
MI_ EQUIP000	MI_ EQUIP000_ EQUIP_ LNG_ DESC_T	Equipment Long Descrip- tion	EQUI	Retrieved using FM READ_TEXT with ID=LTXT, OBJECT=EQUI	Equipment Long Descrip- tion
MI_ EQUIP000	MI_ EQUIP000_ EQUIP_ SHRT_ DESC_C	Equipment Short Descrip- tion	EQKT	EQKTX	Equipment Short Descrip- tion
MI_ EQUIP000	MI_ EQUIP000_ EQUIP_ TECH_ NBR_C	Equipment Technical Num- ber	EQUZ	TIDNR	Equipment Technical Num- ber
MI_ EQUIP000	MI_ EQUIP000_ EQUIP_ VNDR_C	Equipment Vendor	EQUI	ELIEF	Equipment Vendor
MI_ EQUIP000	MI_ EQUIP000_ FNC_LOC_ C	Functional Location	ILOA	TPLNR	Functional Location
MI_ EQUIP000	MI_ EQUIP000_ FNC_LOC_ DESC_C	Functional Location Description	IFLOTX	PLTXT	Functional Location Description
MI_ EQUIP000	MI_ EQUIP000_ INV_NO_C	Inventory Num- ber	EQUI	INVNR	Inventory Num- ber

MI_ EQUIP000	MI_ EQUIP000_ MAIN_ WRK_CN_ DESC_C	Main Work Center Descrip- tion	CRTX	KTEXT	Main Work Center Descrip- tion
MI_ EQUIP000	MI_ EQUIP000_ MAIN_ WRK_CNR_ C	Main Work Center	CRHD	ARBPL	Main Work Center
MI_ EQUIP000	MI_ EQUIP000_ MFR_C	Manufacturer	EQUI	HERST	Manufacturer
MI_ EQUIP000	MI_ EQUIP000_ MOD_NO_ C	Model Number	EQUI	TYPBZ	Model Number
MI_ EQUIP000	MI_ EQUIP000_ OBJ_TYP_C	Object Type	EQUI	EQART	Object Type
MI_ EQUIP000	MI_ EQUIP000_ OBJ_TYP_ DESC_C	Object Type Description	T370K_T	EARTX	Object Type Description
MI_ EQUIP000	MI_ EQUIP000_ PLANG_ GRP_C	Planner Group	EQUZ	INGRP	Planner Group
MI_ EQUIP000	MI_ EQUIP000_ PLANG_ GRP_ DESC_C	Planner Group Description	T024I	INNAM	Planner Group Description
MI_ EQUIP000	MI_ EQUIP000_ PLNNG_ PLNT_C	Planning Plant	EQUZ	IWERK	Planning Plant

MI_ EQUIP000	MI_ EQUIP000_ PLNNG_ PLNT_ DESC_C	Planning Plant Description	T001W	NAME1	Planning Plant Description
MI_ EQUIP000	MI_ EQUIP000_ PO_NO_C	Purchase Order Number	EQBS	KDAUF	Purchase Order Number
MI_ EQUIP000	MI_ EQUIP000_ PRCH_D	Purchase Date	EQUI	ANSDT	Purchase Date
MI_ EQUIP000	MI_ EQUIP000_ PRT_NO_C	Part Number	EQUZ	MAPAR	Part Number
MI_ EQUIP000	MI_ EQUIP000_ SAP_ CATEG_C	Category	EQUI	EQTYP	SAP Category
MI_ EQUIP000	MI_ EQUIP000_ SAP_ CATEG_ DESC_C	Category Description	T370U	TYPTX	SAP Category Description
MI_ EQUIP000	MI_ EQUIP000_ SAP_ CLASS_C	SAP Class	KLAH	CLASS	SAP Class
MI_ EQUIP000	MI_ EQUIP000_ SAP_ CLASS_ DESC_C	SAP Class Description	SWOR	KSCHL	SAP Class Description
MI_ EQUIP000	MI_ EQUIP000_ SAP_ SYSTEM_C	CMMS System	<sy-sid> + <sy-mandt></sy-mandt></sy-sid>		Name of SAP R/3 System - R/3 System, cli- ent number from logon
MI_ EQUIP000	MI_ EQUIP000_ SN_C	Equipment Serial Number	EQUI	SERGE	Serial Number

MI_ EQUIP000	MI_ EQUIP000_ SYS_ST_C	System Status	TJ02T	TXT04	System Status
MI_ EQUIP000	MI_ EQUIP000_ SZ_C	Size/Dimension	EQUI	GROES	Size/Dimension
MI_ EQUIP000	MI_ EQUIP000_ TECH_ DRW_NO_ C	Technical Drawing Number	EQUI	HZEIN	Technical Drawing Number
MI_ EQUIP000	MI_ EQUIP000_ VLD_FRM_ DAT_D	Valid From Date	EQUZ	DATAB	Valid From Date
MI_ EQUIP000	MI_ EQUIP000_ WBS_ ELMNT_C	WBS Element	ILOA	POST1	WBS Element
MI_ EQUIP000	MI_ EQUIP000_ WRNTY_ EXPR_D	Warranty Expired Date	BGMKOBJ	GWLEN	Warranty Expired Date
MI_ EQUIP000	MI_ EQUIP000_ YR_ CONSTRD_ N	Year Con- structed	EQUI	BAUJJ	Year Con- structed
MI_ EQUIP000	MI_ EQUIP000_ MAINT_ PLANT_C	Maintenance Plant	ILOA	SWERK	Maintenance Plant
MI_ EQUIP000	MI_ EQUIP000_ MAINT_ PLANT_ DESC_C	Maintenance Plant Descrip- tion	T001W	NAME1	Maintenance Plant Descrip- tion
MI_ EQUIP000	MI_ EQUIP000_ PLANT_ SECTION_C	Plant Section	ILOA	BEBER	Plant Section

MI_ EQUIP000	MI_ EQUIP000_ PLANT_ SECT_ DESC_C	Plant Section Description	T357	FING	Plant Section Description
MI_ EQUIP000	MI_ EQUIP000_ SORT_ FIELD_C	Sort Field	ILOA	EQFNR	Sort Field

SAP Functional Location Mappings

The following table explains the SAP fields that are used to populate the baseline Functional Location fields when you extract SAP Functional Locations to create Functional Location records in GE Digital APM:

GE Digital APM Fam- ily ID	GE Digital APM Field ID	GE Digital APM Field Caption	SAP Table	SAP Field	SAP Field Caption
MI_ FNCLOC00	MI_FNCLOC00_ BUS_AREA_C	Business Area	ILOA	GSBER	Business Area
MI_ FNCLOC00	MI_FNCLOC00_ BUS_AREA_D_C	Business Area Descrip- tion	TGSBT	GTEXT	Business Area Description
MI_ FNCLOC00	MI_FNCLOC00_ CAT_PROF_C	Catalog Pro- file	IFLOT	RBNR	Catalog Pro- file
MI_ FNCLOC00	MI_FNCLOC00_ CAT_PROF_D_C	Catalog Pro- file Descrip- tion	T352B_ T	RBNRX	Catalog Pro- file Descrip- tion
MI_ FNCLOC00	MI_FNCLOC00_ CATEG_C	Category	IFLOT	FLTYP	Category
MI_ FNCLOC00	MI_FNCLOC00_ CATEG_D_C	Category Description	T370F_ T	TYPTX	Category Description
MI_ FNCLOC00	MI_FNCLOC00_ CHANGE_ DATE_D	CMMS Last Changed Date	IFLOT	AEDAT	SAP Last Changed Date
MI_ FNCLOC00	MI_FNCLOC00_ CO_AREA_C	CO Area	ILOA	KOKRS	Controlling Area
MI_ FNCLOC00	MI_FNCLOC00_ CO_AREA_D_C	CO Area Description	TKA01	BEZEI	Controlling Area Descrip- tion
MI_ FNCLOC00	MI_FNCLOC00_ CO_CD_C	Company Code	ILOA	BUKRS	Company Code
MI_ FNCLOC00	MI_FNCLOC00_ CO_CD_D_C	Company Code Description	T001	BUTXT	Company Code Descrip- tion

					Constr Type
MI_ FNCLOC00	MI_FNCLOC00_ CONST_TYP_C	Construction Type	IFLOT	SUBMT	Material of Object
MI_ FNCLOC00	MI_FNCLOC00_ CONST_TYP_ DESC_C	Construction Type Descrip- tion	MAKT	MAKTX	Constr Type Material of Object Desc
MI_ FNCLOC00	MI_FNCLOC00_ CREATE_DATE_ D	CMMS Creation Date	IFLOT	ERDAT	SAP Creation Date
MI_ FNCLOC00	MI_FNCLOC00_ CRTCAL_IND_C	Criticality Indicator	ILOA	ABCKZ	ABC Indicator
MI_ FNCLOC00	MI_FNCLOC00_ CRTCAL_IND_ D_C	Criticality Indicator Description	T370C_ T	ABCTX	ABC Indicator Description
MI_ FNCLOC00	MI_FNCLOC00_ CST_CNR_C	Cost Center	ILOA	KOSTL	Cost Center
MI_ FNCLOC00	MI_FNCLOC00_ CST_CNR_D_C	Cost Center Description	CSKT	KTEXT	Cost Center Description
MI_ FNCLOC00	MI_FNCLOC00_ FNC_LOC_C	Functional Location	IFLOT	Computed from TPLNR using FM CONVERSION_ EXIT_TPLNR_ OUTPUT	FunctLocation
MI_ FNCLOC00	MI_FNCLOC00_ FNC_LOC_ DESC_C	Functional Location Description	IFLOTX	PLTXT	Description
MI_ FNCLOC00	MI_FNCLOC00_ FNC_LOC_ LNG_DESC_C	Functional Location Long Description	IFLOT	Retrieved using FM READ_TEXT with ID=LTXT, OBJECT=IFLOT	Long Text
MI_ FNCLOC00	MI_FNCLOC00_ INSTLD_ ALWBL_C	Installation Allowed	IFLOT	IEQUI	Installation Allowed
MI_ FNCLOC00	MI_FNCLOC00_ INTERNAL_ID_C	Functional Location Internal ID	IFLOT	TPLNR	FunctLocation

MI_ FNCLOC00	MI_FNCLOC00_ LOCAT_C	Location	ILOA	STORT	Location
MI_	MI_FNCLOC00_	Location	T.1006	LATENT	Location
FNCLOC00	LOCAT_DESC_C	Description	T499S	KTEXT	Description
MI_ FNCLOC00	MI_FNCLOC00_ MAINT_PLNT_C	Maintenance Plant	ILOA	SWERK	Maintenance Plant
MI_ FNCLOC00	MI_FNCLOC00_ MAINT_PLNT_ D_C	Maintenance Plant Description	T001W	NAME1	Maintenance Plant Descrip- tion
MI_ FNCLOC00	MI_FNCLOC00_ OBJ_TYP_C	Object Type	IFLO	EQART	Object Type
MI_ FNCLOC00	MI_FNCLOC00_ OBJ_TYP_ DESC_C	Object Type Description	T370K_ T	EARTX	Object Type Description
MI_ FNCLOC00	MI_FNCLOC00_ PLNNG_PLNT_ C	Planning Plant	IFLOT	IWERK	Planning Plant
MI_ FNCLOC00	MI_FNCLOC00_ PLNNG_PLNT_ D_C	Planning Plant Description	T001W	NAME1	Planning Plant Descrip- tion
MI_ FNCLOC00	MI_FNCLOC00_ PLNT_SECT_C	Plant Sec- tion	ILOA	BEBER	Plant Section
MI_ FNCLOC00	MI_FNCLOC00_ PLNT_SECT_D_ C	Plant Sec- tion Descrip- tion	T357	FING	Plant Section Description
MI_ FNCLOC00	MI_FNCLOC00_ ROOM_C	Room	ILOA	MSGRP	Room
MI_ FNCLOC00	MI_FNCLOC00_ SORT_FLD_C	Sort Field	ILOA	EQFNR	Sort Field
MI_ FNCLOC00	MI_FNCLOC00_ STRUC_INDIC_ C	Structure Indicator	IFLOT	TPLKZ	StrIndicator
MI_ FNCLOC00	MI_FNCLOC00_ SUPR_FNC_ LOC_C	Superior Function Location	IFLOT	TPLMA	SupFunctLoc

MI_ FNCLOC00	MI_FNCLOC00_ SYS_STATUS_C	System Status	TJ02T	TXT04	System Status
MI_ FNCLOC00	MI_FNCLOC00_ WRK_CNTR_C	Work Center	CRHD	ARBPL	Work Center
MI_ FNCLOC00	MI_FNCLOC00_ WRK_CNTR_ DESC_C	Work Center Description	CRTX	KTEXT	Work Center Description
MI_ FNCLOC00	MI_FNCLOC00_ PLANNER_ GROUP_C	Planner Group	IFLOT	INGRP	Planner Group
MI_ FNCLOC00	MI_FNCLOC00_ PLANNER_ GRP_DESC_C	Planner Group Description	T024I	INNAM	Planner Group Description
MI_ FNCLOC00	MI_FNCLOC00_ SAP_CLASS_C	Class	KLAH	CLASS	Class
MI_ FNCLOC00	MI_FNCLOC00_ SAP_CLASS_ DESC_C	Class Description	SWOR	KSCHL	Class Descrip- tion

SAP Work History Mappings

The following tables explain the SAP fields that are used to populate the baseline Work History fields when you extract Orders and Notifications from SAP. The tables are divided into sections, depending on the source of the Work History records. Keep in mind that Work History records can be created from:

- · Orders with Notifications
- Orders without associated Notifications
- Notifications without associated Orders

Values Mapped to Records that were Created from Orders with Notifications

GE Digital APM Field ID	GE Digital APM Field Caption	SAP Table	SAP Field ID	SAP Field Caption
MI_EVWKHIST_ ACT_LABOR_ TIME_N Note: The value in the Actual Labor field is cal- culated as the sum of all actual hours across all Oper- ations that are associated with the Order (in the SAP user interface, this value is visible in the Actual Work text box on the Act. Data tab of the Oper-	Actual Labor	AFVV	ISMNW	Actual Work
ation).				

MI_EVWKHIST_ ASMBLY_C	Assembly	VIAUFKST	BAUTL	Assembly
MI_EVWKHIST_ ASMBLY_DESC_C	Assembly Description	MAKT	MAKTX	Material Description
MI_EVWKHIST_ ASST_TECH_ID_C	Asset Tech ID	EQUZ	TIDNR	Technical identification number
MI_EVWKHIST_ BRKDN_IND_F	Breakdown Indicator	VIQMEL	MSAUS	Breakdown Indicator
MI_EVWKHIST_ SAP_SYSTEM_C	CMMS Sys- tem	SY-HOST + "-" + SY-MANDT	N/A	Name of SAP R/3 System - R/3 System, client num- ber from logon
MI_EVWKHIST_ EFFCT_CD_C	Effect Code	VIQMEL	AUSWK	Effect on Operation
MI_EVWKHIST_ EFFCT_DESC_C	Effect Description	T357A_T	AUSWKT	Text - Effect on Oper- ation
MI_EVWKHIST_ ASST_CTGRY_ DESC_C	Equipment Category Description	T370U	typtx	Equipment category description
MI_EVWKHIST_ ASST_CL_DESC_C	Equipment Class Description	SWOR	KSCHL	Keywords
MI_EVENT_ASST_ ID_CHR	Equipment ID	VIAUFKST/OBJK	EQUNR	Equipment number
MI_EVENT_ASST_ DESC_CHR	Equipment Short Description	EQKT	EQKTX	Description of technical object

MI_EVWKHIST_ ASST_TYP_DESC_C	Equipment Type Descrip- tion	T370K_T	EARTX	Text for Object Type
MI_EVWKHIST_ EST_LABOR_ TIME_N				
Note: The value in the Estimated Labor field is calculated as the sum of all planned hours across all Operations that are associated with the Order (in the SAP user Adapter, this value is visible in the Work text box on the Internal section of the Operation).	Estimated Labor	AFVV	ARBEI	Work involved in the activity
MI_EVWKHIST_ EVENT_DATE_ DESC_C	Event Date Description	Populated with static value "Order Actual Start Date" if notification is not assigned to work order. If notification assigned to work order then it has value "Notification Date"	N/A	N/A

MI_EVENT_ID	Event ID	VIQMEL, VIAUFKST	QMNUM, AUFNR (Com- binaiton of WH- QMNUM- AUFNR)	Notification Number - Order Num- ber
MI_EVENT_LNG_ DSC_TX	Event Long Description	QMEL, AUFK	LTXT, KOPF	Notification long text - work Order long text
MI_EVENT_SHRT_ DSC_CHR	Event Short Description	VIQMEL	QMTXT	Short Text
MI_EVENT_STRT_ DT	Event Start Date	VIQMEL	QMDAT, MZEIT	Date/Time of Notification
MI_EVENT_TYP_ CHR	Event Type	Populated with static value of "Work History"	N/A	N/A
MI_EVWKHIST_ FAILR_MODE_CD_ C	Failure Mode Code	VIQMEL	QMCOD	Coding
MI_EVWKHIST_ FAILR_MODE_ DESC_C	Failure Mode Description	QPCT	KURZTEXT	Short Text for Code
MI_EVENT_LOC_ ID_CHR	Location ID	VIQMEL/OBJK	TPLNR	Functional Location
MI_EVENT_LOC_ SHRT_DESC_CHR	Location Short Description	IFLOTX	PLTXT	Description of functional location
MI_EVWKHIST_ MAINT_COMPL_D	Maintenance Completion Date	VIAUFKST	GETRI, GEUZI	Actual finish date/time

MI_EVWKHIST_ MAINT_CST_N	Maintenance Cost	PMCO	Σ(WRT00 - WRT16)	Sum of (Period value in ledger cur- rency)
MI_EVWKHIST_ MAINT_CST_ UOM_C	Maintenance Cost UOM	PMCO	COCUR	Maintenance Cost UOM
MI_EVWKHIST_ MAINT_START_D	Maintenance Start Date	VIAUFKST	GSTRI, GSUZI	Actual start date/time
MI_EVWKHIST_ MECH_DWN_ TIME_N	Mechanical Down Time	VIQMEL	AUSZT	Breakdown Duration
MI_EVWKHIST_ MECH_AVAIL_D	Mechanically Available Date	VIQMEL	AUSBS, AUZTB	End of Mal- function (Date/Time)
MI_EVWKHIST_ MECH_UNAVL_D	Mechanically Unavailable Date	VIQMEL	AUSVN, AUZTV	Start of Mal- function (Date/Time)
MI_EVWKHIST_ OBJECT_ NUMBER_C	Object Num- ber	VIAUFKST	AUFNR	Work Order Object num- ber
MI_EVWKHIST_ ORDR_CALL_ NBR_C	Order Call Number	VIAUFKST	ABNUM	Maintenance plan call number
MI_EVWKHIST_ ORDR_CRT_DT_D	Order Creation Date	VIAUFKST	ERDAT, ERFZEIT	Created on Date/Time
MI_EVWKHIST_ ORDR_DESC_C	Order Description	VIAUFKST	KTEXT	Short text
MI_EVWKHIST_ ORDR_ID_C	Order ID	VIAUFKST	AUFNR	Order Num- ber

MI_EVWKHIST_ ORDR_CHNG_DT_ D	Order Last Change Date	VIAUFKST	AEDAT, AEZEIT	Change date/- time for Order Master
MI_EVWKHIST_ ORDR_MAINT_ ITEM_C	Order Main- tenance Item	VIAUFKST	WAPOS	Maintenance item
MI_EVWKHIST_ ORDR_MAINT_ PLAN_C	Order Main- tenance Plan	VIAUFKST	WARPL	Maintenance plan
MI_EVWKHIST_ ORDR_PM_ACT_C	Order PM Activity Type	VIAUFKST	ILART	Maintenance activity type
MI_EVWKHIST_ ORDR_PM_ACT_ DESC_C	Order PM Activity Type Description	T353I_T	ILATX	Description of main- tenance activ- ity type
MI_EVWKHIST_ ORDR_PRTY_C	Order Pri- ority	VIAUFKST	PRIOK	Priority
MI_EVWKHIST_ ORDR_PRTY_ DESC_C	Order Pri- ority Descrip- tion	T356_T	PRIOKX	Priority Text
MI_EVWKHIST_ ORDR_SYS_ COND_C	Order Sys- tem Condi- tion	VIAUFKST	ANLZU	Overall condition of technical system
MI_EVWKHIST_ ORDR_SYS_CND_ DES_C	Order Sys- tem Condi- tion Description	T357M_T	ANLZUX	Text on Oper- ating Condi- tion
MI_EVWKHIST_ ORDR_SYS_STAT_ C	Order Sys- tem Status	ТЈ02Т	TXT04	Individual status of an object (short form)

MI_EVWKHIST_ ORDR_TYP_CD_C	Order Type Code	VIAUFKST	AUART	Order Type
MI_EVWKHIST_ ORDR_TYP_DESC_ C	Order Type Description	T003P	TXT	Short Text
MI_EVWKHIST_ ORDR_USER_ STAT_C	Order User Status	ТЈЗОТ	TXT04	Individual status of an object (short form)
MI_EVWKHIST_ RQST_CRT_DT_D	Request Creation Date	VIQMEL	ERDAT, ERZEIT	Date/Time on which the record was created
MI_EVWKHIST_ RQST_DESC_C	Request Description	VIQMEL	QMTXT	Short Text
MI_EVWKHIST_ RQST_ID_C	Request ID	VIQMEL/OBJK	QMNUM/IHNUM	Notification Number
MI_EVWKHIST_ RQST_CHNG_DT_ D	Request Last Change Date	VIQMEL	AEDAT, AEZEIT	Date/Time of Last Change
MI_EVWKHIST_ RQST_PRTY_C	Request Pri- ority	VIQMEL	PRIOK	Priority
MI_EVWKHIST_ RQST_PRTY_ DESC_C	Request Pri- ority Descrip- tion	T356_T	PRIOKX	Priority Text
MI_EVWKHIST_ RQST_SYS_STAT_C	Request Sys- tem Status	ТЈ02Т	TXT04	Individual status of an object (short form)
MI_EVWKHIST_ RQST_TYP_CD_C	Request Type Code	VIQMEL	QMART	Notification Type

MI_EVWKHIST_ RQST_TYP_DESC_ C	Request Type Descrip- tion	TQ80_T	QMARTX	Notification Type Texts
MI_EVWKHIST_ RQST_USER_ STAT_C	Request User Status	ТЈЗОТ	TXT04	Individual status of an object (short form)
MI_EVENT_ASST_ CTGRY_CHR	SAP Cat- egory	EQUI	EQTYP	Equipment category
MI_EVENT_ASST_ CL_CHR	SAP Class	KLAH	CLASS	Class Num- ber
MI_EVENT_ASST_ TYP_CHR	SAP Type	EQUI	EQART	Type of Tech- nical Object
MI_EVWKHIST_ SUB_OBJECT_ NUM_C	Sub Object Number	VIAUFKST/OBJK	OBZAE	Object List Count

Values Mapped to Records that were Created without Notifications

GE Digital APM Field ID GE Digital APM Field Caption	SAP Table	SAP Field ID	SAP Field Caption
---	-----------	--------------	----------------------

MI_EVWKHIST_ ACT_LABOR_ TIME_N Note: The value in the Actual Labor field is calculated as the sum of all actual hours across all Operations that are associated with the Order (in the SAP user interface, this value is visible in the Actual work text box on the Act. Data tab of the Operation).	Actual Labor	AFVV	ISMNW	Actual work
MI_EVWKHIST_ ASMBLY_C	Assembly	VIAUFKST	BAUTL	Assembly
MI_EVWKHIST_ ASMBLY_DESC_C	Assembly Description	MAKT	MAKTX	Material Description
MI_EVWKHIST_ ASST_TECH_ID_C	Asset Tech ID	EQUZ	TIDNR	Technical identification number
MI_EVWKHIST_ BRKDN_IND_F	Breakdown Indicator	VIQMEL	MSAUS	Breakdown Indicator

MI_EVWKHIST_ SAP_SYSTEM_C	CMMS Sys- tem	SY-HOST + "-" + SY- MANDT	N/A	Name of SAP R/3 System - R/3 System, client num- ber from logon
MI_EVWKHIST_ EFFCT_CD_C	Effect Code	VIQMEL	AUSWK	Effect on Operation
MI_EVWKHIST_ EFFCT_DESC_C	Effect Description	T357A_T	AUSWKT	Text - Effect on Oper- ation
MI_EVWKHIST_ ASST_CTGRY_ DESC_C	Equipment Category Description	T370U	ТҮРТХ	Equipment category description
MI_EVWKHIST_ ASST_CL_DESC_C	Equipment Class Description	SWOR	KSCHL	Keywords
MI_EVENT_ASST_ ID_CHR	Equipment ID	VIAUFKST/OBJK	EQUNR	Equipment number
MI_EVENT_ASST_ DESC_CHR	Equipment Short Description	EQKT	EQKTX	Description of technical object
MI_EVWKHIST_ ASST_TYP_DESC_ C	Equipment Type Descrip- tion	T370K_T	EARTX	Text for Object Type

MI_EVWKHIST_ EST_LABOR_ TIME_N				
Note: The value in the Estimated Labor field is calculated as the sum of all planned hours across all Operations that are associated with the Order (in the SAP user Adapter, this value is visible in the Work text box on the Internal section of the Operation).	Estimated Labor	AFVV	ARBEI	Work involved in the activity
MI_EVWKHIST_ EVENT_DATE_ DESC_C	Event Date Description	Populated with static value "Order Actual Start Date" if notification is not assigned to work order. If notification assigned to work order then it has value "Notification Date"	N/A	N/A
MI_EVENT_ID	Event ID	VIAUFKST	AUFNR	Order Num- ber

MI_EVENT_LNG_ DSC_TX	Event Long Description	AUFK	Retrieved by calling FM READ_ TEXT with ID=LTXT, OBJECT- T=AUFK	Long Desc
MI_EVENT_ SHRT_DSC_CHR	Event Short Description	VIAUFKST/VIQMEL	KTEXT / QMTXT	Short text
MI_EVENT_STRT_ DT	Event Start Date	VIAUFKST/VIQMEL	GSTRI, GSUZI / QMDAT/MZEIT	Date, Time of Work Order / Noti- fication
MI_EVENT_TYP_ CHR	Event Type	Populated with static value of "Work History"	N/A	N/A
MI_EVWKHIST_ FAILR_MODE_ CD_C	Failure Mode Code	VIQMEL	QMCOD	Coding
MI_EVWKHIST_ FAILR_MODE_ DESC_C	Failure Mode Description	QPCT	KURZTEXT	Short Text for Code
MI_EVENT_LOC_ ID_CHR	Location ID	VIAUFKST/OBJK	TPLNR	Functional Location
MI_EVENT_LOC_ SHRT_DESC_CHR	Location Short Description	IFLOTX	PLTXT	Description of functional location
MI_EVWKHIST_ MAINT_COMPL_ D	Maintenance Completion Date	VIAUFKST	GETRI, GEUZI	Actual finish date/time
MI_EVWKHIST_ MAINT_CST_N	Maintenance Cost	РМСО	Σ(WRT00 - WRT16)	Sum of (Period value in ledger cur- rency)

MI_EVWKHIST_ MAINT_CST_ UOM_C	Maintenance Cost UOM	PMCO	COCUR	Maintenance Cost UOM
MI_EVWKHIST_ MAINT_START_D	Maintenance Start Date	VIAUFKST	GSTRI, GSUZI	Actual start date/time
MI_EVWKHIST_ MECH_DWN_ TIME_N	Mechanical Down Time	VIQMEL	AUSZT	Breakdown Duration
MI_EVWKHIST_ MECH_AVAIL_D	Mechanically Available Date	VIQMEL	AUSBS, AUZTB	End of Mal- function (Date/Time)
MI_EVWKHIST_ MECH_UNAVL_D	Mechanically Unavailable Date	VIQMEL	AUSVN, AUZTV	Start of Mal- function (Date/Time)
MI_EVWKHIST_ OBJECT_ NUMBER_C	Object Num- ber	VIAUFKST	AUFNR	Work Order Object num- ber
MI_EVWKHIST_ ORDR_CALL_ NBR_C	Order Call Number	VIAUFKST	ABNUM	Maintenance plan call number
MI_EVWKHIST_ ORDR_CRT_DT_ D	Order Creation Date	VIAUFKST	ERDAT, ERFZEIT	Date/Time on which the record was created
MI_EVWKHIST_ ORDR_DESC_C	Order Description	VIAUFKST	KTEXT	Short text
MI_EVWKHIST_ ORDR_ID_C	Order ID	VIAUFKST	AUFNR	Order Num- ber
MI_EVWKHIST_ ORDR_CHNG_ DT_D	Order Last Change Date	VIAUFKST	AEDAT, AEZEIT	Date/Time of Last Change

			1	1
MI_EVWKHIST_ ORDR_MAINT_ ITEM_C	Order Main- tenance Item	VIAUFKST	WAPOS	Maintenance item
MI_EVWKHIST_ ORDR_MAINT_ PLAN_C	Order Main- tenance Plan	VIAUFKST	WARPL	Maintenance plan
MI_EVWKHIST_ ORDR_PM_ACT_ C	Order PM Activity Type	VIAUFKST	ILART	Maintenance activity type
MI_EVWKHIST_ ORDR_PM_ACT_ DESC_C	Order PM Activity Type Description	T353I_T	ILATX	Description of main- tenance activ- ity type
MI_EVWKHIST_ ORDR_PRTY_C	Order Pri- ority	VIAUFKST	PRIOK	Priority
MI_EVWKHIST_ ORDR_PRTY_ DESC_C	Order Pri- ority Descrip- tion	T356_T	PRIOKX	Priority Text
MI_EVWKHIST_ ORDR_SYS_ COND_C	Order Sys- tem Condi- tion	VIAUFKST	ANLZU	Overall condition of technical system
MI_EVWKHIST_ ORDR_SYS_CND_ DES_C	Order Sys- tem Condi- tion Description	T357M_T	ANLZUX	Text on Operating Condition
MI_EVWKHIST_ ORDR_SYS_ STAT_C	Order Sys- tem Status	ТЈ02Т	TXT04	Individual status of an object (short form)
MI_EVWKHIST_ ORDR_TYP_CD_C	Order Type Code	VIAUFKST	AUART	Order Type

MI_EVWKHIST_ ORDR_TYP_ DESC_C	Order Type Description	T003P	TXT	Short Text
MI_EVWKHIST_ ORDR_USER_ STAT_C	Order User Status	ТЈЗОТ	TXT04	Individual status of an object (short form)
MI_EVWKHIST_ RQST_CRT_DT_D	Request Creation Date	VIQMEL	ERDAT, ERZEIT	Date/Time on which the record was created
MI_EVWKHIST_ RQST_DESC_C	Request Description	VIQMEL	QMTXT	Short Text
MI_EVWKHIST_ RQST_ID_C	Request ID	VIQMEL/OBJK	QMNUM/IHNUM	Notification Number
MI_EVWKHIST_ RQST_CHNG_ DT_D	Request Last Change Date	VIQMEL	AEDAT, AEZEIT	Date/Time of Last Change
MI_EVWKHIST_ RQST_PRTY_C	Request Pri- ority	VIQMEL	PRIOK	Priority
MI_EVWKHIST_ RQST_PRTY_ DESC_C	Request Pri- ority Descrip- tion	T356_T	PRIOKX	Priority Text
MI_EVWKHIST_ RQST_SYS_STAT_ C	Request Sys- tem Status	ТЈ02Т	TXT04	Individual status of an object (short form)
MI_EVWKHIST_ RQST_TYP_CD_C	Request Type Code	VIQMEL	QMART	Notification Type
MI_EVWKHIST_ RQST_TYP_ DESC_C	Request Type Descrip- tion	TQ80_T	QMARTX	Notification Type Texts

MI_EVWKHIST_ RQST_USER_ STAT_C	Request User Status	ТЈЗОТ	TXT04	Individual status of an object (short form)
MI_EVENT_ASST_ CTGRY_CHR	SAP Cat- egory	EQUI	EQTYP	Equipment category
MI_EVENT_ASST_ CL_CHR	SAP Class	KLAH	CLASS	Class Num- ber
MI_EVENT_ASST_ TYP_CHR	SAP Type	EQUI	EQART	Type of Tech- nical Object
MI_EVWKHIST_ SUB_OBJECT_ NUM_C	Sub Object Number	VIAUFKST/OBJK	OBZAE	Object List Count

Values Mapped to Records that were Created from Notifications without Associated Orders

GE Digital APM Field ID	GE Digital APM Field Caption	SAP Table	SAP Field ID	SAP Field Caption
MI_ EVWKHIST_ ASMBLY_C	Assembly	VIQMEL	BAUTL	Assembly
MI_ EVWKHIST_ ASMBLY_ DESC_C	Assembly Description	MAKT	MAKTX	Material Descrip- tion
MI_ EVWKHIST_ ASST_ TECH_ID_C	Asset Tech ID	EQUZ	TIDNR	Technical iden- tification number
MI_ EVWKHIST_ BRKDN_ IND_F	Breakdown Indicator	VIQMEL	MSAUS	Breakdown Indic- ator

MI_ EVWKHIST_ SAP_ SYSTEM_C	CMMS Sys- tem	SY-HOST + "-" + SY-MANDT	N/A	Name of SAP R/3 System - R/3 Sys- tem, client number from logon
MI_ EVWKHIST_ EFFCT_CD_ C	Effect Code	VIQMEL	AUSWK	Effect on Operation
MI_ EVWKHIST_ EFFCT_ DESC_C	Effect Description	T357A_T	AUSWKT	Text - Effect on Operation
MI_ EVWKHIST_ ASST_ CTGRY_ DESC_C	Equipment Category Description	T370U	TYPTX	Equipment cat- egory description
MI_ EVWKHIST_ ASST_CL_ DESC_C	Equipment Class Description	SWOR	KSCHL	Keywords
MI_EVENT_ ASST_ID_ CHR	Equipment ID	VIQMEL	EQUNR	Equipment number
MI_EVENT_ ASST_ DESC_CHR	Equipment Short Description	EQKT	EQKTX	Description of tech- nical object
MI_ EVWKHIST_ ASST_TYP_ DESC_C	Equipment Type Descrip- tion	T370K_T	EARTX	Text for Object Type

MI_ EVWKHIST_ EVENT_ DATE_ DESC_C	Event Date Description	Populated with static value of "Notification Date"	N/A	N/A
MI_EVENT_ ID	Event ID	VIQMEL	QMNUM	Notification Num- ber
MI_EVENT_ LNG_DSC_ TX	Event Long Description	QMEL	Retrieved by calling FM READ_TEXT with ID=LTXT, OBJECT=QMEL	Notification Long Desc
MI_EVENT_ SHRT_DSC_ CHR	Event Short Description	VIQMEL	QMTXT	Short Text
MI_EVENT_ STRT_DT	Event Start Date	VIQMEL	QMDAT, MZEIT	Date/Time of Noti- fication
MI_EVENT_ TYP_CHR	Event Type	Populated with static value of "Work History"	N/A	N/A
MI_ EVWKHIST_ FAILR_ MODE_CD_ C	Failure Mode Code	VIQMEL	QMCOD	Coding
MI_ EVWKHIST_ FAILR_ MODE_ DESC_C	Failure Mode Description	QPCT	KURZTEXT	Short Text for Code
MI_EVENT_ LOC_ID_ CHR	Location ID	VIQMEL	TPLNR	Functional Loca- tion

MI_EVENT_ LOC_SHRT_ DESC_CHR	Location Short Description	IFLOTX	PLTXT	Description of functional location
MI_ EVWKHIST_ MECH_ DWN_ TIME_N	Mechanical Down Time	VIQMEL	AUSZT	Breakdown Dur- ation
MI_ EVWKHIST_ MECH_ AVAIL_D	Mechanically Available Date	VIQMEL	AUSBS, AUZTB	End of Malfunction (Date/Time)
MI_ EVWKHIST_ MECH_ UNAVL_D	Mechanically Unavailable Date	VIQMEL	AUSVN, AUZTV	Start of Mal- function (Date/Time)
MI_ EVWKHIST_ OBJECT_ NUMBER_C	Object Num- ber	VIAUFKST	AUFNR	Work Order Object number
MI_ EVWKHIST_ RQST_CRT_ DT_D	Request Creation Date	VIQMEL	ERDAT, ERZEIT	Date/Time on which the record was created
MI_ EVWKHIST_ RQST_ DESC_C	Request Description	VIQMEL	QMTXT	Short Text
MI_ EVWKHIST_ RQST_ID_C	Request ID	VIQMEL	QMNUM	Notification Num- ber

MI_ EVWKHIST_ RQST_ CHNG_DT_ D	Request Last Change Date	VIQMEL	AEDAT, AEZEIT	Date/Time of Last Change
MI_ EVWKHIST_ RQST_ PRTY_C	Request Pri- ority	VIQMEL	PRIOK	Priority
MI_ EVWKHIST_ RQST_ PRTY_ DESC_C	Request Pri- ority Descrip- tion	T356_T	PRIOKX	Priority Text
MI_ EVWKHIST_ RQST_SYS_ STAT_C	Request Sys- tem Status	ТЈ02Т	TXT04	Individual status of an object (short form)
MI_ EVWKHIST_ RQST_TYP_ CD_C	Request Type Code	VIQMEL	QMART	Notification Type
MI_ EVWKHIST_ RQST_TYP_ DESC_C	Request Type Descrip- tion	TQ80_T	QMARTX	Notification Type Texts
MI_ EVWKHIST_ RQST_ USER_ STAT_C	Request User Status	ТЈЗОТ	TXT04	Individual status of an object (short form)
MI_EVENT_ ASST_ CTGRY_ CHR	SAP Cat- egory	EQUI	EQTYP	Equipment cat- egory

MI_EVENT_ ASST_CL_ CHR	SAP Class	KLAH	CLASS	Class Number
MI_EVENT_ ASST_TYP_ CHR	SAP Type	EQUI	EQART	Type of Technical Object
MI_ EVWKHIST_ SUB_ OBJECT_ NUM_C	Sub Object Number	VIAUFKST/OBJK	OBZAE	Object List Count

SAP Work History Detail Mappings

The following table explains the SAP fields that are used to populate the baseline Work History Detail fields when you extract Orders and Notifications from SAP:

Note: If a Technical Object in the object list is associated with a Notification that has items, separate Work History Detail records will be created for each of those items. The Work History Detail records will be linked to the Work History record that was created using that Technical

GE Digital APM Fam- ily ID	GE Digital APM Field ID	GE Digital APM Field Caption	SAP Table	SAP Field	SAP Field Caption
MI_ DTWKHIST	MI_DTWKHIST_ ASST_CLASS_C	Equipment Class	KLAH	CLASS	Class Number
MI_ DTWKHIST	MI_DTWKHIST_ ASST_CLASS_ DESC_C	Equipment Class Descrip- tion	SWOR	KSCHL	Keywords
MI_ DTWKHIST	MI_DTWKHIST_ ASST_CTGRY_C	Equipment Category	EQUI	EQTYP	Equipment cat- egory
MI_ DTWKHIST	MI_DTWKHIST_ ASST_CTGRY_ DESC_C	Equipment Category Description	T370U	TYPTX	Equipment cat- egory descrip- tion
MI_ DTWKHIST	MI_DTWKHIST_ ASST_ID_C	Equipment ID	VIQMEL	EQUNR	Equipment number
MI_ DTWKHIST	MI_DTWKHIST_ ASST_TYP_C	Equipment Type	EQUI	EQART	Type of Tech- nical Object
MI_ DTWKHIST	MI_DTWKHIST_ ASST_TYP_ DESC_C	Equipment Type Descrip- tion	T370K_T	EARTX	Text for Object Type
MI_ DTWKHIST	MI_DTWKHIST_ CAUSE_CD_C	Cause Code	QMUR	URCOD	Cause Code
MI_ DTWKHIST	MI_DTWKHIST_ CAUSE_DESC_C	Cause Description	QPCT	KURZTEXT	Short Text for Code
MI_ EVWKHIST	MI_DTWKHIST_ CHANGE_DATE_ D	CMMS Last Changed Date	VIAUFKS	AEDAT, AEZEIT	SAP Last Changed Date

MI_ DTWKHIST	MI_DTWKHIST_ CNDTN_CD_C	Condition Code	QMFE	FECOD	Problem
MI_ DTWKHIST	MI_DTWKHIST_ CNDTN_DESC_C	Condition Description	QPCT	KURZTEXT	Short Text for Code
MI_ EVWKHIST	MI_DTWKHIST_ CREATE_DATE_ D	CMMS Creation Date	VIAUFKS	ERDAT, ERZEIT	SAP Creation Date
MI_ DTWKHIST	MI_DTWKHIST_ DTL_NARTV_T	Detail Nar- rative	QMFE	LTXT	
MI_ DTWKHIST	MI_DTWKHIST_ EVNT_DTL_ DESC_C	Work History Detail Descrip- tion	VIQMEL	QMTXT	Short Text
MI_ DTWKHIST	MI_DTWKHIST_ EVNT_DTL_ID_C	Work History Detail ID	QMFE, VIQMEL	QMNUM, AUFNR, FENUM	Notification Number - Order Number
MI_ DTWKHIST	MI_DTWKHIST_ LOC_ID_C	Location ID	VIQMEL	TPLNR	Functional Location
MI_ DTWKHIST	MI_DTWKHIST_ MAINT_ACTN_ CD_C	Maintenance Action Code	QMMA	MNCOD	Activity Code
MI_ DTWKHIST	MI_DTWKHIST_ MAINT_ACTN_ DESC_C	Maintenance Action Description	QPCT	KURZTEXT	Short Text for Code
MI_ DTWKHIST	MI_DTWKHIST_ MAINT_ITEM_ CD_C	Maintainable Item Code	QMFE	OTEIL	Part of Object
MI_ DTWKHIST	MI_DTWKHIST_ MAINT_ITEM_ DESC_C	Maintainable Item Descrip- tion	QPCT	KURZTEXT	Short Text for Code
MI_ DTWKHIST	MI_DTWKHIST_ ORDR_ID_C	Order ID	viaufks	AUFNR	Order Number
MI_ DTWKHIST	MI_DTWKHIST_ RQST_ID_C	Request ID	VIQMEL	QMNUM	Notification Number
MI_ DTWKHIST	MI_DTWKHIST_ WRK_HISTRY_ ID_C	Work History ID	viaufks	QMNUM	Notification Number

MI_ MI_DTWKHIST_ MARKED_FOR_ DEL_F	Record marked for deletion	QMFE	KZLOESCH	Delete Data Record
------------------------------------	----------------------------------	------	----------	-----------------------

SAP Technical Characteristics Mappings

The following table explains the SAP fields that are used to populate the baseline Technical Characteristic fields when you extract SAP characteristics to create Technical Characteristic records in GE Digital APM.

GE Digital APM Field Name	GE Digital APM Field Name	SAP Table	SAP Field ID
Data Type	MI_TECHCHAR_TYPE_C	CABN	ATFOR
Length of Data Type	MI_TECHCHAR_NUM_ CHARS_N	CABN	ANZST
Number of Decimal Places	MI_TECHCHAR_NUM_ DEC_PLACES_N	CABN	ANZDZ
Description	MI_TECHCHAR_DESC_C	CABN	ATBEZ
Character Value	MI_TECHCHAR_CHAR_ VALUE_C	AUSP	ATWRT/ATFLB/ATFLV
Numeric Value	MI_TECHCHAR_ NUMERIC_VALUE_N	AUSP	ATWRT/ATFLB/ATFLV
		AUSP	ATWRT/ATFLB/ATFLV
Multiple Value	MI_TECHCHAR_MULTI_ VALUE_C	+	+
Characteristic		TCURC	ISOCD
		T006	MSEH6
CMMS System	MI_TECHCHAR_SAP_ SYSTEM_C	None	<sy-sid> + <sy- MANDT></sy- </sy-sid>
Name	MI_TECHCHAR_NAME_C	CABN	ATNAM
Currency Value	MI_TECHCHAR_CURR_ VALUE_N	AUSP	ATWRT/ATFLB/ATFLV
Equipment ID	MI_TECHCHAR_EQUIP_ ID_C	EQUI	EQUNR
Functional Loca- tion ID	MI_TECHCHAR_FLOC_ ID_C	IFLOT	TPLNR
Technical Char- acteristics ID	MI_TECHCHAR_ID_C	CABNT	ATINN

Unit of Meas-	eas- MI_TECHCHAR_UOM_C		ISOCD
urement	WII_TECHCHAR_OOW_C	T006	MSEH6
Restrictable Characteristic Indicator	MI_TECHCHAR_IS_ RESTRICTABLE_F	CABN	ATGLA
Technical Char- acteristic Value Description	MI_TECHCHAR_VALUE_ DESC_C	CABNT	ATBEZ
		AUSP	ATWRT/ATFLB/ATFLV
Interval Value	MI_TECHCHAR_	+	+
interval value	INTERVAL_VALUE_C	TCURC	ISOCD
		T006	MSEH6

SAP Work Management Mappings

The following table explains the SAP fields that are used to populate the baseline Work Management fields when you extract SAP characteristics to create Work Management records in GE Digital APM.

GE Digital APM Fam- ily ID	GE Digital APM Field ID	SAP Table	SAP Field	SAP Field Cap- tion	Mapping Formula
MI_ TASKCALB/MITASKINS- P	MI_TASK_ MAINT_ PLAN_NBR_ C	MPLA	WARPL	Maintenance Plan	WARPL
MI_ TASKCALB/MITASKINS- P	MI_TASK_ MAINT_ PLAN_ ITEM_NBR_ C	MPOS	WAPO-S	Maintenance item	WAPOS
MI_ TASKCALB/MITASKINS- P	MI_TASK_ TASK_LIST_ TYPE_C	PLKO	PLNTY	Task List Type	PLNTY
MI_ TASKCALB/MITASKINS- P	MI_TASK_ TASK_LIST_ GROUP_C	PLKO	PLNNR	Key for Task List Group	PLNNR
MI_ TASKCALB/MITASKINS- P	MI_TASK_ TASK_LIST_ GROUP_ CNTR_C	PLKO	PLNAL	Group Counter	PLNAL
MI_ TASKCALB/MITASKINS- P	MI_TASK_ OPERATIO- N_NBR_C	PLPO	VORNR	Oper- ation/Activity Number	VORNR
MI_ TASKCALB/MITASKINS- P	MI_TASK_ DESC_TX	VIMPO- S / PLKO	EQUN- R / TPLNR	Equipment / Functional Loca- tion	Con- catenate EQUNR or TPLNR with "-" and PLPO.LTXA- 1 + PLPO.LTXA- 2

MI_ TASKCALB/MITASKINS- P	MI_TASK_ID	PLPO	LTXA1, LTXA2	Oper- ation/Activity Number	LTXA1 + LTXA2
MI_ TASKCALB/MITASKINS- P	MI_TASK_ DESIR_ INTER_NBR	Null	Null	Null	Null
MI_ TASKCALB/MITASKINS- P	MI_TASK_ DESIR_ INTER_ UOM_C	Null	Null	Null	Null
MI_ TASKCALB/MITASKINS- P	MI_TASK_ MIN_INTER_ NBR	Null	Null	Null	Null
MI_ TASKCALB/MITASKINS- P	MI_TASK_ MIN_INTER_ UOM_C	Null	Null	Null	Null
MI_ TASKCALB/MITASKINS- P	MI_TASK_ MAX_ INTER_NBR	Null	Null	Null	Null
MI_ TASKCALB/MITASKINS- P	MI_TASK_ MAX_ INTER_ UOM_C	Null	Null	Null	Null
MI_ TASKCALB/MITASKINS- P	MI_TASK_ CHANGE_ DATE_D	PLPO	AEDAT	SAP Last Changed Date	AEDAT
MI_ TASKCALB/MITASKINS- P	MI_TASK_ CREATE_ DATE_D	PLPO	ANDAT	SAP Creation Date	ANDAT
MI_ TASKCALB/MITASKINS- P	MI_TASK_ MAINT_ PLANT_C	MPOS	SWERK	SAP Main- tenance Plant	SWERK
MI_ TASKCALB/MITASKINS- P	MI_TASK_ SAP_ SYSTEM_C	None	SY-SID, SY- MAND- T	SAP System	Con- catenate SY-SID and SY-MANDT

SAP Recommendation Mappings

The following table explains the Recommendation fields that are used to populate SAP Notification fields when you use the Notification Management Adapter.

GE Di- gital APM Field ID	GE Digital APM Field Caption	SA- P Tab- le ID	SA- P Fiel- d ID	BAPI Struc- ture	BAPI Field	SAP Field Cap- tion	Notes
MI_ REC_ SHORT_ DESCR_ CHR	Recom- mendation Headline	VIQM- EL	QMT- XT	BAPI20- 80_ NOTHD- RI	SHORT_ TEXT	Short Text	None
MI_ REC_ LOC_ ID_CHR	Functional Location ID	VIQM- EL	TPL- NR	BAPI20- 80_ NOTHD- RI	FUNCT_ LOC	Func- tional Location	None
MI_ REC_ ASSET_ ID_CHR	Asset ID	VIQM- EL	EQU- NR	BAPI20- 80_ NOTHD- RI	EQUIPME- NT	Equip- ment number	None
MI_ REC_ LONG_ DESCR_ TX	Recom- mendation Description					Noti- fication Long Text	Multiple Recom- mendation values are concatenated to determine what to map to the Noti- fication Long Text field.

MI_ REC_ NOTIF_ TYPE_C	"M1"	VIQM- EL	QMA- RT		NOTIF_ TYPE	Noti- fication Type	By default, the Notification Type field in SAP is always populated with the value M1. You can, however, configure the GE Digital APM system to create other notification types.
			Non- e	BAPI20- 80_ NOTHD- RI	REPORTE- DBY	Name of Person Report- ing Noti- fication	The Reported By field is populated in SAP with the first twelve characters of the user ID of the Security User that was logged in to the GE Digital APM when the Notification was created.

The following fields are updated in the Recommendation record based on data from the created Notification.

GE Digita- I APM Field ID	GE Digita- I APM Field Cap- tion	SAP Table ID	SAP Field ID	BAPI Struc- ture	BAP- I Field	SAP Field ID	Note- s
MI_REC_ WK_REQ_ REF_CHR	Work Request Reference	VIQME- L	QMNU- M			Noti- fication Number	None
MI_REC_ WR_ EQUIP_C	Work Request Equip- ment	VIQME- L	EQUNR			Equipment number	None

MI_REC_ Request VIQME- WR_LOC_C Functional L Location	TPLNR		ctional ation None
---	-------	--	-----------------------

SAP Task Value Mappings

When you use the Work Management Interface to create Orders from GE Digital APM Task records, several values in the GE Digital APM Task record are passed to the SAP Order and its associated Operations. The following table explains the Task fields whose values are passed to the SAP Function Module /MIAPM/MAINTAIN_ORDER (which calls the SAP BAPI_BAPI_ALM_ORDER_MAINTAIN).

GE Digital APM Field Caption	BAPI Structure	SAP BAPI Field
Work Order Type	BAPI_ALM_ORDER_ HEADERS_I	ORDER_TYPE
Task Description	BAPI_ALM_ORDER_ HEADERS_I	SHORT_TEXT
Task List Type	None	TASKLIST_TYPE
Task List Group	None	TASKLIST_ GROUP
Task List Group Counter	None	TASKLIST_ GROUP_CTR
Task Details	None	IT_TEXT_LINES
Work Order Number	None	ORDER_ NUMBER
The GE Digital APM system maps a value from the Equipment record to which the Task record is linked, based upon the configuration of the query Get SAP ID for Equipment, which is stored in the Catalog folder \Public\Meridium\Modules\SAP Integration Interfaces\Queries.	BAPI_ALM_ORDER_ HEADERS_I	EQUIPMENT
The GE Digital APM system maps a value from the Functional Location record to which the Task record is linked, based upon the configuration of the query Get SAP ID for Functional Location, which is stored in the Catalog folder \Public\Meridium\Modules\SAP Integration Interfaces\Queries.	None	FUNCT_LOC

After these values are passed to the SAP BAPI, the Function Module then sends additional data from the associated SAP Task List to the SAP Order, as described in the following table.

Task List Field	BAPI Structure	Order Field
WERKS	BAPI_ALM_ORDER_HEADERS_I	PLANT
ARBPL	BAPI_ALM_ORDER_HEADERS_I	MN_WK_CTR
None. The value 4 is always mapped.	BAPI_ALM_ORDER_HEADERS_I	SCHED_TYPE
IWERK	BAPI_ALM_ORDER_HEADERS_I	PLANPLANT

Also, for each Operation that belongs to the Task List, a corresponding Operation will belong to the Order. The following table identifies the values that are mapped from each Operation that is attached to the Task List to each Operation that is attached to the Order.

Task List Field	BAPI Structure	Order Field
ARPBL	BAPI_ALM_ORDER_OPERATION	WORK_CNTR
VORNR	BAPI_ALM_ORDER_OPERATION	ACTIVITY
STEUS	BAPI_ALM_ORDER_OPERATION	CONTROL_KEY
WERKS	BAPI_ALM_ORDER_OPERATION	PLANT
LTXA1	BAPI_ALM_ORDER_OPERATION	DESCRIPTION
TXTSP	BAPI_ALM_ORDER_OPERATION	LANGU
KTSCH	BAPI_ALM_ORDER_OPERATION	STANDARD_TEXT_ KEY
LOANZ	BAPI_ALM_ORDER_OPERATION	NO_OF_TIME_ TICKETS
LOART	BAPI_ALM_ORDER_OPERATION	WAGETYPE
QUALF	BAPI_ALM_ORDER_OPERATION	SUITABILITY
LOGRP	BAPI_ALM_ORDER_OPERATION	WAGEGROUP
SORTL	BAPI_ALM_ORDER_OPERATION	SORT_FLD
LIFNR	BAPI_ALM_ORDER_OPERATION	VENDOR_NO
BMSCH	BAPI_ALM_ORDER_OPERATION	QUANTITY

	API_ALM_ORDER_OPERATION	BASE_UOM
DDEIC		D, OL_001VI
FILLIS	API_ALM_ORDER_OPERATION	PRICE
PEINH BA	API_ALM_ORDER_OPERATION	PRICE_UNIT
SAKTO BA	API_ALM_ORDER_OPERATION	COST_ELEMENT
WAERS BA	API_ALM_ORDER_OPERATION	CURRENCY
INFNR BA	API_ALM_ORDER_OPERATION	INFO_REC
EKORG BA	API_ALM_ORDER_OPERATION	PURCH_ORG
EKGRP BA	API_ALM_ORDER_OPERATION	PUR_GROUP
MATKL BA	API_ALM_ORDER_OPERATION	MATL_GROUP
ANZZL BA	API_ALM_ORDER_OPERATION	NUMBR_OF_ CAPACITIES
PRZNT BA	API_ALM_ORDER_OPERATION	PERCENT_OF_ WORK
INDET BA	API_ALM_ORDER_OPERATION	CALC_KEY
LARNT BA	API_ALM_ORDER_OPERATION	ACTTYPE
ANLZU BA	API_ALM_ORDER_OPERATION	SYSTCOND
ISTRU BA	API_ALM_ORDER_OPERATION	ASSEMBLY
VERTN BA	API_ALM_ORDER_OPERATION	INT_DISTR
PLIFZ BA	API_ALM_ORDER_OPERATION	PLND_DELRY
DAUNO BA	API_ALM_ORDER_OPERATION	DURATION_ NORMAL
DAUNE BA	API_ALM_ORDER_OPERATION	DURATION_ NORMAL_UNIT
EINSA BA	API_ALM_ORDER_OPERATION	CONSTRAINT_ TYPE_START
EINSE BA	API_ALM_ORDER_OPERATION	CONSTRAINT_ TYPE_FINISH
ARBEI BA	API_ALM_ORDER_OPERATION	WORK_ACTIVITY
ARBEH BA	API_ALM_ORDER_OPERATION	UN_WORK
AUFKT BA	API_ALM_ORDER_OPERATION	EXECFACTOR

SLWID	BAPI_ALM_ORDER_OPERATION	FIELD_KEY
USR00	BAPI_ALM_ORDER_OPERATION	USR00
USR01	BAPI_ALM_ORDER_OPERATION	USR01
USR02	BAPI_ALM_ORDER_OPERATION	USR02
USR03	BAPI_ALM_ORDER_OPERATION	USR03
USR04	BAPI_ALM_ORDER_OPERATION	USR04
USR05	BAPI_ALM_ORDER_OPERATION	USR05
USE05	BAPI_ALM_ORDER_OPERATION	USE05
USR06	BAPI_ALM_ORDER_OPERATION	USR06
USE06	BAPI_ALM_ORDER_OPERATION	USE06
USR08	BAPI_ALM_ORDER_OPERATION	USR08
USR09	BAPI_ALM_ORDER_OPERATION	USR09
USR10	BAPI_ALM_ORDER_OPERATION	USR10
USR11	BAPI_ALM_ORDER_OPERATION	USR11

Overview of the Maximo Adapters

The APM Connect Maximo Adapters allow you to extract, transform, and load data between your Maximo system and your GE Digital APM system.

Create Maximo Work Orders or Service Requests

<u>MPORTANT</u>: You can only create either a Work Order or a Service Request in Maximo from GE Digital APM. You can not create both at the same time, so <u>you must configure the context file</u> to designate which to create.

Note: The following instructions assume that the Create Work Request field exists on the baseline datasheets for the supported Recommendation families. This field exists on the default datasheets in the baseline GE Digital APM database, so these instructions assume that they have not been removed by an administrative user.

Steps

- 1. Create a new or open an existing Recommendation record.
- 2. If the Recommendation records is not already linked to the Equipment or Functional Location record that represents the equipment or location for which you want to create a Maximo Work Order, link the records.
- 3. Select the appropriate datasheet for the Recommendation record.
- 4. Enter values into the fields as desired to provide information about the recommended action.

Note: The value in the Target Completion Date field must be a date other than the current date.

- 5. Select the **Create Work Request?**.
- 6. Select .

The record is saved.

Results

After you save the recommendation record the following occurs:

- 1. A Work Order or Service Request is created in the Maximo system.
- 2. The **Work Request Reference** field is populated with the ID of the corresponding Work Order or Service Request.
- 3. After the **Work Request Reference** field is populated, the **Create Work Request** field becomes disabled.

Note: If a Work Order could not be created for any reason, a message appears, describing the problem. You will be unable to save the Recommendation record until you clear the **Create Work Request?** check box.

About Extracting Data From Maximo

The extraction adapters allow you to extract data from your Maximo system and import it into your GE Digital APM system. To execute an adapter, you must configure the appropriate <u>parameters in the context file</u>. After the context file is configured, you must <u>run the Adapter job in the APM Connect Administration Center</u>, and then your data is extracted, transformed, and loaded into GE Digital APM.

There are four jobs that can be used to extract data from Maximo and load data into GE Digital APM.

- Maximo_Asset: Loads Maximo Asset records to GE Digital APM as Equipment records.
- Maximo_Location: Loads Maximo Location records to GE Digital APM as Functional Location records.
- Maximo_WorkHistory: Loads Maximo Work Order records, Service Request records, and failure records as GE Digital APM Work History and Work History Detail records.
- Maximo_Master_Interface: Can be used as a wrapper job to run all of the extraction jobs simultaneously.

As a GE Digital APM user, after the adapter job runs, you can use standard GE Digital APM tools (e.g., Search Tool) to access the records that were created automatically.

Details: Extracting Equipment Data

When the Equipment job is run, for each asset in the Maximo system that meets the criteria defined in context file, a corresponding Equipment record will be created in the GE Digital APM database. In addition, if that Maximo asset has a parent asset or location, the GE Digital APM Equipment record will be linked automatically to a parent record belonging to the Equipment family or the Functional Location family, as appropriate.

Note: If an asset is deleted in the Maximo system after an Equipment record has already been created for it in the GE Digital APM system, rerunning the Equipment Adapter job will not delete the GE Digital APM Equipment record.

Details: Extracting Functional Location Data

When the Functional Location Adapter job is run, for each location in the Maximo system that meets the criteria defined in the context file, a corresponding Functional Location record will be created in the GE Digital APM database. In addition, if that Maximo location has a parent asset or location, the GE Digital APM Functional Location record will be linked automatically to a parent record belonging to the Equipment family or the Functional Location family, as appropriate.

Note: The Functional Location Extraction Interface will not extract locations of the type COURIER or LABOR. Additionally, store room functional locations are not extracted.

Note: If an asset is deleted in the Maximo system after a Functional Location record has already been created for it in the GE Digital APM system, rerunning the Functional Location Extraction Interface will not delete the GE Digital APM Functional Location record.

Details: Extracting Work Orders

When the Work History Job is run, for each Work Order in the Maximo system that meets the criteria defined in the scheduled item, a corresponding Work History record will be created in the GE Digital APM database. Each Work History record will be linked to one Equipment or Functional Location record identifying the asset or location against which the Maximo Work Order is written.

If the Work Order is written against a location, the Work History record will be linked to a Functional Location record, and the Location ID field in the Work History record will be populated automatically with the Location ID of that Maximo location.

If the Work Order is written against an asset, the Work History record will be linked to an Equipment record, and the Equipment ID field in the Work History record will be populated automatically with the Location ID of that Maximo asset. In addition, if that Maximo asset has a parent location, the Work History record will also be linked to a Functional Location record representing that parent Maximo location. The Location ID field in the Work History record will also be populated automatically with the Location ID of that parent Maximo location.

Details: Extracting Service Requests

When the Work History Job is run, for each Service Request in the Maximo system that meets the criteria defined in the scheduled item, a corresponding Work History record will be created in the GE Digital APM database. Each Work History record will be linked to one Equipment or Functional Location record identifying the asset or functional location against which the Maximo Service Request is written. Specifically:

If the Service Request is written against a location, the Work History record will be linked to a Functional Location record, and the Location ID field in the Work History record will be populated automatically with the Location ID of that Maximo location.

If the Service Request is written against an asset, the Work History record will be linked to an Equipment record, and the Equipment ID field in the Work History record will be populated automatically with the Location ID of that Maximo asset. In addition, if that

Maximo asset has a parent location, the Work History record will also be linked to a Functional Location record representing that parent Maximo location. The Location ID field in the Work History record will also be populated automatically with the Location ID of that parent Maximo location.

Details: Extracting Failure Information

When the Work History Job is run Work Order and Service Request failure information is extracted from your Maximo system into your GE Digital APM system as Work History Detail records.


Note: If a Work Order does not have any failure information, a Work History Detail record will not be created.

Reference Information: Maximo Adapters

This topic provides a listing of all detailed reference information provided for the Maximo Adapters, such as command syntax, specifications, and table/field descriptions.

Maximo Data Model

The following diagram shows how the families used by the Maximo Adapter are related to one another.



Note: In the diagram, boxes represent entity families and arrows represent relationship families that are configured in the baseline database. You can determine the direction of the each relationship definition from the direction of the arrow head: the box from which the arrow originates is the predecessor, and the box to which the arrow head points is the successor.

Like all GE Digital APM modules, the GE Digital APM Maximo Interfaces feature consists of entity families, relationship families, and business rules. When attempting to understand and make use of the GE Digital APM Maximo Interfaces functionality, it can be helpful to visualize the Maximo Interfaces data model.

Because you should already be familiar with the concept of records and viewing records in the GE Digital APM Record Manager, as you attempt to get your bearings in the Maximo Interfaces, it may be useful to remember that the Maximo Interfaces simply offers functionality that allows you to create and view records.

In addition, you can link each Equipment or Functional Location record to a Site Reference record, which identifies the site to which that equipment or location belongs.

About Interface Log Records used by the Service Request and Work Order Interface Record

Each time an interface is run, an Interface Log record is created automatically to store information about the process, such as the status of the process (e.g., Completed with

warnings), the date the interface was run, and the parameters that were used to run the interface.

If the value in an Interface Log record is Completed with Warnings or Completed with Errors, a Super User or a member of the MI CMMS Interfaces Administrator Security Group can review the warnings or errors and then change the status to Completed with Warnings (Cleared) or Completed with Errors (Cleared).

About Site Filtering in the EAM Adapters

<u>MPORTANT</u>: Site Reference records must preexist in your GE Digital APM system, before you can use the EAM Adapters to populate the Site Reference Key. Additionally, the site entered into the context file must match the exact value in the corresponding Site Reference record.

<u>MPORTANT</u>: The user who is running the EAM Adapters jobs must be assigned, in GE Digital APM, to the site to which the records being loaded will be assigned. Additionally, the credentials for that user must be entered into the context file. If the user is not a member of the appropriate site, then the data load will fail, and an error message will appear.

The EAM Adapters are used to populate the Site Reference on Equipment, Functional Location, and Work History records in GE Digital APM. The adapters populate the MI_SITE_KEY system field with the ENTY_KEY system field associated with the Site Reference value to be populated. On asset records, the Site Reference is stored in the MI_SITE_KEY field, a system field in GE Digital APM. The EAM Adapters use the Site Name (MI_SITE_NAME) to translate the value to the corresponding Site Reference Key and populate the MI_SITE_KEY field; therefore, you do not need to know the key to be able to populate the site reference. This functionality is important because this value can change from one database to another.

When records are loaded using the Equipment, Function Location, and Work History Adapters, the system will assign the Site Reference Key (MI_SITE_KEY) to the assets using the value designated in the context file context file. The following parameters are used to designate the Site Reference Key value:

- SITE_REFERENCE_EQUIP: Used to populate the Site Reference Key on Equipment records being loaded into GE Digital APM. The Site Reference Key determines the Site to which the Equipment record(s) will be assigned.
- SITE_REFERENCE_FLOC: Used to populate the Site Reference Key on Functional Location records loaded into GE Digital APM. The Site Reference Key determines Site to which the Functional Location record(s) will be assigned.

Note: The values entered into these parameters should match, because Equipment records are linked to Functional Location records. Therefore, they should have the same site.

These parameters accept three types of values to determine the site reference value.

- a. **Site Name:** You can enter the site name directly as defined on the preexisting Site Reference record (i.e., Site 100).
- b. **Column Name:** You can enter a column value between two pound symbols (#) to set the site reference. The following columns can be used:

- · SAP columns:
 - MI_EQUIP000_SAP_SYSTEM_C
 - MI_EQUIP000_MAINT_PLANT_C
 - MI_FNCLOC00_MAINT_PLNT_C
 - MI_FNCLOC00_SAP_SYSTEM_C
- Maximo columns:
 - MI_FNCLOC00_SITE_C
 - MI_EQUIP000_SITE_C

For example, if you wanted to use your SAP maintenance plant field as your GE Digital APM site reference, you would enter #MI_EQUIP000_MAINT_PLANT_C#.

c. **Null:** You can leave the value as null. The record will be a global record if a Site Reference value is not mapped in between the tags.

If the assets being loaded into GE Digital APM are global records, meaning they will not be filtered according to site, then the Site Reference parameters can be left blank. When records are loaded with a null values in their Site Reference parameters, those created asset records will be designated as Global.

After the adapters are run, records designated to be transferred into GE Digital APM will be assigned to the site defined in the Site Reference parameters.

In addition to Equipment and Functional Location records loaded by the EAM adapters, Work History records and shell records are impacted by site reference functionality as detailed in the following table.

Action	Result
If the Work History Adapter is run after the Equipment or Functional Location Adapter	The Work History records will inherit the Site Reference Key of their parent Functional Loca- tion or Equipment records.
If the Work History Adapter is run before the Equipment or Functional Location Adapter	The Site Reference Key will inherited from the shell record that will be created for Equipment and Functional Location.
If a shell record is created while loading data	The Site Reference Key will be the value set in the context parameters.

Note: If you are using multiple SAP Systems, you must set up a context file for each system, and then designate the appropriate site(s) for each EAM Systems.

Maximo Values Mapped to GE Digital APM Records

This topic provides a listing of all Mapping information provided for the Maximo Adapters.

Maximo Equipment Records Mappings

The following table explains the Maximo fields that are used to populate the baseline Equipment fields when you uses the Maximo Equipment Adapter to create Equipment records in GE Digital APM:

GE Di- gital APM Family ID	GE Di- gital APM Field ID	GE Digit- al APM Field Caption	Max- imo Table	Maximo Internal ID	Maximo Adapter Label	Com- ments
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ EQUIP_ ID_C	Equip- ment ID	ASSET	ASSETID	None. This value is not visible in the Maximo interface.	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ EQUIP_ TECH_ NBR_C	Equip- ment Technical Number	ASSET	ASSETNUM	Asset	This is a GE Digit- al APM key field.
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ TYPE_C	Equip- ment Type	ASSET	ASSETTYPE	Туре	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ CHANG- E_ DATE_D	CMMS Last Changed Date	ASSET	CHANGEDATE	Changed Date	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ EQUIP_ SHRT_ DESC_C	Equip- ment Short Descrip- tion	ASSET	DESCRIPTION	This value appears to the right of the Asset text box on the Maximo Adapter.	None

MI_ EQUIP0- 00	MI_ EQUIP0- 00_ EQUIP_ LNG_ DESC_T	Equip- ment Long Descrip- tion	ASSET	DESCRIPTION_ LONGDESCRIP- TION	This value appears in the Long Description window.	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ PRCH_D	Purchase Date	ASSET	INSTALLDATE	Installation Date	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_INV_ NO_C	Inventory Number	ASSET	ITEMNUM	Rotating Item	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ FNC_ LOC_C	Func- tional Location	ASSET	LOCATION	Location	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ MFR_C	Man- ufacturer	ASSET	MANUFACTURE-R	Manufacturer	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ CRITI_ IND_C	Criticality Indicator	ASSET	PRIORITY	Priority	None
MI_ EQUIP0- 00	MI_ EQUIPO- 00_ ASSET_ SERIAL_ NBR_C	Asset Serial Number	ASSET	SERIALNUM	Serial #	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ SITE_C	Site	ASSET	SITEID	Site	None

MI_ EQUIP0- 00	MI_ EQUIP0- 00_SYS_ ST_C	System Status	ASSET	STATUS	Status	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_ EQUIP_ VNDR_C	Equip- ment Vendor	ASSET	VENDOR	Vendor	None
MI_ EQUIP0- 00	MI_ EQUIPO- 00_ WRNT- Y_EXPR_ D	Warranty Expiration Date	ASSET	WARRANTYEXP- DATE	None. This value is not visible in the Maximo interface.	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_SN_ C	Man- ufacturer serial number	ASSET	SERIALNUM	Manufacturer serial number	None
MI_ EQUIP0- 00	MI_ EQUIP0- 00_OBJ_ TYP_C	Type of Technical Object	ASSET	ASSETTYPE	Type of Tech- nical Object	None
MI_ EQUIP0- 00	MI_ EQUIPO- 00_SAP_ SYSTE- M_C	CMMS SYSTEM	Auto pop- ulated by the Max- imo Sys- tem.	Auto populated by the Maximo System.	Auto populated by the Maximo System.	This is a GE Digit- al APM key field.

Maximo Functional Location Mappings

The following table explains the Maximo fields that are used to populate the baseline Functional Location fields when you uses the Maximo Functional Location Adapter to create Functional Location records in GE Digital APM:

GE Digital APM Field ID	GE Digital APM Field Caption	MAXIMO Table	Maximo Internal ID	Maximo Adapter Label	Comments
MI_ FNCLOC00_ CHANGE_ DATE_D	CMMS Last Changed Date	LOCATION	CHANGEDATE	None. This value is not visible in the Maximo interface.	None
MI_ FNCLOC00_ FNC_LOC_ DESC_C	Functional Location Description	LOCATION	DESCRIPTION	This value appears to the right of the Location text box on the Maximo Adapter.	None
MI_ FNCLOC00_ FNC_LOC_ LNG_ DESC_C	Functional Location Long Description	LOCATION	DESCRIPTION_ LONGDESCRIPTION	This value appears in the Long Description window.	None
MI_ FNCLOC00_ FAIL_ CLASS_C	Failure Class	LOCATION	FAILURECODE	Failure Class	None
MI_ FNCLOC00_ FNC_LOC_C	Functional Location	LOCATION	LOCATION	Location	This is a GE Digital APM key field.

MI_ FNCLOC00_ INTERNAL_ ID_C	Functional Location Internal ID	LOCATION	LOCATIONSID	None. This value is not visible in the Maximo interface.	None
MI_ FNCLOC00_ CRTCAL_ IND_C	Criticality Indicator	LOCATION	LOCPRIORITY	Priority	None
MI_ FNCLOC00_ SUPR_FNC_ LOC_C	Superior Functional Location	LOCATION	PARENT	Parent	None
MI_ FNCLOC00_ SITE_C	Site	LOCATION	SITEID	Site	None
MI_ FNCLOC00_ SYS_ STATUS_C	System Status	LOCATION	STATUS	Status	None
MI_ FNCLOC00_ TYPE_C	Location Type	LOCATION	TYPE	Туре	None
MI_ FNCLOC00_ SAP_ SYSTEM_C	CMMS Sys- tem	Auto populated by the Maximo System.	Auto populated by the Maximo Sys- tem.	Auto populated by the Maximo System.	This is a GE Digital APM key field.

Maximo Work History Mappings

The following tables explain the Maximo fields that are used to populate the baseline Work History fields when you extract Work Orders and Service Request using the Maximo Work History Adapter to create Work History records in GE Digital APM:

Values Mapped from Maximo Work Orders to GE Digital APM Work History Records

GE Dig- ital APM Family Name	GE Digita- I APM Work His- tory Field ID	GE Digit- al APM Work History Field Caption	Maximo Table Name	Maximo Internal ID	Maximo Interface Label	Com- ments
MI_ EVWKHI- ST	MI_ EVWKHIS- T_MAINT_ COMPL_D	Main- tenance Com- pletion Date	WORKOR- DER	ACTFINISH	Actual Fin- ish	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ACT_ LABOR_ COST_N	Actual Labor Cost	WORKOR- DER	ACTLABCOST	Actual Labor Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ACT_ LABOR_ TIME_N	Actual Labor	WORKOR- DER	ACTLABHRS	Actual Labor Hours	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ACT_ MTRL_ COST_N	Actual Material Cost	WORKOR- DER	ACTMATCOST	Actual Material Cost	None

MI_ EVWKHI- ST	MI_ EVWKHIS- T_ACT_ SERV_ COST_N	Actual Service Cost	WORKOR- DER	ACTSERVCOST	Actual Ser- vice Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_MAINT_ START_D	Main- tenance Start Date	WORKOR- DER	ACTSTART	Actual Start	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ACT_ TOOL_ COST_N	Actual Tool Cost	WORKOR- DER	ACTTOOLCOST	Actual Tool Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_MAINT_ CST_N	Main- tenance Cost	WORKOR- DER	ACTTOTALCOS-	Actual Total Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_EQU_ LOC_ PRIORTY_ N	Equip- ment Location Priority	WORKOR- DER	ASSETLOCPRIO- RITY	Asset/Loca- tion Pri- ority	None
MI_ EVWKHI- ST	MI_ EVENT_ ASST_ID_ CHR	Equip- ment ID	WORKOR- DER	ASSETNUM	Asset	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_CALC_ PRIORTY_ N	Cal- culated Priority	WORKOR- DER	CALCPRIORITY	Asset/Loca- tion Pri- ority	None

MI_ EVWKHI- ST	MI_ EVENT_ MODFD_ BY_CHR	Modified By	WORKOR- DER	CHANGEBY	Modified By	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ORDR_ CHNG_ DT_D	Order Last Change Date	WORKOR- DER	CHANGEDATE	None. This value is not visible in the Maximo interface.	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_CREW_ ID_C	Crew ID	WORKOR- DER	CREWID	Crew	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ORDR_ DESC_C AND MI_ EVENT_ SHRT_CHR	Order Description AND Event Short Description	WORKOR- DER	DESCRIPTION	Descrip- tion	None
MI_ EVWKHI- ST	MI_ EVENT_ LNG_DSC_ TX	Event Long Descrip- tion	WORKOR- DER	DESCRIPTION_ LONGDESCRIP- TION	This value appears in the Long Description window.	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_EST_ LABOR_ COST_N	Estimated Labor Cost	WORKOR- DER	ESTLABCOST	Estimated Labor Cost	None

MI_ EVWKHI- ST	MI_ EVWKHIS- T_EST_ LABOR_ TIME_N	Estimated Labor	WORKOR- DER	ESTLABHRS	Estimated Labor Hours	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_EST_ MTRL_ COST_N	Estimated Material Cost	WORKOR- DER	ESTMATCOST	Estimated Material Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_EST_ SERV_ COST_N	Estimated Service Cost	WORKOR- DER	ESTSERVCOST	Estimated Service Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_EST_ TOOL_ COST_N	Estimated Tool Cost	WORKOR- DER	ESTTOOLCOST	Estimated Tool Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ORDR_ MAINT_ PLAN_C	Order Main- tenance Plan	WORKOR- DER	JPNUM	None. This value is not visible in the Maximo interface.	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ORDR_ PRTY_ DESC_C	Order Priority Description	WORKOR- DER	JUSTIFYPRIORI- TY	Priority Jus- tification	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_LEAD_ CRAFT_C	Lead Craft	WORKOR- DER	LEAD	Lead	None

MI_ EVWKHI- ST	MI_ EVENT_ LOC_ID_ CHR	Location ID	WORKOR- DER	LOCATION	Location	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ACT_ OUT_LBR_ CST_N	Actual Outside Labor Cost	WORKOR- DER	OUTLABCOST	Outside Labor Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ACT_ OUT_ MTR_CST_ N	Actual Outside Material Cost	WORKOR- DER	OUTMATCOST	Outside Material Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ACT_ OUT_TL_ CST_N	Actual Outside Tool Cost	WORKOR- DER	OUTTOOLCOST	Outside Tool Cost	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_PM_ NBR_C	PM Num- ber	WORKOR- DER	PMNUM	None. This value is not visible in the Maximo interface.	None
MI_ EVWKHI- ST	MI_ EVENT_ STRT_DT	Event Start Date	WORKOR- DER	REPORTDATE	Reported Date	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_SCHED_ COMPL_D	Sched- uled Com- pletion Date	WORKOR- DER	SCHEDFINISH	Scheduled Finish	None

MI_ EVWKHI- ST	MI_ EVWKHIS- T_SCHED_ START_D	Sched- uled Start Date	WORKOR- DER	SCHEDSTART	Scheduled Start	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_SITE_C	Site	WORKOR- DER	SITEID	Site	This field is used as a pick list value in GE Digita-I APM.
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ORDR_ SYS_STAT_ C	Order Sys- tem Status	WORKOR- DER	STATUS	Status	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ TARGET_ COMPL_D	Target Com- pletion Date	WORKOR- DER	TARGCOMPDA- TE	Target Fin- ish	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ TARGET_ START_D	Target Start Date	WORKOR- DER	TARGSTARTDA- TE	None. This value is not visible in the Maximo interface.	None
MI_ EVWKHI- ST	MI_ EVENT_ID AND MIEVWKHI- ST_ ORDER_ ID_N	Event ID AND Order ID	WORKOR- DER	WONUM	Work Order	None

MI_ EVWKHI- ST	MI_ EVWKHIS- T_ORDR_ PRTY_C	Order Pri- ority	WORKOR- DER	WOPRIORITY	Priority	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_ORDR_ TYP_CD_C	Order Type Code	WORKOR- DER	WORKTYPE	None. This value is not visible in the Maximo interface.	None
MI_ EVWKHI- ST	MI_ EVWKHIS- T_OBJECT_ NUMBER_ C	Object Number	WORKOR- DER	"OR"+WONUM	None. This value is not visible in the Maximo interface.	This field is used as a pick list value in GE Digita-I APM.
MI_ EVWKHI- ST	MI_ EVWKHIS- T_SAP_ SYSTEM_C	CMMS System	Auto populated by the Maximo System.	Auto pop- ulated by the Maximo Sys- tem.	Auto populated by the Maximo System.	This field is used as a pick list value in GE Digita-I APM.

Values Mapped from Maximo Service Request to GE Digital APM Work History Records

GE Digit- al APM Family	GE Digit- al APM Work His- tory Field ID	GE Digita- I APM Work His- tory Field Caption	Maximo Table	Maximo Internal ID	Maximo Inter- face Label	Com- ments
MI_ EVWKHIS- T	MI_ EVENT_ ASST_ID_ CHR	Equip- ment ID	SR	ASSETNUM	Asset	None

MI_ EVWKHIS- T	MI_ EVENT_ SHRT_ DSC_CHR	Event Short Descrip- tion	SR	DESCRIPTION	Sum- mary	None
MI_ EVWKHIS- T	MI_ EVENT_ LOC_ID_ CHR	Location ID	SR	LOCATION	Location	None
MI_ EVWKHIS- T	MI_ EVWKHIS- T_SITE_C	Site	SR	SITEID	Site	This is a GE Digital APM key field.
MI_ EVWKHIS- T	MI_ EVENT_ID	Event ID	SR	TICKETID	Service Request	None
MI_ EVWKHIS- T	MI_ EVWKHIS- T_ OBJECT_ NUMBER_ C	OBJECT NUMBER	SR	"QM"+TICKETI- D	None. This value is not vis- ible in the Max- imo inter- face.	This is a GE Digital APM key field.
MI_ EVWKHIS- T	MI_ EVWKHIS- T_RQST_ ID_CHNG_ DT_D	Change Date	SR	CHANGEDATE	None. This value is not vis- ible in the Max- imo inter- face.	None
MI_ EVWKHIS- T	MI_ EVWKHIS- T_RQST_ ID_C	Request ID	SR	TICKETID	Service Request	None

MI_ EVWKHIS- T	MI_ EVWKHIS- T_SAP_ SYSTEM_C	Auto pop- ulated by the Max- imo Sys- tem.	Auto pop- ulated by the Maximo Sys- tem.	Auto populated by the Maximo System.	This is a GE Digital APM key field.
----------------------	---------------------------------------	--	---	--------------------------------------	--

Maximo Work History Detail Mappings

The following tables explain the values that are used to populate Work History Detail fields when you extract Work Order failure information or Service Request information from Maximo.

The following tables explain the Maximo fields that are used to populate the baseline Work History Detail fields when you extract Work Order failure information and Service Request information using the Maximo Work History Adapter to create Work History Detail records in GE Digital APM:

Values Mapped from Maximo Work Orders failure to GE Digital APM Work History Detail Records

GE Digi- tal APM Family	GE Digit- al APM Work History Field ID	GE Digit- al APM Work History Field Caption	Maximo Table	Maximo Internal ID	Maximo Inter- face Label	Com- ments
MI_ DTWKHI- ST	MI_ DTWKHIS- T_ASST_ ID_C	Equip- ment ID	WORKORD- ER	ASSETNUM	Asset	None
MI_ DTWKHI- ST	MI_ DTWKHIS- T_EVNT_ DTL_ DESC_C	Work History Detail Description	WORKORD- ER	DESCRIPTION	Descrip- tion	None
MI_ DTWKHI- ST	MI_ DTWKHIS- T_DTL_ NARTV_T	Detail Narrative	WORKORD- ER	DESCRIPTION_ LONGDESCRIPT- ION	This value appears in the Long Description window.	None

MI_ DTWKHI- ST	MI_ DTWKHIS- T_LOC_ ID_C	Location ID	WORKORD- ER	LOCATION	Location	None
MI_ DTWKHI- ST	MI_ DTWKHIS- T_ CNDTN_ CD_C	Condi- tion Code	WORKORD- ER	PROBLEMCODE	Problem Code	None
MI_ DTWKHI- ST	MI_ DTWKHIS- T_SITE_C	Site	WORKORD- ER	SITEID	Site	None
MI_ DTWKHI- ST	MI_ DTWKHIS- T_WRK_ HISTRY_ ID_C	Work His- tory ID	WORKORD- ER	WONUM	Work Order	None
MI_ DTWKHI- ST	MI_ DTWKHIS- T_ORDR_ ID_C	Order ID	WORKORD- ER	WONUM	Work Order	None
MI_ DTWKHI- ST	MI_ DTWKHIS- T_EVNT_ DTL_ID_C	History Detail ID	WORKORD- ER	WONUM	Work Order	This is a GE Digital APM key field.
MI_DTWK DTWKHIS' SYSTEM_C	T_SAP_	CMMS System	Auto populated by the Maximo System.	Auto populated by the Maximo System.	Auto populated by the Maximo System.	This is a GE Digital APM key field.

Values Mapped from Maximo Service Order Request to GE Digital APM Work History Detail Records

GE Digit- al APM Family	GE Digital APM Work His- tory Field ID	GE Digita- I APM Work His- tory Field Caption	Maximo Table	Maximo Internal ID	Maximo Inter- face Label	Com- ments
MI_ DTWKHIS- T	MI_ DTWKHIS- T_ASST_ ID_C	Equip- ment ID	SR	ASSETNUM	Asset	None
MI_ DTWKHIS- T	MI_ DTWKHIS- T_EVNT_ DTL_ DESC_C	Work His- tory Detail Descrip- tion	SR	DESCRIPTIO- N	Sum- mary	None
MI_ DTWKHIS- T	MI_ DTWKHIS- T_LOC_ID_ C	Location ID	SR	LOCATION	Location	None
MI_ DTWKHIS- T	MI_ DTWKHIS- T_SITE_C	Site	SR	SITEID	Site ID	None
MI_ DTWKHIS- T	MI_ DTWKHIS- T_RQST_ ID_C	Request ID	SR	TICKETID	Service Request	None
MI_ DTWKHIS- T	MI_ DTWKHIS- T_EVNT_ DTL_ID_C	History Detail ID	SR	TICKETID	Service Request	This is a GE Digital APM key field.
MI_ DTWKHIS- T	MI_ DTWKHIS- T_SAP_ SYSTEM_C	CMMS Sys- tem	Auto populated by the Maximo System.	Auto populated by the Maximo System.	Auto populated by the Maximo System.	This is a GE Digital APM key field.

Maximo Recommendation Mappings

The following table explains the GE Digital APM Recommendation fields that are used to populate Maximo Work Orders when using the Maximo Notification Management Adapter:

Values Mapped to Maximo Work Orders From GE Digital APM Recommendation Records

GE Digital APM Family	GE Digital APM Field	Maximo Object Structure	Maximo Field
MI_REC	MI_REC_TECHNICAL_ NUM_C	WORKORDER	ASSETNUM
MI_REC	MI_REC_SHORT_ DESCR_CHR	WORKORDER	DESCRIPTION
MI_REC	MI_REC_LONG_DESCR_ TX	WORKORDER	DESCRIPTION_ LONGDESCRIPTION
MI_REC	MI_REC_LOC_ID_CHR	WORKORDER	LOCATION
MI_REC	MI_REC_SITE_C	WORKORDER	SITEID
MI_REC	MI_REC_TARGE_ COMPL_DATE_DT	WORKORDER	TARGCOMPDAE
CONSTANT	"WORKORDER"	WORKORDER	WOCLASS
CONSTANT	"PM"	WORKORDER	WORKTYPE

Values Mapped to Maximo Service Requests From GE Digital APM Recommendation Records

GE Digital APM Family	GE Digital APM Field	Maximo Object Structure	Maximo Field
MI_REC	MI_REC_TECHNICAL_ NUM_C	SR	ASSETNUM
MI_REC	MI_REC_SHORT_ DESCR_CHR	SR	DESCRIPTION
MI_REC	MI_REC_LONG_DESCR_ TX	SR	DESCRIPTION_ LONGDESCRIPTION

MI_REC	MI_REC_LOC_ID_CHR	SR	LOCATION
MI_REC	MI_REC_SITE_C	SR	SITEID
MI_REC	MI_REC_TARGE_ COMPL_DATE_DT	SR	STATUSDATE
CONSTANT	"SR"	SR	CLASS

Manage Jobs in the Administration Center

This topic provides a list of all procedures related to running jobs in the APM Connect Administration Center, as well as links to the related concept and reference topics.

Schedule a Job

Using the APM Connect Administration Center, you can extract items from the EAM source systems to create and update records in the GE Digital APM. While you can run a Job any time you want to extract new or updated items from the EAM source by executing a Run-Now Job, you will probably want to schedule the items to be extracted automatically based on the schedule parameters. This method ensures synchronization between your EAM database and your GE Digital APM database. This topic describes how to schedule a recurring Job in the APM Connect Administration Center.

Note: You cannot run two Jobs of the same kind at the same time. For example, you cannot run two Equipment Jobs at the same time.

Before You Begin


Before you can schedule a Job, you must complete the following:

- Ensure that a Job is imported in the **Job Conductor**.
- Apply the filter parameters for the Job you want to execute in the context file.

Steps


- From the Menu pane, in the Conductor section, select Job Conductor.
 The Job Conductor pane appears, displaying the Jobs that can be executed.
- 2. Select the Job you want to schedule.
 - Note: If the Job you want to execute is not in the workspace, you must import the Job into the Job Conductor.
- 3. At the bottom of the **Job Conductor** workspace, select **Triggers**.

The Triggers section appears.



4. In the Triggers section, select **Add trigger**.

A drop-down menu appears, displaying the options for the types of triggers you can add.



The following trigger is applicable to APM Connect data extractions:

- CRON trigger: A time-based trigger that generates the Job and executes it
 multiple times at a specified date and time. Cron Trigger is most widely used
 because it allows the user to set the repetition of execution with more accuracy. For example, a Cron trigger can be set in such a way that it is executed
 every 10 minutes starting from 10 A.M. to 11 A.M. on every Friday in January,
 March, August, and December in the year 2015.
- 5. Select the **Add CRON trigger** button.

The **Add CRON trigger** section appears on the right side of the page.

- 6. Enter the trigger details using the following guidelines:
 - Label: Enter a name for the trigger.
 - **Description**: Enter a description for the trigger.
 - Time zone strategy: Select JobServer time.
 - Minutes: Enter the time interval (in minutes) after which the execution needs to be repeated.
 - **Hours**: Enter the time (in hours) when the execution should begin.
 - Days of month: Enter the days of the month on which the Job should be executed.
 - Months: Enter the months during which the Job should be executed.
 - Days of week: Enter the days of the week on which the Job should be executed.
 - **Years**: Enter the year during which the Job should be executed.
- 7. Select **Save**.

The new trigger is created and appears in the **Triggers** section.

The Job is scheduled.

Execute a Run-Now Job

While you can use the APM Connect Administration Center to <u>schedule Jobs</u> to run on a recurring basis, you can run a previously scheduled Job at any time to extract new or updated items. This topic describes how to execute a Run-Now Job.

<u>MPORTANT</u>: You cannot run two Jobs of the same kind at the same time. For example, you cannot run two Equipment Jobs at the same time.

Steps

1. In the **Job Conductor** workspace, select the Scheduled Job that you want to run.

Note: If database tables or fields were changed since you last ran a Job, run the CreateStaticData Job first.

2. Select Run.

The Job is run.


View the Execution Log

You can view the execution log for information about the Job execution such as its status, ID, trigger type, and other details. The log also contains information about the errors and warnings that occurred during the execution process. The execution details are available for any Job that appears in the **Job Conductor** workspace. This topic describes how to view the execution log.

Steps

1. In the **Job Conductor** workspace, select the button next to the Job whose execution details you want to view.

The **Task execution details** window appears, displaying the details of the latest execution.



You can view three types of information in the Task execution details window:

- In the Log section, view the sequence of execution, error messages, and warning messages.
- In the **Context values** section, view the values that were passed into the parameters of the executed Job.
- In the Advanced Information section, view information about the executed lob.

Update Existing Jobs

Occasionally, changes will be made to the .zip files associated with an adapter Job. When changes are made to the adapter through a .zip file, the existing Job must be updated by reimporting the .zip file. This topic describes how to update an existing Job.

Steps

- 1. In the **Job Conductor** workspace, select the Job for which the file has been updated.
- 2. On the **Job Conductor** toolbar, select **Delete**.
 - Note: If you do not delete the existing Job, the Job will not update properly, and the Job cannot be executed.
- 3. On the **Job Conductor** toolbar, select **Add**.

The **Execution task** pane is activated.

- 4. In the **Execution task** pane, in the **Label** box, enter a label for the Job.
- 5. In the **Description** box, enter a description for the Job.
- 6. Select the **Active** check box.
- 7. In the **Job** section, select [in].

The **Import generated code** window appears.



- 8. Select **Browse** to navigate to the file containing the adapter Jobs that have been updated.
- 9. Select the appropriate file.
- 10. On the **Import generated code** window, select **Launch upload**.
- 11. The **Project**, **Branch**, **Name**, **Version**, and **Context** text boxes are automatically populated with appropriate values.
- 12. In the Execution Server list, select the server on which the Job should be executed.
- 13. Select Save.

The updated adapter Jobs are imported into the APM Connect Administration Center.

APM Connect Administrative Help

This topic provides a list of help topics related to the APM Connect administrative settings

APM Connect EAM Jobs

The APM Connect EAM Jobs contains a result grid to access the details of the EAM SAP Cloud jobs. Additionally, from the APM Connect EAM Jobs you can access the Interface Log record for each SAP Cloud job.

Access APM Connect EAM Jobs

Steps

Access Operations Manager , and then select APM Connect EAM Jobs.
 The APM Connect EAM Jobs page appears.



Access the Details of an EAM Job

You can view the details of EAM Adapter jobs such as status, time and date, and the associated interface log record.

Steps

- 1. Access the APM Connect EAM Jobs.
- 2. In the **Status and Log** column, view the status of each job.

(i) Tip: If necessary, you can cancel an import job by selecting the \times button that appears in the Status and Log column. If you cancel a job, any changes that have already occurred are *not* removed, therefore, you may need to manually modify records to update or remove unnecessary data.

Status	Description
Waiting	Initial state when job is created. The data import job is queued for pre-processing on the APM Connect Server.
Staging In Progress	The data import job is being prepared on the APM Connect Server.
Staging Failure	The data import job failed during preparation.
Staging Com- plete	The data import job was prepared successfully.
Dataloader Enqueued	The maximum number of data load jobs has been exceeded, as determined in the APM Connect Connection Records, or there is a job of the same type running. The data import will begin once the other jobs are complete.
Configuring Dataloader	The data import job is configuring the proper user roles and arranging data processing for most efficient execution flow.
In Progress	The data import job is loading data into the GE Digital APM Data Source.
Data Syn- chronization in Progress	The data import job is synchronizing the loaded data and relationships across the APM Data Source.
Job Cancelling	The data import job is in the process of being canceled. This occurs after you select \times .

Status	Description		
Cara as II and Iac.	The data import job was cancelled successfully.		
Cancelled by User	Note: When a job is cancelled, the data imported prior to cancelling is not removed.		
Errors	The data import is complete, but encountered one or more errors. You can download the log file to view detailed error messages.		
	Data has been imported into GE Digital APM.		
Complete	Note: If the ▲ icon appears, the data was imported with warnings. You can download the log file to view detailed warning messages.		

3. In the **Status and Log** column, select on the row corresponding to the EAM job for which you want to access the log.

The log file is downloaded.

4. To access the Interface Log record for a specific job, in the **Job ID** column select the job ID that you want to open.

The **Record Manager** page appears, displaying the datasheet for the selected job.

5. To view the information contained in the **Log Text**, select the in the **Log Text** box.

A window appears, displaying details about the job such as error messages, warnings concerning the data load, and general information regarding the data records that were loaded.

APM Connect


In the **APM Connect** section of **Operations Manager**, you can manage the connections used by the APM Connect Adapters. The APM Connect Adapters facilitate data transfers to and from GE Digital APM.

Access the APM Connect Page

Steps

1. Access **Operation Manager**, then select **Connections**, and then select **APM Connect**.

The **APM Connect** workspace appears.



Establish Connection from GE Digital APM

To load data into GE Digital APM using the APM Connect Data Loaders or the EAM Adapters. You must establish the connection between your APM Connect component and GE Digital APM.

Steps

1. Access the **APM Connect** page.

The **APM Connect Configuration** workspace appears.

- 2. In the APM Connect Configuration workspace, configure the parameters on the APM Connect Connection record in the following sections.
 - General Settings: Established the connection between the APM Connect server and GE Digital APM.

<u>MIMPORTANT</u>: The **General Settings** section must be configured if you are using either the Data Loaders or the EAM adapters.

- <u>Data Loaders Settings</u>: Stores the staging database parameters and the remote file server settings.
- <u>EAM Settings</u>: Used to <u>schedule work orders</u>, which determine how frequently work orders will be transferred to your SAP.
 - Note: These settings are only required for the SAP adapters.
- 3. Select Save.

The connection between APM Connect and GE Digital APM is established.

Determine Logging Level

You can set the logging level that will determine the logging messages included in the Data Loader log file.

Steps

1. Access the APM Connect page, and then select Data Loaders settings.

The **Data Loaders Settings** workspace appears.

- 2. In the **Logging Level** box, use the drop-down to select one of the following logging levels:
 - Debug: The default logging level, and the highest level of logging. Selecting debug will return the most details and is helpful when trying to debug the application.
 - Info: Returns information message indicating the progress of the application, and is the second highest level of logging.
 - Warn: Returns warnings detected during the loading process.
 - Error: The lowest level of logging returning errors only.

Note: Logging levels are hierarchical. For example, if you select Info, you will see all warnings and errors. If you select Error, you will only see errors.

3. Select Save.

The record is saved.

Results

 Once the record is saved, subsequent data loads will return log files with the logging level you determined. The logging level will only apply to future data loads.
 Meaning if you change the level from Error to Warn historic log files will not be updated with more details. It will only apply to new data loads.

Schedule Work Orders

Steps

1. Access the **APM Connect** page.

The **APM Connect Configuration** page appears.

2. Select **EAM Settings**.

The **EAM Settings** page appears.

3. In the **Scheduling Properties** section, select **Edit Schedule**.

Note: If there is a previously schedule item, a schedule summary will be displayed next to Edit Schedule. If there is no scheduled item, Not scheduled appears next to the Edit Schedule button.

- 4. On the **Edit Schedule** window, select the **Recurrence** check box.
- 5. In the **Time Zone** box, select the appropriate time zone.
- 6. In the **Start** box, select $\stackrel{\square}{=}$ to schedule the start date and time.
 - a. Select one of the following as appropriate:
 - The current date: Select this option to use the current time and date as the starting point.
 - **Clear**: Select this option to clear the current selection.
 - **<Date>**: Select this option to use the selected date as the start date.
 - b. Select (b), and then select the appropriate time.
 - c. Select Close.
- 7. In the **Every** section, in the interval box, enter the numeric value for how often you want the generation to occur.
- 8. In the **Every** section, in the units box, select the interval unit (i.e., minutes, hours, years, etc).
- 9. In the **Every** section, in the begin box, select one of the following:
 - **From start time**: Select this option to start the recurrence from the previously selected start time.
 - After last occurrence: Select this option to begin the generation after the last time the job ran.
- 10. In the **End** box, based on when you want the recurrence to end, use the drop-down to select one of the following:

- **Never**: If you select this option, then the recurrence will not end.
- After: If you select this option, then you will enter a number of occurrences after which the generation will end.
- **Time & Date**: Select this option to use the calendar to select a time and date when the generation will end.

11. Select **OK**.

The schedule summary appears next to the **Edit Schedule**. Additionally, the scheduled item can be viewed in **Operations Manager** in **Scheduling**.

What's Next?

• Return to the SAP Adapter workflow for the next step in the deployment process.

APM Connect Connection Records

The **APM Connect** workspace stores information about connections used by APM Connect. Specifically, it manages the connection between GE Digital APM and APM Connect components. This topic provides an alphabetical list and description of the fields that exist in the **APM Connect** workspace. The information in the table reflects the baseline state and behavior of these fields.

General Setting

Field	Data Type	Description	Behavior and Usage
Application Server	String	The name of your GE Digital APM Server.	Enter the name of your GE Digital APM Server to establish your connection to your APM Connect sever.
Connection String	String	The URL indicating the APM Connect server host and port used to connect GE Digital APM and the APM Connect sever.	This field is required. The connection string is a combination of the APM Connect Connection parameters APM_CONNECT_HOST and APM_CONNECT_ PORT as defined in the context file. For example, if the host was apmconnect and the port was 8040, the connection string would be http://apmconnect:8040/. Note: This string is used by the file SAP_ RFC_Connector.jar.
Integration Server	String	The location of the APM Connect server.	This field is required.

Maximum Concurrent DL and EAM Jobs	Numeric	The number of Data Loading jobs or EAM jobs that can run at the same time.	This field is required. The default value is 1. This means that only one job can run at a time. The maximum value allowed is 5. When the number of concurrent jobs is low, data ingestion into GE Digital APM is faster and the system is less likely to become overloaded. Note: Two Data Loaders of the same type are not allowed to run at the same time. For example, if you initiated two Taxonomy data loads at the same time the one job would not begin loading until the first is complete no matter
			the value in the field.
Password	String	The password for the APM Connect network.	This field is required only if you are using network authentication.
Password	String	The password of the proxy server.	This field is required only if you are using proxy server authentication.

Port	String	The port number of the PostgreSQL server.	The default value is 5432. This value must match the value specified for the IR_PORT parameter in the Context File.
Proxy Server	String	The location of the proxy server.	This field is required only if you are using proxy server authentication.
Timeout (ms)	Numeric	The time in milliseconds before the connection between the APM Connect server and GE Digital APM will timeout.	The default value is 100,000 ms, and is pop- ulated automatically.
Use Authentication	Boolean	Indicates whether or not authorization will be used.	If the check box is selected, then authentication will be used, and you must enter the network user name and password.
Use Proxy Server	Boolean	Indicates the whether or not to use a proxy server.	If the check box is selected, then the proxy server will be used.
Use Proxy Server Authentication	Boolean	Indicates whether or not authentication will be used to the proxy server.	If the check box is selected, then authentication will be used for the proxy server.
Username	String	The user name for the APM Connect network.	This field is required only if you are using network authentication.
Username	String	The user name for the proxy server.	This field is required only if you are using proxy server authentication.

Data Loader Settings

Field	Data Type	Description	Behavior and Usage
Base File Path	String	The path to the file server.	This field is required. An example of a valid server path is \\host-server\share\subfolder. If an invalid server path is entered, an error message will appear. Falled to save configuration "Base File Path is not a valid UNC path"
Database Name	String	The database name of the Data Loader staging (IR) database.	None.
Host Name	String	The host name of the Data Loaders staging (IR) database.	None.

Logging Level	String	Determines the logging level for the data loader logs.	 The following logging levels can be selected: Debug: The default logging level, and the highest level of logging. Selecting debug will return the most details and is helpful when trying to debug the application. Info: Returns information message indicating the progress of the application, and is the second highest level of logging. Warn: Returns warnings detected during the loading process. Error: The lowest level of logging returning errors only. Note: Logging levels are hierarchical. For example, if you select Info, you will see all warnings and errors. If you select Error, you will only see errors.
Password	String	The Data Loader staging database (IR) password.	None.
Password	String	The password of the file server.	None.

Use File Path Authentication	Boolean	Indicates whether or not to use authentication when accessing the file server.	If selected, authentication will be used for the file path.
UserName	String	The Data Loader staging database (IR) user name.	None.
Username	String	The user name of the file server.	None.

EAM Settings

Field	Data Type	Description	Behavior and Usage
Work Order Gen- eration Schedule	Boolean	Stores the scheduling mechanism for transferring work orders to SAP.	To determine the schedule, you must schedule work orders.